

Run-Time Library (RTL) :  
Reference guide.

---

Free Pascal version 2.4.2rc1:  
Reference guide for RTL units.  
Document version 2.1  
August 2012

Michaël Van Canneyt

---

# Contents

0.1	Overview	100
<b>1</b>	<b>Reference for unit 'BaseUnix'</b>	<b>101</b>
1.1	Used units	101
1.2	Overview	101
1.3	Constants, types and variables	101
1.3.1	Constants	101
1.3.2	Types	124
1.4	Procedures and functions	140
1.4.1	CreateShellArgV	140
1.4.2	FpAccess	141
1.4.3	FpAlarm	141
1.4.4	FpChdir	142
1.4.5	FpChmod	142
1.4.6	FpChown	144
1.4.7	FpClose	145
1.4.8	FpClosedir	145
1.4.9	FpDup	145
1.4.10	FpDup2	146
1.4.11	FpExecv	147
1.4.12	FpExecve	148
1.4.13	FpExit	149
1.4.14	FpFcntl	149
1.4.15	fpfdfillset	150
1.4.16	fpFD_CLR	150
1.4.17	fpFD_ISSET	151
1.4.18	fpFD_SET	151
1.4.19	fpFD_ZERO	151
1.4.20	FpFork	151
1.4.21	FPFStat	152
1.4.22	FpFtruncate	153

1.4.23	FpGetcwd	153
1.4.24	FpGetegid	153
1.4.25	FpGetEnv	154
1.4.26	fpgeterno	154
1.4.27	FpGeteuid	155
1.4.28	FpGetgid	155
1.4.29	FpGetgroups	156
1.4.30	FpGetpggrp	156
1.4.31	FpGetpid	156
1.4.32	FpGetppid	157
1.4.33	fpGetPriority	157
1.4.34	FpGetRLimit	157
1.4.35	FpGetuid	158
1.4.36	FpIOctl	158
1.4.37	FpKill	159
1.4.38	FpLink	159
1.4.39	FpLseek	160
1.4.40	fpLstat	161
1.4.41	FpMkdir	162
1.4.42	FpMkfifo	163
1.4.43	Fpmmmap	163
1.4.44	Fpmunmap	165
1.4.45	FpNanoSleep	165
1.4.46	fpNice	166
1.4.47	FpOpen	166
1.4.48	FpOpendir	168
1.4.49	FpPause	169
1.4.50	FpPipe	169
1.4.51	FpPoll	170
1.4.52	FppRead	170
1.4.53	FppWrite	170
1.4.54	FpRead	171
1.4.55	FpReaddir	172
1.4.56	fpReadLink	172
1.4.57	FpReadV	173
1.4.58	FpRename	174
1.4.59	FpRmdir	174
1.4.60	fpSelect	175
1.4.61	fpseterno	176
1.4.62	FpSetgid	176

---

1.4.63	<code>fpSetPriority</code>	177
1.4.64	<code>FpSetRLimit</code>	177
1.4.65	<code>FpSetsid</code>	177
1.4.66	<code>fpsettimeofday</code>	178
1.4.67	<code>FpSetuid</code>	178
1.4.68	<code>FPSigaction</code>	178
1.4.69	<code>FpSigAddSet</code>	179
1.4.70	<code>FpSigDelSet</code>	180
1.4.71	<code>FpsigEmptySet</code>	180
1.4.72	<code>FpSigFillSet</code>	180
1.4.73	<code>FpSigIsMember</code>	180
1.4.74	<code>FpSignal</code>	181
1.4.75	<code>FpSigPending</code>	181
1.4.76	<code>FpSigProcMask</code>	182
1.4.77	<code>FpSigSuspend</code>	182
1.4.78	<code>FpSleep</code>	182
1.4.79	<code>FpStat</code>	183
1.4.80	<code>fpSymlink</code>	184
1.4.81	<code>fpS_ISBLK</code>	185
1.4.82	<code>fpS_ISCHR</code>	185
1.4.83	<code>fpS_ISDIR</code>	186
1.4.84	<code>fpS_ISFIFO</code>	186
1.4.85	<code>fpS_ISLNK</code>	186
1.4.86	<code>fpS_ISREG</code>	187
1.4.87	<code>fpS_ISSOCK</code>	187
1.4.88	<code>fpTime</code>	187
1.4.89	<code>FpTimes</code>	188
1.4.90	<code>FpUmask</code>	188
1.4.91	<code>FpUname</code>	189
1.4.92	<code>FpUnlink</code>	189
1.4.93	<code>FpUtime</code>	189
1.4.94	<code>FpWait</code>	190
1.4.95	<code>FpWaitPid</code>	191
1.4.96	<code>FpWrite</code>	191
1.4.97	<code>FpWriteV</code>	192
1.4.98	<code>FreeShellArgV</code>	192
1.4.99	<code>wexitStatus</code>	192
1.4.100	<code>wifexited</code>	192
1.4.101	<code>wifsignaled</code>	193
1.4.102	<code>wstopsig</code>	193

1.4.103 wtermsig . . . . .	193
<b>2 Reference for unit 'Classes' . . . . .</b>	<b>194</b>
2.1 Used units . . . . .	194
2.2 Overview . . . . .	194
2.3 Constants, types and variables . . . . .	194
2.3.1 Constants . . . . .	194
2.3.2 Types . . . . .	197
2.3.3 Variables . . . . .	208
2.4 Procedures and functions . . . . .	209
2.4.1 ActivateClassGroup . . . . .	209
2.4.2 BeginGlobalLoading . . . . .	209
2.4.3 BinToHex . . . . .	210
2.4.4 Bounds . . . . .	210
2.4.5 CheckSynchronize . . . . .	210
2.4.6 ClassGroupOf . . . . .	210
2.4.7 CollectionsEqual . . . . .	211
2.4.8 EndGlobalLoading . . . . .	211
2.4.9 ExtractStrings . . . . .	211
2.4.10 FindClass . . . . .	211
2.4.11 FindGlobalComponent . . . . .	212
2.4.12 FindIdentToInt . . . . .	212
2.4.13 FindIntToIdent . . . . .	212
2.4.14 FindNestedComponent . . . . .	212
2.4.15 GetClass . . . . .	213
2.4.16 GetFixupInstanceNames . . . . .	213
2.4.17 GetFixupReferenceNames . . . . .	213
2.4.18 GlobalFixupReferences . . . . .	213
2.4.19 GroupDescendentsWith . . . . .	214
2.4.20 HexToBin . . . . .	214
2.4.21 IdentToInt . . . . .	214
2.4.22 InitComponentRes . . . . .	214
2.4.23 InitInheritedComponent . . . . .	215
2.4.24 IntToIdent . . . . .	215
2.4.25 InvalidPoint . . . . .	215
2.4.26 LineStart . . . . .	216
2.4.27 NotifyGlobalLoading . . . . .	216
2.4.28 ObjectBinaryToText . . . . .	216
2.4.29 ObjectResourceToText . . . . .	216
2.4.30 ObjectTextToBinary . . . . .	216

---

2.4.31	ObjectTextToResource	217
2.4.32	Point	217
2.4.33	PointsEqual	217
2.4.34	ReadComponentRes	217
2.4.35	ReadComponentResEx	218
2.4.36	ReadComponentResFile	218
2.4.37	Rect	218
2.4.38	RedirectFixupReferences	218
2.4.39	RegisterClass	219
2.4.40	RegisterClassAlias	219
2.4.41	RegisterClasses	219
2.4.42	RegisterComponents	219
2.4.43	RegisterFindGlobalComponentProc	220
2.4.44	RegisterInitComponentHandler	220
2.4.45	RegisterIntegerConsts	220
2.4.46	RegisterNoIcon	221
2.4.47	RegisterNonActiveX	221
2.4.48	RemoveFixupReferences	221
2.4.49	RemoveFixups	221
2.4.50	SmallPoint	222
2.4.51	StartClassGroup	222
2.4.52	UnRegisterClass	222
2.4.53	UnRegisterClasses	222
2.4.54	UnregisterFindGlobalComponentProc	222
2.4.55	UnRegisterModuleClasses	223
2.4.56	WriteComponentResFile	223
2.5	EBitsError	223
2.5.1	Description	223
2.6	EClassNotFound	223
2.6.1	Description	223
2.7	EComponentError	224
2.7.1	Description	224
2.8	EFCREATEError	224
2.8.1	Description	224
2.9	EFilerError	224
2.9.1	Description	224
2.10	EFOpenError	224
2.10.1	Description	224
2.11	EInvalidImage	224
2.11.1	Description	224

---

2.12	EInvalidOperation	224
2.12.1	Description	224
2.13	EListError	225
2.13.1	Description	225
2.14	EMethodNotFound	225
2.14.1	Description	225
2.15	EOutOfResources	225
2.15.1	Description	225
2.16	EParserError	225
2.16.1	Description	225
2.17	EReadError	225
2.17.1	Description	225
2.18	EResNotFound	226
2.18.1	Description	226
2.19	EStreamError	226
2.19.1	Description	226
2.20	EStringListError	226
2.20.1	Description	226
2.21	EThread	226
2.21.1	Description	226
2.22	EThreadDestroyCalled	226
2.22.1	Description	226
2.23	EWriteError	227
2.23.1	Description	227
2.24	IDesignerNotify	227
2.24.1	Description	227
2.24.2	Method overview	227
2.24.3	IDesignerNotify.Modified	227
2.24.4	IDesignerNotify.Notification	227
2.25	IInterfaceComponentReference	227
2.25.1	Description	227
2.25.2	Method overview	228
2.25.3	IInterfaceComponentReference.GetComponent	228
2.26	IInterfaceList	228
2.26.1	Description	228
2.26.2	Method overview	228
2.26.3	Property overview	229
2.26.4	IInterfaceList.Get	229
2.26.5	IInterfaceList.GetCapacity	229
2.26.6	IInterfaceList.GetCount	229

2.26.7	<a href="#">InterfaceList.Put</a>	229
2.26.8	<a href="#">InterfaceList.SetCapacity</a>	230
2.26.9	<a href="#">InterfaceList.SetCount</a>	230
2.26.10	<a href="#">InterfaceList.Clear</a>	230
2.26.11	<a href="#">InterfaceList.Delete</a>	230
2.26.12	<a href="#">InterfaceList.Exchange</a>	231
2.26.13	<a href="#">InterfaceList.First</a>	231
2.26.14	<a href="#">InterfaceList.IndexOf</a>	231
2.26.15	<a href="#">InterfaceList.Add</a>	231
2.26.16	<a href="#">InterfaceList.Insert</a>	231
2.26.17	<a href="#">InterfaceList.Last</a>	232
2.26.18	<a href="#">InterfaceList.Remove</a>	232
2.26.19	<a href="#">InterfaceList.Lock</a>	232
2.26.20	<a href="#">InterfaceList.Unlock</a>	232
2.26.21	<a href="#">InterfaceList.Capacity</a>	232
2.26.22	<a href="#">InterfaceList.Count</a>	233
2.26.23	<a href="#">InterfaceList.Items</a>	233
2.27	<a href="#">IStreamPersist</a>	233
2.27.1	<a href="#">Description</a>	233
2.27.2	<a href="#">Method overview</a>	233
2.27.3	<a href="#">IStreamPersist.LoadFromStream</a>	233
2.27.4	<a href="#">IStreamPersist.SaveToStream</a>	234
2.28	<a href="#">IStringsAdapter</a>	234
2.28.1	<a href="#">Description</a>	234
2.28.2	<a href="#">Method overview</a>	234
2.28.3	<a href="#">IStringsAdapter.ReferenceStrings</a>	234
2.28.4	<a href="#">IStringsAdapter.ReleaseStrings</a>	234
2.29	<a href="#">TAbstractObjectReader</a>	234
2.29.1	<a href="#">Description</a>	234
2.29.2	<a href="#">Method overview</a>	235
2.29.3	<a href="#">TAbstractObjectReader.NextValue</a>	235
2.29.4	<a href="#">TAbstractObjectReader.ReadValue</a>	235
2.29.5	<a href="#">TAbstractObjectReader.BeginRootComponent</a>	236
2.29.6	<a href="#">TAbstractObjectReader.BeginComponent</a>	236
2.29.7	<a href="#">TAbstractObjectReader.BeginProperty</a>	236
2.29.8	<a href="#">TAbstractObjectReader.Read</a>	237
2.29.9	<a href="#">TAbstractObjectReader.ReadBinary</a>	237
2.29.10	<a href="#">TAbstractObjectReader.ReadFloat</a>	237
2.29.11	<a href="#">TAbstractObjectReader.ReadSingle</a>	237
2.29.12	<a href="#">TAbstractObjectReader.ReadDate</a>	238



2.29.13	<a href="#">TAbstractObjectReader.ReadCurrency</a>	238
2.29.14	<a href="#">TAbstractObjectReader.ReadIdent</a>	238
2.29.15	<a href="#">TAbstractObjectReader.ReadInt8</a>	239
2.29.16	<a href="#">TAbstractObjectReader.ReadInt16</a>	239
2.29.17	<a href="#">TAbstractObjectReader.ReadInt32</a>	240
2.29.18	<a href="#">TAbstractObjectReader.ReadInt64</a>	240
2.29.19	<a href="#">TAbstractObjectReader.ReadSet</a>	240
2.29.20	<a href="#">TAbstractObjectReader.ReadStr</a>	241
2.29.21	<a href="#">TAbstractObjectReader.ReadString</a>	241
2.29.22	<a href="#">TAbstractObjectReader.ReadWideString</a>	241
2.29.23	<a href="#">TAbstractObjectReader.ReadUnicodeString</a>	241
2.29.24	<a href="#">TAbstractObjectReader.SkipComponent</a>	242
2.29.25	<a href="#">TAbstractObjectReader.SkipValue</a>	242
2.30	<a href="#">TAbstractObjectWriter</a>	242
2.30.1	<a href="#">Description</a>	242
2.30.2	<a href="#">Method overview</a>	243
2.30.3	<a href="#">TAbstractObjectWriter.BeginCollection</a>	243
2.30.4	<a href="#">TAbstractObjectWriter.BeginComponent</a>	243
2.30.5	<a href="#">TAbstractObjectWriter.BeginList</a>	243
2.30.6	<a href="#">TAbstractObjectWriter.EndList</a>	244
2.30.7	<a href="#">TAbstractObjectWriter.BeginProperty</a>	244
2.30.8	<a href="#">TAbstractObjectWriter.EndProperty</a>	244
2.30.9	<a href="#">TAbstractObjectWriter.Write</a>	244
2.30.10	<a href="#">TAbstractObjectWriter.WriteBinary</a>	244
2.30.11	<a href="#">TAbstractObjectWriter.WriteBoolean</a>	245
2.30.12	<a href="#">TAbstractObjectWriter.WriteFloat</a>	245
2.30.13	<a href="#">TAbstractObjectWriter.WriteSingle</a>	245
2.30.14	<a href="#">TAbstractObjectWriter.WriteDate</a>	245
2.30.15	<a href="#">TAbstractObjectWriter.WriteCurrency</a>	245
2.30.16	<a href="#">TAbstractObjectWriter.WriteIdent</a>	246
2.30.17	<a href="#">TAbstractObjectWriter.WriteInteger</a>	246
2.30.18	<a href="#">TAbstractObjectWriter.WriteUInt64</a>	246
2.30.19	<a href="#">TAbstractObjectWriter.WriteVariant</a>	246
2.30.20	<a href="#">TAbstractObjectWriter.WriteMethodName</a>	246
2.30.21	<a href="#">TAbstractObjectWriter.WriteSet</a>	247
2.30.22	<a href="#">TAbstractObjectWriter.WriteString</a>	247
2.30.23	<a href="#">TAbstractObjectWriter.WriteWideString</a>	247
2.30.24	<a href="#">TAbstractObjectWriter.WriteUnicodeString</a>	247
2.31	<a href="#">TBasicAction</a>	247
2.31.1	<a href="#">Description</a>	247

2.31.2	Method overview	248
2.31.3	Property overview	248
2.31.4	TBasicAction.Create	248
2.31.5	TBasicAction.Destroy	248
2.31.6	TBasicAction.HandlesTarget	248
2.31.7	TBasicAction.UpdateTarget	249
2.31.8	TBasicAction.ExecuteTarget	249
2.31.9	TBasicAction.Execute	249
2.31.10	TBasicAction.RegisterChanges	250
2.31.11	TBasicAction.UnRegisterChanges	250
2.31.12	TBasicAction.Update	250
2.31.13	TBasicAction.ActionComponent	250
2.31.14	TBasicAction.OnExecute	251
2.31.15	TBasicAction.OnUpdate	251
2.32	TBasicActionLink	251
2.32.1	Description	251
2.32.2	Method overview	251
2.32.3	Property overview	252
2.32.4	TBasicActionLink.Create	252
2.32.5	TBasicActionLink.Destroy	252
2.32.6	TBasicActionLink.Execute	252
2.32.7	TBasicActionLink.Update	253
2.32.8	TBasicActionLink.Action	253
2.32.9	TBasicActionLink.OnChange	253
2.33	TBinaryObjectReader	253
2.33.1	Description	253
2.33.2	Method overview	254
2.33.3	TBinaryObjectReader.Create	254
2.33.4	TBinaryObjectReader.Destroy	254
2.33.5	TBinaryObjectReader.NextValue	255
2.33.6	TBinaryObjectReader.ReadValue	255
2.33.7	TBinaryObjectReader.BeginRootComponent	255
2.33.8	TBinaryObjectReader.BeginComponent	255
2.33.9	TBinaryObjectReader.BeginProperty	255
2.33.10	TBinaryObjectReader.Read	256
2.33.11	TBinaryObjectReader.ReadBinary	256
2.33.12	TBinaryObjectReader.ReadFloat	256
2.33.13	TBinaryObjectReader.ReadSingle	256
2.33.14	TBinaryObjectReader.ReadDate	256
2.33.15	TBinaryObjectReader.ReadCurrency	257

2.33.16 TBinaryObjectReader.ReadIdent . . . . .	257
2.33.17 TBinaryObjectReader.ReadInt8 . . . . .	257
2.33.18 TBinaryObjectReader.ReadInt16 . . . . .	257
2.33.19 TBinaryObjectReader.ReadInt32 . . . . .	258
2.33.20 TBinaryObjectReader.ReadInt64 . . . . .	258
2.33.21 TBinaryObjectReader.ReadSet . . . . .	258
2.33.22 TBinaryObjectReader.ReadStr . . . . .	258
2.33.23 TBinaryObjectReader.ReadString . . . . .	258
2.33.24 TBinaryObjectReader.ReadWideString . . . . .	259
2.33.25 TBinaryObjectReader.ReadUnicodeString . . . . .	259
2.33.26 TBinaryObjectReader.SkipComponent . . . . .	259
2.33.27 TBinaryObjectReader.SkipValue . . . . .	259
2.34 TBinaryObjectWriter . . . . .	260
2.34.1 Description . . . . .	260
2.34.2 Method overview . . . . .	260
2.34.3 TBinaryObjectWriter.Create . . . . .	260
2.34.4 TBinaryObjectWriter.Destroy . . . . .	260
2.34.5 TBinaryObjectWriter.BeginCollection . . . . .	261
2.34.6 TBinaryObjectWriter.BeginComponent . . . . .	261
2.34.7 TBinaryObjectWriter.BeginList . . . . .	261
2.34.8 TBinaryObjectWriter.EndList . . . . .	261
2.34.9 TBinaryObjectWriter.BeginProperty . . . . .	261
2.34.10 TBinaryObjectWriter.EndProperty . . . . .	261
2.34.11 TBinaryObjectWriter.Write . . . . .	262
2.34.12 TBinaryObjectWriter.WriteBinary . . . . .	262
2.34.13 TBinaryObjectWriter.WriteBoolean . . . . .	262
2.34.14 TBinaryObjectWriter.WriteFloat . . . . .	262
2.34.15 TBinaryObjectWriter.WriteSingle . . . . .	262
2.34.16 TBinaryObjectWriter.WriteDate . . . . .	262
2.34.17 TBinaryObjectWriter.WriteCurrency . . . . .	263
2.34.18 TBinaryObjectWriter.WriteIdent . . . . .	263
2.34.19 TBinaryObjectWriter.WriteInteger . . . . .	263
2.34.20 TBinaryObjectWriter.WriteUInt64 . . . . .	263
2.34.21 TBinaryObjectWriter.WriteMethodName . . . . .	263
2.34.22 TBinaryObjectWriter.WriteSet . . . . .	263
2.34.23 TBinaryObjectWriter.WriteString . . . . .	264
2.34.24 TBinaryObjectWriter.WriteWideString . . . . .	264
2.34.25 TBinaryObjectWriter.WriteUnicodeString . . . . .	264
2.34.26 TBinaryObjectWriter.WriteVariant . . . . .	264
2.35 TBits . . . . .	264

2.35.1	Description	264
2.35.2	Method overview	265
2.35.3	Property overview	265
2.35.4	TBits.Create	265
2.35.5	TBits.Destroy	265
2.35.6	TBits.GetFSize	266
2.35.7	TBits.SetOn	266
2.35.8	TBits.Clear	266
2.35.9	TBits.Clearall	267
2.35.10	TBits.AndBits	267
2.35.11	TBits.OrBits	267
2.35.12	TBits.XorBits	267
2.35.13	TBits.NotBits	268
2.35.14	TBits.Get	268
2.35.15	TBits.Grow	268
2.35.16	TBits.Equals	269
2.35.17	TBits.SetIndex	269
2.35.18	TBits.FindFirstBit	269
2.35.19	TBits.FindNextBit	270
2.35.20	TBits.FindPrevBit	270
2.35.21	TBits.OpenBit	270
2.35.22	TBits.Bits	271
2.35.23	TBits.Size	271
2.36	TCollection	271
2.36.1	Description	271
2.36.2	Method overview	272
2.36.3	Property overview	272
2.36.4	TCollection.Create	272
2.36.5	TCollection.Destroy	272
2.36.6	TCollection.Owner	273
2.36.7	TCollection.Add	273
2.36.8	TCollection.Assign	273
2.36.9	TCollection.BeginUpdate	273
2.36.10	TCollection.Clear	274
2.36.11	TCollection.EndUpdate	274
2.36.12	TCollection.Delete	274
2.36.13	TCollection.GetEnumerator	275
2.36.14	TCollection.GetNamePath	275
2.36.15	TCollection.Insert	275
2.36.16	TCollection.FindItemID	275

---

2.36.17	<a href="#">TCollection.Exchange</a>	276
2.36.18	<a href="#">TCollection.Sort</a>	276
2.36.19	<a href="#">TCollection.Count</a>	276
2.36.20	<a href="#">TCollection.ItemClass</a>	277
2.36.21	<a href="#">TCollection.Items</a>	277
2.37	<a href="#">TCollectionEnumerator</a>	277
2.37.1	<a href="#">Description</a>	277
2.37.2	<a href="#">Method overview</a>	277
2.37.3	<a href="#">Property overview</a>	278
2.37.4	<a href="#">TCollectionEnumerator.Create</a>	278
2.37.5	<a href="#">TCollectionEnumerator.GetCurrent</a>	278
2.37.6	<a href="#">TCollectionEnumerator.MoveNext</a>	278
2.37.7	<a href="#">TCollectionEnumerator.Current</a>	278
2.38	<a href="#">TCollectionItem</a>	279
2.38.1	<a href="#">Description</a>	279
2.38.2	<a href="#">Method overview</a>	279
2.38.3	<a href="#">Property overview</a>	279
2.38.4	<a href="#">TCollectionItem.Create</a>	279
2.38.5	<a href="#">TCollectionItem.Destroy</a>	279
2.38.6	<a href="#">TCollectionItem.GetNamePath</a>	280
2.38.7	<a href="#">TCollectionItem.Collection</a>	280
2.38.8	<a href="#">TCollectionItem.ID</a>	280
2.38.9	<a href="#">TCollectionItem.Index</a>	280
2.38.10	<a href="#">TCollectionItem.DisplayName</a>	281
2.39	<a href="#">TComponent</a>	281
2.39.1	<a href="#">Description</a>	281
2.39.2	<a href="#">Method overview</a>	282
2.39.3	<a href="#">Property overview</a>	282
2.39.4	<a href="#">TComponent.WriteState</a>	282
2.39.5	<a href="#">TComponent.Create</a>	283
2.39.6	<a href="#">TComponent.Destroy</a>	283
2.39.7	<a href="#">TComponent.BeforeDestruction</a>	283
2.39.8	<a href="#">TComponent.DestroyComponents</a>	283
2.39.9	<a href="#">TComponent.Destroying</a>	284
2.39.10	<a href="#">TComponent.ExecuteAction</a>	284
2.39.11	<a href="#">TComponent.FindComponent</a>	284
2.39.12	<a href="#">TComponent.FreeNotification</a>	285
2.39.13	<a href="#">TComponent.RemoveFreeNotification</a>	285
2.39.14	<a href="#">TComponent.FreeOnRelease</a>	285
2.39.15	<a href="#">TComponent.GetEnumerator</a>	285

2.39.16 TComponent.GetNamePath . . . . .	285
2.39.17 TComponent.GetParentComponent . . . . .	286
2.39.18 TComponent.HasParent . . . . .	286
2.39.19 TComponent.InsertComponent . . . . .	286
2.39.20 TComponent.RemoveComponent . . . . .	287
2.39.21 TComponent.SafeCallException . . . . .	287
2.39.22 TComponent.SetSubComponent . . . . .	287
2.39.23 TComponent.UpdateAction . . . . .	287
2.39.24 TComponent.IsImplementorOf . . . . .	288
2.39.25 TComponent.ReferenceInterface . . . . .	288
2.39.26 TComponent.Components . . . . .	288
2.39.27 TComponent.ComponentCount . . . . .	288
2.39.28 TComponent.ComponentIndex . . . . .	289
2.39.29 TComponent.ComponentState . . . . .	289
2.39.30 TComponent.ComponentStyle . . . . .	289
2.39.31 TComponent.DesignInfo . . . . .	290
2.39.32 TComponent.Owner . . . . .	290
2.39.33 TComponent.VCLComObject . . . . .	290
2.39.34 TComponent.Name . . . . .	290
2.39.35 TComponent.Tag . . . . .	291
2.40 TComponentEnumerator . . . . .	291
2.40.1 Description . . . . .	291
2.40.2 Method overview . . . . .	291
2.40.3 Property overview . . . . .	291
2.40.4 TComponentEnumerator.Create . . . . .	291
2.40.5 TComponentEnumerator.GetCurrent . . . . .	292
2.40.6 TComponentEnumerator.MoveNext . . . . .	292
2.40.7 TComponentEnumerator.Current . . . . .	292
2.41 TCustomMemoryStream . . . . .	293
2.41.1 Description . . . . .	293
2.41.2 Method overview . . . . .	293
2.41.3 Property overview . . . . .	293
2.41.4 TCustomMemoryStream.GetSize . . . . .	293
2.41.5 TCustomMemoryStream.Read . . . . .	293
2.41.6 TCustomMemoryStream.Seek . . . . .	294
2.41.7 TCustomMemoryStream.SaveToStream . . . . .	294
2.41.8 TCustomMemoryStream.SaveToFile . . . . .	294
2.41.9 TCustomMemoryStream.Memory . . . . .	295
2.42 TDataModule . . . . .	295
2.42.1 Description . . . . .	295

---

2.42.2	Method overview	295
2.42.3	Property overview	296
2.42.4	TDataModule.Create	296
2.42.5	TDataModule.CreateNew	296
2.42.6	TDataModule.Destroy	296
2.42.7	TDataModule.AfterConstruction	297
2.42.8	TDataModule.BeforeDestruction	297
2.42.9	TDataModule.DesignOffset	297
2.42.10	TDataModule.DesignSize	297
2.42.11	TDataModule.OnCreate	298
2.42.12	TDataModule.OnDestroy	298
2.42.13	TDataModule.OldCreateOrder	298
2.43	TFiler	298
2.43.1	Description	298
2.43.2	Method overview	299
2.43.3	Property overview	299
2.43.4	TFiler.DefineProperty	299
2.43.5	TFiler.DefineBinaryProperty	299
2.43.6	TFiler.Root	299
2.43.7	TFiler.LookupRoot	300
2.43.8	TFiler.Ancestor	300
2.43.9	TFiler.IgnoreChildren	300
2.44	TFileStream	300
2.44.1	Description	300
2.44.2	Method overview	300
2.44.3	Property overview	301
2.44.4	TFileStream.Create	301
2.44.5	TFileStream.Destroy	301
2.44.6	TFileStream.FileName	301
2.45	TFPList	302
2.45.1	Description	302
2.45.2	Method overview	302
2.45.3	Property overview	302
2.45.4	TFPList.Destroy	303
2.45.5	TFPList.AddList	303
2.45.6	TFPList.Add	303
2.45.7	TFPList.Clear	303
2.45.8	TFPList.Delete	304
2.45.9	TFPList.Error	304
2.45.10	TFPList.Exchange	304

---

2.45.11	TFPList.Expand	304
2.45.12	TFPList.Extract	305
2.45.13	TFPList.First	305
2.45.14	TFPList.GetEnumerator	305
2.45.15	TFPList.IndexOf	305
2.45.16	TFPList.Insert	306
2.45.17	TFPList.Last	306
2.45.18	TFPList.Move	306
2.45.19	TFPList.Assign	306
2.45.20	TFPList.Remove	307
2.45.21	TFPList.Pack	307
2.45.22	TFPList.Sort	307
2.45.23	TFPList.ForEachCall	307
2.45.24	TFPList.Capacity	308
2.45.25	TFPList.Count	308
2.45.26	TFPList.Items	308
2.45.27	TFPList.List	309
2.46	TFPListEnumerator	309
2.46.1	Description	309
2.46.2	Method overview	309
2.46.3	Property overview	309
2.46.4	TFPListEnumerator.Create	309
2.46.5	TFPListEnumerator.GetCurrent	309
2.46.6	TFPListEnumerator.MoveNext	310
2.46.7	TFPListEnumerator.Current	310
2.47	THandleStream	310
2.47.1	Description	310
2.47.2	Method overview	310
2.47.3	Property overview	311
2.47.4	THandleStream.Create	311
2.47.5	THandleStream.Read	311
2.47.6	THandleStream.Write	311
2.47.7	THandleStream.Seek	312
2.47.8	THandleStream.Handle	312
2.48	TInterfacedPersistent	312
2.48.1	Description	312
2.48.2	Method overview	312
2.48.3	TInterfacedPersistent.QueryInterface	312
2.48.4	TInterfacedPersistent.AfterConstruction	313
2.49	TInterfaceList	313



---

2.49.1	Description	313
2.49.2	Method overview	313
2.49.3	Property overview	313
2.49.4	TInterfaceList.Create	313
2.49.5	TInterfaceList.Destroy	314
2.49.6	TInterfaceList.Clear	314
2.49.7	TInterfaceList.Delete	314
2.49.8	TInterfaceList.Exchange	314
2.49.9	TInterfaceList.First	315
2.49.10	TInterfaceList.GetEnumerator	315
2.49.11	TInterfaceList.IndexOf	315
2.49.12	TInterfaceList.Add	315
2.49.13	TInterfaceList.Insert	316
2.49.14	TInterfaceList.Last	316
2.49.15	TInterfaceList.Remove	316
2.49.16	TInterfaceList.Lock	316
2.49.17	TInterfaceList.Unlock	317
2.49.18	TInterfaceList.Expand	317
2.49.19	TInterfaceList.Capacity	317
2.49.20	TInterfaceList.Count	317
2.49.21	TInterfaceList.Items	318
2.50	TInterfaceListEnumerator	318
2.50.1	Description	318
2.50.2	Method overview	318
2.50.3	Property overview	318
2.50.4	TInterfaceListEnumerator.Create	318
2.50.5	TInterfaceListEnumerator.GetCurrent	319
2.50.6	TInterfaceListEnumerator.MoveNext	319
2.50.7	TInterfaceListEnumerator.Current	319
2.51	TList	319
2.51.1	Description	319
2.51.2	Method overview	320
2.51.3	Property overview	320
2.51.4	TList.Create	320
2.51.5	TList.Destroy	320
2.51.6	TList.AddList	321
2.51.7	TList.Add	321
2.51.8	TList.Clear	321
2.51.9	TList.Delete	321
2.51.10	TList.Error	322

2.51.11	TList.Exchange	322
2.51.12	TList.Expand	322
2.51.13	TList.Extract	322
2.51.14	TList.First	323
2.51.15	TList.GetEnumerator	323
2.51.16	TList.IndexOf	323
2.51.17	TList.Insert	323
2.51.18	TList.Last	324
2.51.19	TList.Move	324
2.51.20	TList.Assign	324
2.51.21	TList.Remove	324
2.51.22	TList.Pack	325
2.51.23	TList.Sort	325
2.51.24	TList.Capacity	325
2.51.25	TList.Count	326
2.51.26	TList.Items	326
2.51.27	TList.List	326
2.52	TListEnumerator	326
2.52.1	Description	326
2.52.2	Method overview	326
2.52.3	Property overview	327
2.52.4	TListEnumerator.Create	327
2.52.5	TListEnumerator.GetCurrent	327
2.52.6	TListEnumerator.MoveNext	327
2.52.7	TListEnumerator.Current	327
2.53	TMemoryStream	328
2.53.1	Description	328
2.53.2	Method overview	328
2.53.3	TMemoryStream.Destroy	328
2.53.4	TMemoryStream.Clear	328
2.53.5	TMemoryStream.LoadFromStream	328
2.53.6	TMemoryStream.LoadFromFile	329
2.53.7	TMemoryStream.SetSize	329
2.53.8	TMemoryStream.Write	329
2.54	TOwnedCollection	330
2.54.1	Description	330
2.54.2	Method overview	330
2.54.3	TOwnedCollection.Create	330
2.55	TOwnerStream	330
2.55.1	Description	330

2.55.2	Method overview	330
2.55.3	Property overview	331
2.55.4	TOwnerStream.Create	331
2.55.5	TOwnerStream.Destroy	331
2.55.6	TOwnerStream.Source	331
2.55.7	TOwnerStream.SourceOwner	331
2.56	TParser	332
2.56.1	Description	332
2.56.2	Method overview	332
2.56.3	Property overview	332
2.56.4	TParser.Create	332
2.56.5	TParser.Destroy	333
2.56.6	TParser.CheckToken	333
2.56.7	TParser.CheckTokenSymbol	333
2.56.8	TParser.Error	333
2.56.9	TParser.ErrorFmt	334
2.56.10	TParser.ErrorStr	334
2.56.11	TParser.HexToBinary	334
2.56.12	TParser.NextToken	334
2.56.13	TParser.SourcePos	335
2.56.14	TParser.TokenComponentIdent	335
2.56.15	TParser.TokenFloat	335
2.56.16	TParser.TokenInt	336
2.56.17	TParser.TokenString	336
2.56.18	TParser.TokenWideString	336
2.56.19	TParser.TokenSymbolIs	337
2.56.20	TParser.FloatType	337
2.56.21	TParser.SourceLine	337
2.56.22	TParser.Token	338
2.57	TPersistent	338
2.57.1	Description	338
2.57.2	Method overview	338
2.57.3	TPersistent.Destroy	338
2.57.4	TPersistent.Assign	339
2.57.5	TPersistent.GetNamePath	339
2.58	TProxyStream	339
2.58.1	Description	339
2.58.2	Method overview	340
2.58.3	TProxyStream.Create	340
2.58.4	TProxyStream.Read	340

---

2.58.5	TProxyStream.Write	340
2.58.6	TProxyStream.Seek	340
2.58.7	TProxyStream.Check	340
2.59	TReader	341
2.59.1	Description	341
2.59.2	Method overview	341
2.59.3	Property overview	342
2.59.4	TReader.Create	342
2.59.5	TReader.Destroy	342
2.59.6	TReader.BeginReferences	342
2.59.7	TReader.CheckValue	343
2.59.8	TReader.DefineProperty	343
2.59.9	TReader.DefineBinaryProperty	343
2.59.10	TReader.EndOfList	343
2.59.11	TReader.EndReferences	343
2.59.12	TReader.FixupReferences	344
2.59.13	TReader.NextValue	344
2.59.14	TReader.Read	344
2.59.15	TReader.ReadBoolean	344
2.59.16	TReader.ReadChar	344
2.59.17	TReader.ReadWideChar	345
2.59.18	TReader.ReadUnicodeChar	345
2.59.19	TReader.ReadCollection	345
2.59.20	TReader.ReadComponent	345
2.59.21	TReader.ReadComponents	345
2.59.22	TReader.ReadFloat	346
2.59.23	TReader.ReadSingle	346
2.59.24	TReader.ReadDate	346
2.59.25	TReader.ReadCurrency	346
2.59.26	TReader.ReadIdent	346
2.59.27	TReader.ReadInteger	347
2.59.28	TReader.ReadInt64	347
2.59.29	TReader.ReadSet	347
2.59.30	TReader.ReadListBegin	347
2.59.31	TReader.ReadListEnd	347
2.59.32	TReader.ReadRootComponent	348
2.59.33	TReader.ReadVariant	348
2.59.34	TReader.ReadString	348
2.59.35	TReader.ReadWideString	348
2.59.36	TReader.ReadUnicodeString	348

2.59.37 TReader.ReadValue . . . . .	349
2.59.38 TReader.CopyValue . . . . .	349
2.59.39 TReader.Driver . . . . .	349
2.59.40 TReader.Owner . . . . .	349
2.59.41 TReader.Parent . . . . .	349
2.59.42 TReader.OnError . . . . .	350
2.59.43 TReader.OnPropertyNotFound . . . . .	350
2.59.44 TReader.OnFindMethod . . . . .	350
2.59.45 TReader.OnSetMethodProperty . . . . .	350
2.59.46 TReader.OnSetName . . . . .	351
2.59.47 TReader.OnReferenceName . . . . .	351
2.59.48 TReader.OnAncestorNotFound . . . . .	351
2.59.49 TReader.OnCreateComponent . . . . .	351
2.59.50 TReader.OnFindComponentClass . . . . .	351
2.59.51 TReader.OnReadStringProperty . . . . .	352
2.60 TRecall . . . . .	352
2.60.1 Description . . . . .	352
2.60.2 Method overview . . . . .	352
2.60.3 Property overview . . . . .	352
2.60.4 TRecall.Create . . . . .	352
2.60.5 TRecall.Destroy . . . . .	353
2.60.6 TRecall.Store . . . . .	353
2.60.7 TRecall.Forget . . . . .	353
2.60.8 TRecall.Reference . . . . .	354
2.61 TResourceStream . . . . .	354
2.61.1 Description . . . . .	354
2.61.2 Method overview . . . . .	354
2.61.3 TResourceStream.Create . . . . .	354
2.61.4 TResourceStream.CreateFromID . . . . .	354
2.61.5 TResourceStream.Destroy . . . . .	355
2.62 TStream . . . . .	355
2.62.1 Description . . . . .	355
2.62.2 Method overview . . . . .	355
2.62.3 Property overview . . . . .	356
2.62.4 TStream.Read . . . . .	356
2.62.5 TStream.Write . . . . .	356
2.62.6 TStream.Seek . . . . .	356
2.62.7 TStream.ReadBuffer . . . . .	357
2.62.8 TStream.WriteBuffer . . . . .	357
2.62.9 TStream.CopyFrom . . . . .	358

2.62.10 TStream.ReadComponent	358
2.62.11 TStream.ReadComponentRes	358
2.62.12 TStream.WriteComponent	359
2.62.13 TStream.WriteComponentRes	359
2.62.14 TStream.WriteDescendent	359
2.62.15 TStream.WriteDescendentRes	359
2.62.16 TStream.WriteResourceHeader	360
2.62.17 TStream.FixupResourceHeader	360
2.62.18 TStream.ReadResHeader	360
2.62.19 TStream.ReadByte	360
2.62.20 TStream.ReadWord	361
2.62.21 TStream.ReadDWord	361
2.62.22 TStream.ReadQWord	361
2.62.23 TStream.ReadAnsiString	362
2.62.24 TStream.WriteByte	362
2.62.25 TStream.WriteWord	362
2.62.26 TStream.WriteDWord	362
2.62.27 TStream.WriteQWord	363
2.62.28 TStream.WriteAnsiString	363
2.62.29 TStream.Position	363
2.62.30 TStream.Size	364
2.63 TStreamAdapter	364
2.63.1 Description	364
2.63.2 Method overview	364
2.63.3 Property overview	364
2.63.4 TStreamAdapter.Create	365
2.63.5 TStreamAdapter.Destroy	365
2.63.6 TStreamAdapter.Read	365
2.63.7 TStreamAdapter.Write	365
2.63.8 TStreamAdapter.Seek	366
2.63.9 TStreamAdapter.SetSize	366
2.63.10 TStreamAdapter.CopyTo	366
2.63.11 TStreamAdapter.Commit	366
2.63.12 TStreamAdapter.Revert	367
2.63.13 TStreamAdapter.LockRegion	367
2.63.14 TStreamAdapter.UnlockRegion	367
2.63.15 TStreamAdapter.Stat	367
2.63.16 TStreamAdapter.Clone	368
2.63.17 TStreamAdapter.Stream	368
2.63.18 TStreamAdapter.StreamOwnership	368

2.64	TStringList	368
2.64.1	Description	368
2.64.2	Method overview	369
2.64.3	Property overview	369
2.64.4	TStringList.Destroy	369
2.64.5	TStringList.Add	369
2.64.6	TStringList.Clear	370
2.64.7	TStringList.Delete	370
2.64.8	TStringList.Exchange	370
2.64.9	TStringList.Find	370
2.64.10	TStringList.IndexOf	371
2.64.11	TStringList.Insert	371
2.64.12	TStringList.Sort	371
2.64.13	TStringList.CustomSort	371
2.64.14	TStringList.Duplicates	372
2.64.15	TStringList.Sorted	372
2.64.16	TStringList.CaseSensitive	372
2.64.17	TStringList.OnChange	373
2.64.18	TStringList.OnChanging	373
2.65	TStrings	373
2.65.1	Description	373
2.65.2	Method overview	374
2.65.3	Property overview	374
2.65.4	TStrings.Destroy	375
2.65.5	TStrings.Add	375
2.65.6	TStrings.AddObject	375
2.65.7	TStrings.Append	375
2.65.8	TStrings.AddStrings	376
2.65.9	TStrings.Assign	376
2.65.10	TStrings.BeginUpdate	376
2.65.11	TStrings.Clear	377
2.65.12	TStrings.Delete	377
2.65.13	TStrings.EndUpdate	377
2.65.14	TStrings.Equals	377
2.65.15	TStrings.Exchange	378
2.65.16	TStrings.GetEnumerator	378
2.65.17	TStrings.GetText	378
2.65.18	TStrings.IndexOf	379
2.65.19	TStrings.IndexOfName	379
2.65.20	TStrings.IndexOfObject	379

2.65.21	TStrings.Insert	380
2.65.22	TStrings.InsertObject	380
2.65.23	TStrings.LoadFromFile	380
2.65.24	TStrings.LoadFromStream	381
2.65.25	TStrings.Move	381
2.65.26	TStrings.SaveToFile	382
2.65.27	TStrings.SaveToStream	382
2.65.28	TStrings.SetText	382
2.65.29	TStrings.GetNameValue	382
2.65.30	TStrings.ExtractName	383
2.65.31	TStrings.TextLineBreakStyle	383
2.65.32	TStrings.Delimiter	383
2.65.33	TStrings.DelimitedText	384
2.65.34	TStrings.StrictDelimiter	384
2.65.35	TStrings.QuoteChar	384
2.65.36	TStrings.NameValueSeparator	385
2.65.37	TStrings.ValueFromIndex	385
2.65.38	TStrings.Capacity	385
2.65.39	TStrings.CommaText	385
2.65.40	TStrings.Count	386
2.65.41	TStrings.Names	387
2.65.42	TStrings.Objects	387
2.65.43	TStrings.Values	387
2.65.44	TStrings.Strings	388
2.65.45	TStrings.Text	388
2.65.46	TStrings.StringsAdapter	389
2.66	TStringsEnumerator	389
2.66.1	Description	389
2.66.2	Method overview	389
2.66.3	Property overview	389
2.66.4	TStringsEnumerator.Create	389
2.66.5	TStringsEnumerator.GetCurrent	389
2.66.6	TStringsEnumerator.MoveNext	390
2.66.7	TStringsEnumerator.Current	390
2.67	TStringStream	390
2.67.1	Description	390
2.67.2	Method overview	390
2.67.3	Property overview	390
2.67.4	TStringStream.Create	391
2.67.5	TStringStream.Read	391



---

2.67.6	TStringStream.ReadString	391
2.67.7	TStringStream.Seek	391
2.67.8	TStringStream.Write	392
2.67.9	TStringStream.WriteString	392
2.67.10	TStringStream.DataString	392
2.68	TTextObjectWriter	392
2.68.1	Description	392
2.69	TThread	392
2.69.1	Description	392
2.69.2	Method overview	393
2.69.3	Property overview	393
2.69.4	TThread.Create	393
2.69.5	TThread.Destroy	393
2.69.6	TThread.AfterConstruction	393
2.69.7	TThread.Start	394
2.69.8	TThread.Resume	394
2.69.9	TThread.Suspend	394
2.69.10	TThread.Terminate	394
2.69.11	TThread.WaitFor	394
2.69.12	TThread.FreeOnTerminate	395
2.69.13	TThread.Handle	395
2.69.14	TThread.Priority	395
2.69.15	TThread.Suspended	395
2.69.16	TThread.ThreadID	395
2.69.17	TThread.OnTerminate	396
2.69.18	TThread.FatalException	396
2.70	TThreadList	396
2.70.1	Description	396
2.70.2	Method overview	396
2.70.3	Property overview	396
2.70.4	TThreadList.Create	396
2.70.5	TThreadList.Destroy	397
2.70.6	TThreadList.Add	397
2.70.7	TThreadList.Clear	397
2.70.8	TThreadList.LockList	397
2.70.9	TThreadList.Remove	398
2.70.10	TThreadList.UnlockList	398
2.70.11	TThreadList.Duplicates	398
2.71	TWriter	398
2.71.1	Description	398

2.71.2	Method overview	399
2.71.3	Property overview	399
2.71.4	TWriter.Create	399
2.71.5	TWriter.Destroy	400
2.71.6	TWriter.DefineProperty	400
2.71.7	TWriter.DefineBinaryProperty	400
2.71.8	TWriter.Write	400
2.71.9	TWriter.WriteBoolean	400
2.71.10	TWriter.WriteCollection	401
2.71.11	TWriter.WriteComponent	401
2.71.12	TWriter.WriteChar	401
2.71.13	TWriter.WriteWideChar	401
2.71.14	TWriter.WriteDescendent	401
2.71.15	TWriter.WriteFloat	401
2.71.16	TWriter.WriteSingle	402
2.71.17	TWriter.WriteDate	402
2.71.18	TWriter.WriteCurrency	402
2.71.19	TWriter.WriteIdent	402
2.71.20	TWriter.WriteInteger	402
2.71.21	TWriter.WriteSet	403
2.71.22	TWriter.WriteListBegin	403
2.71.23	TWriter.WriteListEnd	403
2.71.24	TWriter.WriteRootComponent	403
2.71.25	TWriter.WriteString	403
2.71.26	TWriter.WriteWideString	404
2.71.27	TWriter.WriteUnicodeString	404
2.71.28	TWriter.WriteVariant	404
2.71.29	TWriter.RootAncestor	404
2.71.30	TWriter.OnFindAncestor	404
2.71.31	TWriter.OnWriteMethodProperty	405
2.71.32	TWriter.OnWriteStringProperty	405
2.71.33	TWriter.Driver	405
2.71.34	TWriter.PropertyPath	405
<b>3</b>	<b>Reference for unit 'clocale'</b>	<b>406</b>
3.1	Overview	406
<b>4</b>	<b>Reference for unit 'cmem'</b>	<b>407</b>
4.1	Overview	407
4.2	Constants, types and variables	407
4.2.1	Constants	407

4.3	Procedures and functions	407
4.3.1	CAlloc	407
4.3.2	Free	407
4.3.3	Malloc	408
4.3.4	ReAlloc	408
<b>5</b>	<b>Reference for unit 'Crt'</b>	<b>409</b>
5.1	Overview	409
5.2	Constants, types and variables	409
5.2.1	Constants	409
5.2.2	Types	412
5.2.3	Variables	412
5.3	Procedures and functions	413
5.3.1	AssignCrt	413
5.3.2	ClrEol	414
5.3.3	ClrScr	414
5.3.4	cursorbig	415
5.3.5	cursoroff	415
5.3.6	cursoron	415
5.3.7	Delay	416
5.3.8	DelLine	416
5.3.9	GotoXY	417
5.3.10	HighVideo	417
5.3.11	InsLine	418
5.3.12	KeyPressed	418
5.3.13	LowVideo	419
5.3.14	NormVideo	419
5.3.15	NoSound	420
5.3.16	ReadKey	420
5.3.17	Sound	421
5.3.18	TextBackground	421
5.3.19	TextColor	422
5.3.20	TextMode	422
5.3.21	WhereX	423
5.3.22	WhereY	423
5.3.23	Window	424
<b>6</b>	<b>Reference for unit 'cthreads'</b>	<b>425</b>
6.1	Overview	425
6.2	Procedures and functions	425
6.2.1	SetCThreadManager	425

<b>7</b>	<b>Reference for unit 'ctypes'</b>	<b>426</b>
7.1	Used units . . . . .	426
7.2	Overview . . . . .	426
7.3	Constants, types and variables . . . . .	426
7.3.1	Types . . . . .	426
7.4	Procedures and functions . . . . .	431
7.4.1	operator *(clongdouble, Double): Double . . . . .	431
7.4.2	operator *(Double, clongdouble): Double . . . . .	431
7.4.3	operator +(clongdouble, Double): Double . . . . .	432
7.4.4	operator +(Double, clongdouble): Double . . . . .	432
7.4.5	operator -(clongdouble, Double): Double . . . . .	432
7.4.6	operator -(Double, clongdouble): Double . . . . .	432
7.4.7	operator /(clongdouble, Double): Double . . . . .	433
7.4.8	operator /(Double, clongdouble): Double . . . . .	433
7.4.9	operator :=(clongdouble): double . . . . .	433
7.4.10	operator :=(double): clongdouble . . . . .	433
7.4.11	operator <(clongdouble, Double): Boolean . . . . .	433
7.4.12	operator <(Double, clongdouble): Boolean . . . . .	434
7.4.13	operator <=(clongdouble, Double): Boolean . . . . .	434
7.4.14	operator <=(Double, clongdouble): Boolean . . . . .	434
7.4.15	operator =(clongdouble, Double): Boolean . . . . .	434
7.4.16	operator =(Double, clongdouble): Boolean . . . . .	435
7.4.17	operator >(clongdouble, Double): Boolean . . . . .	435
7.4.18	operator >(Double, clongdouble): Boolean . . . . .	435
7.4.19	operator >=(clongdouble, Double): Boolean . . . . .	435
7.4.20	operator >=(Double, clongdouble): Boolean . . . . .	436
<b>8</b>	<b>Reference for unit 'cstring'</b>	<b>437</b>
8.1	Overview . . . . .	437
8.2	Procedures and functions . . . . .	437
8.2.1	SetCWidestringManager . . . . .	437
<b>9</b>	<b>Reference for unit 'dateutils'</b>	<b>438</b>
9.1	Used units . . . . .	438
9.2	Overview . . . . .	438
9.3	Constants, types and variables . . . . .	438
9.3.1	Constants . . . . .	438
9.4	Procedures and functions . . . . .	440
9.4.1	CompareDate . . . . .	440
9.4.2	CompareDateTime . . . . .	441
9.4.3	CompareTime . . . . .	442

9.4.4	DateOf	443
9.4.5	DateTimeToDosDateTime	444
9.4.6	DateTimeToJulianDate	444
9.4.7	DateTimeToMac	444
9.4.8	DateTimeToModifiedJulianDate	445
9.4.9	DateTimeToUnix	445
9.4.10	DayOf	445
9.4.11	DayOfTheMonth	445
9.4.12	DayOfTheWeek	446
9.4.13	DayOfTheYear	446
9.4.14	DaysBetween	447
9.4.15	DaysInAMonth	447
9.4.16	DaysInAYear	448
9.4.17	DaysInMonth	449
9.4.18	DaysInYear	449
9.4.19	DaySpan	450
9.4.20	DecodeDateDay	450
9.4.21	DecodeDateMonthWeek	451
9.4.22	DecodeDateTime	452
9.4.23	DecodeDateWeek	452
9.4.24	DecodeDayOfWeekInMonth	453
9.4.25	DosDateTimeToDateTime	453
9.4.26	EncodeDateDay	454
9.4.27	EncodeDateMonthWeek	454
9.4.28	EncodeDateTime	454
9.4.29	EncodeDateWeek	455
9.4.30	EncodeDayOfWeekInMonth	455
9.4.31	EndOfADay	455
9.4.32	EndOfAMonth	456
9.4.33	EndOfAWeek	457
9.4.34	EndOfAYear	457
9.4.35	EndOfTheDay	458
9.4.36	EndOfTheMonth	458
9.4.37	EndOfTheWeek	459
9.4.38	EndOfTheYear	460
9.4.39	HourOf	460
9.4.40	HourOfTheDay	460
9.4.41	HourOfTheMonth	461
9.4.42	HourOfTheWeek	461
9.4.43	HourOfTheYear	462

9.4.44	HoursBetween	462
9.4.45	HourSpan	463
9.4.46	IncDay	464
9.4.47	IncHour	464
9.4.48	IncMilliSecond	465
9.4.49	IncMinute	465
9.4.50	IncSecond	466
9.4.51	IncWeek	466
9.4.52	IncYear	467
9.4.53	InvalidDateDayError	467
9.4.54	InvalidDateMonthWeekError	467
9.4.55	InvalidDateTimeError	468
9.4.56	InvalidDateWeekError	468
9.4.57	InvalidDayOfWeekInMonthError	469
9.4.58	IsInLeapYear	469
9.4.59	IsPM	469
9.4.60	IsSameDay	470
9.4.61	IsToday	470
9.4.62	IsValidDate	471
9.4.63	IsValidDateDay	471
9.4.64	IsValidDateMonthWeek	472
9.4.65	IsValidDateTime	473
9.4.66	IsValidDateWeek	474
9.4.67	IsValidTime	475
9.4.68	JulianDateToDateTime	475
9.4.69	MacTimeStampToUnix	475
9.4.70	MacToDateTime	475
9.4.71	MilliSecondOf	476
9.4.72	MilliSecondOfTheDay	476
9.4.73	MilliSecondOfTheHour	476
9.4.74	MilliSecondOfTheMinute	476
9.4.75	MilliSecondOfTheMonth	477
9.4.76	MilliSecondOfTheSecond	477
9.4.77	MilliSecondOfTheWeek	478
9.4.78	MilliSecondOfTheYear	478
9.4.79	MilliSecondsBetween	478
9.4.80	MilliSecondSpan	479
9.4.81	MinuteOf	480
9.4.82	MinuteOfTheDay	480
9.4.83	MinuteOfTheHour	480

9.4.84 MinuteOfTheMonth . . . . .	481
9.4.85 MinuteOfTheWeek . . . . .	481
9.4.86 MinuteOfTheYear . . . . .	482
9.4.87 MinutesBetween . . . . .	482
9.4.88 MinuteSpan . . . . .	483
9.4.89 ModifiedJulianDateToDateTime . . . . .	484
9.4.90 MonthOf . . . . .	484
9.4.91 MonthOfTheYear . . . . .	484
9.4.92 MonthsBetween . . . . .	484
9.4.93 MonthSpan . . . . .	485
9.4.94 NthDayOfWeek . . . . .	486
9.4.95 PreviousDayOfWeek . . . . .	487
9.4.96 RecodeDate . . . . .	487
9.4.97 RecodeDateTime . . . . .	488
9.4.98 RecodeDay . . . . .	489
9.4.99 RecodeHour . . . . .	489
9.4.100 RecodeMilliSecond . . . . .	490
9.4.101 RecodeMinute . . . . .	491
9.4.102 RecodeMonth . . . . .	491
9.4.103 RecodeSecond . . . . .	492
9.4.104 RecodeTime . . . . .	493
9.4.105 RecodeYear . . . . .	493
9.4.106 SameDate . . . . .	494
9.4.107 SameDateTime . . . . .	495
9.4.108 SameTime . . . . .	496
9.4.109 ScanDateTime . . . . .	496
9.4.110 SecondOf . . . . .	497
9.4.111 SecondOfTheDay . . . . .	497
9.4.112 SecondOfTheHour . . . . .	497
9.4.113 SecondOfTheMinute . . . . .	498
9.4.114 SecondOfTheMonth . . . . .	498
9.4.115 SecondOfTheWeek . . . . .	498
9.4.116 SecondOfTheYear . . . . .	499
9.4.117 SecondsBetween . . . . .	499
9.4.118 SecondSpan . . . . .	500
9.4.119 StartOfADay . . . . .	501
9.4.120 StartOfAMonth . . . . .	502
9.4.121 StartOfAWeek . . . . .	502
9.4.122 StartOfAYear . . . . .	503
9.4.123 StartOfTheDay . . . . .	503

9.4.124 StartOfTheMonth . . . . .	504
9.4.125 StartOfTheWeek . . . . .	504
9.4.126 StartOfTheYear . . . . .	505
9.4.127 TimeOf . . . . .	505
9.4.128 Today . . . . .	506
9.4.129 Tomorrow . . . . .	506
9.4.130 TryEncodeDateDay . . . . .	507
9.4.131 TryEncodeDateMonthWeek . . . . .	507
9.4.132 TryEncodeDateTime . . . . .	508
9.4.133 TryEncodeDateWeek . . . . .	509
9.4.134 TryEncodeDayOfWeekInMonth . . . . .	509
9.4.135 TryJulianDateToDateTime . . . . .	510
9.4.136 TryModifiedJulianDateToDateTime . . . . .	510
9.4.137 TryRecodeDateTime . . . . .	511
9.4.138 UnixTimeStampToMac . . . . .	512
9.4.139 UnixToDateTime . . . . .	512
9.4.140 WeekOf . . . . .	512
9.4.141 WeekOfTheMonth . . . . .	512
9.4.142 WeekOfTheYear . . . . .	513
9.4.143 WeeksBetween . . . . .	514
9.4.144 WeeksInAYear . . . . .	515
9.4.145 WeeksInYear . . . . .	515
9.4.146 WeekSpan . . . . .	516
9.4.147 WithinPastDays . . . . .	517
9.4.148 WithinPastHours . . . . .	518
9.4.149 WithinPastMilliSeconds . . . . .	519
9.4.150 WithinPastMinutes . . . . .	520
9.4.151 WithinPastMonths . . . . .	520
9.4.152 WithinPastSeconds . . . . .	521
9.4.153 WithinPastWeeks . . . . .	522
9.4.154 WithinPastYears . . . . .	523
9.4.155 YearOf . . . . .	524
9.4.156 YearsBetween . . . . .	525
9.4.157 YearSpan . . . . .	526
9.4.158 Yesterday . . . . .	527
<b>10 Reference for unit 'Dos' . . . . .</b>	<b>528</b>
10.1 Used units . . . . .	528
10.2 Overview . . . . .	528
10.3 System information . . . . .	528



---

10.4 Process handling . . . . .	528
10.5 Directory and disk handling . . . . .	529
10.6 File handling . . . . .	529
10.7 File open mode constants. . . . .	530
10.8 File attributes . . . . .	530
10.9 Constants, types and variables . . . . .	531
10.9.1 Constants . . . . .	531
10.9.2 Types . . . . .	532
10.9.3 Variables . . . . .	534
10.10 Procedures and functions . . . . .	535
10.10.1 AddDisk . . . . .	535
10.10.2 DiskFree . . . . .	535
10.10.3 DiskSize . . . . .	536
10.10.4 DosExitCode . . . . .	537
10.10.5 DosVersion . . . . .	537
10.10.6 DTToUnixDate . . . . .	538
10.10.7 EnvCount . . . . .	538
10.10.8 EnvStr . . . . .	539
10.10.9 Exec . . . . .	539
10.10.10 Expand . . . . .	539
10.10.11 FindClose . . . . .	540
10.10.12 FindFirst . . . . .	540
10.10.13 FindNext . . . . .	541
10.10.14 FindSearch . . . . .	541
10.10.15 FindSplit . . . . .	542
10.10.16 GetCBreak . . . . .	543
10.10.17 GetDate . . . . .	543
10.10.18 GetEnv . . . . .	544
10.10.19 GetFAttr . . . . .	544
10.10.20 GetFTime . . . . .	545
10.10.21 GetIntVec . . . . .	546
10.10.22 GetLongName . . . . .	546
10.10.23 GetMsCount . . . . .	546
10.10.24 GetShortName . . . . .	547
10.10.25 GetTime . . . . .	547
10.10.26 GetVerify . . . . .	548
10.10.27 Inr . . . . .	548
10.10.28 Keep . . . . .	548
10.10.29 MSDos . . . . .	549
10.10.30 PackTime . . . . .	549

10.10.3	SetCBreak	550
10.10.3	SetDate	550
10.10.3	SetFAttr	550
10.10.3	SetFTime	551
10.10.3	SetIntVec	551
10.10.3	SetTime	552
10.10.3	SetVerify	552
10.10.3	SwapVectors	552
10.10.3	UnixDateToDt	553
10.10.4	UnpackTime	553
10.10.4	weekday	553
<b>11</b>	<b>Reference for unit 'dxeload'</b>	<b>554</b>
11.1	Overview	554
11.2	Procedures and functions	554
11.2.1	dxeload	554
<b>12</b>	<b>Reference for unit 'dynlibs'</b>	<b>555</b>
12.1	Overview	555
12.2	Constants, types and variables	555
12.2.1	Constants	555
12.2.2	Types	555
12.3	Procedures and functions	556
12.3.1	FreeLibrary	556
12.3.2	GetProcAddress	556
12.3.3	GetProcedureAddress	556
12.3.4	LoadLibrary	556
12.3.5	SafeLoadLibrary	557
12.3.6	UnloadLibrary	557
<b>13</b>	<b>Reference for unit 'emu387'</b>	<b>558</b>
13.1	Overview	558
13.2	Procedures and functions	558
13.2.1	npxsetup	558
<b>14</b>	<b>Reference for unit 'exeinfo'</b>	<b>559</b>
14.1	Overview	559
14.2	Constants, types and variables	559
14.2.1	Types	559
14.3	Procedures and functions	560
14.3.1	CloseExeFile	560

14.3.2	FindExeSection . . . . .	560
14.3.3	GetModuleByAddr . . . . .	560
14.3.4	OpenExeFile . . . . .	560
14.3.5	ReadDebugLink . . . . .	561
<b>15</b>	<b>Reference for unit 'getopts'</b>	<b>562</b>
15.1	Overview . . . . .	562
15.2	Constants, types and variables . . . . .	562
15.2.1	Constants . . . . .	562
15.2.2	Types . . . . .	563
15.2.3	Variables . . . . .	563
15.3	Procedures and functions . . . . .	564
15.3.1	GetLongOpts . . . . .	564
15.3.2	GetOpt . . . . .	564
<b>16</b>	<b>Reference for unit 'go32'</b>	<b>567</b>
16.1	Overview . . . . .	567
16.2	Real mode callbacks . . . . .	567
16.3	Executing software interrupts . . . . .	568
16.4	Software interrupts . . . . .	568
16.5	Hardware interrupts . . . . .	568
16.6	Disabling interrupts . . . . .	569
16.7	Creating your own interrupt handlers . . . . .	569
16.8	Protected mode interrupts vs. Real mode interrupts . . . . .	569
16.9	Handling interrupts with DPMI . . . . .	569
16.10	Interrupt redirection . . . . .	569
16.11	Processor access . . . . .	570
16.12	I/O port access . . . . .	570
16.13	dos memory access . . . . .	570
16.14	FPC specialities . . . . .	570
16.15	Selectors and descriptors . . . . .	570
16.16	What is DPMI . . . . .	571
16.17	Constants, types and variables . . . . .	571
16.17.1	Constants . . . . .	571
16.17.2	Types . . . . .	574
16.17.3	Variables . . . . .	574
16.18	Procedures and functions . . . . .	575
16.18.1	allocate_ldt_descriptors . . . . .	575
16.18.2	allocate_memory_block . . . . .	577
16.18.3	copyfromdos . . . . .	577
16.18.4	copytodos . . . . .	578

16.18.5 create_code_segment_alias_descriptor . . . . .	578
16.18.6 disable . . . . .	578
16.18.7 dpmi_dosmemfillchar . . . . .	579
16.18.8 dpmi_dosmemfillword . . . . .	579
16.18.9 dpmi_dosmemget . . . . .	579
16.18.10 dpmi_dosmemmove . . . . .	579
16.18.11 dpmi_dosmemput . . . . .	580
16.18.12 enable . . . . .	580
16.18.13 free_ldt_descriptor . . . . .	580
16.18.14 free_memory_block . . . . .	581
16.18.15 free_rm_callback . . . . .	581
16.18.16 get_cs . . . . .	581
16.18.17 get_descriptor_access_right . . . . .	582
16.18.18 get_ds . . . . .	582
16.18.19 get_exception_handler . . . . .	582
16.18.20 get_linear_addr . . . . .	582
16.18.21 get_meminfo . . . . .	583
16.18.22 get_next_selector_increment_value . . . . .	584
16.18.23 get_page_size . . . . .	584
16.18.24 get_pm_exception_handler . . . . .	585
16.18.25 get_pm_interrupt . . . . .	585
16.18.26 get_rm_callback . . . . .	585
16.18.27 get_rm_interrupt . . . . .	588
16.18.28 get_run_mode . . . . .	589
16.18.29 get_segment_base_address . . . . .	589
16.18.30 get_segment_limit . . . . .	590
16.18.31 get_ss . . . . .	590
16.18.32 global_dos_alloc . . . . .	591
16.18.33 global_dos_free . . . . .	592
16.18.34 nportb . . . . .	592
16.18.35 nportl . . . . .	593
16.18.36 nportw . . . . .	593
16.18.37 lock_code . . . . .	594
16.18.38 lock_data . . . . .	594
16.18.39 lock_linear_region . . . . .	594
16.18.40 map_device_in_memory_block . . . . .	595
16.18.41 outportb . . . . .	595
16.18.42 outportl . . . . .	596
16.18.43 outportw . . . . .	596
16.18.44 realintr . . . . .	596

16.18.45	request_linear_region . . . . .	597
16.18.46	segment_to_descriptor . . . . .	597
16.18.47	seg_fillchar . . . . .	598
16.18.48	seg_fillword . . . . .	599
16.18.49	seg_move . . . . .	599
16.18.50	set_descriptor_access_right . . . . .	600
16.18.51	set_exception_handler . . . . .	600
16.18.52	set_pm_exception_handler . . . . .	600
16.18.53	set_pm_interrupt . . . . .	600
16.18.54	set_rm_interrupt . . . . .	601
16.18.55	set_segment_base_address . . . . .	602
16.18.56	set_segment_limit . . . . .	602
16.18.57	tb_offset . . . . .	603
16.18.58	tb_segment . . . . .	603
16.18.59	tb_size . . . . .	603
16.18.60	transfer_buffer . . . . .	603
16.18.61	unlock_code . . . . .	604
16.18.62	unlock_data . . . . .	604
16.18.63	unlock_linear_region . . . . .	604
<b>17</b>	<b>Reference for unit 'gpm'</b>	<b>606</b>
17.1	Used units . . . . .	606
17.2	Overview . . . . .	606
17.3	Constants, types and variables . . . . .	606
17.3.1	Constants . . . . .	606
17.3.2	Types . . . . .	608
17.3.3	Variables . . . . .	610
17.4	Procedures and functions . . . . .	611
17.4.1	Gpm_AnyDouble . . . . .	611
17.4.2	Gpm_AnySingle . . . . .	611
17.4.3	Gpm_AnyTriple . . . . .	611
17.4.4	gpm_close . . . . .	612
17.4.5	gpm_fitvalues . . . . .	612
17.4.6	gpm_fitvaluesM . . . . .	612
17.4.7	gpm_getevent . . . . .	612
17.4.8	gpm_getsnapshot . . . . .	614
17.4.9	gpm_lowerroi . . . . .	614
17.4.10	gpm_open . . . . .	614
17.4.11	gpm_poproi . . . . .	615
17.4.12	gpm_pushroi . . . . .	615

17.4.13 gpm_raiseroi . . . . .	615
17.4.14 gpm_repeat . . . . .	615
17.4.15 Gpm_StrictDouble . . . . .	616
17.4.16 Gpm_StrictSingle . . . . .	616
17.4.17 Gpm_StrictTriple . . . . .	616
<b>18 Reference for unit 'Graph' . . . . .</b>	<b>617</b>
18.1 Overview . . . . .	617
18.2 Categorized functions: Text and font handling . . . . .	617
18.3 Categorized functions: Filled drawings . . . . .	617
18.4 Categorized functions: Drawing primitives . . . . .	618
18.5 Categorized functions: Color management . . . . .	618
18.6 Categorized functions: Screen management . . . . .	618
18.7 Categorized functions: Initialization . . . . .	619
18.8 Target specific issues: Linux . . . . .	619
18.9 Target specific issues: DOS . . . . .	620
18.10A word about mode selection . . . . .	621
18.11Requirements . . . . .	622
18.12Constants, types and variables . . . . .	622
18.12.1 Constants . . . . .	622
18.12.2 Types . . . . .	637
18.12.3 Variables . . . . .	642
18.13Procedures and functions . . . . .	644
18.13.1 Arc . . . . .	644
18.13.2 Bar . . . . .	645
18.13.3 Bar3D . . . . .	645
18.13.4 ClearDevice . . . . .	645
18.13.5 Closegraph . . . . .	645
18.13.6 DetectGraph . . . . .	646
18.13.7 DrawPoly . . . . .	646
18.13.8 Ellipse . . . . .	646
18.13.9 FillEllipse . . . . .	646
18.13.10FillPoly . . . . .	647
18.13.11FloodFill . . . . .	647
18.13.12GetArcCoords . . . . .	647
18.13.13GetAspectRatio . . . . .	648
18.13.14GetBkColor . . . . .	648
18.13.15GetColor . . . . .	648
18.13.16GetDefaultPalette . . . . .	648
18.13.17GetDirectVideo . . . . .	649

18.13.18	GetDriverName	649
18.13.19	GetFillPattern	649
18.13.20	GetFillSettings	649
18.13.21	GetGraphMode	650
18.13.22	GetLineSettings	650
18.13.23	GetMaxColor	650
18.13.24	GetMaxMode	650
18.13.25	GetMaxX	651
18.13.26	GetMaxY	651
18.13.27	GetModeName	651
18.13.28	GetModeRange	651
18.13.29	GetPalette	652
18.13.30	GetPaletteSize	652
18.13.31	GetTextSettings	652
18.13.32	GetViewSettings	652
18.13.33	GetX	653
18.13.34	GetY	653
18.13.35	GraphDefaults	653
18.13.36	GraphErrorMsg	653
18.13.37	GraphResult	654
18.13.38	InitGraph	654
18.13.39	InstallUserDriver	655
18.13.40	InstallUserFont	655
18.13.41	LineRel	655
18.13.42	LineTo	656
18.13.43	MoveRel	656
18.13.44	MoveTo	656
18.13.45	OutText	656
18.13.46	PieSlice	657
18.13.47	QueryAdapterInfo	657
18.13.48	Rectangle	657
18.13.49	RegisterBGIDriver	657
18.13.50	RegisterBGIfont	658
18.13.51	RestoreCrtMode	658
18.13.52	Sector	658
18.13.53	SetAspectRatio	658
18.13.54	SetBkColor	659
18.13.55	SetColor	659
18.13.56	SetDirectVideo	659
18.13.57	SetFillPattern	659

18.13.5	SetFillStyle	660
18.13.5	SetGraphMode	660
18.13.6	SetLineStyle	660
18.13.6	SetPalette	661
18.13.6	SetTextJustify	661
18.13.6	SetTextStyle	662
18.13.6	SetUserCharSize	662
18.13.6	SetViewPort	663
18.13.6	SetWriteMode	663
18.13.6	TextHeight	663
18.13.6	TextWidth	663
<b>19</b>	<b>Reference for unit 'heaptrc'</b>	<b>665</b>
19.1	Overview	665
19.2	Controlling HeapTrc with environment variables	665
19.3	HeapTrc Usage	666
19.4	Constants, types and variables	666
19.4.1	Constants	666
19.4.2	Types	667
19.5	Procedures and functions	667
19.5.1	DumpHeap	667
19.5.2	SetHeapExtraInfo	668
19.5.3	SetHeapTraceOutput	669
<b>20</b>	<b>Reference for unit 'ipc'</b>	<b>670</b>
20.1	Used units	670
20.2	Overview	670
20.3	Constants, types and variables	670
20.3.1	Constants	670
20.3.2	Types	673
20.4	Procedures and functions	677
20.4.1	ftok	677
20.4.2	msgctl	677
20.4.3	msgget	680
20.4.4	msgrcv	680
20.4.5	msgsnd	681
20.4.6	semctl	681
20.4.7	semget	686
20.4.8	semop	686
20.4.9	shmat	687
20.4.10	shmctl	688



20.4.11 shmdt . . . . .	690
20.4.12 shmget . . . . .	690
<b>21 Reference for unit 'keyboard'</b>	<b>691</b>
21.1 Overview . . . . .	691
21.2 Unix specific notes . . . . .	691
21.3 Writing a keyboard driver . . . . .	692
21.4 Keyboard scan codes . . . . .	693
21.5 Constants, types and variables . . . . .	693
21.5.1 Constants . . . . .	693
21.5.2 Types . . . . .	698
21.6 Procedures and functions . . . . .	699
21.6.1 AddSequence . . . . .	699
21.6.2 AddSpecialSequence . . . . .	699
21.6.3 DoneKeyboard . . . . .	700
21.6.4 FindSequence . . . . .	700
21.6.5 FunctionKeyName . . . . .	700
21.6.6 GetKeyboardDriver . . . . .	701
21.6.7 GetKeyEvent . . . . .	701
21.6.8 GetKeyEventChar . . . . .	702
21.6.9 GetKeyEventCode . . . . .	702
21.6.10 GetKeyEventFlags . . . . .	703
21.6.11 GetKeyEventShiftState . . . . .	704
21.6.12 GetKeyEventUniCode . . . . .	704
21.6.13 InitKeyboard . . . . .	705
21.6.14 IsFunctionKey . . . . .	705
21.6.15 KeyEventToString . . . . .	706
21.6.16 KeyPressed . . . . .	706
21.6.17 PollKeyEvent . . . . .	706
21.6.18 PollShiftStateEvent . . . . .	707
21.6.19 PutKeyEvent . . . . .	708
21.6.20 RawReadKey . . . . .	709
21.6.21 RawReadString . . . . .	709
21.6.22 RestoreStartMode . . . . .	709
21.6.23 SetKeyboardDriver . . . . .	709
21.6.24 ShiftStateToString . . . . .	710
21.6.25 TranslateKeyEvent . . . . .	710
21.6.26 TranslateKeyEventUniCode . . . . .	710
<b>22 Reference for unit 'lineinfo'</b>	<b>713</b>
22.1 Overview . . . . .	713

22.2	Procedures and functions	713
22.2.1	GetLineInfo	713
<b>23</b>	<b>Reference for unit 'Linux'</b>	<b>714</b>
23.1	Used units	714
23.2	Overview	714
23.3	Constants, types and variables	714
23.3.1	Constants	714
23.3.2	Types	726
23.4	Procedures and functions	728
23.4.1	capget	728
23.4.2	capset	729
23.4.3	clone	729
23.4.4	epoll_create	731
23.4.5	epoll_ctl	731
23.4.6	epoll_wait	732
23.4.7	fdatsync	732
23.4.8	futex_op	732
23.4.9	sync_file_range	733
23.4.10	Sysinfo	733
<b>24</b>	<b>Reference for unit 'Infodwrf'</b>	<b>735</b>
24.1	Overview	735
24.2	Procedures and functions	735
24.2.1	GetLineInfo	735
<b>25</b>	<b>Reference for unit 'math'</b>	<b>736</b>
25.1	Used units	736
25.2	Overview	736
25.3	Geometrical functions	737
25.4	Statistical functions	737
25.5	Number converting	737
25.6	Exponential and logarithmic functions	737
25.7	Hyperbolic functions	737
25.8	Trigonometric functions	737
25.9	Angle unit conversion	737
25.10	Min/max determination	737
25.11	Constants, types and variables	738
25.11.1	Constants	738
25.11.2	Types	739
25.12	Procedures and functions	742

25.12.1 arccos	742
25.12.2 arccosh	742
25.12.3 arcosh	743
25.12.4 arcsin	743
25.12.5 arcsinh	744
25.12.6 arctan2	744
25.12.7 arctanh	745
25.12.8 arsinh	745
25.12.9 artanh	745
25.12.10 ceil	746
25.12.11 ClearExceptions	746
25.12.12 CompareValue	746
25.12.13 cosecant	747
25.12.14 cosh	747
25.12.15 cot	748
25.12.16 cotan	748
25.12.17 csc	748
25.12.18 cycletorad	749
25.12.19 degtograd	749
25.12.20 degtorad	750
25.12.21 DivMod	750
25.12.22 EnsureRange	750
25.12.23 floor	751
25.12.24 frexp	751
25.12.25 GetExceptionMask	752
25.12.26 GetPrecisionMode	752
25.12.27 GetRoundMode	752
25.12.28 gradtodeg	752
25.12.29 gradtorad	753
25.12.30 hypot	754
25.12.31 Ifthen	754
25.12.32 InRange	754
25.12.33 ntpower	755
25.12.34 sInfinite	755
25.12.35 sNan	755
25.12.36 sZero	756
25.12.37 dexp	756
25.12.38 nxp1	757
25.12.39 log10	757
25.12.40 log2	758

25.12.41	logn	758
25.12.42	Max	759
25.12.43	MaxIntValue	759
25.12.44	maxvalue	760
25.12.45	mean	761
25.12.46	meanandstddev	762
25.12.47	Min	762
25.12.48	MinIntValue	763
25.12.49	minvalue	764
25.12.50	momentskewkurtosis	765
25.12.51	norm	765
25.12.52	operator ** (float, float): float	766
25.12.53	operator ** (Int64, Int64): Int64	766
25.12.54	popnstddev	766
25.12.55	popnvariance	767
25.12.56	power	768
25.12.57	radto cycle	768
25.12.58	radto deg	769
25.12.59	radto grad	769
25.12.60	randg	770
25.12.61	RandomFrom	770
25.12.62	RandomRange	771
25.12.63	RoundTo	771
25.12.64	SameValue	771
25.12.65	sec	772
25.12.66	secant	772
25.12.67	SetExceptionMask	772
25.12.68	SetPrecisionMode	772
25.12.69	SetRoundMode	772
25.12.70	Sign	773
25.12.71	SimpleRoundTo	773
25.12.72	sincos	773
25.12.73	sinh	774
25.12.74	stddev	774
25.12.75	sum	775
25.12.76	sumInt	776
25.12.77	sumofsquares	776
25.12.78	sumsandsquares	777
25.12.79	tan	777
25.12.80	tanh	778

25.12.8 totalvariance . . . . .	778
25.12.8 variance . . . . .	779
25.13 InvalidArgument . . . . .	780
25.13.1 Description . . . . .	780
<b>26 Reference for unit 'matrix'</b>	<b>781</b>
26.1 Overview . . . . .	781
26.2 Constants, types and variables . . . . .	782
26.2.1 Types . . . . .	782
26.3 Procedures and functions . . . . .	784
26.3.1 operator *(Tmatrix2_double, double): Tmatrix2_double . . . . .	784
26.3.2 operator *(Tmatrix2_double, Tmatrix2_double): Tmatrix2_double . . . . .	784
26.3.3 operator *(Tmatrix2_double, Tvector2_double): Tvector2_double . . . . .	785
26.3.4 operator *(Tmatrix2_extended, extended): Tmatrix2_extended . . . . .	785
26.3.5 operator *(Tmatrix2_extended, Tmatrix2_extended): Tmatrix2_extended . . . . .	785
26.3.6 operator *(Tmatrix2_extended, Tvector2_extended): Tvector2_extended . . . . .	785
26.3.7 operator *(Tmatrix2_single, single): Tmatrix2_single . . . . .	786
26.3.8 operator *(Tmatrix2_single, Tmatrix2_single): Tmatrix2_single . . . . .	786
26.3.9 operator *(Tmatrix2_single, Tvector2_single): Tvector2_single . . . . .	786
26.3.10 operator *(Tmatrix3_double, double): Tmatrix3_double . . . . .	786
26.3.11 operator *(Tmatrix3_double, Tmatrix3_double): Tmatrix3_double . . . . .	787
26.3.12 operator *(Tmatrix3_double, Tvector3_double): Tvector3_double . . . . .	787
26.3.13 operator *(Tmatrix3_extended, extended): Tmatrix3_extended . . . . .	787
26.3.14 operator *(Tmatrix3_extended, Tmatrix3_extended): Tmatrix3_extended . . . . .	787
26.3.15 operator *(Tmatrix3_extended, Tvector3_extended): Tvector3_extended . . . . .	788
26.3.16 operator *(Tmatrix3_single, single): Tmatrix3_single . . . . .	788
26.3.17 operator *(Tmatrix3_single, Tmatrix3_single): Tmatrix3_single . . . . .	788
26.3.18 operator *(Tmatrix3_single, Tvector3_single): Tvector3_single . . . . .	789
26.3.19 operator *(Tmatrix4_double, double): Tmatrix4_double . . . . .	789
26.3.20 operator *(Tmatrix4_double, Tmatrix4_double): Tmatrix4_double . . . . .	789
26.3.21 operator *(Tmatrix4_double, Tvector4_double): Tvector4_double . . . . .	789
26.3.22 operator *(Tmatrix4_extended, extended): Tmatrix4_extended . . . . .	790
26.3.23 operator *(Tmatrix4_extended, Tmatrix4_extended): Tmatrix4_extended . . . . .	790
26.3.24 operator *(Tmatrix4_extended, Tvector4_extended): Tvector4_extended . . . . .	790
26.3.25 operator *(Tmatrix4_single, single): Tmatrix4_single . . . . .	790
26.3.26 operator *(Tmatrix4_single, Tmatrix4_single): Tmatrix4_single . . . . .	791
26.3.27 operator *(Tmatrix4_single, Tvector4_single): Tvector4_single . . . . .	791
26.3.28 operator *(Tvector2_double, double): Tvector2_double . . . . .	791
26.3.29 operator *(Tvector2_double, Tvector2_double): Tvector2_double . . . . .	791
26.3.30 operator *(Tvector2_extended, extended): Tvector2_extended . . . . .	792

26.3.31 operator *(Tvector2_extended, Tvector2_extended): Tvector2_extended . . .	792
26.3.32 operator *(Tvector2_single, single): Tvector2_single . . . . .	792
26.3.33 operator *(Tvector2_single, Tvector2_single): Tvector2_single . . . . .	792
26.3.34 operator *(Tvector3_double, double): Tvector3_double . . . . .	793
26.3.35 operator *(Tvector3_double, Tvector3_double): Tvector3_double . . . . .	793
26.3.36 operator *(Tvector3_extended, extended): Tvector3_extended . . . . .	793
26.3.37 operator *(Tvector3_extended, Tvector3_extended): Tvector3_extended . . .	793
26.3.38 operator *(Tvector3_single, single): Tvector3_single . . . . .	794
26.3.39 operator *(Tvector3_single, Tvector3_single): Tvector3_single . . . . .	794
26.3.40 operator *(Tvector4_double, double): Tvector4_double . . . . .	794
26.3.41 operator *(Tvector4_double, Tvector4_double): Tvector4_double . . . . .	794
26.3.42 operator *(Tvector4_extended, extended): Tvector4_extended . . . . .	795
26.3.43 operator *(Tvector4_extended, Tvector4_extended): Tvector4_extended . . .	795
26.3.44 operator *(Tvector4_single, single): Tvector4_single . . . . .	795
26.3.45 operator *(Tvector4_single, Tvector4_single): Tvector4_single . . . . .	795
26.3.46 operator **(Tvector2_double, Tvector2_double): double . . . . .	796
26.3.47 operator **(Tvector2_extended, Tvector2_extended): extended . . . . .	796
26.3.48 operator **(Tvector2_single, Tvector2_single): single . . . . .	796
26.3.49 operator **(Tvector3_double, Tvector3_double): double . . . . .	796
26.3.50 operator **(Tvector3_extended, Tvector3_extended): extended . . . . .	797
26.3.51 operator **(Tvector3_single, Tvector3_single): single . . . . .	797
26.3.52 operator **(Tvector4_double, Tvector4_double): double . . . . .	797
26.3.53 operator **(Tvector4_extended, Tvector4_extended): extended . . . . .	797
26.3.54 operator **(Tvector4_single, Tvector4_single): single . . . . .	798
26.3.55 operator +(Tmatrix2_double, double): Tmatrix2_double . . . . .	798
26.3.56 operator +(Tmatrix2_double, Tmatrix2_double): Tmatrix2_double . . . . .	798
26.3.57 operator +(Tmatrix2_extended, extended): Tmatrix2_extended . . . . .	798
26.3.58 operator +(Tmatrix2_extended, Tmatrix2_extended): Tmatrix2_extended . .	799
26.3.59 operator +(Tmatrix2_single, single): Tmatrix2_single . . . . .	799
26.3.60 operator +(Tmatrix2_single, Tmatrix2_single): Tmatrix2_single . . . . .	799
26.3.61 operator +(Tmatrix3_double, double): Tmatrix3_double . . . . .	799
26.3.62 operator +(Tmatrix3_double, Tmatrix3_double): Tmatrix3_double . . . . .	800
26.3.63 operator +(Tmatrix3_extended, extended): Tmatrix3_extended . . . . .	800
26.3.64 operator +(Tmatrix3_extended, Tmatrix3_extended): Tmatrix3_extended . .	800
26.3.65 operator +(Tmatrix3_single, single): Tmatrix3_single . . . . .	800
26.3.66 operator +(Tmatrix3_single, Tmatrix3_single): Tmatrix3_single . . . . .	801
26.3.67 operator +(Tmatrix4_double, double): Tmatrix4_double . . . . .	801
26.3.68 operator +(Tmatrix4_double, Tmatrix4_double): Tmatrix4_double . . . . .	801
26.3.69 operator +(Tmatrix4_extended, extended): Tmatrix4_extended . . . . .	801
26.3.70 operator +(Tmatrix4_extended, Tmatrix4_extended): Tmatrix4_extended . .	802

26.3.71 operator +(Tmatrix4_single, single): Tmatrix4_single . . . . .	802
26.3.72 operator +(Tmatrix4_single, Tmatrix4_single): Tmatrix4_single . . . . .	802
26.3.73 operator +(Tvector2_double, double): Tvector2_double . . . . .	802
26.3.74 operator +(Tvector2_double, Tvector2_double): Tvector2_double . . . . .	803
26.3.75 operator +(Tvector2_extended, extended): Tvector2_extended . . . . .	803
26.3.76 operator +(Tvector2_extended, Tvector2_extended): Tvector2_extended . . .	803
26.3.77 operator +(Tvector2_single, single): Tvector2_single . . . . .	803
26.3.78 operator +(Tvector2_single, Tvector2_single): Tvector2_single . . . . .	804
26.3.79 operator +(Tvector3_double, double): Tvector3_double . . . . .	804
26.3.80 operator +(Tvector3_double, Tvector3_double): Tvector3_double . . . . .	804
26.3.81 operator +(Tvector3_extended, extended): Tvector3_extended . . . . .	804
26.3.82 operator +(Tvector3_extended, Tvector3_extended): Tvector3_extended . . .	805
26.3.83 operator +(Tvector3_single, single): Tvector3_single . . . . .	805
26.3.84 operator +(Tvector3_single, Tvector3_single): Tvector3_single . . . . .	805
26.3.85 operator +(Tvector4_double, double): Tvector4_double . . . . .	805
26.3.86 operator +(Tvector4_double, Tvector4_double): Tvector4_double . . . . .	806
26.3.87 operator +(Tvector4_extended, extended): Tvector4_extended . . . . .	806
26.3.88 operator +(Tvector4_extended, Tvector4_extended): Tvector4_extended . . .	806
26.3.89 operator +(Tvector4_single, single): Tvector4_single . . . . .	806
26.3.90 operator +(Tvector4_single, Tvector4_single): Tvector4_single . . . . .	807
26.3.91 operator -(Tmatrix2_double): Tmatrix2_double . . . . .	807
26.3.92 operator -(Tmatrix2_double, double): Tmatrix2_double . . . . .	807
26.3.93 operator -(Tmatrix2_double, Tmatrix2_double): Tmatrix2_double . . . . .	807
26.3.94 operator -(Tmatrix2_extended): Tmatrix2_extended . . . . .	808
26.3.95 operator -(Tmatrix2_extended, extended): Tmatrix2_extended . . . . .	808
26.3.96 operator -(Tmatrix2_extended, Tmatrix2_extended): Tmatrix2_extended . .	808
26.3.97 operator -(Tmatrix2_single): Tmatrix2_single . . . . .	808
26.3.98 operator -(Tmatrix2_single, single): Tmatrix2_single . . . . .	809
26.3.99 operator -(Tmatrix2_single, Tmatrix2_single): Tmatrix2_single . . . . .	809
26.3.100 operator -(Tmatrix3_double): Tmatrix3_double . . . . .	809
26.3.101 operator -(Tmatrix3_double, double): Tmatrix3_double . . . . .	809
26.3.102 operator -(Tmatrix3_double, Tmatrix3_double): Tmatrix3_double . . . . .	810
26.3.103 operator -(Tmatrix3_extended): Tmatrix3_extended . . . . .	810
26.3.104 operator -(Tmatrix3_extended, extended): Tmatrix3_extended . . . . .	810
26.3.105 operator -(Tmatrix3_extended, Tmatrix3_extended): Tmatrix3_extended . .	810
26.3.106 operator -(Tmatrix3_single): Tmatrix3_single . . . . .	811
26.3.107 operator -(Tmatrix3_single, single): Tmatrix3_single . . . . .	811
26.3.108 operator -(Tmatrix3_single, Tmatrix3_single): Tmatrix3_single . . . . .	811
26.3.109 operator -(Tmatrix4_double): Tmatrix4_double . . . . .	811
26.3.110 operator -(Tmatrix4_double, double): Tmatrix4_double . . . . .	812

26.3.111	operator -(Tmatrix4_double, Tmatrix4_double): Tmatrix4_double . . . . .	812
26.3.112	operator -(Tmatrix4_extended): Tmatrix4_extended . . . . .	812
26.3.113	operator -(Tmatrix4_extended, extended): Tmatrix4_extended . . . . .	812
26.3.114	operator -(Tmatrix4_extended, Tmatrix4_extended): Tmatrix4_extended . . .	813
26.3.115	operator -(Tmatrix4_single): Tmatrix4_single . . . . .	813
26.3.116	operator -(Tmatrix4_single, single): Tmatrix4_single . . . . .	813
26.3.117	operator -(Tmatrix4_single, Tmatrix4_single): Tmatrix4_single . . . . .	813
26.3.118	operator -(Tvector2_double): Tvector2_double . . . . .	814
26.3.119	operator -(Tvector2_double, double): Tvector2_double . . . . .	814
26.3.120	operator -(Tvector2_double, Tvector2_double): Tvector2_double . . . . .	814
26.3.121	operator -(Tvector2_extended): Tvector2_extended . . . . .	814
26.3.122	operator -(Tvector2_extended, extended): Tvector2_extended . . . . .	815
26.3.123	operator -(Tvector2_extended, Tvector2_extended): Tvector2_extended . . .	815
26.3.124	operator -(Tvector2_single): Tvector2_single . . . . .	815
26.3.125	operator -(Tvector2_single, single): Tvector2_single . . . . .	815
26.3.126	operator -(Tvector2_single, Tvector2_single): Tvector2_single . . . . .	816
26.3.127	operator -(Tvector3_double): Tvector3_double . . . . .	816
26.3.128	operator -(Tvector3_double, double): Tvector3_double . . . . .	816
26.3.129	operator -(Tvector3_double, Tvector3_double): Tvector3_double . . . . .	816
26.3.130	operator -(Tvector3_extended): Tvector3_extended . . . . .	817
26.3.131	operator -(Tvector3_extended, extended): Tvector3_extended . . . . .	817
26.3.132	operator -(Tvector3_extended, Tvector3_extended): Tvector3_extended . . .	817
26.3.133	operator -(Tvector3_single): Tvector3_single . . . . .	817
26.3.134	operator -(Tvector3_single, single): Tvector3_single . . . . .	818
26.3.135	operator -(Tvector3_single, Tvector3_single): Tvector3_single . . . . .	818
26.3.136	operator -(Tvector4_double): Tvector4_double . . . . .	818
26.3.137	operator -(Tvector4_double, double): Tvector4_double . . . . .	818
26.3.138	operator -(Tvector4_double, Tvector4_double): Tvector4_double . . . . .	819
26.3.139	operator -(Tvector4_extended): Tvector4_extended . . . . .	819
26.3.140	operator -(Tvector4_extended, extended): Tvector4_extended . . . . .	819
26.3.141	operator -(Tvector4_extended, Tvector4_extended): Tvector4_extended . . .	819
26.3.142	operator -(Tvector4_single): Tvector4_single . . . . .	820
26.3.143	operator -(Tvector4_single, single): Tvector4_single . . . . .	820
26.3.144	operator -(Tvector4_single, Tvector4_single): Tvector4_single . . . . .	820
26.3.145	operator /(Tmatrix2_double, double): Tmatrix2_double . . . . .	820
26.3.146	operator /(Tmatrix2_extended, extended): Tmatrix2_extended . . . . .	821
26.3.147	operator /(Tmatrix2_single, single): Tmatrix2_single . . . . .	821
26.3.148	operator /(Tmatrix3_double, double): Tmatrix3_double . . . . .	821
26.3.149	operator /(Tmatrix3_extended, extended): Tmatrix3_extended . . . . .	821
26.3.150	operator /(Tmatrix3_single, single): Tmatrix3_single . . . . .	822



26.3.151	operator /(Tmatrix4_double, double): Tmatrix4_double . . . . .	822
26.3.152	operator /(Tmatrix4_extended, extended): Tmatrix4_extended . . . . .	822
26.3.153	operator /(Tmatrix4_single, single): Tmatrix4_single . . . . .	822
26.3.154	operator /(Tvector2_double, double): Tvector2_double . . . . .	823
26.3.155	operator /(Tvector2_extended, extended): Tvector2_extended . . . . .	823
26.3.156	operator /(Tvector2_single, single): Tvector2_single . . . . .	823
26.3.157	operator /(Tvector3_double, double): Tvector3_double . . . . .	823
26.3.158	operator /(Tvector3_extended, extended): Tvector3_extended . . . . .	824
26.3.159	operator /(Tvector3_single, single): Tvector3_single . . . . .	824
26.3.160	operator /(Tvector4_double, double): Tvector4_double . . . . .	824
26.3.161	operator /(Tvector4_extended, extended): Tvector4_extended . . . . .	824
26.3.162	operator /(Tvector4_single, single): Tvector4_single . . . . .	825
26.3.163	operator :=(Tmatrix2_double): Tmatrix2_extended . . . . .	825
26.3.164	operator :=(Tmatrix2_double): Tmatrix2_single . . . . .	825
26.3.165	operator :=(Tmatrix2_double): Tmatrix3_double . . . . .	825
26.3.166	operator :=(Tmatrix2_double): Tmatrix3_extended . . . . .	826
26.3.167	operator :=(Tmatrix2_double): Tmatrix3_single . . . . .	826
26.3.168	operator :=(Tmatrix2_double): Tmatrix4_double . . . . .	826
26.3.169	operator :=(Tmatrix2_double): Tmatrix4_extended . . . . .	826
26.3.170	operator :=(Tmatrix2_double): Tmatrix4_single . . . . .	827
26.3.171	operator :=(Tmatrix2_extended): Tmatrix2_double . . . . .	827
26.3.172	operator :=(Tmatrix2_extended): Tmatrix2_single . . . . .	827
26.3.173	operator :=(Tmatrix2_extended): Tmatrix3_double . . . . .	827
26.3.174	operator :=(Tmatrix2_extended): Tmatrix3_extended . . . . .	828
26.3.175	operator :=(Tmatrix2_extended): Tmatrix3_single . . . . .	828
26.3.176	operator :=(Tmatrix2_extended): Tmatrix4_double . . . . .	828
26.3.177	operator :=(Tmatrix2_extended): Tmatrix4_extended . . . . .	828
26.3.178	operator :=(Tmatrix2_extended): Tmatrix4_single . . . . .	829
26.3.179	operator :=(Tmatrix2_single): Tmatrix2_double . . . . .	829
26.3.180	operator :=(Tmatrix2_single): Tmatrix2_extended . . . . .	829
26.3.181	operator :=(Tmatrix2_single): Tmatrix3_double . . . . .	829
26.3.182	operator :=(Tmatrix2_single): Tmatrix3_extended . . . . .	830
26.3.183	operator :=(Tmatrix2_single): Tmatrix3_single . . . . .	830
26.3.184	operator :=(Tmatrix2_single): Tmatrix4_double . . . . .	830
26.3.185	operator :=(Tmatrix2_single): Tmatrix4_extended . . . . .	830
26.3.186	operator :=(Tmatrix2_single): Tmatrix4_single . . . . .	831
26.3.187	operator :=(Tmatrix3_double): Tmatrix2_double . . . . .	831
26.3.188	operator :=(Tmatrix3_double): Tmatrix2_extended . . . . .	831
26.3.189	operator :=(Tmatrix3_double): Tmatrix2_single . . . . .	831
26.3.190	operator :=(Tmatrix3_double): Tmatrix3_extended . . . . .	832

26.3.19boperator :=(Tmatrix3_double): Tmatrix3_single . . . . .	832
26.3.19boperator :=(Tmatrix3_double): Tmatrix4_double . . . . .	832
26.3.19boperator :=(Tmatrix3_double): Tmatrix4_extended . . . . .	832
26.3.19boperator :=(Tmatrix3_double): Tmatrix4_single . . . . .	833
26.3.19boperator :=(Tmatrix3_extended): Tmatrix2_double . . . . .	833
26.3.19boperator :=(Tmatrix3_extended): Tmatrix2_extended . . . . .	833
26.3.19boperator :=(Tmatrix3_extended): Tmatrix2_single . . . . .	834
26.3.19boperator :=(Tmatrix3_extended): Tmatrix3_double . . . . .	834
26.3.19boperator :=(Tmatrix3_extended): Tmatrix3_single . . . . .	834
26.3.20boperator :=(Tmatrix3_extended): Tmatrix4_double . . . . .	834
26.3.20boperator :=(Tmatrix3_extended): Tmatrix4_extended . . . . .	835
26.3.20boperator :=(Tmatrix3_extended): Tmatrix4_single . . . . .	835
26.3.20boperator :=(Tmatrix3_single): Tmatrix2_double . . . . .	835
26.3.20boperator :=(Tmatrix3_single): Tmatrix2_extended . . . . .	835
26.3.20boperator :=(Tmatrix3_single): Tmatrix2_single . . . . .	836
26.3.20boperator :=(Tmatrix3_single): Tmatrix3_double . . . . .	836
26.3.20boperator :=(Tmatrix3_single): Tmatrix3_extended . . . . .	836
26.3.20boperator :=(Tmatrix3_single): Tmatrix4_double . . . . .	836
26.3.20boperator :=(Tmatrix3_single): Tmatrix4_extended . . . . .	837
26.3.21boperator :=(Tmatrix3_single): Tmatrix4_single . . . . .	837
26.3.21boperator :=(Tmatrix4_double): Tmatrix2_double . . . . .	837
26.3.21boperator :=(Tmatrix4_double): Tmatrix2_extended . . . . .	837
26.3.21boperator :=(Tmatrix4_double): Tmatrix2_single . . . . .	838
26.3.21boperator :=(Tmatrix4_double): Tmatrix3_double . . . . .	838
26.3.21boperator :=(Tmatrix4_double): Tmatrix3_extended . . . . .	838
26.3.21boperator :=(Tmatrix4_double): Tmatrix3_single . . . . .	838
26.3.21boperator :=(Tmatrix4_double): Tmatrix4_extended . . . . .	839
26.3.21boperator :=(Tmatrix4_double): Tmatrix4_single . . . . .	839
26.3.21boperator :=(Tmatrix4_extended): Tmatrix2_double . . . . .	839
26.3.22boperator :=(Tmatrix4_extended): Tmatrix2_extended . . . . .	839
26.3.22boperator :=(Tmatrix4_extended): Tmatrix2_single . . . . .	840
26.3.22boperator :=(Tmatrix4_extended): Tmatrix3_double . . . . .	840
26.3.22boperator :=(Tmatrix4_extended): Tmatrix3_extended . . . . .	840
26.3.22boperator :=(Tmatrix4_extended): Tmatrix3_single . . . . .	840
26.3.22boperator :=(Tmatrix4_extended): Tmatrix4_double . . . . .	841
26.3.22boperator :=(Tmatrix4_extended): Tmatrix4_single . . . . .	841
26.3.22boperator :=(Tmatrix4_single): Tmatrix2_double . . . . .	841
26.3.22boperator :=(Tmatrix4_single): Tmatrix2_extended . . . . .	841
26.3.22boperator :=(Tmatrix4_single): Tmatrix2_single . . . . .	842
26.3.23boperator :=(Tmatrix4_single): Tmatrix3_double . . . . .	842

26.3.23	operator :=(Tmatrix4_single): Tmatrix3_extended . . . . .	842
26.3.23	operator :=(Tmatrix4_single): Tmatrix3_single . . . . .	842
26.3.23	operator :=(Tmatrix4_single): Tmatrix4_double . . . . .	843
26.3.23	operator :=(Tmatrix4_single): Tmatrix4_extended . . . . .	843
26.3.23	operator :=(Tvector2_double): Tvector2_extended . . . . .	843
26.3.23	operator :=(Tvector2_double): Tvector2_single . . . . .	843
26.3.23	operator :=(Tvector2_double): Tvector3_double . . . . .	844
26.3.23	operator :=(Tvector2_double): Tvector3_extended . . . . .	844
26.3.23	operator :=(Tvector2_double): Tvector3_single . . . . .	844
26.3.24	operator :=(Tvector2_double): Tvector4_double . . . . .	844
26.3.24	operator :=(Tvector2_double): Tvector4_extended . . . . .	845
26.3.24	operator :=(Tvector2_double): Tvector4_single . . . . .	845
26.3.24	operator :=(Tvector2_extended): Tvector2_double . . . . .	845
26.3.24	operator :=(Tvector2_extended): Tvector2_single . . . . .	845
26.3.24	operator :=(Tvector2_extended): Tvector3_double . . . . .	846
26.3.24	operator :=(Tvector2_extended): Tvector3_extended . . . . .	846
26.3.24	operator :=(Tvector2_extended): Tvector3_single . . . . .	846
26.3.24	operator :=(Tvector2_extended): Tvector4_double . . . . .	846
26.3.24	operator :=(Tvector2_extended): Tvector4_extended . . . . .	847
26.3.25	operator :=(Tvector2_extended): Tvector4_single . . . . .	847
26.3.25	operator :=(Tvector2_single): Tvector2_double . . . . .	847
26.3.25	operator :=(Tvector2_single): Tvector2_extended . . . . .	847
26.3.25	operator :=(Tvector2_single): Tvector3_double . . . . .	848
26.3.25	operator :=(Tvector2_single): Tvector3_extended . . . . .	848
26.3.25	operator :=(Tvector2_single): Tvector3_single . . . . .	848
26.3.25	operator :=(Tvector2_single): Tvector4_double . . . . .	848
26.3.25	operator :=(Tvector2_single): Tvector4_extended . . . . .	849
26.3.25	operator :=(Tvector2_single): Tvector4_single . . . . .	849
26.3.25	operator :=(Tvector3_double): Tvector2_double . . . . .	849
26.3.26	operator :=(Tvector3_double): Tvector2_extended . . . . .	849
26.3.26	operator :=(Tvector3_double): Tvector2_single . . . . .	850
26.3.26	operator :=(Tvector3_double): Tvector3_extended . . . . .	850
26.3.26	operator :=(Tvector3_double): Tvector3_single . . . . .	850
26.3.26	operator :=(Tvector3_double): Tvector4_double . . . . .	850
26.3.26	operator :=(Tvector3_double): Tvector4_extended . . . . .	851
26.3.26	operator :=(Tvector3_double): Tvector4_single . . . . .	851
26.3.26	operator :=(Tvector3_extended): Tvector2_double . . . . .	851
26.3.26	operator :=(Tvector3_extended): Tvector2_extended . . . . .	851
26.3.26	operator :=(Tvector3_extended): Tvector2_single . . . . .	852
26.3.27	operator :=(Tvector3_extended): Tvector3_double . . . . .	852

26.3.271	operator :=(Tvector3_extended): Tvector3_single . . . . .	852
26.3.272	operator :=(Tvector3_extended): Tvector4_double . . . . .	852
26.3.273	operator :=(Tvector3_extended): Tvector4_extended . . . . .	853
26.3.274	operator :=(Tvector3_extended): Tvector4_single . . . . .	853
26.3.275	operator :=(Tvector3_single): Tvector2_double . . . . .	853
26.3.276	operator :=(Tvector3_single): Tvector2_extended . . . . .	853
26.3.277	operator :=(Tvector3_single): Tvector2_single . . . . .	854
26.3.278	operator :=(Tvector3_single): Tvector3_double . . . . .	854
26.3.279	operator :=(Tvector3_single): Tvector3_extended . . . . .	854
26.3.280	operator :=(Tvector3_single): Tvector4_double . . . . .	854
26.3.281	operator :=(Tvector3_single): Tvector4_extended . . . . .	855
26.3.282	operator :=(Tvector3_single): Tvector4_single . . . . .	855
26.3.283	operator :=(Tvector4_double): Tvector2_double . . . . .	855
26.3.284	operator :=(Tvector4_double): Tvector2_extended . . . . .	855
26.3.285	operator :=(Tvector4_double): Tvector2_single . . . . .	856
26.3.286	operator :=(Tvector4_double): Tvector3_double . . . . .	856
26.3.287	operator :=(Tvector4_double): Tvector3_extended . . . . .	856
26.3.288	operator :=(Tvector4_double): Tvector3_single . . . . .	856
26.3.289	operator :=(Tvector4_double): Tvector4_extended . . . . .	857
26.3.290	operator :=(Tvector4_double): Tvector4_single . . . . .	857
26.3.291	operator :=(Tvector4_extended): Tvector2_double . . . . .	857
26.3.292	operator :=(Tvector4_extended): Tvector2_extended . . . . .	858
26.3.293	operator :=(Tvector4_extended): Tvector2_single . . . . .	858
26.3.294	operator :=(Tvector4_extended): Tvector3_double . . . . .	858
26.3.295	operator :=(Tvector4_extended): Tvector3_extended . . . . .	858
26.3.296	operator :=(Tvector4_extended): Tvector3_single . . . . .	859
26.3.297	operator :=(Tvector4_extended): Tvector4_double . . . . .	859
26.3.298	operator :=(Tvector4_extended): Tvector4_single . . . . .	859
26.3.299	operator :=(Tvector4_single): Tvector2_double . . . . .	859
26.3.300	operator :=(Tvector4_single): Tvector2_extended . . . . .	860
26.3.301	operator :=(Tvector4_single): Tvector2_single . . . . .	860
26.3.302	operator :=(Tvector4_single): Tvector3_double . . . . .	860
26.3.303	operator :=(Tvector4_single): Tvector3_extended . . . . .	861
26.3.304	operator :=(Tvector4_single): Tvector3_single . . . . .	861
26.3.305	operator :=(Tvector4_single): Tvector4_double . . . . .	861
26.3.306	operator :=(Tvector4_single): Tvector4_extended . . . . .	861
26.3.307	operator ><(Tvector3_double, Tvector3_double): Tvector3_double . . . . .	862
26.3.308	operator ><(Tvector3_extended, Tvector3_extended): Tvector3_extended . . . . .	862
26.3.309	operator ><(Tvector3_single, Tvector3_single): Tvector3_single . . . . .	862
26.4	Tmatrix2_double . . . . .	863

26.4.1	Description	863
26.4.2	Method overview	863
26.4.3	Tmatrix2_double.init_zero	863
26.4.4	Tmatrix2_double.init_identity	863
26.4.5	Tmatrix2_double.init	863
26.4.6	Tmatrix2_double.get_column	864
26.4.7	Tmatrix2_double.get_row	864
26.4.8	Tmatrix2_double.set_column	864
26.4.9	Tmatrix2_double.set_row	864
26.4.10	Tmatrix2_double.determinant	864
26.4.11	Tmatrix2_double.inverse	864
26.4.12	Tmatrix2_double.transpose	865
26.5	Tmatrix2_extended	865
26.5.1	Description	865
26.5.2	Method overview	865
26.5.3	Tmatrix2_extended.init_zero	865
26.5.4	Tmatrix2_extended.init_identity	865
26.5.5	Tmatrix2_extended.init	866
26.5.6	Tmatrix2_extended.get_column	866
26.5.7	Tmatrix2_extended.get_row	866
26.5.8	Tmatrix2_extended.set_column	866
26.5.9	Tmatrix2_extended.set_row	866
26.5.10	Tmatrix2_extended.determinant	866
26.5.11	Tmatrix2_extended.inverse	867
26.5.12	Tmatrix2_extended.transpose	867
26.6	Tmatrix2_single	867
26.6.1	Description	867
26.6.2	Method overview	867
26.6.3	Tmatrix2_single.init_zero	867
26.6.4	Tmatrix2_single.init_identity	868
26.6.5	Tmatrix2_single.init	868
26.6.6	Tmatrix2_single.get_column	868
26.6.7	Tmatrix2_single.get_row	868
26.6.8	Tmatrix2_single.set_column	868
26.6.9	Tmatrix2_single.set_row	869
26.6.10	Tmatrix2_single.determinant	869
26.6.11	Tmatrix2_single.inverse	869
26.6.12	Tmatrix2_single.transpose	869
26.7	Tmatrix3_double	869
26.7.1	Description	869

26.7.2	Method overview	870
26.7.3	Tmatrix3_double.init_zero	870
26.7.4	Tmatrix3_double.init_identity	870
26.7.5	Tmatrix3_double.init	870
26.7.6	Tmatrix3_double.get_column	870
26.7.7	Tmatrix3_double.get_row	871
26.7.8	Tmatrix3_double.set_column	871
26.7.9	Tmatrix3_double.set_row	871
26.7.10	Tmatrix3_double.determinant	871
26.7.11	Tmatrix3_double.inverse	871
26.7.12	Tmatrix3_double.transpose	871
26.8	Tmatrix3_extended	872
26.8.1	Description	872
26.8.2	Method overview	872
26.8.3	Tmatrix3_extended.init_zero	872
26.8.4	Tmatrix3_extended.init_identity	872
26.8.5	Tmatrix3_extended.init	872
26.8.6	Tmatrix3_extended.get_column	873
26.8.7	Tmatrix3_extended.get_row	873
26.8.8	Tmatrix3_extended.set_column	873
26.8.9	Tmatrix3_extended.set_row	873
26.8.10	Tmatrix3_extended.determinant	873
26.8.11	Tmatrix3_extended.inverse	873
26.8.12	Tmatrix3_extended.transpose	874
26.9	Tmatrix3_single	874
26.9.1	Description	874
26.9.2	Method overview	874
26.9.3	Tmatrix3_single.init_zero	874
26.9.4	Tmatrix3_single.init_identity	874
26.9.5	Tmatrix3_single.init	875
26.9.6	Tmatrix3_single.get_column	875
26.9.7	Tmatrix3_single.get_row	875
26.9.8	Tmatrix3_single.set_column	875
26.9.9	Tmatrix3_single.set_row	875
26.9.10	Tmatrix3_single.determinant	876
26.9.11	Tmatrix3_single.inverse	876
26.9.12	Tmatrix3_single.transpose	876
26.10	Tmatrix4_double	876
26.10.1	Description	876
26.10.2	Method overview	876

26.10.3	<code>Tmatrix4_double.init_zero</code>	877
26.10.4	<code>Tmatrix4_double.init_identity</code>	877
26.10.5	<code>Tmatrix4_double.init</code>	877
26.10.6	<code>Tmatrix4_double.get_column</code>	877
26.10.7	<code>Tmatrix4_double.get_row</code>	877
26.10.8	<code>Tmatrix4_double.set_column</code>	878
26.10.9	<code>Tmatrix4_double.set_row</code>	878
26.10.10	<code>Tmatrix4_double.determinant</code>	878
26.10.11	<code>Tmatrix4_double.inverse</code>	878
26.10.12	<code>Tmatrix4_double.transpose</code>	878
26.11	<code>Tmatrix4_extended</code>	879
26.11.1	Description	879
26.11.2	Method overview	879
26.11.3	<code>Tmatrix4_extended.init_zero</code>	879
26.11.4	<code>Tmatrix4_extended.init_identity</code>	879
26.11.5	<code>Tmatrix4_extended.init</code>	879
26.11.6	<code>Tmatrix4_extended.get_column</code>	880
26.11.7	<code>Tmatrix4_extended.get_row</code>	880
26.11.8	<code>Tmatrix4_extended.set_column</code>	880
26.11.9	<code>Tmatrix4_extended.set_row</code>	880
26.11.10	<code>Tmatrix4_extended.determinant</code>	880
26.11.11	<code>Tmatrix4_extended.inverse</code>	881
26.11.12	<code>Tmatrix4_extended.transpose</code>	881
26.12	<code>Tmatrix4_single</code>	881
26.12.1	Description	881
26.12.2	Method overview	881
26.12.3	<code>Tmatrix4_single.init_zero</code>	881
26.12.4	<code>Tmatrix4_single.init_identity</code>	882
26.12.5	<code>Tmatrix4_single.init</code>	882
26.12.6	<code>Tmatrix4_single.get_column</code>	882
26.12.7	<code>Tmatrix4_single.get_row</code>	882
26.12.8	<code>Tmatrix4_single.set_column</code>	882
26.12.9	<code>Tmatrix4_single.set_row</code>	883
26.12.10	<code>Tmatrix4_single.determinant</code>	883
26.12.11	<code>Tmatrix4_single.inverse</code>	883
26.12.12	<code>Tmatrix4_single.transpose</code>	883
26.13	<code>Tvector2_double</code>	883
26.13.1	Description	883
26.13.2	Method overview	884
26.13.3	<code>Tvector2_double.init_zero</code>	884

---

26.13.4	<a href="#">Tvector2_double.init_one</a>	884
26.13.5	<a href="#">Tvector2_double.init</a>	884
26.13.6	<a href="#">Tvector2_double.length</a>	884
26.13.7	<a href="#">Tvector2_double.squared_length</a>	884
26.14	<a href="#">Tvector2_extended</a>	885
26.14.1	<a href="#">Description</a>	885
26.14.2	<a href="#">Method overview</a>	885
26.14.3	<a href="#">Tvector2_extended.init_zero</a>	885
26.14.4	<a href="#">Tvector2_extended.init_one</a>	885
26.14.5	<a href="#">Tvector2_extended.init</a>	885
26.14.6	<a href="#">Tvector2_extended.length</a>	885
26.14.7	<a href="#">Tvector2_extended.squared_length</a>	886
26.15	<a href="#">Tvector2_single</a>	886
26.15.1	<a href="#">Description</a>	886
26.15.2	<a href="#">Method overview</a>	886
26.15.3	<a href="#">Tvector2_single.init_zero</a>	886
26.15.4	<a href="#">Tvector2_single.init_one</a>	886
26.15.5	<a href="#">Tvector2_single.init</a>	886
26.15.6	<a href="#">Tvector2_single.length</a>	887
26.15.7	<a href="#">Tvector2_single.squared_length</a>	887
26.16	<a href="#">Tvector3_double</a>	887
26.16.1	<a href="#">Description</a>	887
26.16.2	<a href="#">Method overview</a>	887
26.16.3	<a href="#">Tvector3_double.init_zero</a>	887
26.16.4	<a href="#">Tvector3_double.init_one</a>	887
26.16.5	<a href="#">Tvector3_double.init</a>	888
26.16.6	<a href="#">Tvector3_double.length</a>	888
26.16.7	<a href="#">Tvector3_double.squared_length</a>	888
26.17	<a href="#">Tvector3_extended</a>	888
26.17.1	<a href="#">Description</a>	888
26.17.2	<a href="#">Method overview</a>	888
26.17.3	<a href="#">Tvector3_extended.init_zero</a>	888
26.17.4	<a href="#">Tvector3_extended.init_one</a>	889
26.17.5	<a href="#">Tvector3_extended.init</a>	889
26.17.6	<a href="#">Tvector3_extended.length</a>	889
26.17.7	<a href="#">Tvector3_extended.squared_length</a>	889
26.18	<a href="#">Tvector3_single</a>	889
26.18.1	<a href="#">Description</a>	889
26.18.2	<a href="#">Method overview</a>	889
26.18.3	<a href="#">Tvector3_single.init_zero</a>	890



26.18.4 Tvector3_single.init_one . . . . .	890
26.18.5 Tvector3_single.init . . . . .	890
26.18.6 Tvector3_single.length . . . . .	890
26.18.7 Tvector3_single.squared_length . . . . .	890
26.19 Tvector4_double . . . . .	890
26.19.1 Description . . . . .	890
26.19.2 Method overview . . . . .	891
26.19.3 Tvector4_double.init_zero . . . . .	891
26.19.4 Tvector4_double.init_one . . . . .	891
26.19.5 Tvector4_double.init . . . . .	891
26.19.6 Tvector4_double.length . . . . .	891
26.19.7 Tvector4_double.squared_length . . . . .	891
26.20 Tvector4_extended . . . . .	892
26.20.1 Description . . . . .	892
26.20.2 Method overview . . . . .	892
26.20.3 Tvector4_extended.init_zero . . . . .	892
26.20.4 Tvector4_extended.init_one . . . . .	892
26.20.5 Tvector4_extended.init . . . . .	892
26.20.6 Tvector4_extended.length . . . . .	892
26.20.7 Tvector4_extended.squared_length . . . . .	893
26.21 Tvector4_single . . . . .	893
26.21.1 Description . . . . .	893
26.21.2 Method overview . . . . .	893
26.21.3 Tvector4_single.init_zero . . . . .	893
26.21.4 Tvector4_single.init_one . . . . .	893
26.21.5 Tvector4_single.init . . . . .	893
26.21.6 Tvector4_single.length . . . . .	894
26.21.7 Tvector4_single.squared_length . . . . .	894
<b>27 Reference for unit 'mmx'</b>	<b>895</b>
27.1 Overview . . . . .	895
27.2 Constants, types and variables . . . . .	895
27.2.1 Constants . . . . .	895
27.2.2 Types . . . . .	896
27.3 Procedures and functions . . . . .	897
27.3.1 emms . . . . .	897
27.3.2 femms . . . . .	897
<b>28 Reference for unit 'Mouse'</b>	<b>898</b>
28.1 Overview . . . . .	898
28.2 Writing a custom mouse driver . . . . .	898

28.3	Constants, types and variables	898
28.3.1	Constants	898
28.3.2	Types	899
28.3.3	Variables	900
28.4	Procedures and functions	900
28.4.1	DetectMouse	900
28.4.2	DoneMouse	901
28.4.3	GetMouseButtons	901
28.4.4	GetMouseDriver	902
28.4.5	GetMouseEvent	902
28.4.6	GetMouseX	902
28.4.7	GetMouseY	903
28.4.8	HideMouse	903
28.4.9	InitMouse	904
28.4.10	PollMouseEvent	905
28.4.11	PutMouseEvent	905
28.4.12	SetMouseDriver	905
28.4.13	SetMouseXY	906
28.4.14	ShowMouse	906
<b>29</b>	<b>Reference for unit 'Objects'</b>	<b>907</b>
29.1	Overview	907
29.2	Constants, types and variables	907
29.2.1	Constants	907
29.2.2	Types	909
29.2.3	Variables	913
29.3	Procedures and functions	913
29.3.1	Abstract	913
29.3.2	CallPointerConstructor	913
29.3.3	CallPointerLocal	914
29.3.4	CallPointerMethod	914
29.3.5	CallPointerMethodLocal	914
29.3.6	CallVoidConstructor	915
29.3.7	CallVoidLocal	915
29.3.8	CallVoidMethod	915
29.3.9	CallVoidMethodLocal	916
29.3.10	DisposeStr	916
29.3.11	LongDiv	916
29.3.12	LongMul	916
29.3.13	NewStr	917

29.3.14 RegisterObjects . . . . .	917
29.3.15 RegisterType . . . . .	918
29.3.16 SetStr . . . . .	919
29.4 TBufStream . . . . .	920
29.4.1 Description . . . . .	920
29.4.2 Method overview . . . . .	920
29.4.3 TBufStream.Init . . . . .	920
29.4.4 TBufStream.Done . . . . .	921
29.4.5 TBufStream.Close . . . . .	921
29.4.6 TBufStream.Flush . . . . .	921
29.4.7 TBufStream.Truncate . . . . .	922
29.4.8 TBufStream.Seek . . . . .	922
29.4.9 TBufStream.Open . . . . .	923
29.4.10 TBufStream.Read . . . . .	923
29.4.11 TBufStream.Write . . . . .	923
29.5 TCollection . . . . .	924
29.5.1 Description . . . . .	924
29.5.2 Method overview . . . . .	924
29.5.3 TCollection.Init . . . . .	924
29.5.4 TCollection.Load . . . . .	925
29.5.5 TCollection.Done . . . . .	925
29.5.6 TCollection.At . . . . .	926
29.5.7 TCollection.IndexOf . . . . .	926
29.5.8 TCollection.GetItem . . . . .	927
29.5.9 TCollection.LastThat . . . . .	928
29.5.10 TCollection.FirstThat . . . . .	928
29.5.11 TCollection.Pack . . . . .	929
29.5.12 TCollection.FreeAll . . . . .	930
29.5.13 TCollection.DeleteAll . . . . .	931
29.5.14 TCollection.Free . . . . .	932
29.5.15 TCollection.Insert . . . . .	932
29.5.16 TCollection.Delete . . . . .	933
29.5.17 TCollection.AtFree . . . . .	933
29.5.18 TCollection.FreeItem . . . . .	934
29.5.19 TCollection.AtDelete . . . . .	934
29.5.20 TCollection.ForEach . . . . .	935
29.5.21 TCollection.SetLimit . . . . .	936
29.5.22 TCollection.Error . . . . .	936
29.5.23 TCollection.AtPut . . . . .	937
29.5.24 TCollection.AtInsert . . . . .	937

---

29.5.25	TCollection.Store	938
29.5.26	TCollection.PutItem	938
29.6	TDosStream	938
29.6.1	Description	938
29.6.2	Method overview	939
29.6.3	TDosStream.Init	939
29.6.4	TDosStream.Done	939
29.6.5	TDosStream.Close	940
29.6.6	TDosStream.Truncate	940
29.6.7	TDosStream.Seek	941
29.6.8	TDosStream.Open	942
29.6.9	TDosStream.Read	942
29.6.10	TDosStream.Write	943
29.7	TMemoryStream	943
29.7.1	Description	943
29.7.2	Method overview	943
29.7.3	TMemoryStream.Init	943
29.7.4	TMemoryStream.Done	944
29.7.5	TMemoryStream.Truncate	944
29.7.6	TMemoryStream.Read	945
29.7.7	TMemoryStream.Write	945
29.8	TObject	945
29.8.1	Description	945
29.8.2	Method overview	945
29.8.3	TObject.Init	945
29.8.4	TObject.Free	946
29.8.5	TObject.Is_Object	946
29.8.6	TObject.Done	947
29.9	TPoint	947
29.9.1	Description	947
29.10	TRect	947
29.10.1	Description	947
29.10.2	Method overview	947
29.10.3	TRect.Empty	948
29.10.4	TRect.Equals	949
29.10.5	TRect.Contains	949
29.10.6	TRect.Copy	949
29.10.7	TRect.Union	950
29.10.8	TRect.Intersect	950
29.10.9	TRect.Move	951

---

29.10.10 TRect.Grow . . . . .	952
29.10.11 TRect.Assign . . . . .	952
29.11 TResourceCollection . . . . .	953
29.11.1 Description . . . . .	953
29.11.2 Method overview . . . . .	953
29.11.3 TResourceCollection.KeyOf . . . . .	953
29.11.4 TResourceCollection.GetItem . . . . .	954
29.11.5 TResourceCollection.FreeItem . . . . .	954
29.11.6 TResourceCollection.PutItem . . . . .	954
29.12 TResourceFile . . . . .	954
29.12.1 Description . . . . .	954
29.12.2 Method overview . . . . .	955
29.12.3 TResourceFile.Init . . . . .	955
29.12.4 TResourceFile.Done . . . . .	955
29.12.5 TResourceFile.Count . . . . .	955
29.12.6 TResourceFile.KeyAt . . . . .	956
29.12.7 TResourceFile.Get . . . . .	956
29.12.8 TResourceFile.SwitchTo . . . . .	956
29.12.9 TResourceFile.Flush . . . . .	956
29.12.10 TResourceFile.Delete . . . . .	957
29.12.11 TResourceFile.Put . . . . .	957
29.13 TSortedCollection . . . . .	957
29.13.1 Description . . . . .	957
29.13.2 Method overview . . . . .	958
29.13.3 TSortedCollection.Init . . . . .	958
29.13.4 TSortedCollection.Load . . . . .	958
29.13.5 TSortedCollection.KeyOf . . . . .	958
29.13.6 TSortedCollection.IndexOf . . . . .	959
29.13.7 TSortedCollection.Compare . . . . .	959
29.13.8 TSortedCollection.Search . . . . .	960
29.13.9 TSortedCollection.Insert . . . . .	961
29.13.10 TSortedCollection.Store . . . . .	962
29.14 TStrCollection . . . . .	963
29.14.1 Description . . . . .	963
29.14.2 Method overview . . . . .	963
29.14.3 TStrCollection.Compare . . . . .	963
29.14.4 TStrCollection.GetItem . . . . .	964
29.14.5 TStrCollection.FreeItem . . . . .	964
29.14.6 TStrCollection.PutItem . . . . .	964
29.15 TStream . . . . .	965

29.15.1 Description . . . . .	965
29.15.2 Method overview . . . . .	965
29.15.3 TStream.Init . . . . .	965
29.15.4 TStream.Get . . . . .	965
29.15.5 TStream.StrRead . . . . .	966
29.15.6 TStream.GetPos . . . . .	967
29.15.7 TStream.GetSize . . . . .	967
29.15.8 TStream.ReadStr . . . . .	968
29.15.9 TStream.Open . . . . .	969
29.15.10 TStream.Close . . . . .	969
29.15.11 TStream.Reset . . . . .	969
29.15.12 TStream.Flush . . . . .	970
29.15.13 TStream.Truncate . . . . .	970
29.15.14 TStream.Put . . . . .	970
29.15.15 TStream.StrWrite . . . . .	971
29.15.16 TStream.WriteStr . . . . .	971
29.15.17 TStream.Seek . . . . .	971
29.15.18 TStream.Error . . . . .	971
29.15.19 TStream.Read . . . . .	972
29.15.20 TStream.Write . . . . .	972
29.15.21 TStream.CopyFrom . . . . .	973
29.16 TStringCollection . . . . .	973
29.16.1 Description . . . . .	973
29.16.2 Method overview . . . . .	974
29.16.3 TStringCollection.GetItem . . . . .	974
29.16.4 TStringCollection.Compare . . . . .	974
29.16.5 TStringCollection.FreeItem . . . . .	975
29.16.6 TStringCollection.PutItem . . . . .	975
29.17 TStringList . . . . .	975
29.17.1 Description . . . . .	975
29.17.2 Method overview . . . . .	976
29.17.3 TStringList.Load . . . . .	976
29.17.4 TStringList.Done . . . . .	976
29.17.5 TStringList.Get . . . . .	976
29.18 TStrListMaker . . . . .	977
29.18.1 Description . . . . .	977
29.18.2 Method overview . . . . .	977
29.18.3 TStrListMaker.Init . . . . .	977
29.18.4 TStrListMaker.Done . . . . .	977
29.18.5 TStrListMaker.Put . . . . .	977

29.18.6 TStrListMaker.Store . . . . .	978
29.19 TUnSortedStrCollection . . . . .	978
29.19.1 Description . . . . .	978
29.19.2 Method overview . . . . .	978
29.19.3 TUnSortedStrCollection.Insert . . . . .	978
<b>30 Reference for unit 'objpas' . . . . .</b>	<b>980</b>
30.1 Overview . . . . .	980
30.2 Constants, types and variables . . . . .	980
30.2.1 Constants . . . . .	980
30.2.2 Types . . . . .	980
30.2.3 Variables . . . . .	981
30.3 Procedures and functions . . . . .	982
30.3.1 FinalizeResourceTables . . . . .	982
30.3.2 GetResourceStringCurrentValue . . . . .	982
30.3.3 GetResourceStringDefaultValue . . . . .	983
30.3.4 GetResourceStringHash . . . . .	983
30.3.5 GetResourceStringName . . . . .	984
30.3.6 Hash . . . . .	984
30.3.7 LoadResString . . . . .	985
30.3.8 ResetResourceTables . . . . .	985
30.3.9 ResourceStringCount . . . . .	986
30.3.10 ResourceStringTableCount . . . . .	986
30.3.11 SetResourceStrings . . . . .	986
30.3.12 SetResourceStringValue . . . . .	987
30.3.13 SetUnitResourceStrings . . . . .	988
<b>31 Reference for unit 'oldlinux' . . . . .</b>	<b>989</b>
31.1 Overview . . . . .	989
31.2 Utility routines . . . . .	989
31.3 Terminal functions . . . . .	990
31.4 System information . . . . .	990
31.5 Signals . . . . .	990
31.6 Process handling . . . . .	991
31.7 Directory handling routines . . . . .	991
31.8 Pipes, FIFOs and streams . . . . .	992
31.9 General File handling routines . . . . .	992
31.10 File Input/Output routines . . . . .	992
31.11 Constants, types and variables . . . . .	992
31.11.1 Constants . . . . .	992
31.11.2 Types . . . . .	1031

31.11.3 Variables . . . . .	1040
31.12 Procedures and functions . . . . .	1041
31.12.1 Access . . . . .	1041
31.12.2 Alarm . . . . .	1042
31.12.3 AssignPipe . . . . .	1042
31.12.4 AssignStream . . . . .	1043
31.12.5 Basename . . . . .	1045
31.12.6 CFMakeRaw . . . . .	1045
31.12.7 CFSetISpeed . . . . .	1046
31.12.8 CFSetOSpeed . . . . .	1046
31.12.9 Chmod . . . . .	1046
31.12.10 Chown . . . . .	1047
31.12.11 Clone . . . . .	1048
31.12.12 CloseDir . . . . .	1050
31.12.13 CreateShellArgV . . . . .	1051
31.12.14 Dirname . . . . .	1051
31.12.15 Dup . . . . .	1052
31.12.16 Dup2 . . . . .	1053
31.12.17 EpochToLocal . . . . .	1053
31.12.18 Execl . . . . .	1054
31.12.19 Execle . . . . .	1055
31.12.20 Execlp . . . . .	1056
31.12.21 Execv . . . . .	1056
31.12.22 Execve . . . . .	1057
31.12.23 Execvp . . . . .	1058
31.12.24 ExitProcess . . . . .	1059
31.12.25 Fcntl . . . . .	1060
31.12.26 fdClose . . . . .	1060
31.12.27 fdFlush . . . . .	1060
31.12.28 fdOpen . . . . .	1061
31.12.29 fdRead . . . . .	1062
31.12.30 fdSeek . . . . .	1063
31.12.31 fdTruncate . . . . .	1063
31.12.32 fdWrite . . . . .	1064
31.12.33 FD_Clr . . . . .	1064
31.12.34 FD_IsSet . . . . .	1064
31.12.35 FD_Set . . . . .	1065
31.12.36 FD_Zero . . . . .	1065
31.12.37 FExpand . . . . .	1065
31.12.38 Flock . . . . .	1066



31.12.39FNMatch . . . . .	1066
31.12.40Fork . . . . .	1067
31.12.41FReName . . . . .	1067
31.12.42FSearch . . . . .	1068
31.12.43FSplit . . . . .	1068
31.12.44FSSStat . . . . .	1069
31.12.45FStat . . . . .	1070
31.12.46GetDate . . . . .	1071
31.12.47GetDateTime . . . . .	1072
31.12.48GetDomainName . . . . .	1072
31.12.49GetEGid . . . . .	1073
31.12.50GetEnv . . . . .	1073
31.12.51GetEpochTime . . . . .	1074
31.12.52GetEUid . . . . .	1074
31.12.53GetFS . . . . .	1075
31.12.54GetGid . . . . .	1075
31.12.55GetHostName . . . . .	1076
31.12.56GetLocalTimezone . . . . .	1076
31.12.57GetPid . . . . .	1077
31.12.58GetPPid . . . . .	1077
31.12.59GetPriority . . . . .	1078
31.12.60GetTime . . . . .	1078
31.12.61GetTimeOfDay . . . . .	1079
31.12.62GetTimezoneFile . . . . .	1079
31.12.63GetUid . . . . .	1079
31.12.64Glob . . . . .	1080
31.12.65Globfree . . . . .	1081
31.12.66IOCtl . . . . .	1081
31.12.67IOperm . . . . .	1081
31.12.68IoPL . . . . .	1082
31.12.69IsATTY . . . . .	1082
31.12.70Kill . . . . .	1082
31.12.71Link . . . . .	1083
31.12.72LocalToEpoch . . . . .	1084
31.12.73Lstat . . . . .	1085
31.12.74mkFifo . . . . .	1086
31.12.75MMap . . . . .	1086
31.12.76MUnMap . . . . .	1088
31.12.77NanoSleep . . . . .	1088
31.12.78Nice . . . . .	1089

31.12.7	Octal	1090
31.12.8	OpenDir	1090
31.12.8	Pause	1091
31.12.8	PClose	1092
31.12.8	POpen	1092
31.12.8	ReadDir	1093
31.12.8	ReadLink	1093
31.12.8	ReadPort	1094
31.12.8	ReadPortB	1094
31.12.8	ReadPortL	1095
31.12.8	ReadPortW	1095
31.12.9	ReadTimezoneFile	1095
31.12.9	SeekDir	1095
31.12.9	Select	1095
31.12.9	SelectText	1097
31.12.9	SetDate	1097
31.12.9	SetDateTime	1097
31.12.9	SetPriority	1098
31.12.9	SetTime	1098
31.12.9	Shell	1098
31.12.9	SigAction	1099
31.12.10	Signal	1100
31.12.10	SigPending	1101
31.12.10	SigProcMask	1101
31.12.10	SigRaise	1102
31.12.10	SigSuspend	1103
31.12.10	StringToPPChar	1103
31.12.10	SymLink	1104
31.12.10	SysCall	1105
31.12.10	Sysinfo	1105
31.12.10	_ISBLK	1106
31.12.10	_ISCHR	1107
31.12.10	_ISDIR	1107
31.12.10	_ISFIFO	1107
31.12.10	_ISLNK	1107
31.12.10	_ISREG	1108
31.12.10	_ISSOCK	1108
31.12.10	TCDrain	1109
31.12.10	TCFlow	1109
31.12.10	TCFlush	1109

31.12.1	<del>EC</del> GetAttr . . . . .	1110
31.12.1	<del>EC</del> GetPGrp . . . . .	1110
31.12.1	<del>EC</del> SendBreak . . . . .	1111
31.12.1	<del>EC</del> SetAttr . . . . .	1111
31.12.1	<del>EC</del> SetPGrp . . . . .	1112
31.12.1	<del>EC</del> llDir . . . . .	1112
31.12.1	<del>EC</del> Yname . . . . .	1112
31.12.1	<del>EC</del> mask . . . . .	1113
31.12.1	<del>EC</del> name . . . . .	1113
31.12.1	<del>EC</del> nLink . . . . .	1113
31.12.1	<del>EC</del> time . . . . .	1114
31.12.1	<del>EC</del> WaitPid . . . . .	1115
31.12.1	<del>EC</del> WaitProcess . . . . .	1115
31.12.1	<del>EC</del> EXITSTATUS . . . . .	1116
31.12.1	<del>EC</del> WIFEXITED . . . . .	1116
31.12.1	<del>EC</del> WIFSIGNALED . . . . .	1116
31.12.1	<del>EC</del> WIFSTOPPED . . . . .	1116
31.12.1	<del>EC</del> WritePort . . . . .	1117
31.12.1	<del>EC</del> WritePortB . . . . .	1117
31.12.1	<del>EC</del> WritePortL . . . . .	1117
31.12.1	<del>EC</del> WritePortW . . . . .	1117
31.12.1	<del>EC</del> WSTOPSIG . . . . .	1117
31.12.1	<del>EC</del> WTERMSIG . . . . .	1117
31.12.1	<del>EC</del> _EXITCODE . . . . .	1118
31.12.1	<del>EC</del> _STOPCODE . . . . .	1118
<b>32</b>	<b>Reference for unit 'ports' . . . . .</b>	<b>1119</b>
32.1	Overview . . . . .	1119
32.2	Constants, types and variables . . . . .	1119
32.2.1	Variables . . . . .	1119
32.3	tport . . . . .	1120
32.3.1	Description . . . . .	1120
32.3.2	Property overview . . . . .	1120
32.3.3	tport.pp . . . . .	1120
32.4	tportl . . . . .	1120
32.4.1	Description . . . . .	1120
32.4.2	Property overview . . . . .	1121
32.4.3	tportl.pp . . . . .	1121
32.5	tportw . . . . .	1121
32.5.1	Description . . . . .	1121

32.5.2	Property overview	1121
32.5.3	tportw.pp	1121
<b>33</b>	<b>Reference for unit 'printer'</b>	<b>1122</b>
33.1	Overview	1122
33.2	Constants, types and variables	1122
33.2.1	Variables	1122
33.3	Procedures and functions	1122
33.3.1	AssignLst	1122
33.3.2	InitPrinter	1123
33.3.3	IsLstAvailable	1123
<b>34</b>	<b>Reference for unit 'Sockets'</b>	<b>1124</b>
34.1	Used units	1124
34.2	Overview	1124
34.3	Constants, types and variables	1124
34.3.1	Constants	1124
34.3.2	Types	1145
34.4	Procedures and functions	1148
34.4.1	Accept	1148
34.4.2	Bind	1150
34.4.3	CloseSocket	1150
34.4.4	Connect	1150
34.4.5	fpaccept	1152
34.4.6	fpbind	1154
34.4.7	fpconnect	1154
34.4.8	fpgetpeername	1156
34.4.9	fpgetsockname	1156
34.4.10	fpgetsockopt	1157
34.4.11	fplisten	1157
34.4.12	fprecv	1157
34.4.13	fprecvfrom	1158
34.4.14	fp send	1158
34.4.15	fp sendto	1159
34.4.16	fpsetsockopt	1159
34.4.17	fpshutdown	1160
34.4.18	fpsocket	1160
34.4.19	fpsocketpair	1161
34.4.20	HostAddrToStr	1161
34.4.21	HostAddrToStr6	1161
34.4.22	HostToNet	1161

34.4.23 htonl	1162
34.4.24 htons	1162
34.4.25 NetAddrToStr	1162
34.4.26 NetAddrToStr6	1162
34.4.27 NetToHost	1163
34.4.28 NToHl	1163
34.4.29 NToHs	1163
34.4.30 ShortHostToNet	1163
34.4.31 ShortNetToHost	1164
34.4.32 Sock2File	1164
34.4.33 Sock2Text	1164
34.4.34 socketerror	1164
34.4.35 Str2UnixSockAddr	1165
34.4.36 StrToHostAddr	1165
34.4.37 StrToHostAddr6	1165
34.4.38 StrToNetAddr	1165
34.4.39 StrToNetAddr6	1166
<b>35 Reference for unit 'strings'</b>	<b>1167</b>
35.1 Overview	1167
35.2 Procedures and functions	1167
35.2.1 stralloc	1167
35.2.2 strcat	1167
35.2.3 strcmp	1168
35.2.4 strcpy	1168
35.2.5 strdispose	1169
35.2.6 strecopy	1169
35.2.7 strend	1170
35.2.8 stricmp	1171
35.2.9 stripos	1171
35.2.10 striscan	1172
35.2.11 strlcat	1172
35.2.12 strlcomp	1173
35.2.13 strlcopy	1173
35.2.14 strlen	1174
35.2.15 strlicomp	1174
35.2.16 strlower	1175
35.2.17 strmove	1175
35.2.18 strnew	1176
35.2.19 strpas	1177

35.2.20	strcpy	1177
35.2.21	strpos	1178
35.2.22	striscan	1178
35.2.23	strrscan	1179
35.2.24	strscan	1179
35.2.25	strupper	1179
<b>36</b>	<b>Reference for unit 'strutils'</b>	<b>1180</b>
36.1	Used units	1180
36.2	Constants, types and variables	1180
36.2.1	Resource strings	1180
36.2.2	Constants	1180
36.2.3	Types	1181
36.3	Procedures and functions	1182
36.3.1	AddChar	1182
36.3.2	AddCharR	1182
36.3.3	AnsiContainsStr	1182
36.3.4	AnsiContainsText	1182
36.3.5	AnsiEndsStr	1183
36.3.6	AnsiEndsText	1183
36.3.7	AnsiIndexStr	1183
36.3.8	AnsiIndexText	1184
36.3.9	AnsiLeftStr	1184
36.3.10	AnsiMatchStr	1184
36.3.11	AnsiMatchText	1185
36.3.12	AnsiMidStr	1185
36.3.13	AnsiProperCase	1185
36.3.14	AnsiReplaceStr	1186
36.3.15	AnsiReplaceText	1186
36.3.16	AnsiResemblesText	1186
36.3.17	AnsiReverseString	1186
36.3.18	AnsiRightStr	1187
36.3.19	AnsiStartsStr	1187
36.3.20	AnsiStartsText	1187
36.3.21	BinToHex	1188
36.3.22	Copy2Space	1188
36.3.23	Copy2SpaceDel	1188
36.3.24	Copy2Symb	1189
36.3.25	Copy2SymbDel	1189
36.3.26	Dec2Numb	1189

36.3.27 DecodeSoundexInt . . . . .	1189
36.3.28 DecodeSoundexWord . . . . .	1190
36.3.29 DelChars . . . . .	1190
36.3.30 DelSpace . . . . .	1190
36.3.31 DelSpace1 . . . . .	1190
36.3.32 DupeString . . . . .	1191
36.3.33 ExtractDelimited . . . . .	1191
36.3.34 ExtractSubstr . . . . .	1191
36.3.35 ExtractWord . . . . .	1192
36.3.36 ExtractWordPos . . . . .	1192
36.3.37 FindPart . . . . .	1192
36.3.38 GetCmdLineArg . . . . .	1193
36.3.39 Hex2Dec . . . . .	1193
36.3.40 HexToBin . . . . .	1194
36.3.41 IfThen . . . . .	1194
36.3.42 IntToBin . . . . .	1194
36.3.43 IntToRoman . . . . .	1195
36.3.44 IsEmptyStr . . . . .	1195
36.3.45 IsWild . . . . .	1195
36.3.46 IsWordPresent . . . . .	1196
36.3.47 LeftBStr . . . . .	1196
36.3.48 LeftStr . . . . .	1196
36.3.49 MidBStr . . . . .	1197
36.3.50 MidStr . . . . .	1197
36.3.51 NPos . . . . .	1197
36.3.52 Numb2Dec . . . . .	1198
36.3.53 Numb2USA . . . . .	1198
36.3.54 PadCenter . . . . .	1198
36.3.55 PadLeft . . . . .	1198
36.3.56 PadRight . . . . .	1199
36.3.57 PosEx . . . . .	1199
36.3.58 PosSet . . . . .	1199
36.3.59 PosSetEx . . . . .	1199
36.3.60 RandomFrom . . . . .	1200
36.3.61 Removeleadingchars . . . . .	1200
36.3.62 RemovePadChars . . . . .	1200
36.3.63 RemoveTrailingChars . . . . .	1201
36.3.64 ReverseString . . . . .	1201
36.3.65 RightBStr . . . . .	1201
36.3.66 RightStr . . . . .	1201

36.3.67 RomanToInt	1202
36.3.68 RPos	1202
36.3.69 RPosex	1202
36.3.70 SearchBuf	1203
36.3.71 Soundex	1203
36.3.72 SoundexCompare	1203
36.3.73 SoundexInt	1204
36.3.74 SoundexProc	1204
36.3.75 SoundexSimilar	1205
36.3.76 SoundexWord	1205
36.3.77 StringsReplace	1205
36.3.78 StuffString	1206
36.3.79 Tab2Space	1206
36.3.80 TrimLeftSet	1206
36.3.81 TrimRightSet	1206
36.3.82 TrimSet	1207
36.3.83 WordCount	1207
36.3.84 WordPosition	1207
36.3.85 XorDecode	1208
36.3.86 XorEncode	1208
36.3.87 XorString	1208
<b>37 Reference for unit 'System'</b>	<b>1209</b>
37.1 Overview	1209
37.2 Miscellaneous functions	1209
37.3 Operating System functions	1210
37.4 String handling	1210
37.5 Mathematical routines	1210
37.6 Memory management functions	1211
37.7 File handling functions	1211
37.8 Constants, types and variables	1211
37.8.1 Constants	1211
37.8.2 Types	1233
37.8.3 Variables	1255
37.9 Procedures and functions	1258
37.9.1 abs	1258
37.9.2 AbstractError	1258
37.9.3 AcquireExceptionObject	1258
37.9.4 AddExitProc	1259
37.9.5 Addr	1259



37.9.6 Align	1260
37.9.7 AllocMem	1260
37.9.8 AnsiToUtf8	1260
37.9.9 Append	1260
37.9.10 arctan	1261
37.9.11 ArrayStringToPPchar	1261
37.9.12 Assert	1262
37.9.13 Assign	1262
37.9.14 Assigned	1263
37.9.15 BasicEventCreate	1264
37.9.16 basiceventdestroy	1264
37.9.17 basiceventResetEvent	1264
37.9.18 basiceventSetEvent	1264
37.9.19 basiceventWaitFor	1264
37.9.20 BeginThread	1265
37.9.21 BEtoN	1265
37.9.22 binStr	1265
37.9.23 BlockRead	1266
37.9.24 BlockWrite	1267
37.9.25 Break	1267
37.9.26 chdir	1268
37.9.27 chr	1269
37.9.28 Close	1269
37.9.29 CloseThread	1270
37.9.30 CompareByte	1270
37.9.31 CompareChar	1271
37.9.32 CompareChar0	1273
37.9.33 CompareDWord	1273
37.9.34 CompareWord	1274
37.9.35 Concat	1275
37.9.36 Continue	1276
37.9.37 Copy	1277
37.9.38 cos	1277
37.9.39 Cseg	1278
37.9.40 Dec	1278
37.9.41 DefaultAnsi2UnicodeMove	1279
37.9.42 DefaultAnsi2WideMove	1279
37.9.43 DefaultUnicode2AnsiMove	1280
37.9.44 DefaultWide2AnsiMove	1280
37.9.45 Delete	1280

37.9.46 Dispose . . . . .	1281
37.9.47 DoneCriticalSection . . . . .	1282
37.9.48 DoneThread . . . . .	1282
37.9.49 Dseg . . . . .	1282
37.9.50 DumpExceptionBackTrace . . . . .	1283
37.9.51 Dump_Stack . . . . .	1283
37.9.52 DynArraySetLength . . . . .	1283
37.9.53 EndThread . . . . .	1284
37.9.54 EnterCriticalSection . . . . .	1284
37.9.55 EnumResourceLanguages . . . . .	1285
37.9.56 EnumResourceNames . . . . .	1285
37.9.57 EnumResourceTypes . . . . .	1285
37.9.58 EOF . . . . .	1286
37.9.59 EOLn . . . . .	1286
37.9.60 Erase . . . . .	1287
37.9.61 Error . . . . .	1288
37.9.62 Exclude . . . . .	1288
37.9.63 Exit . . . . .	1289
37.9.64 exp . . . . .	1290
37.9.65 FilePos . . . . .	1291
37.9.66 FileSize . . . . .	1291
37.9.67 FillByte . . . . .	1292
37.9.68 FillChar . . . . .	1293
37.9.69 FillDWord . . . . .	1293
37.9.70 FillQWord . . . . .	1294
37.9.71 FillWord . . . . .	1294
37.9.72 FindResource . . . . .	1295
37.9.73 FindResourceEx . . . . .	1295
37.9.74 float_raise . . . . .	1296
37.9.75 Flush . . . . .	1296
37.9.76 FlushThread . . . . .	1296
37.9.77 FPower10 . . . . .	1297
37.9.78 frac . . . . .	1297
37.9.79 Freemem . . . . .	1297
37.9.80 Freememory . . . . .	1298
37.9.81 FreeResource . . . . .	1298
37.9.82 GetCurrentThreadId . . . . .	1298
37.9.83 getdir . . . . .	1299
37.9.84 GetFPCHeapStatus . . . . .	1299
37.9.85 GetHeapStatus . . . . .	1299

37.9.86 GetMem . . . . .	1299
37.9.87 GetMemory . . . . .	1300
37.9.88 GetMemoryManager . . . . .	1300
37.9.89 GetProcessID . . . . .	1300
37.9.90 GetResourceManager . . . . .	1301
37.9.91 GetThreadID . . . . .	1301
37.9.92 GetThreadManager . . . . .	1301
37.9.93 GetUnicodeStringManager . . . . .	1301
37.9.94 GetVariantManager . . . . .	1302
37.9.95 GetWideStringManager . . . . .	1302
37.9.96 get_caller_addr . . . . .	1302
37.9.97 get_caller_frame . . . . .	1302
37.9.98 get_cmdline . . . . .	1303
37.9.99 get_frame . . . . .	1303
37.9.100 halt . . . . .	1303
37.9.101 hexStr . . . . .	1303
37.9.102 hi . . . . .	1304
37.9.103 High . . . . .	1305
37.9.104 HINSTANCE . . . . .	1306
37.9.105 inc . . . . .	1306
37.9.106 include . . . . .	1307
37.9.107 IndexByte . . . . .	1307
37.9.108 IndexChar . . . . .	1308
37.9.109 IndexChar0 . . . . .	1309
37.9.110 IndexDWord . . . . .	1309
37.9.111 IndexQWord . . . . .	1310
37.9.112 Indexword . . . . .	1310
37.9.113 InitCriticalSection . . . . .	1311
37.9.114 InitThread . . . . .	1311
37.9.115 InitThreadVars . . . . .	1311
37.9.116 Insert . . . . .	1312
37.9.117 Int . . . . .	1312
37.9.118 InterlockedCompareExchange . . . . .	1313
37.9.119 InterLockedDecrement . . . . .	1313
37.9.120 InterLockedExchange . . . . .	1313
37.9.121 InterLockedExchangeAdd . . . . .	1314
37.9.122 InterLockedIncrement . . . . .	1314
37.9.123 IOResult . . . . .	1315
37.9.124 sMemoryManagerSet . . . . .	1316
37.9.125 s_IntResource . . . . .	1316

37.9.126	KillThread	1316
37.9.127	LeaveCriticalSection	1317
37.9.128	Length	1317
37.9.129	LEtoN	1318
37.9.130	n	1318
37.9.131	Io	1319
37.9.132	LoadResource	1319
37.9.133	LockResource	1320
37.9.134	longjmp	1320
37.9.135	Low	1320
37.9.136	lowerCase	1321
37.9.137	MakeLangID	1321
37.9.138	MemSize	1321
37.9.139	mkdir	1322
37.9.140	Move	1322
37.9.141	MoveChar0	1322
37.9.142	New	1323
37.9.143	NtoBE	1323
37.9.144	NtoLE	1324
37.9.145	Null	1324
37.9.146	OctStr	1324
37.9.147	odd	1325
37.9.148	Ofs	1325
37.9.149	operator *(variant, variant): variant	1326
37.9.150	operator **(variant, variant): variant	1326
37.9.151	operator +(variant, variant): variant	1326
37.9.152	operator -(variant): variant	1327
37.9.153	operator -(variant, variant): variant	1327
37.9.154	operator /(variant, variant): variant	1327
37.9.155	operator :=(ansistring): olevariant	1328
37.9.156	operator :=(ansistring): variant	1328
37.9.157	operator :=(Boolean): olevariant	1328
37.9.158	operator :=(Boolean): variant	1328
37.9.159	operator :=(Byte): olevariant	1328
37.9.160	operator :=(Byte): variant	1329
37.9.161	operator :=(Char): olevariant	1329
37.9.162	operator :=(Char): variant	1329
37.9.163	operator :=(comp): olevariant	1329
37.9.164	operator :=(comp): variant	1329
37.9.165	operator :=(currency): olevariant	1329

37.9.166operator :=(currency): variant . . . . .	1330
37.9.167operator :=(double): olevariant . . . . .	1330
37.9.168operator :=(double): variant . . . . .	1330
37.9.169operator :=(DWord): olevariant . . . . .	1330
37.9.170operator :=(DWord): variant . . . . .	1330
37.9.171operator :=(extended): olevariant . . . . .	1331
37.9.172operator :=(extended): variant . . . . .	1331
37.9.173operator :=(Int64): olevariant . . . . .	1331
37.9.174operator :=(Int64): variant . . . . .	1331
37.9.175operator :=(longbool): olevariant . . . . .	1331
37.9.176operator :=(longbool): variant . . . . .	1332
37.9.177operator :=(LongInt): olevariant . . . . .	1332
37.9.178operator :=(LongInt): variant . . . . .	1332
37.9.179operator :=(olevariant): ansistring . . . . .	1332
37.9.180operator :=(olevariant): Boolean . . . . .	1333
37.9.181operator :=(olevariant): Byte . . . . .	1333
37.9.182operator :=(olevariant): Char . . . . .	1333
37.9.183operator :=(olevariant): comp . . . . .	1333
37.9.184operator :=(olevariant): currency . . . . .	1333
37.9.185operator :=(olevariant): double . . . . .	1334
37.9.186operator :=(olevariant): DWord . . . . .	1334
37.9.187operator :=(olevariant): extended . . . . .	1334
37.9.188operator :=(olevariant): Int64 . . . . .	1334
37.9.189operator :=(olevariant): longbool . . . . .	1334
37.9.190operator :=(olevariant): LongInt . . . . .	1335
37.9.191operator :=(olevariant): qword . . . . .	1335
37.9.192operator :=(olevariant): Real . . . . .	1335
37.9.193operator :=(olevariant): ShortInt . . . . .	1335
37.9.194operator :=(olevariant): shortstring . . . . .	1335
37.9.195operator :=(olevariant): single . . . . .	1336
37.9.196operator :=(olevariant): SmallInt . . . . .	1336
37.9.197operator :=(olevariant): TDateTime . . . . .	1336
37.9.198operator :=(olevariant): TError . . . . .	1336
37.9.199operator :=(olevariant): UnicodeString . . . . .	1336
37.9.200operator :=(olevariant): variant . . . . .	1337
37.9.201operator :=(olevariant): widechar . . . . .	1337
37.9.202operator :=(olevariant): widestring . . . . .	1337
37.9.203operator :=(olevariant): Word . . . . .	1337
37.9.204operator :=(olevariant): wordbool . . . . .	1338
37.9.205operator :=(qword): olevariant . . . . .	1338

37.9.206operator :=(qword): variant . . . . .	1338
37.9.207operator :=(Real): olevariant . . . . .	1338
37.9.208operator :=(Real): variant . . . . .	1338
37.9.209operator :=(real48): double . . . . .	1338
37.9.210operator :=(real48): extended . . . . .	1339
37.9.211operator :=(ShortInt): olevariant . . . . .	1339
37.9.212operator :=(ShortInt): variant . . . . .	1339
37.9.213operator :=(shortstring): olevariant . . . . .	1339
37.9.214operator :=(shortstring): variant . . . . .	1339
37.9.215operator :=(single): olevariant . . . . .	1340
37.9.216operator :=(single): variant . . . . .	1340
37.9.217operator :=(SmallInt): olevariant . . . . .	1340
37.9.218operator :=(SmallInt): variant . . . . .	1340
37.9.219operator :=(TDateTime): olevariant . . . . .	1340
37.9.220operator :=(TDateTime): variant . . . . .	1341
37.9.221operator :=(TErrors): olevariant . . . . .	1341
37.9.222operator :=(TErrors): variant . . . . .	1341
37.9.223operator :=(UCS4String): variant . . . . .	1341
37.9.224operator :=(UnicodeString): olevariant . . . . .	1341
37.9.225operator :=(UnicodeString): variant . . . . .	1342
37.9.226operator :=(UTF8String): variant . . . . .	1342
37.9.227operator :=(variant): ansistring . . . . .	1342
37.9.228operator :=(variant): Boolean . . . . .	1342
37.9.229operator :=(variant): Byte . . . . .	1342
37.9.230operator :=(variant): Char . . . . .	1343
37.9.231operator :=(variant): comp . . . . .	1343
37.9.232operator :=(variant): currency . . . . .	1343
37.9.233operator :=(variant): double . . . . .	1343
37.9.234operator :=(variant): DWord . . . . .	1343
37.9.235operator :=(variant): extended . . . . .	1344
37.9.236operator :=(variant): Int64 . . . . .	1344
37.9.237operator :=(variant): longbool . . . . .	1344
37.9.238operator :=(variant): LongInt . . . . .	1344
37.9.239operator :=(variant): olevariant . . . . .	1344
37.9.240operator :=(variant): qword . . . . .	1345
37.9.241operator :=(variant): Real . . . . .	1345
37.9.242operator :=(variant): ShortInt . . . . .	1345
37.9.243operator :=(variant): shortstring . . . . .	1345
37.9.244operator :=(variant): single . . . . .	1345
37.9.245operator :=(variant): SmallInt . . . . .	1346

37.9.246	operator :=(variant): TDateTime . . . . .	1346
37.9.247	operator :=(variant): TError . . . . .	1346
37.9.248	operator :=(variant): unicodestring . . . . .	1346
37.9.249	operator :=(variant): UTF8String . . . . .	1346
37.9.250	operator :=(variant): widechar . . . . .	1347
37.9.251	operator :=(variant): widestring . . . . .	1347
37.9.252	operator :=(variant): Word . . . . .	1347
37.9.253	operator :=(variant): wordbool . . . . .	1347
37.9.254	operator :=(widechar): olevariant . . . . .	1348
37.9.255	operator :=(widechar): variant . . . . .	1348
37.9.256	operator :=(widestring): olevariant . . . . .	1348
37.9.257	operator :=(widestring): variant . . . . .	1348
37.9.258	operator :=(Word): olevariant . . . . .	1349
37.9.259	operator :=(Word): variant . . . . .	1349
37.9.260	operator :=(wordbool): olevariant . . . . .	1349
37.9.261	operator :=(wordbool): variant . . . . .	1349
37.9.262	operator <(variant, variant): Boolean . . . . .	1349
37.9.263	operator <=(variant, variant): Boolean . . . . .	1350
37.9.264	operator =(variant, variant): Boolean . . . . .	1350
37.9.265	operator >(variant, variant): Boolean . . . . .	1350
37.9.266	operator >=(variant, variant): Boolean . . . . .	1351
37.9.267	operator and(variant, variant): variant . . . . .	1351
37.9.268	operator div(variant, variant): variant . . . . .	1351
37.9.269	operator mod(variant, variant): variant . . . . .	1352
37.9.270	operator not(variant): variant . . . . .	1352
37.9.271	operator or(variant, variant): variant . . . . .	1352
37.9.272	operator shl(variant, variant): variant . . . . .	1353
37.9.273	operator shr(variant, variant): variant . . . . .	1353
37.9.274	operator xor(variant, variant): variant . . . . .	1353
37.9.275	Ord . . . . .	1354
37.9.276	Pack . . . . .	1354
37.9.277	Paramcount . . . . .	1355
37.9.278	ParamStr . . . . .	1355
37.9.279	Pi . . . . .	1356
37.9.280	Pos . . . . .	1356
37.9.281	Pred . . . . .	1357
37.9.282	prefetch . . . . .	1357
37.9.283	ptr . . . . .	1358
37.9.284	RaiseList . . . . .	1358
37.9.285	Random . . . . .	1359

37.9.28 <del>R</del> andomize . . . . .	1359
37.9.28 <del>R</del> ead . . . . .	1360
37.9.28 <del>R</del> eadBarrier . . . . .	1360
37.9.28 <del>R</del> eadDependencyBarrier . . . . .	1361
37.9.29 <del>R</del> eadLn . . . . .	1361
37.9.29 <del>R</del> eadStr . . . . .	1361
37.9.29 <del>R</del> eadWriteBarrier . . . . .	1362
37.9.29 <del>R</del> eal2Double . . . . .	1362
37.9.29 <del>R</del> eAllocMem . . . . .	1363
37.9.29 <del>R</del> eAllocMemory . . . . .	1363
37.9.29 <del>R</del> eleaseExceptionObject . . . . .	1363
37.9.29 <del>R</del> ename . . . . .	1364
37.9.29 <del>R</del> eset . . . . .	1364
37.9.29 <del>R</del> esumeThread . . . . .	1365
37.9.30 <del>R</del> ewrite . . . . .	1365
37.9.30 <del>R</del> mdir . . . . .	1366
37.9.30 <del>R</del> olByte . . . . .	1367
37.9.30 <del>R</del> olDWord . . . . .	1367
37.9.30 <del>R</del> olQWord . . . . .	1367
37.9.30 <del>R</del> olWord . . . . .	1368
37.9.30 <del>R</del> orByte . . . . .	1368
37.9.30 <del>R</del> orDWord . . . . .	1368
37.9.30 <del>R</del> orQWord . . . . .	1369
37.9.30 <del>R</del> orWord . . . . .	1369
37.9.31 <del>R</del> ound . . . . .	1369
37.9.31 <del>R</del> TLEventCreate . . . . .	1370
37.9.31 <del>R</del> TLeventdestroy . . . . .	1370
37.9.31 <del>R</del> TLeventResetEvent . . . . .	1370
37.9.31 <del>R</del> TLeventSetEvent . . . . .	1371
37.9.31 <del>R</del> TLeventsync . . . . .	1371
37.9.31 <del>R</del> TLeventWaitFor . . . . .	1371
37.9.31 <del>R</del> unError . . . . .	1371
37.9.31 <del>S</del> eek . . . . .	1372
37.9.31 <del>S</del> eekEOF . . . . .	1373
37.9.32 <del>S</del> eekEOLn . . . . .	1373
37.9.32 <del>S</del> eg . . . . .	1374
37.9.32 <del>S</del> etjmp . . . . .	1374
37.9.32 <del>S</del> etLength . . . . .	1375
37.9.32 <del>S</del> etMemoryManager . . . . .	1376
37.9.32 <del>S</del> etResourceManager . . . . .	1376



37.9.32	SetString	1376
37.9.32	SetTextBuf	1377
37.9.32	SetTextLineEnding	1378
37.9.32	SetThreadManager	1378
37.9.33	SetUnicodeStringManager	1378
37.9.33	SetVariantManager	1379
37.9.33	SetWideStringManager	1379
37.9.33	ShortCompareText	1380
37.9.33	sin	1380
37.9.33	SizeOf	1380
37.9.33	SizeofResource	1381
37.9.33	Space	1381
37.9.33	Sptr	1382
37.9.33	qr	1382
37.9.34	qrt	1383
37.9.34	Sseg	1383
37.9.34	Str	1383
37.9.34	StringOfChar	1384
37.9.34	StringToPPChar	1385
37.9.34	StringToUnicodeChar	1385
37.9.34	StringToWideChar	1386
37.9.34	strlen	1386
37.9.34	strpas	1386
37.9.34	Succ	1386
37.9.35	SuspendThread	1387
37.9.35	Swap	1387
37.9.35	SwapEndian	1388
37.9.35	SysAllocMem	1388
37.9.35	SysAssert	1388
37.9.35	SysBackTraceStr	1388
37.9.35	SysFreemem	1389
37.9.35	SysFreememSize	1389
37.9.35	SysGetFPCHeapStatus	1389
37.9.35	SysGetHeapStatus	1389
37.9.36	SysGetmem	1389
37.9.36	SysInitExceptions	1390
37.9.36	SysInitFPU	1390
37.9.36	SysInitStdIO	1390
37.9.36	SysMemSize	1390
37.9.36	SysReAllocMem	1390

37.9.366	SysResetFPU	1391
37.9.367	SysSetCtrlBreakHandler	1391
37.9.368	SysTryResizeMem	1391
37.9.369	ThreadGetPriority	1391
37.9.370	ThreadSetPriority	1392
37.9.371	ThreadSwitch	1392
37.9.372	Trunc	1392
37.9.373	Truncate	1393
37.9.374	TryEnterCriticalSection	1393
37.9.375	UCS4StringToUnicodeString	1393
37.9.376	UCS4StringToWideString	1394
37.9.377	Unassigned	1394
37.9.378	UnicodeCharLenToString	1394
37.9.379	UnicodeCharLenToStrVar	1394
37.9.380	UnicodeCharToString	1395
37.9.381	UnicodeCharToStrVar	1395
37.9.382	UnicodeStringToUCS4String	1395
37.9.383	UnicodeToUtf8	1396
37.9.384	UniqueString	1396
37.9.385	UnlockResource	1396
37.9.386	UnPack	1397
37.9.387	UpCase	1397
37.9.388	UTF8Decode	1398
37.9.389	UTF8Encode	1398
37.9.390	Utf8ToAnsi	1398
37.9.391	Utf8ToUnicode	1398
37.9.392	Val	1399
37.9.393	VarArrayGet	1399
37.9.394	VarArrayPut	1400
37.9.395	VarArrayRedim	1400
37.9.396	VarCast	1400
37.9.397	WaitForThreadTerminate	1401
37.9.398	WideCharLenToString	1401
37.9.399	WideCharLenToStrVar	1401
37.9.400	WideCharToString	1401
37.9.401	WideCharToStrVar	1402
37.9.402	WideStringToUCS4String	1402
37.9.403	Write	1402
37.9.404	WriteBarrier	1403
37.9.405	WriteLn	1403

37.9.406WriteStr . . . . .	1404
37.10IDispatch . . . . .	1404
37.10.1 Description . . . . .	1404
37.10.2 Method overview . . . . .	1404
37.10.3 IDispatch.GetTypeInfoCount . . . . .	1404
37.10.4 IDispatch.GetTypeInfo . . . . .	1405
37.10.5 IDispatch.GetIDsOfNames . . . . .	1405
37.10.6 IDispatch.Invoke . . . . .	1405
37.11IEnumerable . . . . .	1405
37.11.1 Description . . . . .	1405
37.11.2 Method overview . . . . .	1405
37.11.3 IEnumerable.GetEnumerator . . . . .	1405
37.12IEnumerator . . . . .	1406
37.12.1 Description . . . . .	1406
37.12.2 Method overview . . . . .	1406
37.12.3 Property overview . . . . .	1406
37.12.4 IEnumerator.GetCurrent . . . . .	1406
37.12.5 IEnumerator.MoveNext . . . . .	1407
37.12.6 IEnumerator.Reset . . . . .	1407
37.12.7 IEnumerator.Current . . . . .	1407
37.13Invokable . . . . .	1407
37.13.1 Description . . . . .	1407
37.14IUnknown . . . . .	1408
37.14.1 Description . . . . .	1408
37.14.2 Method overview . . . . .	1408
37.14.3 IUnknown.QueryInterface . . . . .	1408
37.14.4 IUnknown._AddRef . . . . .	1408
37.14.5 IUnknown._Release . . . . .	1408
37.15TAggregatedObject . . . . .	1408
37.15.1 Description . . . . .	1408
37.15.2 Method overview . . . . .	1409
37.15.3 Property overview . . . . .	1409
37.15.4 TAggregatedObject.Create . . . . .	1409
37.15.5 TAggregatedObject.Controller . . . . .	1409
37.16TContainedObject . . . . .	1409
37.16.1 Description . . . . .	1409
37.17TInterfacedObject . . . . .	1410
37.17.1 Description . . . . .	1410
37.17.2 Method overview . . . . .	1410
37.17.3 Property overview . . . . .	1410

37.17.4 TInterfacedObject.AfterConstruction	1410
37.17.5 TInterfacedObject.BeforeDestruction	1410
37.17.6 TInterfacedObject.NewInstance	1410
37.17.7 TInterfacedObject.RefCount	1411
37.18 TObject	1411
37.18.1 Description	1411
37.18.2 Method overview	1412
37.18.3 TObject.Create	1412
37.18.4 TObject.Destroy	1413
37.18.5 TObject.newinstance	1413
37.18.6 TObject.FreeInstance	1413
37.18.7 TObject.SafeCallException	1413
37.18.8 TObject.DefaultHandler	1414
37.18.9 TObject.Free	1414
37.18.10 TObject.InitInstance	1414
37.18.11 TObject.CleanupInstance	1414
37.18.12 TObject.ClassType	1415
37.18.13 TObject.ClassInfo	1415
37.18.14 TObject.ClassName	1415
37.18.15 TObject.ClassNameIs	1415
37.18.16 TObject.ClassParent	1416
37.18.17 TObject.InstanceSize	1416
37.18.18 TObject.InheritsFrom	1416
37.18.19 TObject.StringMessageTable	1416
37.18.20 TObject.MethodAddress	1417
37.18.21 TObject.MethodName	1417
37.18.22 TObject.FieldAddress	1417
37.18.23 TObject.AfterConstruction	1417
37.18.24 TObject.BeforeDestruction	1418
37.18.25 TObject.DefaultHandlerStr	1418
37.18.26 TObject.Dispatch	1418
37.18.27 TObject.DispatchStr	1418
37.18.28 TObject.GetInterface	1419
37.18.29 TObject.GetInterfaceByStr	1419
37.18.30 TObject.GetInterfaceEntry	1419
37.18.31 TObject.GetInterfaceEntryByStr	1420
37.18.32 TObject.GetInterfaceTable	1420
37.18.33 TObject.UnitName	1420
37.18.34 TObject.Equals	1420
37.18.35 TObject.GetHashCode	1421

37.18.36	Object.ToString . . . . .	1421
<b>38</b>	<b>Reference for unit 'sysutils' . . . . .</b>	<b>1426</b>
38.1	Used units . . . . .	1426
38.2	Overview . . . . .	1426
38.3	Localization support . . . . .	1426
38.4	Miscellaneous conversion routines . . . . .	1427
38.5	Date/time routines . . . . .	1427
38.6	FileName handling routines . . . . .	1427
38.7	File input/output routines . . . . .	1427
38.8	PChar related functions . . . . .	1427
38.9	Date and time formatting characters . . . . .	1429
38.10	Formatting strings . . . . .	1430
38.11	String functions . . . . .	1430
38.12	Constants, types and variables . . . . .	1430
38.12.1	Constants . . . . .	1430
38.12.2	Types . . . . .	1436
38.12.3	Variables . . . . .	1442
38.13	Procedures and functions . . . . .	1446
38.13.1	AbandonSignalHandler . . . . .	1446
38.13.2	Abort . . . . .	1446
38.13.3	AddDisk . . . . .	1447
38.13.4	AddTerminateProc . . . . .	1447
38.13.5	AdjustLineBreaks . . . . .	1447
38.13.6	AnsiCompareFileName . . . . .	1448
38.13.7	AnsiCompareStr . . . . .	1448
38.13.8	AnsiCompareText . . . . .	1449
38.13.9	AnsiDequotedStr . . . . .	1450
38.13.10	AnsiExtractQuotedStr . . . . .	1450
38.13.11	AnsiLastChar . . . . .	1451
38.13.12	AnsiLowerCase . . . . .	1452
38.13.13	AnsiLowerCaseFileName . . . . .	1452
38.13.14	AnsiPos . . . . .	1453
38.13.15	AnsiQuotedStr . . . . .	1453
38.13.16	AnsiSameStr . . . . .	1453
38.13.17	AnsiSameText . . . . .	1453
38.13.18	AnsiStrComp . . . . .	1454
38.13.19	AnsiStrIComp . . . . .	1454
38.13.20	AnsiStrLastChar . . . . .	1455
38.13.21	AnsiStrLComp . . . . .	1456

38.13.22AnsiStrLComp . . . . .	1457
38.13.23AnsiStrLower . . . . .	1458
38.13.24AnsiStrPos . . . . .	1458
38.13.25AnsiStrRScan . . . . .	1459
38.13.26AnsiStrScan . . . . .	1459
38.13.27AnsiStrUpper . . . . .	1459
38.13.28AnsiUpperCase . . . . .	1460
38.13.29AnsiUpperCaseFileName . . . . .	1460
38.13.30AppendStr . . . . .	1461
38.13.31ApplicationName . . . . .	1461
38.13.32AssignStr . . . . .	1462
38.13.33BCDToInt . . . . .	1462
38.13.34Beep . . . . .	1463
38.13.35BoolToStr . . . . .	1463
38.13.36ByteToCharIndex . . . . .	1463
38.13.37ByteToCharLen . . . . .	1464
38.13.38ByteType . . . . .	1464
38.13.39CallTerminateProcs . . . . .	1464
38.13.40ChangeFileExt . . . . .	1464
38.13.41CharToByteLen . . . . .	1465
38.13.42CompareMem . . . . .	1465
38.13.43CompareMemRange . . . . .	1465
38.13.44CompareStr . . . . .	1466
38.13.45CompareText . . . . .	1467
38.13.46ComposeDateTime . . . . .	1467
38.13.47CreateDir . . . . .	1468
38.13.48CreateGUID . . . . .	1468
38.13.49CurrentYear . . . . .	1469
38.13.50CurrToStr . . . . .	1469
38.13.51CurrToStrF . . . . .	1469
38.13.52Date . . . . .	1470
38.13.53DateTimeToFileDate . . . . .	1470
38.13.54DateTimeToStr . . . . .	1471
38.13.55DateTimeToString . . . . .	1471
38.13.56DateTimeToSystemTime . . . . .	1472
38.13.57DateTimeToTimeStamp . . . . .	1473
38.13.58DateToStr . . . . .	1473
38.13.59DayOfWeek . . . . .	1474
38.13.60DecodeDate . . . . .	1475
38.13.61DecodeDateFully . . . . .	1475

38.13.6DecodeTime	1475
38.13.6DeleteFile	1476
38.13.6DirectoryExists	1477
38.13.6DiskFree	1477
38.13.6DiskSize	1478
38.13.6DisposeStr	1478
38.13.6DoDirSeparators	1478
38.13.6EncodeDate	1479
38.13.7EncodeTime	1480
38.13.7ExceptAddr	1480
38.13.7ExceptFrameCount	1481
38.13.7ExceptFrames	1481
38.13.7ExceptionErrorMessage	1481
38.13.7ExceptObject	1481
38.13.7ExcludeTrailingBackslash	1482
38.13.7ExcludeTrailingPathDelimiter	1482
38.13.7ExecuteProcess	1482
38.13.7ExeSearch	1482
38.13.8ExpandFileName	1483
38.13.8ExpandUNCFileName	1483
38.13.8ExtractFileDir	1484
38.13.8ExtractFileDrive	1484
38.13.8ExtractFileExt	1485
38.13.8ExtractFileName	1485
38.13.8ExtractFilePath	1485
38.13.8ExtractRelativepath	1486
38.13.8ExtractShortPathName	1486
38.13.8FileAge	1486
38.13.9FileClose	1487
38.13.9FileCreate	1487
38.13.9FileDateToDateTime	1488
38.13.9FileExists	1489
38.13.9FileGetAttr	1490
38.13.9FileGetDate	1491
38.13.9FileIsReadOnly	1491
38.13.9FileOpen	1492
38.13.9FileRead	1493
38.13.9FileSearch	1493
38.13.10FileSeek	1494
38.13.10FileSetAttr	1494

38.13.10FileSetDate . . . . .	1495
38.13.10FileTruncate . . . . .	1495
38.13.10FileWrite . . . . .	1495
38.13.10FileClose . . . . .	1496
38.13.10FindCmdLineSwitch . . . . .	1496
38.13.10FindFirst . . . . .	1496
38.13.10FindNext . . . . .	1497
38.13.10FloattoCurr . . . . .	1498
38.13.1FloatToDateTime . . . . .	1498
38.13.1FloatToDecimal . . . . .	1498
38.13.1FloatToStr . . . . .	1499
38.13.1FloatToStrF . . . . .	1500
38.13.1FloatToText . . . . .	1502
38.13.1FloatToTextFmt . . . . .	1503
38.13.1FmtStr . . . . .	1503
38.13.1ForceDirectories . . . . .	1504
38.13.1Format . . . . .	1504
38.13.1FormatBuf . . . . .	1509
38.13.1FormatCurr . . . . .	1510
38.13.1FormatDateTime . . . . .	1510
38.13.1FormatFloat . . . . .	1511
38.13.1FreeAndNil . . . . .	1512
38.13.1GetAppConfigDir . . . . .	1513
38.13.1GetAppConfigFile . . . . .	1513
38.13.1GetCurrentDir . . . . .	1514
38.13.1GetDirs . . . . .	1514
38.13.1GetEnvironmentString . . . . .	1515
38.13.1GetEnvironmentVariable . . . . .	1515
38.13.1GetEnvironmentVariableCount . . . . .	1515
38.13.1GetFileHandle . . . . .	1516
38.13.1GetLastError . . . . .	1516
38.13.1GetLocalTime . . . . .	1516
38.13.1GetModuleName . . . . .	1517
38.13.1GetTempDir . . . . .	1517
38.13.1GetTempFileName . . . . .	1517
38.13.1GetUserDir . . . . .	1518
38.13.1GuidCase . . . . .	1518
38.13.1GUIDToString . . . . .	1518
38.13.1HookSignal . . . . .	1519
38.13.1IncAMonth . . . . .	1519



38.13.14	includeTrailingBackslash	1519
38.13.14	includeTrailingPathDelimiter	1519
38.13.14	Month	1520
38.13.14	RequireSignal	1520
38.13.14	toHex	1521
38.13.14	toStr	1521
38.13.14	Delimiter	1522
38.13.14	EqualGUID	1522
38.13.14	LeapYear	1522
38.13.14	PathDelimiter	1523
38.13.14	ValidIdent	1523
38.13.14	LastDelimiter	1524
38.13.14	LeftStr	1524
38.13.14	LoadStr	1525
38.13.14	LowerCase	1525
38.13.14	MsecsToTimeStamp	1526
38.13.14	NewStr	1526
38.13.14	Now	1527
38.13.14	OutOfMemoryError	1527
38.13.14	QuotedStr	1528
38.13.14	RaiseLastError	1528
38.13.14	RemoveDir	1528
38.13.14	RenameFile	1529
38.13.14	ReplaceDate	1529
38.13.14	ReplaceTime	1530
38.13.14	RightStr	1530
38.13.14	SafeLoadLibrary	1530
38.13.14	SameFileName	1531
38.13.14	SameText	1531
38.13.14	SetCurrentDir	1531
38.13.14	SetDirSeparators	1531
38.13.14	ShowException	1532
38.13.14	Sleep	1532
38.13.14	Scanf	1532
38.13.14	StrAlloc	1533
38.13.14	StrBufSize	1533
38.13.14	StrByteType	1534
38.13.14	Strcat	1534
38.13.14	StrCharLength	1535
38.13.14	Strcomp	1535

38.13.182	StrCopy	1535
38.13.183	StrDispose	1536
38.13.184	Strncpy	1536
38.13.185	Strnd	1537
38.13.186	StrFmt	1537
38.13.187	Stricmp	1538
38.13.188	StringReplace	1539
38.13.189	StringToGUID	1539
38.13.190	Strcat	1540
38.13.191	Strlcomp	1540
38.13.192	Strlcopy	1541
38.13.193	Strlen	1542
38.13.194	StrLFmt	1542
38.13.195	Strlicomp	1543
38.13.196	Strlower	1543
38.13.197	Strmove	1544
38.13.198	Strnew	1544
38.13.199	StrNextChar	1545
38.13.200	StrPas	1545
38.13.201	StrPCopy	1545
38.13.202	StrPLCopy	1546
38.13.203	Strpos	1546
38.13.204	Strrscan	1546
38.13.205	Strscan	1547
38.13.206	StrToBool	1547
38.13.207	StrToBoolDef	1547
38.13.208	StrToCurr	1548
38.13.209	StrToCurrDef	1548
38.13.210	StrToDate	1548
38.13.211	StrToDateDef	1549
38.13.212	StrToDateTime	1549
38.13.213	StrToDateTimeDef	1550
38.13.214	StrToFloat	1551
38.13.215	StrToFloatDef	1552
38.13.216	StrToInt	1552
38.13.217	StrToInt64	1553
38.13.218	StrToInt64Def	1553
38.13.219	StrToIntDef	1553
38.13.220	StrToQWord	1554
38.13.221	StrToQWordDef	1554

38.13.23	StrToTime	1554
38.13.23	StrToTimeDef	1555
38.13.23	StrToUpper	1556
38.13.23	Supports	1556
38.13.23	SysErrorMessage	1556
38.13.23	SystemTimeToDateTime	1557
38.13.23	TextToFloat	1557
38.13.23	Time	1558
38.13.23	TimeStampToDateTime	1559
38.13.23	TimeStampToMSecs	1559
38.13.23	TimeToStr	1560
38.13.23	Trim	1560
38.13.23	TrimLeft	1561
38.13.23	TrimRight	1562
38.13.23	TryEncodeDate	1562
38.13.23	TryEncodeTime	1563
38.13.23	TryFloatToCurr	1563
38.13.23	TryStringToGUID	1563
38.13.24	TryStrToBool	1564
38.13.24	TryStrToCurr	1564
38.13.24	TryStrToDate	1564
38.13.24	TryStrToDateTime	1565
38.13.24	TryStrToFloat	1565
38.13.24	TryStrToInt	1566
38.13.24	TryStrToInt64	1566
38.13.24	TryStrToQWord	1566
38.13.24	TryStrToTime	1566
38.13.24	UnhookSignal	1567
38.13.25	UpperCase	1567
38.13.25	VendorName	1568
38.13.25	WideCompareStr	1568
38.13.25	WideCompareText	1568
38.13.25	WideFmtStr	1569
38.13.25	WideFormat	1569
38.13.25	WideFormatBuf	1569
38.13.25	WideLowerCase	1570
38.13.25	WideSameStr	1570
38.13.25	WideSameText	1570
38.13.26	WideUpperCase	1570
38.13.26	WrapText	1571

38.14EAbort . . . . .	1571
38.14.1 Description . . . . .	1571
38.15EAbstractError . . . . .	1571
38.15.1 Description . . . . .	1571
38.16EAccessViolation . . . . .	1571
38.16.1 Description . . . . .	1571
38.17EAssertionFailed . . . . .	1571
38.17.1 Description . . . . .	1571
38.18EBusError . . . . .	1571
38.18.1 Description . . . . .	1571
38.19EControlC . . . . .	1572
38.19.1 Description . . . . .	1572
38.20EConvertError . . . . .	1572
38.20.1 Description . . . . .	1572
38.21EDivByZero . . . . .	1572
38.21.1 Description . . . . .	1572
38.22EExternal . . . . .	1572
38.22.1 Description . . . . .	1572
38.23EExternalException . . . . .	1572
38.23.1 Description . . . . .	1572
38.24EFormatError . . . . .	1572
38.24.1 Description . . . . .	1572
38.25EHeapMemoryError . . . . .	1572
38.25.1 Description . . . . .	1572
38.25.2 Method overview . . . . .	1573
38.25.3 EHeapMemoryError.FreeInstance . . . . .	1573
38.26EInOutError . . . . .	1573
38.26.1 Description . . . . .	1573
38.27EInterror . . . . .	1573
38.27.1 Description . . . . .	1573
38.28EIntfCastError . . . . .	1573
38.28.1 Description . . . . .	1573
38.29EIntOverflow . . . . .	1573
38.29.1 Description . . . . .	1573
38.30EInvalidCast . . . . .	1573
38.30.1 Description . . . . .	1573
38.31EInvalidContainer . . . . .	1574
38.31.1 Description . . . . .	1574
38.32EInvalidInsert . . . . .	1574
38.32.1 Description . . . . .	1574

---

38.33EInvalidOp	1574
38.33.1 Description	1574
38.34EInvalidPointer	1574
38.34.1 Description	1574
38.35EMathError	1574
38.35.1 Description	1574
38.36ENoThreadSupport	1574
38.36.1 Description	1574
38.37ENoWideStringSupport	1574
38.37.1 Description	1574
38.38EOSError	1575
38.38.1 Description	1575
38.39EOOutOfMemory	1575
38.39.1 Description	1575
38.40EOOverflow	1575
38.40.1 Description	1575
38.41EPackageError	1575
38.41.1 Description	1575
38.42EPrivilege	1575
38.42.1 Description	1575
38.43EPropReadOnly	1575
38.43.1 Description	1575
38.44EPropWriteOnly	1575
38.44.1 Description	1575
38.45ERangeError	1576
38.45.1 Description	1576
38.46ESafecallException	1576
38.46.1 Description	1576
38.47EStackOverflow	1576
38.47.1 Description	1576
38.48EUnderflow	1576
38.48.1 Description	1576
38.49EVariantError	1576
38.49.1 Description	1576
38.49.2 Method overview	1576
38.49.3 EVariantError.CreateCode	1576
38.50Exception	1577
38.50.1 Description	1577
38.50.2 Method overview	1577
38.50.3 Property overview	1577

38.50.4	Exception.Create	1577
38.50.5	Exception.CreateFmt	1577
38.50.6	Exception.CreateRes	1578
38.50.7	Exception.CreateResFmt	1578
38.50.8	Exception.CreateHelp	1578
38.50.9	Exception.CreateFmtHelp	1578
38.50.10	Exception.CreateResHelp	1579
38.50.11	Exception.CreateResFmtHelp	1579
38.50.12	Exception.HelpContext	1579
38.50.13	Exception.Message	1579
38.51	EZeroDivide	1580
38.51.1	Description	1580
38.52	IReadWriteSync	1580
38.52.1	Description	1580
38.52.2	Method overview	1580
38.52.3	IReadWriteSync.BeginRead	1580
38.52.4	IReadWriteSync.EndRead	1580
38.52.5	IReadWriteSync.BeginWrite	1581
38.52.6	IReadWriteSync.EndWrite	1581
38.53	TMultiReadExclusiveWriteSynchronizer	1581
38.53.1	Description	1581
38.53.2	Method overview	1581
38.53.3	TMultiReadExclusiveWriteSynchronizer.Create	1581
38.53.4	TMultiReadExclusiveWriteSynchronizer.Destroy	1582
38.53.5	TMultiReadExclusiveWriteSynchronizer.Beginwrite	1582
38.53.6	TMultiReadExclusiveWriteSynchronizer.Endwrite	1582
38.53.7	TMultiReadExclusiveWriteSynchronizer.Beginread	1583
38.53.8	TMultiReadExclusiveWriteSynchronizer.Endread	1583
<b>39</b>	<b>Reference for unit 'types'</b>	<b>1587</b>
39.1	Overview	1587
39.2	Constants, types and variables	1587
39.2.1	Constants	1587
39.2.2	Types	1592
39.3	Procedures and functions	1598
39.3.1	Bounds	1598
39.3.2	CenterPoint	1598
39.3.3	EqualRect	1598
39.3.4	InflateRect	1599
39.3.5	IntersectRect	1599

39.3.6	IsRectEmpty	1599
39.3.7	OffsetRect	1599
39.3.8	Point	1600
39.3.9	PtInRect	1600
39.3.10	Rect	1600
39.3.11	Size	1600
39.3.12	UnionRect	1601
39.4	IClassFactory	1601
39.4.1	Description	1601
39.4.2	Method overview	1601
39.4.3	IClassFactory.CreateInstance	1601
39.4.4	IClassFactory.LockServer	1601
39.5	ISequentialStream	1602
39.5.1	Description	1602
39.5.2	Method overview	1602
39.5.3	ISequentialStream.Read	1602
39.5.4	ISequentialStream.Write	1602
39.6	IStream	1602
39.6.1	Description	1602
39.6.2	Method overview	1603
39.6.3	IStream.Seek	1603
39.6.4	IStream.SetSize	1603
39.6.5	IStream.CopyTo	1603
39.6.6	IStream.Commit	1604
39.6.7	IStream.Revert	1604
39.6.8	IStream.LockRegion	1604
39.6.9	IStream.UnlockRegion	1604
39.6.10	IStream.Stat	1605
39.6.11	IStream.Clone	1605
<b>40</b>	<b>Reference for unit 'typinfo'</b>	<b>1606</b>
40.1	Used units	1606
40.2	Overview	1606
40.3	Auxiliary functions	1606
40.4	Getting or setting property values	1606
40.5	Examining published property information	1607
40.6	Constants, types and variables	1607
40.6.1	Constants	1607
40.6.2	Types	1609
40.7	Procedures and functions	1614

40.7.1 FindPropInfo . . . . .	1614
40.7.2 GetEnumName . . . . .	1615
40.7.3 GetEnumNameCount . . . . .	1616
40.7.4 GetEnumProp . . . . .	1616
40.7.5 GetEnumValue . . . . .	1617
40.7.6 GetFloatProp . . . . .	1617
40.7.7 GetInt64Prop . . . . .	1618
40.7.8 GetInterfaceProp . . . . .	1619
40.7.9 GetMethodProp . . . . .	1620
40.7.10 GetObjectProp . . . . .	1622
40.7.11 GetObjectPropClass . . . . .	1623
40.7.12 GetOrdProp . . . . .	1623
40.7.13 GetPropInfo . . . . .	1624
40.7.14 GetPropInfos . . . . .	1625
40.7.15 GetPropList . . . . .	1626
40.7.16 GetPropValue . . . . .	1627
40.7.17 GetSetProp . . . . .	1627
40.7.18 GetStrProp . . . . .	1628
40.7.19 GetTypeData . . . . .	1629
40.7.20 GetUnicodeStrProp . . . . .	1629
40.7.21 GetVariantProp . . . . .	1630
40.7.22 GetWideStrProp . . . . .	1630
40.7.23 IsPublishedProp . . . . .	1630
40.7.24 IsStoredProp . . . . .	1631
40.7.25 PropIsType . . . . .	1632
40.7.26 PropType . . . . .	1633
40.7.27 SetEnumProp . . . . .	1634
40.7.28 SetFloatProp . . . . .	1634
40.7.29 SetInt64Prop . . . . .	1635
40.7.30 SetInterfaceProp . . . . .	1635
40.7.31 SetMethodProp . . . . .	1635
40.7.32 SetObjectProp . . . . .	1636
40.7.33 SetOrdProp . . . . .	1636
40.7.34 SetPropValue . . . . .	1637
40.7.35 SetSetProp . . . . .	1637
40.7.36 SetStrProp . . . . .	1638
40.7.37 SetToString . . . . .	1638
40.7.38 SetUnicodeStrProp . . . . .	1639
40.7.39 SetVariantProp . . . . .	1639
40.7.40 SetWideStrProp . . . . .	1640



40.7.41 StringToSet . . . . .	1640
40.8 EPropertyConvertError . . . . .	1640
40.8.1 Description . . . . .	1640
40.9 EPropertyError . . . . .	1641
40.9.1 Description . . . . .	1641
<b>41 Reference for unit 'Unix' . . . . .</b>	<b>1642</b>
41.1 Used units . . . . .	1642
41.2 Constants, types and variables . . . . .	1642
41.2.1 Constants . . . . .	1642
41.2.2 Types . . . . .	1649
41.2.3 Variables . . . . .	1658
41.3 Procedures and functions . . . . .	1658
41.3.1 AssignPipe . . . . .	1658
41.3.2 AssignStream . . . . .	1659
41.3.3 FpExecL . . . . .	1660
41.3.4 FpExecLE . . . . .	1661
41.3.5 FpExecLP . . . . .	1662
41.3.6 FpExecLPE . . . . .	1663
41.3.7 FpExecV . . . . .	1663
41.3.8 FpExecVP . . . . .	1664
41.3.9 FpExecVPE . . . . .	1665
41.3.10 fpFlock . . . . .	1666
41.3.11 fpfStatFS . . . . .	1666
41.3.12 fpfsync . . . . .	1667
41.3.13 fpgettimeofday . . . . .	1667
41.3.14 fpStatFS . . . . .	1667
41.3.15 fpSystem . . . . .	1668
41.3.16 FSearch . . . . .	1668
41.3.17 fStatFS . . . . .	1669
41.3.18 fsync . . . . .	1670
41.3.19 GetDomainName . . . . .	1670
41.3.20 GetHostName . . . . .	1671
41.3.21 GetLocalTimezone . . . . .	1671
41.3.22 GetTimezoneFile . . . . .	1672
41.3.23 PClose . . . . .	1672
41.3.24 POpen . . . . .	1672
41.3.25 ReadTimezoneFile . . . . .	1673
41.3.26 SeekDir . . . . .	1674
41.3.27 SelectText . . . . .	1674

41.3.28 Shell . . . . .	1674
41.3.29 SigRaise . . . . .	1675
41.3.30 StatFS . . . . .	1676
41.3.31 Telldir . . . . .	1677
41.3.32 WaitProcess . . . . .	1677
41.3.33 WIFSTOPPED . . . . .	1678
41.3.34 W_EXITCODE . . . . .	1678
41.3.35 W_STOPCODE . . . . .	1678
<b>42 Reference for unit 'unixtype'</b>	<b>1679</b>
42.1 Overview . . . . .	1679
42.2 Constants, types and variables . . . . .	1679
42.2.1 Constants . . . . .	1679
42.2.2 Types . . . . .	1680
<b>43 Reference for unit 'unixutil'</b>	<b>1693</b>
43.1 Overview . . . . .	1693
43.2 Constants, types and variables . . . . .	1693
43.2.1 Types . . . . .	1693
43.2.2 Variables . . . . .	1693
43.3 Procedures and functions . . . . .	1694
43.3.1 ArrayStringToPPchar . . . . .	1694
43.3.2 Basename . . . . .	1694
43.3.3 Dirname . . . . .	1695
43.3.4 EpochToLocal . . . . .	1695
43.3.5 FNMatch . . . . .	1696
43.3.6 FSplit . . . . .	1697
43.3.7 GetFS . . . . .	1697
43.3.8 GregorianToJulian . . . . .	1698
43.3.9 JulianToGregorian . . . . .	1698
43.3.10 LocalToEpoch . . . . .	1698
43.3.11 StringToPPChar . . . . .	1699
<b>44 Reference for unit 'video'</b>	<b>1701</b>
44.1 Overview . . . . .	1701
44.2 Examples utility unit . . . . .	1702
44.3 Writing a custom video driver . . . . .	1702
44.4 Constants, types and variables . . . . .	1703
44.4.1 Constants . . . . .	1703
44.4.2 Types . . . . .	1707
44.4.3 Variables . . . . .	1709

44.5	Procedures and functions	1710
44.5.1	ClearScreen	1710
44.5.2	DefaultErrorHandler	1711
44.5.3	DoneVideo	1711
44.5.4	GetCapabilities	1711
44.5.5	GetCursorType	1712
44.5.6	GetLockScreenCount	1713
44.5.7	GetVideoDriver	1714
44.5.8	GetVideoMode	1714
44.5.9	GetVideoModeCount	1715
44.5.10	GetVideoModeData	1716
44.5.11	InitVideo	1716
44.5.12	LockScreenUpdate	1717
44.5.13	SetCursorPos	1717
44.5.14	SetCursorType	1718
44.5.15	SetVideoDriver	1719
44.5.16	SetVideoMode	1719
44.5.17	UnlockScreenUpdate	1719
44.5.18	UpdateScreen	1720
<b>45</b>	<b>Reference for unit 'winrt'</b>	<b>1721</b>
45.1	Overview	1721
45.2	Constants, types and variables	1721
45.2.1	Variables	1721
45.3	Procedures and functions	1721
45.3.1	delay	1721
45.3.2	keypressed	1721
45.3.3	nosound	1722
45.3.4	readkey	1722
45.3.5	sound	1722
45.3.6	textmode	1722
<b>46</b>	<b>Reference for unit 'x86'</b>	<b>1723</b>
46.1	Used units	1723
46.2	Overview	1723
46.3	Procedures and functions	1723
46.3.1	fpIOperm	1723
46.3.2	fpIoPL	1724
46.3.3	ReadPort	1724
46.3.4	ReadPortB	1724
46.3.5	ReadPortL	1725

46.3.6 ReadPortW . . . . .	1725
46.3.7 WritePort . . . . .	1725
46.3.8 WritePortB . . . . .	1726
46.3.9 WritePortL . . . . .	1726
46.3.10 WritePortW . . . . .	1726

## About this guide

This document describes all constants, types, variables, functions and procedures as they are declared in the units that come standard with the Free Pascal Run-Time library (RTL).

Throughout this document, we will refer to functions, types and variables with `typewriter` font. Functions and procedures have their own subsections, and for each function or procedure we have the following topics:

**Declaration** The exact declaration of the function.

**Description** What does the procedure exactly do ?

**Errors** What errors can occur.

**See Also** Cross references to other related functions/commands.

## 0.1 Overview

The Run-Time Library is the basis of all Free Pascal programs. It contains the basic units that most programs will use, and are made available on all platforms supported by Free pascal (well, more or less).

There are units for compatibility with the Turbo Pascal Run-Time library, and there are units for compatibility with Delphi.

On top of these two sets, there are also a series of units to handle keyboard/mouse and text screens in a cross-platform way.

Other units include platform specific units that implement the specifics of a platform, these are usually needed to support the Turbo Pascal or Delphi units.

Units that fall outside the above outline do not belong in the RTL, but should be included in the packages, or in the FCL.

# Chapter 1

## Reference for unit 'BaseUnix'

### 1.1 Used units

Table 1.1: Used units by unit 'BaseUnix'

Name	Page
unixtype	<a href="#">1679</a>

### 1.2 Overview

The `BaseUnix` unit was implemented by Marco Van de Voort. It contains basic unix functionality. It supersedes the `Linux` unit of version 1.0.X of the compiler, but does not implement all functionality of the `linux` unit.

People that have code which heavily uses the old `Linux` unit, can simply change `linux` by `oldlinux` in the `uses` clause of their projects, but they should really consider moving to the `Unix` and `BaseUnix` units.

For porting FPC to new unix-like platforms, it should be sufficient to implement the functionality in this unit for the new platform.

### 1.3 Constants, types and variables

#### 1.3.1 Constants

`ARG_MAX = UnixType.ARG_MAX`

Maximum number of arguments to a program.

`BITSINWORD = 8*sizeof(cuLong)`

Number of bits in a word.

`ESysE2BIG = 7`

System error: Argument list too long

ESysEACCES = 13

System error: Permission denied

ESysEADDRINUSE = 98

System error: Address already in use

ESysEADDRNOTAVAIL = 99

System error: Cannot assign requested address

ESysEADV = 68

System error: Advertise error

ESysEAFNOSUPPORT = 97

System error: Address family not supported by protocol

ESysEAGAIN = 11

System error: Try again

ESysEALREADY = 114

System error: Operation already in progress

ESysEBADE = 52

System error: Invalid exchange

ESysEBADF = 9

System error: Bad file number

ESysEBADFD = 77

System error: File descriptor in bad state

ESysEBADMSG = 74

System error: Not a data message

ESysEBADR = 53

System error: Invalid request descriptor

ESysEBADRQC = 56

System error: Invalid request code

ESysEBADSLT = 57

System error: Invalid slot

ESysEBFONT = 59

System error: Bad font file format

ESysEBUSY = 16

System error: Device or resource busy

ESysECHILD = 10

System error: No child processes

ESysECHRNG = 44

System error: Channel number out of range

ESysECOMM = 70

System error: Communication error on send

ESysECONNABORTED = 103

System error: Software caused connection abort

ESysECONNREFUSED = 111

System error: Connection refused

ESysECONNRESET = 104

System error: Connection reset by peer

ESysEDEADLK = 35

System error: Resource deadlock would occur

ESysEDEADLOCK = 58

System error: File locking deadlock error

ESysEDESTADDRREQ = 89

System error: Destination address required

ESysEDOM = 33



System error: Math argument out of domain of func

ESysEDOTDOT = 73

System error: RFS specific error

ESysEDQUOT = 122

System error: Quota exceeded

ESysEEXIST = 17

System error: File exists

ESysEFAULT = 14

System error: Bad address

ESysEFBIG = 27

System error: File too large

ESysEHOSTDOWN = 112

System error: Host is down

ESysEHOSTUNREACH = 113

System error: No route to host

ESysEIDRM = 43

System error: Identifier removed

ESysEILSEQ = 84

System error: Illegal byte sequence

ESysEINPROGRESS = 115

System error: Operation now in progress

ESysEINTR = 4

System error: Interrupted system call

ESysEINVAL = 22

System error: Invalid argument

ESysEIO = 5

System error: I/O error

ESysEISCONN = 106

System error: Transport endpoint is already connected

ESysEISDIR = 21

System error: Is a directory

ESysEISNAM = 120

System error: Is a named type file

ESysEL2HLT = 51

System error: Level 2 halted

ESysEL2NSYNC = 45

System error: Level 2 not synchronized

ESysEL3HLT = 46

System error: Level 3 halted

ESysEL3RST = 47

System error: Level 3 reset

ESysELIBACC = 79

System error: Can not access a needed shared library

ESysELIBBAD = 80

System error: Accessing a corrupted shared library

ESysELIBEXEC = 83

System error: Cannot exec a shared library directly

ESysELIBMAX = 82

System error: Attempting to link in too many shared libraries

ESysELIBSCN = 81

System error: .lib section in a.out corrupted

ESysELNRNG = 48

System error: Link number out of range

ESysELOOP = 40

System error: Too many symbolic links encountered

ESysEMFILE = 24

System error: Too many open files

ESysEMLINK = 31

System error: Too many links

ESysEMSGSIZE = 90

System error: Message too long

ESysEMULTIHOP = 72

System error: Multihop attempted

ESysENAMETOOLONG = 36

System error: File name too long

ESysENAVAIL = 119

System error: No XENIX semaphores available

ESysENETDOWN = 100

System error: Network is down

ESysENETRESET = 102

System error: Network dropped connection because of reset

ESysENETUNREACH = 101

System error: Network is unreachable

ESysENFILE = 23

System error: File table overflow

ESysENOANO = 55

System error: No anode

ESysENOBUFFS = 105

System error: No buffer space available

ESysENOC SI = 50

System error: No CSI structure available

ESysENODATA = 61

System error: No data available

ESysENODEV = 19

System error: No such device

ESysENOENT = 2

System error: No such file or directory

ESysENOEXEC = 8

System error: Exec format error

ESysENOLCK = 37

System error: No record locks available

ESysENOLINK = 67

System error: Link has been severed

ESysENOMEM = 12

System error: Out of memory

ESysENOMSG = 42

System error: No message of desired type

ESysENONET = 64

System error: Machine is not on the network

ESysENOPKG = 65

System error: Package not installed

ESysENOPROTOOPT = 92

System error: Protocol not available

ESysENOSPC = 28

System error: No space left on device

ESysENOSR = 63

System error: Out of streams resources

ESysENOSTR = 60

System error: Device not a stream

ESysENOSYS = 38

System error: Function not implemented

ESysENOTBLK = 15

System error: Block device required

ESysENOTCONN = 107

System error: Transport endpoint is not connected

ESysENOTDIR = 20

System error: Not a directory

ESysENOTEMPTY = 39

System error: Directory not empty

ESysENOTNAM = 118

System error: Not a XENIX named type file

ESysENOTSOCK = 88

System error: Socket operation on non-socket

ESysENOTTY = 25

System error: Not a typewriter

ESysENOTUNIQ = 76

System error: Name not unique on network

ESysENXIO = 6

System error: No such device or address

ESysEOPNOTSUPP = 95

System error: Operation not supported on transport endpoint

ESysEOVERFLOW = 75

System error: Value too large for defined data type

ESysEPERM = 1

System error: Operation not permitted.

ESysEPFNOSUPPORT = 96

System error: Protocol family not supported

ESysEPIPE = 32

System error: Broken pipe

ESysEPROTO = 71

System error: Protocol error

ESysEPROTONOSUPPORT = 93

System error: Protocol not supported

ESysEPROTOTYPE = 91

System error: Protocol wrong type for socket

ESysERANGE = 34

System error: Math result not representable

ESysEREMCHG = 78

System error: Remote address changed

ESysEREMOTE = 66

System error: Object is remote

ESysEREMOTEIO = 121

System error: Remote I/O error

ESysERESTART = 85

System error: Interrupted system call should be restarted

ESysEROFS = 30

System error: Read-only file system

ESysESHUTDOWN = 108

System error: Cannot send after transport endpoint shutdown

ESysESOCKTNOSUPPORT = 94

System error: Socket type not supported

ESysESPIPE = 29

System error: Illegal seek

ESysESRCH = 3

System error: No such process

ESysESRMNT = 69

System error: Srmount error

ESysESTALE = 116

System error: Stale NFS file handle

ESysESTRPIPE = 86

System error: Streams pipe error

ESysETIME = 62

System error: Timer expired

ESysETIMEDOUT = 110

System error: Connection timed out

ESysETOOMANYREFS = 109

System error: Too many references: cannot splice

ESysETXTBSY = 26

System error: Text (code segment) file busy

ESysEUCLEAN = 117

System error: Structure needs cleaning

ESysEUNATCH = 49

System error: Protocol driver not attached

ESysEUSERS = 87

System error: Too many users

ESysEWOULDBLOCK = ESysEAGAIN

System error: Operation would block

ESysEXDEV = 18

System error: Cross-device link

ESysEXFULL = 54

System error: Exchange full

FD\_MAXFDSET = 1024

Maximum elements in a TFDSet ([135](#)) array.

FPE\_FLTDIV = 3

Value signalling floating point divide by zero in case of SIGFPE signal

FPE\_FLTINV = 7

Value signalling floating point invalid operation in case of SIGFPE signal

FPE\_FLTOVF = 4

Value signalling floating point overflow in case of SIGFPE signal

FPE\_FLTRES = 6

Value signalling floating point inexact result in case of SIGFPE signal

FPE\_FLTSUB = 8

Value signalling floating point subscript out of range in case of SIGFPE signal

FPE\_FLTUND = 5

Value signalling floating point underflow in case of SIGFPE signal

FPE\_INTDIV = 1

Value signalling integer divide in case of SIGFPE signal

FPE\_INTOVF = 2



Value signalling integer overflow in case of SIGFPE signal

`F_GetFd = 1`

`fpFCntl (149)` command: Get close-on-exec flag

`F_GetFl = 3`

`fpFCntl (149)` command: Get filedescriptor flags

`F_GetLk = 5`

`fpFCntl (149)` command: Get lock

`F_GetOwn = 9`

`fpFCntl (149)` command: get owner of filedescriptor events

`F_OK = 0`

`fpAccess (141)` call test: file exists.

`F_SetFd = 2`

`fpFCntl (149)` command: Set close-on-exec flag

`F_SetFl = 4`

`fpFCntl (149)` command: Set filedescriptor flags

`F_SetLk = 6`

`fpFCntl (149)` command: Set lock

`F_SetLkW = 7`

`fpFCntl (149)` command: Test lock

`F_SetOwn = 8`

`fpFCntl (149)` command: Set owner of filedescriptor events

`ln2bitmask = 1shl ln2bitsinword-1`

Last bit in word.

`ln2bitsinword = 5`

Power of 2 number of bits in word.

`MAP_ANON = MAP_ANONYMOUS`

Anonymous memory mapping (data private to application)

`MAP_ANONYMOUS = $20`

`FpMMap (163)` map type: Don't use a file

`MAP_FAILED = pointer(-1)`

Memory mapping failed error code

`MAP_FIXED = $10`

`FpMMap (163)` map type: Interpret addr exactly

`MAP_PRIVATE = $2`

`FpMMap (163)` map type: Changes are private

`MAP_SHARED = $1`

`FpMMap (163)` map type: Share changes

`MAP_TYPE = $f`

`FpMMap (163)` map type: Bitmask for type of mapping

`NAME_MAX = UnixType.NAME_MAX`

Maximum filename length.

`O_APPEND = $400`

`fpOpen (166)` file open mode: Append to file

`O_CREAT = $40`

`fpOpen (166)` file open mode: Create if file does not yet exist.

`O_DIRECT = $4000`

`fpOpen (166)` file open mode: Minimize caching effects

`O_DIRECTORY = $10000`

`fpOpen (166)` file open mode: File must be directory.

`O_EXCL = $80`

`fpOpen (166)` file open mode: Open exclusively

`O_NDELAY = O_NONBLOCK`

`fpOpen (166)` file open mode: Alias for `O_NonBlock (114)`

`O_NOCTTY = $100`

`fpOpen (166)` file open mode: No TTY control.

`O_NOFOLLOW = $20000`

`fpOpen (166)` file open mode: Fail if file is symbolic link.

`O_NONBLOCK = $800`

`fpOpen (166)` file open mode: Open in non-blocking mode

`O_RDONLY = 0`

`fpOpen (166)` file open mode: Read only

`O_RDWR = 2`

`fpOpen (166)` file open mode: Read/Write

`O_SYNC = $1000`

`fpOpen (166)` file open mode: Write to disc at once

`O_TRUNC = $200`

`fpOpen (166)` file open mode: Truncate file to length 0

`O_WRONLY = 1`

`fpOpen (166)` file open mode: Write only

`PATH_MAX = UnixType.PATH_MAX`

Maximum pathname length.

`POLLERR = $0008`

Error condition on output file descriptor

`POLLHUP = $0010`

Hang up

`POLLIN = $0001`

Data is available for reading

`POLLNVAL = $0020`

Invalid request, file descriptor not open.

POLLOUT = \$0004

Writing data will not block the write call

POLLPRI = \$0002

Urgent data is available for reading.

POLLRDBAND = \$0080

Priority data ready for reading.

POLLRDNORM = \$0040

Same as POLLIN.

POLLWRBAND = \$0200

Priority data may be written.

POLLWRNORM = \$0100

Equivalent to POLLOUT.

PRIO\_PGRP = UnixType.PRIO\_PGRP

Easy access alias for unixtype.PRIO\_PGRP ([1679](#))

PRIO\_PROCESS = UnixType.PRIO\_PROCESS

Easy access alias for unixtype.PRIO\_PROCESS ([1679](#))

PRIO\_USER = UnixType.PRIO\_USER

Easy access alias for unixtype.PRIO\_USER ([1679](#))

PROT\_EXEC = \$4

FpMMap ([163](#)) memory access: page can be executed

PROT\_NONE = \$0

FpMMap ([163](#)) memory access: page can not be accessed

PROT\_READ = \$1

FpMMap ([163](#)) memory access: page can be read

PROT\_WRITE = \$2

FpMMap (163) memory access: page can be written

RLIMIT\_AS = 9

RLimit request address space limit

RLIMIT\_CORE = 4

RLimit request max core file size

RLIMIT\_CPU = 0

RLimit request CPU time in ms

RLIMIT\_DATA = 2

RLimit request max data size

RLIMIT\_FSIZE = 1

Rlimit request maximum filesize

RLIMIT\_LOCKS = 10

RLimit request maximum file locks held

RLIMIT\_MEMLOCK = 8

RLimit request max locked-in-memory address space

RLIMIT\_NOFILE = 7

RLimit request max number of open files

RLIMIT\_NPROC = 6

RLimit request max number of processes

RLIMIT\_RSS = 5

RLimit request max resident set size

RLIMIT\_STACK = 3

RLimit request max stack size

R\_OK = 4

fpAccess (141) call test: read allowed

SA\_INTERRUPT = \$20000000

Sigaction options: ?

SA\_NOCLDSTOP = 1

Sigaction options: Do not receive notification when child processes stop

SA\_NOCLDWAIT = 2

Sigaction options: ?

SA\_NODEFER = \$40000000

Sigaction options: Do not mask signal in its own signal handler

SA\_NOMASK = SA\_NODEFER

Sigaction options: Do not prevent the signal from being received when it is handled.

SA\_ONESHOT = SA\_RESETHAND

Sigaction options: Restore the signal action to the default state.

SA\_ONSTACK = \$08000000

SA\_ONSTACK is used in the `fp_sigaction` (178) to indicate the signal handler must be called on an alternate signal stack provided by `fp_sigaltstack` (101). If an alternate stack is not available, the default stack will be used.

SA\_RESETHAND = \$80000000

Sigaction options: Restore signal action to default state when signal handler exits.

SA\_RESTART = \$10000000

Sigaction options: Provide behaviour compatible with BSD signal semantics

SA\_RESTORER = \$04000000

Signal restorer handler

SA\_SIGINFO = 4

Sigaction options: The signal handler takes 3 arguments, not one.

SEEK\_CUR = 1

`fpLseek` (160) option: Set position relative to current position.

SEEK\_END = 2

`fpLseek` (160) option: Set position relative to end of file.

SEEK\_SET = 0

fpLSeek (160) option: Set absolute position.

SIGABRT = 6

Signal: ABRT (Abort)

SIGALRM = 14

Signal: ALRM (Alarm clock)

SIGBUS = 7

Signal: BUS (bus error)

SIGCHLD = 17

Signal: CHLD (child status changed)

SIGCONT = 18

Signal: CONT (Continue)

SIGFPE = 8

Signal: FPE (Floating point error)

SIGHUP = 1

Signal: HUP (Hangup)

SIGILL = 4

Signal: ILL (Illegal instruction)

SIGINT = 2

Signal: INT (Interrupt)

SIGIO = 29

Signal: IO (I/O operation possible)

SIGIOT = 6

Signal: IOT (IOT trap)

SIGKILL = 9

Signal: KILL (unblockable)

SIGPIPE = 13

Signal: PIPE (Broken pipe)

SIGPOLL = SIGIO

Signal: POLL (Pollable event)

SIGPROF = 27

Signal: PROF (Profiling alarm)

SIGPWR = 30

Signal: PWR (power failure restart)

SIGQUIT = 3

Signal: QUIT

SIGSEGV = 11

Signal: SEGV (Segmentation violation)

SIGSTKFLT = 16

Signal: STKFLT (Stack Fault)

SIGSTOP = 19

Signal: STOP (Stop, unblockable)

SIGTerm = 15

Signal: TERM (Terminate)

SIGTRAP = 5

Signal: TRAP (Trace trap)

SIGTSTP = 20

Signal: TSTP (keyboard stop)

SIGTTIN = 21

Signal: TTIN (Terminal input, background)

SIGTTOU = 22

Signal: TTOU (Terminal output, background)



SIGUNUSED = 31

Signal: Unused

SIGURG = 23

Signal: URG (Socket urgent condition)

SIGUSR1 = 10

Signal: USR1 (User-defined signal 1)

SIGUSR2 = 12

Signal: USR2 (User-defined signal 2)

SIGVTALRM = 26

Signal: VTALRM (Virtual alarm clock)

SIGWINCH = 28

Signal: WINCH (Window/Terminal size change)

SIGXCPU = 24

Signal: XCPU (CPU limit exceeded)

SIGXFSZ = 25

Signal: XFSZ (File size limit exceeded)

SIG\_BLOCK = 0

Sigprocmask flags: Add signals to the set of blocked signals.

SIG\_DFL = 0

Signal handler: Default signal handler

SIG\_ERR = -1

Signal handler: error

SIG\_IGN = 1

Signal handler: Ignore signal

SIG\_MAXSIG = UnixType.SIG\_MAXSIG

Maximum system signal number.

`SIG_SETMASK = 2`

Sigprocmask flags: Set of blocked signals is given.

`SIG_UNBLOCK = 1`

Sigprocmask flags: Remove signals from the set set of blocked signals.

`SI_PAD_SIZE = ((128div sizeof(longint))-3)`

Signal information pad size.

`SYS_NMLN = UnixType.SYS_NMLN`

Max system name length.

`S_IFBLK = 24576`

File (#rtl.baseunix.stat (135) record) mode: Block device

`S_IFCHR = 8192`

File (#rtl.baseunix.stat (135) record) mode: Character device

`S_IFDIR = 16384`

File (#rtl.baseunix.stat (135) record) mode: Directory

`S_IFIFO = 4096`

File (#rtl.baseunix.stat (135) record) mode: FIFO

`S_IFLNK = 40960`

File (#rtl.baseunix.stat (135) record) mode: Link

`S_IFMT = 61440`

File (#rtl.baseunix.stat (135) record) mode: File type bit mask

`S_IFREG = 32768`

File (#rtl.baseunix.stat (135) record) mode: Regular file

`S_IFSOCK = 49152`

File (#rtl.baseunix.stat (135) record) mode: Socket

`S_IRGRP = %0000100000`

Mode flag: Read by group.

S\_IROTH = %0000000100

Mode flag: Read by others.

S\_IRUSR = %0100000000

Mode flag: Read by owner.

S\_IRWXG = S\_IRGRP or S\_IWGRP or S\_IXGRP

Mode flag: Read, write, execute by groups.

S\_IRWXO = S\_IROTH or S\_IWOTH or S\_IXOTH

Mode flag: Read, write, execute by others.

S\_IRWXU = S\_IRUSR or S\_IWUSR or S\_IXUSR

Mode flag: Read, write, execute by user.

S\_IWGRP = %0000010000

Mode flag: Write by group.

S\_IWOTH = %0000000010

Mode flag: Write by others.

S\_IWUSR = %0010000000

Mode flag: Write by owner.

S\_IXGRP = %0000001000

Mode flag: Execute by group.

S\_IXOTH = %0000000001

Mode flag: Execute by others.

S\_IXUSR = %0001000000

Mode flag: Execute by owner.

UTSNAME\_DOMAIN\_LENGTH = UTSNAME\_LENGTH

Max length of utsname (140) domain name.

UTSNAME\_LENGTH = SYS\_NMLN

Max length of utsname (140) system name, release, version, machine.

UTSNAME\_NODENAME\_LENGTH = UTSNAME\_LENGTH

Max length of utsname (140) node name.

WNOHANG = 1

#rtl.baseunix.fpWaitpid (191) option: Do not wait for processes to terminate.

wordsinfdset = FD\_MAXFDSET div BITSINWORD

Number of words in a TFDSet (135) array

wordsinsigset = SIG\_MAXSIG div BITSINWORD

Number of words in a signal set.

WUNTRACED = 2

#rtl.baseunix.fpWaitpid (191) option: Also report children which were stopped but not yet reported

W\_OK = 2

fpAccess (141) call test: write allowed

X\_OK = 1

fpAccess (141) call test: execute allowed

\_STAT\_VER = \_STAT\_VER\_LINUX

Stat version number

\_STAT\_VER\_KERNEL = 1

Current version of stat record

\_STAT\_VER\_LINUX = 3

Version of linux stat record

\_STAT\_VER\_LINUX\_OLD = 1

Old kernel definition of stat

\_STAT\_VER\_SVR4 = 2

SVR 4 definition of stat

### 1.3.2 Types

`Blkcnt64_t = cuint64`

64-bit block count

`Blkcnt_t = cuint`

Block count type.

`Blksize_t = cuint`

Block size type.

`cbool = UnixType.cbool`

Boolean type

`cchar = UnixType.cchar`

Alias for `#rtl.UnixType.cchar` ([1681](#))

`cdouble = UnixType.cdouble`

Double precision real format.

`cfloat = UnixType.cfloat`

Floating-point real format

`cint = UnixType.cint`

C type: integer (natural size)

`cint16 = UnixType.cint16`

C type: 16 bits sized, signed integer.

`cint32 = UnixType.cint32`

C type: 32 bits sized, signed integer.

`cint64 = UnixType.cint64`

C type: 64 bits sized, signed integer.

`cint8 = UnixType.cint8`

C type: 8 bits sized, signed integer.

`clock_t = UnixType.clock_t`

Clock ticks type

`clong = UnixType.clong`

C type: long signed integer (double sized)

`clonglong = UnixType.clonglong`

C type: 64-bit (double long) signed integer.

`coff_t = UnixType.TOff`

Character offset type

`cschar = UnixType.cschar`

Signed character type

`cshort = UnixType.cshort`

C type: short signed integer (half sized)

`csigned = UnixType.csigned`

`csigned` is an alias for `cint` ([124](#)).

`csint = UnixType.csint`

Signed integer

`csize_t = UnixType.size_t`

Character size type

`cslong = UnixType.cslong`

The size is CPU dependent.

`cslonglong = UnixType.cslonglong`

`cslonglong` is an alias for `clonglong` ([125](#)).

`csshort = UnixType.csshort`

Short signed integer type

`cuchar = UnixType.cuchar`

Alias for `#rtl.UnixType.cuchar` ([1682](#))

`cuint = UnixType.cuint`

C type: unsigned integer (natural size)

```
cuint16 = UnixType.cuint16
```

C type: 16 bits sized, unsigned integer.

```
cuint32 = UnixType.cuint32
```

C type: 32 bits sized, unsigned integer.

```
cuint64 = UnixType.cuint64
```

C type: 64 bits sized, unsigned integer.

```
cuint8 = UnixType.cuint8
```

C type: 8 bits sized, unsigned integer.

```
culong = UnixType.culong
```

C type: long unsigned integer (double sized)

```
culonglong = UnixType.culonglong
```

C type: 64-bit (double long) unsigned integer.

```
cunsigned = UnixType.cunsigned
```

Alias for `#rtl.unixtype.cunsigned` ([1683](#))

```
cushort = UnixType.cushort
```

C type: short unsigned integer (half sized)

```
dev_t = UnixType.dev_t
```

Device descriptor type.

```
Dir = record
  dd_fd : Integer;
  dd_loc : LongInt;
  dd_size : Integer;
  dd_buf : pDirent;
  dd_nextoff : cardinal;
  dd_max : Integer;
  dd_lock : pointer;
end
```

Record used in `fpOpenDir` ([168](#)) and `fpReadDir` ([172](#)) calls

```
Dirent = packed record
  d_fileno : ino64_t;
  d_off : off_t;
  d_reclen : cushort;
  d_type : cuchar;
  d_name : Array[0..(255+1)-1] of Char;
end
```

Record used in the `fpReadDir` (172) function to return files in a directory.

```
FLock = record
  l_type : cshort;
  l_whence : cshort;
  l_start : kernel_off_t;
  l_len : kernel_off_t;
  l_pid : pid_t;
end
```

Lock description type for `fpFCntl` (149) lock call.

```
FLock64 = record
  l_type : cshort;
  l_whence : cshort;
  l_start : kernel_loff_t;
  l_len : kernel_loff_t;
  l_pid : pid_t;
end
```

`FLock64` is the record used in the `FpFcntl` (149) file locking call. It is the same as the `FLock` (127) type, only contains 64-bit offsets.

```
gid_t = UnixType.gid_t
```

Group ID type.

```
ino_t = UnixType.ino_t
```

Inode type.

```
iovec = record
  iov_base : pointer;
  iov_len : size_t;
end
```

`iovec` is used in `freadv` (173) for IO to multiple buffers to describe a buffer location.

```
kernel_loff_t = clonglong
```

Long kernel offset type



`kernel_off_t = clong`

Kernel offset type

`mode_t = UnixType.mode_t`

Inode mode type.

`nlink_t = UnixType.nlink_t`

Number of links type.

`off_t = UnixType.off_t`

Offset type.

`PBlkCnt = ^Blkcnt_t`

pointer to TBlkCnt (135) type.

`PBlkSize = ^Blksize_t`

Pointer to TBlkSize (135) type.

`pcbool = UnixType.pcbbool`

Pointer to boolean type cbool (124)

`pcchar = UnixType.pcchar`

Alias for #rtl.UnixType.pcchar (1684)

`pcdouble = UnixType.pcdouble`

Pointer to cdouble (124) type.

`pcfloat = UnixType.pcfloating`

Pointer to cfloat (124) type.

`pcint = UnixType.pcint`

Pointer to cInt (124) type.

`pcint16 = UnixType.pcint16`

Pointer to 16-bit signed integer type

`pcint32 = UnixType.pcint32`

Pointer to signed 32-bit integer type

`pcint64 = UnixType.pcint64`

Pointer to signed 64-bit integer type

`pcint8 = UnixType.pcint8`

Pointer to 8-bits signed integer type

`pClock = UnixType.pClock`

Pointer to TClock (135) type.

`pclong = UnixType.pclong`

Pointer to cLong (125) type.

`pclonglong = UnixType.pclonglong`

Pointer to longlong type.

`pcschar = UnixType.pcschar`

Pointer to character type cschar (125).

`pcshort = UnixType.pcsshort`

Pointer to cShort (125) type.

`pcsigned = UnixType.pcsigned`

Pointer to signed integer type csigned (125).

`pcsint = UnixType.pcsint`

Pointer to signed integer type csint (125)

`pctest_t = UnixType.pctest_t`

Pointer to csize\_t

`pcslong = UnixType.pcslong`

Pointer of the signed long cslong (125)

`pcslonglong = UnixType.pcslonglong`

Pointer to Signed longlong type cslonglong (125)

`pcsshort = UnixType.pcsshort`

Pointer to short signed integer type csshort (125)

`pcuchar = UnixType.pcuchar`

Alias for `#rtl.UnixType.pcuchar` (1685)

`pcuint = UnixType.pcuint`

Pointer to `cUInt` (126) type.

`pcuint16 = UnixType.pcuint16`

Pointer to 16-bit unsigned integer type

`pcuint32 = UnixType.pcuint32`

Pointer to unsigned 32-bit integer type

`pcuint64 = UnixType.pcuint64`

Pointer to unsigned 64-bit integer type

`pcuint8 = UnixType.pcuint8`

Pointer to 8-bits unsigned integer type

`pculong = UnixType.pculong`

Pointer to `cuLong` (126) type.

`pculonglong = UnixType.pculonglong`

Unsigned longlong type

`pcunsigned = UnixType.pcunsigned`

Alias for `#rtl.unixtype.pcunsigned` (1686)

`pcushort = UnixType.pcushort`

Pointer to `cuShort` (126) type.

`pDev = UnixType.pDev`

Pointer to `TDev` (135) type.

`pDir = ^Dir`

Pointer to `TDir` (135) record

`pDirent = ^Dirent`

Pointer to `TDirent` (135) record.

`pFDSet = ^TFDSet`

Pointer to TFDSet (135) type.

`pFilDes = ^TFilDes`

Pointer to TFilDes (135) type.

`pfpstate = ^tfpstate`

Pointer to tfpstate (136) record.

`pGid = UnixType.pGid`

Pointer to TGid (136) type.

`pGrpArr = ^TGrpArr`

Pointer to TGrpArr (136) array.

`pid_t = UnixType.pid_t`

Process ID type.

`pIno = UnixType.pIno`

Pointer to TIno (136) type.

`piovec = ^tiovec`

pointer to a iovec (127) record

`pMode = UnixType.pMode`

Pointer to TMode (137) type.

`pnLink = UnixType.pnLink`

Pointer to TnLink (137) type.

`pOff = UnixType.pOff`

Pointer to TOff (137) type.

```
pollfd = record
  fd : cint;
  events : cshort;
  revents : cshort;
end
```

`pollfd` is used in the `fpPoll` (170) call to describe the various actions.

`pPid = UnixType.pPid`

Pointer to `TPid` (137) type.

`ppollfd = ^pollfd`

Pointer to `tpollfd`.

`PRLimit = ^TRLimit`

Pointer to `TRLimit` (137) record

`psigactionrec = ^sigactionrec`

Pointer to `SigActionRec` (134) record type.

`PSigContext = ^TSigContext`

Pointer to `#rtl.baseunix.TSigContext` (138) record type.

`psiginfo = ^tsiginfo`

Pointer to `#rtl.baseunix.TSigInfo` (138) record type.

`psigset = ^tsigset`

Pointer to `SigSet` (134) type.

`pSize = UnixType.pSize`

Pointer to `TSize` (139) type.

`pSize_t = UnixType.pSize_t`

Pointer to `Size_t`

`pSocklen = UnixType.pSocklen`

Pointer to `TSockLen` (139) type.

`psSize = UnixType.psSize`

Pointer to `TsSize` (139) type

`PStat = ^Stat`

Pointer to `TStat` (139) type.

`pthread_cond_t = UnixType.pthread_cond_t`

Thread conditional variable type.

```
pthread_mutex_t = UnixType.pthread_mutex_t
```

Thread mutex type.

```
pthread_t = UnixType.pthread_t
```

Posix thread type.

```
pTime = UnixType.pTime
```

Pointer to TTime (139) type.

```
ptimespec = UnixType.ptimespec
```

Pointer to timespec (136) type.

```
ptimeval = UnixType.ptimeval
```

Pointer to timeval (136) type.

```
ptimezone = ^timezone
```

Pointer to TimeZone (136) record.

```
ptime_t = UnixType.ptime_t
```

Pointer to time\_t (136) type.

```
PTms = ^tms
```

Pointer to TTms (139) type.

```
Pucontext = ^Tucontext
```

Pointer to TUContext (140) type.

```
pUId = UnixType.pUId
```

Pointer to TUid (140) type.

```
pUtimBuf = ^UtimBuf
```

Pointer to TUTimBuf (140) type.

```
PUtsName = ^TUTsName
```

Pointer to TUtName (140) type.

```
rlim_t = culong
```

`rlim_t` is used as the type for the various fields in the `TRLimit` (137) record.

`sigactionhandler = sigactionhandler_t`

When installing a signal handler, the actual signal handler must be of type `SigActionHandler`.

```
sigactionhandler_t = procedure(signal: LongInt; info: psiginfo;
                               context: PSigContext) of object
```

Standard signal action handler prototype

```
sigactionrec = record
  sa_handler : sigactionhandler_t;
  sa_flags : culong;
  sa_restorer : sigrestorerhandler_t;
  sa_mask : sigset_t;
end
```

Record used in `fpSigAction` (178) call.

`signalhandler = signalhandler_t`

Simple signal handler prototype

```
signalhandler_t = procedure(signal: LongInt) of object
```

Standard signal handler prototype

`sigrestorerhandler = sigrestorerhandler_t`

Alias for `sigrestorerhandler_t` (134) type.

```
sigrestorerhandler_t = procedure of object
```

Standard signal action restorer prototype

`sigset = sigset_t`

Signal set type

```
sigset_t = Array[0..wordsinsigset-1] of culong
```

Signal set type

```
size_t = UnixType.size_t
```

Size specification type.

```
socklen_t = UnixType.socklen_t
```

Socket address length type.

```
ssize_t = UnixType.ssize_t
```

Small size type.

```
Stat = packed record
end
```

Record describing an inode (file) in the FPFstat (152) call.

```
TBlkCnt = Blkcnt_t
```

Alias for Blkcnt\_t (124) type.

```
TBlkSize = Blksize_t
```

Alias for blksize\_t (124) type.

```
TClock = UnixType.TClock
```

Alias for clock\_t (125) type.

```
TDev = UnixType.TDev
```

Alias for dev\_t (126) type.

```
TDir = Dir
```

Alias for Dir (126) type.

```
TDirent = Dirent
```

Alias for Dirent (127) type.

```
TFDSet = Array[0..(FD_MAXFDSETdivBITSINWORD)-1] of culong
```

File descriptor set for fpSelect (175) call.

```
TFilDes = Array[0..1] of cint
```

Array of file descriptors as used in fpPipe (169) call.

```
tfpreg = record
  significand : Array[0..3] of Word;
  exponent : Word;
end
```

Record describing floating point register in signal handler.



```
tfpstate = record
  cw : cardinal;
  sw : cardinal;
  tag : cardinal;
  ipoff : cardinal;
  cssel : cardinal;
  dataoff : cardinal;
  datasel : cardinal;
  st : Array[0..7] of tfpreg;
  status : cardinal;
end
```

Record describing floating point unit in signal handler.

```
TGid = UnixType.TGid
```

Alias for `gid_t` (127) type.

```
TGrpArr = Array[0..0] of TGid
```

Array of `gid_t` (127) IDs

```
timespec = UnixType.timespec
```

Short time specification type.

```
timeval = UnixType.timeval
```

Time specification type.

```
timezone = packed record
  tz_minuteswest : cint;
  tz_dsttime : cint;
end
```

Record describing a timezone

```
time_t = UnixType.time_t
```

Time span type

```
TIno = UnixType.TIno
```

Alias for `ino_t` (127) type.

```
TIOCtlRequest = UnixType.TIOCtlRequest
```

Easy access alias for `unixtype.TIOCtlRequest` (1691)

```
tiovec = iovec
```

Alias for the `iovec` (127) record type.

```
TMode = UnixType.TMode
```

Alias for `mode_t` (128) type.

```
tms = packed record
  tms_utime : clock_t;
  tms_stime : clock_t;
  tms_cutime : clock_t;
  tms_cstime : clock_t;
end
```

Record containing timings for `fpTimes` (188) call.

```
TnLink = UnixType.TnLink
```

Alias for `nlink_t` (128) type.

```
TOff = UnixType.TOff
```

Alias for `off_t` (128) type.

```
TPid = UnixType.TPid
```

Alias for `pid_t` (131) type.

```
tpollfd = pollfd
```

Alias for `pollfd` type

```
TRLimit = record
  rlim_cur : rlim_t;
  rlim_max : rlim_t;
end
```

`TRLimit` is the structure used by the kernel to return resource limit information in.

```
tsigactionhandler = sigactionhandler_t
```

Alias for `sigactionhandler_t` (134) type.

```
tsigaltstack = record
  ss_sp : pointer;
  ss_flags : LongInt;
  ss_size : LongInt;
end
```

Provide the location of an alternate signal handler stack.

```

TSigContext = record
  gs : Word;
  __gsh : Word;
  fs : Word;
  __fsh : Word;
  es : Word;
  __esh : Word;
  ds : Word;
  __dsh : Word;
  edi : cardinal;
  esi : cardinal;
  ebp : cardinal;
  esp : cardinal;
  ebx : cardinal;
  edx : cardinal;
  ecx : cardinal;
  eax : cardinal;
  trapno : cardinal;
  err : cardinal;
  eip : cardinal;
  cs : Word;
  __csh : Word;
  eflags : cardinal;
  esp_at_signal : cardinal;
  ss : Word;
  __ssh : Word;
  fpstate : pfpstate;
  oldmask : cardinal;
  cr2 : cardinal;
end

```

This type is CPU dependent. Cross-platform code should not use the contents of this record.

```

tsiginfo = record
  si_signo : LongInt;
  si_errno : LongInt;
  si_code : LongInt;
  _sifields : record
    end;
end

```

This type describes the signal that occurred.

```
tsignalhandler = signalhandler_t
```

Alias for `signalhandler_t` (134) type.

```
tsigrestorerhandler = sigrestorerhandler_t
```

Alias for `sigrestorerhandler_t` (134) type.

`tsigset = sigset_t`

Alias for `SigSet` (134) type.

`TSize = UnixType.TSize`

Alias for `size_t` (134) type

`TSocklen = UnixType.TSocklen`

Alias for `socklen_t` (135) type.

`TsSize = UnixType.TsSize`

Alias for `ssize_t` (135) type

`TStat = Stat`

Alias for `Stat` (135) type.

`tstatfs = UnixType.TStatFs`

Record describing a file system in the `baseunix.fpstatfs` (101) call.

`TTime = UnixType.TTime`

Alias for `TTime` (139) type.

`Ttimespec = UnixType.Ttimespec`

Alias for `TimeSpec` (136) type.

`TTimeVal = UnixType.TTimeVal`

Alias for `timeval` (136) type.

`TTimeZone = timezone`

Alias for `TimeZone` (136) record.

`TTms = tms`

Alias for `Tms` (137) record type.

```
TUcontext = record
  uc_flags : cardinal;
  uc_link : Pucontext;
  uc_stack : tsigaltstack;
  uc_mcontext : TSigContext;
  uc_sigmask : tsigset;
end
```

This structure is used to describe the user context in a program or thread. It is not used in this unit, but is provided for completeness.

`TUId = UnixType.TUId`

Alias for `uid_t` (140) type.

`TUtimBuf = UtimBuf`

Alias for `UtimBuf` (140) type.

`TUtsName = UtsName`

Alias for `UtsName` (140) type.

`uid_t = UnixType.uid_t`

User ID type

```
UtimBuf = record
  actime : time_t;
  modtime : time_t;
end
```

Record used in `fpUtime` (189) to set file access and modification times.

```
UtsName = record
  Sysname : Array[0..UTSNAME_LENGTH-1] of Char;
  Nodename : Array[0..UTSNAME_NODENAME_LENGTH-1] of Char;
  Release : Array[0..UTSNAME_LENGTH-1] of Char;
  Version : Array[0..UTSNAME_LENGTH-1] of Char;
  Machine : Array[0..UTSNAME_LENGTH-1] of Char;
  Domain : Array[0..UTSNAME_DOMAIN_LENGTH-1] of Char;
end
```

The elements of this record are null-terminated C style strings, you cannot access them directly. Note that the `Domain` field is a GNU extension, and may not be available on all platforms.

## 1.4 Procedures and functions

### 1.4.1 CreateShellArgV

**Synopsis:** Create a null-terminated array of strings from a command-line string

**Declaration:** `function CreateShellArgV(const prog: String) : ppchar`  
`function CreateShellArgV(const prog: Ansistring) : ppchar`

**Visibility:** default

**Description:** `CreateShellArgV` creates a command-line string for executing a shell command using `'sh -c'`. The result is a null-terminated array of null-terminated strings suitable for use in `fpExecv` (147) and friends.

**Errors:** If no more memory is available, a heap error may occur.

**See also:** `fpExecv` (147), `FreeShellArgV` (192)

### 1.4.2 FpAccess

Synopsis: Check file access

Declaration: `function FpAccess(pathname: pChar;aMode: cint) : cint`  
`function FpAccess(pathname: AnsiString;aMode: cint) : cint`

Visibility: default

Description: `FpAccess` tests user's access rights on the specified file. Mode is a mask existing of one or more of the following:

**R\_OK**User has read rights.

**W\_OK**User has write rights.

**X\_OK**User has execute rights.

**F\_OK**File exists.

The test is done with the real user ID, instead of the effective user ID. If the user has the requested rights, zero is returned. If access is denied, or an error occurred, a nonzero value is returned.

Errors: Extended error information can be retrieved using `fpGetErrno` ([154](#)).

**sys\_eaccess**The requested access is denied, either to the file or one of the directories in its path.

**sys\_einval**Mode was incorrect.

**sys\_enoent**A directory component in `Path` doesn't exist or is a dangling symbolic link.

**sys\_enotdir**A directory component in `Path` is not a directory.

**sys\_enomem**Insufficient kernel memory.

**sys\_eloop**`Path` has a circular symbolic link.

See also: `FpChown` ([144](#)), `FpChmod` ([142](#))

**Listing:** `./bunixex/ex26.pp`

---

**Program** Example26;

*{ Program to demonstrate the Access function. }*

**Uses** BaseUnix;

**begin**

**if** `fpAccess ( '/etc/passwd',W_OK)=0` **then**

**begin**

**Writeln** ( 'Better check your system.' );

**Writeln** ( 'I can write to the /etc/passwd file !' );

**end**;

**end.**

---

### 1.4.3 FpAlarm

Synopsis: Schedule an alarm signal to be delivered

Declaration: `function FpAlarm(seconds: cuint) : cuint`

Visibility: default

**Description:** `FpAlarm` schedules an alarm signal to be delivered to your process in `Seconds` seconds. When `Seconds` seconds have elapsed, the system will send a `SIGALRM` signal to the current process. If `Seconds` is zero, then no new alarm will be set. Whatever the value of `Seconds`, any previous alarm is cancelled.

The function returns the number of seconds till the previously scheduled alarm was due to be delivered, or zero if there was none. A negative value indicates an error.

See also: `fpSigAction` (178), `fpPause` (169)

**Listing:** `./bunixex/ex59.pp`

**Program** `Example59`;

*{ Program to demonstrate the Alarm function. }*

**Uses** `BaseUnix`;

**Procedure** `AlarmHandler(Sig : cint); cdecl`;

**begin**

**Writeln** ( 'Got to alarm handler' );

**end**;

**begin**

**Writeln** ( 'Setting alarm handler' );

`fpSignal`(`SIGALRM`, `SignalHandler(@AlarmHandler)`);

**Writeln** ( 'Scheduling Alarm in 10 seconds' );

`fpAlarm`(10);

**Writeln** ( 'Pausing' );

`fpPause`;

**Writeln** ( 'Pause returned' );

**end**.

#### 1.4.4 FpChdir

**Synopsis:** Change current working directory.

**Declaration:** `function FpChdir(path: pChar) : cint`  
    `function FpChdir(path: AnsiString) : cint`

**Visibility:** `default`

**Description:** `fpChDir` sets the current working directory to `Path`.

It returns zero if the call was succesful, -1 on error.

**Note:** There exist a portable alternative to `fpChDir`: `system.chdir`. Please use `fpChDir` only if you are writing Unix specific code. `System.chdir` will work on all operating systems.

**Errors:** Extended error information can be retrieved using `fpGetErrno` (154).

See also: `fpGetCwd` (153)

#### 1.4.5 FpChmod

**Synopsis:** Change file permission bits

**Declaration:** `function FpChmod(path: pChar;Mode: TMode) : cint`  
`function FpChmod(path: AnsiString;Mode: TMode) : cint`

**Visibility:** `default`

**Description:** `fpChmod` sets the `Mode` bits of the file in `Path` to `Mode`. `Mode` can be specified by 'or'-ing the following values:

**S\_ISUID**Set user ID on execution.  
**S\_ISGID**Set Group ID on execution.  
**S\_ISVTX**Set sticky bit.  
**S\_IRUSR**Read by owner.  
**S\_IWUSR**Write by owner.  
**S\_IXUSR**Execute by owner.  
**S\_IRGRP**Read by group.  
**S\_IWGRP**Write by group.  
**S\_IXGRP**Execute by group.  
**S\_IROTH**Read by others.  
**S\_IWOTH**Write by others.  
**S\_IXOTH**Execute by others.  
**S\_IRWXO**Read, write, execute by others.  
**S\_IRWXG**Read, write, execute by groups.  
**S\_IRWXU**Read, write, execute by user.

If the function is successful, zero is returned. A nonzero return value indicates an error.

**Errors:** The following error codes are returned:

**sys\_eperm**The effective UID doesn't match the ownership of the file, and is not zero. Owner or group were not specified correctly.  
**sys\_eaccess**One of the directories in `Path` has no search (=execute) permission.  
**sys\_enoent**A directory entry in `Path` does not exist or is a symbolic link pointing to a non-existent directory.  
**sys\_enomem**Insufficient kernel memory.  
**sys\_erofs**The file is on a read-only filesystem.  
**sys\_eLOOP**`Path` has a reference to a circular symbolic link, i.e. a symbolic link, whose expansion points to itself.

See also: `fpChown` ([144](#)), `fpAccess` ([141](#))

**Listing:** `./bunixex/ex23.pp`

---

**Program** `Example23`;

*{ Program to demonstrate the Chmod function. }*

**Uses** `BaseUnix, Unix`;

**Var** `F : Text`;

**begin**



---

```

{ Create a file }
Assign (f, 'testex21');
Rewrite (F);
WriteLn (f, '#!/bin/sh');
WriteLn (f, 'echo Some text for this file');
Close (F);
fpChmod ('testex21', &777);
{ File is now executable }
fpexecl ('./testex21', []);
end.

```

---

### 1.4.6 FpChown

Synopsis: Change owner of file

Declaration: `function FpChown(path: pChar; owner: TUid; group: TGid) : cint`  
`function FpChown(path: AnsiString; owner: TUid; group: TGid) : cint`

Visibility: default

Description: `fpChown` sets the User ID and Group ID of the file in `Path` to `Owner, Group`.

The function returns zero if the call was successful, a nonzero return value indicates an error.

Errors: The following error codes are returned:

**sys\_eperm** The effective UID doesn't match the ownership of the file, and is not zero. Owner or group were not specified correctly.

**sys\_eaccess** One of the directories in `Path` has no search (=execute) permission.

**sys\_enoent** A directory entry in `Path` does not exist or is a symbolic link pointing to a non-existent directory.

**sys\_enomem** Insufficient kernel memory.

**sys\_erofs** The file is on a read-only filesystem.

**sys\_eloop** `Path` has a reference to a circular symbolic link, i.e. a symbolic link, whose expansion points to itself.

See also: `fpChmod` ([142](#)), `fpAccess` ([141](#))

**Listing:** `./bunixex/ex24.pp`

---

**Program** Example24;

*{ Program to demonstrate the Chown function. }*

**Uses** BaseUnix;

**Var** UID : TUid;  
 GID : TGid;  
 F : Text;

**begin**

```

WriteLn ('This will only work if you are root. ');
Write ('Enter a UID : '); readln(UID);
Write ('Enter a GID : '); readln(GID);
Assign (f, 'test.txt');

```

---

```

Rewrite (f);
Writeln (f, 'The owner of this file should become : ');
Writeln (f, 'UID : ', UID);
Writeln (f, 'GID : ', GID);
Close (F);
if fpChown ('test.txt', UID, GID) <> 0 then
  if fpgeterrno = ESysEPERM then
    Writeln ('You are not root !')
  else
    Writeln ('Chmod failed with exit code : ', fpgeterrno)
else
  Writeln ('Changed owner successfully !');
end.

```

---

### 1.4.7 FpClose

Synopsis: Close file descriptor

Declaration: `function FpClose(fd: cint) : cint`

Visibility: default

Description: `FpClose` closes a file with file descriptor `Fd`. The function returns zero if the file was closed successfully, a nonzero return value indicates an error.

For an example, see `FpOpen` ([166](#)).

Errors: Extended error information can be retrieved using `fpGetErrno` ([154](#)).

See also: `FpOpen` ([166](#)), `FpRead` ([171](#)), `FpWrite` ([191](#)), `FpFTruncate` ([153](#)), `FpLSeek` ([160](#))

### 1.4.8 FpClosedir

Synopsis: Close directory file descriptor

Declaration: `function FpClosedir(var dirp: Dir) : cint`

Visibility: default

Description: `FpCloseDir` closes the directory pointed to by `dirp`. It returns zero if the directory was closed successfully, -1 otherwise.

For an example, see `fpOpenDir` ([168](#)).

Errors: Extended error information can be retrieved using `fpGetErrno` ([154](#)).

See also: `FpOpenDir` ([168](#)), `FpReadDir` ([172](#))

### 1.4.9 FpDup

Synopsis: Duplicate a file handle

Declaration: `function FpDup(fildes: cint) : cint`

```

function FpDup(var oldfile: text; var newfile: text) : cint
function FpDup(var oldfile: File; var newfile: File) : cint

```

Visibility: default

**Description:** `FpDup` returns a file descriptor that is a duplicate of the file descriptor `fildes`.

The second and third forms make `NewFile` an exact copy of `OldFile`, after having flushed the buffer of `OldFile` in case it is a Text file or untyped file. Due to the buffering mechanism of Pascal, these calls do not have the same functionality as the `dup` call in C. The internal Pascal buffers are not the same after this call, but when the buffers are flushed (e.g. after output), the output is sent to the same file. Doing an `lseek` will, however, work as in C, i.e. doing a `lseek` will change the fileposition in both files.

The function returns a negative value in case of an error, a positive value is a file handle, and indicates succes.

**Errors:** A negative value can be one of the following error codes:

**sys\_ebadf**`OldFile` hasn't been assigned.

**sys\_emfile**Maximum number of open files for the process is reached.

See also: `fpDup2` ([146](#))

**Listing:** `./bunixex/ex31.pp`

---

```
program Example31 ;

{ Program to demonstrate the Dup function . }

uses baseunix ;

var f : text ;

begin
  if fpdup ( output , f ) < > 0 then
    Writeln ( 'Dup Failed ! ' ) ;
    writeln ( 'This is written to stdout . ' ) ;
    writeln ( f , 'This is written to the dup file , and flushed ' ) ; flush ( f ) ;
    writeln
  end .
```

---

### 1.4.10 FpDup2

**Synopsis:** Duplicate one filehandle to another

**Declaration:** `function FpDup2(fildes: cint;fildes2: cint) : cint`  
`function FpDup2(var oldfile: text;var newfile: text) : cint`  
`function FpDup2(var oldfile: File;var newfile: File) : cint`

**Visibility:** default

**Description:** Makes `fildes2` or `NewFile` an exact copy of `fildes` or `OldFile`, after having flushed the buffer of `OldFile` in the case of text or untyped files.

After a call to `fdup2`, the 2 file descriptors point to the same physical device (a file, socket, or a terminal).

`NewFile` can be an assigned file. If `newfile` or `fildes` was open, it is closed first. Due to the buffering mechanism of Pascal, this has not the same functionality as the `dup2` call in C. The internal Pascal buffers are not the same after this call, but when the buffers are flushed (e.g. after output), the output is sent to the same file. Doing an `lseek` will, however, work as in C, i.e. doing a `lseek` will change the fileposition in both files.

The function returns zero if succesful, a nonzero return value means the call failed.

Errors: In case of error, the following error codes can be reported:

**sys\_ebadf**OldFile (or fildes) hasn't been assigned.

**sys\_emfile**Maximum number of open files for the process is reached.

See also: `fpDup` ([145](#))

**Listing:** `./bunixex/ex32.pp`

---

```

program Example31;

{ Program to demonstrate the FpDup2 function. }

uses BaseUnix;

var f : text;
    i : longint;

begin
  Assign (f, 'text.txt');
  Rewrite (F);
  For i:=1 to 10 do writeln (F, 'Line : ', i);
  if fpdup2 (output, f)=-1 then
    writeln ('Dup2 Failed !');
  writeln ('This is written to stdout. ');
  writeln (f, 'This is written to the dup file , and flushed');
  flush(f);
  writeln;
  { Remove file . Comment this if you want to check flushing.}
  fpUnlink ('text.txt');
end.
```

---

### 1.4.11 FpExecv

Synopsis: Execute process

**Declaration:** `function FpExecv(path: pChar;argv: ppChar) : cint`  
`function FpExecv(path: AnsiString;argv: ppchar) : cint`

Visibility: default

**Description:** Replaces the currently running program with the program, specified in `path`. It gives the program the options in `argv`. This is a pointer to an array of pointers to null-terminated strings. The last pointer in this array should be nil. The current environment is passed to the program. On success, `execv` does not return.

Errors: Errors are reported in `fpErrno` ([101](#)):

**sys\_eaccess**File is not a regular file, or has no execute permission. A component of the path has no search permission.

**sys\_eperm**The file system is mounted `\textit{noexec}`.

**sys\_e2big**Argument list too big.

**sys\_enoexec**The magic number in the file is incorrect.

**sys\_enoent**The file does not exist.

**sys\_enomem**Not enough memory for kernel.

**sys\_enotdir** A component of the path is not a directory.

**sys\_eloop** The path contains a circular reference (via symlinks).

See also: `fpExecve` (148), `fpFork` (151)

**Listing:** `./bunixex/ex8.pp`

---

**Program** `Example8`;

*{ Program to demonstrate the Execv function. }*

**Uses** `Unix`, `strings`;

**Const** `Arg0 : PChar = '/bin/lS'`;  
           `Arg1 : Pchar = '-l'`;

**Var** `PP : PPchar`;

**begin**

`GetMem (PP, 3*SizeOf(Pchar));`

`PP[0]:=Arg0;`

`PP[1]:=Arg1;`

`PP[3]:=Nil;`

*{ Execute '/bin/lS -l', with current environment }*

`fpExecv ('/bin/lS',pp);`

**end.**

---

### 1.4.12 FpExecve

**Synopsis:** Execute process using environment

**Declaration:** `function FpExecve(path: pChar;argv: ppChar;envp: ppChar) : cint`  
                   `function FpExecve(path: AnsiString;argv: ppchar;envp: ppchar) : cint`

**Visibility:** `default`

**Description:** Replaces the currently running program with the program, specified in `path`. It gives the program the options in `argv`, and the environment in `envp`. They are pointers to an array of pointers to null-terminated strings. The last pointer in this array should be `nil`. On success, `execve` does not return.

**Errors:** Extended error information can be retrieved with `fpGetErrno` (154), and includes the following:

**sys\_eaccess** File is not a regular file, or has no execute permission. A component of the path has no search permission.

**sys\_eperm** The file system is mounted `\textit{noexec}`.

**sys\_e2big** Argument list too big.

**sys\_enoexec** The magic number in the file is incorrect.

**sys\_enoent** The file does not exist.

**sys\_enomem** Not enough memory for kernel.

**sys\_enotdir** A component of the path is not a directory.

**sys\_eloop** The path contains a circular reference (via symlinks).

See also: [fpExecv \(147\)](#), [fpFork \(151\)](#)

**Listing:** ./bunixex/ex7.pp

---

**Program** Example7;

*{ Program to demonstrate the Execve function. }*

**Uses** BaseUnix, strings;

**Const** Arg0 : PChar = '/bin/l*s*';  
           Arg1 : Pchar = '-l';

**Var** PP : PPchar;

**begin**

**GetMem** (PP,3\***SizeOf**(Pchar));  
   PP[0]:=Arg0;  
   PP[1]:=Arg1;  
   PP[3]:=**Nil**;  
   *{ Execute '/bin/l*s* -l', with current environment }*  
   *{ Env is defined in system.inc }*  
   fpExecVe ('/bin/l*s*',pp,envp);

**end.**

---

### 1.4.13 FpExit

**Synopsis:** Exit the current process

**Declaration:** procedure FpExit(Status: cint)

**Visibility:** default

**Description:** FpExit exits the currently running process, and report Status as the exit status.

**Remark:** If this call is executed, the normal unit finalization code will not be executed. This may lead to unexpected errors and stray files on your system. It is therefore recommended to use the Halt call instead.

**Errors:** None.

See also: [FpFork \(151\)](#), [FpExecve \(148\)](#)

### 1.4.14 FpFcntl

**Synopsis:** File control operations.

**Declaration:** function FpFcntl(fildes: cint;cmd: cint) : cint  
           function FpFcntl(fildes: cint;cmd: cint;arg: cint) : cint  
           function FpFcntl(fildes: cint;cmd: cint;var arg: FLock) : cint

**Visibility:** default

**Description:** Read/set a file's attributes. Fildes a valid file descriptor. Cmd specifies what to do, and is one of the following:

**F\_GetFd**Read the `close_on_exec` flag. If the low-order bit is 0, then the file will remain open across `execve` calls.

**F\_GetFl**Read the descriptor's flags.

**F\_GetOwn**Get the Process ID of the owner of a socket.

**F\_SetFd**Set the `close_on_exec` flag of `filides`. (only the least significant bit is used).

**F\_GetLk**Return the `flock` record that prevents this process from obtaining the lock, or set the `l_type` field of the lock if there is no obstruction. `Arg` is the `flock` record.

**F\_SetLk**Set the lock or clear it (depending on `l_type` in the `flock` structure). if the lock is held by another process, an error occurs.

**F\_GetLkw**Same as for **F\_Setlk**, but wait until the lock is released.

**F\_SetOwn**Set the Process or process group that owns a socket.

The function returns 0 if successful, -1 otherwise.

Errors: On error, -1 is returned. Use `fpGetErrno` (154) for extended error information.

**sys\_ebadf**`Fd` has a bad file descriptor.

**sys\_eagain** or **sys\_eaccess**For `\textbf{F_SetLk}`, if the lock is held by another process.

### 1.4.15 fpfdfillset

Synopsis: Set all filedescriptors in the set.

Declaration: `function fpfdfillset(var nset: TFDSet) : cint`

Visibility: default

Description: `fpfdfillset` sets all filedescriptors in `nset`.

See also: `FpSelect` (175), `FpFD_ZERO` (151), `FpFD_IsSet` (151), `FpFD_Clr` (150), `FpFD_Set` (151)

### 1.4.16 fpFD\_CLR

Synopsis: Clears a filedescriptor in a set

Declaration: `function fpFD_CLR(fdno: cint; var nset: TFDSet) : cint`

Visibility: default

Description: `FpFD_Clr` clears file descriptor `fdno` in filedescriptor set `nset`.

For an example, see `FpSelect` (175).

Errors: None.

See also: `FpSelect` (175), `FpFD_ZERO` (151), `FpFD_Set` (151), `FpFD_IsSet` (151)

### 1.4.17 fpFD\_ISSET

Synopsis: Check whether a filedescriptor is set

Declaration: `function fpFD_ISSET(fdno: cint; const nset: TFDSet) : cint`

Visibility: default

Description: `FpFD_Set` Checks whether file descriptor `fdNo` in filedescriptor set `fds` is set. It returns zero if the descriptor is not set, 1 if it is set. If the number of the filedescriptor it wrong, -1 is returned.

For an example, see `FpSelect` (175).

Errors: If an invalid file descriptor number is passed, -1 is returned.

See also: `FpSelect` (175), `FpFD_ZERO` (151), `FpFD_Clr` (150), `FpFD_Set` (151)

### 1.4.18 fpFD\_SET

Synopsis: Set a filedescriptor in a set

Declaration: `function fpFD_SET(fdno: cint; var nset: TFDSet) : cint`

Visibility: default

Description: `FpFD_Set` sets file descriptor `fdno` in filedescriptor set `nset`.

For an example, see `FpSelect` (175).

Errors: None.

See also: `FpSelect` (175), `FpFD_ZERO` (151), `FpFD_Clr` (150), `FpFD_IsSet` (151)

### 1.4.19 fpFD\_ZERO

Synopsis: Clear all file descriptors in set

Declaration: `function fpFD_ZERO(out nset: TFDSet) : cint`

Visibility: default

Description: `FpFD_ZERO` clears all the filedescriptors in the file descriptor set `nset`.

For an example, see `FpSelect` (175).

Errors: None.

See also: `FpSelect` (175), `FpFD_Clr` (150), `FpFD_Set` (151), `FpFD_IsSet` (151)

### 1.4.20 FpFork

Synopsis: Create child process

Declaration: `function FpFork : TPid`

Visibility: default

Description: `FpFork` creates a child process which is a copy of the parent process. `FpFork` returns the process ID in the parent process, and zero in the child's process. (you can get the parent's PID with `fpGetPPid` (157)).



Errors: On error, -1 is returned to the parent, and no child is created.

**sys\_eagain** Not enough memory to create child process.

See also: [fpExecve \(148\)](#), [#rtl.linux.Clone \(729\)](#)

### 1.4.21 FPFStat

Synopsis: Retrieve file information about a file descriptor.

Declaration: `function FpFStat(fd: cint;var sb: Stat) : cint`  
`function FPFStat(var F: Text;var Info: Stat) : Boolean`  
`function FPFStat(var F: File;var Info: Stat) : Boolean`

Visibility: default

Description: `FpFStat` gets information about the file specified in one of the following:

**Fd** a valid file descriptor.

**F** an opened text file or untyped file.

and stores it in `Info`, which is of type `stat` ([135](#)). The function returns zero if the call was successful, a nonzero return value indicates failure.

Errors: Extended error information can be retrieved using `fpGetErrno` ([154](#)).

**sys\_enoent** `Path` does not exist.

See also: [FpStat \(183\)](#), [FpLStat \(161\)](#)

**Listing:** `./bunixex/ex28.pp`

---

```

program example28;

{ Program to demonstrate the FStat function. }

uses BaseUnix;

var f : text;
    i : byte;
    info : stat;

begin
  { Make a file }
  assign (f, 'test.fil');
  rewrite (f);
  for i:=1 to 10 do writeln (f, 'Testline # ',i);
  close (f);
  { Do the call on made file. }
  if fpstat ('test.fil',info)<>0 then
    begin
      writeln('Fstat failed. Errno : ',fpgeterrno);
      halt (1);
    end;
  writeln;
  writeln ('Result of fstat on file ''test.fil''.');
  writeln ('Inode    : ',info.st_ino);
  writeln ('Mode     : ',info.st_mode);

```

---

```

writeln ( 'nlink    : ', info.st_nlink );
writeln ( 'uid      : ', info.st_uid );
writeln ( 'gid      : ', info.st_gid );
writeln ( 'rdev     : ', info.st_rdev );
writeln ( 'Size     : ', info.st_size );
writeln ( 'Blksize  : ', info.st_blksize );
writeln ( 'Blocks   : ', info.st_blocks );
writeln ( 'atime    : ', info.st_atime );
writeln ( 'mtime    : ', info.st_mtime );
writeln ( 'ctime    : ', info.st_ctime );
  { Remove file }
  erase ( f );
end .

```

---

### 1.4.22 FpFtruncate

Synopsis: Truncate file on certain size.

Declaration: `function FpFtruncate(fd: cint; flength: TOff) : cint`

Visibility: default

Description: `FpFtruncate` sets the length of a file in `fd` on `flength` bytes, where `flength` must be less than or equal to the current length of the file in `fd`.

The function returns zero if the call was successful, a nonzero return value indicates that an error occurred.

Errors: Extended error information can be retrieved using `fpGetErrno` ([154](#)).

See also: `FpOpen` ([166](#)), `FpClose` ([145](#)), `FpRead` ([171](#)), `FpWrite` ([191](#)), `FpLSeek` ([160](#))

### 1.4.23 FpGetcwd

Synopsis: Retrieve the current working directory.

Declaration: `function FpGetcwd(path: pChar; siz: TSize) : pChar`  
`function FpGetcwd : AnsiString`

Visibility: default

Description: `fpgetCWD` returns the current working directory of the running process. It is returned in `Path`, which points to a memory location of at least `siz` bytes.

If the function is succesful, a pointer to `Path` is returned, or a string with the result. On error `Nil` or an empty string are returned.

Errors: On error `Nil` or an empty string are returned.

See also: `FpGetPID` ([156](#)), `FpGetUID` ([158](#))

### 1.4.24 FpGetegid

Synopsis: Return effective group ID

Declaration: `function FpGetegid : TGid`

Visibility: default

**Description:** `FpGetegid` returns the effective group ID of the currently running process.

**Errors:** None.

**See also:** `FpGetGid` (155), `FpGetUid` (158), `FpGetEUid` (155), `FpGetPid` (156), `FpGetPPid` (157), `fpSetUID` (178), `FpSetGid` (176)

**Listing:** `./bunixex/ex18.pp`

---

**Program** `Example18`;

*{ Program to demonstrate the GetGid and GetEGid functions. }*

**Uses** `BaseUnix`;

```
begin
  writeLn ( 'Group Id = ',fpgetgid, ' Effective group Id = ',fpgetegid);
end.
```

---

### 1.4.25 FpGetEnv

**Synopsis:** Return value of environment variable.

**Declaration:** `function FpGetEnv(name: pChar) : pChar`  
`function FpGetEnv(name: String) : pChar`

**Visibility:** default

**Description:** `FPGetEnv` returns the value of the environment variable in `Name`. If the variable is not defined, `nil` is returned. The value of the environment variable may be the empty string. A `PChar` is returned to accomodate for strings longer than 255 bytes, `TERMCAP` and `LS_COLORS`, for instance.

**Errors:** None.

**Listing:** `./bunixex/ex41.pp`

---

**Program** `Example41`;

*{ Program to demonstrate the GetEnv function. }*

**Uses** `BaseUnix`;

```
begin
  WriteLn ( 'Path is : ',fpGetenv( 'PATH' ));
end.
```

---

### 1.4.26 fpgeterrno

**Synopsis:** Retrieve extended error information.

**Declaration:** `function fpgeterrno : LongInt`

**Visibility:** default

**Description:** `fpgeterrno` returns extended information on the latest error. It is set by all functions that communicate with the kernel or C library.

**Errors:** None.

**See also:** `fpseterrno` (176)

### 1.4.27 FpGeteuid

Synopsis: Return effective user ID

Declaration: `function FpGeteuid : TUid`

Visibility: default

Description: `FpGeteuid` returns the effective user ID of the currently running process.

Errors: None.

See also: `FpGetUid` (158), `FpGetGid` (155), `FpGetEGid` (153), `FpGetPid` (156), `FpGetPPid` (157), `fpSetUID` (178), `FpSetGid` (176)

**Listing:** `./bunixex/ex17.pp`

---

**Program** `Example17;`

*{ Program to demonstrate the GetUid and GetEUid functions. }*

**Uses** `BaseUnix;`

**begin**

`writeln ( 'User Id = ',fpgetuid , ' Effective user Id = ',fpgeteuid );`

`end.`

---

### 1.4.28 FpGetgid

Synopsis: Return real group ID

Declaration: `function FpGetgid : TGid`

Visibility: default

Description: `FpGetgid` returns the real group ID of the currently running process.

Errors: None.

See also: `FpGetEGid` (153), `FpGetUid` (158), `FpGetEUid` (155), `FpGetPid` (156), `FpGetPPid` (157), `fpSetUID` (178), `FpSetGid` (176)

**Listing:** `./bunixex/ex18.pp`

---

**Program** `Example18;`

*{ Program to demonstrate the GetGid and GetEGid functions. }*

**Uses** `BaseUnix;`

**begin**

`writeln ( 'Group Id = ',fpgetgid , ' Effective group Id = ',fpgetegid );`

`end.`

---

### 1.4.29 FpGetgroups

Synopsis: Get the list of supplementary groups.

Declaration: `function FpGetgroups(gidsetsize: cint; var grouplist: TGrpArr) : cint`

Visibility: default

Description: FpGetgroups returns up to gidsetsize groups in GroupList

If the function is successful, then number of groups that were stored is returned. On error, -1 is returned.

Errors: On error, -1 is returned. Extended error information can be retrieved with fpGetErrNo ([154](#))

See also: FpGetpgrp ([156](#)), FpGetGID ([155](#)), FpGetEGID ([153](#))

### 1.4.30 FpGetpgrp

Synopsis: Get process group ID

Declaration: `function FpGetpgrp : TPid`

Visibility: default

Description: FpGetpgrp returns the process group ID of the current process.

Errors: None.

See also: fpGetPID ([156](#)), fpGetPPID ([157](#)), FpGetGID ([155](#)), FpGetUID ([158](#))

### 1.4.31 FpGetpid

Synopsis: Return current process ID

Declaration: `function FpGetpid : TPid`

Visibility: default

Description: FpGetpid returns the process ID of the currently running process.

Note: There exist a portable alternative to fpGetpid: `system.GetProcessID`. Please use fpGetpid only if you are writing Unix specific code. `System.GetProcessID` will work on all operating systems.

Errors: None.

See also: FpGetPPid ([157](#))

---

**Listing:** ./bunixex/ex16.pp

**Program** Example16;

*{ Program to demonstrate the GetPid, GetPPid function. }*

**Uses** BaseUnix;

**begin**

**WriteLn** ( 'Process Id = ', fpgetpid, ' Parent process Id = ', fpgetppid );  
**end.**

---

### 1.4.32 FpGetppid

Synopsis: Return parent process ID

Declaration: `function FpGetppid : TPid`

Visibility: default

Description: `FpGetppid` returns the Process ID of the parent process.

Errors: None.

See also: `FpGetPid` ([156](#))

**Listing:** `./bunixex/ex16.pp`

---

**Program** `Example16;`

*{ Program to demonstrate the GetPid, GetPPid function. }*

**Uses** `BaseUnix;`

**begin**

`WriteLn ( 'Process Id = ',fpgetpid, ' Parent process Id = ',fpgetppid);`  
**end.**

---

### 1.4.33 fpGetPriority

Synopsis: Return process priority

Declaration: `function fpGetPriority(Which: cint;Who: cint) : cint`

Visibility: default

Description: `GetPriority` returns the priority with which a process is running. Which process(es) is determined by the `Which` and `Who` variables. `Which` can be one of the pre-defined `Prio_Process`, `Prio_PGrp`, `Prio_User`, in which case `Who` is the process ID, Process group ID or User ID, respectively.

For an example, see `FpNice` ([166](#)).

Errors: Error information is returned solely by the `FpGetErrno` ([154](#)) function: a priority can be a positive or negative value.

**sys\_esrch**No process found using `which` and `who`.

**sys\_einval**`Which` was not one of `Prio_Process`, `Prio_Grp` or `Prio_User`.

See also: `FpSetPriority` ([177](#)), `FpNice` ([166](#))

### 1.4.34 FpGetRLimit

Synopsis: Get process resource limits

Declaration: `function FpGetRLimit(resource: cint;rlim: PRLimit) : cint`

Visibility: default

**Description:** `FpGetRLimit` gets the resource limits for the current process: `resource` determines the resource of which the kernel should return the limits (one of the many `RLIMIT_*` constants). `rlim` should point to a `TRLimit` (1679) record and on success will contain the resource limits.

The function returns zero if the resource limits were correctly returned.

**Errors:** On error, -1 is returned and `fpgeterrno` (154) can be used to retrieve the error code.

**See also:** `FpSetRLimit` (177)

### 1.4.35 FpGetuid

**Synopsis:** Return current user ID

**Declaration:** `function FpGetuid : TUid`

**Visibility:** default

**Description:** `FpGetuid` returns the real user ID of the currently running process.

**Errors:** None.

**See also:** `FpGetGid` (155), `FpGetEuid` (155), `FpGetEGid` (153), `FpGetPid` (156), `FpGetPPid` (157), `fpSetUID` (178)

**Listing:** `./bunixex/ex17.pp`

---

**Program** Example17;

*{ Program to demonstrate the GetUid and GetEuid functions. }*

**Uses** BaseUnix;

**begin**

**writeln** ( 'User Id = ', fpgetuid, ' Effective user Id = ', fpgeteuid );

**end.**

---

### 1.4.36 FpIOctl

**Synopsis:** General kernel IOCTL call.

**Declaration:** `function FpIOctl(Handle: cint;Ndx: TIOctlRequest;Data: Pointer) : cint`

**Visibility:** default

**Description:** This is a general interface to the Unix/ linux ioctl call. It performs various operations on the filedescriptor `Handle`. `Ndx` describes the operation to perform. `Data` points to data needed for the `Ndx` function. The structure of this data is function-dependent, so we don't elaborate on this here. For more information on this, see various manual pages under linux.

**Errors:** Extended error information can be retrieved using `fpGetErrno` (154).

**Listing:** `./bunixex/ex54.pp`

---

```

Program Example54;

uses BaseUnix,Termio;

{ Program to demonstrate the IOCTL function. }

var
    tios : Termios;

begin
    { $ifdef FreeBSD}
    fpIOCtl(1,TIOCGETA,@tios); // these constants are very OS dependant.
                                // see the tcgetattr example for a better way
    { $endif}
    WriteLn('Input Flags : $',hexstr(tios.c_iflag,8));
    WriteLn('Output Flags : $',hexstr(tios.c_oflag,8));
    WriteLn('Line Flags : $',hexstr(tios.c_lflag,8));
    WriteLn('Control Flags: $',hexstr(tios.c_cflag,8));
end.

```

---

### 1.4.37 FpKill

Synopsis: Send a signal to a process

Declaration: `function FpKill(pid: TPid;sig: cint) : cint`

Visibility: default

Description: `fpKill` sends a signal `Sig` to a process or process group. If `Pid`>0 then the signal is sent to `Pid`, if it equals -1, then the signal is sent to all processes except process 1. If `Pid`<-1 then the signal is sent to process group -`Pid`.

The return value is zero, except in case three, where the return value is the number of processes to which the signal was sent.

Errors: Extended error information can be retrieved using `fpGetErrno` ([154](#)):

**sys\_einval**An invalid signal is sent.

**sys\_esrch**The `Pid` or process group don't exist.

**sys\_eperm**The effective userid of the current process doesn't math the one of process `Pid`.

See also: `FpSigAction` ([178](#)), `FpSignal` ([181](#))

### 1.4.38 FpLink

Synopsis: Create a hard link to a file

Declaration: `function FpLink(existing: pChar;newone: pChar) : cint`  
`function FpLink(existing: AnsiString;newone: AnsiString) : cint`

Visibility: default

Description: `fpLink` makes `NewOne` point to the same file als `Existing`. The two files then have the same inode number. This is known as a 'hard' link. The function returns zero if the call was succesfull, and returns a non-zero value if the call failed.



Errors: The following error codes are returned:

- sys\_exdev** Existing and NewOne are not on the same filesystem.
- sys\_eperm** The filesystem containing Existing and NewOne doesn't support linking files.
- sys\_eaccess** Write access for the directory containing NewOne is disallowed, or one of the directories in Existing or NewOne has no search (=execute) permission.
- sys\_enoent** A directory entry in Existing or NewOne does not exist or is a symbolic link pointing to a non-existent directory.
- sys\_enotdir** A directory entry in Existing or NewOne is not a directory.
- sys\_enomem** Insufficient kernel memory.
- sys\_erofs** The files are on a read-only filesystem.
- sys\_eexist** NewOne already exists.
- sys\_mlink** Existing has reached maximal link count.
- sys\_eloop** Existing or NewOne has a reference to a circular symbolic link, i.e. a symbolic link, whose expansion points to itself.
- sys\_enosp** The device containing NewOne has no room for another entry.
- sys\_eperm** Existing points to . or .. of a directory.

See also: `fpSymLink` (184), `fpUnLink` (189)

**Listing:** `./bunixex/ex21.pp`

---

**Program** Example21;

*{ Program to demonstrate the Link and UnLink functions. }*

**Uses** BaseUnix;

**Var** F : Text;

    S : **String**;

**begin**

    Assign (F, 'test.txt');

**Rewrite** (F);

**Writeln** (F, 'This is written to test.txt');

    Close(f);

*{ new.txt and test.txt are now the same file }*

**if** fpLink ('test.txt', 'new.txt') <> 0 **then**

**writeln** ('Error when linking !');

*{ Removing test.txt still leaves new.txt }*

**If** fpUnlink ('test.txt') <> 0 **then**

**Writeln** ('Error when unlinking !');

    Assign (f, 'new.txt');

**Reset** (F);

**While not EOF**(f) **do**

**begin**

**Readln**(F,S);

**Writeln** ('> ',s);

**end**;

    Close (f);

*{ Remove new.txt also }*

**If not** FPUntlink ('new.txt') <> 0 **then**

**Writeln** ('Error when unlinking !');

**end.**

---

### 1.4.39 FpLseek

Synopsis: Set file pointer position.

Declaration: `function FpLseek(fd: cint; offset: TOff; whence: cint) : TOff`

Visibility: default

Description: `FpLseek` sets the current fileposition of file `fd` to `Offset`, starting from `Whence`, which can be one of the following:

`Seek_SetOffset` is the absolute position in the file.

`Seek_CurOffset` is relative to the current position.

`Seek_endOffset` is relative to the end of the file.

The function returns the new fileposition, or -1 of an error occurred.

For an example, see `FpOpen` (166).

Errors: Extended error information can be retrieved using `fpGetErrno` (154).

See also: `FpOpen` (166), `FpWrite` (191), `FpClose` (145), `FpRead` (171), `FpFTruncate` (153)

### 1.4.40 fpLstat

Synopsis: Return information about symbolic link. Do not follow the link

Declaration: `function fpLstat(path: pchar; Info: PStat) : cint`  
`function fpLstat(path: Ansistring; Info: PStat) : cint`  
`function fpLstat(path: pchar; var Info: Stat) : cint`  
`function fpLstat(Filename: ansistring; var Info: Stat) : cint`

Visibility: default

Description: `fpLstat` gets information about the link specified in `Path` (or `FileName`, and stores it in `Info`, which points to a record of type `TStat`. Contrary to `FpFstat` (152), it stores information about the link, not about the file the link points to. The function returns zero if the call was succesful, a nonzero return value indicates failure. failed.

Errors: Extended error information is returned by the `FpGetErrno` (154) function.

`sys_enoentPath` does not exist.

See also: `FpFStat` (152), `#rtl.unix.StatFS` (1676)

**Listing:** `./unixex/ex29.pp`

---

```
program example29;

{ Program to demonstrate the LStat function. }

uses BaseUnix, Unix;

var f : text;
    i : byte;
    info : stat;

begin
  { Make a file }
```

---

```

assign (f, 'test.fil');
rewrite (f);
for i:=1 to 10 do writeln (f, 'Testline # ', i);
close (f);
{ Do the call on made file. }
if fpstat ('test.fil', info) <> 0 then
begin
  writeln('Fstat failed. Errno : ', fpgeterrno);
  halt (1);
end;
writeln;
writeln ('Result of stat on file ''test.fil''.');
writeln ('Inode   : ', info.st_ino);
writeln ('Mode    : ', info.st_mode);
writeln ('nlink   : ', info.st_nlink);
writeln ('uid     : ', info.st_uid);
writeln ('gid     : ', info.st_gid);
writeln ('rdev    : ', info.st_rdev);
writeln ('Size    : ', info.st_size);
writeln ('Blksize : ', info.st_blksize);
writeln ('Blocks  : ', info.st_blocks);
writeln ('atime   : ', info.st_atime);
writeln ('mtime   : ', info.st_mtime);
writeln ('ctime   : ', info.st_ctime);

If fpSymLink ('test.fil', 'test.lnk') <> 0 then
  writeln ('Link failed ! Errno : ', fpgeterrno);

if fplstat ('test.lnk', @info) <> 0 then
begin
  writeln('LStat failed. Errno : ', fpgeterrno);
  halt (1);
end;
writeln;
writeln ('Result of fstat on file ''test.lnk''.');
writeln ('Inode   : ', info.st_ino);
writeln ('Mode    : ', info.st_mode);
writeln ('nlink   : ', info.st_nlink);
writeln ('uid     : ', info.st_uid);
writeln ('gid     : ', info.st_gid);
writeln ('rdev    : ', info.st_rdev);
writeln ('Size    : ', info.st_size);
writeln ('Blksize : ', info.st_blksize);
writeln ('Blocks  : ', info.st_blocks);
writeln ('atime   : ', info.st_atime);
writeln ('mtime   : ', info.st_mtime);
writeln ('ctime   : ', info.st_ctime);
{ Remove file and link }
erase (f);
fpunlink ('test.lnk');
end.

```

---

### 1.4.41 FpMkdir

Synopsis: Create a new directory

Declaration: `function FpMkdir(path: pChar; Mode: TMode) : cint`

```
function FpMkdir(path: AnsiString;Mode: TMode) : cint
```

Visibility: default

**Description:** `FpMkDir` creates a new directory `Path`, and sets the new directory's mode to `Mode`. `Path` can be an absolute path or a relative path. Note that only the last element of the directory will be created, higher level directories must already exist, and must be writeable by the current user.

On succes, 0 is returned. if the function fails, -1 is returned.

**Note:** There exist a portable alternative to `fpMkDir`: `system.mkdir`. Please use `fpMkDir` only if you are writing Unix specific code. `System.mkdir` will work on all operating systems.

**Errors:** Extended error information can be retrieved using `fpGetErrno` ([154](#)).

See also: `fpGetCWD` ([153](#)), `fpChDir` ([142](#))

### 1.4.42 FpMkfifo

**Synopsis:** Create FIFO (named pipe) in file system

**Declaration:** `function FpMkfifo(path: pChar;Mode: TMode) : cint`  
`function FpMkfifo(path: AnsiString;Mode: TMode) : cint`

Visibility: default

**Description:** `fpMkFifo` creates named a named pipe in the filesystem, with name `Path` and mode `Mode`.

The function returns zero if the command was succesful, and nonzero if it failed.

**Errors:** The error codes include:

**sys\_enfile**Too many file descriptors for this process.

**sys\_enfile**The system file table is full.

### 1.4.43 Fpmmmap

**Synopsis:** Create memory map of a file

**Declaration:** `function Fpmmmap(start: pointer;len: size_t;prot: cint;flags: cint;`  
`fd: cint;offst: off_t) : pointer`

Visibility: default

**Description:** `FpMMap` maps or unmaps files or devices into memory. The different arguments determine what and how the file is mapped:

**adr**Address where to mmap the device. This address is a hint, and may not be followed.

**len**Size (in bytes) of area to be mapped.

**prot**Protection of mapped memory. This is a OR-ed combination of the following constants:

**PROT\_EXEC**The memory can be executed.

**PROT\_READ**The memory can be read.

**PROT\_WRITE**The memory can be written.

**PROT\_NONE**The memory can not be accessed.

**flags**Contains some options for the `mmap` call. It is an OR-ed combination of the following constants:

**MAP\_FIXED**Do not map at another address than the given address. If the address cannot be used, `MMap` will fail.

**MAP\_SHARED** Share this map with other processes that map this object.

**MAP\_PRIVATE** Create a private map with copy-on-write semantics.

**MAP\_ANONYMOUS** `fd` does not have to be a file descriptor.

One of the options `MAP_SHARED` and `MAP_PRIVATE` must be present, but not both at the same time.

**fd** File descriptor from which to map.

**off** Offset to be used in file descriptor `fd`.

The function returns a pointer to the mapped memory, or a -1 in case of an error.

**Errors:** On error, -1 is returned and extended error information is returned by the `FpGetErrno` (154) function.

**Sys\_EBADF** `fd` is not a valid file descriptor and `MAP_ANONYMOUS` was not specified.

**Sys\_EACCES** `MAP_PRIVATE` was specified, but `fd` is not open for reading. Or `MAP_SHARED` was asked and `PROT_WRITE` is set, `fd` is not open for writing

**Sys\_EINVAL** One of the record fields `Start`, `length` or `offset` is invalid.

**Sys\_ETXTBUSY** `MAP_DENYWRITE` was set but the object specified by `fd` is open for writing.

**Sys\_EAGAIN** `fd` is locked, or too much memory is locked.

**Sys\_ENOMEM** Not enough memory for this operation.

See also: `FpMUnMap` (165)

**Listing:** `./unixex/ex66.pp`

---

**Program** Example66;

*{ Program to demonstrate the MMap function. }*

**Uses** BaseUnix, Unix;

**Var** S : String;  
       fd : cint;  
       Len : longint;  
       // args : tmmmapargs;  
       P : PChar;

**begin**  
   s:= 'This is the string';  
   Len:=Length(S);  
   fd:=fpOpen('testfile.txt',O\_wrOnly or o\_creat);  
   **if** fd=-1 **then**  
     Halt(1);  
   **if** fpWrite(fd,S[1],Len)=-1 **then**  
     Halt(2);  
   fpClose(fd);  
   fd:=fpOpen('testfile.txt',O\_rdOnly);  
   **if** fd=-1 **then**  
     Halt(3);  
   P:=Pchar(fpmmap(nil, len+1 ,PROT\_READ or PROT\_WRITE,MAP\_PRIVATE, fd ,0));  
  
   **if** longint(P)=-1 **then**  
     Halt(4);  
   Writeln('Read in memory :',P);  
   fpclose(fd);  
   **if** fpMUnMap(P, Len)<>0 **Then**

```

    Halt(fpgeterrno);
end.

```

---

#### 1.4.44 Fpmunmap

Synopsis: Unmap previously mapped memory block

Declaration: `function Fpmunmap(start: pointer; len: size_t) : cint`

Visibility: default

Description: `FpMUnMap` unmaps the memory block of size `Len`, pointed to by `Adr`, which was previously allocated with `FpMMap` (163).

The function returns `True` if successful, `False` otherwise.

For an example, see `FpMMap` (163).

Errors: In case of error the function returns a nonzero value, extended error information is returned by the `FpGetErrno` (154) function. See `FpMMap` (163) for possible error values.

See also: `FpMMap` (163)

#### 1.4.45 FpNanoSleep

Synopsis: Suspend process for a short time

Declaration: `function FpNanoSleep(req: timespec; rem: timespec) : cint`

Visibility: default

Description: `FpNanoSleep` suspends the process till a time period as specified in `req` has passed. Then the function returns. If the call was interrupted (e.g. by some signal) then the function may return earlier, and `rem` will contain the remaining time till the end of the intended period. In this case the return value will be -1, and `fpErrNo` will be set to `EINTR`

If the function returns without error, the return value is zero.

Errors: If an error occurred or the call was interrupted, -1 is returned. Extended error information can be retrieved using `fpGetErrno` (154).

See also: `FpPause` (169), `FpAlarm` (141)

**Listing:** `./bunixex/ex72.pp`

---

**program** example72;

*{ Program to demonstrate the NanoSleep function. }*

**uses** BaseUnix;

**Var**

Req, Rem : TimeSpec;  
Res : Longint;

**begin**

**With** Req **do**

**begin**

tv\_sec := 10;

---

```

    tv_nsec:=100;
  end;
  Write( 'NanoSleep returned : ');
  Flush( Output);
  Res:=(fpNanoSleep (@Req,@rem));
  WriteLn( res );
  If ( res < > 0) then
    With rem do
      begin
        WriteLn( 'Remaining seconds      : ',tv_sec );
        WriteLn( 'Remaining nanoseconds : ',tv_nsec );
      end;
    end;
  end.

```

---

#### 1.4.46 fpNice

Synopsis: Set process priority

Declaration: function fpNice(N: cint) : cint

Visibility: default

Description: Nice adds -N to the priority of the running process. The lower the priority numerically, the less the process is favored. Only the superuser can specify a negative N, i.e. increase the rate at which the process is run.

If the function is succesful, zero is returned. On error, a nonzero value is returned.

Errors: Extended error information is returned by the FpGetErrno ([154](#)) function.

**sys\_eperm**A non-superuser tried to specify a negative N, i.e. do a priority increase.

See also: FpGetPriority ([157](#)), FpSetPriority ([177](#))

**Listing:** ./unixex/ex15.pp

---

**Program** Example15;

*{ Program to demonstrate the Nice and Get/SetPriority functions. }*

**Uses** BaseUnix, Unix;

**begin**

```

  writeln ( 'Setting priority to 5 ');
  fpsetpriority (prio_process,fpgetpid,5);
  writeln ( 'New priority = ',fpgetpriority (prio_process,fpgetpid));
  writeln ( 'Doing nice 10 ');
  fpnice (10);
  writeln ( 'New Priority = ',fpgetpriority (prio_process,fpgetpid));
end.

```

---

#### 1.4.47 FpOpen

Synopsis: Open file and return file descriptor

**Declaration:** function FpOpen(path: pChar; flags: cint; Mode: TMode) : cint  
 function FpOpen(path: pChar; flags: cint) : cint  
 function FpOpen(path: AnsiString; flags: cint) : cint  
 function FpOpen(path: AnsiString; flags: cint; Mode: TMode) : cint  
 function FpOpen(path: String; flags: cint) : cint  
 function FpOpen(path: String; flags: cint; Mode: TMode) : cint

**Visibility:** default

**Description:** FpOpen opens a file in Path with flags flags and mode Mode One of the following:

**O\_RdOnlyFile** is opened Read-only

**O\_WrOnlyFile** is opened Write-only

**O\_RdWrFile** is opened Read-Write

The flags may beOR-ed with one of the following constants:

**O\_CreatFile** is created if it doesn't exist.

**O\_ExclIf** the file is opened with O\_Creat and it already exists, the call will fail.

**O\_NoCttyIf** the file is a terminal device, it will NOT become the process' controlling terminal.

**O\_TruncIf** the file exists, it will be truncated.

**O\_Append** the file is opened in append mode. *Before each write*, the file pointer is positioned at the end of the file.

**O\_NonBlock** The file is opened in non-blocking mode. No operation on the file descriptor will cause the calling process to wait till.

**O\_NDelayIdem** as O\_NonBlock

**O\_Sync** The file is opened for synchronous IO. Any write operation on the file will not return until the data is physically written to disk.

**O\_NoFollow** if the file is a symbolic link, the open fails. (linux 2.1.126 and higher only)

**O\_Directory** if the file is not a directory, the open fails. (linux 2.1.126 and higher only)

Path can be of type PChar or String. The optional mode argument specifies the permissions to set when opening the file. This is modified by the umask setting. The real permissions are Mode and not umask. The return value of the function is the filedescriptor, or a negative value if there was an error.

**Errors:** Extended error information can be retrieved using fpGetErrno ([154](#)).

See also: FpClose ([145](#)), FpRead ([171](#)), FpWrite ([191](#)), FpFTruncate ([153](#)), FpLSeek ([160](#))

**Listing:** ./bunixex/ex19.pp

---

**Program** Example19;

*{ Program to demonstrate the fdOpen, fdwrite and fdCLose functions. }*

**Uses** BaseUnix;

**Const** Line : **String**[80] = 'This is easy writing !';

**Var** FD : Cint;

**begin**

FD:=fpOpen ( 'Test.dat', O\_WrOnly or O\_Creat );



---

```

if FD>0 then
  begin
    if length(Line)<>fpwrite (FD,Line[1],Length(Line)) then
      Writeln ('Error when writing to file !');
    fpClose(FD);
  end;
end.

```

---

### 1.4.48 FpOpendir

Synopsis: Open a directory for reading

Declaration: function FpOpendir(dirname: pChar) : pDir  
 function FpOpendir(dirname: AnsiString) : pDir  
 function FpOpendir(dirname: shortString) : pDir

Visibility: default

Description: FpOpenDir opens the directory DirName, and returns a pdir pointer to a Dir (126) record, which can be used to read the directory structure. If the directory cannot be opened, nil is returned.

Errors: Extended error information can be retrieved using fpGetErrno (154).

See also: FpCloseDir (145), FpReadDir (172)

**Listing:** ./bunixex/ex35.pp

---

**Program** Example35;

```

{ Program to demonstrate the
  OpenDir, ReadDir, SeekDir and TelDir functions. }

```

**Uses** BaseUnix;

```

Var TheDir : PDir;
      ADirent : PDirent;
      Entry : Longint;

```

```

begin
  TheDir:=fpOpenDir( './. ' );
  Repeat
    // Entry:=fpTelDir(TheDir);
    ADirent:=fpReadDir ( TheDir^ );
    If ADirent<>Nil then
      With ADirent^ do
        begin
          Writeln ( 'Entry No : ',Entry );
          Writeln ( 'Inode      : ',d_fileno );
          // Writeln ( 'Offset      : ',d_off );
          Writeln ( 'Reclen     : ',d_reclen );
          Writeln ( 'Name       : ',pchar(@d_name[0]));
        end;
      Until ADirent=Nil;
    Repeat
      Write ( 'Entry No. you would like to see again (-1 to stop): ');
      ReadLn ( Entry );
      If Entry<>-1 then
        begin

```

---

```

//      fpSeekDir ( TheDir, Entry );                                // not implemented for various platforms
ADirent:=fpReadDir ( TheDir^);
If ADirent<>Nil then
  With ADirent^ do
    begin
      Writeln ( 'Entry No : ', Entry );
      Writeln ( 'Inode   : ', d_fileno );
//      Writeln ( 'Offset  : ', off );
      Writeln ( 'Reclen  : ', d_reclen );
      Writeln ( 'Name    : ', pchar(@d_name[0]));
    end;
  end;
Until Entry=-1;
fpCloseDir ( TheDir^);
end.

```

---

### 1.4.49 FpPause

Synopsis: Wait for a signal to arrive

Declaration: `function FpPause : cint`

Visibility: default

Description: `FpPause` puts the process to sleep and waits until the application receives a signal. If a signal handler is installed for the received signal, the handler will be called and after that pause will return control to the process.

For an example, see `fpAlarm` (141).

### 1.4.50 FpPipe

Synopsis: Create a set of pipe file handlers

Declaration: `function FpPipe(var fildes: TFileDes) : cint`

Visibility: default

Description: `FpPipe` creates a pipe, i.e. two file objects, one for input, one for output. The filehandles are returned in the array `fildes`. The input handle is in the 0-th element of the array, the output handle is in the 1-st element.

The function returns zero if everything went successfully, a nonzero return value indicates an error.

Errors: In case the function fails, the following return values are possible:

**sys\_emfile** Too many file descriptors for this process.

**sys\_emfile** The system file table is full.

See also: `#rtl.unix.POpen` (1672), `fpMkFifo` (163)

**Listing:** `./bunixex/ex36.pp`

---

**Program** Example36;

*{ Program to demonstrate the AssignPipe function. }*

**Uses** BaseUnix, Unix;

```

Var pipi ,pipo : Text;
      s : String;

begin
  Writeln ( 'Assigning Pipes.' );
  If assignpipe(pipi ,pipo)<>0 then
    Writeln( 'Error assigning pipes !',fpgeterrno);
  Writeln ( 'Writing to pipe, and flushing.' );
  Writeln (pipo,'This is a textstring');close(pipo);
  Writeln ( 'Reading from pipe.' );
  While not eof(pipi) do
    begin
      Readln ( pipi ,s);
      Writeln ( 'Read from pipe : ',s);
    end;
  close ( pipi );
  writeln ( 'Closed pipes.' );
  writeln
end.

```

---

### 1.4.51 FpPoll

Synopsis: Poll a file descriptor for events.

Declaration: `function FpPoll(fds: ppollfd;nfds: cuint;timeout: clong) : cint`

Visibility: default

Description: `fpPoll` waits for events on file descriptors. `fds` points to an array of `tpollfd` records, each of these records describes a file descriptor on which to wait for events. The number of file descriptors is given by `nfds`. `>timeout` specifies the maximum time (in milliseconds) to wait for events.

On timeout, the result value is 0. If an event occurred on some descriptors, then the return value is the number of descriptors on which an event (or error) occurred. The `revents` field of the `tpollfd` records will contain the events for the file descriptor it described.

See also: `tpollfd` ([137](#))

### 1.4.52 FpPRead

Synopsis: Positional read: read from file descriptor at a certain position.

Declaration: `function FpPRead(fd: cint;buf: pChar;nbytes: TSize;offset: TOff) : TsSize`  
`function FpPRead(fd: cint;var buf;nbytes: TSize;offset: TOff) : TsSize`

Visibility: default

Description: `FpPRead` reads `nbytes` bytes from file descriptor `fd` into buffer `buf` starting at offset `offset`. Offset is measured from the start of the file. This function can only be used on files, not on pipes or sockets (i.e. any seekable file descriptor).

The function returns the number of bytes actually read, or -1 on error.

Errors: On error, -1 is returned.

See also: `FpReadV` ([173](#)), `FpPWrite` ([170](#))

### 1.4.53 FppWrite

Synopsis: Positional write: write to file descriptor at a certain position.

Declaration: `function FppWrite(fd: cint;buf: pChar;nbytes: TSize;offset: TOff) : TsSize`  
`function FppWrite(fd: cint;const buf;nbytes: TSize;offset: TOff) : TsSize`

Visibility: default

Description: `FppWrite` writes `nbytes` bytes from buffer `buf` into file descriptor `fd` starting at offset `offset`. Offset is measured from the start of the file. This function can only be used on files, not on pipes or sockets (i.e. any seekable file descriptor).

The function returns the number of bytes actually written, or -1 on error.

Errors: On error, -1 is returned.

See also: `FpPRead` (170), `FpWriteV` (192)

### 1.4.54 FpRead

Synopsis: Read data from file descriptor

Declaration: `function FpRead(fd: cint;buf: pChar;nbytes: TSize) : TsSize`  
`function FpRead(fd: cint;var buf;nbytes: TSize) : TsSize`

Visibility: default

Description: `FpdRead` reads at most `nbytes` bytes from the file descriptor `fd`, and stores them in `buf`.

The function returns the number of bytes actually read, or -1 if an error occurred. No checking on the length of `buf` is done.

Errors: Extended error information can be retrieved using `fpGetErrno` (154).

See also: `FpOpen` (166), `FpClose` (145), `FpWrite` (191), `FpFTruncate` (153), `FpLSeek` (160)

**Listing:** `./bunixex/ex20.pp`

---

**Program** `Example20`;

*{ Program to demonstrate the fdRead and fdTruncate functions. }*

**Uses** `BaseUnix`;

**Const** `Data : string[10] = '1234567890'`;

**Var** `FD : cint`;  
`l : longint`;

**begin**

`FD:=fpOpen('test.dat',o_wronly or o_creat,&666);`

`if fd>0 then`

`begin`

`{ Fill file with data }`

`for l:=1 to 10 do`

`if fpWrite (FD,Data[l],10)<>10 then`

`begin`

`writeln ('Error when writing !');`

---

```

        halt(1);
    end;
    fpClose(FD);
    FD:=fpOpen('test.dat',o_rdonly);
    { Read data again }
    If FD>0 then
    begin
        For l:=1 to 5 do
            if fpRead (FD,Data[1],10)<>10 then
            begin
                WriteLn ('Error when Reading !');
                Halt(2);
            end;
            fpClose(FD);
            { Truncating file at 60 bytes }
            { For truncating , file must be open or write }
            FD:=fpOpen('test.dat',o_wronly,&666);
            if FD>0 then
            begin
                if fpfTruncate(FD,60)<>0 then
                    WriteLn('Error when truncating !');
                fpClose (FD);
            end;
        end;
    end;
end.

```

---

### 1.4.55 FpReaddir

Synopsis: Read entry from directory

Declaration: `function FpReaddir(var dirp: Dir) : pDirent`

Visibility: default

Description: `FpReadDir` reads the next entry in the directory pointed to by `dirp`. It returns a `pdirent` pointer to a `dirent` (127) record describing the entry. If the next entry can't be read, `Nil` is returned.

For an example, see `FpOpenDir` (168).

Errors: Extended error information can be retrieved using `fpGetErrno` (154).

See also: `FpCloseDir` (145), `FpOpenDir` (168)

### 1.4.56 fpReadLink

Synopsis: Read destination of symbolic link

Declaration: `function fpReadLink(name: pchar;linkname: pchar;maxlen: size_t) : cint`  
`function fpReadLink(Name: ansistring) : ansistring`

Visibility: default

Description: `FpReadLink` returns the file the symbolic link name is pointing to. The first form of this function accepts a buffer `linkname` of length `maxlen` where the filename will be stored. It returns the actual number of characters stored in the buffer.

The second form of the function returns simply the name of the file.

**Errors:** On error, the first form of the function returns -1; the second one returns an empty string. Extended error information is returned by the `FpGetErrno` (154) function.

**SYS\_ENOTDIR**A part of the path in `Name` is not a directory.

**SYS\_EINVAL**`maxlen` is not positive, or the file is not a symbolic link.

**SYS\_ENAMETOOLONG**A pathname, or a component of a pathname, was too long.

**SYS\_ENOENT**the link `name` does not exist.

**SYS\_EACCES**No permission to search a directory in the path

**SYS\_ELOOP**Too many symbolic links were encountered in translating the pathname.

**SYS\_EIO**An I/O error occurred while reading from the file system.

**SYS\_EFAULT**The buffer is not part of the process's memory space.

**SYS\_ENOMEM**Not enough kernel memory was available.

See also: `FpSymLink` (184)

**Listing:** `./unixex/ex62.pp`

---

**Program** `Example62`;

*{ Program to demonstrate the ReadLink function. }*

**Uses** `BaseUnix, Unix`;

**Var** `F : Text;`  
       `S : String;`

```
begin
  Assign (F, 'test.txt');
  Rewrite (F);
  Writeln (F, 'This is written to test.txt');
  Close(f);
  { new.txt and test.txt are now the same file }
  if fpSymLink ('test.txt', 'new.txt') <> 0 then
    writeln ('Error when symlinking !');
  S:=fpReadLink('new.txt');
  if S='' then
    Writeln ('Error reading link !')
  Else
    Writeln ('Link points to : ',S);
  { Now remove links }
  if fpUnlink ('new.txt') <> 0 then
    Writeln ('Error when unlinking !');
  if fpUnlink ('test.txt') <> 0 then
    Writeln ('Error when unlinking !');
end.
```

---

### 1.4.57 FpReadV

**Synopsis:** Vector read: Read into multiple buffers

**Declaration:** `function FpReadV(fd: cint; const iov: piovec; iovcnt: cint) : TsSize`

**Visibility:** default

**Description:** `FpReadV` reads data from file descriptor `fd` and writes it into `iovcnt` buffers described by the `tiovec` (137) buffers pointed to by `iov`. It works like `fpRead` (171) only on multiple buffers.

**Errors:** On error, -1 is returned.

See also: `FpWriteV` (192), `FpPWrite` (170), `FpPRead` (170)

## 1.4.58 FpRename

**Synopsis:** Rename file

**Declaration:** `function FpRename(old: pChar; newpath: pChar) : cint`  
`function FpRename(old: AnsiString; newpath: AnsiString) : cint`

**Visibility:** default

**Description:** `FpRename` renames the file `Old` to `NewPath`. `NewPath` can be in a different directory than `Old`, but it cannot be on another partition (device). Any existing file on the new location will be replaced.

If the operation fails, then the `Old` file will be preserved.

The function returns zero on succes, a nonzero value indicates failure.

**Note:** There exist a portable alternative to `fpRename`: `system.rename`. Please use `fpRename` only if you are writing Unix specific code. `System.rename` will work on all operating systems.

**Errors:** Extended error information can be retrieved using `fpGetErrno` (154).

**sys\_eisdir** `NewPath` exists and is a directory, but `Old` is not a directory.

**sys\_exdev** `NewPath` and `Old` are on different devices.

**sys\_enotempty or sys\_eexist** `NewPath` is an existing, non-empty directory.

**sys\_ebusy** `Old` or `NewPath` is a directory and is in use by another process.

**sys\_einval** `NewPath` is part of `Old`.

**sys\_emlink** `OldPath` or `NewPath` already have the maximum amount of links pointing to them.

**sys\_enotdir** part of `Old` or `NewPath` is not directory.

**sys\_efault** For the `pchar` case: One of the pointers points to an invalid address.

**sys\_eaccess** access is denied when attempting to move the file.

**sys\_enametoolong** Either `Old` or `NewPath` is too long.

**sys\_enoenta** directory component in `Old` or `NewPath` didn't exist.

**sys\_enomem** not enough kernel memory.

**sys\_erofs** `NewPath` or `Old` is on a read-only file system.

**sys\_eloop** too many symbolic links were encountered trying to expand `Old` or `NewPath`

**sys\_enosp** the filesystem has no room for the new directory entry.

See also: `FpUnLink` (189)

### 1.4.59 FpRmdir

**Synopsis:** Remove a directory.

**Declaration:** `function FpRmdir(path: pChar) : cint`  
`function FpRmdir(path: AnsiString) : cint`

**Visibility:** default

**Description:** `FpRmdir` removes the directory `Path` from the system. The directory must be empty for this call to succeed, and the user must have the necessary permissions in the parent directory. Only the last component of the directory is removed, i.e. higher-lying directories are not removed.

On success, zero is returned. A nonzero return value indicates failure.

**Note:** There exist a portable alternative to `fpRmdir`: `system.rmdir`. Please use `fpRmdir` only if you are writing Unix specific code. `System.rmdir` will work on all operating systems.

**Errors:** Extended error information can be retrieved using `fpGetErrno` (154).

### 1.4.60 fpSelect

**Synopsis:** Wait for events on file descriptors

**Declaration:** `function FPSelect(N: cint; readfds: pFDSet; writefds: pFDSet;`  
`exceptfds: pFDSet; Timeout: ptimeval) : cint`  
`function fpSelect(N: cint; readfds: pFDSet; writefds: pFDSet;`  
`exceptfds: pFDSet; Timeout: cint) : cint`  
`function fpSelect(var T: Text; Timeout: ptimeval) : cint`  
`function fpSelect(var T: Text; Timeout: time_t) : cint`

**Visibility:** default

**Description:** `FpSelect` checks one of the file descriptors in the `FDSet`s to see if the following I/O operation on the file descriptors will block.

`readfds`, `writefds` and `exceptfds` are pointers to arrays of 256 bits. If you want a file descriptor to be checked, you set the corresponding element in the array to 1. The other elements in the array must be set to zero. Three arrays are passed : The entries in `readfds` are checked to see if the following read operation will block. The entries in `writefds` are checked to see if the following write operation will block, while entries in `exceptfds` are checked to see if an exception occurred on them.

You can use the functions `fpFD_ZERO` (151), `fpFD_Clr` (150), `fpFD_Set` (151) or `fpFD_IsSet` (151) to manipulate the individual elements of a set.

The pointers can be `Nil`.

`N` is the value of the largest file descriptor in one of the sets, + 1. In other words, it is the position of the last bit which is set in the array of bits.

`Timeout` can be used to set a time limit. If `Timeout` can be two types :

1. `Timeout` is of type `ptimeval` and contains a zero time, the call returns immediately. If `Timeout` is `Nil`, the kernel will wait forever, or until a status changed.
2. `Timeout` is of type `cint`. If it is -1, this has the same effect as a `Timeout` of type `PTime` which is `Nil`. Otherwise, `Timeout` contains a time in milliseconds.

When the `Timeout` is reached, or one of the file descriptors has changed, the `Select` call returns. On return, it will have modified the entries in the array which have actually changed, and it returns



the number of entries that have been changed. If the timeout was reached, and no descriptor changed, zero is returned; The arrays of indexes are undefined after that. On error, -1 is returned.

The variant with the text file will execute the `FpSelect` call on the file descriptor associated with the text file `T`

**Errors:** On error, the function returns -1. Extended error information can be retrieved using `fpGetErrno` (154).

**SYS\_EBADF**An invalid descriptor was specified in one of the sets.

**SYS\_EINTR**A non blocked signal was caught.

**SYS\_EINVAL**N is negative or too big.

**SYS\_ENOMEM**`Select` was unable to allocate memory for its internal tables.

See also: `fpFD_ZERO` (151), `fpFD_Clr` (150), `fpFD_Set` (151), `fpFD_IsSet` (151)

**Listing:** `./bunixex/ex33.pp`

**Program** `Example33`;

*{ Program to demonstrate the Select function . }*

**Uses** `BaseUnix`;

**Var** `FDS : Tfdset`;

**begin**

`fpfd_zero(FDS);`

`fpfd_set(0,FDS);`

**Writeln** ( 'Press the <ENTER> to continue the program.' );

*{ Wait until File descriptor 0 (=Input) changes }*

`fpSelect (1,@FDS,nil , nil , nil );`

*{ Get rid of <ENTER> in buffer }*

**readln**;

**Writeln** ( 'Press <ENTER> key in less than 2 seconds...' );

`Fpfd_zero(FDS);`

`FpFd_set (0 ,FDS);`

**if** `fpSelect (1,@FDS,nil , nil ,2000)>0` **then**

**Writeln** ( 'Thank you !' )

*{ FD\_ISSET(0,FDS) would be true here. }*

**else**

**Writeln** ( 'Too late !' );

**end.**

### 1.4.61 fpseterrno

**Synopsis:** Set extended error information.

**Declaration:** `procedure fpseterrno(err: LongInt)`

**Visibility:** default

**Description:** `fpseterrno` sets the extended information on the latest error. It is called by all functions that communicate with the kernel or C library.

Unless a direct kernel call is performed, there should never be any need to call this function.

**Errors:**

See also: `fpgeterrno` (154)

### 1.4.62 FpSetgid

Synopsis: Set the current group ID

Declaration: `function FpSetgid(gid: TGid) : cint`

Visibility: default

Description: `fpSetUID` sets the group ID of the current process. This call will only work if it is executed as root, or the program is `setgid` root.

On success, zero is returned, on error -1 is returned.

Errors: Extended error information can be retrieved with `fpGetErrNo` (154).

See also: `FpSetUid` (178), `FpGetGid` (155), `FpGetUid` (158), `FpGetEUid` (155), `FpGetEGid` (153), `FpGetPid` (156), `FpGetPPid` (157)

### 1.4.63 fpSetPriority

Synopsis: Set process priority

Declaration: `function fpSetPriority(Which: cint;Who: cint;What: cint) : cint`

Visibility: default

Description: `fpSetPriority` sets the priority with which a process is running. Which process(es) is determined by the `Which` and `Who` variables. Which can be one of the pre-defined constants:

**Prio\_Process**`Who` is interpreted as process ID

**Prio\_PGrp**`Who` is interpreted as process group ID

**Prio\_User**`Who` is interpreted as user ID

`Prio` is a value in the range -20 to 20.

For an example, see `FpNice` (166).

The function returns zero on success, -1 on failure

Errors: Extended error information is returned by the `FpGetErrno` (154) function.

**sys\_esrch**No process found using `which` and `who`.

**sys\_einval**`Which` was not one of `Prio_Process`, `Prio_Grp` or `Prio_User`.

**sys\_eperm**A process was found, but neither its effective or real user ID match the effective user ID of the caller.

**sys\_eaccess**A non-superuser tried to a priority increase.

See also: `FpGetPriority` (157), `FpNice` (166)

### 1.4.64 FpSetRLimit

Synopsis: Set process resource limits

Declaration: `function FpSetRLimit(Resource: cint;rlim: PRLimit) : cint`

Visibility: default

**Description:** `FpGetRLimit` sets the resource limits for the current process: `resource` determines the resource of which the kernel should set the limits (one of the many `RLIMIT_*` constants). `rlim` should point to a `TRLimit` (1679) record which contains the new limits for the resource indicated in `resource`.

The function returns zero if the resource limits were successfully set.

**Errors:** On error, -1 is returned and `fpgeterrno` (154) can be used to retrieve the error code.

See also: `FpGetRLimit` (157)

### 1.4.65 FpSetsid

**Synopsis:** Create a new session.

**Declaration:** `function FpSetsid : TPid`

**Visibility:** default

**Description:** `FpSetsid` creates a new session (process group). It returns the new process group id (as returned by `FpGetpgrp` (156)). This call will fail if the current process is already the process group leader.

**Errors:** On error, -1 is returned. Extended error information can be retrieved with `fpGetErrNo` (154)

### 1.4.66 fpsettimeofday

**Synopsis:** Set kernel time

**Declaration:** `function fpsettimeofday(tp: ptimeval;tzp: ptimezone) : cint`

**Visibility:** default

**Description:** `FpSetTimeOfDay` sets the kernel time to the number of seconds since 00:00, January 1 1970, GMT specified in the `tp` record. This time NOT corrected any way, not taking into account time-zones, daylight savings time and so on.

It is simply a wrapper to the kernel system call.

See also: `#rtl.unix.FPGetTimeOfDay` (1667)

### 1.4.67 FpSetuid

**Synopsis:** Set the current user ID

**Declaration:** `function FpSetuid(uid: TUid) : cint`

**Visibility:** default

**Description:** `fpSetUID` sets the user ID of the current process. This call will only work if it is executed as root, or the program is setuid root.

On success, zero is returned, on error -1 is returned.

**Errors:** Extended error information can be retrieved with `fpGetErrNo` (154).

See also: `FpGetGid` (155), `FpGetUid` (158), `FpGetEuid` (155), `FpGetEGid` (153), `FpGetPid` (156), `FpGetPPid` (157), `FpSetGid` (176)

### 1.4.68 FPSigaction

Synopsis: Install signal handler

Declaration: `function FPSigaction(sig: cint;act: psigactionrec;oact: psigactionrec)  
: cint`

Visibility: default

Description: `FPSigaction` changes the action to take upon receipt of a signal. `Act` and `Oact` are pointers to a `SigActionRec` (134) record. `Sig` specifies the signal, and can be any signal except **SIGKILL** or **SIGSTOP**.

If `Act` is non-nil, then the new action for signal `Sig` is taken from it. If `Oact` is non-nil, the old action is stored there. `Sa_Handler` may be `SIG_DFL` for the default action or `SIG_IGN` to ignore the signal. `Sa_Mask` Specifies which signals should be ignored during the execution of the signal handler. `Sa_Flags` Specifies a series of flags which modify the behaviour of the signal handler. You can 'or' none or more of the following :

**SA\_NOCLDSTOP**If `sig` is **SIGCHLD** do not receive notification when child processes stop.

**SA\_ONESHOT** or **SA\_RESETHAND**Restore the signal action to the default state once the signal handler has been called.

**SA\_RESTART**For compatibility with BSD signals.

**SA\_NOMASK** or **SA\_NODEFER**Do not prevent the signal from being received from within its own signal handler.

Errors: Extended error information can be retrieved using `fpGetErrno` (154).

**sys\_einval**an invalid signal was specified, or it was **SIGKILL** or **SIGSTOP**.

**sys\_efault**`Act`, `OldAct` point outside this process address space

**sys\_eintr**System call was interrupted.

See also: `FpSigProcMask` (182), `FpSigPending` (181), `FpSigSuspend` (182), `FpKill` (159)

**Listing:** `./bunixex/ex57.pp`

**Program** `example57;`

```
{ Program to demonstrate the SigAction function.}

{
do a kill -USR1 pid from another terminal to see what happens.
replace pid with the real pid of this program.
You can get this pid by running 'ps'.
}
```

**uses** `BaseUnix;`

**Var**

`oa, na : PSigActionRec;`

**Procedure** `DoSig(sig : cint); cdecl;`

**begin**

`writeln('Receiving signal: ',sig);`

**end;**

---

```

begin
  new(na);
  new(oa);
  na^.sa_Handler:= SigActionHandler(@DoSig);
  fillchar(na^.Sa_Mask, sizeof(na^.sa_mask), #0);
  na^.Sa_Flags:=0;
  {$ifdef Linux}           // Linux specific
    na^.Sa_Restorer:= Nil;
  {$endif}
  if fpSigAction(SigUsr1, na, oa) <> 0 then
    begin
      writeln('Error: ', fpgeterrno, '.');
      halt(1);
    end;
  Writeln('Send USR1 signal or press <ENTER> to exit');
  readln;
end.

```

---

### 1.4.69 FpSigAddSet

Synopsis: Set a signal in a signal set.

Declaration: `function FpSigAddSet(var nset: tsigset; signo: cint) : cint`

Visibility: default

Description: `FpSigAddSet` adds signal `Signo` to the signal set `nset`. The function returns 0 on success.

Errors: If an invalid signal number is given, -1 is returned.

See also: `FpSigEmptySet` (180), `FpSigFillSet` (180), `FpSigDelSet` (180), `FpSigIsMember` (180)

### 1.4.70 FpSigDelSet

Synopsis: Remove a signal from a signal set.

Declaration: `function FpSigDelSet(var nset: tsigset; signo: cint) : cint`

Visibility: default

Description: `FpSigDelSet` removes signal `Signo` to the signal set `nset`. The function returns 0 on success.

Errors: If an invalid signal number is given, -1 is returned.

See also: `FpSigEmptySet` (180), `FpSigFillSet` (180), `FpSigAddSet` (179), `FpSigIsMember` (180)

### 1.4.71 FpsigEmptySet

Synopsis: Clear all signals from signal set.

Declaration: `function FpsigEmptySet(var nset: tsigset) : cint`

Visibility: default

Description: `FpSigEmptySet` clears all signals from the signal set `nset`.

Errors: None. This function always returns zero.

See also: `FpSigFillSet` (180), `FpSigAddSet` (179), `FpSigDelSet` (180), `FpSigIsMember` (180)

### 1.4.72 FpSigFillSet

Synopsis: Set all signals in signal set.

Declaration: `function FpSigFillSet (var nset: tsigset) : cint`

Visibility: default

Description: `FpSigFillSet` sets all signals in the signal set `nset`.

Errors: None. This function always returns zero.

See also: `FpSigEmptySet` (180), `FpSigAddSet` (179), `FpSigDelSet` (180), `FpSigIsMember` (180)

### 1.4.73 FpSigIsMember

Synopsis: Check whether a signal appears in a signal set.

Declaration: `function FpSigIsMember (const nset: tsigset; signo: cint) : cint`

Visibility: default

Description: `FpSigIsMember` checks whether `SigNo` appears in the set `nset`. If it is a member, then 1 is returned. If not, zero is returned.

Errors: If an invalid signal number is given, -1 is returned.

See also: `FpSigEmptySet` (180), `FpSigFillSet` (180), `FpSigAddSet` (179), `FpSigDelSet` (180)

### 1.4.74 FpSignal

Synopsis: Install signal handler (deprecated)

Declaration: `function FpSignal (signum: LongInt; Handler: signalhandler)  
: signalhandler`

Visibility: default

Description: `FpSignal` installs a new signal handler (specified by `Handler`) for signal `SigNum`.

This call has a subset of the functionality provided by the `FpSigAction` (178) call. The return value for `FpSignal` is the old signal handler, or nil on error.

Errors: Extended error information can be retrieved using `fpGetErrno` (154).

**SIG\_ERR** An error occurred.

See also: `FpSigAction` (178), `FpKill` (159)

**Listing:** `./bunixex/ex58.pp`

---

**Program** `example58;`

```
{ Program to demonstrate the Signal function. }

{
do a kill -USR1 pid from another terminal to see what happens.
replace pid with the real pid of this program.
You can get this pid by running 'ps'.
}
```

```

uses BaseUnix;

Procedure DoSig(sig : cint);cdecl;

begin
    writeln( 'Receiving signal: ',sig);
end;

begin
    if fpSignal( SigUsrc1 , SignalHandler (@DoSig))= signalhandler (SIG_ERR) then
        begin
            writeln( 'Error: ',fpGetErrno , '. ');
            halt(1);
        end;
        Writeln ( 'Send USR1 signal or press <ENTER> to exit ');
        readln;
end.

```

---

### 1.4.75 FpSigPending

Synopsis: Return set of currently pending signals

Declaration: `function FpSigPending(var nset: tsigset) : cint`

Visibility: default

Description: `fpSigpending` allows the examination of pending signals (which have been raised while blocked.)  
The signal mask of pending signals is returned.

Errors: None

See also: `fpSigAction` (178), `fpSigProcMask` (182), `fpSigSuspend` (182), `fpSignal` (181), `fpKill` (159)

### 1.4.76 FpSigProcMask

Synopsis: Set list of blocked signals

Declaration: `function FpSigProcMask(how: cint;nset: psigset;oset: psigset) : cint`  
`function FpSigProcMask(how: cint;const nset: tsigset;var oset: tsigset)`  
`: cint`

Visibility: default

Description: Changes the list of currently blocked signals. The behaviour of the call depends on `How` :

**SIG\_BLOCK**The set of blocked signals is the union of the current set and the `nset` argument.

**SIG\_UNBLOCK**The signals in `nset` are removed from the set of currently blocked signals.

**SIG\_SETMASK**The list of blocked signals is set so `nset`.

If `oset` is non-nil, then the old set is stored in it.

Errors: `Errno` is used to report errors.

**sys\_efault**`oset` or `nset` point to an adress outside the range of the process.

**sys\_eintr**System call was interrupted.

See also: `fpSigAction` (178), `fpSigPending` (181), `fpSigSuspend` (182), `fpKill` (159)

### 1.4.77 FpSigSuspend

Synopsis: Set signal mask and suspend process till signal is received

Declaration: `function FpSigSuspend(const sigmask: tsigset) : cint`

Visibility: default

Description: `fpSigSuspend` temporarily replaces the signal mask for the process with the one given in `SigMask`, and then suspends the process until a signal is received.

Errors: None

See also: `fpSigAction` (178), `fpSigProcMask` (182), `fpSigPending` (181), `fpSignal` (181), `fpKill` (159)

### 1.4.78 FpSleep

Synopsis: Suspend process for several seconds

Declaration: `function FpSleep(seconds: cuint) : cuint`

Visibility: default

Description: `FpSleep` suspends the process till a time period as specified in `seconds` has passed, then the function returns. If the call was interrupted (e.g. by some signal) then the function may return earlier, and the return value is the remaining time till the end of the intended period.

If the function returns without error, the return value is zero.

See also: `fpPause` (169), `fpAlarm` (141), `fpNanoSleep` (165)

**Listing:** `./bunixex/ex73.pp`

---

```

program example73;

  { Program to demonstrate the FpSleep function. }

uses BaseUnix;

Var
  Res : Longint;

begin
  Write( 'Sleep returned : ');
  Flush( Output );
  Res:=(fpSleep(10));
  Writeln( res );
  If (res<>0) then
    Writeln( 'Remaining seconds      : ',res );
end.

```

---

### 1.4.79 FpStat

Synopsis: Retrieve file information about a file descriptor.

Declaration: `function FpStat(path: pChar;var buf: Stat) : cint`  
`function FpStat(path: AnsiString;var buf: Stat) : cint`  
`function FpStat(path: String;var buf: Stat) : cint`



Visibility: default

Description: `FpFStat` gets information about the file specified in `Path`, and stores it in `Info`, which is of type `stat` (135). The function returns zero if the call was successful, a nonzero return value indicates failure.

Errors: Extended error information can be retrieved using `fpGetErrno` (154).

`sys_enoentPath` does not exist.

See also: `FpStat` (183), `FpLStat` (161)

**Listing:** `./bunixex/ex28.pp`

---

```

program example28;

{ Program to demonstrate the FStat function. }

uses BaseUnix;

var f : text;
    i : byte;
    info : stat;

begin
  { Make a file }
  assign (f, 'test.fil');
  rewrite (f);
  for i:=1 to 10 do writeln (f, 'Testline # ', i);
  close (f);
  { Do the call on made file. }
  if fpstat ('test.fil', info) <> 0 then
    begin
      writeln ('Fstat failed. Errno : ', fpgeterrno);
      halt (1);
    end;
  writeln;
  writeln ('Result of fstat on file ''test.fil''.');
  writeln ('Inode   : ', info.st_ino);
  writeln ('Mode    : ', info.st_mode);
  writeln ('nlink   : ', info.st_nlink);
  writeln ('uid     : ', info.st_uid);
  writeln ('gid     : ', info.st_gid);
  writeln ('rdev    : ', info.st_rdev);
  writeln ('Size    : ', info.st_size);
  writeln ('Blksize  : ', info.st_blksize);
  writeln ('Blocks  : ', info.st_blocks);
  writeln ('atime   : ', info.st_atime);
  writeln ('mtime   : ', info.st_mtime);
  writeln ('ctime   : ', info.st_ctime);
  { Remove file }
  erase (f);
end.

```

---

### 1.4.80 fpSymlink

Synopsis: Create a symbolic link

**Declaration:** `function fpSymlink(oldname: pchar;newname: pchar) : cint`

**Visibility:** default

**Description:** `SymLink` makes `NewName` point to the file in `OldName`, which doesn't necessarily exist. The two files DO NOT have the same inode number. This is known as a 'soft' link.

The permissions of the link are irrelevant, as they are not used when following the link. Ownership of the file is only checked in case of removal or renaming of the link.

The function returns zero if the call was succesful, a nonzero value if the call failed.

**Errors:** Extended error information is returned by the `FpGetErrno` (154) function.

**sys\_eperm**The filesystem containing `oldpath` and `newpath` does not support linking files.

**sys\_eaccess**Write access for the directory containing `Newpath` is disallowed, or one of the directories in `OldPath` or `NewPath` has no search (=execute) permission.

**sys\_enoent**A directory entry in `OldPath` or `NewPath` does not exist or is a symbolic link pointing to a non-existent directory.

**sys\_enotdir**A directory entry in `OldPath` or `NewPath` is nor a directory.

**sys\_enomem**Insufficient kernel memory.

**sys\_erofs**The files are on a read-only filesystem.

**sys\_eexist**`NewPath` already exists.

**sys\_eloop**`OldPath` or `NewPath` has a reference to a circular symbolic link, i.e. a symbolic link, whose expansion points to itself.

**sys\_enospc**The device containing `NewPath` has no room for another entry.

See also: `FpLink` (159), `FpUnLink` (189), `FpReadLink` (172)

**Listing:** `./unixex/ex22.pp`

---

**Program** `Example22`;

*{ Program to demonstrate the SymLink and UnLink functions. }*

**Uses** `baseunix`, `Unix`;

**Var** `F` : `Text`;  
       `S` : **String**;

**begin**  
   Assign (`F`, 'test.txt');  
   Rewrite (`F`);  
   Writeln (`F`, 'This is written to test.txt');  
   Close(`f`);  
   *{ new.txt and test.txt are now the same file }*  
   if `fpSymLink` ( 'test.txt', 'new.txt') <> 0 then  
     writeln ( 'Error when symlinking !' );  
   *{ Removing test.txt still leaves new.txt*  
   *Pointing now to a non-existent file ! }*  
   If `fpUnlink` ( 'test.txt') <> 0 then  
     Writeln ( 'Error when unlinking !' );  
   Assign (`f`, 'new.txt');  
   *{ This should fail, since the symbolic link*  
   *points to a non-existent file ! }*  
   *{ \$i- }*

---

```

Reset (F);
{ $i+ }
If IOResult=0 then
  Writeln ( 'This shouldn''t happen' );
{ Now remove new.txt also }
If fpUnlink ( 'new.txt ' ) <> 0 then
  Writeln ( 'Error when unlinking !' );
end.

```

---

### 1.4.81 fpS\_ISBLK

Synopsis: Is file a block device

Declaration: function fpS\_ISBLK(m: TMode) : Boolean

Visibility: default

Description: FpS\_ISBLK checks the file mode m to see whether the file is a block device file. If so it returns True.

See also: FpFStat ([152](#)), FpS\_ISLNK ([186](#)), FpS\_ISREG ([187](#)), FpS\_ISDIR ([186](#)), FpS\_ISCHR ([185](#)), FpS\_ISFIFO ([186](#)), FpS\_ISSOCK ([187](#))

### 1.4.82 fpS\_ISCHR

Synopsis: Is file a character device

Declaration: function fpS\_ISCHR(m: TMode) : Boolean

Visibility: default

Description: FpS\_ISCHR checks the file mode m to see whether the file is a character device file. If so it returns True.

See also: FpFStat ([152](#)), FpS\_ISLNK ([186](#)), FpS\_ISREG ([187](#)), FpS\_ISDIR ([186](#)), FpS\_ISBLK ([185](#)), FpS\_ISFIFO ([186](#)), FpS\_ISSOCK ([187](#))

### 1.4.83 fpS\_ISDIR

Synopsis: Is file a directory

Declaration: function fpS\_ISDIR(m: TMode) : Boolean

Visibility: default

Description: fpS\_ISDIR checks the file mode m to see whether the file is a directory. If so, it returns True

See also: FpFStat ([152](#)), FpS\_ISLNK ([186](#)), FpS\_ISREG ([187](#)), FpS\_ISCHR ([185](#)), FpS\_ISBLK ([185](#)), FpS\_ISFIFO ([186](#)), FpS\_ISSOCK ([187](#))

### 1.4.84 fpS\_ISFIFO

Synopsis: Is file a FIFO

Declaration: `function fpS_ISFIFO(m: TMode) : Boolean`

Visibility: default

Description: `FpS_ISFIFO` checks the file mode `m` to see whether the file is a fifo (a named pipe). If so it returns `True`.

See also: `FpFStat` (152), `FpS_ISLNK` (186), `FpS_ISREG` (187), `FpS_ISCHR` (185), `FpS_ISBLK` (185), `FpS_ISDIR` (186), `FpS_ISSOCK` (187)

### 1.4.85 fpS\_ISLNK

Synopsis: Is file a symbolic link

Declaration: `function fpS_ISLNK(m: TMode) : Boolean`

Visibility: default

Description: `FpS_ISLNK` checks the file mode `m` to see whether the file is a symbolic link. If so it returns `True`

See also: `FpFStat` (152), `FpS_ISFIFO` (186), `FpS_ISREG` (187), `FpS_ISCHR` (185), `FpS_ISBLK` (185), `FpS_ISDIR` (186), `FpS_ISSOCK` (187)

**Listing:** `./bunixex/ex53.pp`

**Program** `Example53;`

*{ Program to demonstrate the S\_ISLNK function. }*

**Uses** `BaseUnix, Unix;`

**Var** `Info : Stat;`

**begin**

**if** `fpLStat (paramstr(1), @info)=0` **then**

**begin**

**if** `fpS_ISLNK(info.st_mode)` **then**

**WriteLn** ( 'File is a link' );

**if** `fpS_ISREG(info.st_mode)` **then**

**WriteLn** ( 'File is a regular file' );

**if** `fpS_ISDIR(info.st_mode)` **then**

**WriteLn** ( 'File is a directory' );

**if** `fpS_ISCHR(info.st_mode)` **then**

**WriteLn** ( 'File is a character device file' );

**if** `fpS_ISBLK(info.st_mode)` **then**

**WriteLn** ( 'File is a block device file' );

**if** `fpS_ISFIFO(info.st_mode)` **then**

**WriteLn** ( 'File is a named pipe (FIFO)' );

**if** `fpS_ISSOCK(info.st_mode)` **then**

**WriteLn** ( 'File is a socket' );

**end;**

**end.**

### 1.4.86 fpS\_ISREG

Synopsis: Is file a regular file

Declaration: `function fpS_ISREG(m: TMode) : Boolean`

Visibility: default

Description: `FpS_ISREG` checks the file mode `m` to see whether the file is a regular file. If so it returns `True`

See also: `FpFStat` (152), `FpS_ISFIFO` (186), `FpS_ISLNK` (186), `FpS_ISCHR` (185), `FpS_ISBLK` (185), `FpS_ISDIR` (186), `FpS_ISSOCK` (187)

### 1.4.87 fpS\_ISSOCK

Synopsis: Is file a unix socket

Declaration: `function fpS_ISSOCK(m: TMode) : Boolean`

Visibility: default

Description: `FpS_ISSOCK` checks the file mode `m` to see whether the file is a socket. If so it returns `True`.

See also: `FpFStat` (152), `FpS_ISFIFO` (186), `FpS_ISLNK` (186), `FpS_ISCHR` (185), `FpS_ISBLK` (185), `FpS_ISDIR` (186), `FpS_ISREG` (187)

### 1.4.88 fptime

Synopsis: Return the current unix time

Declaration: `function FpTime(var tloc: TTime) : TTime`  
`function fptime : time_t`

Visibility: default

Description: `FpTime` returns the number of seconds since 00:00:00 GMT, january 1, 1970. it is adjusted to the local time zone, but not to DST. The result is also stored in `tloc`, if it is specified.

Errors: On error, -1 is returned. Extended error information can be retrieved using `fpGetErrno` (154).

**Listing:** `./bunixex/ex1.pp`

---

**Program** `Example1`;

*{ Program to demonstrate the fptime function. }*

**Uses** `baseunix`;

**begin**

**Write** ( 'Secs past the start of the Epoch (00:00 1/1/1980) : ' );

**Writeln** ( fptime );

**end.**

---

### 1.4.89 FpTimes

Synopsis: Return execution times for the current process

Declaration: `function FpTimes (var buffer: tms) : TClock`

Visibility: default

Description: `fpTimes` stores the execution time of the current process and child processes in `buffer`.

The return value (on linux) is the number of clock ticks since boot time. On error, -1 is returned, and extended error information can be retrieved with `fpGetErrno` (154).

See also: `fpUTime` (189)

### 1.4.90 FpUmask

Synopsis: Set file creation mask.

Declaration: `function FpUmask (cmask: TMode) : TMode`

Visibility: default

Description: `fpUmask` changes the file creation mask for the current user to `cmask`. The current mask is returned.

See also: `fpChmod` (142)

**Listing:** `./bunixex/ex27.pp`

---

**Program** `Example27`;

*{ Program to demonstrate the Umask function. }*

**Uses** `BaseUnix`;

**begin**

**WriteLn** ( 'Old Umask was : ', `fpUmask(&111)`);

**WRiteLn** ( 'New Umask is : ', `&111`);

**end.**

---

### 1.4.91 FpUname

Synopsis: Return system name.

Declaration: `function FpUname (var name: UtsName) : cint`

Visibility: default

Description: `Uname` gets the name and configuration of the current linux kernel, and returns it in the `name` record.

On success, 0 is returned, on error, -1 is returned.

Errors: Extended error information can be retrieved using `fpGetErrno` (154).

See also: `FpUTime` (189)

### 1.4.92 FpUnlink

Synopsis: Unlink (i.e. remove) a file.

Declaration: `function FpUnlink(path: PChar) : cint`  
`function FpUnlink(path: AnsiString) : cint`

Visibility: default

Description: `FpUnlink` decreases the link count on file `Path`. `Path` can be of type `AnsiString` or `PChar`. If the link count is zero, the file is removed from the disk.

The function returns zero if the call was successful, a nonzero value indicates failure.

Note: There exist a portable alternative to erase files: `system.erase`. Please use `fpUnlink` only if you are writing Unix specific code. `System.erase` will work on all operating systems.

For an example, see `FpLink` (159).

Errors: Extended error information can be retrieved using `fpGetErrno` (154).

**sys\_eaccess** You have no write access right in the directory containing `Path`, or you have no search permission in one of the directory components of `Path`.

**sys\_eperm** The directory containing `pathname` has the sticky-bit set and the process's effective uid is neither the uid of the file to be deleted nor that of the directory containing it.

**sys\_enoent** A component of the path doesn't exist.

**sys\_enotdir** A directory component of the path is not a directory.

**sys\_eisdir** `Path` refers to a directory.

**sys\_enomem** Insufficient kernel memory.

**sys\_erofs** `Path` is on a read-only filesystem.

See also: `FpLink` (159), `FpSymLink` (184)

### 1.4.93 FpUtime

Synopsis: Set access and modification times of a file (touch).

Declaration: `function FpUtime(path: PChar; times: pUtimBuf) : cint`  
`function FpUtime(path: AnsiString; times: pUtimBuf) : cint`

Visibility: default

Description: `FpUtime` sets the access and modification times of the file specified in `Path`. the `times` record contains 2 fields, `actime`, and `modtime`, both of type `time_t` (commonly a `longint`). They should be filled with an epoch-like time, specifying, respectively, the last access time, and the last modification time. For some filesystem (most notably, FAT), these times are the same.

The function returns zero on success, a nonzero return value indicates failure.

Errors: Extended error information can be retrieved using `fpGetErrno` (154).

**sys\_eaccess** One of the directories in `Path` has no search (=execute) permission.

**sys\_enoent** A directory entry in `Path` does not exist or is a symbolic link pointing to a non-existent directory.

Other errors may occur, but aren't documented.

See also: `FpTime` (187), `FpChown` (144), `FpAccess` (141)

**Listing:** ./bunixex/ex25.pp

**Program** Example25;

*{ Program to demonstrate the UTime function. }*

**Uses** Dos, BaseUnix, Unix, UnixUtil;

**Var** utim : utimbuf;  
       dow, msec, year, month, day, hour, minute, second : Word;

**begin**  
   *{ Set access and modification time of executable source }*  
   GetTime ( hour, minute, second, msec );  
   GetDate ( year, month, day, dow );  
   utim.actime := LocalToEpoch ( year, month, day, hour, minute, second );  
   utim.modtime := utim.actime;  
   **if** Fputime ( 'ex25.pp', @utim ) < > 0 **then**  
     **writeln** ( 'Call to UTime failed !' )  
   **else**  
     **begin**  
       **Write** ( 'Set access and modification times to : ' );  
       **Write** ( Hour:2, ':', minute:2, ':', second, ', ' );  
       **Writeln** ( Day:2, '/', month:2, '/', year:4 );  
     **end**;  
**end.**

### 1.4.94 FpWait

**Synopsis:** Wait for a child to exit.

**Declaration:** function FpWait (var stat\_loc: cint) : TPid

**Visibility:** default

**Description:** fpWait suspends the current process and waits for any child to exit or stop due to a signal. It reports the exit status of the exited child in stat\_loc.

The return value of the function is the process ID of the child that exited, or -1 on error.

**Errors:** Extended error information can be retrieved using fpgetErrno ([154](#)).

**See also:** fpFork ([151](#)), fpExecve ([148](#)), fpWaitPid ([191](#))

### 1.4.95 FpWaitPid

**Synopsis:** Wait for a process to terminate

**Declaration:** function FpWaitpid (pid: TPid; stat\_loc: pcint; options: cint) : TPid  
       function FpWaitPid (pid: TPid; var Status: cint; Options: cint) : TPid

**Visibility:** default

**Description:** fpWaitPid waits for a child process with process ID Pid to exit. The value of Pid can be one of the following:

**Pid < -1** Causes fpWaitPid to wait for any child process whose process group ID equals the absolute value of pid.



**Pid = -1** Causes `fpWaitPid` to wait for any child process.

**Pid = 0** Causes `fpWaitPid` to wait for any child process whose process group ID equals the one of the calling process.

**Pid > 0** Causes `fpWaitPid` to wait for the child whose process ID equals the value of `Pid`.

The `Options` parameter can be used to specify further how `fpWaitPid` behaves:

**WNOHANG** Causes `fpWaitpid` to return immediately if no child has exited.

**WUNTRACED** Causes `fpWaitPid` to return also for children which are stopped, but whose status has not yet been reported.

**\_\_WCLONE** Causes `fpWaitPid` also to wait for threads created by the `#rtl.linux.Clone` (729) call.

The exit status of the process that caused `fpWaitPID` is reported in `stat_loc` or `Status`.

Upon return, it returns the process id of the process that exited, 0 if no process exited, or -1 in case of failure.

For an example, see `fpFork` (151).

Errors: Extended error information can be retrieved using `fpgetErrno` (154).

See also: `fpFork` (151), `fpExecve` (148), `fpWait` (190)

### 1.4.96 FpWrite

Synopsis: Write data to file descriptor

Declaration: `function FpWrite(fd: cint; buf: pChar; nbytes: TSize) : TSize`  
`function FpWrite(fd: cint; const buf; nbytes: TSize) : TSize`

Visibility: default

Description: `FpWrite` writes at most `nbytes` bytes from `buf` to file descriptor `fd`.

The function returns the number of bytes actually written, or -1 if an error occurred.

Errors: Extended error information can be retrieved using `fpGetErrno` (154).

See also: `FpOpen` (166), `FpClose` (145), `FpRead` (171), `FpFTruncate` (153), `FpLSeek` (160)

### 1.4.97 FpWriteV

Synopsis: Vector write: Write from multiple buffers to a file descriptor

Declaration: `function FpWriteV(fd: cint; const iov: piovec; iovcnt: cint) : TSize`

Visibility: default

Description: `FpWriteV` writes data to file descriptor `fd`. The data is taken from `iovcnt` buffers described by the `tiovec` (137) buffers pointed to by `iov`. It works like `fpWrite` (191) only from multiple buffers.

Errors: On error, -1 is returned.

See also: `FpReadV` (173), `FpPWrite` (170), `FpPRead` (170)

### 1.4.98 FreeShellArgV

Synopsis: Free the result of a CreateShellArgV (140) function

Declaration: `procedure FreeShellArgV(p: ppchar)`

Visibility: default

Description: `FreeShellArgV` frees the memory pointed to by `P`, which was allocated by a call to `CreateShellArgV` (140).

Errors: None.

See also: `CreateShellArgV` (140)

### 1.4.99 wexitStatus

Synopsis: Extract the exit status from the `fpWaitPID` (191) result.

Declaration: `function wexitStatus(Status: cint) : cint`

Visibility: default

Description: `WEXITSTATUS` can be used to extract the exit status from `Status`, the result of the `FpWaitPID` (191) call.

See also: `FpWaitPID` (191), `WTERMSIG` (193), `WSTOPSIG` (193), `WIFEXITED` (192), `WIFSIGNALED` (193)

### 1.4.100 wifexited

Synopsis: Check whether the process exited normally

Declaration: `function wifexited(Status: cint) : Boolean`

Visibility: default

Description: `WIFEXITED` checks `Status` and returns `True` if the status indicates that the process terminated normally, i.e. was not stopped by a signal.

See also: `FpWaitPID` (191), `WTERMSIG` (193), `WSTOPSIG` (193), `WIFSIGNALED` (193), `WEXITSTATUS` (192)

### 1.4.101 wifsignaled

Synopsis: Check whether the process was exited by a signal.

Declaration: `function wifsignaled(Status: cint) : Boolean`

Visibility: default

Description: `WIFSIGNALED` returns `True` if `Status` indicates that the process exited because it received a signal.

See also: `FpWaitPID` (191), `WTERMSIG` (193), `WSTOPSIG` (193), `WIFEXITED` (192), `WEXITSTATUS` (192)

### 1.4.102 wstopsig

Synopsis: Return the exit code from the process.

Declaration: `function wstopsig(Status: cint) : cint`

Visibility: default

Description: WSTOPSIG is an alias for WEXITSTATUS ([192](#)).

See also: FpWaitPID ([191](#)), WTERMSIG ([193](#)), WIFEXITED ([192](#)), WIFSIGNALED ([193](#)), WEXITSTATUS ([192](#))

### 1.4.103 wtermsig

Synopsis: Return the signal that caused a process to exit.

Declaration: `function wtermsig(Status: cint) : cint`

Visibility: default

Description: WTERMSIG extracts from Status the signal number which caused the process to exit.

See also: FpWaitPID ([191](#)), WSTOPSIG ([193](#)), WIFEXITED ([192](#)), WIFSIGNALED ([193](#)), WEXITSTATUS ([192](#))

## Chapter 2

# Reference for unit 'Classes'

### 2.1 Used units

Table 2.1: Used units by unit 'Classes'

Name	Page
rtlconsts	<a href="#">194</a>
sysutils	<a href="#">1426</a>
types	<a href="#">1587</a>
typinfo	<a href="#">1606</a>

### 2.2 Overview

This documentation describes the FPC `classes` unit. The `Classes` unit contains basic classes for the Free Component Library (FCL):

- a `TList` ([319](#)) class for maintaining lists of pointers,
- `TStringList` ([368](#)) for lists of strings,
- `TCollection` ([271](#)) to manage collections of objects
- `TStream` ([355](#)) classes to support streaming.

Furthermore it introduces methods for object persistence, and classes that understand an owner-owned relationship, with automatic memory management.

### 2.3 Constants, types and variables

#### 2.3.1 Constants

`BITSHIFT = 5`

Used to calculate the size of a bits array

`dupAccept = Types.dupAccept`

Duplicate values can be added to the list.

`dupError = Types.dupError`

If an attempt is made to add a duplicate value to the list, an `EStringListError` (226) exception is raised.

`dupIgnore = Types.dupIgnore`

Duplicate values will not be added to the list, but no error will be triggered.

`FilerSignature : Array[1..4] of Char = 'TPF0'`

Constant that is found at the start of a binary stream containing a streamed component.

`fmCreate = $FFFF`

`TFileStream.Create` (301) creates a new file if needed.

`fmOpenRead = 0`

`TFileStream.Create` (301) opens a file with read-only access.

`fmOpenReadWrite = 2`

`TFileStream.Create` (301) opens a file with read-write access.

`fmOpenWrite = 1`

`TFileStream.Create` (301) opens a file with write-only access.

`MASK = 31`

Bitmask with all bits on.

`MaxBitFlags = $7FFFFFFE0`

Maximum number of bits in `TBits` collection.

`MaxBitRec = MaxBitFlags div (SizeOf(cardinal) * 8)`

Maximum number of bit records in `TBits`.

`MaxListSize = Maxint div 16`

This constant sets the maximum number of elements in a `TList` (319).

`scAlt = $8000`

Indicates ALT key in a keyboard shortcut.

```
scCtrl = $4000
```

indicates CTRL key in a keyboard shortcut.

```
scNone = 0
```

Indicates no special key is pressed in a keyboard shortcut.

```
scShift = $2000
```

Indicates Shift key in a keyboard shortcut.

```
soFromBeginning = 0
```

Seek (356) starts relative to the stream origin.

```
soFromCurrent = 1
```

Seek (356) starts relative to the current position in the stream.

```
soFromEnd = 2
```

Seek (356) starts relative to the stream end.

```
toEOF = Char(0)
```

Value returned by `TParser.Token` (338) when the end of the input stream was reached.

```
toFloat = Char(4)
```

Value returned by `TParser.Token` (338) when a floating point value was found in the input stream.

```
toInteger = Char(3)
```

Value returned by `TParser.Token` (338) when an integer was found in the input stream.

```
toString = Char(2)
```

Value returned by `TParser.Token` (338) when a string was found in the input stream.

```
toSymbol = Char(1)
```

Value returned by `TParser.Token` (338) when a symbol was found in the input stream.

```
toWString = Char(5)
```

Value returned by `TParser.Token` (338) when a wstring was found in the input stream.

### 2.3.2 Types

```
HMODULE = puint
```

FPC doesn't support modules yet, so this is a dummy type.

```
HRSRC = TFPResourceHandle
```

This type is provided for Delphi compatibility, it is used for resource streams.

```
PPointerList = ^TPointerList
```

Pointer to an array of pointers.

```
PStringItem = ^TStringItem
```

Pointer to a TStringItem (206) record.

```
PStringItemList = ^TStringItemList
```

Pointer to a TStringItemList (206).

```
TActiveXRegType = (axrComponentOnly, axrIncludeDescendants)
```

Table 2.2: Enumeration values for type TActiveXRegType

Value	Explanation
axrComponentOnly	
axrIncludeDescendants	

This type is provided for compatibility only, and is currently not used in Free Pascal.

```
TAlignment = (taLeftJustify, taRightJustify, taCenter)
```

Table 2.3: Enumeration values for type TAlignment

Value	Explanation
taCenter	Text is displayed centered.
taLeftJustify	Text is displayed aligned to the left
taRightJustify	Text is displayed aligned to the right.

The TAlignment type is used to specify the alignment of the text in controls that display a text.

```
TAncestorNotFoundEvent = procedure (Reader: TReader;
                                     const ComponentName: String;
                                     ComponentClass: TPersistentClass;
                                     var Component: TComponent) of object
```

This event occurs when an ancestor component cannot be found.

`TBasicActionClass = Class of TBasicAction`

`TBasicAction` (247) class reference.

`TBasicActionLinkClass = Class of TBasicActionLink`

`TBasicActionLink` (251) class reference.

`TBiDiMode = (bdLeftToRight, bdRightToLeft, bdRightToLeftNoAlign,  
bdRightToLeftReadingOnly)`

Table 2.4: Enumeration values for type `TBiDiMode`

Value	Explanation
<code>bdLeftToRight</code>	Texts read from left to right.
<code>bdRightToLeft</code>	Texts read from right to left.
<code>bdRightToLeftNoAlign</code>	Texts read from right to left, but not right-aligned
<code>bdRightToLeftReadingOnly</code>	Texts read from right to left

`TBiDiMode` describes bi-directional support for displaying texts.

`TBitArray = Array[0..MaxBitRec-1] of cardinal`

Array to store bits.

`TCollectionItemClass = Class of TCollectionItem`

`TCollectionItemClass` is used by the `TCollection.ItemClass` (277) property of `TCollection` (271) to identify the descendent class of `TCollectionItem` (279) which should be created and managed.

`TCollectionNotification = (cnAdded, cnExtracting, cnDeleting)`

Table 2.5: Enumeration values for type `TCollectionNotification`

Value	Explanation
<code>cnAdded</code>	An item is added to the collection.
<code>cnDeleting</code>	An item is deleted from the collection.
<code>cnExtracting</code>	An item is extracted from the collection.

`TCollectionNotification` is used in the `TCollection` (271) class to send notifications about changes to the collection.

`TCollectionSortCompare = function (Item1: TCollectionItem;  
Item2: TCollectionItem) : Integer`

`TCollectionSortCompare` is the prototype for a callback used in the `TCollection.Sort` (276) method. The procedure should compare `Item1` and `Item2` and return an integer:



**Result < 0** if Item1 comes before Item2

**Result = 0** if Item1 is at the same level as Item2

**Result > 0** if Item1 comes after Item2

`TComponentClass = Class of TComponent`

The `TComponentClass` type is used when constructing `TComponent` (281) descendent instances and when registering components.

`TComponentName = String`

Names of components are of type `TComponentName`. By specifying a different type, the Object inspector can handle this property differently than a standard string property.

`TComponentState= Set of (csLoading,csReading,csWriting,csDestroying,  
csDesigning,csAncestor,csUpdating,csFixups,  
csFreeNotification,csInline,csDesignInstance)`

Indicates the state of the component during the streaming process.

`TComponentStyle= Set of (csInheritable,csCheckPropAvail,csSubComponent,  
csTransient)`

Describes the style of the component.

`TCreateComponentEvent = procedure(Reader: TReader;  
ComponentClass: TComponentClass;  
var Component: TComponent) of object`

Event handler type, occurs when a component instance must be created when a component is read from a stream.

`TDataModuleClass = Class of TDataModule`

`TDataModuleClass` defines the class pointer for `TDataModule` (295).

`TDuplicates = Types.TDuplicates`

Type to describe what to do with duplicate values in a `TStringlist` (368).

`TFilerFlag = (ffInherited,ffChildPos,ffInline)`

The `TFiler` class uses this enumeration type to decide whether the streamed object was streamed as part of an inherited form or not.

`TFilerFlags= Set of (ffChildPos,ffInherited,ffInline)`

Set of `TFilerFlag` (199)

Table 2.6: Enumeration values for type TFileFlag

Value	Explanation
ffChildPos	The position of the child on it's parent is included.
ffInherited	Stored object is an inherited object.
ffInline	Used for frames.

```
TFindAncestorEvent = procedure(Writer: TWriter;Component: TComponent;
                               const Name: String;
                               var Ancestor: TComponent;
                               var RootAncestor: TComponent) of object
```

Event that occurs w

```
TFindComponentClassEvent = procedure(Reader: TReader;
                                     const ClassName: String;
                                     var ComponentClass: TComponentClass)
                               of object
```

Event handler type, occurs when a component class pointer must be found when reading a component from a stream.

```
TFindGlobalComponent = function(const Name: String) : TComponent
```

TFindGlobalComponent is a callback used to find a component in a global scope. It is used when the streaming system needs to find a component which is not part of the component which is currently being streamed. It should return the component with name Name, or Nil if none is found.

The variable FindGlobalComponent (212) is a callback of type TFindGlobalComponent. It can be set by the IDE when an unknown reference is found, to offer the designer to redirect the link to a new component.

```
TFindMethodEvent = procedure(Reader: TReader;const MethodName: String;
                             var Address: Pointer;var Error: Boolean)
                             of object
```

If a TReader (341) instance needs to locate a method and it doesn't find it in the streamed form, then the OnFindMethod (350) event handler will be called, if one is installed. This event can be assigned in order to use different locating methods. If a method is found, then its address should be returned in Address. The Error should be set to True if the reader should raise an exception after the event was handled. If it is set to False no exception will be raised, even if no method was found. On entry, Error will be set to True.

```
TGetChildProc = procedure(Child: TComponent) of object
```

Callback used when obtaining child components.

```
TGetStrProc = procedure(const S: String) of object
```

This event is used as a callback to retrieve string values. It is used, among other things, to pass along string properties in property editors.

```
THandle = System.THandle
```

This type is used as the handle for THandleStream (310) stream descendents

```
THelpContext = -MaxLongint..MaxLongint
```

Range type to specify help contexts.

```
THelpEvent = function(Command: Word;Data: LongInt;var CallHelp: Boolean)
               : Boolean of object
```

This event is used for display of online help.

```
THelpType = (htKeyword,htContext)
```

Table 2.7: Enumeration values for type THelpType

Value	Explanation
htContext	Help type: Context ID help.
htKeyword	Help type: Keyword help

Enumeration type specifying the kind of help requested.

```
TIdentMapEntry = record
    Value : Integer;
    Name : String;
end
```

TIdentMapEntry is used internally by the IdentToInt (214) and IntToIdent (215) calls to store the mapping between the identifiers and the integers they represent.

```
TIdentToInt = function(const Ident: String;var Int: LongInt) : Boolean
```

TIdentToInt is a callback used to look up identifiers (Ident) and return an integer value corresponding to this identifier (Int). The callback should return True if a value corresponding to integer Ident was found, False if not.

A callback of type TIdentToInt should be specified when an integer is registered using the RegisterIntegerConsts (220) call.

```
TInitComponentHandler = function(Instance: TComponent;
                                RootAncestor: TClass) : Boolean
```

TInitComponentHandler is a callback type. It is used in the InitInheritedComponent (??) call to initialize a component. Callbacks of this type are registered with the RegisterInitComponentHandler (220) call.

```
TIntToIdent = function(Int: LongInt;var Ident: String) : Boolean
```

`TIdentToInt` is a callback used to look up integers (`Ident`) and return an identifier (`Ident`) that can be used to represent this integer value in an IDE. The callback should return `True` if a value corresponding to integer `Ident` was found, `False` if not.

A callback of type `TIntToIdent` should be specified when an integer is registered using the `RegisterIntegerConsts` (220) call.

```
TLeftRight = taLeftJustify..taRightJustify
```

`TLeftRight` is a subrange type based on the `TAlignment` (197) enumerated type. It contains only the left and right alignment constants.

```
TListAssignOp = (laCopy, laAnd, laOr, laXor, laSrcUnique, laDestUnique)
```

Table 2.8: Enumeration values for type `TListAssignOp`

Value	Explanation
<code>laAnd</code>	Remove all elements not first second list
<code>laCopy</code>	Clear list and copy all strings from second list.
<code>laDestUnique</code>	Keep all elements that exists only in list2
<code>laOr</code>	Add all elements from second (and optional third) list, eliminate duplicates
<code>laSrcUnique</code>	Just keep all elements that exist only in source list
<code>laXor</code>	Remove elements in second lists, Add all elements from second list not in first list

This type determines what operation `TList.Assign` (324) or `TFPList.assign` (306) performs.

```
TListCallback = Types.TListCallback
```

`TListCallback` is the method callback prototype for the function that is passed to the `TFPList.ForEachCall` (307) call. The `data` argument will be filled with all the pointers in the list (one per call) and the `arg` argument is the `Arg` argument passed to the `ForEachCall` call.

```
TListNotification = (lnAdded, lnExtracted, lnDeleted)
```

Table 2.9: Enumeration values for type `TListNotification`

Value	Explanation
<code>lnAdded</code>	List change notification: Element added to the list.
<code>lnDeleted</code>	List change notification: Element deleted from the list.
<code>lnExtracted</code>	List change notification: Element extracted from the list.

Kind of list notification event.

```
TListSortCompare = function(Item1: Pointer;Item2: Pointer) : Integer
```

Callback type for the list sort algorithm.

```
TListStaticCallback = Types.TListStaticCallback
```

`TListCallback` is the procedural callback prototype for the function that is passed to the `TFPList.ForEachCall` (307) call. The `data` argument will be filled with all the pointers in the list (one per call) and the `arg` argument is the `Arg` argument passed to the `ForEachCall` call.

`TNotifyEvent` = procedure(Sender: TObject) of object

Most event handlers are implemented as a property of type `TNotifyEvent`. When this is set to a certain method of a class, when the event occurs, the method will be called, and the class that generated the event will pass itself along as the `Sender` argument.

`TObjectTextEncoding` = (oteDFM,oteLFM)

Table 2.10: Enumeration values for type `TObjectTextEncoding`

Value	Explanation
oteDFM	Characters are in DFM (Delphi) format: widechar encoded.
oteLFM	Characters are in LFM format: UTF-8 encoded.

`TObjectTextEncoding` is an enumerated type which denotes the encoding of non ascii characters in an object stream file. It is needed for correct encoding when reading string values in the text stream.

`TOperation` = (opInsert,opRemove)

Table 2.11: Enumeration values for type `TOperation`

Value	Explanation
opInsert	A new component is being inserted in the child component list.
opRemove	A component is being removed from the child component list.

Operation of which a component is notified.

`TPersistentClass` = Class of `TPersistent`

`TPersistentClass` is the class reference type for the `TPersistent` (338) class.

`TPoint` = Types.TPoint

This record describes a coordinate. It is used to handle the `Top` (281) and `Left` (281) properties of `TComponent` (281).

`X` represents the X-Coordinate of the point described by the record. `Y` represents the Y-Coordinate of the point described by the record.

`TPointerList` = Array[0..MaxListSize-1] of Pointer

Type for an Array of pointers.

```
TPropertyNotFoundEvent = procedure(Reader: TReader;
                                   Instance: TPersistent;
                                   var PropName: String; IsPath: Boolean;
                                   var Handled: Boolean;
                                   var Skip: Boolean) of object
```

TPropertyNotFoundEvent is the prototype for the TReader.OnPropertyNotFound (350) event. Reader is the sender of the event, Instance is the instance that is being streamed. PropInfo is a pointer to the RTTI information for the property being read. Handled should be set to True if the handler redirected the unknown property successfully, and Skip should be set to True if the value should be skipped. IsPath determines whether the property refers to a sub-property.

```
TReadComponentsProc = procedure(Component: TComponent) of object
```

Callback type when reading a component from a stream

```
TReaderError = procedure(Reader: TReader; const Message: String;
                          var Handled: Boolean) of object
```

Event handler type, called when an error occurs during the streaming.

```
TReaderProc = procedure(Reader: TReader) of object
```

The TReaderProc reader procedure is a callback procedure which will be used by a TPersistent (338) descendent to read user properties from a stream during the streaming process. The Reader argument is the writer object which can be used read properties from the stream.

```
TReadWriteStringPropertyEvent = procedure(Sender: TObject;
                                           const Instance: TPersistent;
                                           PropInfo: PPropInfo;
                                           var Content: String) of object
```

TReadWriteStringPropertyEvent is the prototype for the TReader.OnReadStringProperty (352) event handler. Reader is the sender of the event, Instance is the instance that is being streamed. PropInfo is a pointer to the RTTI information for the property being read. Content is the string as it was read from the stream.

```
TRect = Types.TRect
```

TRect describes a rectangle in space with its upper-left (in (Top,Left>)) and lower-right (in (Bottom,Right)) corners.

```
TReferenceNameEvent = procedure(Reader: TReader; var Name: String)
                             of object
```

Occurs when a named object needs to be looked up.

```
TSeekOrigin = (soBeginning, soCurrent, soEnd)
```

Specifies the origin of the TStream.Seek (356) method.

Table 2.12: Enumeration values for type TSeekOrigin

Value	Explanation
soBeginning	Offset is interpreted relative to the start of the stream.
soCurrent	Offset is interpreted relative to the current position in the stream.
soEnd	Offset is interpreted relative to the end of the stream.

```
TSetMethodPropertyEvent = procedure(Reader: TReader;
                                     Instance: TPersistent;
                                     PropInfo: PPropInfo;
                                     const TheMethodName: String;
                                     var Handled: Boolean) of object
```

TSetMethodPropertyEvent is the prototype for the TReader.OnSetMethodProperty (350) event. Reader is the sender of the event, Instance is the instance that is being streamed. PropInfo is a pointer to the RTTI information for the property being read, and TheMethodName is the name of the method that the property should be set to. Handled should be set to True if the handler set the property successfully.

```
TSetNameEvent = procedure(Reader: TReader; Component: TComponent;
                          var Name: String) of object
```

Occurs when the reader needs to set a component's name.

```
TShiftState= Set of (ssShift, ssAlt, ssCtrl, ssLeft, ssRight, ssMiddle,
                     ssDouble, ssMeta, ssSuper, ssHyper, ssAltGr, ssCaps,
                     ssNum, ssScroll, ssTriple, ssQuad, ssExtral, ssExtra2)
```

This type is used when describing a shortcut key or when describing what special keys are pressed on a keyboard when a key event is generated.

The set contains the special keys that can be used in combination with a 'normal' key.

```
TShiftStateEnum = (ssShift, ssAlt, ssCtrl, ssLeft, ssRight, ssMiddle,
                   ssDouble, ssMeta, ssSuper, ssHyper, ssAltGr, ssCaps, ssNum,
                   ssScroll, ssTriple, ssQuad, ssExtral, ssExtra2)
```

Keyboard/Mouse shift state enumerator

```
TShortCut = Low(Word) .. High(Word)
```

Enumeration type to identify shortcut key combinations.

```
TSmallPoint = record
  x : SmallInt;
  y : SmallInt;
end
```

Same as TPoint (203), only the X and Y ranges are limited to 2-byte integers instead of 4-byte integers.

Table 2.13: Enumeration values for type TShiftStateEnum

Value	Explanation
ssAlt	Alt key pressed
ssAltGr	Alt-GR key pressed.
ssCaps	Caps lock key pressed
ssCtrl	Ctrl key pressed
ssDouble	Double mouse click.
ssExtra1	Extra key 1
ssExtra2	Extra key 2
ssHyper	Hyper key pressed.
ssLeft	Left mouse button pressed.
ssMeta	Meta key pressed.
ssMiddle	Middle mouse button pressed.
ssNum	Num lock key pressed
ssQuad	Quadruple mouse click
ssRight	Right mouse button pressed.
ssScroll	Scroll lock key pressed
ssShift	Shift key pressed
ssSuper	Super key pressed.
ssTriple	Triple mouse click

Table 2.14: Enumeration values for type TStreamOwnership

Value	Explanation
soOwned	Stream is owned: it will be freed when the adapter is freed.
soReference	Stream is referenced only, it is not freed by the adapter

```
TStreamOwnership = (soReference, soOwned)
```

The ownership of a streamadapter determines what happens with the stream on which a TStreamAdapter (364) acts, when the adapter is freed.

```
TStreamProc = procedure(Stream: TStream) of object
```

Procedure type used in streaming.

```
TStringItem = record
  FString : String;
  FObject : TObject;
end
```

The TStringItem is used to store the string and object items in a TStringList (368) string list instance. It should never be used directly.

```
TStringItemList = Array[0..MaxListSize] of TStringItem
```

This declaration is provided for Delphi compatibility, it is not used in Free Pascal.



```
TStringListSortCompare = function(List: TStringList; Index1: Integer;
                                Index2: Integer) : Integer
```

Callback type used in stringlist compares.

```
TSynchronizeProcVar = procedure
```

Synchronize callback type

```
TThreadMethod = procedure of object
```

Procedure variable used when synchronizing threads.

```
TThreadPriority = (tpIdle, tpLowest, tpLower, tpNormal, tpHigher, tpHighest,
                  tpTimeCritical)
```

Table 2.15: Enumeration values for type TThreadPriority

Value	Explanation
tpHigher	Thread runs at high priority
tpHighest	Thread runs at highest possible priority.
tpIdle	Thread only runs when other processes are idle.
tpLower	Thread runs at a lower priority.
tpLowest	Thread runs at the lowest priority.
tpNormal	Thread runs at normal process priority.
tpTimeCritical	Thread runs at realtime priority.

Enumeration specifying the priority at which a thread runs.

```
TValueType = (vaNull, vaList, vaInt8, vaInt16, vaInt32, vaExtended, vaString,
              vaIdent, vaFalse, vaTrue, vaBinary, vaSet, vaLString, vaNil,
              vaCollection, vaSingle, vaCurrency, vaDate, vaWString, vaInt64,
              vaUTF8String, vaUString, vaQWord)
```

Enumerated type used to identify the kind of streamed property

```
TWriteMethodPropertyEvent = procedure(Writer: TWriter;
                                     Instance: TPersistent;
                                     PropInfo: PPropInfo;
                                     const MethodValue: TMethod;
                                     const DefMethodValue: TMethod;
                                     var Handled: Boolean) of object
```

TWriteMethodPropertyEvent is the prototype for the TWriter.OnWriteMethodProperty (405) event. Writer is the sender of the event, Instance is the instance that is being streamed. PropInfo is a pointer to the RTTI information for the property being written, and MethodValue is the value of the method that the property was set to. DefMethodCodeValue is set to the default value of the property (Nil or the parent value). Handled should be set to True if the handler set the property successfully.

```
TWriterProc = procedure(Writer: TWriter) of object
```

The TWriterProc writer procedure is a callback procedure which will be used by a TPersistent (338) descendent to write user properties from a stream during the streaming process. The Writer argument is the writer object which can be used write properties to the stream.

Table 2.16: Enumeration values for type TValueType

Value	Explanation
vaBinary	Binary data follows.
vaCollection	Collection follows
vaCurrency	Currency value follows
vaDate	Date value follows
vaExtended	Extended value.
vaFalse	Boolean <code>False</code> value.
vaIdent	Identifier.
vaInt16	Integer value, 16 bits long.
vaInt32	Integer value, 32 bits long.
vaInt64	Integer value, 64 bits long.
vaInt8	Integer value, 8 bits long.
vaList	Identifies the start of a list of values
vaLString	Ansistring data follows.
vaNil	Nil pointer.
vaNull	Empty value. Ends a list.
vaQWord	QWord (64-bit word) value
vaSet	Set data follows.
vaSingle	Single type follows.
vaString	String value.
vaTrue	Boolean <code>True</code> value.
vaUString	UnicodeString value
vaUTF8String	UTF8 encoded unicode string.
vaWString	Widestring value follows.

### 2.3.3 Variables

`AddDataModule` : `procedure(DataModule: TDataModule) of object`

`AddDataModule` can be set by an IDE or a streaming mechanism to receive notification when a new instance of a `TDataModule` (295) descendent is created.

`ApplicationHandleException` : `procedure(Sender: TObject) of object`

`ApplicationHandleException` can be set by an application object to handle any exceptions that may occur when a `TDataModule` (295) is created.

`ApplicationShowException` : `procedure(E: Exception) of object`

Unused.

`GlobalNameSpace` : `IReadWriteSync`

An interface protecting the global namespace. Used when reading/writing to the global namespace list during streaming of forms.

`MainThreadID` : `TThreadID`

ID of main thread. Unused at this point.

`RegisterComponentsProc : procedure(const Page: String;ComponentClasses: Array of TComponentClass)`

`RegisterComponentsProc` can be set by an IDE to be notified when new components are being registered. Application programmers should never have to set `RegisterComponentsProc`

`RegisterNoIconProc : procedure(ComponentClasses: Array of TComponentClass)`

`RegisterNoIconProc` can be set by an IDE to be notified when new components are being registered, and which do not need an Icon in the component palette. Application programmers should never have to set `RegisterComponentsProc`

`RemoveDataModule : procedure(DataModule: TDataModule) of object`

`RemoveDataModule` can be set by an IDE or a streaming mechanism to receive notification when an instance of a `TDataModule` (295) descendent is freed.

`WakeMainThread : TNotifyEvent = nil`

`WakeMainThread` is called by the `TThread.synchronize` (392) call. It should alert the main program thread that a thread is waiting for synchronization. The call is executed by the thread, and should therefore NOT synchronize the thread, but should somehow signal the main thread that a thread is waiting for synchronization. For example, by sending a message.

## 2.4 Procedures and functions

### 2.4.1 ActivateClassGroup

Synopsis: Activates a class group

Declaration: `function ActivateClassGroup(AClass: TPersistentClass) : TPersistentClass`

Visibility: default

Description: `ActivateClassGroup` activates the group of classes to which `AClass` belongs. The function returns the class that was last used to activate the class group.

The class registration and streaming mechanism allows to organize the classes in groups. This allows an IDE to form groups of classes, which can be enabled or disabled. It is not needed at Run-Time.

Errors: If `AClass` does not belong to a class group, an exception is raised.

See also: `StartClassGroup` (222), `GroupDescendentsWith` (214), `ClassGroupOf` (210)

### 2.4.2 BeginGlobalLoading

Synopsis: Not yet implemented

Declaration: `procedure BeginGlobalLoading`

Visibility: default

Description: Not yet implemented

### 2.4.3 BinToHex

Synopsis: Convert a binary buffer to a hexadecimal string

Declaration: `procedure BinToHex (BinValue: PChar; HexValue: PChar; BinBufSize: Integer)`

Visibility: default

Description: `BinToHex` converts the byte values in `BinValue` to a string consisting of 2-character hexadecimal strings in `HexValue`. `BufSize` specifies the length of `BinValue`, which means that `HexValue` must have size  $2 * \text{BufSize}$ .

For example a buffer containing the byte values 255 and 0 will be converted to FF00.

Errors: No length checking is done, so if an invalid size is specified, an exception may follow.

See also: `HexToBin` ([214](#))

### 2.4.4 Bounds

Synopsis: Returns a `TRect` structure with the bounding rect of the given location and size.

Declaration: `function Bounds (ALeft: Integer; ATop: Integer; AWidth: Integer; AHeight: Integer) : TRect`

Visibility: default

Description: `Bounds` returns a `TRect` ([204](#)) record with the given origin (`ALeft`, `ATop`) and dimensions (`AWidth`, `AHeight`) filled in. The bottom-right corner is calculated by adding `AWidth` to `ALeft` and `AHeight` to `ATop`. As a result, a rectangle with width/height set to 0 is exactly 1 pixel.

See also: `Rect` ([218](#))

### 2.4.5 CheckSynchronize

Synopsis: Check whether there are any synchronize calls in the synchronize queue.

Declaration: `function CheckSynchronize (timeout: LongInt) : Boolean`

Visibility: default

Description: `CheckSynchronize` should be called regularly by the main application thread to handle any `TThread.synchronize` ([392](#)) calls that may be waiting for execution by the main thread.

See also: `TThread.synchronize` ([392](#))

### 2.4.6 ClassGroupOf

Synopsis: Returns the class group to which an instance or class belongs

Declaration: `function ClassGroupOf (AClass: TPersistentClass) : TPersistentClass`  
`function ClassGroupOf (Instance: TPersistent) : TPersistentClass`

Visibility: default

Description: `ClassGroupOf` returns the class group to which `AClass` or `Instance` belongs.

Errors: The result is `Nil` if no matching class group is found.

See also: `StartClassGroup` ([222](#)), `ActivateClassGroup` ([209](#)), `GroupDescendentsWith` ([214](#))

### 2.4.7 CollectionsEqual

Synopsis: Returns True if two collections are equal.

Declaration: `function CollectionsEqual (C1: TCollection; C2: TCollection) : Boolean`  
`function CollectionsEqual (C1: TCollection; C2: TCollection;`  
`Owner1: TComponent; Owner2: TComponent)`  
`: Boolean`

Visibility: default

Description: `CollectionsEqual` is not yet implemented. It simply returns False

### 2.4.8 EndGlobalLoading

Synopsis: Not yet implemented.

Declaration: `procedure EndGlobalLoading`

Visibility: default

Description: Not yet implemented.

### 2.4.9 ExtractStrings

Synopsis: Split a string in different words.

Declaration: `function ExtractStrings (Separators: TSysCharSet; WhiteSpace: TSysCharSet;`  
`Content: PChar; Strings: TStrings) : Integer`

Visibility: default

Description: `ExtractStrings` splits `Content` (a null-terminated string) into words, and adds the words to the `Strings` stringlist. The words are separated by `Separators` and any characters in `whitespace` are stripped from the strings. The space and CR/LF characters are always considered whitespace.

Errors: No length checking is performed on `Content`. If no null-termination character is present, an access violation may occur. Likewise, if `Strings` is not valid, an access violation may occur.

### 2.4.10 FindClass

Synopsis: Returns the class pointer of a class with given name.

Declaration: `function FindClass (const AClassName: String) : TPersistentClass`

Visibility: default

Description: `FindClass` searches for the class named `ClassName` in the list of registered classes and returns a class pointer to the definition. If no class with the given name could be found, an exception is raised.

The `GetClass` (213) function does not raise an exception when it does not find the class, but returns a `Nil` pointer instead.

See also: `RegisterClass` (219), `GetClass` (213)

### 2.4.11 FindGlobalComponent

Synopsis: Callback used when a component must be found.

Declaration: `function FindGlobalComponent (const Name: String) : TComponent`

Visibility: default

Description: `FindGlobalComponent` is a callback of type `TFindGlobalComponent` (200). It can be set by the IDE when an unknown reference is found, to offer the user to redirect the link to a new component.

It is a callback used to find a component in a global scope. It is used when the streaming system needs to find a component which is not part of the component which is currently being streamed. It should return the component with name `Name`, or `Nil` if none is found.

See also: `TFindGlobalComponent` (200)

### 2.4.12 FindIdentToInt

Synopsis: Return the string to integer converter for an integer type

Declaration: `function FindIdentToInt (AIntegerType: Pointer) : TIdentToInt`

Visibility: default

Description: `FindIdentToInt` returns the handler that handles the conversion of a string representation to an integer that can be used in component streaming, when `IdentToInt` (214) is called.

Errors: `Nil` is returned if no handler is registered for the given type.

### 2.4.13 FindIntToIdent

Synopsis: Return the integer to string converter for an integer type

Declaration: `function FindIntToIdent (AIntegerType: Pointer) : TIntToIdent`

Visibility: default

Description: `FindIntToIdent` returns the handler that handles the conversion of an integer to a string representation that can be used in component streaming, when `IntToIdent` (215) is called.

Errors: `Nil` is returned if no handler is registered for the given type.

See also: `IntToIdent` (215), `TIntToIdent` (202), `FindIdentToInt` (212)

### 2.4.14 FindNestedComponent

Synopsis: Finds the component with name path starting at the indicated root component.

Declaration: `function FindNestedComponent (Root: TComponent; APath: String; CStyle: Boolean) : TComponent`

Visibility: default

Description: `FindNestedComponent` will descend through the list of owned components (starting at `Root`) and will return the component whose name path matches `NamePath`. As a path separator the characters `.` (dot), `-` (dash) and `>` (greater than) can be used

See also: `GlobalFixupReferences` (213)

### 2.4.15 GetClass

Synopsis: Returns the class pointer of a class with given name.

Declaration: `function GetClass(const AClassName: String) : TPersistentClass`

Visibility: default

Description: `GetClass` searches for the class named `ClassName` in the list of registered classes and returns a class pointer to the definition. If no class with the given name could be found, `Nil` is returned.

The `FindClass` (211) function will raise an exception if it does not find the class.

See also: `RegisterClass` (219), `GetClass` (213)

### 2.4.16 GetFixupInstanceNames

Synopsis: Returns the names of elements that need to be resolved for the `root` component, whose reference contains `ReferenceRootName`

Declaration: `procedure GetFixupInstanceNames(Root: TComponent;  
const ReferenceRootName: String;  
Names: TStrings)`

Visibility: default

Description: `GetFixupInstanceNames` examines the list of unresolved references and returns the names of classes that contain unresolved references to the `Root` component in the list `Names`. The list is not cleared prior to filling it.

See also: `GetFixupReferenceNames` (213), `GlobalFixupReferences` (213)

### 2.4.17 GetFixupReferenceNames

Synopsis: Returns the names of elements that need to be resolved for the `root` component.

Declaration: `procedure GetFixupReferenceNames(Root: TComponent; Names: TStrings)`

Visibility: default

Description: `GetFixupReferenceNames` examines the list of unresolved references and returns the names of properties that must be resolved for the component `Root` in the list `Names`. The list is not cleared prior to filling it.

See also: `GetFixupInstanceNames` (213), `GlobalFixupReferences` (213)

### 2.4.18 GlobalFixupReferences

Synopsis: Called to resolve unresolved references after forms are loaded.

Declaration: `procedure GlobalFixupReferences`

Visibility: default

Description: `GlobalFixupReferences` runs over the list of unresolved references and tries to resolve them. This routine should under normal circumstances not be called in an application programmer's code. It is called automatically by the streaming system after a component has been instantiated and its properties read from a stream. It will attempt to resolve references to other global components.

See also: `GetFixupReferenceNames` (213), `GetFixupInstanceNames` (213)

### 2.4.19 GroupDescendentsWith

Synopsis: Add class to the group of another class.

Declaration: `procedure GroupDescendentsWith(AClass: TPersistentClass;  
AClassGroup: TPersistentClass)`

Visibility: default

Description: `GroupDescendentsWith` adds `AClass` to the group that `AClassGroup` belongs to. If `AClassGroup` belongs to more than 1 group, then it is added to the group which contains the nearest ancestor.

The class registration and streaming mechanism allows to organize the classes in groups. This allows an IDE to form groups of classes, which can be enabled or disabled. It is not needed at Run-Time.

Errors:

See also: `StartClassGroup` (222), `ActivateClassGroup` (209), `ClassGroupOf` (210)

### 2.4.20 HexToBin

Synopsis: Convert a hexadecimal string to a binary buffer

Declaration: `function HexToBin(HexValue: PChar; BinValue: PChar; BinBufSize: Integer)  
: Integer`

Visibility: default

Description: `HexToBin` scans the hexadecimal string representation in `HexValue` and transforms every 2 character hexadecimal number to a byte and stores it in `BinValue`. The buffer size is the size of the binary buffer. Scanning will stop if the size of the binary buffer is reached or when an invalid character is encountered. The return value is the number of stored bytes.

Errors: No length checking is done, so if an invalid size is specified, an exception may follow.

See also: `BinToHex` (210)

### 2.4.21 IdentToInt

Synopsis: Looks up an integer value in a integer-to-identifier map list.

Declaration: `function IdentToInt(const Ident: String; var Int: LongInt;  
const Map: Array of TIdentMapEntry) : Boolean`

Visibility: default

Description: `IdentToInt` searches `Map` for an entry whose `Name` field matches `Ident` and returns the corresponding integer value in `Int`. If a match was found, the function returns `True`, otherwise, `False` is returned.

See also: `TIdentToInt` (201), `TIntToIdent` (202), `IntToIdent` (215), `TIdentMapEntry` (201)

### 2.4.22 InitComponentRes

Synopsis: Provided for Delphi compatibility only

Declaration: `function InitComponentRes(const ResName: String; Instance: TComponent)  
: Boolean`



Visibility: default

Description: This function is provided for Delphi compatibility. It always returns *false*.

See also: [ReadComponentRes \(217\)](#)

### 2.4.23 InitInheritedComponent

Synopsis: Initializes a component descending from `RootAncestor`

Declaration: `function InitInheritedComponent (Instance: TComponent;  
RootAncestor: TClass) : Boolean`

Visibility: default

Description: `InitInheritedComponent` should be called from a constructor to read properties of the component `Instance` from the streaming system. The `RootAncestor` class is the root class from which `Instance` is a descendent. This must be one of `TDatamodule`, `TCustomForm` or `TFrame`.

The function returns `True` if the properties were successfully read from a stream or `False` if some error occurred.

See also: [ReadComponentRes \(217\)](#), [ReadComponentResEx \(218\)](#), [ReadComponentResFile \(218\)](#)

### 2.4.24 IntToIdent

Synopsis: Looks up an identifier for an integer value in a identifier-to-integer map list.

Declaration: `function IntToIdent (Int: LongInt; var Ident: String;  
const Map: Array of TIdentMapEntry) : Boolean`

Visibility: default

Description: `IntToIdent` searches `Map` for an entry whose `Value` field matches `Int` and returns the corresponding identifier in `Ident`. If a match was found, the function returns `True`, otherwise, `False` is returned.

See also: [TIdentToInt \(201\)](#), [TintToIdent \(202\)](#), [IdentToInt \(214\)](#), [TIdentMapEntry \(201\)](#)

### 2.4.25 InvalidPoint

Synopsis: Check whether a point is invalid.

Declaration: `function InvalidPoint (X: Integer; Y: Integer) : Boolean  
function InvalidPoint (const At: TPoint) : Boolean  
function InvalidPoint (const At: TSmallPoint) : Boolean`

Visibility: default

Description: `InvalidPoint` returns `True` if the `X` and `Y` coordinates (of the `TPoint` or `TSmallPoint` records, if one of these versions is used) are `-1`.

See also: [TPoint \(203\)](#), [TSmallPoint \(205\)](#), [PointsEqual \(217\)](#)

### 2.4.26 LineStart

Synopsis: Finds the start of a line in `Buffer` before `BufPos`.

Declaration: `function LineStart (Buffer: PChar; BufPos: PChar) : PChar`

Visibility: default

Description: `LineStart` reversely scans `Buffer` starting at `BufPos` for a linefeed character. It returns a pointer at the linefeed character.

### 2.4.27 NotifyGlobalLoading

Synopsis: Not yet implemented.

Declaration: `procedure NotifyGlobalLoading`

Visibility: default

Description: Not yet implemented.

### 2.4.28 ObjectBinaryToText

Synopsis: Converts an object stream from a binary to a text format.

Declaration: `procedure ObjectBinaryToText (Input: TStream; Output: TStream;  
Encoding: TObjectTextEncoding)  
procedure ObjectBinaryToText (Input: TStream; Output: TStream)`

Visibility: default

Description: `ObjectBinaryToText` reads an object stream in binary format from `Input` and writes the object stream in text format to `Output`. No components are instantiated during the process, this is a pure conversion routine.

See also: `ObjectTextToBinary` ([216](#))

### 2.4.29 ObjectResourceToText

Synopsis: Converts an object stream from a (windows) resource to a text format.

Declaration: `procedure ObjectResourceToText (Input: TStream; Output: TStream)`

Visibility: default

Description: `ObjectResourceToText` reads the resource header from the `Input` stream and then passes the streams to `ObjectBinaryToText` ([216](#))

See also: `ObjectBinaryToText` ([216](#)), `ObjectTextToResource` ([217](#))

### 2.4.30 ObjectTextToBinary

Synopsis: Converts an object stream from a text to a binary format.

Declaration: `procedure ObjectTextToBinary (Input: TStream; Output: TStream)`

Visibility: default

Description: Converts an object stream from a text to a binary format.

### 2.4.31 ObjectTextToResource

**Synopsis:** Converts an object stream from a text to a (windows) resource format.

**Declaration:** `procedure ObjectTextToResource (Input: TStream; Output: TStream)`

**Visibility:** default

**Description:** `ObjectTextToResource` reads an object stream in text format from `Input` and writes a resource stream to `Output`.

Note that for the current implementation of this method in Free Pascal, the output stream should support positioning. (e.g. it should not be a pipe)

See also: `ObjectBinaryToText` (216), `ObjectResourceToText` (216)

### 2.4.32 Point

**Synopsis:** Returns a `TPoint` record with the given coordinates.

**Declaration:** `function Point (AX: Integer; AY: Integer) : TPoint`

**Visibility:** default

**Description:** `Point` returns a `TPoint` (203) record with the given coordinates `AX` and `AY` filled in.

See also: `TPoint` (203), `SmallPoint` (222), `Rect` (218), `Bounds` (210)

### 2.4.33 PointsEqual

**Synopsis:** Check whether two `TPoint` variables are equal.

**Declaration:** `function PointsEqual (const P1: TPoint; const P2: TPoint) : Boolean`  
`function PointsEqual (const P1: TSmallPoint; const P2: TSmallPoint)`  
`: Boolean`

**Visibility:** default

**Description:** `PointsEqual` compares the `P1` and `P2` points (of type `TPoint` (203) or `TSmallPoint` (205)) and returns `True` if the `X` and `Y` coordinates of the points are equal, or `False` otherwise.

See also: `TPoint` (203), `TSmallPoint` (205), `InvalidPoint` (215)

### 2.4.34 ReadComponentRes

**Synopsis:** Read component properties from a resource in the current module

**Declaration:** `function ReadComponentRes (const ResName: String; Instance: TComponent)`  
`: TComponent`

**Visibility:** default

**Description:** This function is provided for Delphi compatibility. It always returns `Nil`.

### 2.4.35 ReadComponentResEx

Synopsis: Read component properties from a resource in the specified module

Declaration: `function ReadComponentResEx (HInstance: THandle; const ResName: String)  
: TComponent`

Visibility: default

Description: This function is provided for Delphi compatibility. It always returns Nil.

### 2.4.36 ReadComponentResFile

Synopsis: Read component properties from a specified resource file

Declaration: `function ReadComponentResFile (const FileName: String;  
Instance: TComponent) : TComponent`

Visibility: default

Description: `ReadComponentResFile` starts reading properties for `Instance` from the file `FileName`. It creates a filestream from `FileName` and then calls the `TStream.ReadComponentRes` (358) method to read the state of the component from the stream.

See also: `TStream.ReadComponentRes` (358), `WriteComponentResFile` (223)

### 2.4.37 Rect

Synopsis: Returns a `TRect` record with the given coordinates.

Declaration: `function Rect (ALeft: Integer; ATop: Integer; ARight: Integer;  
ABottom: Integer) : TRect`

Visibility: default

Description: `Rect` returns a `TRect` (204) record with the given top-left (`ALeft`, `ATop`) and bottom-right (`ABottom`, `ARight`) corners filled in.

No checking is done to see whether the coordinates are valid.

See also: `TRect` (204), `Point` (217), `SmallPoint` (222), `Bounds` (210)

### 2.4.38 RedirectFixupReferences

Synopsis: Redirects references under the root object from `OldRootName` to `NewRootName`

Declaration: `procedure RedirectFixupReferences (Root: TComponent;  
const OldRootName: String;  
const NewRootName: String)`

Visibility: default

Description: `RedirectFixupReferences` examines the list of unresolved references and replaces references to a root object named `OldRootName` with references to root object `NewRootName`.

An application programmer should never need to call `RedirectFixupReferences`. This function can be used by an IDE to support redirection of broken component links.

See also: `RemoveFixupReferences` (221)

### 2.4.39 RegisterClass

Synopsis: Registers a class with the streaming system.

Declaration: `procedure RegisterClass (AClass: TPersistentClass)`

Visibility: default

Description: `RegisterClass` registers the class `AClass` in the streaming system. After the class has been registered, it can be read from a stream when a reference to this class is encountered.

See also: `RegisterClasses` (219), `RegisterClassAlias` (219), `RegisterComponents` (219), `UnregisterClass` (222)

### 2.4.40 RegisterClassAlias

Synopsis: Registers a class alias with the streaming system.

Declaration: `procedure RegisterClassAlias (AClass: TPersistentClass;  
const Alias: String)`

Visibility: default

Description: `RegisterClassAlias` registers a class alias in the streaming system. If a reference to a class `Alias` is encountered in a stream, then an instance of the class `AClass` will be created instead by the streaming code.

See also: `RegisterClass` (219), `RegisterClasses` (219), `RegisterComponents` (219), `UnregisterClass` (222)

### 2.4.41 RegisterClasses

Synopsis: Registers multiple classes with the streaming system.

Declaration: `procedure RegisterClasses (AClasses: Array of TPersistentClass)`

Visibility: default

Description: `RegisterClasses` registers the specified classes `AClass` in the streaming system. After the classes have been registered, they can be read from a stream when a reference to this class is encountered.

See also: `RegisterClass` (219), `RegisterClassAlias` (219), `RegisterComponents` (219), `UnregisterClass` (222)

### 2.4.42 RegisterComponents

Synopsis: Registers components for the component palette.

Declaration: `procedure RegisterComponents (const Page: String;  
ComponentClasses: Array of TComponentClass)`

Visibility: default

Description: `RegisterComponents` registers the component on the appropriate component page. The component pages can be used by an IDE to display the known components so an application programmer may pick and use the components in his programs.

`Registercomponents` inserts the component class in the correct component page. If the `RegisterComponentsProc` procedure is set, this is called as well. Note that this behaviour is different from Delphi's behaviour where an exception will be raised if the procedural variable is not set.

See also: `RegisterClass` (219), `RegisterNoIcon` (221)

### 2.4.43 RegisterFindGlobalComponentProc

Synopsis: Register a component searching handler

Declaration: `procedure RegisterFindGlobalComponentProc`  
`(AFindGlobalComponent: TFindGlobalComponent`

Visibility: default

Description: `RegisterFindGlobalComponentProc` registers a global component search callback `AFindGlobalComponent`. When `FindGlobalComponent` (212) is called, then this callback will be used to search for the component.

Errors: None.

See also: `FindGlobalComponent` (212), `UnRegisterFindGlobalComponentProc` (222)

### 2.4.44 RegisterInitComponentHandler

Synopsis: Register a component initialization handler

Declaration: `procedure RegisterInitComponentHandler(ComponentClass: TComponentClass;`  
`Handler: TInitComponentHandler)`

Visibility: default

Description: `RegisterInitComponentHandler` registers a component initialization handler `Handler` for the component `ComponentClass`. This handler will be used to initialize descendents of `ComponentClass` in the `InitInheritedComponent` (215) call.

See also: `InitInheritedComponent` (215), `TInitComponentHandler` (201)

### 2.4.45 RegisterIntegerConsts

Synopsis: Registers some integer-to-identifier mappings.

Declaration: `procedure RegisterIntegerConsts(IntegerType: Pointer;`  
`IdentToIntFn: TIdentToInt;`  
`IntToIdentFn: TIntToIdent)`

Visibility: default

Description: `RegisterIntegerConsts` registers a pair of callbacks to be used when an integer of type `IntegerType` must be mapped to an identifier (using `IntToIdentFn`) or when an identifier must be mapped to an integer (using `IdentToIntFn`).

Component programmers can use `RegisterIntegerConsts` to associate a series of identifier strings with integer values for a property. A necessary condition is that the property should have a separate type declared using the `type integer` syntax. If a type of integer is defined in this way, an IDE can show symbolic names for the values of these properties.

The `IntegerType` should be a pointer to the type information of the integer type. The `IntToIdentFn` and `IdentToIntFn` are two callbacks that will be used when converting between the identifier and integer value and vice versa. The functions `IdentToInt` (214) and `IntToIdent` (215) can be used to implement these callback functions.

See also: `TIdentToInt` (201), `TIntToIdent` (202), `IdentToInt` (214), `IntToIdent` (215)

### 2.4.46 RegisterNoIcon

Synopsis: Registers components that have no icon on the component palette.

Declaration: `procedure RegisterNoIcon(ComponentClasses: Array of TComponentClass)`

Visibility: default

Description: `RegisterNoIcon` performs the same function as `RegisterComponents` (219) except that it calls `RegisterNoIconProc` (209) instead of `RegisterComponentsProc` (209)

See also: `RegisterNoIconProc` (209), `RegisterComponents` (219)

### 2.4.47 RegisterNonActiveX

Synopsis: Register non-activex component.

Declaration: `procedure RegisterNonActiveX(ComponentClasses: Array of TComponentClass;  
AxRegType: TActiveXRegType)`

Visibility: default

Description: Not yet implemented in Free Pascal

### 2.4.48 RemoveFixupReferences

Synopsis: Removes references to rootname from the fixup list.

Declaration: `procedure RemoveFixupReferences(Root: TComponent; const RootName: String)`

Visibility: default

Description: `RemoveFixupReferences` examines the list of unresolved references and removes references to a root object pointing at `Root` or a root component named `RootName`.

An application programmer should never need to call `RemoveFixupReferences`. This function can be used by an IDE to support removal of broken component links.

See also: `RedirectFixupReferences` (218)

### 2.4.49 RemoveFixups

Synopsis: Removes `Instance` from the fixup list.

Declaration: `procedure RemoveFixups(Instance: TPersistent)`

Visibility: default

Description: `RemoveFixups` removes all entries for component `Instance` from the list of unresolved references.

See also: `RedirectFixupReferences` (218), `RemoveFixupReferences` (221)

### 2.4.50 SmallPoint

Synopsis: Returns a `TSmallPoint` record with the given coordinates.

Declaration: `function SmallPoint (AX: SmallInt; AY: SmallInt) : TSmallPoint`

Visibility: default

Description: `SmallPoint` returns a `TSmallPoint` (205) record with the given coordinates `AX` and `AY` filled in.

See also: `TSmallPoint` (205), `Point` (217), `Rect` (218), `Bounds` (210)

### 2.4.51 StartClassGroup

Synopsis: Start new class group.

Declaration: `procedure StartClassGroup (AClass: TPersistentClass)`

Visibility: default

Description: `StartClassGroup` starts a new class group and adds `AClass` to it.

The class registration and streaming mechanism allows to organize the classes in groups. This allows an IDE to form groups of classes, which can be enabled or disabled. It is not needed at Run-Time.

See also: `GroupDescendentsWith` (214), `ActivateClassGroup` (209), `ClassGroupOf` (210)

### 2.4.52 UnRegisterClass

Synopsis: Unregisters a class from the streaming system.

Declaration: `procedure UnRegisterClass (AClass: TPersistentClass)`

Visibility: default

Description: `UnRegisterClass` removes the class `AClass` from the class definitions in the streaming system.

See also: `UnRegisterClasses` (222), `UnRegisterModuleClasses` (223), `RegisterClass` (219)

### 2.4.53 UnRegisterClasses

Synopsis: Unregisters multiple classes from the streaming system.

Declaration: `procedure UnRegisterClasses (AClasses: Array of TPersistentClass)`

Visibility: default

Description: `UnRegisterClasses` removes the classes in `AClasses` from the class definitions in the streaming system.

### 2.4.54 UnregisterFindGlobalComponentProc

Synopsis: Remove a previously registered component searching handler.

Declaration: `procedure UnregisterFindGlobalComponentProc`  
`(AFindGlobalComponent: TFindGlobalComponent)`

Visibility: default



**Description:** `UnRegisterFindGlobalComponentProc` unregisters the previously registered global component search callback `AFindGlobalComponent`. After this call, when `FindGlobalComponent` (212) is called, then this callback will be no longer be used to search for the component.

**Errors:** None.

**See also:** `FindGlobalComponent` (212), `RegisterFindGlobalComponentProc` (220)

### 2.4.55 UnRegisterModuleClasses

**Synopsis:** Unregisters classes registered by module.

**Declaration:** `procedure UnRegisterModuleClasses(Module: HMODULE)`

**Visibility:** default

**Description:** `UnRegisterModuleClasses` unregisters all classes which reside in the module `Module`. For each registered class, the definition pointer is checked to see whether it resides in the module, and if it does, the definition is removed.

**See also:** `UnRegisterClass` (222), `UnRegisterClasses` (222), `RegisterClasses` (219)

### 2.4.56 WriteComponentResFile

**Synopsis:** Write component properties to a specified resource file

**Declaration:** `procedure WriteComponentResFile(const FileName: String;  
Instance: TComponent)`

**Visibility:** default

**Description:** `WriteComponentResFile` starts writing properties of `Instance` to the file `FileName`. It creates a filestream from `FileName` and then calls `TStream.WriteComponentRes` (359) method to write the state of the component to the stream.

**See also:** `TStream.WriteComponentRes` (359), `ReadComponentResFile` (218)

## 2.5 EBitsError

### 2.5.1 Description

When an index of a bit in a `TBits` (264) is out of the valid range (0 to `Count-1`) then a `EBitsError` exception is raised.

## 2.6 EClassNotFound

### 2.6.1 Description

When the streaming system needs to create a component, it looks for the class pointer (VMT) in the list of registered classes by its name. If this name is not found, then an `EClassNotFound` is raised.

## 2.7 EComponentError

### 2.7.1 Description

When an error occurs during the registration of a component, or when naming a component, then a `EComponentError` is raised. Possible causes are:

1. An name with an illegal character was assigned to a component.
2. A component with the same name and owner already exists.
3. The component registration system isn't set up properly.

## 2.8 ECreateError

### 2.8.1 Description

When the operating system reports an error during creation of a new file in the Filestream Constructor (301), a `ECreateError` is raised.

## 2.9 EFilerError

### 2.9.1 Description

This class serves as an ancestor class for exceptions that are raised when an error occurs during component streaming. A `EFilerError` exception is raised when a class is registered twice.

## 2.10 EOpenError

### 2.10.1 Description

When the operating system reports an error during the opening of a file in the Filestream Constructor (301), a `EOpenError` is raised.

## 2.11 EInvalidImage

### 2.11.1 Description

This exception is not used by Free Pascal but is provided for Delphi compatibility.

## 2.12 EInvalidOperation

### 2.12.1 Description

This exception is not used in Free Pascal, it is defined for Delphi compatibility purposes only.

## 2.13 EListError

### 2.13.1 Description

If an error occurs in one of the `TList` (319) or `TStrings` (373) methods, then a `EListError` exception is raised. This can occur in one of the following cases:

1. There is not enough memory to expand the list.
2. The list tried to grow beyond its maximal capacity.
3. An attempt was made to reduce the capacity of the list below the current element count.
4. An attempt was made to set the list count to a negative value.
5. A non-existent element of the list was referenced. (i.e. the list index was out of bounds)
6. An attempt was made to move an item to a position outside the list's bounds.

## 2.14 EMethodNotFound

### 2.14.1 Description

This exception is no longer used in the streaming system. This error is replaced by a `EReadError` (225).

## 2.15 EOutOfResources

### 2.15.1 Description

This exception is not used in Free Pascal, it is defined for Delphi compatibility purposes only.

## 2.16 EParserError

### 2.16.1 Description

When an error occurs during the parsing of a stream, an `EParserError` is raised. Usually this indicates that an invalid token was found on the input stream, or the token read from the stream wasn't the expected token.

## 2.17 EReadError

### 2.17.1 Description

If an error occurs when reading from a stream, a `EReadError` exception is raised. Possible causes for this are:

1. Not enough data is available when reading from a stream
2. The stream containing a component's data contains invalid data. this will occur only when reading a component from a stream.

## 2.18 EResNotFound

### 2.18.1 Description

This exception is not used by Free Pascal but is provided for Delphi compatibility.

## 2.19 EStreamError

### 2.19.1 Description

An `EStreamError` is raised when an error occurs during reading from or writing to a stream:  
Possible causes are

1. Not enough data is available in the stream.
2. Trying to seek beyond the beginning or end of the stream.
3. Trying to set the capacity of a memory stream and no memory is available.
4. Trying to write to a read-only stream, such as a resource stream.
5. Trying to read from a write-only stream.

## 2.20 EStringListError

### 2.20.1 Description

When an error occurs in one of the methods of `TStrings` ([373](#)) then an `EStringListError` is raised. This can have one of the following causes:

1. There is not enough memory to expand the list.
2. The list tried to grow beyond its maximal capacity.
3. A non-existent element of the list was referenced. (i.e. the list index was out of bounds)
4. An attempt was made to add a duplicate entry to a `TStringList` ([368](#)) when `TStringList.AllowDuplicates` ([368](#)) is `False`.

## 2.21 EThread

### 2.21.1 Description

Thread error exception.

## 2.22 EThreadDestroyCalled

### 2.22.1 Description

Exception raised when a thread is destroyed illegally.

## 2.23 EWriteError

### 2.23.1 Description

If an error occurs when writing to a stream, a `EWriteError` exception is raised. Possible causes for this are:

1. The stream doesn't allow writing.
2. An error occurred when writing a property to a stream.

## 2.24 IDesignerNotify

### 2.24.1 Description

`IDesignerNotify` is an interface that can be used to communicate changes to a designer mechanism. It offers functionality for detecting changes, and notifications when the component is destroyed.

### 2.24.2 Method overview

Page	Property	Description
<a href="#">227</a>	Modified	Notify that the component is modified.
<a href="#">227</a>	Notification	Notification of owner changes

### 2.24.3 IDesignerNotify.Modified

Synopsis: Notify that the component is modified.

Declaration: `procedure Modified`

Visibility: default

Description: `Modified` can be used to notify a designer of changes, indicating that components should be streamed.

### 2.24.4 IDesignerNotify.Notification

Synopsis: Notification of owner changes

Declaration: `procedure Notification(AnObject: TPersistent; Operation: TOperation)`

Visibility: default

Description: `Notification` is the interface counterpart of `TComponent.Notification` ([281](#)) which is used to communicate adds to the components.

See also: `TComponent.Notification` ([281](#))

## 2.25 IInterfaceComponentReference

### 2.25.1 Description

`IInterfaceComponentReference` is an interface to return the component that implements a given interface. It is implemented by `TComponent` ([281](#)).

### 2.25.2 Method overview

Page	Property	Description
<a href="#">228</a>	GetComponent	Return component instance

### 2.25.3 IInterfaceComponentReference.GetComponent

Synopsis: Return component instance

Declaration: `function GetComponent : TComponent`

Visibility: default

Description: `GetComponent` returns the component instance.

Errors: None.

See also: `TComponent` ([281](#))

## 2.26 IInterfaceList

### 2.26.1 Description

`IInterfaceList` is an interface for maintaining a list of interfaces, strongly resembling the standard `TList` ([319](#)) class. It offers the same list of public methods as `TList`, with the exception that it uses interfaces instead of pointers.

All interfaces in the list should descend from `IUnknown`.

More detailed descriptions of how the various methods behave can be found in the `TList` reference.

### 2.26.2 Method overview

Page	Property	Description
<a href="#">231</a>	Add	Add an interface to the list
<a href="#">230</a>	Clear	Clear the list
<a href="#">230</a>	Delete	Remove an interface from the list
<a href="#">231</a>	Exchange	Exchange 2 interfaces in the list
<a href="#">231</a>	First	Return the first non-empty interface in the list.
<a href="#">229</a>	Get	Retrieve an interface pointer from the list.
<a href="#">229</a>	GetCapacity	Return the capacity of the list.
<a href="#">229</a>	GetCount	Return the current number of elements in the list.
<a href="#">231</a>	IndexOf	Return the index of an interface.
<a href="#">231</a>	Insert	Insert an interface in the list.
<a href="#">232</a>	Last	Returns the last non-nil interface in the list.
<a href="#">232</a>	Lock	Lock the list
<a href="#">229</a>	Put	Write an item to the list
<a href="#">232</a>	Remove	Remove an interface from the list
<a href="#">230</a>	SetCapacity	Set the capacity of the list
<a href="#">230</a>	SetCount	Set the number of items in the list
<a href="#">232</a>	Unlock	Unlock the list.

### 2.26.3 Property overview

Page	Property	Access	Description
<a href="#">232</a>	Capacity	rw	Capacity of the list
<a href="#">233</a>	Count	rw	Current number of elements in the list.
<a href="#">233</a>	Items	rw	Provides Index-based, sequential, access to the interfaces in the list.

### 2.26.4 IInterfaceList.Get

Synopsis: Retrieve an interface pointer from the list.

Declaration: `function Get(i: Integer) : IUnknown`

Visibility: default

Description: `Get` returns the interface pointer at position `i` in the list. It serves as the `Read` method for the `Items` ([233](#)) property.

See also: `IInterfaceList.Items` ([233](#)), `TList.Items` ([326](#))

### 2.26.5 IInterfaceList.GetCapacity

Synopsis: Return the capacity of the list.

Declaration: `function GetCapacity : Integer`

Visibility: default

Description: `GetCapacity` returns the current capacity of the list. It serves as the `Read` method for the `Capacity` ([232](#)) property.

See also: `IInterfaceList.Capacity` ([232](#)), `TList.Capacity` ([325](#))

### 2.26.6 IInterfaceList.GetCount

Synopsis: Return the current number of elements in the list.

Declaration: `function GetCount : Integer`

Visibility: default

Description: It serves as the `Read` method for the `Count` ([233](#)) property.

See also: `IInterfaceList.Count` ([233](#)), `TList.Count` ([326](#))

### 2.26.7 IInterfaceList.Put

Synopsis: Write an item to the list

Declaration: `procedure Put(i: Integer; item: IUnknown)`

Visibility: default

Description: `Put` writes the interface `Item` at position `I` in the list. It servers as the `Write` method for the `Items` ([233](#)) property.

See also: `IInterfaceList.Items` ([233](#)), `TList.Items` ([326](#))

### 2.26.8 IList.SetCapacity

Synopsis: Set the capacity of the list

Declaration: `procedure SetCapacity(NewCapacity: Integer)`

Visibility: default

Description: `SetCapacity` sets the capacity of the list to `NewCapacity`. It serves as the `Write` method for the `Capacity` (232) property.

See also: `IInterfaceList.Capacity` (232), `TList.Capacity` (325)

### 2.26.9 IList.SetCount

Synopsis: Set the number of items in the list

Declaration: `procedure SetCount(NewCount: Integer)`

Visibility: default

Description: `SetCount` sets the count of the list to `NewCount`. It serves as the `Write` method for the `Capacity` (232)

See also: `IInterfaceList.Count` (233), `TList.Count` (326)

### 2.26.10 IList.Clear

Synopsis: Clear the list

Declaration: `procedure Clear`

Visibility: default

Description: `Clear` removes all interfaces from the list. All interfaces in the list will be cleared (i.e. their reference count will decrease with 1)

See also: `TList.Clear` (321)

### 2.26.11 IList.Delete

Synopsis: Remove an interface from the list

Declaration: `procedure Delete(index: Integer)`

Visibility: default

Description: `Delete` removes the interface at position `Index` from the list. It does this by explicitly clearing the interface and then removing the slot.

See also: `TList.Clear` (321), `IInterfaceList.Add` (231), `IInterfaceList.Delete` (230), `IInterfaceList.Insert` (231)



### 2.26.12 **IInterfaceList.Exchange**

Synopsis: Exchange 2 interfaces in the list

Declaration: `procedure Exchange(index1: Integer; index2: Integer)`

Visibility: default

Description: `Exchange` exchanges 2 interfaces in the list at locations `index1` and `Index2`.

See also: `TList.Exchange` (322), `IInterfaceList.Add` (231), `IInterfaceList.Delete` (230), `IInterfaceList.Insert` (231)

### 2.26.13 **IInterfaceList.First**

Synopsis: Return the first non-empty interface in the list.

Declaration: `function First : IUnknown`

Visibility: default

Description: `First` returns the first non-empty interface in the list.

See also: `TList.First` (323), `IInterfaceList.IndexOf` (231), `IInterfaceList.Last` (232)

### 2.26.14 **IInterfaceList.IndexOf**

Synopsis: Return the index of an interface.

Declaration: `function IndexOf(item: IUnknown) : Integer`

Visibility: default

Description: `IndexOf` returns the location in the list of the interface `Item`. If there is no such interface in the list, then -1 is returned.

See also: `TList.IndexOf` (323), `IInterfaceList.First` (231), `IInterfaceList.Last` (232)

### 2.26.15 **IInterfaceList.Add**

Synopsis: Add an interface to the list

Declaration: `function Add(item: IUnknown) : Integer`

Visibility: default

Description: `Add` adds the interface `Item` to the list, and returns the position at which it has been added.

See also: `TList.Add` (321), `IInterfaceList.Insert` (231), `IInterfaceList.Delete` (230)

### 2.26.16 **IInterfaceList.Insert**

Synopsis: Insert an interface in the list.

Declaration: `procedure Insert(i: Integer; item: IUnknown)`

Visibility: default

Description: `Insert` inserts the interface `Item` in the list, at position `I`, shifting all items one position.

See also: `TList.Insert` (323), `IInterfaceList.Add` (231), `IInterfaceList.Delete` (230)

### 2.26.17 **IInterfaceList.Last**

Synopsis: Returns the last non-nil interface in the list.

Declaration: `function Last : IUnknown`

Visibility: default

Description: `Last` returns the last non-empty interface in the list.

See also: `TList.Last` ([324](#)), `IInterfaceList.First` ([231](#)), `IInterfaceList.IndexOf` ([231](#))

### 2.26.18 **IInterfaceList.Remove**

Synopsis: Remove an interface from the list

Declaration: `function Remove(item: IUnknown) : Integer`

Visibility: default

Description: `Remove` searches for the first occurrence of `Item` in the list and deletes it.

See also: `TList.Remove` ([324](#)), `IInterfaceList.Delete` ([230](#)), `IInterfaceList.IndexOf` ([231](#))

### 2.26.19 **IInterfaceList.Lock**

Synopsis: Lock the list

Declaration: `procedure Lock`

Visibility: default

Description: `Lock` locks the list. After a call to lock, the object list can only be accessed by the current thread, untill `UnLock` ([232](#)) is called.

See also: `TList.Lock` ([319](#)), `IInterfaceList.Unlock` ([232](#))

### 2.26.20 **IInterfaceList.Unlock**

Synopsis: Unlock the list.

Declaration: `procedure Unlock`

Visibility: default

Description: `Unlock` unlocks a locked list. After a call to `UnLock`, other threads are again able to access the list.

See also: `TList.UnLock` ([319](#)), `IInterfaceList.Lock` ([232](#))

### 2.26.21 **IInterfaceList.Capacity**

Synopsis: Capacity of the list

Declaration: `Property Capacity : Integer`

Visibility: default

Access: Read,Write

**Description:** `Capacity` is the maximum number of elements the list can hold without needing to reallocate memory for the list. It can be set to improve speed when adding a lot of items to the list.

See also: `TList.Capacity` ([325](#)), `IInterfaceList.Count` ([233](#))

## 2.26.22 IInterfaceList.Count

**Synopsis:** Current number of elements in the list.

**Declaration:** `Property Count : Integer`

**Visibility:** default

**Access:** Read,Write

**Description:** `Count` is the current number of elements in the list. Setting it to a larger number will allocate empty slots. Setting it to a smaller number will clear any interfaces that fall outside the new border.

See also: `IInterfaceList.Capacity` ([232](#)), `TList.Count` ([326](#))

## 2.26.23 IInterfaceList.Items

**Synopsis:** Provides Index-based, sequential, access to the interfaces in the list.

**Declaration:** `Property Items[index: Integer]: IUnknown; default`

**Visibility:** default

**Access:** Read,Write

**Description:** `Items` is the default property of the interface list and provides index-based array access to the interfaces in the list. Allowed values for `Index` include 0 to `Count-1`

See also: `IInterfaceList.Count` ([233](#)), `TList.Items` ([326](#))

## 2.27 IStreamPersist

### 2.27.1 Description

`IStreamPersist` defines an interface for object persistence streaming to a stream. Any class implementing this interface is expected to be able to save or load it's state from or to a stream.

### 2.27.2 Method overview

Page	Property	Description
<a href="#">233</a>	<code>LoadFromStream</code>	Load persistent data from stream.
<a href="#">234</a>	<code>SaveToStream</code>	Save persistent data to stream.

### 2.27.3 IStreamPersist.LoadFromStream

**Synopsis:** Load persistent data from stream.

**Declaration:** `procedure LoadFromStream(Stream: TStream)`

**Visibility:** default

**Description:** `LoadFromStream` is the method called when the object should load it's state from the stream `stream`. It should be able to read the data which was written using the `SaveToStream` method.

See also: [TPersistent \(338\)](#), [TComponent \(281\)](#), [TStream \(355\)](#), [IStreamPersist.SaveToStream \(234\)](#)

## 2.27.4 IStreamPersist.SaveToStream

**Synopsis:** Save persistent data to stream.

**Declaration:** `procedure SaveToStream(Stream: TStream)`

**Visibility:** default

**Description:** `SaveFromStream` is the method called when the object should load it's state from the stream `stream`. The data written by this method should be readable by the `LoadFromStream` method.

See also: [TPersistent \(338\)](#), [TComponent \(281\)](#), [TStream \(355\)](#), [IStreamPersist.LoadFromStream \(233\)](#)

## 2.28 IStringsAdapter

### 2.28.1 Description

Is not yet supported in Free Pascal.

### 2.28.2 Method overview

Page	Property	Description
<a href="#">234</a>	<code>ReferenceStrings</code>	Add a reference to the indicated strings.
<a href="#">234</a>	<code>ReleaseStrings</code>	Release the reference to the strings.

### 2.28.3 IStringsAdapter.ReferenceStrings

**Synopsis:** Add a reference to the indicated strings.

**Declaration:** `procedure ReferenceStrings(S: TStrings)`

**Visibility:** default

### 2.28.4 IStringsAdapter.ReleaseStrings

**Synopsis:** Release the reference to the strings.

**Declaration:** `procedure ReleaseStrings`

**Visibility:** default

## 2.29 TAbstractObjectReader

### 2.29.1 Description

The Free Pascal streaming mechanism, while compatible with Delphi's mechanism, differs from it in the sense that the streaming mechanism uses a driver class when streaming components. The

`TAbstractObjectReader` class is the base driver class for reading property values from streams. It consists entirely of abstract methods, which must be implemented by descendent classes.

Different streaming mechanisms can be implemented by making a descendent from `TAbstractObjectReader`. The `TBinaryObjectReader` (253) class is such a descendent class, which streams data in binary (Delphi compatible) format.

All methods described in this class, mustbe implemented by descendent classes.

### 2.29.2 Method overview

Page	Property	Description
236	<code>BeginComponent</code>	Marks the reading of a new component.
236	<code>BeginProperty</code>	Marks the reading of a property value.
236	<code>BeginRootComponent</code>	Starts the reading of the root component.
235	<code>NextValue</code>	Returns the type of the next value in the stream.
237	<code>Read</code>	Read raw data from stream
237	<code>ReadBinary</code>	Read binary data from the stream.
238	<code>ReadCurrency</code>	Read a currency value from the stream.
238	<code>ReadDate</code>	Read a date value from the stream.
237	<code>ReadFloat</code>	Read a float value from the stream.
238	<code>ReadIdent</code>	Read an identifier from the stream.
239	<code>ReadInt16</code>	Read a 16-bit integer from the stream.
240	<code>ReadInt32</code>	Read a 32-bit integer from the stream.
240	<code>ReadInt64</code>	Read a 64-bit integer from the stream.
239	<code>ReadInt8</code>	Read an 8-bit integer from the stream.
240	<code>ReadSet</code>	Reads a set from the stream.
237	<code>ReadSingle</code>	Read a single (real-type) value from the stream.
241	<code>ReadStr</code>	Read a shortstring from the stream
241	<code>ReadString</code>	Read a string of type <code>StringType</code> from the stream.
241	<code>ReadUnicodeString</code>	Read a unicode string value
235	<code>ReadValue</code>	Reads the type of the next value.
241	<code>ReadWideString</code>	Read a widestring value from the stream.
242	<code>SkipComponent</code>	Skip till the end of the component.
242	<code>SkipValue</code>	Skip the current value.

### 2.29.3 TAbstractObjectReader.NextValue

Synopsis: Returns the type of the next value in the stream.

Declaration: `function NextValue : TValueType; Virtual; Abstract`

Visibility: `public`

Description: This function should return the type of the next value in the stream, but should not read the actual value, i.e. the stream position should not be altered by this method. This is used to 'peek' in the stream what value is next.

See also: `TAbstractObjectReader.ReadValue` (235)

### 2.29.4 TAbstractObjectReader.ReadValue

Synopsis: Reads the type of the next value.

Declaration: `function ReadValue : TValueType; Virtual; Abstract`

Visibility: public

Description: This function returns the type of the next value in the stream and reads it. i.e. after the call to this method, the stream is positioned to read the value of the type returned by this function.

See also: `TAbstractObjectReader.ReadValue` ([235](#))

### 2.29.5 `TAbstractObjectReader.BeginRootComponent`

Synopsis: Starts the reading of the root component.

Declaration: `procedure BeginRootComponent; Virtual; Abstract`

Visibility: public

Description: This function can be used to initialize the driver class for reading a component. It is called once at the beginning of the read process, and is immediately followed by a call to `BeginComponent` ([236](#)).

See also: `TAbstractObjectReader.BeginComponent` ([236](#))

### 2.29.6 `TAbstractObjectReader.BeginComponent`

Synopsis: Marks the reading of a new component.

Declaration: `procedure BeginComponent (var Flags: TFileFlags; var AChildPos: Integer;  
var CompClassName: String; var CompName: String)  
; Virtual; Abstract`

Visibility: public

Description: This method is called when the streaming process wants to start reading a new component.

Descendent classes should override this method to read the start of a component new component definition and return the needed arguments. `Flags` should be filled with any flags that were found at the component definition, as well as `AChildPos`. The `CompClassName` should be filled with the class name of the streamed component, and the `CompName` argument should be filled with the name of the component.

`AChildPos` is used to change the ordering in which components appear below their parent component when streaming descendent forms.

See also: `TAbstractObjectReader.BeginRootComponent` ([236](#)), `TAbstractObjectReader.BeginProperty` ([236](#))

### 2.29.7 `TAbstractObjectReader.BeginProperty`

Synopsis: Marks the reading of a property value.

Declaration: `function BeginProperty : String; Virtual; Abstract`

Visibility: public

Description: `BeginProperty` is called by the streaming system when it wants to read a new property. The return value of the function is the name of the property which can be read from the stream.

See also: `TAbstractObjectReader.BeginComponent` ([236](#))

### 2.29.8 TAbstractObjectReader.Read

Synopsis: Read raw data from stream

Declaration: `procedure Read(var Buf; Count: LongInt); Virtual; Abstract`

Visibility: public

Description: `Read` is introduced for Delphi compatibility to read raw data from the component stream. This should not be used in production code as it will totally mess up the streaming.

See also: `TBinaryObjectReader.Read` (256), `TReader.Read` (344)

### 2.29.9 TAbstractObjectReader.ReadBinary

Synopsis: Read binary data from the stream.

Declaration: `procedure ReadBinary(const DestData: TMemoryStream); Virtual; Abstract`

Visibility: public

Description: `ReadBinary` is called when binary data should be read from the stream (i.e. after `ReadValue` (235) returned a valuetype of `vaBinary`). The data should be stored in the `DestData` memory stream by descendent classes.

See also: `TAbstractObjectReader.ReadFloat` (237), `TAbstractObjectReader.ReadDate` (238), `TAbstractObjectReader.ReadSingle` (237), `TAbstractObjectReader.ReadIdent` (238), `TAbstractObjectReader.ReadInt8` (239), `TAbstractObjectReader.ReadInt16` (239), `TAbstractObjectReader.ReadInt32` (240), `TAbstractObjectReader.ReadInt64` (240), `TabstractObjectReader.ReadSet` (240), `TabstractObjectReader.ReadStr` (241), `TabstractObjectReader.ReadString` (241)

### 2.29.10 TAbstractObjectReader.ReadFloat

Synopsis: Read a float value from the stream.

Declaration: `function ReadFloat : Extended; Virtual; Abstract`

Visibility: public

Description: `ReadFloat` is called by the streaming system when it wants to read a float from the stream (i.e. after `ReadValue` (235) returned a valuetype of `vaExtended`). The return value should be the value of the float.

See also: `TAbstractObjectReader.ReadFloat` (237), `TAbstractObjectReader.ReadDate` (238), `TAbstractObjectReader.ReadSingle` (237), `TAbstractObjectReader.ReadIdent` (238), `TAbstractObjectReader.ReadInt8` (239), `TAbstractObjectReader.ReadInt16` (239), `TAbstractObjectReader.ReadInt32` (240), `TAbstractObjectReader.ReadInt64` (240), `TabstractObjectReader.ReadSet` (240), `TabstractObjectReader.ReadStr` (241), `TabstractObjectReader.ReadString` (241)

### 2.29.11 TAbstractObjectReader.ReadSingle

Synopsis: Read a single (real-type) value from the stream.

Declaration: `function ReadSingle : Single; Virtual; Abstract`

Visibility: public

**Description:** `ReadSingle` is called by the streaming system when it wants to read a single-type float from the stream (i.e. after `ReadValue` (235) returned a valuetype of `vaSingle`). The return value should be the value of the float.

**See also:** `TAbstractObjectReader.ReadFloat` (237), `TAbstractObjectReader.ReadDate` (238), `TAbstractObjectReader.ReadSingle` (237), `TAbstractObjectReader.ReadIdent` (238), `TAbstractObjectReader.ReadInt8` (239), `TAbstractObjectReader.ReadInt16` (239), `TAbstractObjectReader.ReadInt32` (240), `TAbstractObjectReader.ReadInt64` (240), `TabstractObjectReader.ReadSet` (240), `TabstractObjectReader.ReadStr` (241), `TabstractObjectReader.ReadString` (241)

### 2.29.12 TAbstractObjectReader.ReadDate

**Synopsis:** Read a date value from the stream.

**Declaration:** `function ReadDate : TDateTime; Virtual; Abstract`

**Visibility:** public

**Description:** `ReadDate` is called by the streaming system when it wants to read a date/time value from the stream (i.e. after `ReadValue` (235) returned a valuetype of `vaDate`). The return value should be the date/time value. (This value can be stored as a float, since `TDateTime` is nothing but a float.)

**See also:** `TAbstractObjectReader.ReadFloat` (237), `TAbstractObjectReader.ReadSingle` (237), `TAbstractObjectReader.ReadIdent` (238), `TAbstractObjectReader.ReadInt8` (239), `TAbstractObjectReader.ReadInt16` (239), `TAbstractObjectReader.ReadInt32` (240), `TAbstractObjectReader.ReadInt64` (240), `TabstractObjectReader.ReadSet` (240), `TabstractObjectReader.ReadStr` (241), `TabstractObjectReader.ReadString` (241)

### 2.29.13 TAbstractObjectReader.ReadCurrency

**Synopsis:** Read a currency value from the stream.

**Declaration:** `function ReadCurrency : Currency; Virtual; Abstract`

**Visibility:** public

**Description:** `ReadCurrency` is called when a currency-typed value should be read from the stream. This abstract method should be overridden by descendent classes, and should return the currency value read from the stream.

**See also:** `TAbstractObjectWriter.WriteCurrency` (245)

### 2.29.14 TAbstractObjectReader.ReadIdent

**Synopsis:** Read an identifier from the stream.

**Declaration:** `function ReadIdent(ValueType: TValueType) : String; Virtual; Abstract`

**Visibility:** public

**Description:** `ReadIdent` is called by the streaming system if it expects to read an identifier of type `ValueType` from the stream after a call to `ReadValue` (235) returned `vaIdent`. The identifier should be returned as a string. Note that in some cases the identifier does not actually have to be in the stream. The following table indicates which identifiers must actually be read:



Table 2.17:

ValueType	Expected value
valIdent	Read from stream.
vaNil	'Nil'. This does not have to be read from the stream.
vaFalse	'False'. This does not have to be read from the stream.
vaTrue	'True'. This does not have to be read from the stream.
vaNull	'Null'. This does not have to be read from the stream.

See also: `TAbstractObjectReader.ReadFloat` (237), `TAbstractObjectReader.ReadDate` (238), `TAbstractObjectReader.ReadSingle` (237), `TAbstractObjectReader.ReadInt8` (239), `TAbstractObjectReader.ReadInt16` (239), `TAbstractObjectReader.ReadInt32` (240), `TAbstractObjectReader.ReadInt64` (240), `TabstractObjectReader.ReadSet` (240), `TabstractObjectReader.ReadStr` (241), `TabstractObjectReader.ReadString` (241)

### 2.29.15 TAbstractObjectReader.ReadInt8

Synopsis: Read an 8-bit integer from the stream.

Declaration: `function ReadInt8 : ShortInt; Virtual; Abstract`

Visibility: public

Description: `ReadInt8` is called by the streaming process if it expects to read an integer value with a size of 8 bits (1 byte) from the stream (i.e. after `ReadValue` (235) returned a valuetype of `vaInt8`). The return value is the value if the integer. Note that the size of the value in the stream does not actually have to be 1 byte.

See also: `TAbstractObjectReader.ReadFloat` (237), `TAbstractObjectReader.ReadDate` (238), `TAbstractObjectReader.ReadSingle` (237), `TAbstractObjectReader.ReadIdent` (238), `TAbstractObjectReader.ReadInt8` (239), `TAbstractObjectReader.ReadInt32` (240), `TAbstractObjectReader.ReadInt64` (240), `TabstractObjectReader.ReadSet` (240), `TabstractObjectReader.ReadStr` (241), `TabstractObjectReader.ReadString` (241)

### 2.29.16 TAbstractObjectReader.ReadInt16

Synopsis: Read a 16-bit integer from the stream.

Declaration: `function ReadInt16 : SmallInt; Virtual; Abstract`

Visibility: public

Description: `ReadInt16` is called by the streaming process if it expects to read an integer value with a size of 16 bits (2 bytes) from the stream (i.e. after `ReadValue` (235) returned a valuetype of `vaInt16`). The return value is the value if the integer. Note that the size of the value in the stream does not actually have to be 2 bytes.

See also: `TAbstractObjectReader.ReadFloat` (237), `TAbstractObjectReader.ReadDate` (238), `TAbstractObjectReader.ReadSingle` (237), `TAbstractObjectReader.ReadIdent` (238), `TAbstractObjectReader.ReadInt8` (239), `TAbstractObjectReader.ReadInt32` (240), `TAbstractObjectReader.ReadInt64` (240), `TabstractObjectReader.ReadSet` (240), `TabstractObjectReader.ReadStr` (241), `TabstractObjectReader.ReadString` (241)

### 2.29.17 TAbstractObjectReader.ReadInt32

Synopsis: Read a 32-bit integer from the stream.

Declaration: `function ReadInt32 : LongInt; Virtual; Abstract`

Visibility: public

Description: `ReadInt32` is called by the streaming process if it expects to read an integer value with a size of 32 bits (4 bytes) from the stream (i.e. after `ReadValue` (235) returned a valuetype of `vaInt32`). The return value is the value of the integer. Note that the size of the value in the stream does not actually have to be 4 bytes.

See also: `TAbstractObjectReader.ReadFloat` (237), `TAbstractObjectReader.ReadDate` (238), `TAbstractObjectReader.ReadSingle` (237), `TAbstractObjectReader.ReadIdent` (238), `TAbstractObjectReader.ReadInt8` (239), `TAbstractObjectReader.ReadInt16` (239), `TAbstractObjectReader.ReadInt64` (240), `TabstractObjectReader.ReadSet` (240), `TabstractObjectReader.ReadStr` (241), `TabstractObjectReader.ReadString` (241)

### 2.29.18 TAbstractObjectReader.ReadInt64

Synopsis: Read a 64-bit integer from the stream.

Declaration: `function ReadInt64 : Int64; Virtual; Abstract`

Visibility: public

Description: `ReadInt64` is called by the streaming process if it expects to read an `int64` value with a size of 64 bits (8 bytes) from the stream (i.e. after `ReadValue` (235) returned a valuetype of `vaInt64`). The return value is the value if the integer. Note that the size of the value in the stream does not actually have to be 8 bytes.

See also: `TAbstractObjectReader.ReadFloat` (237), `TAbstractObjectReader.ReadDate` (238), `TAbstractObjectReader.ReadSingle` (237), `TAbstractObjectReader.ReadIdent` (238), `TAbstractObjectReader.ReadInt8` (239), `TAbstractObjectReader.ReadInt16` (239), `TAbstractObjectReader.ReadInt32` (240), `TabstractObjectReader.ReadSet` (240), `TabstractObjectReader.ReadStr` (241), `TabstractObjectReader.ReadString` (241)

### 2.29.19 TAbstractObjectReader.ReadSet

Synopsis: Reads a set from the stream.

Declaration: `function ReadSet (EnumType: Pointer) : Integer; Virtual; Abstract`

Visibility: public

Description: This method is called by the streaming system if it expects to read a set from the stream (i.e. after `ReadValue` (235) returned a valuetype of `vaSet`). The return value is the contents of the set, encoded in a bitmask the following way:

For each (enumerated) value in the set, the bit corresponding to the ordinal value of the enumerated value should be set. i.e. `as 1 shl ord(value)`.

See also: `TAbstractObjectReader.ReadFloat` (237), `TAbstractObjectReader.ReadDate` (238), `TAbstractObjectReader.ReadSingle` (237), `TAbstractObjectReader.ReadIdent` (238), `TAbstractObjectReader.ReadInt8` (239), `TAbstractObjectReader.ReadInt16` (239), `TAbstractObjectReader.ReadInt32` (240), `TAbstractObjectReader.ReadInt64` (240), `TabstractObjectReader.ReadStr` (241), `TabstractObjectReader.ReadString` (241)

**2.29.20 TAbstractObjectReader.ReadStr**

Synopsis: Read a shortstring from the stream

Declaration: `function ReadStr : String; Virtual; Abstract`

Visibility: public

Description: `ReadStr` is called by the streaming system if it expects to read a string from the stream (i.e. after `ReadValue` (235) returned a valuetype of `vaLString`, `vaWstring` or `vaString`). The return value is the string.

See also: `TAbstractObjectReader.ReadFloat` (237), `TAbstractObjectReader.ReadDate` (238), `TAbstractObjectReader.ReadSingle` (237), `TAbstractObjectReader.ReadIdent` (238), `TAbstractObjectReader.ReadInt8` (239), `TAbstractObjectReader.ReadInt16` (239), `TAbstractObjectReader.ReadInt32` (240), `TAbstractObjectReader.ReadInt64` (240), `TabstractObjectReader.ReadSet` (240), `TabstractObjectReader.ReadString` (241)

**2.29.21 TAbstractObjectReader.ReadString**

Synopsis: Read a string of type `StringType` from the stream.

Declaration: `function ReadString(StringType: TValueType) : String; Virtual; Abstract`

Visibility: public

Description: `ReadStr` is called by the streaming system if it expects to read a string from the stream (i.e. after `ReadValue` (235) returned a valuetype of `vaLString`, `vaWstring` or `vaString`). The return value is the string.

See also: `TAbstractObjectReader.ReadFloat` (237), `TAbstractObjectReader.ReadDate` (238), `TAbstractObjectReader.ReadSingle` (237), `TAbstractObjectReader.ReadIdent` (238), `TAbstractObjectReader.ReadInt8` (239), `TAbstractObjectReader.ReadInt16` (239), `TAbstractObjectReader.ReadInt32` (240), `TAbstractObjectReader.ReadInt64` (240), `TabstractObjectReader.ReadSet` (240), `TabstractObjectReader.ReadStr` (241)

**2.29.22 TAbstractObjectReader.ReadWideString**

Synopsis: Read a widestring value from the stream.

Declaration: `function ReadWideString : WideString; Virtual; Abstract`

Visibility: public

Description: `ReadWideString` is called when a widestring-typed value should be read from the stream. This abstract method should be overridden by descendent classes.

See also: `TAbstractObjectWriter.WriteWideString` (247)

**2.29.23 TAbstractObjectReader.ReadUnicodeString**

Synopsis: Read a unicode string value

Declaration: `function ReadUnicodeString : UnicodeString; Virtual; Abstract`

Visibility: public

**Description:** `ReadUnicodeString` should read a `UnicodeString` value from the stream. (indicated by the `vaUString` value type).

Descendent classes should override this method to actually read a `UnicodeString` value.

See also: `TBinaryObjectWriter.WriteUnicodeString` ([264](#)), `TAbstractObjectReader.ReadWideString` ([241](#))

## 2.29.24 TAbstractObjectReader.SkipComponent

**Synopsis:** Skip till the end of the component.

**Declaration:** `procedure SkipComponent(SkipComponentInfos: Boolean); Virtual`  
`; Abstract`

**Visibility:** public

**Description:** This method is used to skip the entire declaration of a component in the stream. Each descendent of `TAbstractObjectReader` should implement this in a way which is optimal for the implemented stream format.

See also: `TAbstractObjectReader.BeginComponent` ([236](#)), `TAbstractObjectReader.SkipValue` ([242](#))

## 2.29.25 TAbstractObjectReader.SkipValue

**Synopsis:** Skip the current value.

**Declaration:** `procedure SkipValue; Virtual; Abstract`

**Visibility:** public

**Description:** `SkipValue` should be used when skipping a value in the stream; The method should determine the type of the value which should be skipped by itself, if this is necessary.

See also: `TAbstractObjectReader.SkipComponent` ([242](#))

## 2.30 TAbstractObjectWriter

### 2.30.1 Description

Abstract driver class for writing component data.

### 2.30.2 Method overview

Page	Property	Description
<a href="#">243</a>	BeginCollection	Start writing a collection.
<a href="#">243</a>	BeginComponent	Start writing a component
<a href="#">243</a>	BeginList	Start writing a list.
<a href="#">244</a>	BeginProperty	Start writing a property
<a href="#">244</a>	EndList	Mark the end of a list.
<a href="#">244</a>	EndProperty	Marks the end of writing of a property.
<a href="#">244</a>	Write	Write raw data to stream
<a href="#">244</a>	WriteBinary	Writes binary data to the stream.
<a href="#">245</a>	WriteBoolean	Writes a boolean value to the stream.
<a href="#">245</a>	WriteCurrency	Write a currency value to the stream
<a href="#">245</a>	WriteDate	Writes a date type to the stream.
<a href="#">245</a>	WriteFloat	Writes a float value to the stream.
<a href="#">246</a>	WriteIdent	Writes an identifier to the stream.
<a href="#">246</a>	WriteInteger	Writes an integer value to the stream
<a href="#">246</a>	WriteMethodName	Writes a methodname to the stream.
<a href="#">247</a>	WriteSet	Writes a set value to the stream.
<a href="#">245</a>	WriteSingle	Writes a single-type real value to the stream.
<a href="#">247</a>	WriteString	Writes a string value to the stream.
<a href="#">246</a>	WriteUInt64	Write an unsigned 64-bit integer
<a href="#">247</a>	WriteUnicodeString	Write a unicode string to the stream.
<a href="#">246</a>	WriteVariant	Write a variant to the stream
<a href="#">247</a>	WriteWideString	Write a widestring value to the stream

### 2.30.3 TAbstractObjectWriter.BeginCollection

Synopsis: Start writing a collection.

Declaration: `procedure BeginCollection; Virtual; Abstract`

Visibility: `public`

Description: Start writing a collection.

### 2.30.4 TAbstractObjectWriter.BeginComponent

Synopsis: Start writing a component

Declaration: `procedure BeginComponent(Component: TComponent; Flags: TFileFlags;  
ChildPos: Integer); Virtual; Abstract`

Visibility: `public`

Description: Start writing a component

### 2.30.5 TAbstractObjectWriter.BeginList

Synopsis: Start writing a list.

Declaration: `procedure BeginList; Virtual; Abstract`

Visibility: `public`

Description: Start writing a list.

### 2.30.6 TAbstractObjectWriter.EndList

Synopsis: Mark the end of a list.

Declaration: `procedure EndList; Virtual; Abstract`

Visibility: `public`

Description: Mark the end of a list.

### 2.30.7 TAbstractObjectWriter.BeginProperty

Synopsis: Start writing a property

Declaration: `procedure BeginProperty(const PropName: String); Virtual; Abstract`

Visibility: `public`

Description: Start writing a property

### 2.30.8 TAbstractObjectWriter.EndProperty

Synopsis: Marks the end of writing of a property.

Declaration: `procedure EndProperty; Virtual; Abstract`

Visibility: `public`

Description: Marks the end of writing of a property.

### 2.30.9 TAbstractObjectWriter.Write

Synopsis: Write raw data to stream

Declaration: `procedure Write(const Buffer;Count: LongInt); Virtual; Abstract`

Visibility: `public`

Description: `Write` is introduced for Delphi compatibility to write raw data to the component stream. This should not be used in new production code as it will totally mess up the streaming.

See also: `TBinaryObjectWriter.Write` ([262](#)), `TWriter.Write` ([400](#))

### 2.30.10 TAbstractObjectWriter.WriteBinary

Synopsis: Writes binary data to the stream.

Declaration: `procedure WriteBinary(const Buffer;Count: LongInt); Virtual; Abstract`

Visibility: `public`

Description: Writes binary data to the stream.

### 2.30.11 TAbstractObjectWriter.WriteBoolean

Synopsis: Writes a boolean value to the stream.

Declaration: `procedure WriteBoolean(Value: Boolean); Virtual; Abstract`

Visibility: `public`

Description: Writes a boolean value to the stream.

### 2.30.12 TAbstractObjectWriter.WriteFloat

Synopsis: Writes a float value to the stream.

Declaration: `procedure WriteFloat(const Value: Extended); Virtual; Abstract`

Visibility: `public`

Description: Writes a float value to the stream.

### 2.30.13 TAbstractObjectWriter.WriteSingle

Synopsis: Writes a single-type real value to the stream.

Declaration: `procedure WriteSingle(const Value: Single); Virtual; Abstract`

Visibility: `public`

Description: Writes a single-type real value to the stream.

### 2.30.14 TAbstractObjectWriter.WriteDate

Synopsis: Writes a date type to the stream.

Declaration: `procedure WriteDate(const Value: TDateTime); Virtual; Abstract`

Visibility: `public`

Description: Writes a date type to the stream.

### 2.30.15 TAbstractObjectWriter.WriteCurrency

Synopsis: Write a currency value to the stream

Declaration: `procedure WriteCurrency(const Value: Currency); Virtual; Abstract`

Visibility: `public`

Description: `WriteCurrency` is called when a currency-typed value should be written to the stream. This abstract method should be overridden by descendent classes.

See also: `TAbstractObjectReader.ReadCurrency` ([238](#))

### 2.30.16 TAbstractObjectWriter.WriteIdent

Synopsis: Writes an identifier to the stream.

Declaration: `procedure WriteIdent(const Ident: String); Virtual; Abstract`

Visibility: public

Description: Writes an identifier to the stream.

### 2.30.17 TAbstractObjectWriter.WriteInteger

Synopsis: Writes an integer value to the stream

Declaration: `procedure WriteInteger(Value: Int64); Virtual; Abstract`

Visibility: public

Description: Writes an integer value to the stream

### 2.30.18 TAbstractObjectWriter.WriteUInt64

Synopsis: Write an unsigned 64-bit integer

Declaration: `procedure WriteUInt64(Value: QWord); Virtual; Abstract`

Visibility: public

Description: `WriteUInt64` must be overridden by descendent classes to write a 64-bit unsigned Value (value type `QWord`) to the stream.

Errors: None.

See also: `TBinaryObjectWriter.WriteUInt64` ([263](#))

### 2.30.19 TAbstractObjectWriter.WriteVariant

Synopsis: Write a variant to the stream

Declaration: `procedure WriteVariant(const Value: Variant); Virtual; Abstract`

Visibility: public

Description: `WriteVariant` must be overridden by descendent classes to write a simple variant type to the stream. `WriteVariant` does not write arrays types or complex types.

See also: `TBinaryObjectWriter.WriteVariant` ([264](#))

### 2.30.20 TAbstractObjectWriter.WriteMethodName

Synopsis: Writes a methodname to the stream.

Declaration: `procedure WriteMethodName(const Name: String); Virtual; Abstract`

Visibility: public

Description: Writes a methodname to the stream.



### 2.30.21 TAbstractObjectWriter.WriteSet

Synopsis: Writes a set value to the stream.

Declaration: `procedure WriteSet(Value: LongInt; SetType: Pointer); Virtual; Abstract`

Visibility: public

Description: Writes a set value to the stream.

### 2.30.22 TAbstractObjectWriter.WriteString

Synopsis: Writes a string value to the stream.

Declaration: `procedure WriteString(const Value: String); Virtual; Abstract`

Visibility: public

Description: Writes a string value to the stream.

### 2.30.23 TAbstractObjectWriter.WriteWideString

Synopsis: Write a widestring value to the stream

Declaration: `procedure WriteWideString(const Value: WideString); Virtual; Abstract`

Visibility: public

Description: `WriteCurrency` is called when a currency-typed value should be written to the stream. This abstract method should be overridden by descendent classes.

See also: `TAbstractObjectReader.ReadWideString` ([241](#))

### 2.30.24 TAbstractObjectWriter.WriteUnicodeString

Synopsis: Write a unicode string to the stream.

Declaration: `procedure WriteUnicodeString(const Value: UnicodeString); Virtual  
; Abstract`

Visibility: public

Description: `WriteUnicodeString` must be overridden by descendent classes to write a unicodestring (value type `vaUString`) value to the stream.

See also: `TBinaryObjectWriter.WriteUnicodeString` ([264](#))

## 2.31 TBasicAction

### 2.31.1 Description

`TBasicAction` implements a basic action class from which all actions are derived. It introduces all basic methods of an action, and implements functionality to maintain a list of clients, i.e. components that are connected with this action.

Do not create instances of `TBasicAction`. Instead, create a descendent class and create an instance of this class instead.

### 2.31.2 Method overview

Page	Property	Description
<a href="#">248</a>	Create	Creates a new instance of a TBasicAction ( <a href="#">247</a> ) class.
<a href="#">248</a>	Destroy	Destroys the action.
<a href="#">249</a>	Execute	Triggers the OnExecute ( <a href="#">251</a> ) event
<a href="#">249</a>	ExecuteTarget	Executes the action on the Target object
<a href="#">248</a>	HandlesTarget	Determines whether Target can be handled by this action
<a href="#">250</a>	RegisterChanges	Registers a new client with the action.
<a href="#">250</a>	UnRegisterChanges	Unregisters a client from the list of clients
<a href="#">250</a>	Update	Triggers the OnUpdate ( <a href="#">251</a> ) event
<a href="#">249</a>	UpdateTarget	Notify client controls when the action updates itself.

### 2.31.3 Property overview

Page	Property	Access	Description
<a href="#">250</a>	ActionComponent	rw	Returns the component that initiated the action.
<a href="#">251</a>	OnExecute	rw	Event triggered when the action executes.
<a href="#">251</a>	OnUpdate	rw	Event triggered when the application is idle.

### 2.31.4 TBasicAction.Create

Synopsis: Creates a new instance of a TBasicAction ([247](#)) class.

Declaration: `constructor Create(AOwner: TComponent); Override`

Visibility: `public`

Description: `Create` calls the inherited constructor, and then initializes the list of clients controls (or action lists).

Under normal circumstances it should not be necessary to create a TBasicAction descendent manually, actions are created in an IDE.

See also: TBasicAction.Destroy ([248](#)), TBasicAction.AssignClient ([247](#))

### 2.31.5 TBasicAction.Destroy

Synopsis: Destroys the action.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` cleans up the list of client controls and then calls the inherited destructor.

An application programmer should not call `Destroy` directly; Instead `Free` should be called, if it needs to be called at all. Normally the controlling class (e.g. a TActionList) will destroy the action.

### 2.31.6 TBasicAction.HandlesTarget

Synopsis: Determines whether Target can be handled by this action

Declaration: `function HandlesTarget(Target: TObject) : Boolean; Virtual`

Visibility: `public`

**Description:** `HandlesTarget` returns `True` if `Target` is a valid client for this action and if so, if it is in a suitable state to execute the action. An application programmer should never need to call `HandlesTarget` directly, it will be called by the action itself when needed.

In `TBasicAction` this method is empty; descendent classes should override this method to implement appropriate checks.

See also: `TBasicAction.UpdateTarget` (249), `TBasicAction.ExecuteTarget` (249)

### 2.31.7 TBasicAction.UpdateTarget

**Synopsis:** Notify client controls when the action updates itself.

**Declaration:** `procedure UpdateTarget(Target: TObject); Virtual`

**Visibility:** `public`

**Description:** `UpdateTarget` should update the client control specified by `Target` when the action updates itself. In `TBasicAction`, the implementation of `UpdateTarget` is empty. Descendent classes should override and implement `UpdateTarget` to actually update the `Target` object.

An application programmer should never need to call `HandlesTarget` directly, it will be called by the action itself when needed.

See also: `TBasicAction.HandlesTarget` (248), `TBasicAction.ExecuteTarget` (249)

### 2.31.8 TBasicAction.ExecuteTarget

**Synopsis:** Executes the action on the `Target` object

**Declaration:** `procedure ExecuteTarget(Target: TObject); Virtual`

**Visibility:** `public`

**Description:** `ExecuteTarget` performs the action on the `Target` object. In `TBasicAction` this method does nothing. Descendent classes should implement the action to be performed. For instance an action to post data in a dataset could call the `Post` method of the dataset.

An application programmer should never call `ExecuteTarget` directly.

See also: `TBasicAction.HandlesTarget` (248), `TBasicAction.ExecuteTarget` (249), `TBasicAction.Execute` (249)

### 2.31.9 TBasicAction.Execute

**Synopsis:** Triggers the `OnExecute` (251) event

**Declaration:** `function Execute : Boolean; Dynamic`

**Visibility:** `public`

**Description:** `Execute` triggers the `OnExecute` event, if one is assigned. It returns `True` if the event handler was called, `False` otherwise.

### 2.31.10 TBasicAction.RegisterChanges

Synopsis: Registers a new client with the action.

Declaration: `procedure RegisterChanges (Value: TBasicActionLink)`

Visibility: `public`

Description: `RegisterChanges` adds `Value` to the list of clients.

See also: `TBasicAction.UnregisterChanges` ([250](#))

### 2.31.11 TBasicAction.UnRegisterChanges

Synopsis: Unregisters a client from the list of clients

Declaration: `procedure UnRegisterChanges (Value: TBasicActionLink)`

Visibility: `public`

Description: `UnregisterChanges` removes `Value` from the list of clients. This is called for instance when the action is destroyed, or when the client is assigned a new action.

See also: `TBasicAction.UnregisterChanges` ([250](#)), `TBasicAction.Destroy` ([248](#))

### 2.31.12 TBasicAction.Update

Synopsis: Triggers the `OnUpdate` ([251](#)) event

Declaration: `function Update : Boolean; Virtual`

Visibility: `public`

Description: `Update` triggers the `OnUpdate` event, if one is assigned. It returns `True` if the event was triggered, or `False` if no event was assigned.

Application programmers should never run `Update` directly. The `Update` method is called automatically by the action mechanism; Normally this is in the Idle time of an application. An application programmer should assign the `OnUpdate` ([251](#)) event, and perform any checks in that handler.

See also: `TBasicAction.OnUpdate` ([251](#)), `TBasicAction.Execute` ([249](#)), `TBasicAction.UpdateTarget` ([249](#))

### 2.31.13 TBasicAction.ActionComponent

Synopsis: Returns the component that initiated the action.

Declaration: `Property ActionComponent : TComponent`

Visibility: `public`

Access: `Read,Write`

Description: `ActionComponent` is set to the component that caused the action to execute, e.g. a toolbutton or a menu item. The property is set just before the action executes, and is reset to nil after the action was executed.

See also: `TBasicAction.Execute` ([249](#)), `TBasicAction.OnExecute` ([251](#))

### 2.31.14 TBasicAction.OnExecute

Synopsis: Event triggered when the action executes.

Declaration: Property OnExecute : TNotifyEvent

Visibility: public

Access: Read,Write

Description: OnExecute is the event triggered when the action is activated (executed). The event is triggered e.g. when the user clicks e.g. on a menu item or a button associated to the action. The application programmer should provide a OnExecute event handler to execute whatever code is necessary when the button is pressed or the menu item is chosen.

Note that assigning an OnExecute handler will result in the Execute (249) method returning a True value. Predefined actions (such as dataset actions) will check the result of Execute and will not perform their normal task if the OnExecute handler was called.

See also: TBasicAction.Execute (249), TBasicAction.OnUpdate (251)

### 2.31.15 TBasicAction.OnUpdate

Synopsis: Event triggered when the application is idle.

Declaration: Property OnUpdate : TNotifyEvent

Visibility: public

Access: Read,Write

Description: OnUpdate is the event triggered when the application is idle, and the action is being updated. The OnUpdate event can be used to set the state of the action, for instance disable it if the action cannot be executed at this point in time.

See also: TBasicAction.Update (250), TBasicAction.OnExecute (251)

## 2.32 TBasicActionLink

### 2.32.1 Description

TBasicActionLink links an Action to its clients. With each client for an action, a TBasicActionLink class is instantiated to handle the communication between the action and the client. It passes events between the action and its clients, and thus presents the action with a uniform interface to the clients.

An application programmer should never use a TBasicActionLink instance directly; They are created automatically when an action is associated with a component. Component programmers should create specialized descendents of TBasicActionLink which communicate changes in the action to the component.

### 2.32.2 Method overview

Page	Property	Description
<a href="#">252</a>	Create	Creates a new instance of the TBasicActionLink class
<a href="#">252</a>	Destroy	Destroys the TBasicActionLink instance.
<a href="#">252</a>	Execute	Calls the action's Execute method.
<a href="#">253</a>	Update	Calls the action's Update method

### 2.32.3 Property overview

Page	Property	Access	Description
<a href="#">253</a>	Action	rw	The action to which the link was assigned.
<a href="#">253</a>	OnChange	rw	Event handler triggered when the action's properties change

### 2.32.4 TBasicActionLink.Create

Synopsis: Creates a new instance of the TBasicActionLink class

Declaration: `constructor Create(AClient: TObject); Virtual`

Visibility: `public`

Description: `Create` creates a new instance of a TBasicActionLink and assigns `AClient` as the client of the link.

Application programmers should never instantiate TBasicActionLink classes directly. An instance is created automatically when an action is assigned to a control (client).

Component programmers can override the create constructor to initialize further properties.

See also: TBasicActionLink.Destroy ([252](#))

### 2.32.5 TBasicActionLink.Destroy

Synopsis: Destroys the TBasicActionLink instance.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` unregisters the TBasicActionLink with the action, and then calls the inherited destructor.

Application programmers should never call `Destroy` directly. If a link should be destroyed at all, the `Free` method should be called instead.

See also: TBasicActionLink.Create ([252](#))

### 2.32.6 TBasicActionLink.Execute

Synopsis: Calls the action's Execute method.

Declaration: `function Execute(AComponent: TComponent) : Boolean; Virtual`

Visibility: `public`

Description: `Execute` sets the `ActionComponent` ([250](#)) property of the associated Action ([253](#)) to `AComponent` and then calls the Action's `execute` ([249](#)) method. After the action has executed, the `ActionComponent` property is cleared again.

The return value of the function is the return value of the Action's `execute` method.

Application programmers should never call `Execute` directly. This method will be called automatically when the associated control is activated. (e.g. a button is clicked on)

Component programmers should call `Execute` whenever the action should be activated.

See also: TBasicActionLink.Action ([253](#)), TBasicAction.ActionComponent ([250](#)), TBasicAction.Execute ([249](#)), TBasicAction.onExecute ([251](#))

### 2.32.7 TBasicActionLink.Update

Synopsis: Calls the action's Update method

Declaration: `function Update : Boolean; Virtual`

Visibility: `public`

Description: `Update` calls the associated Action's `Update` (250) method.

Component programmers can override the `Update` method to provide additional processing when the `Update` method occurs.

### 2.32.8 TBasicActionLink.Action

Synopsis: The action to which the link was assigned.

Declaration: `Property Action : TBasicAction`

Visibility: `public`

Access: `Read,Write`

Description: `Action` represents the Action (247) which was assigned to the client. Setting this property will unregister the client at the old action (if one existed) and registers the client at the new action.

See also: `TBasicAction` (247)

### 2.32.9 TBasicActionLink.OnChange

Synopsis: Event handler triggered when the action's properties change

Declaration: `Property OnChange : TNotifyEvent`

Visibility: `public`

Access: `Read,Write`

Description: `OnChange` is the event triggered when the action's properties change.

Application programmers should never need to assign this event. Component programmers can assign this event to have a client control reflect any changes in an Action's properties.

See also: `TBasicActionLink.Change` (251), `TBasicAction.Change` (247)

## 2.33 TBinaryObjectReader

### 2.33.1 Description

The `TBinaryObjectReader` class reads component data stored in binary form in a file. For this, it overrides or implements all abstract methods from `TAbstractObjectReader` (234). No new functionality is added by this class, it is a driver class for the streaming system.

**2.33.2 Method overview**

Page	Property	Description
<a href="#">255</a>	<code>BeginComponent</code>	Start reading a component.
<a href="#">255</a>	<code>BeginProperty</code>	Start reading a property.
<a href="#">255</a>	<code>BeginRootComponent</code>	Start reading the root component.
<a href="#">254</a>	<code>Create</code>	Creates a new binary data reader instance.
<a href="#">254</a>	<code>Destroy</code>	Destroys the binary data reader.
<a href="#">255</a>	<code>NextValue</code>	Return the type of the next value.
<a href="#">256</a>	<code>Read</code>	Read raw data from stream
<a href="#">256</a>	<code>ReadBinary</code>	Start reading a binary value.
<a href="#">257</a>	<code>ReadCurrency</code>	Read a currency value from the stream.
<a href="#">256</a>	<code>ReadDate</code>	Read a date.
<a href="#">256</a>	<code>ReadFloat</code>	Read a float value
<a href="#">257</a>	<code>ReadIdent</code>	Read an identifier
<a href="#">257</a>	<code>ReadInt16</code>	Read a 16-bits integer.
<a href="#">258</a>	<code>ReadInt32</code>	Read a 32-bits integer.
<a href="#">258</a>	<code>ReadInt64</code>	Read a 64-bits integer.
<a href="#">257</a>	<code>ReadInt8</code>	Read an 8-bits integer.
<a href="#">258</a>	<code>ReadSet</code>	Read a set
<a href="#">256</a>	<code>ReadSingle</code>	Read a single-size float value
<a href="#">258</a>	<code>ReadStr</code>	Read a short string
<a href="#">258</a>	<code>ReadString</code>	Read a string
<a href="#">259</a>	<code>ReadUnicodeString</code>	Read a unicode string value
<a href="#">255</a>	<code>ReadValue</code>	Read the next value in the stream
<a href="#">259</a>	<code>ReadWideString</code>	Read a widestring value from the stream.
<a href="#">259</a>	<code>SkipComponent</code>	Skip a component's data
<a href="#">259</a>	<code>SkipValue</code>	Skip a value's data

**2.33.3 TBinaryObjectReader.Create**

Synopsis: Creates a new binary data reader instance.

Declaration: `constructor Create(Stream: TStream; BufSize: Integer)`

Visibility: `public`

Description: `Create` instantiates a new binary component data reader. The `Stream` stream is the stream from which data will be read. The `BufSize` argument is the size of the internal buffer that will be used by the reader. This can be used to optimize the reading process.

See also: `TAbstractObjectReader` ([234](#))

**2.33.4 TBinaryObjectReader.Destroy**

Synopsis: Destroys the binary data reader.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` frees the buffer allocated when the instance was created. It also positions the stream on the last used position in the stream (the buffering may cause the reader to read more bytes than were actually used.)

See also: `TBinaryObjectReader.Create` ([254](#))



### 2.33.5 TBinaryObjectReader.NextValue

Synopsis: Return the type of the next value.

Declaration: `function NextValue : TValueType; Override`

Visibility: public

Description: `NextValue` returns the type of the next value in a binary stream, but does not read the value.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` ([234](#))

### 2.33.6 TBinaryObjectReader.ReadValue

Synopsis: Read the next value in the stream

Declaration: `function ReadValue : TValueType; Override`

Visibility: public

Description: `NextValue` reads the next value in a binary stream and returns the type of the read value.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` ([234](#))

### 2.33.7 TBinaryObjectReader.BeginRootComponent

Synopsis: Start reading the root component.

Declaration: `procedure BeginRootComponent; Override`

Visibility: public

Description: `BeginRootComponent` starts reading the root component in a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` ([234](#))

### 2.33.8 TBinaryObjectReader.BeginComponent

Synopsis: Start reading a component.

Declaration: `procedure BeginComponent (var Flags: TFileFlags; var AChildPos: Integer;  
var CompClassName: String; var CompName: String)  
; Override`

Visibility: public

Description: This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` ([234](#))

### 2.33.9 TBinaryObjectReader.BeginProperty

Synopsis: Start reading a property.

Declaration: `function BeginProperty : String; Override`

Visibility: public

Description: This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` ([234](#))

### 2.33.10 TBinaryObjectReader.Read

Synopsis: Read raw data from stream

Declaration: `procedure Read(var Buf; Count: LongInt); Override`

Visibility: public

Description: `Read` is introduced for Delphi compatibility to read raw data from the component stream. This should not be used in production code as it will totally mess up the streaming.

See also: `TAbstractObjectReader.Read` ([237](#)), `TReader.Read` ([344](#))

### 2.33.11 TBinaryObjectReader.ReadBinary

Synopsis: Start reading a binary value.

Declaration: `procedure ReadBinary(const DestData: TMemoryStream); Override`

Visibility: public

Description: `ReadBinary` reads a binary value from a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` ([234](#))

### 2.33.12 TBinaryObjectReader.ReadFloat

Synopsis: Read a float value

Declaration: `function ReadFloat : Extended; Override`

Visibility: public

Description: `ReadFloat` reads a float value from a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` ([234](#))

### 2.33.13 TBinaryObjectReader.ReadSingle

Synopsis: Read a single-size float value

Declaration: `function ReadSingle : Single; Override`

Visibility: public

Description: `ReadSingle` reads a single-sized float value from a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` ([234](#))

### 2.33.14 TBinaryObjectReader.ReadDate

Synopsis: Read a date.

Declaration: `function ReadDate : TDateTime; Override`

Visibility: public

**Description:** `ReadDate` reads a date value from a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` ([234](#))

### 2.33.15 `TBinaryObjectReader.ReadCurrency`

**Synopsis:** Read a currency value from the stream.

**Declaration:** `function ReadCurrency : Currency; Override`

**Visibility:** `public`

**Description:** `var>ReadCurrency` reads a currency-typed value from a binary stream. It is the implementation of the method introduced in `TAbstractObjectReader` ([234](#)).

See also: `TAbstractObjectReader.ReadCurrency` ([238](#)), `TBinaryObjectWriter.WriteCurrency` ([263](#))

### 2.33.16 `TBinaryObjectReader.ReadIdent`

**Synopsis:** Read an identifier

**Declaration:** `function ReadIdent(ValueType: TValueType) : String; Override`

**Visibility:** `public`

**Description:** `ReadIdent` reads an identifier from a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` ([234](#))

### 2.33.17 `TBinaryObjectReader.ReadInt8`

**Synopsis:** Read an 8-bits integer.

**Declaration:** `function ReadInt8 : ShortInt; Override`

**Visibility:** `public`

**Description:** `Read8Int` reads an 8-bits signed integer from a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` ([234](#))

### 2.33.18 `TBinaryObjectReader.ReadInt16`

**Synopsis:** Read a 16-bits integer.

**Declaration:** `function ReadInt16 : SmallInt; Override`

**Visibility:** `public`

**Description:** `Read16Int` reads a 16-bits signed integer from a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` ([234](#))

### 2.33.19 TBinaryObjectReader.ReadInt32

Synopsis: Read a 32-bits integer.

Declaration: `function ReadInt32 : LongInt; Override`

Visibility: `public`

Description: `Read32Int` reads a 32-bits signed integer from a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` ([234](#))

### 2.33.20 TBinaryObjectReader.ReadInt64

Synopsis: Read a 64-bits integer.

Declaration: `function ReadInt64 : Int64; Override`

Visibility: `public`

Description: `Read64Int` reads a 64-bits signed integer from a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` ([234](#))

### 2.33.21 TBinaryObjectReader.ReadSet

Synopsis: Read a set

Declaration: `function ReadSet (EnumType: Pointer) : Integer; Override`

Visibility: `public`

Description: `ReadSet` reads a set from a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` ([234](#))

### 2.33.22 TBinaryObjectReader.ReadStr

Synopsis: Read a short string

Declaration: `function ReadStr : String; Override`

Visibility: `public`

Description: `ReadStr` reads a short string from a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` ([234](#))

### 2.33.23 TBinaryObjectReader.ReadString

Synopsis: Read a string

Declaration: `function ReadString (StringType: TValueType) : String; Override`

Visibility: `public`

**Description:** `ReadStr` reads a string of type `StringType` from a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` (234)

### 2.33.24 `TBinaryObjectReader.ReadWideString`

**Synopsis:** Read a widestring value from the stream.

**Declaration:** `function ReadWideString : WideString; Override`

**Visibility:** `public`

**Description:** `var>ReadWideString` reads a widestring-typed value from a binary stream. It is the implementation of the method introduced in `TAbstractObjectReader` (234).

See also: `TAbstractObjectReader.ReadWideString` (241), `TBinaryObjectWriter.WriteWideString` (264)

### 2.33.25 `TBinaryObjectReader.ReadUnicodeString`

**Synopsis:** Read a unicode string value

**Declaration:** `function ReadUnicodeString : UnicodeString; Override`

**Visibility:** `public`

**Description:** `ReadUnicodeString` is overridden by `TBinaryObjectReader` to read a `UnicodeString` value from the binary stream.

See also: `TAbstractObjectReader.ReadUnicodeString` (241)

### 2.33.26 `TBinaryObjectReader.SkipComponent`

**Synopsis:** Skip a component's data

**Declaration:** `procedure SkipComponent (SkipComponentInfos: Boolean); Override`

**Visibility:** `public`

**Description:** `SkipComponent` skips the data of a component in a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` (234).

### 2.33.27 `TBinaryObjectReader.SkipValue`

**Synopsis:** Skip a value's data

**Declaration:** `procedure SkipValue; Override`

**Visibility:** `public`

**Description:** `SkipComponent` skips the data of the next value in a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` (234)

## 2.34 TBinaryObjectWriter

### 2.34.1 Description

Driver class which stores component data in binary form.

### 2.34.2 Method overview

Page	Property	Description
<a href="#">261</a>	BeginCollection	Start writing a collection.
<a href="#">261</a>	BeginComponent	Start writing a component
<a href="#">261</a>	BeginList	Start writing a list.
<a href="#">261</a>	BeginProperty	Start writing a property
<a href="#">260</a>	Create	Creates a new instance of a binary object writer.
<a href="#">260</a>	Destroy	Destroys an instance of the binary object writer.
<a href="#">261</a>	EndList	Mark the end of a list.
<a href="#">261</a>	EndProperty	Marks the end of writing of a property.
<a href="#">262</a>	Write	Write raw data to stream
<a href="#">262</a>	WriteBinary	Writes binary data to the stream.
<a href="#">262</a>	WriteBoolean	Writes a boolean value to the stream.
<a href="#">263</a>	WriteCurrency	Write a currency-valued type to a stream
<a href="#">262</a>	WriteDate	Writes a date type to the stream.
<a href="#">262</a>	WriteFloat	Writes a float value to the stream.
<a href="#">263</a>	WriteIdent	Writes an identifier to the stream.
<a href="#">263</a>	WriteInteger	Writes an integer value to the stream.
<a href="#">263</a>	WriteMethodName	Writes a methodname to the stream.
<a href="#">263</a>	WriteSet	Writes a set value to the stream.
<a href="#">262</a>	WriteSingle	Writes a single-type real value to the stream.
<a href="#">264</a>	WriteString	Writes a string value to the stream.
<a href="#">263</a>	WriteUInt64	Write an unsigned 64-bit integer
<a href="#">264</a>	WriteUnicodeString	Write a unicode string to the stream.
<a href="#">264</a>	WriteVariant	Write a variant to the stream
<a href="#">264</a>	WriteWideString	Write a widestring-valued type to a stream

### 2.34.3 TBinaryObjectWriter.Create

Synopsis: Creates a new instance of a binary object writer.

Declaration: constructor `Create(Stream: TStream; BufSize: Integer)`

Visibility: public

Description: Creates a new instance of a binary object writer.

### 2.34.4 TBinaryObjectWriter.Destroy

Synopsis: Destroys an instance of the binary object writer.

Declaration: destructor `Destroy; Override`

Visibility: public

Description: Destroys an instance of the binary object writer.

### **2.34.5 TBinaryObjectWriter.BeginCollection**

Synopsis: Start writing a collection.

Declaration: `procedure BeginCollection; Override`

Visibility: `public`

### **2.34.6 TBinaryObjectWriter.BeginComponent**

Synopsis: Start writing a component

Declaration: `procedure BeginComponent(Component: TComponent; Flags: TFileFlags;  
ChildPos: Integer); Override`

Visibility: `public`

### **2.34.7 TBinaryObjectWriter.BeginList**

Synopsis: Start writing a list.

Declaration: `procedure BeginList; Override`

Visibility: `public`

### **2.34.8 TBinaryObjectWriter.EndList**

Synopsis: Mark the end of a list.

Declaration: `procedure EndList; Override`

Visibility: `public`

### **2.34.9 TBinaryObjectWriter.BeginProperty**

Synopsis: Start writing a property

Declaration: `procedure BeginProperty(const PropName: String); Override`

Visibility: `public`

### **2.34.10 TBinaryObjectWriter.EndProperty**

Synopsis: Marks the end of writing of a property.

Declaration: `procedure EndProperty; Override`

Visibility: `public`

### 2.34.11 TBinaryObjectWriter.Write

Synopsis: Write raw data to stream

Declaration: `procedure Write(const Buffer; Count: LongInt); Override`

Visibility: public

Description: `Write` is introduced for Delphi compatibility to write raw data to the component stream. This should not be used in new production code as it will totally mess up the streaming.

See also: `TAbstractObjectWriter.Write` ([244](#)), `TWriter.Write` ([400](#))

### 2.34.12 TBinaryObjectWriter.WriteBinary

Synopsis: Writes binary data to the stream.

Declaration: `procedure WriteBinary(const Buffer; Count: LongInt); Override`

Visibility: public

### 2.34.13 TBinaryObjectWriter.WriteBoolean

Synopsis: Writes a boolean value to the stream.

Declaration: `procedure WriteBoolean(Value: Boolean); Override`

Visibility: public

### 2.34.14 TBinaryObjectWriter.WriteFloat

Synopsis: Writes a float value to the stream.

Declaration: `procedure WriteFloat(const Value: Extended); Override`

Visibility: public

### 2.34.15 TBinaryObjectWriter.WriteSingle

Synopsis: Writes a single-type real value to the stream.

Declaration: `procedure WriteSingle(const Value: Single); Override`

Visibility: public

### 2.34.16 TBinaryObjectWriter.WriteDate

Synopsis: Writes a date type to the stream.

Declaration: `procedure WriteDate(const Value: TDateTime); Override`

Visibility: public



### 2.34.17 TBinaryObjectWriter.WriteCurrency

Synopsis: Write a currency-valued type to a stream

Declaration: `procedure WriteCurrency(const Value: Currency); Override`

Visibility: public

Description: `WriteCurrency` writes a currency-typed value to a binary stream. It is the implementation of the method introduced in `TAbstractObjectWriter` (242).

See also: `TAbstractObjectWriter.WriteCurrency` (245)

### 2.34.18 TBinaryObjectWriter.WriteIdent

Synopsis: Writes an identifier to the stream.

Declaration: `procedure WriteIdent(const Ident: String); Override`

Visibility: public

### 2.34.19 TBinaryObjectWriter.WriteInteger

Synopsis: Writes an integer value to the stream.

Declaration: `procedure WriteInteger(Value: Int64); Override`

Visibility: public

### 2.34.20 TBinaryObjectWriter.WriteUInt64

Synopsis: Write an unsigned 64-bit integer

Declaration: `procedure WriteUInt64(Value: QWord); Override`

Visibility: public

Description: `WriteUInt64` is overridden by `TBinaryObjectWriter` to write an unsigned 64-bit integer (QWord) to the stream. It tries to use the smallest possible storage for the value that is passed. (largest valuetype will be `vaQWord`).

See also: `TAbstractObjectWriter.WriteUInt64` (246)

### 2.34.21 TBinaryObjectWriter.WriteMethodName

Synopsis: Writes a methodname to the stream.

Declaration: `procedure WriteMethodName(const Name: String); Override`

Visibility: public

### 2.34.22 TBinaryObjectWriter.WriteSet

Synopsis: Writes a set value to the stream.

Declaration: `procedure WriteSet(Value: LongInt; SetType: Pointer); Override`

Visibility: public

### 2.34.23 TBinaryObjectWriter.WriteString

Synopsis: Writes a string value to the stream.

Declaration: `procedure WriteString(const Value: String); Override`

Visibility: public

### 2.34.24 TBinaryObjectWriter.WriteString

Synopsis: Write a widestring-valued type to a stream

Declaration: `procedure WriteWideString(const Value: WideString); Override`

Visibility: public

Description: `WriteWideString` writes a widestring-typed value to a binary stream. It is the implementation of the method introduced in `TAbstractObjectWriter` (242).

See also: `TAbstractObjectWriter.WriteString` (247)

### 2.34.25 TBinaryObjectWriter.WriteString

Synopsis: Write a unicode string to the stream.

Declaration: `procedure WriteUnicodeString(const Value: UnicodeString); Override`

Visibility: public

Description: `WriteUnicodeString` is overridden `TBinaryObjectWriter` to write a unicodestring (value type `vaUString`) value to the stream. It simply writes the character length and then all widecharacters.

See also: `TAbstractObjectWriter.WriteString` (247)

### 2.34.26 TBinaryObjectWriter.WriteVariant

Synopsis: Write a variant to the stream

Declaration: `procedure WriteVariant(const VarValue: Variant); Override`

Visibility: public

Description: `WriteVariant` is overridden by `TBinaryObjectWriter` to write a simple variant type to the stream. `WriteVariant` does not write arrays types or complex types. Only null, integer (ordinal) float and string types are written.

Errors: If a non-supported type is written, then an `EWriteError` exception is.

## 2.35 TBits

### 2.35.1 Description

`TBits` can be used to store collections of bits in an indexed array. This is especially useful for storing collections of booleans: Normally the size of a boolean is the size of the smallest enumerated type, i.e. 1 byte. Since a bit can take 2 values it can be used to store a boolean as well. Since `TBits`

can store 8 bits in a byte, it takes 8 times less space to store an array of booleans in a `TBits` class than it would take to store them in a conventional array.

`TBits` introduces methods to store and retrieve bit values, apply masks, and search for bits.

### 2.35.2 Method overview

Page	Property	Description
<a href="#">267</a>	<code>AndBits</code>	Performs an <code>and</code> operation on the bits.
<a href="#">266</a>	<code>Clear</code>	Clears a particular bit.
<a href="#">267</a>	<code>Clearall</code>	Clears all bits in the array.
<a href="#">265</a>	<code>Create</code>	Creates a new bits collection.
<a href="#">265</a>	<code>Destroy</code>	Destroys a bit collection
<a href="#">269</a>	<code>Equals</code>	Determines whether the bits of 2 arrays are equal.
<a href="#">269</a>	<code>FindFirstBit</code>	Find first bit with a particular value
<a href="#">270</a>	<code>FindNextBit</code>	Searches the next bit with a particular value.
<a href="#">270</a>	<code>FindPrevBit</code>	Searches the previous bit with a particular value.
<a href="#">268</a>	<code>Get</code>	Retrieve the value of a particular bit
<a href="#">266</a>	<code>GetFSIZE</code>	Returns the number of records used to store the bits.
<a href="#">268</a>	<code>Grow</code>	Expands the bits array to the requested size.
<a href="#">268</a>	<code>NotBits</code>	Performs a <code>not</code> operation on the bits.
<a href="#">270</a>	<code>OpenBit</code>	Returns the position of the first bit that is set to <code>False</code> .
<a href="#">267</a>	<code>OrBits</code>	Performs an <code>or</code> operation on the bits.
<a href="#">269</a>	<code>SetIndex</code>	Sets the start position for <code>FindNextBit</code> ( <a href="#">270</a> ) and <code>FindPrevBit</code> ( <a href="#">270</a> )
<a href="#">266</a>	<code>SetOn</code>	Turn a particular bit on.
<a href="#">267</a>	<code>XorBits</code>	Performs a <code>xor</code> operation on the bits.

### 2.35.3 Property overview

Page	Property	Access	Description
<a href="#">271</a>	<code>Bits</code>	<code>rw</code>	Access to all bits in the array.
<a href="#">271</a>	<code>Size</code>	<code>rw</code>	Current size of the array of bits.

### 2.35.4 TBits.Create

Synopsis: Creates a new bits collection.

Declaration: `constructor Create(TheSize: LongInt); Virtual`

Visibility: `public`

Description: `Create` creates a new bit collection with initial size `TheSize`. The size of the collection can be changed later on.

All bits are initially set to zero.

See also: `TBits.Destroy` ([265](#))

### 2.35.5 TBits.Destroy

Synopsis: Destroys a bit collection

Declaration: `destructor Destroy; Override`

Visibility: `public`

**Description:** `Destroy` destroys a previously created bit collection and releases all memory used to store the bit collection.

`Destroy` should never be called directly, `Free` should be used instead.

**Errors:** None.

See also: `TBits.Create` (265)

### 2.35.6 TBits.GetFSize

**Synopsis:** Returns the number of records used to store the bits.

**Declaration:** `function GetFSize : LongInt`

**Visibility:** `public`

**Description:** `GetFSize` returns the number of records used to store the current number of bits.

**Errors:** None.

See also: `TBits.Size` (271)

### 2.35.7 TBits.SetOn

**Synopsis:** Turn a particular bit on.

**Declaration:** `procedure SetOn(Bit: LongInt)`

**Visibility:** `public`

**Description:** `SetOn` turns on the bit at position `bit`, i.e. sets it to 1. If `bit` is at a position bigger than the current size, the collection is expanded to the required size using `Grow` (268).

**Errors:** If `bit` is larger than the maximum allowed bits array size or is negative, an `EBitsError` (223) exception is raised.

See also: `TBits.Bits` (271), `TBits.clear` (266)

### 2.35.8 TBits.Clear

**Synopsis:** Clears a particular bit.

**Declaration:** `procedure Clear(Bit: LongInt)`

**Visibility:** `public`

**Description:** `Clear` clears the bit at position `bit`. If the array If `bit` is at a position bigger than the current size, the collection is expanded to the required size using `Grow` (268).

**Errors:** If `bit` is larger than the maximum allowed bits array size or is negative, an `EBitsError` (223) exception is raised.

See also: `TBits.Bits` (271), `TBits.clear` (266)

### 2.35.9 TBits.Clearall

Synopsis: Clears all bits in the array.

Declaration: `procedure Clearall`

Visibility: `public`

Description: `ClearAll` clears all bits in the array, i.e. sets them to zero. `ClearAll` works faster than clearing all individual bits, since it uses the packed nature of the bits.

Errors: None.

See also: `TBits.Bits` ([271](#)), `TBits.clear` ([266](#))

### 2.35.10 TBits.AndBits

Synopsis: Performs an `and` operation on the bits.

Declaration: `procedure AndBits(BitSet: TBits)`

Visibility: `public`

Description: `andbits` performs an `and` operation on the bits in the array with the bits of array `BitSet`. If `BitSet` contains less bits than the current array, then all bits which have no counterpart in `BitSet` are cleared.

Errors: None.

See also: `TBits.clearall` ([267](#)), `TBits.orbits` ([267](#)), `TBits.xorbits` ([267](#)), `TBits.notbits` ([268](#))

### 2.35.11 TBits.OrBits

Synopsis: Performs an `or` operation on the bits.

Declaration: `procedure OrBits(BitSet: TBits)`

Visibility: `public`

Description: `andbits` performs an `or` operation on the bits in the array with the bits of array `BitSet`.

If `BitSet` contains less bits than the current array, then all bits which have no counterpart in `BitSet` are left untouched.

If the current array contains less bits than `BitSet` then it is grown to the size of `BitSet` before the `or` operation is performed.

Errors: None.

See also: `TBits.clearall` ([267](#)), `TBits.andbits` ([267](#)), `TBits.xorbits` ([267](#)), `TBits.notbits` ([268](#))

### 2.35.12 TBits.XorBits

Synopsis: Performs a `xor` operation on the bits.

Declaration: `procedure XorBits(BitSet: TBits)`

Visibility: `public`

**Description:** `XorBits` performs a `xor` operation on the bits in the array with the bits of array `BitSet`.

If `BitSet` contains less bits than the current array, then all bits which have no counterpart in `BitSet` are left untouched.

If the current array contains less bits than `BitSet` then it is grown to the size of `BitSet` before the `xor` operation is performed.

Errors: None.

See also: `TBits.clearall` (267), `TBits.andbits` (267), `TBits.orbits` (267), `TBits.notbits` (268)

### 2.35.13 TBits.NotBits

**Synopsis:** Performs a `not` operation on the bits.

**Declaration:** `procedure NotBits(BitSet: TBits)`

Visibility: `public`

**Description:** `NotBits` performs a `not` operation on the bits in the array with the bits of array `Bitset`.

If `BitSet` contains less bits than the current array, then all bits which have no counterpart in `BitSet` are left untouched.

Errors: None.

See also: `TBits.clearall` (267), `TBits.andbits` (267), `TBits.orbits` (267), `TBits.xorbits` (267)

### 2.35.14 TBits.Get

**Synopsis:** Retrieve the value of a particular bit

**Declaration:** `function Get(Bit: LongInt) : Boolean`

Visibility: `public`

**Description:** `Get` returns `True` if the bit at position `bit` is set, or `False` if it is not set.

Errors: If `bit` is not a valid bit index then an `EBitsError` (223) exception is raised.

See also: `TBits.Bits` (271), `TBits.FindFirstBit` (269), `TBits.seton` (266)

### 2.35.15 TBits.Grow

**Synopsis:** Expands the bits array to the requested size.

**Declaration:** `procedure Grow(NBit: LongInt)`

Visibility: `public`

**Description:** `Grow` expands the bit array so it can at least contain `nbit` bits. If `nbit` is less than the current size, nothing happens.

Errors: If there is not enough memory to complete the operation, then an `EBitsError` (223) is raised.

See also: `TBits.Size` (271)

### 2.35.16 TBits.Equals

Synopsis: Determines whether the bits of 2 arrays are equal.

Declaration: `function Equals(Obj: TObject) : Boolean; Override; Overload`  
`function Equals(BitSet: TBits) : Boolean; Overload`

Visibility: public

Description: `equals` returns `True` if all the bits in `BitSet` are the same as the ones in the current `BitSet`; if not, `False` is returned.

If the sizes of the two `BitSets` are different, the arrays are still reported equal when all the bits in the larger set, which are not present in the smaller set, are zero.

Errors: None.

See also: `TBits.clearall` (267), `TBits.andbits` (267), `TBits.orbits` (267), `TBits.xorbits` (267)

### 2.35.17 TBits.SetIndex

Synopsis: Sets the start position for `FindNextBit` (270) and `FindPrevBit` (270)

Declaration: `procedure SetIndex(Index: LongInt)`

Visibility: public

Description: `SetIndex` sets the search start position for `FindNextBit` (270) and `FindPrevBit` (270) to `Index`. This means that these calls will start searching from position `Index`.

This mechanism provides an alternative to `FindFirstBit` (269) which can also be used to position for the `FindNextBit` and `FindPrevBit` calls.

Errors: None.

See also: `TBits.FindNextBit` (270), `TBits.FindPrevBit` (270), `TBits.FindFirstBit` (269), `TBits.OpenBit` (270)

### 2.35.18 TBits.FindFirstBit

Synopsis: Find first bit with a particular value

Declaration: `function FindFirstBit(State: Boolean) : LongInt`

Visibility: public

Description: `FindFirstBit` searches for the first bit with value `State`. It returns the position of this bit, or `-1` if no such bit was found.

The search starts at position 0 in the array. If the first search returned a positive result, the found position is saved, and the `FindNextBit` (270) and `FindPrevBit` (270) will use this position to resume the search. To start a search from a certain position, the start position can be set with the `SetIndex` (269) instead.

Errors: None.

See also: `TBits.FindNextBit` (270), `TBits.FindPrevBit` (270), `TBits.OpenBit` (270), `TBits.SetIndex` (269)

**2.35.19 TBits.FindNextBit**

Synopsis: Searches the next bit with a particular value.

Declaration: `function FindNextBit : LongInt`

Visibility: `public`

Description: `FindNextBit` resumes a previously started search. It searches for the next bit with the value specified in the `FindFirstBit` (269). The search is done towards the end of the array and starts at the position last reported by one of the `Find` calls or at the position set with `SetIndex` (269).

If another bit with the same value is found, its position is returned. If no more bits with the same value are present in the array, `-1` is returned.

Errors: None.

See also: `TBits.FindFirstBit` (269), `TBits.FindPrevBit` (270), `TBits.OpenBit` (270), `TBits.SetIndex` (269)

**2.35.20 TBits.FindPrevBit**

Synopsis: Searches the previous bit with a particular value.

Declaration: `function FindPrevBit : LongInt`

Visibility: `public`

Description: `FindPrevBit` resumes a previously started search. It searches for the previous bit with the value specified in the `FindFirstBit` (269). The search is done towards the beginning of the array and starts at the position last reported by one of the `Find` calls or at the position set with `SetIndex` (269).

If another bit with the same value is found, its position is returned. If no more bits with the same value are present in the array, `-1` is returned.

Errors: None.

See also: `TBits.FindFirstBit` (269), `TBits.FindNextBit` (270), `TBits.OpenBit` (270), `TBits.SetIndex` (269)

**2.35.21 TBits.OpenBit**

Synopsis: Returns the position of the first bit that is set to `False`.

Declaration: `function OpenBit : LongInt`

Visibility: `public`

Description: `OpenBit` returns the position of the first bit whose value is `0` (`False`), or `-1` if no open bit was found. This call is equivalent to `FindFirstBit(False)`, except that it doesn't set the position for the next searches.

Errors: None.

See also: `TBits.FindFirstBit` (269), `TBits.FindPrevBit` (270), `TBits.FindFirstBit` (269), `TBits.SetIndex` (269)



### 2.35.22 TBits.Bits

Synopsis: Access to all bits in the array.

Declaration: `Property Bits[Bit: LongInt]: Boolean; default`

Visibility: `public`

Access: `Read, Write`

Description: `Bits` allows indexed access to all of the bits in the array. It gives `True` if the bit is 1, `False` otherwise; Assigning to this property will set, respectively clear the bit.

Errors: If an index is specified which is out of the allowed range then an `EBitsError` (223) exception is raised.

See also: `TBits.Size` (271)

### 2.35.23 TBits.Size

Synopsis: Current size of the array of bits.

Declaration: `Property Size : LongInt`

Visibility: `public`

Access: `Read, Write`

Description: `Size` is the current size of the bit array. Setting this property will adjust the size; this is equivalent to calling `Grow(Value-1)`

Errors: If an invalid size (negative or too large) is specified, a `EBitsError` (223) exception is raised.

See also: `TBits.Bits` (271)

## 2.36 TCollection

### 2.36.1 Description

`TCollection` implements functionality to manage a collection of named objects. Each of these objects needs to be a descendent of the `TCollectionItem` (279) class. Exactly which type of object is managed can be seen from the `TCollection.ItemClass` (277) property.

Normally, no `TCollection` is created directly. Instead, a descendent of `TCollection` and `TCollectionItem` (279) are created as a pair.

### 2.36.2 Method overview

Page	Property	Description
<a href="#">273</a>	Add	Creates and adds a new item to the collection.
<a href="#">273</a>	Assign	Assigns one collection to another.
<a href="#">273</a>	BeginUpdate	Start an update batch.
<a href="#">274</a>	Clear	Removes all items from the collection.
<a href="#">272</a>	Create	Creates a new collection.
<a href="#">274</a>	Delete	Delete an item from the collection.
<a href="#">272</a>	Destroy	Destroys the collection and frees all the objects it manages.
<a href="#">274</a>	EndUpdate	Ends an update batch.
<a href="#">276</a>	Exchange	Exchange 2 items in the collection
<a href="#">275</a>	FindItemID	Searches for an Item in the collection, based on its TCollectionItem.ID ( <a href="#">280</a> ) property.
<a href="#">275</a>	GetEnumerator	Create an IEnumerator instance
<a href="#">275</a>	GetNamePath	Overrides TPersistent.GetNamePath ( <a href="#">339</a> ) to return a proper pathname.
<a href="#">275</a>	Insert	Insert an item in the collection.
<a href="#">273</a>	Owner	Owner of the collection.
<a href="#">276</a>	Sort	Sort the items in the collection

### 2.36.3 Property overview

Page	Property	Access	Description
<a href="#">276</a>	Count	r	Number of items in the collection.
<a href="#">277</a>	ItemClass	r	Class pointer for each item in the collection.
<a href="#">277</a>	Items	rw	Indexed array of items in the collection.

### 2.36.4 TCollection.Create

Synopsis: Creates a new collection.

Declaration: constructor Create(AItemClass: TCollectionItemClass)

Visibility: public

Description: Create instantiates a new instance of the TCollection class which will manage objects of class AItemClass. It creates the list used to hold all objects, and stores the AItemClass for the adding of new objects to the collection.

See also: TCollection.ItemClass ([277](#)), TCollection.Destroy ([272](#))

### 2.36.5 TCollection.Destroy

Synopsis: Destroys the collection and frees all the objects it manages.

Declaration: destructor Destroy; Override

Visibility: public

Description: Destroy first clears the collection, and then frees all memory allocated to this instance.

Don't call Destroy directly, call Free instead.

See also: TCollection.Create ([272](#))

### 2.36.6 TCollection.Owner

Synopsis: Owner of the collection.

Declaration: `function Owner : TPersistent`

Visibility: `public`

Description: `Owner` returns a reference to the owner of the collection. This property is required by the object inspector to be able to show the collection.

### 2.36.7 TCollection.Add

Synopsis: Creates and adds a new item to the collection.

Declaration: `function Add : TCollectionItem`

Visibility: `public`

Description: `Add` instantiates a new item of class `TCollection.ItemClass` (277) and adds it to the list. The newly created object is returned.

See also: `TCollection.ItemClass` (277), `TCollection.Clear` (274)

### 2.36.8 TCollection.Assign

Synopsis: Assigns one collection to another.

Declaration: `procedure Assign(Source: TPersistent); Override`

Visibility: `public`

Description: `Assign` assigns the contents of one collection to another. It does this by clearing the items list, and adding as much elements as there are in the `Source` collection; it assigns to each created element the contents of it's counterpart in the `Source` element.

Two collections cannot be assigned to each other if instances of the `ItemClass` classes cannot be assigned to each other.

Errors: If the objects in the collections cannot be assigned to one another, then an `EConvertError` is raised.

See also: `TPersistent.Assign` (339), `TCollectionItem` (279)

### 2.36.9 TCollection.BeginUpdate

Synopsis: Start an update batch.

Declaration: `procedure BeginUpdate; Virtual`

Visibility: `public`

Description: `BeginUpdate` is called at the beginning of a batch update. It raises the update count with 1.

Call `BeginUpdate` at the beginning of a series of operations that will change the state of the collection. This will avoid the call to `TCollection.Update` (271) for each operation. At the end of the operations, a corresponding call to `EndUpdate` must be made. It is best to do this in the context of a `Try ... finally` block:

```

With MyCollection Do
  try
    BeginUpdate;
    // Some Lengthy operations
  finally
    EndUpdate;
  end;

```

This insures that the number of calls to `BeginUpdate` always matches the number of calls to `TCollection.EndUpdate` (274), even in case of an exception.

See also: `TCollection.EndUpdate` (274), `TCollection.Changed` (271), `TCollection.Update` (271)

### 2.36.10 TCollection.Clear

Synopsis: Removes all items from the collection.

Declaration: `procedure Clear`

Visibility: `public`

Description: `Clear` will clear the collection, i.e. each item in the collection is destroyed and removed from memory. After a call to `Clear`, `Count` is zero.

See also: `TCollection.Add` (273), `TCollectionItem.Destroy` (279), `TCollection.Destroy` (272)

### 2.36.11 TCollection.EndUpdate

Synopsis: Ends an update batch.

Declaration: `procedure EndUpdate; Virtual`

Visibility: `public`

Description: `EndUpdate` signals the end of a series of operations that change the state of the collection, possibly triggering an update event. It does this by decreasing the update count with 1 and calling `TCollection.Changed` (271) it should always be used in conjunction with `TCollection.BeginUpdate` (273), preferably in the `Finally` section of a `Try ... Finally` block.

See also: `TCollection.BeginUpdate` (273), `TCollection.Changed` (271), `TCollection.Update` (271)

### 2.36.12 TCollection.Delete

Synopsis: Delete an item from the collection.

Declaration: `procedure Delete(Index: Integer)`

Visibility: `public`

Description: `Delete` deletes the item at (zero based) position `Index` from the collection. This will result in a `cnDeleted` notification.

Errors: If an invalid index is specified, an `EListError` exception is raised.

See also: `TCollection.Items` (277), `TCollection.Insert` (275), `TCollection.Clear` (274)

### 2.36.13 TCollection.GetEnumerator

Synopsis: Create an `IEnumerator` instance

Declaration: `function GetEnumerator : TCollectionEnumerator`

Visibility: public

Description: `GetEnumerator` is the implementation of the `IEnumerable` (1405) interface for `TCollection`. It creates a `TCollectionEnumerator` (277) instance and returns its `IEnumerator` (1406) interface.

See also: `TCollectionEnumerator` (277), `#rtl.system.IEnumerator` (1406), `#rtl.system.IEnumerable` (1405)

### 2.36.14 TCollection.GetNamePath

Synopsis: Overrides `TPersistent.GetNamePath` (339) to return a proper pathname.

Declaration: `function GetNamePath : String; Override`

Visibility: public

Description: `GetNamePath` returns the name path for this collection. If the following conditions are satisfied:

1. There is an owner object.
2. The owner object returns a non-empty name path.
3. The `TCollection.Propname` (271) property is not empty

collection has an owner and the owning object has a name, then the function returns the owner name, followed by the propname. If one of the conditions is not satisfied, then the classname is returned.

See also: `TCollection.GetOwner` (271), `TCollection.Propname` (271)

### 2.36.15 TCollection.Insert

Synopsis: Insert an item in the collection.

Declaration: `function Insert(Index: Integer) : TCollectionItem`

Visibility: public

Description: `Insert` creates a new item instance and inserts it in the collection at position `Index`, and returns the new instance.

In contrast, `TCollection.Add` (273) adds a new item at the end.

Errors: None.

See also: `TCollection.Add` (273), `TCollection.Delete` (274), `TCollection.Items` (277)

### 2.36.16 TCollection.FindItemID

Synopsis: Searches for an Item in the collection, based on its `TCollectionItem.ID` (280) property.

Declaration: `function FindItemID(ID: Integer) : TCollectionItem`

Visibility: public

**Description:** `FindItemID` searches through the collection for the item that has a value of `ID` for its `TCollectionItem.ID` (280) property, and returns the found item. If no such item is found in the collection, `Nil` is returned.

The routine performs a linear search, so this can be slow on very large collections.

See also: `TCollection.Items` (277), `TCollectionItem.ID` (280)

### 2.36.17 TCollection.Exchange

**Synopsis:** Exchange 2 items in the collection

**Declaration:** `procedure Exchange(const Index1: Integer; const index2: Integer)`

**Visibility:** public

**Description:** `Exchange` exchanges the items at indexes `Index1` and `Index2` in the collection.

**Errors:** If one of the two indexes is invalid (less than zero or larger than the number of items) an `EListError` exception is raised.

See also: `TCollection.Items` (277), `TCollectionItem.Index` (280)

### 2.36.18 TCollection.Sort

**Synopsis:** Sort the items in the collection

**Declaration:** `procedure Sort(const Compare: TCollectionSortCompare)`

**Visibility:** public

**Description:** `Sort` sorts the items in the collection, and uses the `Compare` procedure to compare 2 items in the collection. It is more efficient to use this method than to perform the sort manually, because the list items are manipulated directly.

For more information on how the `Compare` function should behave, see the `TCollectionSortCompare` (198) type.

See also: `TCollectionSortCompare` (198)

### 2.36.19 TCollection.Count

**Synopsis:** Number of items in the collection.

**Declaration:** `Property Count : Integer`

**Visibility:** public

**Access:** Read

**Description:** `Count` contains the number of items in the collection.

**Remark:** The items in the collection are identified by their `TCollectionItem.Index` (280) property, which is a zero-based index, meaning that it can take values between 0 and `Count-1`, borders included.

See also: `TCollectionItem.Index` (280), `TCollection.Items` (277)

### 2.36.20 TCollection.ItemClass

Synopsis: Class pointer for each item in the collection.

Declaration: `Property ItemClass : TCollectionItemClass`

Visibility: public

Access: Read

Description: `ItemClass` is the class pointer with which each new item in the collection is created. It is the value that was passed to the collection's constructor when it was created, and does not change during the lifetime of the collection.

See also: `TCollectionItem` (279), `TCollection.Items` (277)

### 2.36.21 TCollection.Items

Synopsis: Indexed array of items in the collection.

Declaration: `Property Items[Index: Integer]: TCollectionItem`

Visibility: public

Access: Read, Write

Description: `Items` provides indexed access to the items in the collection. Since the array is zero-based, `Index` should be an integer between 0 and `Count-1`.

It is possible to set or retrieve an element in the array. When setting an element of the array, the object that is assigned should be compatible with the class of the objects in the collection, as given by the `TCollection.ItemClass` (277) property.

Adding an element to the array can be done with the `TCollection.Add` (273) method. The array can be cleared with the `TCollection.Clear` (274) method. Removing an element of the array should be done by freeing that element.

See also: `TCollection.Count` (276), `TCollection.ItemClass` (277), `TCollection.Clear` (274), `TCollection.Add` (273)

## 2.37 TCollectionEnumerator

### 2.37.1 Description

`TCollectionEnumerator` implements the `#rtl.system.IEnumerator` (1406) interface for the `TCollection` (271) class, so the `TCollection` class can be used in a `for ... in` loop. It is returned by the `TCollection.GetEnumerator` (275) method of `TCollection`.

### 2.37.2 Method overview

Page	Property	Description
278	Create	Initialize a new instance of <code>TCollectionEnumerator</code>
278	GetCurrent	Return the current pointer in the list
278	MoveNext	Move the position of the enumerator to the next position in the collection.

### 2.37.3 Property overview

Page	Property	Access	Description
<a href="#">278</a>	Current	r	Current pointer in the list

### 2.37.4 TCollectionEnumerator.Create

Synopsis: Initialize a new instance of `TCollectionEnumerator`

Declaration: `constructor Create (ACollection: TCollection)`

Visibility: `public`

Description: `Create` initializes a new instance of `TCollectionEnumerator` and keeps a reference to the collection `ACollection` that will be enumerated.

See also: `TCollection` ([271](#))

### 2.37.5 TCollectionEnumerator.GetCurrent

Synopsis: Return the current pointer in the list

Declaration: `function GetCurrent : TCollectionItem`

Visibility: `public`

Description: `GetCurrent` returns the current `TCollectionItem` ([279](#)) instance in the enumerator.

Errors: No checking is done on the validity of the current position.

See also: `TCollectionEnumerator.MoveNext` ([278](#)), `TCollectionItem` ([279](#))

### 2.37.6 TCollectionEnumerator.MoveNext

Synopsis: Move the position of the enumerator to the next position in the collection.

Declaration: `function MoveNext : Boolean`

Visibility: `public`

Description: `MoveNext` puts the pointer on the next item in the collection, and returns `True` if this succeeded, or `False` if the pointer is past the last element in the list.

Errors: Note that if `False` is returned, calling `GetCurrent` will result in an exception.

See also: `TCollectionEnumerator.GetCurrent` ([278](#))

### 2.37.7 TCollectionEnumerator.Current

Synopsis: Current pointer in the list

Declaration: `Property Current : TCollectionItem`

Visibility: `public`

Access: `Read`

Description: `Current` redefines `GetCurrent` ([278](#)) as a property.

See also: `TCollectionEnumerator.GetCurrent` ([278](#))



## 2.38 TCollectionItem

### 2.38.1 Description

TCollectionItem and TCollection (271) form a pair of base classes that manage a collection of named objects. The TCollectionItem is the named object that is managed, it represents one item in the collection. An item in the collection is represented by three properties: TCollectionItem.DisplayName (281), TCollection.Index (271) and TCollectionItem.ID (280).

A TCollectionItem object is never created directly. To manage a set of named items, it is necessary to make a descendant of TCollectionItem to which needed properties and methods are added. This descendant can then be managed with a TCollection (271) class. The managing collection will create and destroy it's items by itself, it should therefore never be necessary to create TCollectionItem descendents manually.

### 2.38.2 Method overview

Page	Property	Description
<a href="#">279</a>	Create	Creates a new instance of this collection item.
<a href="#">279</a>	Destroy	Destroys this collection item.
<a href="#">280</a>	GetNamePath	Returns the namepath of this collection item.

### 2.38.3 Property overview

Page	Property	Access	Description
<a href="#">280</a>	Collection	rw	Pointer to the collection managing this item.
<a href="#">281</a>	DisplayName	rw	Name of the item, displayed in the object inspector.
<a href="#">280</a>	ID	r	Initial index of this item.
<a href="#">280</a>	Index	rw	Index of the item in its managing collection TCollection.Items ( <a href="#">277</a> ) property.

### 2.38.4 TCollectionItem.Create

Synopsis: Creates a new instance of this collection item.

Declaration: `constructor Create(ACollection: TCollection); Virtual`

Visibility: `public`

Description: `Create` instantiates a new item in a TCollection (271). It is called by the TCollection.Add (273) function and should under normal circumstances never be called directly. called

See also: TCollectionItem.Destroy ([279](#))

### 2.38.5 TCollectionItem.Destroy

Synopsis: Destroys this collection item.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` removes the item from the managing collection and Destroys the item instance.

This is the only way to remove items from a collection;

See also: TCollectionItem.Create ([279](#))

### 2.38.6 TCollectionItem.GetNamePath

Synopsis: Returns the namepath of this collection item.

Declaration: `function GetNamePath : String; Override`

Visibility: public

Description: `GetNamePath` overrides the `TPersistent.GetNamePath` (339) method to return the name of the managing collection and appends its `TCollectionItem.Index` (280) property.

See also: `TCollectionItem.Collection` (280), `TPersistent.GetNamePath` (339), `TCollectionItem.Index` (280)

### 2.38.7 TCollectionItem.Collection

Synopsis: Pointer to the collection managing this item.

Declaration: `Property Collection : TCollection`

Visibility: public

Access: Read,Write

Description: `Collection` points to the collection managing this item. This property can be set to point to a new collection. If this is done, the old collection will be notified that the item should no longer be managed, and the new collection is notified that it should manage this item as well.

See also: `TCollection` (271)

### 2.38.8 TCollectionItem.ID

Synopsis: Initial index of this item.

Declaration: `Property ID : Integer`

Visibility: public

Access: Read

Description: `ID` is the initial value of `TCollectionItem.Index` (280); it doesn't change after the index changes. It can be used to uniquely identify the item. The `ID` property doesn't change as items are added and removed from the collection.

While the `TCollectionItem.Index` (280) property forms a continuous series, `ID` does not. If items are removed from the collection, their `ID` is not used again, leaving gaps. Only when the collection is initially created, the `ID` and `Index` properties will be equal.

See also: `TCollection.Items` (277), `TCollectionItem.Index` (280)

### 2.38.9 TCollectionItem.Index

Synopsis: Index of the item in its managing collection `TCollection.Items` (277) property.

Declaration: `Property Index : Integer`

Visibility: public

Access: Read,Write

**Description:** `Index` is the current index of the item in its managing collection's `TCollection.Items` (277) property. This property may change as items are added and removed from the collection.

The index of an item is zero-based, i.e. the first item has index zero. The last item has index `Count-1` where `Count` is the number of items in the collection.

The `Index` property of the items in a collection form a continuous series ranging from 0 to `Count-1`. The `TCollectionItem.ID` (280) property does not form a continuous series, but can also be used to identify an item.

See also: `TCollectionItem.ID` (280), `TCollection.Items` (277)

### 2.38.10 TCollectionItem.DisplayName

**Synopsis:** Name of the item, displayed in the object inspector.

**Declaration:** `Property DisplayName : String`

**Visibility:** `public`

**Access:** `Read,Write`

**Description:** `DisplayName` contains the name of this item as shown in the object inspector. For `TCollectionItem` this returns always the class name of the managing collection, followed by the index of the item.

`TCollectionItem` does not implement any functionality to store the `DisplayName` property. The property can be set, but this will have no effect other than that the managing collection is notified of a change. The actual displayname will remain unchanged. To store the `DisplayName` property, `TCollectionItem` descendants should override the `TCollectionItem.SetDisplayName` (279) and `TCollectionItem.GetDisplayName` (279) to add storage functionality.

See also: `TCollectionItem.Index` (280), `TCollectionItem.ID` (280), `TCollectionItem.GetDisplayName` (279), `TCollectionItem.SetDisplayName` (279)

## 2.39 TComponent

### 2.39.1 Description

`TComponent` is the base class for any set of classes that needs owner-owned functionality, and which needs support for property streaming. All classes that should be handled by an IDE (Integrated Development Environment) must descend from `TComponent`, as it includes all support for streaming all its published properties.

Components can 'own' other components. `TComponent` introduces methods for enumerating the child components. It also allows to name the owned components with a unique name. Furthermore, functionality for sending notifications when a component is removed from the list or removed from memory altogether is also introduced in `TComponent`.

`TComponent` introduces a form of automatic memory management: When a component is destroyed, all its child components will be destroyed first.

**2.39.2 Method overview**

Page	Property	Description
<a href="#">283</a>	BeforeDestruction	Overrides standard BeforeDestruction.
<a href="#">283</a>	Create	Creates a new instance of the component.
<a href="#">283</a>	Destroy	Destroys the instance of the component.
<a href="#">283</a>	DestroyComponents	Destroy child components.
<a href="#">284</a>	Destroying	Called when the component is being destroyed
<a href="#">284</a>	ExecuteAction	Standard action execution method.
<a href="#">284</a>	FindComponent	Finds and returns the named component in the owned components.
<a href="#">285</a>	FreeNotification	Ask the component to notify called when it is being destroyed.
<a href="#">285</a>	FreeOnRelease	Part of the <code>IVCLComObject</code> interface.
<a href="#">285</a>	GetEnumerator	Create an <code>IEnumerator</code> instance
<a href="#">285</a>	GetNamePath	Returns the name path of this component.
<a href="#">286</a>	GetParentComponent	Returns the parent component.
<a href="#">286</a>	HasParent	Does the component have a parent ?
<a href="#">286</a>	InsertComponent	Insert the given component in the list of owned components.
<a href="#">288</a>	IsImplementorOf	Checks if the current component is the implementor of the interface
<a href="#">288</a>	ReferenceInterface	Interface implementation of Notification
<a href="#">287</a>	RemoveComponent	Remove the given component from the list of owned components.
<a href="#">285</a>	RemoveFreeNotification	Remove a component from the Free Notification list.
<a href="#">287</a>	SafeCallException	Part of the <code>IVCLComObject</code> Interface.
<a href="#">287</a>	SetSubComponent	Sets the <code>csSubComponent</code> style.
<a href="#">287</a>	UpdateAction	Updates the state of an action.
<a href="#">282</a>	WriteState	Writes the component to a stream.

**2.39.3 Property overview**

Page	Property	Access	Description
<a href="#">288</a>	ComponentCount	r	Count of owned components
<a href="#">289</a>	ComponentIndex	rw	Index of component in it's owner's list.
<a href="#">288</a>	Components	r	Indexed list (zero-based) of all owned components.
<a href="#">289</a>	ComponentState	r	Current component's state.
<a href="#">289</a>	ComponentStyle	r	Current component's style.
<a href="#">290</a>	DesignInfo	rw	Information for IDE designer.
<a href="#">290</a>	Name	rws	Name of the component.
<a href="#">290</a>	Owner	r	Owner of this component.
<a href="#">291</a>	Tag	rw	Tag value of the component.
<a href="#">290</a>	VCLComObject	rw	Not implemented.

**2.39.4 TComponent.WriteState**

Synopsis: Writes the component to a stream.

Declaration: `procedure WriteState(Writer: TWriter); Virtual`

Visibility: `public`

Description: `WriteState` writes the component's current state to a stream through the writer ([398](#)) object `writer`. Values for all published properties of the component can be written to the stream. Normally there is no need to call `WriteState` directly. The streaming system calls `WriteState` itself.

The `TComponent` (281) implementation of `WriteState` simply calls `TWriter.WriteData` (398). Descendent classes can, however, override `WriteState` to provide additional processing of stream data.

See also: `TComponent.ReadState` (281), `TStream.WriteComponent` (359), `TWriter.WriteData` (398)

### 2.39.5 TComponent.Create

Synopsis: Creates a new instance of the component.

Declaration: `constructor Create(AOwner: TComponent); Virtual`

Visibility: `public`

Description: `Create` creates a new instance of a `TComponent` class. If `AOwner` is not `Nil`, the new component attempts to insert itself in the list of owned components of the owner.

See also: `TComponent.Insert` (281), `TComponent.Owner` (290)

### 2.39.6 TComponent.Destroy

Synopsis: Destroys the instance of the component.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` sends a `opRemove` notification to all components in the free-notification list. After that, all owned components are destroyed by calling `DestroyComponents` (283) (and hence removed from the list of owned components). When this is done, the component removes itself from its owner's child component list. After that, the parent's destroy method is called.

See also: `TComponent.Notification` (281), `TComponent.Owner` (290), `TComponent.DestroyComponents` (283), `TComponent.Components` (288)

### 2.39.7 TComponent.BeforeDestruction

Synopsis: Overrides standard `BeforeDestruction`.

Declaration: `procedure BeforeDestruction; Override`

Visibility: `public`

Description: `BeforeDestruction` is overridden by `TComponent` to set the `csDestroying` flag in `ComponentState` (194)

See also: `ComponentState` (194)

### 2.39.8 TComponent.DestroyComponents

Synopsis: Destroy child components.

Declaration: `procedure DestroyComponents`

Visibility: `public`

**Description:** `DestroyComponents` calls the destructor of all owned components, till no more components are left in the `Components` (288) array.

Calling the destructor of an owned component has as the effect that the component will remove itself from the list of owned components, if nothing has disrupted the sequence of destructors.

**Errors:** If an overridden 'destroy' method does not call it's inherited destructor or raises an exception, it's `TComponent.Destroy` (283) destructor will not be called, which may result in an endless loop.

See also: `TComponent.Destroy` (283), `TComponent.Components` (288)

### 2.39.9 TComponent.Destroying

**Synopsis:** Called when the component is being destroyed

**Declaration:** `procedure Destroying`

**Visibility:** public

**Description:** `Destroying` sets the `csDestroying` flag in the component's state (281) property, and does the same for all owned components.

It is not necessary to call `Destroying` directly, the destructor `Destroy` (283) does this automatically.

See also: `TComponent.State` (281), `TComponent.Destroy` (283)

### 2.39.10 TComponent.ExecuteAction

**Synopsis:** Standard action execution method.

**Declaration:** `function ExecuteAction(Action: TBasicAction) : Boolean; Dynamic`

**Visibility:** public

**Description:** `ExecuteAction` checks whether `Action` handles the current component, and if yes, calls the `ExecuteAction` method, passing itself as a parameter. The function returns `True` if the action handles the current component.

See also: `TBasicAction` (247), `TBasicAction.ExecuteAction` (247), `TBasicAction.HandlesTarget` (248), `UpdateAction` (194)

### 2.39.11 TComponent.FindComponent

**Synopsis:** Finds and returns the named component in the owned components.

**Declaration:** `function FindComponent(const AName: String) : TComponent`

**Visibility:** public

**Description:** `FindComponent` searches the component with name `AName` in the list of owned components. If `AName` is empty, then `Nil` is returned.

See also: `TComponent.Components` (288), `TComponent.Name` (290)

### 2.39.12 TComponent.FreeNotification

Synopsis: Ask the component to notify called when it is being destroyed.

Declaration: `procedure FreeNotification (AComponent: TComponent)`

Visibility: `public`

Description: `FreeNotification` inserts `AComponent` in the `freenotification` list. When the component is destroyed, the `Notification` (281) method is called for all components in the `freenotification` list.

See also: `TComponent.Components` (288), `TComponent.Notification` (281), `TComponent.RemoveFreeNotification` (285)

### 2.39.13 TComponent.RemoveFreeNotification

Synopsis: Remove a component from the Free Notification list.

Declaration: `procedure RemoveFreeNotification (AComponent: TComponent)`

Visibility: `public`

Description: `RemoveFreeNotification` removes `AComponent` from the `freenotification` list.

See also: `TComponent.FreeNotification` (285)

### 2.39.14 TComponent.FreeOnRelease

Synopsis: Part of the `IVCLComObject` interface.

Declaration: `procedure FreeOnRelease`

Visibility: `public`

Description: Provided for Delphi compatibility, but is not yet implemented.

### 2.39.15 TComponent.GetEnumerator

Synopsis: Create an `IEnumerator` instance

Declaration: `function GetEnumerator : TComponentEnumerator`

Visibility: `public`

Description: `GetEnumerator` is the implementation of the `IEnumerable` (1405) interface for `TComponent`. It creates a `TComponentEnumerator` (291) instance and returns its `IEnumerator` (1406) interface. The enumerator enumerates all child components of the component instance.

See also: `TComponentEnumerator` (291), `#rtl.system.IEnumerator` (1406), `#rtl.system.IEnumerable` (1405)

### 2.39.16 TComponent.GetNamePath

Synopsis: Returns the name path of this component.

Declaration: `function GetNamePath : String; Override`

Visibility: `public`

**Description:** `GetNamePath` returns the name of the component as it will be shown in the object inspector.

`TComponent` overrides `GetNamePath` so it returns the `Name` (290) property of the component.

See also: `TComponent.Name` (290), `TPersistent.GetNamePath` (339)

### 2.39.17 TComponent.GetParentComponent

**Synopsis:** Returns the parent component.

**Declaration:** `function GetParentComponent : TComponent; Dynamic`

**Visibility:** `public`

**Description:** `GetParentComponent` can be implemented to return the parent component of this component.

The implementation of this method in `TComponent` always returns `Nil`. Descendent classes must override this method to return the visual parent of the component.

See also: `TComponent.HasParent` (286), `TComponent.Owner` (290)

### 2.39.18 TComponent.HasParent

**Synopsis:** Does the component have a parent ?

**Declaration:** `function HasParent : Boolean; Dynamic`

**Visibility:** `public`

**Description:** `HasParent` can be implemented to return whether the parent of the component exists. The implementation of this method in `TComponent` always returns `False`, and should be overridden by descendent classes to return `True` when a parent is available. If `HasParent` returns `True`, then `GetParentComponent` (286) will return the parent component.

See also: `TComponent.HasParent` (286), `TComponent.Owner` (290)

### 2.39.19 TComponent.InsertComponent

**Synopsis:** Insert the given component in the list of owned components.

**Declaration:** `procedure InsertComponent (AComponent : TComponent)`

**Visibility:** `public`

**Description:** `InsertComponent` attempts to insert `AComponent` in the list with owned components. It first calls `ValidateComponent` (281) to see whether the component can be inserted. It then checks whether there are no name conflicts by calling `ValidateRename` (281). If neither of these checks have raised an exception the component is inserted, and notified of the insert.

See also: `TComponent.RemoveComponent` (287), `TComponent.Insert` (281), `TComponent.ValidateContainer` (281), `TComponent.ValidateRename` (281), `TComponent.Notification` (281)



### 2.39.20 TComponent.RemoveComponent

Synopsis: Remove the given component from the list of owned components.

Declaration: `procedure RemoveComponent (AComponent : TComponent)`

Visibility: `public`

Description: `RemoveComponent` will send an `opRemove` notification to `AComponent` and will then proceed to remove `AComponent` from the list of owned components.

See also: `TComponent.InsertComponent` (286), `TComponent.Remove` (281), `TComponent.ValidateRename` (281), `TComponent.Notification` (281)

### 2.39.21 TComponent.SafeCallException

Synopsis: Part of the `IVCLComObject` Interface.

Declaration: `function SafeCallException (ExceptObject : TObject; ExceptAddr : Pointer)  
: Integer; Override`

Visibility: `public`

Description: Provided for Delphi compatibility, but not implemented.

### 2.39.22 TComponent.SetSubComponent

Synopsis: Sets the `csSubComponent` style.

Declaration: `procedure SetSubComponent (ASubComponent : Boolean)`

Visibility: `public`

Description: `SetSubComponent` includes `csSubComponent` in the `ComponentStyle` (289) property if `ASubComponent` is `True`, and excludes it again if `ASubComponent` is `False`.

See also: `TComponent.ComponentStyle` (289)

### 2.39.23 TComponent.UpdateAction

Synopsis: Updates the state of an action.

Declaration: `function UpdateAction (Action : TBasicAction) : Boolean; Dynamic`

Visibility: `public`

Description: `UpdateAction` checks whether `Action` handles the current component, and if yes, calls the `UpdateTarget` method, passing itself as a parameter. The function returns `True` if the action handles the current component.

See also: `TBasicAction` (247), `TBasicAction.UpdateTarget` (249), `TBasicAction.HandlesTarget` (248), `ExecuteAction` (194)

**2.39.24 TComponent.IsImplementorOf**

Synopsis: Checks if the current component is the implementor of the interface

Declaration: `function IsImplementorOf(const Intf: IInterface) : Boolean`

Visibility: public

Description: `IsImplementorOf` returns `True` if the current component implements the given interface. The interface should descend from `IInterfaceComponentReference` (227) and the `GetComponent` method should return the current instance.

See also: `IInterfaceComponentReference` (227)

**2.39.25 TComponent.ReferenceInterface**

Synopsis: Interface implementation of Notification

Declaration: `procedure ReferenceInterface(const intf: IInterface; op: TOperation)`

Visibility: public

Description: `ReferenceInterface` can be used to notify an interface of a component operation: it is the equivalent of the `TComponent.Notification` (281) method of `TComponent` for interfaces. If the interface implements `IInterfaceComponentReference` (227), then the component that implements the interface is notified of the given operation `Op`.

Errors: None.

See also: `TComponent.Notification` (281), `IInterfaceComponentReference` (227)

**2.39.26 TComponent.Components**

Synopsis: Indexed list (zero-based) of all owned components.

Declaration: `Property Components[Index: Integer]: TComponent`

Visibility: public

Access: Read

Description: `Components` provides indexed access to the list of owned components. `Index` can range from 0 to `ComponentCount-1` (288).

See also: `TComponent.ComponentCount` (288), `TComponent.Owner` (290)

**2.39.27 TComponent.ComponentCount**

Synopsis: Count of owned components

Declaration: `Property ComponentCount : Integer`

Visibility: public

Access: Read

Description: `ComponentCount` returns the number of components that the current component owns. It can be used to determine the valid index range in the `Component` (288) array.

See also: `TComponent.Components` (288), `TComponent.Owner` (290)

**2.39.28 TComponent.ComponentIndex**

Synopsis: Index of component in it's owner's list.

Declaration: `Property ComponentIndex : Integer`

Visibility: public

Access: Read,Write

Description: `ComponentIndex` is the index of the current component in its owner's list of components. If the component has no owner, the value of this property is -1.

See also: `TComponent.Components` (288), `TComponent.ComponentCount` (288), `TComponent.Owner` (290)

**2.39.29 TComponent.ComponentState**

Synopsis: Current component's state.

Declaration: `Property ComponentState : TComponentState`

Visibility: public

Access: Read

Description: `ComponentState` indicates the current state of the component. It is a set of flags which indicate the various stages in the lifetime of a component. The following values can occur in this set:

Table 2.18: Component states

Flag	Meaning
<code>csLoading</code>	The component is being loaded from stream
<code>csReading</code>	Component properties are being read from stream.
<code>csWriting</code>	Component properties are weing written to stream.
<code>csDestroying</code>	The component or one of it's owners is being destroyed.
<code>csAncestor</code>	The component is being streamed as part of a frame
<code>csUpdating</code>	The component is being updated
<code>csFixups</code>	References to other components are being resolved
<code>csFreeNotification</code>	The component has freenotifications.
<code>csInline</code>	The component is being loaded as part of a frame
<code>csDesignInstance</code>	? not used.

The component state is set by various actions such as reading it from stream, destroying it etc.

See also: `TComponent.SetAncestor` (281), `TComponent.SetDesigning` (281), `TComponent.SetInline` (281), `TComponent.SetDesignInstance` (281), `TComponent.Updating` (281), `TComponent.Updated` (281), `TComponent.Loaded` (281)

**2.39.30 TComponent.ComponentStyle**

Synopsis: Current component's style.

Declaration: `Property ComponentStyle : TComponentStyle`

Visibility: public

Access: Read

Description: Current component's style.

### 2.39.31 TComponent.DesignInfo

Synopsis: Information for IDE designer.

Declaration: `Property DesignInfo : LongInt`

Visibility: `public`

Access: `Read,Write`

Description: `DesignInformation` can be used by an IDE to store design information in the component. It should not be used by an application programmer.

See also: `TComponent.Tag` ([291](#))

### 2.39.32 TComponent.Owner

Synopsis: Owner of this component.

Declaration: `Property Owner : TComponent`

Visibility: `public`

Access: `Read`

Description: `Owner` returns the owner of this component. The owner cannot be set except by explicitly inserting the component in another component's owned components list using that component's `InsertComponent` ([286](#)) method, or by removing the component from it's owner's owned component list using the `RemoveComponent` ([287](#)) method.

See also: `TComponent.Components` ([288](#)), `TComponent.InsertComponent` ([286](#)), `TComponent.RemoveComponent` ([287](#))

### 2.39.33 TComponent.VCLComObject

Synopsis: Not implemented.

Declaration: `Property VCLComObject : Pointer`

Visibility: `public`

Access: `Read,Write`

Description: `VCLComObject` is not yet implemented in Free Pascal.

### 2.39.34 TComponent.Name

Synopsis: Name of the component.

Declaration: `Property Name : TComponentName`

Visibility: `published`

Access: `Read,Write`

**Description:** `Name` is the name of the component. This name should be a valid identifier, i.e. must start with a letter or underscore, and can contain only letters, numbers and the underscore character. When attempting to set the name of a component, the name will be checked for validity. Furthermore, when a component is owned by another component, the name must be either empty or must be unique among the child component names.

By "letters", 7-bit letters are meant.

**Errors:** Attempting to set the name to an invalid value will result in an exception being raised.

See also: `TComponent.ValidateRename` (281), `TComponent.Owner` (290)

### 2.39.35 TComponent.Tag

**Synopsis:** Tag value of the component.

**Declaration:** `Property Tag : LongInt`

**Visibility:** published

**Access:** Read,Write

**Description:** `Tag` can be used to store an integer value in the component. This value is streamed together with all other published properties. It can be used for instance to quickly identify a component in an event handler.

See also: `TComponent.Name` (290)

## 2.40 TComponentEnumerator

### 2.40.1 Description

`TComponentEnumerator` implements the `#rtl.system.IEnumerator` (1406) interface for the `TComponent` (281) class, so the `TComponent` class can be used in a `for ... in` loop over the `TComponent.Components` (288) child components of the component. It is returned by the `TComponent.GetEnumerator` (285) method of `TComponent`.

### 2.40.2 Method overview

Page	Property	Description
<a href="#">291</a>	Create	Initialize a new instance of <code>TComponentEnumerator</code>
<a href="#">292</a>	GetCurrent	Return the current pointer in the list
<a href="#">292</a>	MoveNext	Move the position of the enumerator to the next position in the children of the component.

### 2.40.3 Property overview

Page	Property	Access	Description
<a href="#">292</a>	Current	r	Current pointer in the list

### 2.40.4 TComponentEnumerator.Create

**Synopsis:** Initialize a new instance of `TComponentEnumerator`

**Declaration:** `constructor Create (AComponent : TComponent)`

**Visibility:** `public`

**Description:** `Create` initializes a new instance of `TComponentEnumerator` and keeps a reference to the component `AComponent` that will be enumerated.

**See also:** `TComponent` ([281](#))

### 2.40.5 TComponentEnumerator.GetCurrent

**Synopsis:** Return the current pointer in the list

**Declaration:** `function GetCurrent : TComponent`

**Visibility:** `public`

**Description:** `GetCurrent` returns the current `TComponent` ([281](#)) child component instance in the enumerator.

**Errors:** No checking is done on the validity of the current position.

**See also:** `TComponentEnumerator.MoveNext` ([292](#)), `TComponent.Components` ([288](#))

### 2.40.6 TComponentEnumerator.MoveNext

**Synopsis:** Move the position of the enumerator to the next position in the children of the component.

**Declaration:** `function MoveNext : Boolean`

**Visibility:** `public`

**Description:** `MoveNext` puts the pointer on the next child in the components child components, and returns `True` if this succeeded, or `False` if the pointer is past the last child in the list.

**Errors:** Note that if `False` is returned, calling `GetCurrent` will result in an exception.

**See also:** `TComponentEnumerator.GetCurrent` ([292](#))

### 2.40.7 TComponentEnumerator.Current

**Synopsis:** Current pointer in the list

**Declaration:** `Property Current : TComponent`

**Visibility:** `public`

**Access:** `Read`

**Description:** `Current` redefines `GetCurrent` ([292](#)) as a property.

**See also:** `TComponentEnumerator.GetCurrent` ([292](#))

## 2.41 TCustomMemoryStream

### 2.41.1 Description

TCustomMemoryStream is the parent class for streams that stored their data in memory. It introduces all needed functions to handle reading from and navigating through the memory, and introduces a Memory (295) property which points to the memory area where the stream data is kept.

The only thing which TCustomMemoryStream does not do is obtain memory to store data when writing data or the writing of data. This functionality is implemented in descendent streams such as TMemoryStream (328). The reason for this approach is that this way it is possible to create e.g. read-only descendents of TCustomMemoryStream that point to a fixed part in memory which can be read from, but not written to.

**Remark:** Since TCustomMemoryStream is an abstract class, do not create instances of TMemoryStream directly. Instead, create instances of descendents such as TMemoryStream (328).

### 2.41.2 Method overview

Page	Property	Description
<a href="#">293</a>	GetSize	return the size of the stream.
<a href="#">293</a>	Read	Reads Count bytes from the stream into buffer.
<a href="#">294</a>	SaveToFile	Writes the contents of the stream to a file.
<a href="#">294</a>	SaveToStream	Writes the contents of the memory stream to another stream.
<a href="#">294</a>	Seek	Sets a new position in the stream.

### 2.41.3 Property overview

Page	Property	Access	Description
<a href="#">295</a>	Memory	r	Pointer to the data kept in the memory stream.

### 2.41.4 TCustomMemoryStream.GetSize

Synopsis: return the size of the stream.

Declaration: `function GetSize : Int64; Override`

Visibility: public

Description: GetSize returns the size of the reserved memory. It should not be used directly.

See also: TStream.Size (364)

### 2.41.5 TCustomMemoryStream.Read

Synopsis: Reads Count bytes from the stream into buffer.

Declaration: `function Read(var Buffer; Count: LongInt) : LongInt; Override`

Visibility: public

Description: Read reads Count bytes from the stream into the memory pointed to by buffer. It returns the number of bytes actually read.

This method overrides the TStream.Read (356) method of TStream (355). It will read as much bytes as are still available in the memory area pointer to by Memory (295). After the bytes are read, the internal stream position is updated.

See also: `TCustomMemoryStream.Memory` (295), `TStream.Read` (356)

### 2.41.6 `TCustomMemoryStream.Seek`

Synopsis: Sets a new position in the stream.

Declaration: `function Seek(Offset: LongInt; Origin: Word) : LongInt; Override`

Visibility: public

Description: `Seek` overrides the abstract `TStream.Seek` (356) method. It simply updates the internal stream position, and returns the new position.

Errors: No checking is done whether the new position is still a valid position, i.e. whether the position is still within the range `0..Size`. Attempting a seek outside the valid memory range of the stream may result in an exception at the next read or write operation.

See also: `TStream.Position` (363), `TStream.Size` (364), `TCustomMemoryStream.Memory` (295)

### 2.41.7 `TCustomMemoryStream.SaveToStream`

Synopsis: Writes the contents of the memory stream to another stream.

Declaration: `procedure SaveToStream(Stream: TStream)`

Visibility: public

Description: `SaveToStream` writes the contents of the memory stream to `Stream`. The content of `Stream` is not cleared first. The current position of the memory stream is not changed by this action.

**Remark:** This method will work much faster than the use of the `TStream.CopyFrom` (358) method:

```
Seek(0, soFromBeginning);
Stream.CopyFrom(Self, Size);
```

because the `CopyFrom` method copies the contents in blocks, while `SaveToStream` writes the contents of the memory as one big block.

Errors: If an error occurs when writing to `Stream` an `EStreamError` (226) exception will be raised.

See also: `TCustomMemoryStream.SaveToFile` (294), `TStream.CopyFrom` (358)

### 2.41.8 `TCustomMemoryStream.SaveToFile`

Synopsis: Writes the contents of the stream to a file.

Declaration: `procedure SaveToFile(const FileName: String)`

Visibility: public

Description: `SaveToFile` writes the contents of the stream to a file with name `FileName`. It simply creates a filestream and writes the contents of the memorystream to this file stream using `TCustomMemoryStream.SaveToStream` (294).

**Remark:** This method will work much faster than the use of the `TStream.CopyFrom` (358) method:

```
Stream:=TFileStream.Create(fmCreate, FileName);
Seek(0, soFromBeginning);
Stream.CopyFrom(Self, Size);
```



because the `CopyFrom` method copies the contents in blocks, while `SaveToFile` writes the contents of the memory as one big block.

**Errors:** If an error occurs when creating or writing to the file, an `EStreamError` (226) exception may occur.

See also: `TCustomMemoryStream.SaveToStream` (294), `TFileStream` (300), `TStream.CopyFrom` (358)

### 2.41.9 TCustomMemoryStream.Memory

**Synopsis:** Pointer to the data kept in the memory stream.

**Declaration:** `Property Memory : Pointer`

**Visibility:** `public`

**Access:** `Read`

**Description:** `Memory` points to the memory area where stream keeps it's data. The property is read-only, so the pointer cannot be set this way.

**Remark:** Do not write to the memory pointed to by `Memory`, since the memory content may be read-only, and thus writing to it may cause errors.

See also: `TStream.Size` (364)

## 2.42 TDataModule

### 2.42.1 Description

`TDataModule` is a container for non-visual objects which can be used in an IDE to group non-visual objects which can be used by various other containers (forms) in a project. Notably, data access components are typically stored on a datamodule. Web components and services can also be implemented as descendents of datamodules.

`TDataModule` introduces some events which make it easier to program, and provides the needed streaming capabilities for persistent storage.

An IDE will typically allow to create a descendent of `TDataModule` which contains non-visual components in it's published property list.

### 2.42.2 Method overview

Page	Property	Description
<a href="#">297</a>	<code>AfterConstruction</code>	Overrides standard <code>TObject</code> ( <a href="#">194</a> ) behaviour.
<a href="#">297</a>	<code>BeforeDestruction</code>	
<a href="#">296</a>	<code>Create</code>	Create a new instance of a <code>TDataModule</code> .
<a href="#">296</a>	<code>CreateNew</code>	
<a href="#">296</a>	<code>Destroy</code>	Destroys the <code>TDataModule</code> instance.

### 2.42.3 Property overview

Page	Property	Access	Description
<a href="#">297</a>	DesignOffset	rw	Position property needed for manipulation in an IDE.
<a href="#">297</a>	DesignSize	rw	Size property needed for manipulation in an IDE.
<a href="#">298</a>	OldCreateOrder	rw	Determines when <code>OnCreate</code> and <code>OnDestroy</code> are triggered.
<a href="#">298</a>	OnCreate	rw	Event handler, called when the datamodule is created.
<a href="#">298</a>	OnDestroy	rw	Event handler, called when the datamodule is destroyed.

### 2.42.4 TDataModule.Create

Synopsis: Create a new instance of a `TDataModule`.

Declaration: `constructor Create(AOwner: TComponent); Override`

Visibility: `public`

Description: `Create` creates a new instance of the `TDataModule` and calls `TDataModule.CreateNew` ([296](#)). After that it reads the published properties from a stream using `InitInheritedComponent` ([215](#)) if a descendent class is instantiated. If the `OldCreateOrder` ([298](#)) property is `True`, the `OnCreate` ([194](#)) event is called.

Errors: An exception can be raised during the streaming operation.

See also: `TDataModule.CreateNew` ([296](#))

### 2.42.5 TDataModule.CreateNew

Synopsis:

Declaration: `constructor CreateNew(AOwner: TComponent)`  
`constructor CreateNew(AOwner: TComponent; CreateMode: Integer); Virtual`

Visibility: `public`

Description: `CreateNew` creates a new instance of the class, but bypasses the streaming mechanism. The `CreateMode` parameter (by default zero) is not used in `TDataModule`. If the `AddDataModule` ([208](#)) handler is set, then it is called, with the newly created instance as an argument.

See also: `TDataModule.Create` ([296](#)), `AddDataModule` ([208](#)), `TDataModule.OnCreate` ([298](#))

### 2.42.6 TDataModule.Destroy

Synopsis: Destroys the `TDataModule` instance.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` destroys the `TDataModule` instance. If the `OldCreateOrder` ([298](#)) property is `True` the `OnDestroy` ([298](#)) event handler is called prior to destroying the data module.

Before calling the inherited destroy, the `RemoveDataModule` ([209](#)) handler is called if it is set, and `Self` is passed as a parameter.

Errors: An event can be raised during the `OnDestroy` event handler.

See also: `TDataModule.OnDestroy` ([298](#)), `RemoveDataModule` ([209](#))

### 2.42.7 TDataModule.AfterConstruction

Synopsis: Overrides standard TObject (194) behaviour.

Declaration: `procedure AfterConstruction; Override`

Visibility: `public`

Description: `AfterConstruction` calls the `OnCreate` (298) handler if the `OldCreateOrder` (298) property is `False`.

See also: `TDataModule.OldCreateOrder` (298), `TDataModule.OnCreate` (298)

### 2.42.8 TDataModule.BeforeDestruction

Synopsis:

Declaration: `procedure BeforeDestruction; Override`

Visibility: `public`

Description: `BeforeDestruction` calls the `OnDestroy` (298) handler if the `OldCreateOrder` (298) property is `False`.

See also: `TDataModule.OldCreateOrder` (298), `TDataModule.OnDestroy` (298)

### 2.42.9 TDataModule.DesignOffset

Synopsis: Position property needed for manipulation in an IDE.

Declaration: `Property DesignOffset : TPoint`

Visibility: `public`

Access: `Read,Write`

Description: `DesignOffset` is the position of the datamodule when displayed in an IDE. It is streamed to the form file, and should not be used at run-time.

See also: `TDataModule.DesignSize` (297)

### 2.42.10 TDataModule.DesignSize

Synopsis: Size property needed for manipulation in an IDE.

Declaration: `Property DesignSize : TPoint`

Visibility: `public`

Access: `Read,Write`

Description: `DesignSize` is the size of the datamodule when displayed in an IDE. It is streamed to the form file, and should not be used at run-time.

See also: `TDataModule.DesignOffset` (297)

### 2.42.11 TDataModule.OnCreate

Synopsis: Event handler, called when the datamodule is created.

Declaration: `Property OnCreate : TNotifyEvent`

Visibility: published

Access: Read,Write

Description: The `OnCreate` event is triggered when the datamodule is created and streamed. The exact moment of triggering is dependent on the value of the `OldCreateOrder` (298) property.

See also: `TDataModule.Create` (296), `TDataModule.CreateNew` (296), `TDataModule.OldCreateOrder` (298)

### 2.42.12 TDataModule.OnDestroy

Synopsis: Event handler, called when the datamodule is destroyed.

Declaration: `Property OnDestroy : TNotifyEvent`

Visibility: published

Access: Read,Write

Description: The `OnDestroy` event is triggered when the datamodule is destroyed. The exact moment of triggering is dependent on the value of the `OldCreateOrder` (298) property.

See also: `TDataModule.Destroy` (296), `TDataModule.OnCreate` (298), `TDataModule.Create` (296), `TDataModule.CreateNew` (296), `TDataModule.OldCreateOrder` (298)

### 2.42.13 TDataModule.OldCreateOrder

Synopsis: Determines when `OnCreate` and `OnDestroy` are triggered.

Declaration: `Property OldCreateOrder : Boolean`

Visibility: published

Access: Read,Write

Description: `OldCreateOrder` determines when exactly the `OnCreate` (298) and `OnDestroy` (298) event handlers are called.

If set to `True`, then the `OnCreate` event handler is called after the data module was streamed. If it is set to `False`, then the handler is called prior to the streaming process.

If set to `True`, then the `OnDestroy` event handler is called before the data module is removed from the streaming system. If it is set to `False`, then the handler is called after the data module was removed from the streaming process.

See also: `TDataModule.OnDestroy` (298), `TDataModule.OnCreate` (298), `TDataModule.Destroy` (296), `TDataModule.Create` (296), `TDataModule.CreateNew` (296), `TDataModule.OldCreateOrder` (298)

## 2.43 TFiler

### 2.43.1 Description

Class responsible for streaming of components.

### 2.43.2 Method overview

Page	Property	Description
<a href="#">299</a>	DefineBinaryProperty	
<a href="#">299</a>	DefineProperty	

### 2.43.3 Property overview

Page	Property	Access	Description
<a href="#">300</a>	Ancestor	rw	Ancestor component from which an inherited component is streamed.
<a href="#">300</a>	IgnoreChildren	rw	Determines whether children will be streamed as well.
<a href="#">300</a>	LookupRoot	r	Component used to look up ancestor components.
<a href="#">299</a>	Root	rw	The root component is the initial component which is being streamed.

### 2.43.4 TFiler.DefineProperty

Synopsis:

Declaration: `procedure DefineProperty(const Name: String; ReadData: TReaderProc;  
WriteData: TWriterProc; HasData: Boolean)  
; Virtual; Abstract`

Visibility: public

Description:

### 2.43.5 TFiler.DefineBinaryProperty

Synopsis:

Declaration: `procedure DefineBinaryProperty(const Name: String; ReadData: TStreamProc;  
WriteData: TStreamProc; HasData: Boolean)  
; Virtual; Abstract`

Visibility: public

Description:

### 2.43.6 TFiler.Root

Synopsis: The root component is the initial component which is being streamed.

Declaration: `Property Root : TComponent`

Visibility: public

Access: Read, Write

Description: The streaming process will stream a component and all the components which it owns. The `Root` component is the component which is initially streamed.

See also: `TFiler.LookupRoot` ([300](#))

### 2.43.7 TFile.LookupRoot

Synopsis: Component used to look up ancestor components.

Declaration: `Property LookupRoot : TComponent`

Visibility: `public`

Access: `Read`

Description: When comparing inherited component's values against parent values, the values are compared with the component in `LookupRoot`. Initially, it is set to `Root` (299).

See also: `TFile.Root` (299)

### 2.43.8 TFile.Ancestor

Synopsis: Ancestor component from which an inherited component is streamed.

Declaration: `Property Ancestor : TPersistent`

Visibility: `public`

Access: `Read,Write`

Description: When streaming a component, this is the parent component. Only properties that differ from the parent's property value will be streamed.

See also: `TFile.Root` (299), `TFile.LookupRoot` (300)

### 2.43.9 TFile.IgnoreChildren

Synopsis: Determines whether children will be streamed as well.

Declaration: `Property IgnoreChildren : Boolean`

Visibility: `public`

Access: `Read,Write`

Description: By default, all children (i.e. owned objects) will also be streamed when streaming a component. This property can be used to prevent owned objects from being streamed.

## 2.44 TFileStream

### 2.44.1 Description

`TFileStream` is a `TStream` (355) descendent that stores or reads it's data from a named file in the filesystem of the operating system.

To this end, it overrides some of the methods in `TStream` and implements them for the case of files on disk, and it adds the `FileName` (301) property to the list of public properties.

### 2.44.2 Method overview

Page	Property	Description
301	Create	Creates a file stream.
301	Destroy	Destroys the file stream.

### 2.44.3 Property overview

Page	Property	Access	Description
<a href="#">301</a>	FileName	r	The filename of the stream.

### 2.44.4 TFileStream.Create

Synopsis: Creates a file stream.

Declaration: `constructor Create(const AFileName: String; Mode: Word)`  
`constructor Create(const AFileName: String; Mode: Word; Rights: Cardinal)`

Visibility: public

Description: `Create` creates a new instance of a `TFileStream` class. It opens the file `AFileName` with mode `Mode`, which can have one of the following values:

Table 2.19:

<code>fmCreate</code>	<code>TFileStream.Create</code> ( <a href="#">301</a> ) creates a new file if needed.
<code>fmOpenRead</code>	<code>TFileStream.Create</code> ( <a href="#">301</a> ) opens a file with read-only access.
<code>fmOpenWrite</code>	<code>TFileStream.Create</code> ( <a href="#">301</a> ) opens a file with write-only access.
<code>fmOpenReadWrite</code>	<code>TFileStream.Create</code> ( <a href="#">301</a> ) opens a file with read-write access.

After the file has been opened in the requested mode and a handle has been obtained from the operating system, the inherited constructor is called.

Errors: If the file could not be opened in the requested mode, an `EOpenError` ([224](#)) exception is raised.

See also: `TStream` ([355](#)), `TFileStream.FileName` ([301](#)), `THandleStream.Create` ([311](#))

### 2.44.5 TFileStream.Destroy

Synopsis: Destroys the file stream.

Declaration: `destructor Destroy; Override`

Visibility: public

Description: `Destroy` closes the file (causing possible buffered data to be written to disk) and then calls the inherited destructor.

Do not call `destroy` directly, instead call the `Free` method. `Destroy` does not check whether `Self` is nil, while `Free` does.

See also: `TFileStream.Create` ([301](#))

### 2.44.6 TFileStream.FileName

Synopsis: The filename of the stream.

Declaration: `Property FileName : String`

Visibility: public

Access: Read

**Description:** `FileName` is the name of the file that the stream reads from or writes to. It is the name as passed in the constructor of the stream; it cannot be changed. To write to another file, the stream must be freed and created again with the new filename.

See also: `TFileStream.Create` (301)

## 2.45 TFPList

### 2.45.1 Description

`TFPList` is a class that can be used to manage collections of pointers. It introduces methods and properties to store the pointers, search in the list of pointers, sort them. It manages its memory by itself, no intervention for that is needed. Contrary to `TList` (319), `TFPList` has no notification mechanism. If no notification mechanism is used, it is better to use `TFPList` instead of `TList`, as the performance of `TFPList` is much higher.

To manage collections of strings, it is better to use a `TStrings` (373) descendent such as `TStringList` (368). To manage general objects, a `TCollection` (271) class exists, from which a descendent can be made to manage collections of various kinds.

### 2.45.2 Method overview

Page	Property	Description
303	Add	Adds a new pointer to the list.
303	AddList	Add all pointers from another list
306	Assign	Assign performs the given operation on the list.
303	Clear	Clears the pointer list.
304	Delete	Removes a pointer from the list.
303	Destroy	Destroys the list and releases the memory used to store the list elements.
304	Error	Raises an <code>EListError</code> (225) exception.
304	Exchange	Exchanges two pointers in the list.
304	Expand	Increases the capacity of the list if needed.
305	Extract	Remove the first occurrence of a pointer from the list.
305	First	Returns the first non-nil pointer in the list.
307	ForEachCall	Call a procedure or method for each pointer in the list.
305	GetEnumerator	Create an <code>IEnumerator</code> instance
305	IndexOf	Returns the index of a given pointer.
306	Insert	Inserts a new pointer in the list at a given position.
306	Last	Returns the last non-nil pointer in the list.
306	Move	Moves a pointer from one position in the list to another.
307	Pack	Removes <code>Nil</code> pointers from the list and frees unused memory.
307	Remove	Removes a value from the list.
307	Sort	Sorts the pointers in the list.

### 2.45.3 Property overview

Page	Property	Access	Description
308	Capacity	rw	Current capacity (i.e. number of pointers that can be stored) of the list.
308	Count	rw	Current number of pointers in the list.
308	Items	rw	Provides access to the pointers in the list.
309	List	r	Memory array where pointers are stored.



#### 2.45.4 TFPList.Destroy

Synopsis: Destroys the list and releases the memory used to store the list elements.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` destroys the list and releases the memory used to store the list elements. The elements themselves are in no way touched, i.e. any memory they point to must be explicitly released before calling the destructor.

#### 2.45.5 TFPList.AddList

Synopsis: Add all pointers from another list

Declaration: `procedure AddList (AList: TFPList)`

Visibility: `public`

Description: `AddList` adds all pointers from `AList` to the list. If a pointer is already present, it is added a second time.

See also: `TFPList.Assign` (306), `TList.AddList` (321)

#### 2.45.6 TFPList.Add

Synopsis: Adds a new pointer to the list.

Declaration: `function Add (Item: Pointer) : Integer`

Visibility: `public`

Description: `Add` adds a new pointer to the list after the last pointer (i.e. at position `Count`, thus increasing the item count with 1. If the list is at full capacity, the capacity of the list is expanded, using the `Grow` (302) method.

To insert a pointer at a certain position in the list, use the `Insert` (306) method instead.

See also: `TFPList.Delete` (304), `TFPList.Grow` (302), `TFPList.Insert` (306)

#### 2.45.7 TFPList.Clear

Synopsis: Clears the pointer list.

Declaration: `procedure Clear`

Visibility: `public`

Description: `Clear` removes all pointers from the list, and sets the capacity to 0, thus freeing any memory allocated to maintain the list.

See also: `TFPList.Destroy` (303)

### 2.45.8 TFPList.Delete

Synopsis: Removes a pointer from the list.

Declaration: `procedure Delete(Index: Integer)`

Visibility: `public`

Description: `Delete` removes the pointer at position `Index` from the list, shifting all following pointers one position up (or to the left).

The memory the pointer is pointing to is *not* deallocated.

### 2.45.9 TFPList.Error

Synopsis: Raises an `EListError` (225) exception.

Declaration: `procedure Error(const Msg: String; Data: PtrInt)`

Visibility: `public`

Description: `Error` raises an `EListError` (225) exception, with a message formatted with `Msg` and `Data`.

### 2.45.10 TFPList.Exchange

Synopsis: Exchanges two pointers in the list.

Declaration: `procedure Exchange(Index1: Integer; Index2: Integer)`

Visibility: `public`

Description: `Exchange` exchanges the pointers at positions `Index1` and `Index2`. Both pointers must be within the current range of the list, or an `EListError` (225) exception will be raised.

### 2.45.11 TFPList.Expand

Synopsis: Increases the capacity of the list if needed.

Declaration: `function Expand : TFPList`

Visibility: `public`

Description: `Expand` increases the capacity of the list if the current element count matches the current list capacity.

The capacity is increased according to the following algorithm:

- 1.If the capacity is less than 3, the capacity is increased with 4.
- 2.If the capacity is larger than 3 and less than 8, the capacity is increased with 8.
- 3.If the capacity is larger than 8, the capacity is increased with 16.

The return value is `Self`.

See also: `TFPList.Capacity` (308)

### 2.45.12 TFPList.Extract

Synopsis: Remove the first occurrence of a pointer from the list.

Declaration: `function Extract (Item: Pointer) : Pointer`

Visibility: public

Description: `Extract` searches for the first occurrence of `Item` in the list and deletes it from the list. If `Item` was found, it's value is returned. If `Item` was not found, `Nil` is returned.

See also: `TFPList.Delete` (304)

### 2.45.13 TFPList.First

Synopsis: Returns the first non-nil pointer in the list.

Declaration: `function First : Pointer`

Visibility: public

Description: `First` returns the value of the first non-nil pointer in the list.

If there are no pointers in the list or all pointers equal `Nil`, then `Nil` is returned.

See also: `TFPList.Last` (306)

### 2.45.14 TFPList.GetEnumerator

Synopsis: Create an `IEnumerator` instance

Declaration: `function GetEnumerator : TFPListEnumerator`

Visibility: public

Description: `GetEnumerator` is the implementation of the `IEnumerable` (1405) interface for `TFPList`. It creates a `TFPListEnumerator` (309) instance and returns it's `IEnumerator` (1406) interface.

See also: `TFPListEnumerator` (309), `#rtl.system.IEnumerator` (1406), `#rtl.system.IEnumerable` (1405)

### 2.45.15 TFPList.IndexOf

Synopsis: Returns the index of a given pointer.

Declaration: `function IndexOf (Item: Pointer) : Integer`

Visibility: public

Description: `IndexOf` searches for the pointer `Item` in the list of pointers, and returns the index of the pointer, if found.

If no pointer with the value `Item` was found, -1 is returned.

### 2.45.16 TFPList.Insert

Synopsis: Inserts a new pointer in the list at a given position.

Declaration: `procedure Insert (Index: Integer; Item: Pointer)`

Visibility: public

Description: `Insert` inserts pointer `Item` at position `Index` in the list. All pointers starting from `Index` are shifted to the right.

If `Index` is not a valid position, then a `EListError` (225) exception is raised.

See also: `TFPList.Add` (303), `TFPList.Delete` (304)

### 2.45.17 TFPList.Last

Synopsis: Returns the last non-nil pointer in the list.

Declaration: `function Last : Pointer`

Visibility: public

Description: `Last` returns the value of the last non-nil pointer in the list.

If there are no pointers in the list or all pointers equal `Nil`, then `Nil` is returned.

See also: `TFPList.First` (305)

### 2.45.18 TFPList.Move

Synopsis: Moves a pointer from one position in the list to another.

Declaration: `procedure Move (CurIndex: Integer; NewIndex: Integer)`

Visibility: public

Description: `Move` moves the pointer at position `CurIndex` to position `NewIndex`. This is done by storing the value at position `CurIndex`, deleting the pointer at position `CurIndex`, and reinserting the value at position `NewIndex`.

If `CurIndex` or `NewIndex` are not inside the valid range of indices, an `EListError` (225) exception is raised.

See also: `TFPList.Exchange` (304)

### 2.45.19 TFPList.Assign

Synopsis: `Assign` performs the given operation on the list.

Declaration: `procedure Assign (ListA: TFPList; AOperator: TListAssignOp; ListB: TFPList)`

Visibility: public

Description: `Assign` can be used to merge or assign lists. It is an extended version of the usual `TPersistent.Assign` mechanism. The arguments `ListA` and `ListB` are used as sources of pointers to add or remove elements from the current list, depending on the operation `AOperation`. The available operations are documented in the `TListAssignOp` (202) type.

See also: `TFPList.Add` (303), `TFPList.Clear` (303)

### 2.45.20 TFPList.Remove

Synopsis: Removes a value from the list.

Declaration: `function Remove(Item: Pointer) : Integer`

Visibility: public

Description: `Remove` searches `Item` in the list, and, if it finds it, deletes the item from the list. Only the first occurrence of `Item` is removed.

See also: `TFPList.Delete` (304), `TFPList.IndexOf` (305), `TFPList.Insert` (306)

### 2.45.21 TFPList.Pack

Synopsis: Removes `Nil` pointers from the list and frees unused memory.

Declaration: `procedure Pack`

Visibility: public

Description: `Pack` removes all `nil` pointers from the list. The capacity of the list is then set to the number of pointers in the list. This method can be used to free unused memory if the list has grown to very large sizes and has a lot of unneeded `nil` pointers in it.

See also: `TFPList.Clear` (303)

### 2.45.22 TFPList.Sort

Synopsis: Sorts the pointers in the list.

Declaration: `procedure Sort(Compare: TListSortCompare)`

Visibility: public

Description: `Sort` sorts the pointers in the list. Two pointers are compared by passing them to the `Compare` function. The result of this function determines how the pointers will be sorted:

- If the result of this function is negative, the first pointer is assumed to be 'less' than the second and will be moved before the second in the list.
- If the function result is positive, the first pointer is assumed to be 'greater than' the second and will be moved after the second in the list.
- If the function result is zero, the pointers are assumed to be 'equal' and no moving will take place.

The sort is done using a quicksort algorithm.

### 2.45.23 TFPList.ForEachCall

Synopsis: Call a procedure or method for each pointer in the list.

Declaration: `procedure ForEachCall(proc2call: TListCallback; arg: pointer)`  
`procedure ForEachCall(proc2call: TListStaticCallback; arg: pointer)`

Visibility: public

Description: `ForEachCall` iterates over all pointers in the list and calls `proc2call`, passing it the pointer and the additional `arg` data pointer. `Proc2Call` can be a method or a static procedure.

Errors: None.

See also: `TListStaticCallback` (203), `TListCallback` (202)

### 2.45.24 TFPList.Capacity

Synopsis: Current capacity (i.e. number of pointers that can be stored) of the list.

Declaration: `Property Capacity : Integer`

Visibility: public

Access: Read,Write

Description: `Capacity` contains the number of pointers the list can store before it starts to grow.

If a new pointer is added to the list using `add` (303) or `insert` (306), and there is not enough memory to store the new pointer, then the list will try to allocate more memory to store the new pointer. Since this is a time consuming operation, it is important that this operation be performed as little as possible. If it is known how many pointers there will be before filling the list, it is a good idea to set the capacity first before filling. This ensures that the list doesn't need to grow, and will speed up filling the list.

See also: `TFPList.SetCapacity` (302), `TFPList.Count` (308)

### 2.45.25 TFPList.Count

Synopsis: Current number of pointers in the list.

Declaration: `Property Count : Integer`

Visibility: public

Access: Read,Write

Description: `Count` is the current number of (possibly `Nil`) pointers in the list. Since the list is zero-based, the index of the largest pointer is `Count-1`.

### 2.45.26 TFPList.Items

Synopsis: Provides access to the pointers in the list.

Declaration: `Property Items[Index: Integer]: Pointer; default`

Visibility: public

Access: Read,Write

Description: `Items` is used to access the pointers in the list. It is the default property of the `TFPList` class, so it can be omitted.

The list is zero-based, so `Index` must be in the range 0 to `Count-1`.

### 2.45.27 TFPList.List

Synopsis: Memory array where pointers are stored.

Declaration: `Property List : PPointerList`

Visibility: `public`

Access: `Read`

Description: `List` points to the memory space where the pointers are stored. This can be used to quickly copy the list of pointers to another location.

## 2.46 TFPListEnumerator

### 2.46.1 Description

`TFPListEnumerator` implements the `#rtl.system.IEnumerator` (1406) interface for the `TFPList` (302) class, so the `TFPList` class can be used in a `for ... in` loop. It is returned by the `TFPList.GetEnumerator` (305) method of `TFPList`.

### 2.46.2 Method overview

Page	Property	Description
<a href="#">309</a>	<code>Create</code>	Initialize a new instance of <code>TFPListEnumerator</code>
<a href="#">309</a>	<code>GetCurrent</code>	Return the current pointer in the list
<a href="#">310</a>	<code>MoveNext</code>	Move the position of the enumerator to the next position in the list.

### 2.46.3 Property overview

Page	Property	Access	Description
<a href="#">310</a>	<code>Current</code>	<code>r</code>	Current pointer in the list

### 2.46.4 TFPListEnumerator.Create

Synopsis: Initialize a new instance of `TFPListEnumerator`

Declaration: `constructor Create (AList : TFPList)`

Visibility: `public`

Description: `Create` initializes a new instance of `TFPListEnumerator` and keeps a reference to the list `AList` that will be enumerated.

See also: `TFPList` (302)

### 2.46.5 TFPListEnumerator.GetCurrent

Synopsis: Return the current pointer in the list

Declaration: `function GetCurrent : Pointer`

Visibility: `public`

Description: `GetCurrent` returns the current pointer in the enumerator.

Errors: No checking is done on the validity of the current position.

See also: [TFPListEnumerator.MoveNext \(310\)](#)

### 2.46.6 TFPListEnumerator.MoveNext

Synopsis: Move the position of the enumerator to the next position in the list.

Declaration: `function MoveNext : Boolean`

Visibility: `public`

Description: `MoveNext` puts the pointer on the next item in the list, and returns `True` if this succeeded, or `False` if the pointer is past the last element in the list.

Errors: Note that if `False` is returned, calling `GetCurrent` will result in an exception.

See also: [TFPListEnumerator.GetCurrent \(309\)](#)

### 2.46.7 TFPListEnumerator.Current

Synopsis: Current pointer in the list

Declaration: `Property Current : Pointer`

Visibility: `public`

Access: `Read`

Description: `Current` redefines `GetCurrent` ([309](#)) as a property.

See also: [TFPListEnumerator.GetCurrent \(309\)](#)

## 2.47 THandleStream

### 2.47.1 Description

`THandleStream` is an abstract descendent of the `TStream` ([355](#)) class that provides methods for a stream to handle all reading and writing to and from a handle, provided by the underlying OS. To this end, it overrides the `Read` ([311](#)) and `Write` ([311](#)) methods of `TStream`.

#### Remark:

- `THandleStream` does not obtain a handle from the OS by itself, it just handles reading and writing to such a handle by wrapping the system calls for reading and writing; Descendent classes should obtain a handle from the OS by themselves and pass it on in the inherited constructor.
- Contrary to Delphi, no seek is implemented for `THandleStream`, since pipes and sockets do not support this. The seek is implemented in descendent methods that support it.

### 2.47.2 Method overview

Page	Property	Description
<a href="#">311</a>	Create	Create a handlestream from an OS Handle.
<a href="#">311</a>	Read	Overrides standard read method.
<a href="#">312</a>	Seek	Overrides the Seek method.
<a href="#">311</a>	Write	Overrides standard write method.



### 2.47.3 Property overview

Page	Property	Access	Description
<a href="#">312</a>	Handle	r	The OS handle of the stream.

### 2.47.4 THandleStream.Create

Synopsis: Create a handlestream from an OS Handle.

Declaration: `constructor Create(AHandle: Integer)`

Visibility: `public`

Description: `Create` creates a new instance of a `THandleStream` class. It stores `AHandle` in an internal variable and then calls the inherited constructor.

See also: `TStream` ([355](#))

### 2.47.5 THandleStream.Read

Synopsis: Overrides standard read method.

Declaration: `function Read(var Buffer; Count: LongInt) : LongInt; Override`

Visibility: `public`

Description: `Read` overrides the `Read` ([356](#)) method of `TStream`. It uses the `Handle` ([312](#)) property to read the `Count` bytes into `Buffer`

If no error occurs while reading, the number of bytes actually read will be returned.

Errors: If the operating system reports an error while reading from the handle, -1 is returned.

See also: `TStream.Read` ([356](#)), `THandleStream.Write` ([311](#)), `THandleStream.Handle` ([312](#))

### 2.47.6 THandleStream.Write

Synopsis: Overrides standard write method.

Declaration: `function Write(const Buffer; Count: LongInt) : LongInt; Override`

Visibility: `public`

Description: `Write` overrides the `Write` ([356](#)) method of `TStream`. It uses the `Handle` ([312](#)) property to write the `Count` bytes from `Buffer`.

If no error occurs while writing, the number of bytes actually written will be returned.

Errors: If the operating system reports an error while writing to the handle, 0 is returned.

See also: `TStream.Read` ([356](#)), `THandleStream.Write` ([311](#)), `THandleStream.Handle` ([312](#))

### 2.47.7 THandleStream.Seek

Synopsis: Overrides the Seek method.

Declaration: `function Seek(const Offset: Int64; Origin: TSeekOrigin) : Int64  
; Override`

Visibility: public

Description: `seek` uses the `FileSeek` (1494) method to position the stream on the desired position. Note that handle stream descendents (notably pipes) can override the method to prevent the seek.

### 2.47.8 THandleStream.Handle

Synopsis: The OS handle of the stream.

Declaration: `Property Handle : Integer`

Visibility: public

Access: Read

Description: `Handle` represents the Operating system handle to which reading and writing is done. The handle can be read only, i.e. it cannot be set after the `THandleStream` instance was created. It should be passed to the constructor `THandleStream.Create` (311)

See also: `THandleStream` (310), `THandleStream.Create` (311)

## 2.48 TInterfacedPersistent

### 2.48.1 Description

`TInterfacedPersistent` is a direct descendent of `TPersistent` (338) which implements the `#rtl.system.IInterface` (1234) interface. In particular, it implements the `QueryInterface` as a public method.

### 2.48.2 Method overview

Page	Property	Description
<a href="#">313</a>	<code>AfterConstruction</code>	Overrides the standard <code>AfterConstruction</code> method.
<a href="#">312</a>	<code>QueryInterface</code>	Implementation of <code>IInterface.QueryInterface</code>

### 2.48.3 TInterfacedPersistent.QueryInterface

Synopsis: Implementation of `IInterface.QueryInterface`

Declaration: `function QueryInterface(const IID: TGUID; out Obj) : HRESULT; Virtual`

Visibility: public

Description: `QueryInterface` simply calls `GetInterface` using the specified IID, and returns the correct values.

See also: `#rtl.system.tobject.GetInterface` (1419)

### 2.48.4 TInterfacedPersistent.AfterConstruction

Synopsis: Overrides the standard `AfterConstruction` method.

Declaration: `procedure AfterConstruction; Override`

Visibility: `public`

Description: `AfterConstruction` is overridden to do some extra interface housekeeping: a reference to the `IInterface` interface of the owning class is obtained (if it exists).

## 2.49 TInterfaceList

### 2.49.1 Description

`TInterfaceList` is a standard implementation of the `IInterfaceList` (228) interface. It uses a `TThreadList` (396) instance to store the list of interfaces.

### 2.49.2 Method overview

Page	Property	Description
<a href="#">315</a>	Add	Add an interface to the list
<a href="#">314</a>	Clear	Removes all interfaces from the list.
<a href="#">313</a>	Create	Create a new instance of <code>TInterfaceList</code>
<a href="#">314</a>	Delete	Delete an interface from the list.
<a href="#">314</a>	Destroy	Destroys the list of interfaces
<a href="#">314</a>	Exchange	Exchange 2 interfaces in the list
<a href="#">317</a>	Expand	Expands the list
<a href="#">315</a>	First	Returns the first non- <code>Nil</code> element in the list.
<a href="#">315</a>	GetEnumerator	Create an <code>IEnumerator</code> instance
<a href="#">315</a>	IndexOf	Returns the index of an interface.
<a href="#">316</a>	Insert	Insert an interface to the list
<a href="#">316</a>	Last	Returns the last non- <code>Nil</code> element in the list.
<a href="#">316</a>	Lock	Lock the list
<a href="#">316</a>	Remove	Remove an interface from the list
<a href="#">317</a>	Unlock	UnLocks a locked list

### 2.49.3 Property overview

Page	Property	Access	Description
<a href="#">317</a>	Capacity	rw	The current capacity of the list.
<a href="#">317</a>	Count	rw	The current number of elements in the list.
<a href="#">318</a>	Items	rw	Array-based access to the list's items.

### 2.49.4 TInterfaceList.Create

Synopsis: Create a new instance of `TInterfaceList`

Declaration: `constructor Create`

Visibility: `public`

Description: `Create` creates a new instance of the `TInterfaceList` class. It sets up the internal structures needed to store the list of interfaces.

See also: `TInterfaceList.Destroy` ([314](#))

### 2.49.5 `TInterfaceList.Destroy`

Synopsis: Destroys the list of interfaces

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` first calls `Clear` ([314](#)) and then frees the `TInterfaceList` instance from memory.

Note that the `Clear` method decreases the reference count of all interfaces.

See also: `TInterfaceList.Create` ([313](#)), `TInterfaceList.Clear` ([314](#))

### 2.49.6 `TInterfaceList.Clear`

Synopsis: Removes all interfaces from the list.

Declaration: `procedure Clear`

Visibility: `public`

Description: `Clear` is the implementation of the `IInterfaceList.Clear` ([230](#)) method. It removes all interfaces from the list. It does this by setting each element in the list to `Nil`, in this way the reference count of each interface in the list is decreased.

See also: `IInterfaceList.Clear` ([230](#)), `TInterfaceList.Add` ([315](#)), `TInterfaceList.Destroy` ([314](#)), `TList.Clear` ([321](#)), `TFPList.Clear` ([303](#))

### 2.49.7 `TInterfaceList.Delete`

Synopsis: Delete an interface from the list.

Declaration: `procedure Delete(index: Integer)`

Visibility: `public`

Description: `Delete` is the implementation of the `IInterfaceList.Delete` ([230](#)) method. It clears the slot first and then removes the element from the list.

See also: `IInterfaceList.Delete` ([230](#)), `TInterfaceList.Remove` ([316](#)), `TInterfaceList.Add` ([315](#)), `TList.Delete` ([321](#)), `TFPList.Delete` ([304](#))

### 2.49.8 `TInterfaceList.Exchange`

Synopsis: Exchange 2 interfaces in the list

Declaration: `procedure Exchange(index1: Integer; index2: Integer)`

Visibility: `public`

Description: `Exchange` is the implementation of the `IInterfaceList.Exchange` ([231](#)) method. It exchanges the position of 2 interfaces in the list.

See also: `IInterfaceList.Exchange` ([231](#)), `TInterfaceList.Delete` ([314](#)), `TInterfaceList.Add` ([315](#)), `TList.Exchange` ([322](#)), `TFPList.Exchange` ([304](#))

### 2.49.9 TInterfaceList.First

Synopsis: Returns the first non-`Nil` element in the list.

Declaration: `function First : IUnknown`

Visibility: `public`

Description: `First` is the implementation of the `IInterfaceList.First` (231) method. It returns the first non-`Nil` element from the list.

See also: `IInterfaceList.First` (231), `TList.First` (323)

### 2.49.10 TInterfaceList.GetEnumerator

Synopsis: Create an `IEnumerator` instance

Declaration: `function GetEnumerator : TInterfaceListEnumerator`

Visibility: `public`

Description: `GetEnumerator` is the implementation of the `IEnumerable` (1405) interface for `TInterfaceList`. It creates a `TInterfaceListEnumerator` (318) instance and returns it's `IEnumerator` (1406) interface. The enumerator enumerates all interfaces in the list.

See also: `TInterfaceListEnumerator` (318), `#rtl.system.IEnumerator` (1406), `#rtl.system.IEnumerable` (1405)

### 2.49.11 TInterfaceList.IndexOf

Synopsis: Returns the index of an interface.

Declaration: `function IndexOf(item: IUnknown) : Integer`

Visibility: `public`

Description: `IndexOf` is the implementation of the `IInterfaceList.IndexOf` (231) method. It returns the zero-based index in the list of the indicated interface, or -1 if the index is not in the list.

See also: `IInterfaceList.IndexOf` (231), `TList.IndexOf` (323)

### 2.49.12 TInterfaceList.Add

Synopsis: Add an interface to the list

Declaration: `function Add(item: IUnknown) : Integer`

Visibility: `public`

Description: `Add` is the implementation of the `IInterfaceList.Add` (231) method. It adds an interface to the list, and returns the location of the new element in the list. This operation will increment the reference count of the interface.

See also: `IInterfaceList.Add` (231), `TInterfaceList.Delete` (314), `TInterfaceList.Insert` (316), `TList.Add` (321), `TFPList.Add` (303)

**2.49.13 TInterfaceList.Insert**

Synopsis: Insert an interface to the list

Declaration: `procedure Insert(i: Integer; item: IUnknown)`

Visibility: public

Description: `Insert` is the implementation of the `IInterfaceList.Insert` (231) method. It inserts an interface in the list at the indicated position. This operation will increment the reference count of the interface.

See also: `IInterfaceList.Insert` (231), `TInterfaceList.Delete` (314), `TInterfaceList.Add` (315), `TList.Insert` (323), `TFPList.Insert` (306)

**2.49.14 TInterfaceList.Last**

Synopsis: Returns the last non-`Nil` element in the list.

Declaration: `function Last : IUnknown`

Visibility: public

Description: `Last` is the implementation of the `IInterfaceList.Last` (232) method. It returns the last non-`Nil` element from the list.

See also: `IInterfaceList.Last` (232), `TInterfaceList.First` (315), `TList.Last` (324), `TFPList.Last` (306)

**2.49.15 TInterfaceList.Remove**

Synopsis: Remove an interface from the list

Declaration: `function Remove(item: IUnknown) : Integer`

Visibility: public

Description: `Remove` is the implementation of the `IInterfaceList.Remove` (232) method. It removes the first occurrence of the interface from the list.

See also: `IInterfaceList.Remove` (232), `TInterfaceList.Delete` (314), `TInterfaceList.IndexOf` (315), `TList.Remove` (324), `TFList.Remove` (194)

**2.49.16 TInterfaceList.Lock**

Synopsis: Lock the list

Declaration: `procedure Lock`

Visibility: public

Description: `Lock` locks the list. It is the implementation of the `IInterfaceList.Lock` (232) method. It limits access to the list to the current thread.

See also: `IInterfaceList.Lock` (232), `TInterfaceList.UnLock` (317), `TThreadList.LockList` (397)

### 2.49.17 TInterfaceList.Unlock

Synopsis: UnLocks a locked list

Declaration: `procedure Unlock`

Visibility: `public`

Description: `UnLock` unlocks the list. It is the implementation of the `IInterfaceList.Unlock` (232) method. After a call to unlock, the current thread releases the list for manipulation by other threads.

See also: `IInterfaceList.Unlock` (232), `TInterfaceList.Lock` (316), `TThreadList.UnlockList` (398)

### 2.49.18 TInterfaceList.Expand

Synopsis: Expands the list

Declaration: `function Expand : TInterfaceList`

Visibility: `public`

Description: `Expand` calls the `expand` method from the internally used list. It returns itself.

See also: `TList.Expand` (322)

### 2.49.19 TInterfaceList.Capacity

Synopsis: The current capacity of the list.

Declaration: `Property Capacity : Integer`

Visibility: `public`

Access: `Read,Write`

Description: `Capacity` is the number of elements that the list can contain without needing to allocate more memory.

See also: `IInterfaceList.Capacity` (232), `TInterfaceList.Count` (317), `TList.Capacity` (325), `TFPList.Capacity` (308)

### 2.49.20 TInterfaceList.Count

Synopsis: The current number of elements in the list.

Declaration: `Property Count : Integer`

Visibility: `public`

Access: `Read,Write`

Description: `Count` is the number of elements in the list. This can include `Nil` elements. Note that the elements are zero-based, and thus are indexed from 0 to `Count-1`.

See also: `IInterfaceList.Count` (233), `TInterfaceList.Items` (318), `TInterfaceList.Capacity` (317), `TList.Count` (326), `TFPList.Count` (308)

### 2.49.21 TInterfaceList.Items

Synopsis: Array-based access to the list's items.

Declaration: `Property Items[Index: Integer]: IUnknown; default`

Visibility: public

Access: Read,Write

Description: `Items` provides indexed access to the elements in the list. Note that the elements are zero-based, and thus are indexed from 0 to `Count-1`. The items are read-write. It is not possible to add elements to the list by accessing an element with index larger or equal to `Count` (317).

See also: `IInterfaceList.Items` (233), `TInterfaceList.Count` (317), `TList.Items` (326), `TFPList.Items` (308)

## 2.50 TInterfaceListEnumerator

### 2.50.1 Description

`TInterfaceListEnumerator` implements the `#rtl.system.IEnumerator` (1406) interface for the `TInterfaceList` (313) class, so the `TInterfaceList` class can be used in a `for ... in` loop over the `TInterfaceList.Components` (313) child components of the component. It is returned by the `TInterfaceList.GetEnumerator` (315) method of `TInterfaceList`.

### 2.50.2 Method overview

Page	Property	Description
318	Create	Initialize a new instance of <code>TInterfaceListEnumerator</code>
319	GetCurrent	Return the current pointer in the list
319	MoveNext	Move the position of the enumerator to the next position in the children of the component.

### 2.50.3 Property overview

Page	Property	Access	Description
319	Current	r	Current pointer in the list

### 2.50.4 TInterfaceListEnumerator.Create

Synopsis: Initialize a new instance of `TInterfaceListEnumerator`

Declaration: `constructor Create(AList: TInterfaceList)`

Visibility: public

Description: `Create` initializes a new instance of `TInterfaceListEnumerator` and keeps a reference to the component `AComponent` that will be enumerated.

See also: `TInterfaceList` (313)



### 2.50.5 TInterfaceListEnumerator.GetCurrent

Synopsis: Return the current pointer in the list

Declaration: `function GetCurrent : IUnknown`

Visibility: `public`

Description: `GetCurrent` returns the current interface in the `TInterfaceList` (313) list.

Errors: No checking is done on the validity of the current position.

See also: `TInterfaceListEnumerator.MoveNext` (319), `TInterfaceList.Components` (313)

### 2.50.6 TInterfaceListEnumerator.MoveNext

Synopsis: Move the position of the enumerator to the next position in the children of the component.

Declaration: `function MoveNext : Boolean`

Visibility: `public`

Description: `MoveNext` puts the pointer on the next interface in the list, and returns `True` if this succeeded, or `False` if the pointer is past the last interface in the list.

Errors: Note that if `False` is returned, calling `GetCurrent` will result in an exception.

See also: `TInterfaceListEnumerator.GetCurrent` (319)

### 2.50.7 TInterfaceListEnumerator.Current

Synopsis: Current pointer in the list

Declaration: `Property Current : IUnknown`

Visibility: `public`

Access: `Read`

Description: `Current` redefines `GetCurrent` (319) as a property.

See also: `TInterfaceListEnumerator.GetCurrent` (319)

## 2.51 TList

### 2.51.1 Description

`TList` is a class that can be used to manage collections of pointers. It introduces methods and properties to store the pointers, search in the list of pointers, sort them. It manages its memory by itself, no intervention for that is needed. It has an event notification mechanism which allows to notify of list changes. This slows down some of `TList` mechanisms, and if no notification is used, `TFPList` (302) may be used instead.

To manage collections of strings, it is better to use a `TStrings` (373) descendent such as `TStringList` (368). To manage general objects, a `TCollection` (271) class exists, from which a descendent can be made to manage collections of various kinds.

### 2.51.2 Method overview

Page	Property	Description
<a href="#">321</a>	Add	Adds a new pointer to the list.
<a href="#">321</a>	AddList	Add all pointers from another list
<a href="#">324</a>	Assign	Copy the contents of other lists.
<a href="#">321</a>	Clear	Clears the pointer list.
<a href="#">320</a>	Create	Class to manage collections of pointers.
<a href="#">321</a>	Delete	Removes a pointer from the list.
<a href="#">320</a>	Destroy	Destroys the list and releases the memory used to store the list elements.
<a href="#">322</a>	Error	Raises an <code>EListError</code> ( <a href="#">225</a> ) exception.
<a href="#">322</a>	Exchange	Exchanges two pointers in the list.
<a href="#">322</a>	Expand	Increases the capacity of the list if needed.
<a href="#">322</a>	Extract	Remove the first occurrence of a pointer from the list.
<a href="#">323</a>	First	Returns the first non-nil pointer in the list.
<a href="#">323</a>	GetEnumerator	Create an <code>IEnumerator</code> instance
<a href="#">323</a>	IndexOf	Returns the index of a given pointer.
<a href="#">323</a>	Insert	Inserts a new pointer in the list at a given position.
<a href="#">324</a>	Last	Returns the last non-nil pointer in the list.
<a href="#">324</a>	Move	Moves a pointer from one position in the list to another.
<a href="#">325</a>	Pack	Removes <code>Nil</code> pointers from the list and frees unused memory.
<a href="#">324</a>	Remove	Removes a value from the list.
<a href="#">325</a>	Sort	Sorts the pointers in the list.

### 2.51.3 Property overview

Page	Property	Access	Description
<a href="#">325</a>	Capacity	rw	Current capacity (i.e. number of pointers that can be stored) of the list.
<a href="#">326</a>	Count	rw	Current number of pointers in the list.
<a href="#">326</a>	Items	rw	Provides access to the pointers in the list.
<a href="#">326</a>	List	r	Memory array where pointers are stored.

### 2.51.4 TList.Create

Synopsis: Class to manage collections of pointers.

Declaration: `constructor Create`

Visibility: `public`

Description: `TList.Create` creates a new instance of `TList`. It clears the list and prepares it for use.

See also: `TList` ([319](#)), `TList.Destroy` ([320](#))

### 2.51.5 TList.Destroy

Synopsis: Destroys the list and releases the memory used to store the list elements.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` destroys the list and releases the memory used to store the list elements. The elements themselves are in no way touched, i.e. any memory they point to must be explicitly released before calling the destructor.

### 2.51.6 TList.AddList

Synopsis: Add all pointers from another list

Declaration: `procedure AddList (AList: TList)`

Visibility: `public`

Description: `AddList` adds all pointers from `AList` to the list. If a pointer is already present, it is added a second time.

See also: `TList.Assign` (324), `TFPList.AddList` (303)

### 2.51.7 TList.Add

Synopsis: Adds a new pointer to the list.

Declaration: `function Add (Item: Pointer) : Integer`

Visibility: `public`

Description: `Add` adds a new pointer to the list after the last pointer (i.e. at position `Count`, thus increasing the item count with 1. If the list is at full capacity, the capacity of the list is expanded, using the `Grow` (319) method.

To insert a pointer at a certain position in the list, use the `Insert` (323) method instead.

See also: `TList.Delete` (321), `TList.Grow` (319), `TList.Insert` (323)

### 2.51.8 TList.Clear

Synopsis: Clears the pointer list.

Declaration: `procedure Clear; Virtual`

Visibility: `public`

Description: `Clear` removes all pointers from the list, and sets the capacity to 0, thus freeing any memory allocated to maintain the list.

See also: `TList.Destroy` (320)

### 2.51.9 TList.Delete

Synopsis: Removes a pointer from the list.

Declaration: `procedure Delete (Index: Integer)`

Visibility: `public`

Description: `Delete` removes the pointer at position `Index` from the list, shifting all following pointers one position up (or to the left).

The memory the pointer is pointing to is *not* deallocated.

### 2.51.10 TList.Error

Synopsis: Raises an `EListError` (225) exception.

Declaration: `procedure Error(const Msg: String; Data: PtrInt); Virtual`

Visibility: `public`

Description: `Error` raises an `EListError` (225) exception, with a message formatted with `Msg` and `Data`.

### 2.51.11 TList.Exchange

Synopsis: Exchanges two pointers in the list.

Declaration: `procedure Exchange(Index1: Integer; Index2: Integer)`

Visibility: `public`

Description: `Exchange` exchanges the pointers at positions `Index1` and `Index2`. Both pointers must be within the current range of the list, or an `EListError` (225) exception will be raised.

### 2.51.12 TList.Expand

Synopsis: Increases the capacity of the list if needed.

Declaration: `function Expand : TList`

Visibility: `public`

Description: `Expand` increases the capacity of the list if the current element count matches the current list capacity.

The capacity is increased according to the following algorithm:

- 1.If the capacity is less than 3, the capacity is increased with 4.
- 2.If the capacity is larger than 3 and less than 8, the capacity is increased with 8.
- 3.If the capacity is larger than 8, the capacity is increased with 16.

The return value is `Self`.

See also: `TList.Capacity` (325)

### 2.51.13 TList.Extract

Synopsis: Remove the first occurrence of a pointer from the list.

Declaration: `function Extract(item: Pointer) : Pointer`

Visibility: `public`

Description: `Extract` searched for an occurrence of `item`, and if a match is found, the match is deleted from the list. If no match is found, nothing is deleted. If `Item` was found, the result is `Item`. If `Item` was not found, the result is `Nil`. A `lnExtracted` notification event is triggered if an element is extracted from the list.

See also: `TList.Delete` (321), `TList.IndexOf` (323), `TList.Remove` (324)

**2.51.14 TList.First**

Synopsis: Returns the first non-nil pointer in the list.

Declaration: `function First : Pointer`

Visibility: `public`

Description: `First` returns the value of the first non-nil pointer in the list.

If there are no pointers in the list or all pointers equal `Nil`, then `Nil` is returned.

See also: `TList.Last` ([324](#))

**2.51.15 TList.GetEnumerator**

Synopsis: Create an `IEnumerator` instance

Declaration: `function GetEnumerator : TListEnumerator`

Visibility: `public`

Description: `GetEnumerator` is the implementation of the `IEnumerable` ([1405](#)) interface for `TList`. It creates a `TListEnumerator` ([326](#)) instance and returns it's `IEnumerator` ([1406](#)) interface.

See also: `TListEnumerator` ([326](#)), `#rtl.system.IEnumerator` ([1406](#)), `#rtl.system.IEnumerable` ([1405](#))

**2.51.16 TList.IndexOf**

Synopsis: Returns the index of a given pointer.

Declaration: `function IndexOf(Item: Pointer) : Integer`

Visibility: `public`

Description: `IndexOf` searches for the pointer `Item` in the list of pointers, and returns the index of the pointer, if found.

If no pointer with the value `Item` was found, -1 is returned.

**2.51.17 TList.Insert**

Synopsis: Inserts a new pointer in the list at a given position.

Declaration: `procedure Insert(Index: Integer; Item: Pointer)`

Visibility: `public`

Description: `Insert` inserts pointer `Item` at position `Index` in the list. All pointers starting from `Index` are shifted to the right.

If `Index` is not a valid position, then a `EListError` ([225](#)) exception is raised.

See also: `TList.Add` ([321](#)), `Tlist.Delete` ([321](#))

### 2.51.18 TList.Last

Synopsis: Returns the last non-nil pointer in the list.

Declaration: `function Last : Pointer`

Visibility: `public`

Description: `Last` returns the value of the last non-nil pointer in the list.

If there are no pointers in the list or all pointers equal `Nil`, then `Nil` is returned.

See also: `TList.First` ([323](#))

### 2.51.19 TList.Move

Synopsis: Moves a pointer from one position in the list to another.

Declaration: `procedure Move (CurIndex: Integer; NewIndex: Integer)`

Visibility: `public`

Description: `Move` moves the pointer at position `CurIndex` to position `NewIndex`. This is done by storing the value at position `CurIndex`, deleting the pointer at position `CurIndex`, and reinserting the value at position `NewIndex`.

If `CurIndex` or `Newindex` are not inside the valid range of indices, an `EListError` ([225](#)) exception is raised.

See also: `TList.Exchange` ([322](#))

### 2.51.20 TList.Assign

Synopsis: Copy the contents of other lists.

Declaration: `procedure Assign (ListA: TList; AOperator: TListAssignOp; ListB: TList)`

Visibility: `public`

Description: `Assign` can be used to merge or assign lists. It is an extended version of the usual `TPersistent.Assign` mechanism. The arguments `ListA` and `ListB` are used as sources of pointers to add or remove elements from the current list, depending on the operation `AOperation`. The available operations are documented in the `TListAssignOp` ([202](#)) type.

See also: `TList.Clear` ([321](#))

### 2.51.21 TList.Remove

Synopsis: Removes a value from the list.

Declaration: `function Remove (Item: Pointer) : Integer`

Visibility: `public`

Description: `Remove` searches `Item` in the list, and, if it finds it, deletes the item from the list. Only the first occurrence of `Item` is removed.

See also: `TList.Delete` ([321](#)), `TList.IndexOf` ([323](#)), `TList.Insert` ([323](#))

### 2.51.22 TList.Pack

**Synopsis:** Removes Nil pointers from the list and frees unused memory.

**Declaration:** `procedure Pack`

**Visibility:** `public`

**Description:** `Pack` removes all `nil` pointers from the list. The capacity of the list is then set to the number of pointers in the list. This method can be used to free unused memory if the list has grown to very large sizes and has a lot of unneeded `nil` pointers in it.

See also: `TList.Clear` ([321](#))

### 2.51.23 TList.Sort

**Synopsis:** Sorts the pointers in the list.

**Declaration:** `procedure Sort (Compare: TListSortCompare)`

**Visibility:** `public`

**Description:** `Sort` sorts the pointers in the list. Two pointers are compared by passing them to the `Compare` function. The result of this function determines how the pointers will be sorted:

- If the result of this function is negative, the first pointer is assumed to be 'less' than the second and will be moved before the second in the list.
- If the function result is positive, the first pointer is assumed to be 'greater than' the second and will be moved after the second in the list.
- If the function result is zero, the pointers are assumed to be 'equal' and no moving will take place.

The sort is done using a quicksort algorithm.

### 2.51.24 TList.Capacity

**Synopsis:** Current capacity (i.e. number of pointers that can be stored) of the list.

**Declaration:** `Property Capacity : Integer`

**Visibility:** `public`

**Access:** Read, Write

**Description:** `Capacity` contains the number of pointers the list can store before it starts to grow.

If a new pointer is added to the list using `add` ([321](#)) or `insert` ([323](#)), and there is not enough memory to store the new pointer, then the list will try to allocate more memory to store the new pointer. Since this is a time consuming operation, it is important that this operation be performed as little as possible. If it is known how many pointers there will be before filling the list, it is a good idea to set the capacity first before filling. This ensures that the list doesn't need to grow, and will speed up filling the list.

See also: `TList.SetCapacity` ([319](#)), `TList.Count` ([326](#))

### 2.51.25 TList.Count

Synopsis: Current number of pointers in the list.

Declaration: `Property Count : Integer`

Visibility: `public`

Access: `Read,Write`

Description: `Count` is the current number of (possibly `Nil`) pointers in the list. Since the list is zero-based, the index of the largest pointer is `Count-1`.

### 2.51.26 TList.Items

Synopsis: Provides access to the pointers in the list.

Declaration: `Property Items[Index: Integer]: Pointer; default`

Visibility: `public`

Access: `Read,Write`

Description: `Items` is used to access the pointers in the list. It is the default property of the `TList` class, so it can be omitted.

The list is zero-based, so `Index` must be in the range 0 to `Count-1`.

### 2.51.27 TList.List

Synopsis: Memory array where pointers are stored.

Declaration: `Property List : PPointerList`

Visibility: `public`

Access: `Read`

Description: `List` points to the memory space where the pointers are stored. This can be used to quickly copy the list of pointers to another location.

## 2.52 TListEnumerator

### 2.52.1 Description

`TListEnumerator` implements the `#rtl.system.IEnumerator` (1406) interface for the `TList` (319) class, so the `TList` class can be used in a `for ... in` loop. It is returned by the `TList.GetEnumerator` (323) method of `TList`.

### 2.52.2 Method overview

Page	Property	Description
<a href="#">327</a>	<code>Create</code>	Initialize a new instance of <code>TListEnumerator</code>
<a href="#">327</a>	<code>GetCurrent</code>	Return the current pointer in the list
<a href="#">327</a>	<code>MoveNext</code>	Move the position of the enumerator to the next position in the list.



### 2.52.3 Property overview

Page	Property	Access	Description
<a href="#">327</a>	Current	r	Current pointer in the list

### 2.52.4 TListEnumerator.Create

Synopsis: Initialize a new instance of `TListEnumerator`

Declaration: `constructor Create (AList: TList)`

Visibility: `public`

Description: `Create` initializes a new instance of `TListEnumerator` and keeps a reference to the list `AList` that will be enumerated.

See also: `TList` ([319](#))

### 2.52.5 TListEnumerator.GetCurrent

Synopsis: Return the current pointer in the list

Declaration: `function GetCurrent : Pointer`

Visibility: `public`

Description: `GetCurrent` returns the current pointer in the enumerator.

Errors: No checking is done on the validity of the current position.

See also: `TListEnumerator.MoveNext` ([327](#))

### 2.52.6 TListEnumerator.MoveNext

Synopsis: Move the position of the enumerator to the next position in the list.

Declaration: `function MoveNext : Boolean`

Visibility: `public`

Description: `MoveNext` puts the pointer on the next item in the list, and returns `True` if this succeeded, or `False` if the pointer is past the last element in the list.

Errors: Note that if `False` is returned, calling `GetCurrent` will result in an exception.

See also: `TListEnumerator.GetCurrent` ([327](#))

### 2.52.7 TListEnumerator.Current

Synopsis: Current pointer in the list

Declaration: `Property Current : Pointer`

Visibility: `public`

Access: `Read`

Description: `Current` redefines `GetCurrent` ([327](#)) as a property.

See also: `TListEnumerator.GetCurrent` ([327](#))

## 2.53 TMemoryStream

### 2.53.1 Description

`TMemoryStream` is a `TStream` (355) descendent that stores its data in memory. It descends directly from `TCustomMemoryStream` (293) and implements the necessary to allocate and de-allocate memory directly from the heap. It implements the `Write` (329) method which is missing in `TCustomMemoryStream`.

`TMemoryStream` also introduces methods to load the contents of another stream or a file into the memory stream.

It is not necessary to do any memory management manually, as the stream will allocate or de-allocate memory as needed. When the stream is freed, all allocated memory will be freed as well.

### 2.53.2 Method overview

Page	Property	Description
<a href="#">328</a>	<code>Clear</code>	Zeroes the position, capacity and size of the stream.
<a href="#">328</a>	<code>Destroy</code>	Frees any allocated memory and destroys the memory stream.
<a href="#">329</a>	<code>LoadFromFile</code>	Loads the contents of a file into memory.
<a href="#">328</a>	<code>LoadFromStream</code>	Loads the contents of a stream into memory.
<a href="#">329</a>	<code>SetSize</code>	Sets the size for the memory stream.
<a href="#">329</a>	<code>Write</code>	Writes data to the stream's memory.

### 2.53.3 TMemoryStream.Destroy

Synopsis: Frees any allocated memory and destroys the memory stream.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` clears the memory stream, thus in effect freeing any memory allocated for it, and then frees the memory stream.

### 2.53.4 TMemoryStream.Clear

Synopsis: Zeroes the position, capacity and size of the stream.

Declaration: `procedure Clear`

Visibility: `public`

Description: `Clear` sets the position and size to 0, and sets the capacity of the stream to 0, thus freeing all memory allocated for the stream.

See also: `TStream.Size` (364), `TStream.Position` (363), `TCustomMemoryStream.Memory` (295)

### 2.53.5 TMemoryStream.LoadFromStream

Synopsis: Loads the contents of a stream into memory.

Declaration: `procedure LoadFromStream(Stream: TStream)`

Visibility: `public`

**Description:** `LoadFromStream` loads the contents of `Stream` into the memorybuffer of the stream. Any previous contents of the memory stream are overwritten. Memory is allocated as needed.

**Remark:** The `LoadFromStream` uses the `Size` (364) property of `Stream` to determine how much memory must be allocated. Some streams do not allow the stream size to be determined, so care must be taken when using this method.

This method will work much faster than the use of the `TStream.CopyFrom` (358) method:

```
Seek(0, soFromBeginning);
CopyFrom(Stream, Stream.Size);
```

because the `CopyFrom` method copies the contents in blocks, while `LoadFromStream` reads the contents of the stream as one big block.

**Errors:** If an error occurs when reading from the stream, an `EStreamError` (226) may occur.

See also: `TStream.CopyFrom` (358), `TMemoryStream.LoadFromFile` (329)

### 2.53.6 TMemoryStream.LoadFromFile

**Synopsis:** Loads the contents of a file into memory.

**Declaration:** `procedure LoadFromFile(const FileName: String)`

**Visibility:** public

**Description:** `LoadFromFile` loads the contents of the file with name `FileName` into the memory stream. The current contents of the memory stream is replaced by the contents of the file. Memory is allocated as needed.

The `LoadFromFile` method simply creates a filestream and then calls the `TMemoryStream.LoadFromStream` (328) method.

See also: `TMemoryStream.LoadFromStream` (328)

### 2.53.7 TMemoryStream.SetSize

**Synopsis:** Sets the size for the memory stream.

**Declaration:** `procedure SetSize(NewSize: LongInt); Override`

**Visibility:** public

**Description:** `SetSize` sets the size of the memory stream to `NewSize`. This will set the capacity of the stream to `NewSize` and correct the current position in the stream when needed.

See also: `TStream.Position` (363), `TStream.Size` (364)

### 2.53.8 TMemoryStream.Write

**Synopsis:** Writes data to the stream's memory.

**Declaration:** `function Write(const Buffer; Count: LongInt) : LongInt; Override`

**Visibility:** public

**Description:** `Write` writes `Count` bytes from `Buffer` to the stream's memory, starting at the current position in the stream. If more memory is needed than currently allocated, more memory will be allocated. Any contents in the memory stream at the current position will be overwritten. The function returns the number of bytes actually written (which should under normal circumstances always equal `Count`).

This method overrides the `TStream.Write` (356) method.

**Errors:** If no more memory could be allocated, then an exception will be raised.

See also: `TCustomMemoryStream.Read` (293)

## 2.54 TOwnedCollection

### 2.54.1 Description

`TOwnedCollection` automatically maintains owner information, so it can be displayed in an IDE. Collections that should be displayed in an IDE should descend from `TOwnedCollection` or must implement a `GetOwner` function.

### 2.54.2 Method overview

Page	Property	Description
<a href="#">330</a>	Create	Create a new <code>TOwnerCollection</code> instance.

### 2.54.3 TOwnedCollection.Create

**Synopsis:** Create a new `TOwnerCollection` instance.

**Declaration:** `constructor Create(AOwner: TPersistent; AItemClass: TCollectionItemClass)`

**Visibility:** public

**Description:** `Create` creates a new instance of `TOwnedCollection` and stores the `AOwner` references. It will the value returned in the `TCollection.Owner` (273) property of the collection. The `ItemClass` class reference is passed on to the inherited constructor, and will be used to create new instances in the `Insert` (275) and `Add` (273) methods.

See also: `TCollection.Create` (272), `TCollection.Owner` (273)

## 2.55 TOwnerStream

### 2.55.1 Description

`TOwnerStream` can be used when creating stream chains such as when using encryption and compression streams. It keeps a reference to the source stream and will automatically free the source stream when ready (if the `SourceOwner` (331) property is set to `True`).

### 2.55.2 Method overview

Page	Property	Description
<a href="#">331</a>	Create	Create a new instance of <code>TOwnerStream</code> .
<a href="#">331</a>	Destroy	Destroys the <code>TOwnerStream</code> instance and the source stream.

### 2.55.3 Property overview

Page	Property	Access	Description
<a href="#">331</a>	Source	r	Reference to the source stream.
<a href="#">331</a>	SourceOwner	rw	Indicates whether the ownerstream owns it's source

### 2.55.4 TOwnerStream.Create

Synopsis: Create a new instance of `TOwnerStream`.

Declaration: constructor `Create (ASource: TStream)`

Visibility: public

Description: `Create` instantiates a new instance of `TOwnerStream` and stores the reference to `AStream`. If `SourceOwner` is `True`, the source stream will also be freed when the instance is destroyed.

See also: `TOwnerStream.Destroy` ([331](#)), `TOwnerStream.Source` ([331](#)), `TOwnerStream.SourceOwner` ([331](#))

### 2.55.5 TOwnerStream.Destroy

Synopsis: Destroys the `TOwnerStream` instance and the source stream.

Declaration: destructor `Destroy; Override`

Visibility: public

Description: `Destroy` frees the source stream if the `SourceOwner` property is `True`.

Errors:

See also: `TOwnerStream.Create` ([331](#)), `TOwnerStream.Source` ([331](#)), `TOwnerStream.SourceOwner` ([331](#))

### 2.55.6 TOwnerStream.Source

Synopsis: Reference to the source stream.

Declaration: Property `Source : TStream`

Visibility: public

Access: Read

Description: `Source` is the source stream. It should be used by descendent streams to access the source stream to read from or write to.

Do not free the `Source` reference directly if `SourceOwner` is `True`. In that case the owner stream instance will free the source stream itself.

See also: `TOwnerStream.Create` ([331](#))

### 2.55.7 TOwnerStream.SourceOwner

Synopsis: Indicates whether the ownerstream owns it's source

Declaration: Property `SourceOwner : Boolean`

Visibility: public

Access: Read,Write

Description: `SourceOwner` indicates whether the `TOwnerStream` owns it's `Source` stream or not. If this property is `True` then the `Source` stream is freed when the `TOwnerStream` instance is freed.

See also: `TOwnerStream.Source` (331), `TOwnerStream.Destroy` (331)

## 2.56 TParser

### 2.56.1 Description

This class breaks a stream of text data in tokens. Its primary use is to help reading the contents of a form file (usually a file with `dfm`, `xfm` or `lfm` extension), and for this reason it isn't suitable to be used as a general parser.

The parser is always positioned on a certain token, whose type is stored in the `Token` (338) property. Various methods are provided to obtain the token value in the desired format.

To advance to the next token, invoke `NextToken` (334) method.

### 2.56.2 Method overview

Page	Property	Description
333	<code>CheckToken</code>	Checks whether the token if of the given type.
333	<code>CheckTokenSymbol</code>	Checks whether the token equals the given symbol
332	<code>Create</code>	Creates a new parser instance.
333	<code>Destroy</code>	Destroys the parser instance.
333	<code>Error</code>	Raises an <code>EParserError</code> (225) exception with the given message
334	<code>ErrorFmt</code>	Raises an <code>EParserError</code> (225) exception and formats the message.
334	<code>ErrorStr</code>	Raises an <code>EParserError</code> (225) exception with the given message
334	<code>HexToBinary</code>	Writes hexadecimal data to a stream.
334	<code>NextToken</code>	Reads the next token and returns its type.
335	<code>SourcePos</code>	Returns the current position in the stream.
335	<code>TokenComponentIdent</code>	Returns the path of a subcomponent starting from the current token.
335	<code>TokenFloat</code>	Returns the current token as a float.
336	<code>TokenInt</code>	Returns the current token as an integer.
336	<code>TokenString</code>	Returns the current token as a string.
337	<code>TokenSymbolIs</code>	Returns <code>True</code> if the token equals the given symbol.
336	<code>TokenWideString</code>	Returns the current token as a widestring

### 2.56.3 Property overview

Page	Property	Access	Description
337	<code>FloatType</code>	r	The type of a float token.
337	<code>SourceLine</code>	r	Current source line number.
338	<code>Token</code>	r	The type of the current token.

### 2.56.4 TParser.Create

Synopsis: Creates a new parser instance.

Declaration: `constructor Create(Stream: TStream)`

Visibility: public

Description: `Create` creates a new `TParser` instance, using `Stream` as the stream to read data from, and reads the first token from the stream.

Errors: If an error occurs while parsing the first token, an `EParseError` (225) exception is raised.

See also: `TParser.NextToken` (334), `TParser.Token` (338)

### 2.56.5 `TParser.Destroy`

Synopsis: Destroys the parser instance.

Declaration: `destructor Destroy; Override`

Visibility: public

Description: Destroys the parser instance.

Errors: None.

### 2.56.6 `TParser.CheckToken`

Synopsis: Checks whether the token is of the given type.

Declaration: `procedure CheckToken(T: Char)`

Visibility: public

Description: Checks whether the token is of the given type.

Errors: If current token isn't of type `T`, an `EParseError` (225) exception is raised.

See also: `TParser.Token` (338)

### 2.56.7 `TParser.CheckTokenSymbol`

Synopsis: Checks whether the token equals the given symbol

Declaration: `procedure CheckTokenSymbol(const S: String)`

Visibility: public

Description: `CheckTokenSymbol` performs a case-insensitive comparison of current token value with `S`.

Current token must be of type `toSymbol` (196), otherwise an `EParseError` (225) exception is raised.

Errors: If the comparison fails, or current token isn't a symbol, an `EParseError` (225) exception is raised.

See also: `TParser.TokenSymbolIs` (337), `toSymbol` (196)

### 2.56.8 `TParser.Error`

Synopsis: Raises an `EParseError` (225) exception with the given message

Declaration: `procedure Error(const Ident: String)`

Visibility: public

Description: Raises an `EParseError` (225) exception with the given message

### 2.56.9 TParser.ErrorFmt

**Synopsis:** Raises an EParserError (225) exception and formats the message.

**Declaration:** `procedure ErrorFmt(const Ident: String; const Args: Array of const)`

**Visibility:** public

**Description:** Raises an EParserError (225) exception and formats the message.

### 2.56.10 TParser.ErrorStr

**Synopsis:** Raises an EParserError (225) exception with the given message

**Declaration:** `procedure ErrorStr(const Message: String)`

**Visibility:** public

**Description:** Raises an EParserError (225) exception with the given message

### 2.56.11 TParser.HexToBinary

**Synopsis:** Writes hexadecimal data to a stream.

**Declaration:** `procedure HexToBinary(Stream: TStream)`

**Visibility:** public

**Description:** HexToBinary reads a sequence of hexadecimal characters from the input stream and converts them to a sequence of bytes which is written to Stream. Each byte is represented by two contiguous hexadecimal characters.

Whitespace is allowed between hexadecimal characters if it doesn't appear between two characters that form the same byte.

HexToBinary stops when the first non-hexadecimal and non-whitespace character is found, or the end of the input stream is reached.

**Remark:** This method begins reading after the current token: that is, current token, even if it's a valid hexadecimal value, isn't included.

**Errors:** If a single hexadecimal character is found, an EParserError (225) exception is raised.

### 2.56.12 TParser.NextToken

**Synopsis:** Reads the next token and returns its type.

**Declaration:** `function NextToken : Char`

**Visibility:** public

**Description:** NextToken parses the next token in the stream and returns its type. The type of the token can also be retrieved later reading Token (338) property.

If the end of the stream is reached, toEOF (196) is returned.

For details about token types, see TParser.Token (338)

**Errors:** If an error occurs while parsing the token, an EParserError (225) exception is raised.

**See also:** TParser.Token (338)



### 2.56.13 TParser.SourcePos

Synopsis: Returns the current position in the stream.

Declaration: `function SourcePos : LongInt`

Visibility: public

Description: This is not the character position relative to the current source line, but the byte offset from the beginning of the stream.

Errors: None.

See also: `TParser.SourceLine` (337)

### 2.56.14 TParser.TokenComponentIdent

Synopsis: Returns the path of a subcomponent starting from the current token.

Declaration: `function TokenComponentIdent : String`

Visibility: public

Description: If current token is `toSymbol` (196), `TokenComponentIdent` tries to find subcomponent names separated by a dot (.). The returned string is the longest subcomponent path found. If there are no subcomponents, current symbol is returned.

**Remark:** After this method has been called, subsequent calls to `TokenString` (336) or `TokenWideString` (336) return the same value returned by `TokenComponentIdent`.

#### Example

If source stream contains `a.b.c` and `TParser` is positioned on the first token (`a`), this method returns `a.b.c`.

Errors: If `Token` (338) isn't `toSymbol` (196), or no valid symbol is found after a dot, an `EParserError` (225) exception is raised.

See also: `TParser.NextToken` (334), `TParser.Token` (338), `TParser.TokenString` (336), `TParser.TokenWideString` (336), `toSymbol` (196)

### 2.56.15 TParser.TokenFloat

Synopsis: Returns the current token as a float.

Declaration: `function TokenFloat : Extended`

Visibility: public

Description: If current token type is `toFloat` (196), this method returns the token value as a float.

To specify a negative number, no space must exist between unary minus and number.

Floating point numbers can be postfixed with a character that specifies the floating point type. See `FloatType` (337) for further information.

**Remark:** In the input stream the decimal separator, if present, must be a dot (.).

Errors: If `Token` (338) isn't `toFloat` (196), an `EParserError` (225) exception is raised.

See also: `TParser.FloatType` (337), `TParser.NextToken` (334), `TParser.Token` (338), `toFloat` (196)

### 2.56.16 TParser.TokenInt

Synopsis: Returns the current token as an integer.

Declaration: `function TokenInt : Int64`

Visibility: public

Description: If current token type is `toInteger` (196), this method returns the token value as an integer.

In the input stream an integer can be an hexadecimal (prefixed by ' \$ ' character) or decimal number. Decimal numbers can be prefixed by an unary minus: if this is the case, no space must exist between minus and number.

Errors: If Token (338) isn't `toInteger` (196), an `EConvertError` (194) exception is raised.

See also: `TParser.NextToken` (334), `TParser.Token` (338), `toInteger` (196)

### 2.56.17 TParser.TokenString

Synopsis: Returns the current token as a string.

Declaration: `function TokenString : String`

Visibility: public

Description: If current token type is `toString` (196) or `toWString` (196), this method returns the contents of the string. That is, enclosing quotes are removed, embedded quotes are unescaped and control strings are converted to the appropriate sequence of characters.

If current token type isn't a string, a string containing the token representation in the input stream is returned, without any conversion: hexadecimal integers are returned with the leading \$, and floating point suffixes like `s`, `c` or `d` are kept. For tokens whose type isn't a special type, return value of `TokenString` equals `Token` (338).

**Remark:** If Token (338) is `toWString` (196), `TokenWideString` (336) should be used instead.

Errors: None.

See also: `TParser.NextToken` (334), `TParser.TokenWideString` (336), `TParser.Token` (338), `toString` (196), `toWString` (196)

### 2.56.18 TParser.TokenWideString

Synopsis: Returns the current token as a widestring

Declaration: `function TokenWideString : WideString`

Visibility: public

Description: If current token type is `toWString` (196), this method returns the contents of the string. That is, enclosing quotes are removed, embedded quotes are unescaped and control strings are converted to the appropriate sequence of characters.

If current token isn't a widestring, `TokenWideString` behaviour is the same as `TokenString` (336).

Errors: None.

See also: `TParser.NextToken` (334), `TParser.TokenString` (336), `TParser.Token` (338), `toWString` (196)

### 2.56.19 TParser.TokenSymbols

Synopsis: Returns `True` if the token equals the given symbol.

Declaration: `function TokenSymbolIs(const S: String) : Boolean`

Visibility: `public`

Description: `TokenSymbolIs` performs a case-insensitive comparison of current token value with `S`.

If current token isn't of type `toSymbol` (196), or comparison fails, `False` is returned.

Errors: None.

See also: `TParser.CheckTokenSymbol` (333), `TParser.Token` (338)

### 2.56.20 TParser.FloatType

Synopsis: The type of a float token.

Declaration: `Property FloatType : Char`

Visibility: `public`

Access: `Read`

Description: Floating point numbers can be postfixed with a character specifying the type of floating point value.

When specified, this property holds the character postfixed to the number.

It can be one of the following values:

Table 2.20:

<code>s</code> or <code>S</code>	Value is a single.
<code>c</code> or <code>C</code>	Value is a currency.
<code>d</code> or <code>D</code>	Value is a date.

If `Token` (338) isn't `toFloat` (196) or one of the above characters wasn't specified, `FloatType` is the null character (zero).

See also: `TParser.NextToken` (334), `TParser.Token` (338), `TParser.TokenFloat` (335), `toFloat` (196)

### 2.56.21 TParser.SourceLine

Synopsis: Current source line number.

Declaration: `Property SourceLine : Integer`

Visibility: `public`

Access: `Read`

Description: Current source line number.

See also: `TParser.SourcePos` (335)

### 2.56.22 TParser.Token

Synopsis: The type of the current token.

Declaration: `Property Token : Char`

Visibility: `public`

Access: `Read`

Description: This property holds the type of the current token. When `Token` isn't one of the special token types (whose value can be retrieved with specific methods) it is the character representing the current token.

Special token types:

Table 2.21:

<code>toEOF</code> (196)	Value returned by <code>TParser.Token</code> (338) when the end of the input stream was reached.
<code>toSymbol</code> (196)	Value returned by <code>TParser.Token</code> (338) when a symbol was found in the input stream.
<code>toString</code> (196)	Value returned by <code>TParser.Token</code> (338) when a string was found in the input stream.
<code>toInteger</code> (196)	Value returned by <code>TParser.Token</code> (338) when an integer was found in the input stream.
<code>toFloat</code> (196)	Value returned by <code>TParser.Token</code> (338) when a floating point value was found in the input stream.
<code>toWString</code> (196)	Value returned by <code>TParser.Token</code> (338) when a widestring was found in the input stream.

To advance to the next token, use `NextToken` (334) method.

See also: `TParser.CheckToken` (333), `TParser.NextToken` (334), `TParser.TokenComponentIdent` (335), `TParser.TokenFloat` (335), `TParser.TokenInt` (336), `TParser.TokenString` (336), `TParser.TokenWideString` (336)

## 2.57 TPersistent

### 2.57.1 Description

`TPersistent` is the basic class for the streaming system. Since it is compiled in the `{ $M+ }` state, the compiler generates RTTI (Run-Time Type Information) for it and all classes that descend from it. This information can be used to stream all properties of classes.

It also introduces functionality to assign the contents of 2 classes to each other.

### 2.57.2 Method overview

Page	Property	Description
339	<code>Assign</code>	Assign the contents of one class to another.
338	<code>Destroy</code>	Destroys the <code>TPersistent</code> instance.
339	<code>GetNamePath</code>	Returns a string that can be used to identify the class instance.

### 2.57.3 TPersistent.Destroy

Synopsis: Destroys the `TPersistent` instance.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` disposes of the persistent object. This method should never be called directly. Instead the `Free` method should be used.

### 2.57.4 TPersistent.Assign

**Synopsis:** Assign the contents of one class to another.

**Declaration:** `procedure Assign(Source: TPersistent); Virtual`

**Visibility:** public

**Description:** Assign copies the contents of Source to Self, if the classes of the destination and source classes are compatible.

The TPersistent implementation of Assign does nothing but calling the AssignTo (338) method of source. This means that if the destination class does not know how to assign the contents of the source class, the source class instance is asked to assign itself to the destination class. This means that it is necessary to implement only one of the two methods so that two classes can be assigned to one another.

**Remark:** In general, a statement of the form

```
Destination:=Source;
```

(where Destination and Source are classes) does not achieve the same as a statement of the form

```
Destination.Assign(Source);
```

After the former statement, both Source and Destination will point to the same object. The latter statement will copy the *contents* of the Source class to the Destination class.

See also: TPersistent.AssignTo (338)

### 2.57.5 TPersistent.GetNamePath

**Synopsis:** Returns a string that can be used to identify the class instance.

**Declaration:** `function GetNamePath : String; Virtual`

**Visibility:** public

**Description:** GetNamePath returns a string that can be used to identify the class instance. This can be used to display a name for this instance in a Object designer.

GetNamePath constructs a name by recursively prepending the Classname of the Owner instance to the Classname of this instance, separated by a dot.

See also: TPersistent.GetOwner (338)

## 2.58 TProxyStream

### 2.58.1 Description

TProxyStream is a proxy class for the IStream (194) interface. It implements all stream methods by relaying them to the IStream interface.

### 2.58.2 Method overview

Page	Property	Description
<a href="#">340</a>	Check	Check errors
<a href="#">340</a>	Create	Create a new instance of the TProxyStream class.
<a href="#">340</a>	Read	
<a href="#">340</a>	Seek	
<a href="#">340</a>	Write	

### 2.58.3 TProxyStream.Create

Synopsis: Create a new instance of the TProxyStream class.

Declaration: `constructor Create(const Stream: IStream)`

Visibility: `public`

Description: `Create` initializes a new instance of the TProxyStream class. It saves `var stream` for use in the other methods.

See also: `IStream` ([194](#))

### 2.58.4 TProxyStream.Read

Declaration: `function Read(var Buffer; Count: LongInt) : LongInt; Override`

Visibility: `public`

### 2.58.5 TProxyStream.Write

Declaration: `function Write(const Buffer; Count: LongInt) : LongInt; Override`

Visibility: `public`

### 2.58.6 TProxyStream.Seek

Declaration: `function Seek(Offset: LongInt; Origin: Word) : LongInt; Override`

Visibility: `public`

### 2.58.7 TProxyStream.Check

Synopsis: Check errors

Declaration: `procedure Check(err: LongInt); Virtual`

Visibility: `public`

Description: `Check` will check the result of the `IStream` interface. This method must be overridden by descendent classes to return interface-specific errors.

See also: `IStream` ([194](#))

## 2.59 TReader

### 2.59.1 Description

The `TReader` class is a reader class that implements generic component streaming capabilities, independent of the format of the data in the stream. It uses a driver class `TAbstractObjectReader` (234) to do the actual reading of data. The interface of the `TReader` class should be identical to the interface in Delphi.

### 2.59.2 Method overview

Page	Property	Description
342	<code>BeginReferences</code>	Initializes the component referencing mechanism.
343	<code>CheckValue</code>	Raises an exception if the next value in the stream is not of type <code>Value</code>
349	<code>CopyValue</code>	Copy a value to a writer.
342	<code>Create</code>	Creates a new reader class
343	<code>DefineBinaryProperty</code>	Reads a user-defined binary property from the stream.
343	<code>DefineProperty</code>	Reads a user-defined property from the stream.
342	<code>Destroy</code>	Destroys a reader class.
343	<code>EndOfList</code>	Returns true if the stream contains an end-of-list marker.
343	<code>EndReferences</code>	Finalizes the component referencing mechanism.
344	<code>FixupReferences</code>	Tries to resolve all unresolved component references.
344	<code>NextValue</code>	Returns the type of the next value.
344	<code>Read</code>	Read raw data from stream
344	<code>ReadBoolean</code>	Reads a boolean from the stream.
344	<code>ReadChar</code>	Reads a character from the stream.
345	<code>ReadCollection</code>	Reads a collection from the stream.
345	<code>ReadComponent</code>	Starts reading a component from the stream.
345	<code>ReadComponents</code>	Starts reading child components from the stream.
346	<code>ReadCurrency</code>	Read a currency value from the stream.
346	<code>ReadDate</code>	Reads a date from the stream
346	<code>ReadFloat</code>	Reads a float from the stream.
346	<code>ReadIdent</code>	Reads an identifier from the stream.
347	<code>ReadInt64</code>	Reads a 64-bit integer from the stream.
347	<code>ReadInteger</code>	Reads an integer from the stream
347	<code>ReadListBegin</code>	Checks for the beginning of a list.
347	<code>ReadListEnd</code>	Checks for the end of a list.
348	<code>ReadRootComponent</code>	Starts reading a root component.
347	<code>ReadSet</code>	Read a set value from the stream
346	<code>ReadSingle</code>	Reads a single-type real from the stream.
348	<code>ReadString</code>	Reads a string from the stream.
345	<code>ReadUnicodeChar</code>	Read unicode character
348	<code>ReadUnicodeString</code>	Read a <code>UnicodeString</code> value from the stream
349	<code>ReadValue</code>	Reads the next value type from the stream.
348	<code>ReadVariant</code>	Read a variant from the stream
345	<code>ReadWideChar</code>	Read widechar from the stream
348	<code>ReadWideString</code>	Read a <code>WideString</code> value from the stream.

**2.59.3 Property overview**

Page	Property	Access	Description
<a href="#">349</a>	Driver	r	The driver in use for streaming the data.
<a href="#">351</a>	OnAncestorNotFound	rw	Handler called when the ancestor component cannot be found.
<a href="#">351</a>	OnCreateComponent	rw	Handler called when a component needs to be created.
<a href="#">350</a>	OnError	rw	Handler called when an error occurs.
<a href="#">351</a>	OnFindComponentClass	rw	Handler called when a component class reference needs to be found.
<a href="#">350</a>	OnFindMethod	rw	Handler to find or change a method address.
<a href="#">350</a>	OnPropertyNotFound	rw	Handler for treating missing properties.
<a href="#">352</a>	OnReadStringProperty	rw	Handler for translating strings when read from the stream.
<a href="#">351</a>	OnReferenceName	rw	Handler called when another component is referenced.
<a href="#">350</a>	OnSetMethodProperty	rw	Handler for setting method properties.
<a href="#">351</a>	OnSetName	rw	Handler called when setting a component name.
<a href="#">349</a>	Owner	rw	Owner of the component being read
<a href="#">349</a>	Parent	rw	Parent of the component being read.

**2.59.4 TReader.Create**

Synopsis: Creates a new reader class

Declaration: `constructor Create(Stream: TStream; BufSize: Integer)`

Visibility: `public`

Description: Creates a new reader class

**2.59.5 TReader.Destroy**

Synopsis: Destroys a reader class.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: Destroys a reader class.

**2.59.6 TReader.BeginReferences**

Synopsis: Initializes the component referencing mechanism.

Declaration: `procedure BeginReferences`

Visibility: `public`

Description: When streaming components, the streaming mechanism keeps a list of existing components that can be referenced to. This method initializes up that system.



**2.59.7 TReader.CheckValue**

Synopsis: Raises an exception if the next value in the stream is not of type Value

Declaration: `procedure CheckValue(Value: TValueType)`

Visibility: public

Description: Raises an exception if the next value in the stream is not of type Value

**2.59.8 TReader.DefineProperty**

Synopsis: Reads a user-defined property from the stream.

Declaration: `procedure DefineProperty(const Name: String; AReadData: TReaderProc;  
WriteData: TWriterProc; HasData: Boolean)  
; Override`

Visibility: public

Description: Reads a user-defined property from the stream.

**2.59.9 TReader.DefineBinaryProperty**

Synopsis: Reads a user-defined binary property from the stream.

Declaration: `procedure DefineBinaryProperty(const Name: String;  
AReadData: TStreamProc;  
WriteData: TStreamProc; HasData: Boolean)  
; Override`

Visibility: public

Description: Reads a user-defined binary property from the stream.

**2.59.10 TReader.EndOfList**

Synopsis: Returns true if the stream contains an end-of-list marker.

Declaration: `function EndOfList : Boolean`

Visibility: public

Description: Returns true if the stream contains an end-of-list marker.

**2.59.11 TReader.EndReferences**

Synopsis: Finalizes the component referencing mechanism.

Declaration: `procedure EndReferences`

Visibility: public

Description: When streaming components, the streaming mechanism keeps a list of existing components that can be referenced to. This method cleans up that system.

### 2.59.12 TReader.FixupReferences

Synopsis: Tries to resolve all unresolved component references.

Declaration: `procedure FixupReferences`

Visibility: `public`

Description: Tries to resolve all unresolved component references.

### 2.59.13 TReader.NextValue

Synopsis: Returns the type of the next value.

Declaration: `function NextValue : TValueType`

Visibility: `public`

Description: Returns the type of the next value.

### 2.59.14 TReader.Read

Synopsis: Read raw data from stream

Declaration: `procedure Read(var Buf; Count: LongInt); Virtual`

Visibility: `public`

Description: `Read` is introduced for Delphi compatibility to read raw data from the component stream. This should not be used in new production code as it will totally mess up the streaming.

See also: `TAbstractObjectReader.Read` ([237](#)), `TBinaryObjectReader.Read` ([256](#))

### 2.59.15 TReader.ReadBoolean

Synopsis: Reads a boolean from the stream.

Declaration: `function ReadBoolean : Boolean`

Visibility: `public`

Description: Reads a boolean from the stream.

### 2.59.16 TReader.ReadChar

Synopsis: Reads a character from the stream.

Declaration: `function ReadChar : Char`

Visibility: `public`

Description: Reads a character from the stream.

### 2.59.17 TReader.ReadWideChar

Synopsis: Read widechar from the stream

Declaration: `function ReadWideChar : WideChar`

Visibility: public

Description: `TReader.ReadWideChar` reads a widechar from the stream. This actually reads a widestring and returns the first character.

See also: `TReader.ReadWideString` ([348](#)), `TWriter.WriteWideChar` ([401](#))

### 2.59.18 TReader.ReadUnicodeChar

Synopsis: Read unicode character

Declaration: `function ReadUnicodeChar : UnicodeChar`

Visibility: public

Description: `ReadUnicodeChar` reads a single unicode character from the stream. It does this by reading a `UnicodeString` string from the stream and returning the first character.

Errors: If the string has a length different from 1, an `EReadError` exception will occur.

See also: `TReader.ReadUnicodeString` ([348](#))

### 2.59.19 TReader.ReadCollection

Synopsis: Reads a collection from the stream.

Declaration: `procedure ReadCollection(Collection: TCollection)`

Visibility: public

Description: Reads a collection from the stream.

### 2.59.20 TReader.ReadComponent

Synopsis: Starts reading a component from the stream.

Declaration: `function ReadComponent(Component: TComponent) : TComponent`

Visibility: public

Description: Starts reading a component from the stream.

### 2.59.21 TReader.ReadComponents

Synopsis: Starts reading child components from the stream.

Declaration: `procedure ReadComponents(AOwner: TComponent; AParent: TComponent;  
Proc: TReadComponentsProc)`

Visibility: public

Description: Starts reading child components from the stream.

### 2.59.22 TReader.ReadFloat

Synopsis: Reads a float from the stream.

Declaration: `function ReadFloat : Extended`

Visibility: `public`

Description: Reads a float from the stream.

### 2.59.23 TReader.ReadSingle

Synopsis: Reads a single-type real from the stream.

Declaration: `function ReadSingle : Single`

Visibility: `public`

Description: Reads a single-type real from the stream.

### 2.59.24 TReader.ReadDate

Synopsis: Reads a date from the stream

Declaration: `function ReadDate : TDateTime`

Visibility: `public`

Description: Reads a date from the stream

### 2.59.25 TReader.ReadCurrency

Synopsis: Read a currency value from the stream.

Declaration: `function ReadCurrency : Currency`

Visibility: `public`

Description: `ReadCurrency` reads a currency typed value from the stream and returns the result. This method does nothing except call the driver method of the driver being used.

See also: `TWriter.WriteCurrency` ([402](#))

### 2.59.26 TReader.ReadIdent

Synopsis: Reads an identifier from the stream.

Declaration: `function ReadIdent : String`

Visibility: `public`

Description: Reads an identifier from the stream.

### 2.59.27 TReader.ReadInteger

Synopsis: Reads an integer from the stream

Declaration: `function ReadInteger : LongInt`

Visibility: `public`

Description: Reads an integer from the stream

### 2.59.28 TReader.ReadInt64

Synopsis: Reads a 64-bit integer from the stream.

Declaration: `function ReadInt64 : Int64`

Visibility: `public`

Description: Reads a 64-bit integer from the stream.

### 2.59.29 TReader.ReadSet

Synopsis: Read a set value from the stream

Declaration: `function ReadSet (EnumType: Pointer) : Integer`

Visibility: `public`

Description: `ReadSet` reads a set of elements with type `EnumType` and returns them as an integer where each element is encoded in a bit of the integer. Thus, at most an enumerated type with 32 elements can be read with this function.

Errors: No checking is performed on the validity of `EnumType`. It is assumed to be a valid `PTypeInfo` pointer.

See also: `TWriter.WriteSet` ([403](#))

### 2.59.30 TReader.ReadListBegin

Synopsis: Checks for the beginning of a list.

Declaration: `procedure ReadListBegin`

Visibility: `public`

Description: Checks for the beginning of a list.

### 2.59.31 TReader.ReadListEnd

Synopsis: Checks for the end of a list.

Declaration: `procedure ReadListEnd`

Visibility: `public`

Description: Checks for the end of a list.

### 2.59.32 TReader.ReadRootComponent

Synopsis: Starts reading a root component.

Declaration: `function ReadRootComponent (ARoot: TComponent) : TComponent`

Visibility: public

Description: Starts reading a root component.

### 2.59.33 TReader.ReadVariant

Synopsis: Read a variant from the stream

Declaration: `function ReadVariant : Variant`

Visibility: public

Description: `ReadVariant` reads the next value from the stream and returns it as a variant. No variant array can be read from the stream, only single values.

Errors: If no variant manager is installed, the function will raise an `EReadError` exception. If the next value is not a simple value, again an `EReadError` exception is raised. exception is

See also: `TBinaryObjectWriter.WriteVariant` ([264](#))

### 2.59.34 TReader.ReadString

Synopsis: Reads a string from the stream.

Declaration: `function ReadString : String`

Visibility: public

Description: Reads a string from the stream.

### 2.59.35 TReader.ReadWideString

Synopsis: Read a WideString value from the stream.

Declaration: `function ReadWideString : WideString`

Visibility: public

Description: `ReadWidestring` reads a widestring typed value from the stream and returns the result. This method does nothing except call the driver method of the driver being used.

See also: `TWriter.WriteString` ([404](#))

### 2.59.36 TReader.ReadUnicodeString

Synopsis: Read a UnicodeString value from the stream

Declaration: `function ReadUnicodeString : UnicodeString`

Visibility: public

Description: `ReadUnicodeString` reads a `UnicodeString` string from the stream. The stream can contain a string from any type, it will be converted to `UnicodeString`.

See also: `TAbstractObjectReader.ReadUnicodeString` ([241](#)), `TWriter.WriteString` ([404](#))

### **2.59.37 TReader.ReadValue**

Synopsis: Reads the next value type from the stream.

Declaration: `function ReadValue : TValueType`

Visibility: `public`

Description: Reads the next value type from the stream.

### **2.59.38 TReader.CopyValue**

Synopsis: Copy a value to a writer.

Declaration: `procedure CopyValue(Writer: TWriter)`

Visibility: `public`

Description: `CopyValue` reads the next value from the reader stream, and writes it to the passed `Writer`.

### **2.59.39 TReader.Driver**

Synopsis: The driver in use for streaming the data.

Declaration: `Property Driver : TAbstractObjectReader`

Visibility: `public`

Access: `Read`

Description: The driver in use for streaming the data.

### **2.59.40 TReader.Owner**

Synopsis: Owner of the component being read

Declaration: `Property Owner : TComponent`

Visibility: `public`

Access: `Read,Write`

Description: Owner of the component being read

### **2.59.41 TReader.Parent**

Synopsis: Parent of the component being read.

Declaration: `Property Parent : TComponent`

Visibility: `public`

Access: `Read,Write`

Description: Parent of the component being read.

### 2.59.42 TReader.OnError

Synopsis: Handler called when an error occurs.

Declaration: `Property OnError : TReaderError`

Visibility: public

Access: Read,Write

Description: Handler called when an error occurs.

### 2.59.43 TReader.OnPropertyNotFound

Synopsis: Handler for treating missing properties.

Declaration: `Property OnPropertyNotFound : TPropertyNotFoundEvent`

Visibility: public

Access: Read,Write

Description: `OnPropertyNotFound` can be used to take appropriate action when a property is read from a stream and no such property is found in the RTTI information of the Instance that is being read from the stream. It can be set at runtime, or at designtime by an IDE.

For more information about the meaning of the various arguments to the event handler, see `TPropertyNotFoundEvent` (204).

See also: `TPropertyNotFoundEvent` (204), `TReader.OnSetMethodProperty` (350), `TReader.OnReadStringProperty` (352)

### 2.59.44 TReader.OnFindMethod

Synopsis: Handler to find or change a method address.

Declaration: `Property OnFindMethod : TFindMethodEvent`

Visibility: public

Access: Read,Write

Description: Handler to find or change a method address.

### 2.59.45 TReader.OnSetMethodProperty

Synopsis: Handler for setting method properties.

Declaration: `Property OnSetMethodProperty : TSetMethodPropertyEvent`

Visibility: public

Access: Read,Write

Description: `OnSetMethodProperty` can be set to handle the setting of method properties. This handler can be used by an IDE to prevent methods from actually being assigned when an object is being streamed in the designer.

See also: `TReader.OnReadStringProperty` (352), `TReader.OnPropertyNotFound` (350)



#### **2.59.46 TReader.OnSetName**

Synopsis: Handler called when setting a component name.

Declaration: `Property OnSetName : TSetNameEvent`

Visibility: `public`

Access: `Read,Write`

Description: Handler called when setting a component name.

#### **2.59.47 TReader.OnReferenceName**

Synopsis: Handler called when another component is referenced.

Declaration: `Property OnReferenceName : TReferenceNameEvent`

Visibility: `public`

Access: `Read,Write`

Description: Handler called when another component is referenced.

#### **2.59.48 TReader.OnAncestorNotFound**

Synopsis: Handler called when the ancestor component cannot be found.

Declaration: `Property OnAncestorNotFound : TAncestorNotFoundEvent`

Visibility: `public`

Access: `Read,Write`

Description: Handler called when the ancestor component cannot be found.

#### **2.59.49 TReader.OnCreateComponent**

Synopsis: Handler called when a component needs to be created.

Declaration: `Property OnCreateComponent : TCreateComponentEvent`

Visibility: `public`

Access: `Read,Write`

Description: Handler called when a component needs to be created.

#### **2.59.50 TReader.OnFindComponentClass**

Synopsis: Handler called when a component class reference needs to be found.

Declaration: `Property OnFindComponentClass : TFindComponentClassEvent`

Visibility: `public`

Access: `Read,Write`

Description: Handler called when a component class reference needs to be found.

### 2.59.51 TReader.OnReadStringProperty

Synopsis: Handler for translating strings when read from the stream.

Declaration: `Property OnReadStringProperty : TReadWriteStringPropertyEvent`

Visibility: `public`

Access: `Read, Write`

Description: `OnReadStringProperty` is called whenever a string property is read from the stream. It can be used e.g. by a translation mechanism to translate the strings on the fly, when a form is loaded. See `TReadWriteStringPropertyEvent` (204) for a description of the various parameters.

See also: `TReader.OnPropertyNotFound` (350), `TReader.OnSetMethodProperty` (350), `TReadWriteStringPropertyEvent` (204)

## 2.60 TRecall

### 2.60.1 Description

`TRecall` is a helper class used to copy published properties of a class (the reference object) in another class (the storage object). The reference object and storage object must be assignable to each other.

The `TRecall` can be used to store the state of a persistent class, and restore it at a later time.

When a `TRecall` object is created, it gets passed a reference instance and a storage instance. It immediatly stores the properties of the reference object in the storage object.

The `Store` (353) method can be called throughout the lifetime of the reference object to update the stored properties.

When the `TRecall` instance is destroyed then the properties are copied from the storage object to the reference object. The storage object is freed automatically.

If the properties should not be copied back from the storage to the reference object, the `Forget` (353) can be called.

### 2.60.2 Method overview

Page	Property	Description
352	Create	Creates a new instance of <code>TRecall</code> .
353	Destroy	Copies the stored properties to the reference object and destroys the <code>TRecall</code> instance.
353	Forget	Clear the reference property.
353	Store	Assigns the reference instance to the storage instance.

### 2.60.3 Property overview

Page	Property	Access	Description
354	Reference	<code>r</code>	The reference object.

### 2.60.4 TRecall.Create

Synopsis: Creates a new instance of `TRecall`.

**Declaration:** `constructor Create (AStorage: TPersistent; AReference: TPersistent)`

**Visibility:** `public`

**Description:** `Create` creates a new instance of `TRecall` and initializes the `Reference` and `Storage` instances. It calls `Store` (353) to assign the reference object properties to the storage instance.

**See also:** `TRecall.Store` (353), `TRecall.Destroy` (353)

### 2.60.5 TRecall.Destroy

**Synopsis:** Copies the stored properties to the reference object and destroys the `TRecall` instance.

**Declaration:** `destructor Destroy; Override`

**Visibility:** `public`

**Description:** `Destroy` assigns the storage instance to the reference instance, if the latter is still valid. After this, it frees the storage and calls the inherited `destroy`.

**Errors:** `Destroy` does not check whether the reference (354) instance is still valid. If the reference pointer was invalidated, call `TRecall.Forget` (353) to clear the reference instance.

**See also:** `TRecall.Store` (353), `TRecall.Forget` (353)

### 2.60.6 TRecall.Store

**Synopsis:** Assigns the reference instance to the storage instance.

**Declaration:** `procedure Store`

**Visibility:** `public`

**Description:** `Store` assigns the reference instance to the storage instance. This will only work if the two classes can be assigned to each other.

This method can be used to refresh the storage.

**Errors:** `Store` does not check whether the reference (354) instance is still valid. If the reference pointer was invalidated, call `TRecall.Forget` (353) to clear the reference instance.

### 2.60.7 TRecall.Forget

**Synopsis:** Clear the reference property.

**Declaration:** `procedure Forget`

**Visibility:** `public`

**Description:** `Forget` sets the `Reference` (194) property to `Nil`. When the `TRecall` instance is destroyed, the reference instance will not be restored.

Note that after a call to `Forget`, a call to `Store` (353) has no effect.

**Errors:** None.

**See also:** `TRecall.Reference` (354), `TRecall.Store` (353), `TRecall.Destroy` (353)

### 2.60.8 TRecall.Reference

Synopsis: The reference object.

Declaration: `Property Reference : TPersistent`

Visibility: `public`

Access: `Read`

Description: `Reference` is the instance of the reference object. Do not free the reference directly. Call `Forget` (353) to clear the reference and then free the reference object.

See also: `TRecall.Forget` (353)

## 2.61 TResourceStream

### 2.61.1 Description

Stream that reads its data from a resource object.

### 2.61.2 Method overview

Page	Property	Description
<a href="#">354</a>	<code>Create</code>	Creates a new instance of a resource stream.
<a href="#">354</a>	<code>CreateFromID</code>	Creates a new instance of a resource stream with a resource
<a href="#">355</a>	<code>Destroy</code>	Destroys the instance of the resource stream.

### 2.61.3 TResourceStream.Create

Synopsis: Creates a new instance of a resource stream.

Declaration: `constructor Create (Instance: THandle; const ResName: String;  
ResType: PChar)`

Visibility: `public`

Description: Creates a new instance of a resource stream.

### 2.61.4 TResourceStream.CreateFromID

Synopsis: Creates a new instance of a resource stream with a resource

Declaration: `constructor CreateFromID (Instance: THandle; ResID: Integer;  
ResType: PChar)`

Visibility: `public`

Description: The resource is loaded from the loaded module (identified by the handle `Instance`), identifier `ResID` and type `ResType`.

### 2.61.5 TResourceStream.Destroy

Synopsis: Destroys the instance of the resource stream.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: Destroys the instance of the resource stream.

## 2.62 TStream

### 2.62.1 Description

`TStream` is the base class for all streaming classes. It defines methods for reading (356), writing (356) from and to streams, as well as functions to determine the size of the stream as well as the current position of the stream.

Descendent classes such as `TMemoryStream` (328) or `TFileStream` (300) then override these methods to write streams to memory or file.

### 2.62.2 Method overview

Page	Property	Description
358	<code>CopyFrom</code>	Copy data from one stream to another
360	<code>FixupResourceHeader</code>	Not implemented in FPC
356	<code>Read</code>	Reads data from the stream to a buffer and returns the number of bytes read.
362	<code>ReadAnsiString</code>	Read an ansistring from the stream and return its value.
357	<code>ReadBuffer</code>	Reads data from the stream to a buffer
360	<code>ReadByte</code>	Read a byte from the stream and return its value.
358	<code>ReadComponent</code>	Reads component data from a stream
358	<code>ReadComponentRes</code>	Reads component data and resource header from a stream
361	<code>ReadDWord</code>	Read a DWord from the stream and return its value.
361	<code>ReadQWord</code>	Read a QWord value from the stream and return its value
360	<code>ReadResHeader</code>	Read a resource header from the stream.
361	<code>ReadWord</code>	Read a word from the stream and return its value.
356	<code>Seek</code>	Sets the current position in the stream
356	<code>Write</code>	Writes data from a buffer to the stream and returns the number of bytes written.
363	<code>WriteAnsiString</code>	Write an ansistring to the stream.
357	<code>WriteBuffer</code>	Writes data from the stream to the buffer
362	<code>WriteByte</code>	Write a byte to the stream.
359	<code>WriteComponent</code>	Write component data to the stream
359	<code>WriteComponentRes</code>	Write resource header and component data to a stream
359	<code>WriteDescendent</code>	Write component data to a stream, relative to an ancestor
359	<code>WriteDescendentRes</code>	Write resource header and component data to a stream, relative to an ancestor
362	<code>WriteDWord</code>	Write a DWord to the stream.
363	<code>WriteQWord</code>	Write a QWord value to the stream
360	<code>WriteResourceHeader</code>	Write resource header to the stream
362	<code>WriteWord</code>	Write a word to the stream.

### 2.62.3 Property overview

Page	Property	Access	Description
<a href="#">363</a>	Position	rw	The current position in the stream.
<a href="#">364</a>	Size	rw	The current size of the stream.

### 2.62.4 TStream.Read

**Synopsis:** Reads data from the stream to a buffer and returns the number of bytes read.

**Declaration:** `function Read(var Buffer;Count: LongInt) : LongInt; Virtual`

**Visibility:** public

**Description:** Read attempts to read Count from the stream to Buffer and returns the number of bytes actually read.

This method should be used when the number of bytes is not determined. If a specific number of bytes is expected, use TStream.ReadBuffer ([357](#)) instead.

As implemented in TStream, Read does nothing but raises an EStreamError ([226](#)) exception to indicate that reading is not supported. Descendent classes that allow reading must override this method to do the actual reading.

**Errors:** In case a descendent class does not allow reading from the stream, an exception is raised.

**See also:** TStream.Write ([356](#)), TStream.ReadBuffer ([357](#))

### 2.62.5 TStream.Write

**Synopsis:** Writes data from a buffer to the stream and returns the number of bytes written.

**Declaration:** `function Write(const Buffer;Count: LongInt) : LongInt; Virtual`

**Visibility:** public

**Description:** Write attempts to write Count bytes from Buffer to the stream. It returns the actual number of bytes written to the stream.

This method should be used when the number of bytes that should be written is not determined. If a specific number of bytes should be written, use TStream.WriteBuffer ([357](#)) instead.

As implemented in TStream, Write does nothing but raises EStreamError ([226](#)) exception to indicate that writing is not supported. Descendent classes that allow writing must override this method to do the actual writing.

**Errors:** In case a descendent class does not allow writing to the stream, an exception is raised.

**See also:** TStream.Read ([356](#)), TStream.WriteBuffer ([357](#))

### 2.62.6 TStream.Seek

**Synopsis:** Sets the current position in the stream

**Declaration:** `function Seek(Offset: LongInt;Origin: Word) : LongInt; Virtual  
; Overload  
function Seek(const Offset: Int64;Origin: TSeekOrigin) : Int64; Virtual  
; Overload`

**Visibility:** public

**Description:** `Seek` sets the position of the stream to `Offset` bytes from `Origin`. `Origin` can have one of the following values:

Table 2.22:

Constant	Meaning
<code>soFromBeginning</code>	Set the position relative to the start of the stream.
<code>soFromCurrent</code>	Set the position relative to the current position in the stream.
<code>soFromEnd</code>	Set the position relative to the end of the stream.

`Offset` should be negative when the origin is `SoFromEnd`. It should be positive for `soFromBeginning` and can have both signs for `soFromCurrent`.

This is an abstract method, which must be overridden by descendent classes. They may choose not to implement this method for all values of `Origin` and `Offset`.

**Errors:** An exception may be raised if this method is called with an invalid pair of `Offset`, `Origin` values. e.g. a negative offset for `soFromBeginning`.

See also: `TStream.Position` (363)

### 2.62.7 TStream.ReadBuffer

**Synopsis:** Reads data from the stream to a buffer

**Declaration:** `procedure ReadBuffer (var Buffer; Count: LongInt)`

**Visibility:** `public`

**Description:** `ReadBuffer` reads `Count` bytes of the stream into `Buffer`. If the stream does not contain `Count` bytes, then an exception is raised.

`ReadBuffer` should be used to read in a fixed number of bytes, such as when reading structures or the content of variables. If the number of bytes is not determined, use `TStream.Read` (356) instead. `ReadBuffer` uses `Read` internally to do the actual reading.

**Errors:** If the stream does not allow to read `Count` bytes, then an exception is raised.

See also: `TStream.Read` (356), `TStream.WriteBuffer` (357)

### 2.62.8 TStream.WriteBuffer

**Synopsis:** Writes data from the stream to the buffer

**Declaration:** `procedure WriteBuffer (const Buffer; Count: LongInt)`

**Visibility:** `public`

**Description:** `WriteBuffer` writes `Count` bytes to the stream from `Buffer`. If the stream does not allow `Count` bytes to be written, then an exception is raised.

`WriteBuffer` should be used to read in a fixed number of bytes, such as when writing structures or the content of variables. If the number of bytes is not determined, use `TStream.Write` (356) instead. `WriteBuffer` uses `Write` internally to do the actual reading.

**Errors:** If the stream does not allow to write `Count` bytes, then an exception is raised.

See also: `TStream.Write` (356), `TStream.ReadBuffer` (357)

### 2.62.9 TStream.CopyFrom

Synopsis: Copy data from one stream to another

Declaration: `function CopyFrom(Source: TStream; Count: Int64) : Int64`

Visibility: public

Description: `CopyFrom` reads `Count` bytes from `Source` and writes them to the current stream. This updates the current position in the stream. After the action is completed, the number of bytes copied is returned.

This can be used to quickly copy data from one stream to another or to copy the whole contents of the stream.

See also: `TStream.Read` (356), `TStream.Write` (356)

### 2.62.10 TStream.ReadComponent

Synopsis: Reads component data from a stream

Declaration: `function ReadComponent(Instance: TComponent) : TComponent`

Visibility: public

Description: `ReadComponent` reads a component state from the stream and transfers this state to `Instance`. If `Instance` is nil, then it is created first based on the type stored in the stream. `ReadComponent` returns the component as it is read from the stream.

`ReadComponent` simply creates a `TReader` (341) object and calls its `ReadRootComponent` (348) method.

Errors: If an error occurs during the reading of the component, an `EFileError` (224) exception is raised.

See also: `TStream.WriteComponent` (359), `TStream.ReadComponentRes` (358), `TReader.ReadRootComponent` (348)

### 2.62.11 TStream.ReadComponentRes

Synopsis: Reads component data and resource header from a stream

Declaration: `function ReadComponentRes(Instance: TComponent) : TComponent`

Visibility: public

Description: `ReadComponentRes` reads a resource header from the stream, and then calls `ReadComponent` (358) to read the component state from the stream into `Instance`.

This method is usually called by the global streaming method when instantiating forms and datamodules as created by an IDE. It should be used mainly on Windows, to store components in Windows resources.

Errors: If an error occurs during the reading of the component, an `EFileError` (224) exception is raised.

See also: `TStream.ReadComponent` (358), `TStream.WriteComponentRes` (359)



### 2.62.12 TStream.WriteComponent

Synopsis: Write component data to the stream

Declaration: `procedure WriteComponent (Instance: TComponent)`

Visibility: public

Description: `WriteComponent` writes the published properties of `Instance` to the stream, so they can later be read with `TStream.ReadComponent` (358). This method is intended to be used by an IDE, to preserve the state of a form or datamodule as designed in the IDE.

`WriteComponent` simply calls `WriteDescendent` (359) with `Nil` ancestor.

See also: `TStream.ReadComponent` (358), `TStream.WriteComponentRes` (359)

### 2.62.13 TStream.WriteComponentRes

Synopsis: Write resource header and component data to a stream

Declaration: `procedure WriteComponentRes (const ResName: String; Instance: TComponent)`

Visibility: public

Description: `WriteComponentRes` writes a `ResName` resource header to the stream and then calls `WriteComponent` (359) to write the published properties of `Instance` to the stream.

This method is intened for use by an IDE that can use it to store forms or datamodules as designed in a Windows resource stream.

See also: `TStream.WriteComponent` (359), `TStream.ReadComponentRes` (358)

### 2.62.14 TStream.WriteDescendent

Synopsis: Write component data to a stream, relative to an ancestor

Declaration: `procedure WriteDescendent (Instance: TComponent; Ancestor: TComponent)`

Visibility: public

Description: `WriteDescendent` writes the state of `Instance` to the stream where it differs from `Ancestor`, i.e. only the changed properties are written to the stream.

`WriteDescendent` creates a `TWriter` (398) object and calls its `WriteDescendent` (401) object. The writer is passed a binary driver object (260) by default.

### 2.62.15 TStream.WriteDescendentRes

Synopsis: Write resource header and component data to a stream, relative to an ancestor

Declaration: `procedure WriteDescendentRes (const ResName: String; Instance: TComponent; Ancestor: TComponent)`

Visibility: public

Description: `WriteDescendentRes` writes a `ResName` resource header, and then calls `WriteDescendent` (359) to write the state of `Instance` to the stream where it differs from `Ancestor`, i.e. only the changed properties are written to the stream.

This method is intened for use by an IDE that can use it to store forms or datamodules as designed in a Windows resource stream.

### 2.62.16 TStream.WriteResourceHeader

Synopsis: Write resource header to the stream

Declaration: `procedure WriteResourceHeader(const ResName: String;  
var FixupInfo: Integer)`

Visibility: public

Description: `WriteResourceHeader` writes a resource-file header for a resource called `ResName`. It returns in `FixupInfo` the argument that should be passed on to `TStream.FixupResourceHeader` (360).

`WriteResourceHeader` should not be used directly. It is called by the `TStream.WriteComponentRes` (359) and `TStream.WriteDescendentRes` (359) methods.

See also: `TStream.FixupResourceHeader` (360), `TStream.WriteComponentRes` (359), `TStream.WriteDescendentRes` (359)

### 2.62.17 TStream.FixupResourceHeader

Synopsis: Not implemented in FPC

Declaration: `procedure FixupResourceHeader(FixupInfo: Integer)`

Visibility: public

Description: `FixupResourceHeader` is used to write the size of the resource after a component was written to stream. The size is determined from the current position, and it is written at position `FixupInfo`. After that the current position is restored.

`FixupResourceHeader` should never be called directly; it is handled by the streaming system.

See also: `TStream.WriteResourceHeader` (360), `TStream.WriteComponentRes` (359), `TStream.WriteDescendentRes` (359)

### 2.62.18 TStream.ReadResHeader

Synopsis: Read a resource header from the stream.

Declaration: `procedure ReadResHeader`

Visibility: public

Description: `ReadResourceHeader` reads a resource file header from the stream. It positions the stream just beyond the header.

`ReadResourceHeader` should not be called directly, it is called by the streaming system when needed.

Errors: If the resource header is invalid an `EInvalidImage` (224) exception is raised.

See also: `TStream.ReadComponentRes` (358), `EInvalidImage` (224)

### 2.62.19 TStream.ReadByte

Synopsis: Read a byte from the stream and return its value.

Declaration: `function ReadByte : Byte`

Visibility: public

**Description:** `ReadByte` reads one byte from the stream and returns its value.

**Errors:** If the byte cannot be read, a `EStreamError` (226) exception will be raised. This is a utility function which simply calls the `Read` (356) function.

**See also:** `TStream.Read` (356), `TStream.WriteByte` (362), `TStream.ReadWord` (361), `TStream.ReadDWord` (361), `TStream.ReadAnsiString` (362)

### 2.62.20 `TStream.ReadWord`

**Synopsis:** Read a word from the stream and return its value.

**Declaration:** `function ReadWord : Word`

**Visibility:** `public`

**Description:** `ReadWord` reads one `Word` (i.e. 2 bytes) from the stream and returns its value. This is a utility function which simply calls the `Read` (356) function.

**Errors:** If the word cannot be read, a `EStreamError` (226) exception will be raised.

**See also:** `TStream.Read` (356), `TStream.WriteWord` (362), `TStream.ReadByte` (360), `TStream.ReadDWord` (361), `TStream.ReadAnsiString` (362)

### 2.62.21 `TStream.ReadDWord`

**Synopsis:** Read a `DWord` from the stream and return its value.

**Declaration:** `function ReadDWord : Cardinal`

**Visibility:** `public`

**Description:** `ReadDWord` reads one `DWord` (i.e. 4 bytes) from the stream and returns its value. This is a utility function which simply calls the `Read` (356) function.

**Errors:** If the `DWord` cannot be read, a `EStreamError` (226) exception will be raised.

**See also:** `TStream.Read` (356), `TStream.WriteDWord` (362), `TStream.ReadByte` (360), `TStream.ReadWord` (361), `TStream.ReadAnsiString` (362)

### 2.62.22 `TStream.ReadQWord`

**Synopsis:** Read a `QWord` value from the stream and return its value

**Declaration:** `function ReadQWord : QWord`

**Visibility:** `public`

**Description:** `ReadQWord` reads a `QWord` value (8 bytes) from the stream and returns its value.

**Errors:** If not enough bytes are available on the stream, an `EStreamError` (226) exception will be raised.

**See also:** `TStream.Read` (356), `TStream.WriteByte` (362), `TStream.ReadWord` (361), `TStream.ReadDWord` (361), `TStream.ReadAnsiString` (362)

**2.62.23 TStream.ReadAnsiString**

Synopsis: Read an ansistring from the stream and return its value.

Declaration: `function ReadAnsiString : String`

Visibility: `public`

Description: `ReadAnsiString` reads an ansistring from the stream and returns its value. This is a utility function which simply calls the read function several times. The Ansistring should be stored as 4 bytes (a DWord) representing the length of the string, and then the string value itself. The `WriteAnsiString` (363) function writes an ansistring in such a format.

Errors: If the `AnsiString` cannot be read, an `EStreamError` (226) exception will be raised.

See also: `TStream.Read` (356), `TStream.WriteAnsiString` (363), `TStream.ReadByte` (360), `TStream.ReadWord` (361), `TStream.ReadDWord` (361)

**2.62.24 TStream.WriteByte**

Synopsis: Write a byte to the stream.

Declaration: `procedure WriteByte(b: Byte)`

Visibility: `public`

Description: `WriteByte` writes the byte `B` to the stream. This is a utility function which simply calls the `Write` (356) function. The byte can be read from the stream using the `ReadByte` (360) function.

Errors: If an error occurs when attempting to write, an `EStreamError` (226) exception will be raised.

See also: `TStream.Write` (356), `TStream.ReadByte` (360), `TStream.WriteWord` (362), `TStream.WriteDWord` (362), `TStream.WriteAnsiString` (363)

**2.62.25 TStream.WriteWord**

Synopsis: Write a word to the stream.

Declaration: `procedure WriteWord(w: Word)`

Visibility: `public`

Description: `WriteWord` writes the word `W` (i.e. 2 bytes) to the stream. This is a utility function which simply calls the `Write` (356) function. The word can be read from the stream using the `ReadWord` (361) function.

Errors: If an error occurs when attempting to write, an `EStreamError` (226) exception will be raised.

See also: `TStream.Write` (356), `TStream.ReadWord` (361), `TStream.WriteByte` (362), `TStream.WriteDWord` (362), `TStream.WriteAnsiString` (363)

**2.62.26 TStream.WriteDWord**

Synopsis: Write a DWord to the stream.

Declaration: `procedure WriteDWord(d: Cardinal)`

Visibility: `public`

**Description:** `WriteDWord` writes the `DWord D` (i.e. 4 bytes) to the stream. This is a utility function which simply calls the `Write` (356) function. The `DWord` can be read from the stream using the `ReadDWord` (361) function.

**Errors:** If an error occurs when attempting to write, an `EStreamError` (226) exception will be raised.

**See also:** `TStream.Write` (356), `TStream.ReadDWord` (361), `TStream.WriteByte` (362), `TStream.WriteWord` (362), `TStream.WriteString` (363)

### 2.62.27 TStream.WriteQWord

**Synopsis:** Write a `QWord` value to the stream

**Declaration:** `procedure WriteQWord(q: QWord)`

**Visibility:** `public`

**Description:** `WriteQWord` writes the word `W` (i.e. 8 bytes) to the stream. This is a utility function which simply calls the `Write` (356) function. The word can be read from the stream using the `ReadQWord` (361) function.

**Errors:** If an error occurs when attempting to write, an `EStreamError` (226) exception will be raised.

**See also:** `TStream.Write` (356), `TStream.ReadByte` (360), `TStream.WriteWord` (362), `TStream.WriteDWord` (362), `TStream.WriteString` (363)

### 2.62.28 TStream.WriteString

**Synopsis:** Write an ansistring to the stream.

**Declaration:** `procedure WriteAnsiString(const S: String)`

**Visibility:** `public`

**Description:** `WriteAnsiString` writes the `AnsiString S` (i.e. 4 bytes) to the stream. This is a utility function which simply calls the `Write` (356) function. The ansistring is written as a 4 byte length specifier, followed by the ansistring's content. The ansistring can be read from the stream using the `ReadAnsiString` (362) function.

**Errors:** If an error occurs when attempting to write, an `EStreamError` (226) exception will be raised.

**See also:** `TStream.Write` (356), `TStream.ReadAnsiString` (362), `TStream.WriteByte` (362), `TStream.WriteWord` (362), `TStream.WriteDWord` (362)

### 2.62.29 TStream.Position

**Synopsis:** The current position in the stream.

**Declaration:** `Property Position : Int64`

**Visibility:** `public`

**Access:** `Read, Write`

**Description:** `Position` can be read to determine the current position in the stream. It can be written to to set the (absolute) position in the stream. The position is zero-based, so to set the position at the beginning of the stream, the position must be set to zero.

**Remark:** Not all `TStream` descendants support setting the position in the stream, so this should be used with care.

**Errors:** Some descendents may raise an `EStreamError` (226) exception if they do not support setting the stream position.

See also: `TStream.Size` (364), `TStream.Seek` (356)

### 2.62.30 TStream.Size

**Synopsis:** The current size of the stream.

**Declaration:** `Property Size : Int64`

**Visibility:** `public`

**Access:** `Read,Write`

**Description:** `Size` can be read to determine the stream size or to set the stream size.

**Remark:** Not all descendents of `TStream` support getting or setting the stream size; they may raise an exception if the `Size` property is read or set.

See also: `TStream.Position` (363), `TStream.Seek` (356)

## 2.63 TStreamAdapter

### 2.63.1 Description

Implements `IStream` for `TStream` (355) descendents

### 2.63.2 Method overview

Page	Property	Description
368	<code>Clone</code>	Clone the stream
366	<code>Commit</code>	Commit data to the stream
366	<code>CopyTo</code>	Copy data to destination stream
365	<code>Create</code>	Create a new instance of <code>TStreamAdapter</code>
365	<code>Destroy</code>	Free the <code>TStreamAdapter</code> instance
367	<code>LockRegion</code>	Lock a region of the stream
365	<code>Read</code>	Read from the stream.
367	<code>Revert</code>	Revert operations on the stream
366	<code>Seek</code>	Set the stream position
366	<code>SetSize</code>	Set the stream size
367	<code>Stat</code>	Return statistical data about the stream
367	<code>UnlockRegion</code>	Unlock a region of the stream
365	<code>Write</code>	Write to the stream

### 2.63.3 Property overview

Page	Property	Access	Description
368	<code>Stream</code>	<code>r</code>	Stream on which adaptor works
368	<code>StreamOwnership</code>	<code>rw</code>	Determines what happens with the stream when the adaptor is freed

### 2.63.4 TStreamAdapter.Create

Synopsis: Create a new instance of `TStreamAdapter`

Declaration: `constructor Create(Stream: TStream;Ownership: TStreamOwnership)`

Visibility: `public`

Description: `Create` creates a new instance of `TStreamAdaptor`. It initializes `TStreamAdapter.Stream` (368) with `Stream` and initializes `StreamOwnerShip` (368) with `Ownership`.

`TStreamAdapter` is an abstract class: descendents must be created that implement the actual functionality.

Errors:

See also: `TStreamAdapter.StreamOwnerShip` (368), `TStreamAdapter.Stream` (368)

### 2.63.5 TStreamAdapter.Destroy

Synopsis: Free the `TStreamAdapter` instance

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: Explicitly free the `TStreamAdapter` instance. Normally, this is done automatically if a reference to the `IStream` interface is freed.

### 2.63.6 TStreamAdapter.Read

Synopsis: Read from the stream.

Declaration: `function Read(pv: Pointer;cb: DWORD;pcbRead: PDWord) : HRESULT; Virtual`

Visibility: `public`

Description: `Read` implements `IStream.Read` (194) by reading from the stream specified at creation.

Errors: This function must be overridden and will raise a `runerror 217` when called directly.

See also: `IStream.Read` (194)

### 2.63.7 TStreamAdapter.Write

Synopsis: Write to the stream

Declaration: `function Write(pv: Pointer;cb: DWORD;pcbWritten: PDWord) : HRESULT; Virtual`

Visibility: `public`

Description: `Write` implements `IStream.Write` (194) by writing to the stream specified at creation.

Errors: This function must be overridden and will raise a `runerror 217` when called directly.

See also: `IStream.Write` (194)

### 2.63.8 TStreamAdapter.Seek

Synopsis: Set the stream position

Declaration: `function Seek(dlibMove: Largeint; dwOrigin: LongInt;  
out libNewPosition: Largeint) : HRESULT; Virtual`

Visibility: public

Description: `Seek` implements `IStream.Seek` (194) by setting the position of the stream specified at creation.

Errors: This function must be overridden and will raise a `runerror 217` when called directly.

See also: `IStream.Seek` (194)

### 2.63.9 TStreamAdapter.SetSize

Synopsis: Set the stream size

Declaration: `function SetSize(libNewSize: Largeint) : HRESULT; Virtual`

Visibility: public

Description: `SetSize` implements `IStream.SetSize` (194) by setting the size of the stream specified at creation.

Errors: This function must be overridden and will raise a `runerror 217` when called directly.

See also: `IStream.SetSize` (194)

### 2.63.10 TStreamAdapter.CopyTo

Synopsis: Copy data to destination stream

Declaration: `function CopyTo(stm: IStream; cb: Largeint; out cbRead: Largeint;  
out cbWritten: Largeint) : HRESULT; Virtual`

Visibility: public

Description: `CopyTo` implements `IStream.CopyTo` (194).

Errors: This function must be overridden and will raise a `runerror 217` when called directly.

### 2.63.11 TStreamAdapter.Commit

Synopsis: Commit data to the stream

Declaration: `function Commit(grfCommitFlags: LongInt) : HRESULT; Virtual`

Visibility: public

Description: `Commit` implements `IStream.Commit` (194).

Errors: This function must be overridden and will raise a `runerror 217` when called directly.

See also: `IStream.Commit` (194)



### 2.63.12 TStreamAdapter.Revert

Synopsis: Revert operations on the stream

Declaration: `function Revert : HRESULT; Virtual`

Visibility: public

Description: `Revert` implements `IStream.Revert` (194).

Errors: This function must be overridden and will raise a `runerror 217` when called directly.

See also: `IStream.Revert` (194)

### 2.63.13 TStreamAdapter.LockRegion

Synopsis: Lock a region of the stream

Declaration: `function LockRegion(libOffset: Largeint;cb: Largeint;  
dwLockType: LongInt) : HRESULT; Virtual`

Visibility: public

Description: `LockRegion` implements `IStream.LockRegion` (194).

Errors: This function must be overridden and will raise a `runerror 217` when called directly.

See also: `IStream.LockRegion` (194)

### 2.63.14 TStreamAdapter.UnlockRegion

Synopsis: Unlock a region of the stream

Declaration: `function UnlockRegion(libOffset: Largeint;cb: Largeint;  
dwLockType: LongInt) : HRESULT; Virtual`

Visibility: public

Description: `UnLockRegion` implements `IStream.UnLockRegion` (194).

Errors: This function must be overridden and will raise a `runerror 217` when called directly.

See also: `IStream.UnLockRegion` (194)

### 2.63.15 TStreamAdapter.Stat

Synopsis: Return statistical data about the stream

Declaration: `function Stat(out statstg: TStatStg;grfStatFlag: LongInt) : HRESULT  
; Virtual`

Visibility: public

Description: `Stat` implements `IStream.Stat` (194).

Errors: This function must be overridden and will raise a `runerror 217` when called directly.

See also: `IStream.Stat` (194)

### 2.63.16 TStreamAdapter.Clone

Synopsis: Clone the stream

Declaration: `function Clone(out stm: IStream) : HRESULT; Virtual`

Visibility: public

Description: `Clone` implements `IStream.Clone` ([194](#)).

Errors: This function must be overridden and will raise a `runerror 217` when called directly.

See also: `IStream.Clone` ([194](#))

### 2.63.17 TStreamAdapter.Stream

Synopsis: Stream on which adaptor works

Declaration: `Property Stream : TStream`

Visibility: public

Access: Read

Description: This is the stream on which the adaptor works. It was specified at creation.

### 2.63.18 TStreamAdapter.StreamOwnership

Synopsis: Determines what happens with the stream when the adaptor is freed

Declaration: `Property StreamOwnership : TStreamOwnership`

Visibility: public

Access: Read, Write

Description: `StreamOwnership` determines what happens when the adaptor

## 2.64 TStringList

### 2.64.1 Description

`TStringList` is a descendent class of `TStrings` ([373](#)) that implements all of the abstract methods introduced there. It also introduces some additional methods:

- Sort the list, or keep the list sorted at all times
- Special handling of duplicates in sorted lists
- Notification of changes in the list

### 2.64.2 Method overview

Page	Property	Description
<a href="#">369</a>	Add	Implements the TStrings.Add ( <a href="#">375</a> ) function.
<a href="#">370</a>	Clear	Implements the TStrings.Clear ( <a href="#">377</a> ) function.
<a href="#">371</a>	CustomSort	Sort the stringlist using a custom sort algorithm
<a href="#">370</a>	Delete	Implements the TStrings.Delete ( <a href="#">377</a> ) function.
<a href="#">369</a>	Destroy	Destroys the stringlist.
<a href="#">370</a>	Exchange	Implements the TStrings.Exchange ( <a href="#">378</a> ) function.
<a href="#">370</a>	Find	Locates the index for a given string in sorted lists.
<a href="#">371</a>	IndexOf	Overrides the TStrings.IndexOf ( <a href="#">379</a> ) property.
<a href="#">371</a>	Insert	Overrides the TStrings.Insert ( <a href="#">380</a> ) method.
<a href="#">371</a>	Sort	Sorts the strings in the list.

### 2.64.3 Property overview

Page	Property	Access	Description
<a href="#">372</a>	CaseSensitive	rw	
<a href="#">372</a>	Duplicates	rw	Describes the behaviour of a sorted list with respect to duplicate strings.
<a href="#">373</a>	OnChange	rw	Event triggered after the list was modified.
<a href="#">373</a>	OnChanging	rw	Event triggered when the list is about to be modified.
<a href="#">372</a>	Sorted	rw	Determines whether the list is sorted or not.

### 2.64.4 TStringList.Destroy

Synopsis: Destroys the stringlist.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` clears the stringlist, release all memory allocated for the storage of the strings, and then calls the inherited destroy method.

**Remark:** Any objects associated to strings in the list will *not* be destroyed; it is the responsibility of the caller to destroy all objects associated with strings in the list.

### 2.64.5 TStringList.Add

Synopsis: Implements the TStrings.Add ([375](#)) function.

Declaration: `function Add(const S: String) : Integer; Override`

Visibility: `public`

Description: `Add` will add `S` to the list. If the list is sorted and the string `S` is already present in the list and `TStringList.Duplicates` ([372](#)) is `dupError` then an `EStringListError` ([226](#)) exception is raised. If `Duplicates` is set to `dupIgnore` then the return value is undefined.

If the list is sorted, new strings will not necessarily be added to the end of the list, rather they will be inserted at their alphabetical position.

Errors: If the list is sorted and the string `S` is already present in the list and `TStringList.Duplicates` ([372](#)) is `dupError` then an `EStringListError` ([226](#)) exception is raised.

See also: `TStringList.Insert` ([371](#)), `TStringList.Duplicates` ([372](#))

### 2.64.6 TStringList.Clear

Synopsis: Implements the `TStrings.Clear` (377) function.

Declaration: `procedure Clear; Override`

Visibility: `public`

Description: Implements the `TStrings.Clear` (377) function.

### 2.64.7 TStringList.Delete

Synopsis: Implements the `TStrings.Delete` (377) function.

Declaration: `procedure Delete(Index: Integer); Override`

Visibility: `public`

Description: Implements the `TStrings.Delete` (377) function.

### 2.64.8 TStringList.Exchange

Synopsis: Implements the `TStrings.Exchange` (378) function.

Declaration: `procedure Exchange(Index1: Integer; Index2: Integer); Override`

Visibility: `public`

Description: `Exchange` will exchange two items in the list as described in `TStrings.Exchange` (378).

**Remark:** `Exchange` will not check whether the list is sorted or not; if `Exchange` is called on a sorted list and the strings are not identical, the sort order of the list will be destroyed.

See also: `TStringList.Sorted` (372), `TStrings.Exchange` (378)

### 2.64.9 TStringList.Find

Synopsis: Locates the index for a given string in sorted lists.

Declaration: `function Find(const S: String; var Index: Integer) : Boolean; Virtual`

Visibility: `public`

Description: `Find` returns `True` if the string `S` is present in the list. Upon exit, the `Index` parameter will contain the position of the string in the list. If the string is not found, the function will return `False` and `Index` will contain the position where the string will be inserted if it is added to the list.

**Remark:**

1. Use this method only on sorted lists. For unsorted lists, use `TStringList.IndexOf` (371) instead.
2. `Find` uses a binary search method to locate the string

### 2.64.10 TStringList.IndexOf

Synopsis: Overrides the TStrings.IndexOf ([379](#)) property.

Declaration: `function IndexOf(const S: String) : Integer; Override`

Visibility: public

Description: `IndexOf` overrides the ancestor method `TStrings.IndexOf` ([379](#)). It tries to optimize the search by executing a binary search if the list is sorted. The function returns the position of `S` if it is found in the list, or -1 if the string is not found in the list.

See also: `TStrings.IndexOf` ([379](#)), `TStringList.Find` ([370](#))

### 2.64.11 TStringList.Insert

Synopsis: Overrides the TStrings.Insert ([380](#)) method.

Declaration: `procedure Insert(Index: Integer; const S: String); Override`

Visibility: public

Description: `Insert` will insert the string `S` at position `Index` in the list. If the list is sorted, an `EStringListError` ([226](#)) exception will be raised instead. `Index` is a zero-based position.

Errors: If `Index` contains an invalid value (less than zero or larger than `Count`, or the list is sorted, an `EStringListError` ([226](#)) exception will be raised.

See also: `TStringList.Add` ([369](#)), `TStrings.Insert` ([380](#)), `TStringList.InsertObject` ([368](#))

### 2.64.12 TStringList.Sort

Synopsis: Sorts the strings in the list.

Declaration: `procedure Sort; Virtual`

Visibility: public

Description: `Sort` will sort the strings in the list using the quicksort algorithm. If the list has its `TStringList.Sorted` ([372](#)) property set to `True` then nothing will be done.

See also: `TStringList.Sorted` ([372](#))

### 2.64.13 TStringList.CustomSort

Synopsis: Sort the stringlist using a custom sort algorithm

Declaration: `procedure CustomSort(CompareFn: TStringListSortCompare); Virtual`

Visibility: public

Description: `CustomSort` sorts the stringlist with a custom comparison function. The function should compare 2 elements in the list, and return a negative number if the first item is before the second. It should return 0 if the elements are equal, and a positive result indicates that the second elements should be before the first.

See also: `TStringList.Sorted` ([372](#)), `TStringList.Sort` ([371](#))

### 2.64.14 TStringList.Duplicates

**Synopsis:** Describes the behaviour of a sorted list with respect to duplicate strings.

**Declaration:** `Property Duplicates : TDuplicates`

**Visibility:** `public`

**Access:** `Read,Write`

**Description:** `Duplicates` describes what to do in case a duplicate value is added to the list:

Table 2.23:

<code>dupIgnore</code>	Duplicate values will not be added to the list, but no error will be triggered.
<code>dupError</code>	If an attempt is made to add a duplicate value to the list, an <code>EStringListError</code> (226) exception is raised.
<code>dupAccept</code>	Duplicate values can be added to the list.

If the stringlist is not sorted, the `Duplicates` setting is ignored.

### 2.64.15 TStringList.Sorted

**Synopsis:** Determines whether the list is sorted or not.

**Declaration:** `Property Sorted : Boolean`

**Visibility:** `public`

**Access:** `Read,Write`

**Description:** `Sorted` can be set to `True` in order to cause the list of strings to be sorted. Further additions to the list will be inserted at the correct position so the list remains sorted at all times. Setting the property to `False` has no immediate effect, but will allow strings to be inserted at any position.

**Remark:**

1. When `Sorted` is `True`, `TStringList.Insert` (371) cannot be used. For sorted lists, `TStringList.Add` (369) should be used instead.
2. If `Sorted` is `True`, the `TStringList.Duplicates` (372) setting has effect. This setting is ignored when `Sorted` is `False`.

See also: `TStringList.Sort` (371), `TStringList.Duplicates` (372), `TStringList.Add` (369), `TstringList.Insert` (371)

### 2.64.16 TStringList.CaseSensitive

**Synopsis:**

**Declaration:** `Property CaseSensitive : Boolean`

**Visibility:** `public`

**Access:** `Read,Write`

**Description:** Indicates whether locating strings happens in a case sensitive manner.

### 2.64.17 TStringList.OnChange

Synopsis: Event triggered after the list was modified.

Declaration: `Property OnChange : TNotifyEvent`

Visibility: `public`

Access: `Read,Write`

Description: `OnChange` can be assigned to respond to changes that have occurred in the list. The handler is called whenever strings are added, moved, modified or deleted from the list.

The `OnChange` event is triggered after the modification took place. When the modification is about to happen, an `TStringList.OnChanging` (373) event occurs.

See also: `TStringList.OnChanging` (373)

### 2.64.18 TStringList.OnChanging

Synopsis: Event triggered when the list is about to be modified.

Declaration: `Property OnChanging : TNotifyEvent`

Visibility: `public`

Access: `Read,Write`

Description: `OnChanging` can be assigned to respond to changes that will occurred in the list. The handler is called whenever strings will be added, moved, modified or deleted from the list.

The `OnChanging` event is triggered before the modification will take place. When the modification has happened, an `TStringList.OnChange` (373) event occurs.

See also: `TStringList.OnChange` (373)

## 2.65 TStrings

### 2.65.1 Description

`TStrings` implements an abstract class to manage an array of strings. It introduces methods to set and retrieve strings in the array, searching for a particular string, concatenating the strings and so on. It also allows an arbitrary object to be associated with each string.

It also introduces methods to manage a series of `name=value` settings, as found in many configuration files.

An instance of `TStrings` is never created directly, instead a descendent class such as `TStringList` (368) should be created. This is because `TStrings` is an abstract class which does not implement all methods; `TStrings` also doesn't store any strings, this is the functionality introduced in descendents such as `TStringList` (368).

**2.65.2 Method overview**

Page	Property	Description
<a href="#">375</a>	Add	Add a string to the list
<a href="#">375</a>	AddObject	Add a string and associated object to the list.
<a href="#">376</a>	AddStrings	Add contents of another stringlist to this list.
<a href="#">375</a>	Append	Add a string to the list.
<a href="#">376</a>	Assign	Assign the contents of another stringlist to this one.
<a href="#">376</a>	BeginUpdate	Mark the beginning of an update batch.
<a href="#">377</a>	Clear	Removes all strings and associated objects from the list.
<a href="#">377</a>	Delete	Delete a string from the list.
<a href="#">375</a>	Destroy	Frees all strings and objects, and removes the list from memory.
<a href="#">377</a>	EndUpdate	Mark the end of an update batch.
<a href="#">377</a>	Equals	Compares the contents of two stringlists.
<a href="#">378</a>	Exchange	Exchanges two strings in the list.
<a href="#">383</a>	ExtractName	Extract the name part of a string
<a href="#">378</a>	GetEnumerator	Create an <code>IEnumerator</code> instance
<a href="#">382</a>	GetNameValue	Return both name and value of a name,value pair based on it's index.
<a href="#">378</a>	GetText	Returns the contents as a <code>PChar</code>
<a href="#">379</a>	IndexOf	Find a string in the list and return its position.
<a href="#">379</a>	IndexOfName	Finds the index of a name in the name-value pairs.
<a href="#">379</a>	IndexOfObject	Finds an object in the list and returns its index.
<a href="#">380</a>	Insert	Insert a string in the list.
<a href="#">380</a>	InsertObject	Insert a string and associated object in the list.
<a href="#">380</a>	LoadFromFile	Load the contents of a file as a series of strings.
<a href="#">381</a>	LoadFromStream	Load the contents of a stream as a series of strings.
<a href="#">381</a>	Move	Move a string from one place in the list to another.
<a href="#">382</a>	SaveToFile	Save the contents of the list to a file.
<a href="#">382</a>	SaveToStream	Save the contents of the string to a stream.
<a href="#">382</a>	SetText	Set the contents of the list from a <code>PChar</code> .

**2.65.3 Property overview**

Page	Property	Access	Description
<a href="#">385</a>	Capacity	rw	Capacity of the list, i.e. number of strings that the list can currently hold before it tries to expand.
<a href="#">385</a>	CommaText	rw	Contents of the list as a comma-separated string.
<a href="#">386</a>	Count	r	Number of strings in the list.
<a href="#">384</a>	DelimitedText	rw	Get or set all strings in the list in a delimited form.
<a href="#">383</a>	Delimiter	rw	Delimiter character used in <code>DelimitedText</code> ( <a href="#">384</a> ).
<a href="#">387</a>	Names	r	Name parts of the name-value pairs in the list.
<a href="#">385</a>	NameValueSeparator	rw	Value of the character used to separate name,value pairs
<a href="#">387</a>	Objects	rw	Indexed access to the objects associated with the strings in the list.
<a href="#">384</a>	QuoteChar	rw	Quote character used in <code>DelimitedText</code> ( <a href="#">384</a> ).
<a href="#">384</a>	StrictDelimiter	rw	Should only the delimiter character be considered a delimiter
<a href="#">388</a>	Strings	rw	Indexed access to the strings in the list.
<a href="#">389</a>	StringsAdapter	rw	Not implemented in Free Pascal.
<a href="#">388</a>	Text	rw	Contents of the list as one big string.
<a href="#">383</a>	TextLineBreakStyle	rw	Determines which line breaks to use in the <code>Text</code> ( <a href="#">388</a> ) property
<a href="#">385</a>	ValueFromIndex	rw	Return the value part of a string based on it's index.
<a href="#">387</a>	Values	rw	Value parts of the name-value pairs in the list.



### 2.65.4 TStrings.Destroy

Synopsis: Frees all strings and objects, and removes the list from memory.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` is the destructor of `TStrings` it does nothing except calling the inherited destructor.

### 2.65.5 TStrings.Add

Synopsis: Add a string to the list

Declaration: `function Add(const S: String) : Integer; Virtual`

Visibility: `public`

Description: `Add` adds `S` at the end of the list and returns the index of `S` in the list (which should equal `TStrings.Count` [\(386\)](#))

See also: `TStrings.Items` [\(373\)](#), `TStrings.AddObject` [\(375\)](#), `TStrings.Insert` [\(380\)](#), `TStrings.Delete` [\(377\)](#), `TStrings.Strings` [\(388\)](#), `TStrings.Count` [\(386\)](#)

### 2.65.6 TStrings.AddObject

Synopsis: Add a string and associated object to the list.

Declaration: `function AddObject(const S: String; AObject: TObject) : Integer; Virtual`

Visibility: `public`

Description: `AddObject` adds `S` to the list of strings, and associates `AObject` with it. It returns the index of `S`.

**Remark:** An object added to the list is not automatically destroyed by the list if the list is destroyed or the string it is associated with is deleted. It is the responsibility of the application to destroy any objects associated with strings.

See also: `TStrings.Add` [\(375\)](#), `TStrings.Items` [\(373\)](#), `TStrings.Objects` [\(387\)](#), `TStrings.InsertObject` [\(380\)](#)

### 2.65.7 TStrings.Append

Synopsis: Add a string to the list.

Declaration: `procedure Append(const S: String)`

Visibility: `public`

Description: `Append` does the same as `TStrings.Add` [\(375\)](#), only it does not return the index of the inserted string.

See also: `TStrings.Add` [\(375\)](#)

### 2.65.8 TStrings.AddStrings

**Synopsis:** Add contents of another stringlist to this list.

**Declaration:** `procedure AddStrings(TheStrings: TStrings); Virtual`

**Visibility:** public

**Description:** `AddStrings` adds the contents of `TheStrings` to the stringlist. Any associated objects are added as well.

See also: `TStrings.Add` (375), `TStrings.Assign` (376)

### 2.65.9 TStrings.Assign

**Synopsis:** Assign the contents of another stringlist to this one.

**Declaration:** `procedure Assign(Source: TPersistent); Override`

**Visibility:** public

**Description:** `Assign` replaces the contents of the stringlist with the contents of `Source` if `Source` is also of type `TStrings`. Any associated objects are copied as well.

See also: `TStrings.Add` (375), `TStrings.AddStrings` (376), `TPersistent.Assign` (339)

### 2.65.10 TStrings.BeginUpdate

**Synopsis:** Mark the beginning of an update batch.

**Declaration:** `procedure BeginUpdate`

**Visibility:** public

**Description:** `BeginUpdate` increases the update count by one. It is advisable to call `BeginUpdate` before lengthy operations on the stringlist. At the end of these operation, `TStrings.EndUpdate` (377) should be called to mark the end of the operation. Descendent classes may use this information to perform optimizations. e.g. updating the screen only once after many strings were added to the list.

All `TStrings` methods that modify the string list call `BeginUpdate` before the actual operation, and call `endUpdate` when the operation is finished. Descendent classes should also call these methods when modifying the string list.

**Remark:** Always put the corresponding call to `TStrings.EndUpdate` (377) in the context of a `Finally` block, to ensure that the update count is always decreased at the end of the operation, even if an exception occurred:

```
With MyStrings do
  try
    BeginUpdate;
    // Some lengthy operation.
  finally
    EndUpdate
  end;
```

See also: `TStrings.EndUpdate` (377)

### 2.65.11 TStrings.Clear

Synopsis: Removes all strings and associated objects from the list.

Declaration: `procedure Clear; Virtual; Abstract`

Visibility: `public`

Description: `Clear` will remove all strings and their associated objects from the list. After a call to `clear`, `TStrings.Count` (386) is zero.

Since it is an abstract method, `TStrings` itself does not implement `Clear`. Descendent classes such as `TStringList` (368) implement this method.

See also: `TStrings.Items` (373), `TStrings.Delete` (377), `TStrings.Count` (386)

### 2.65.12 TStrings.Delete

Synopsis: Delete a string from the list.

Declaration: `procedure Delete(Index: Integer); Virtual; Abstract`

Visibility: `public`

Description: `Delete` deletes the string at position `Index` from the list. The associated object is also removed from the list, but not destroyed. `Index` is zero-based, and should be in the range 0 to `Count-1`.

Since it is an abstract method, `TStrings` itself does not implement `Delete`. Descendent classes such as `TStringList` (368) implement this method.

Errors: If `Index` is not in the allowed range, an `EStringListError` (226) is raised.

See also: `TStrings.Insert` (380), `TStrings.Items` (373), `TStrings.Clear` (377)

### 2.65.13 TStrings.EndUpdate

Synopsis: Mark the end of an update batch.

Declaration: `procedure EndUpdate`

Visibility: `public`

Description: `EndUpdate` should be called at the end of a lengthy operation on the stringlist, but only if there was a call to `BeginUpdate` before the operation was started. It is best to put the call to `EndUpdate` in the context of a `Finally` block, so it will be called even if an exception occurs.

For more information, see `TStrings.BeginUpdate` (376).

See also: `TStrings.BeginUpdate` (376)

### 2.65.14 TStrings.Equals

Synopsis: Compares the contents of two stringlists.

Declaration: `function Equals(Obj: TObject) : Boolean; Override; Overload`  
`function Equals(TheStrings: TStrings) : Boolean; Overload`

Visibility: `public`

**Description:** `Equals` compares the contents of the stringlist with the contents of `TheStrings`. If the contents match, i.e. the stringlist contain an equal amount of strings, and all strings match, then `True` is returned. If the number of strings in the lists is unequal, or they contain one or more different strings, `False` is returned.

**Remark:**

1. The strings are compared case-insensitively.
2. The associated objects are not compared

See also: `TStrings.Items` (373), `TStrings.Count` (386), `TStrings.Assign` (376)

### 2.65.15 TStrings.Exchange

**Synopsis:** Exchanges two strings in the list.

**Declaration:** `procedure Exchange(Index1: Integer; Index2: Integer); Virtual`

**Visibility:** `public`

**Description:** `Exchange` exchanges the strings at positions `Index1` and `Index2`. The associated objects are also exchanged.

Both indexes must be in the range of valid indexes, i.e. must have a value between 0 and `Count-1`.

**Errors:** If either `Index1` or `Index2` is not in the range of valid indexes, an `EStringListError` (226) exception is raised.

See also: `TStrings.Move` (381), `TStrings.Strings` (388), `TStrings.Count` (386)

### 2.65.16 TStrings.GetEnumerator

**Synopsis:** Create an `IEnumerator` instance

**Declaration:** `function GetEnumerator : TStringsEnumerator`

**Visibility:** `public`

**Description:** `GetEnumerator` is the implementation of the `IEnumerable` (1405) interface for `TStrings`. It creates a `TStringsEnumerator` (389) instance and returns its `IEnumerator` (1406) interface.

See also: `TStringsEnumerator` (389), `#rtl.system.IEnumerator` (1406), `#rtl.system.IEnumerable` (1405)

### 2.65.17 TStrings.GetText

**Synopsis:** Returns the contents as a `PChar`

**Declaration:** `function GetText : PChar; Virtual`

**Visibility:** `public`

**Description:** `GetText` allocates a memory buffer and copies the contents of the stringlist to this buffer as a series of strings, separated by an end-of-line marker. The buffer is zero terminated.

**Remark:** The caller is responsible for freeing the returned memory buffer.

### 2.65.18 TStrings.IndexOf

Synopsis: Find a string in the list and return its position.

Declaration: `function IndexOf(const S: String) : Integer; Virtual`

Visibility: public

Description: `IndexOf` searches the list for `S`. The search is case-insensitive. If a matching entry is found, its position is returned. If no matching string is found, `-1` is returned.

**Remark:**

1. Only the first occurrence of the string is returned.
2. The returned position is zero-based, i.e. 0 indicates the first string in the list.

See also: `TStrings.IndexOfObject` (379), `TStrings.IndexOfName` (379), `TStrings.Strings` (388)

### 2.65.19 TStrings.IndexOfName

Synopsis: Finds the index of a name in the name-value pairs.

Declaration: `function IndexOfName(const Name: String) : Integer; Virtual`

Visibility: public

Description: `IndexOfName` searches in the list of strings for a name-value pair with name part `Name`. If such a pair is found, it returns the index of the pair in the stringlist. If no such pair is found, the function returns `-1`. The search is done case-insensitive.

**Remark:**

1. Only the first occurrence of a matching name-value pair is returned.
2. The returned position is zero-based, i.e. 0 indicates the first string in the list.

See also: `TStrings.IndexOf` (379), `TStrings.IndexOfObject` (379), `TStrings.Strings` (388)

### 2.65.20 TStrings.IndexOfObject

Synopsis: Finds an object in the list and returns its index.

Declaration: `function IndexOfObject(AObject: TObject) : Integer; Virtual`

Visibility: public

Description: `IndexOfObject` searches through the list of strings till it find a string associated with `AObject`, and returns the index of this string. If no such string is found, `-1` is returned.

**Remark:**

1. Only the first occurrence of a string with associated object `AObject` is returned; if more strings in the list can be associated with `AObject`, they will not be found by this routine.
2. The returned position is zero-based, i.e. 0 indicates the first string in the list.

### 2.65.21 TStrings.Insert

Synopsis: Insert a string in the list.

Declaration: `procedure Insert(Index: Integer; const S: String); Virtual; Abstract`

Visibility: public

Description: `Insert` inserts the string `S` at position `Index` in the list. `Index` is a zero-based position, and can have values from 0 to `Count`. If `Index` equals `Count` then the string is appended to the list.

**Remark:**

1. All methods that add strings to the list use `Insert` to add a string to the list.
2. If the string has an associated object, use `TStrings.InsertObject` (380) instead.

Errors: If `Index` is less than zero or larger than `Count` then an `EStringListError` (226) exception is raised.

See also: `TStrings.Add` (375), `TStrings.InsertObject` (380), `TStrings.Append` (375), `TStrings.Delete` (377)

### 2.65.22 TStrings.InsertObject

Synopsis: Insert a string and associated object in the list.

Declaration: `procedure InsertObject(Index: Integer; const S: String; AObject: TObject)`

Visibility: public

Description: `InsertObject` inserts the string `S` and its associated object `AObject` at position `Index` in the list. `Index` is a zero-based position, and can have values from 0 to `Count`. If `Index` equals `Count` then the string is appended to the list.

Errors: If `Index` is less than zero or larger than `Count` then an `EStringListError` (226) exception is raised.

See also: `TStrings.Insert` (380), `TStrings.AddObject` (375), `TStrings.Append` (375), `TStrings.Delete` (377)

### 2.65.23 TStrings.LoadFromFile

Synopsis: Load the contents of a file as a series of strings.

Declaration: `procedure LoadFromFile(const FileName: String); Virtual`

Visibility: public

Description: `LoadFromFile` loads the contents of a file into the stringlist. Each line in the file (as marked by the end-of-line marker of the particular OS the application runs on) becomes one string in the stringlist. This action replaces the contents of the stringlist, it does not append the strings to the current content.

`LoadFromFile` simply creates a file stream (300) with the given filename, and then executes `TStrings.LoadfromStream` (381); after that the file stream object is destroyed again.

See also: `TStrings.LoadFromStream` (381), `TStrings.SaveToFile` (382), `Tstrings.SaveToStream` (382)

### 2.65.24 TStrings.LoadFromStream

**Synopsis:** Load the contents of a stream as a series of strings.

**Declaration:** `procedure LoadFromStream(Stream: TStream); Virtual`

**Visibility:** public

**Description:** `LoadFromStream` loads the contents of `Stream` into the stringlist. Each line in the stream (as marked by the end-of-line marker of the particular OS the application runs on) becomes one string in the stringlist. This action replaces the contents of the stringlist, it does not append the strings to the current content.

See also: `TStrings.LoadFromFile` (380), `TStrings.SaveToFile` (382), `Tstrings.SaveToStream` (382)

### 2.65.25 TStrings.Move

**Synopsis:** Move a string from one place in the list to another.

**Declaration:** `procedure Move(CurIndex: Integer; NewIndex: Integer); Virtual`

**Visibility:** public

**Description:** `Move` moves the string at position `CurIndex` so it has position `NewIndex` after the move operation. The object associated to the string is also moved. `CurIndex` and `NewIndex` should be in the range of 0 to `Count-1`.

**Remark:** `NewIndex` is *not* the position in the stringlist before the move operation starts. The move operation

1. removes the string from position `CurIndex`
2. inserts the string at position `NewIndex`

This may not lead to the desired result if `NewIndex` is bigger than `CurIndex`. Consider the following example:

```
With MyStrings do
begin
  Clear;
  Add('String 0');
  Add('String 1');
  Add('String 2');
  Add('String 3');
  Add('String 4');
  Move(1, 3);
end;
```

After the `Move` operation has completed, 'String 1' will be between 'String 3' and 'String 4'.

**Errors:** If either `CurIndex` or `NewIndex` is outside the allowed range, an `EStringListError` (226) is raised.

See also: `TStrings.Exchange` (378)

### 2.65.26 TStrings.SaveToFile

Synopsis: Save the contents of the list to a file.

Declaration: `procedure SaveToFile(const FileName: String); Virtual`

Visibility: public

Description: `SaveToFile` saves the contents of the stringlist to the file with name `FileName`. It writes the strings to the file, separated by end-of-line markers, so each line in the file will contain 1 string from the stringlist.

`SaveToFile` creates a file stream (300) with name `FileName`, calls `TStrings.SaveToStream` (382) and then destroys the file stream object.

Errors: An `EStreamError` (226) exception can be raised if the file `FileName` cannot be opened, or if it cannot be written to.

See also: `TStrings.SaveToStream` (382), `Tstrings.LoadFromStream` (381), `TStrings.LoadFromFile` (380)

### 2.65.27 TStrings.SaveToStream

Synopsis: Save the contents of the string to a stream.

Declaration: `procedure SaveToStream(Stream: TStream); Virtual`

Visibility: public

Description: `SaveToStream` saves the contents of the stringlist to `Stream`. It writes the strings to the stream, separated by end-of-line markers, so each 'line' in the stream will contain 1 string from the stringlist.

Errors: An `EStreamError` (226) exception can be raised if the stream cannot be written to.

See also: `TStrings.SaveToFile` (382), `Tstrings.LoadFromStream` (381), `TStrings.LoadFromFile` (380)

### 2.65.28 TStrings.SetText

Synopsis: Set the contents of the list from a PChar.

Declaration: `procedure SetText(TheText: PChar); Virtual`

Visibility: public

Description: `SetText` parses the contents of `TheText` and fills the stringlist based on the contents. It regards `TheText` as a series of strings, separated by end-of-line markers. Each of these strings is added to the stringlist.

See also: `TStrings.Text` (388)

### 2.65.29 TStrings.GetNameValue

Synopsis: Return both name and value of a name,value pair based on it's index.

Declaration: `procedure GetNameValue(Index: Integer;out AName: String;  
out AValue: String)`

Visibility: public

Description: Return both name and value of a name,value pair based on it's index.



### 2.65.30 TStrings.ExtractName

Synopsis: Extract the name part of a string

Declaration: `function ExtractName(const S: String) : String`

Visibility: public

Description: `ExtractName` returns the name part (the part before the `NameValueSeparator` (385) character) of the string. If the character is not present, an empty string is returned. The resulting string is not trimmed, it can end or start with spaces.

See also: `TStrings.NameValueSeparator` (385)

### 2.65.31 TStrings.TextLineBreakStyle

Synopsis: Determines which line breaks to use in the `Text` (388) property

Declaration: `Property TextLineBreakStyle : TTextLineBreakStyle`

Visibility: public

Access: Read,Write

Description: `TextLineBreakStyle` determines which linebreak style is used when constructing the `Text` property: the same rules are used as in the writing to text files:

**tlbsLFLines** are separated with a linefeed character #10.

**tlbsCRLFLines** are separated with a carriage-return/linefeed character pair: #13#10.

**tlbsCRLines** are separated with a carriage-return character #13.

It has no effect when setting the text property.

See also: `#rtl.classes.TStrings.Text` (388)

### 2.65.32 TStrings.Delimiter

Synopsis: Delimiter character used in `DelimitedText` (384).

Declaration: `Property Delimiter : Char`

Visibility: public

Access: Read,Write

Description: `Delimiter` is the delimiter character used to separate the different strings in the stringlist when they are read or set through the `DelimitedText` (384) property.

See also: `TStrings.DelimitedText` (384)

### 2.65.33 TStrings.DelimitedText

Synopsis: Get or set all strings in the list in a delimited form.

Declaration: `Property DelimitedText : String`

Visibility: `public`

Access: `Read,Write`

Description: `DelimitedText` returns all strings, properly quoted with `QuoteChar` (384) and separated by the `Delimiter` (383) character.

Strings are quoted if they contain a space or any character with ASCII value less than 32.

The `CommaText` (385) property is a special case of delimited text where the delimiter character is a comma and the quote character is a double quote.

If `StrictDelimiter` (384) is set to `True`, then no quoting is done (The `QuoteChar` property is disregarded completely): the returned text will contain the items in the stringlist, separated by the `Delimiter` character. When writing the `DelimitedText` property, the text will be split at all occurrences of the `Delimiter` character, again disregarding the `QuoteChar` property.

See also: `TStrings.Delimiter` (383), `TStrings.Text` (388), `TStrings.QuoteChar` (384), `TStrings.CommaText` (385)

### 2.65.34 TStrings.StrictDelimiter

Synopsis: Should only the delimiter character be considered a delimiter

Declaration: `Property StrictDelimiter : Boolean`

Visibility: `public`

Access: `Read,Write`

Description: `StrictDelimiter` can be used to indicate that only the delimiter character should be considered a delimiter when setting `DelimitedText` (384): under normal circumstances, quotes and spaces are considered specially (see the `TStrings.CommaText` (385) property for more information). When `StrictDelimiter` is set to `True` then only the `Delimiter` (383) character is considered when splitting the text in items: no quoting whatsoever is performed (or expected) when writing the `DelimitedText` property.

See also: `TStrings.DelimitedText` (384), `TStrings.CommaText` (385), `TStrings.Delimiter` (383)

### 2.65.35 TStrings.QuoteChar

Synopsis: Quote character used in `DelimitedText` (384).

Declaration: `Property QuoteChar : Char`

Visibility: `public`

Access: `Read,Write`

Description: `QuoteChar` is the character used by the `DelimitedText` (384) property to quote strings that have a space or non-printing character in it.

### 2.65.36 TStrings.NameValueSeparator

Synopsis: Value of the character used to separate name,value pairs

Declaration: `Property NameValueSeparator : Char`

Visibility: `public`

Access: `Read,Write`

Description: `NameValueSeparator` is the character used to separate name,value pair. By default, this is the equal sign (=), resulting in `Name=Value` pairs.

It can be set to a colon for `Name : Value` pairs.

### 2.65.37 TStrings.ValueFromIndex

Synopsis: Return the value part of a string based on it's index.

Declaration: `Property ValueFromIndex[Index: Integer]: String`

Visibility: `public`

Access: `Read,Write`

Description: `ValueFromIndex` returns the value part of a string based on the string index. The value part are all characters in the string after the `NameValueSeparator` (385) character, or all characters if the `NameValueSeparator` character is not present.

### 2.65.38 TStrings.Capacity

Synopsis: Capacity of the list, i.e. number of strings that the list can currently hold before it tries to expand.

Declaration: `Property Capacity : Integer`

Visibility: `public`

Access: `Read,Write`

Description: `Capacity` is the number of strings that the list can hold before it tries to allocate more memory.

`TStrings` returns `TStrings.Count` (386) when read. Trying to set the capacity has no effect. Descendent classes such as `TStringList` (368) can override this property such that it actually sets the new capacity.

See also: `TStringList` (368), `TStrings.Count` (386)

### 2.65.39 TStrings.CommaText

Synopsis: Contents of the list as a comma-separated string.

Declaration: `Property CommaText : String`

Visibility: `public`

Access: `Read,Write`

Description: `CommaText` represents the stringlist as a single string, consisting of a comma-separated concatenation of the strings in the list. If one of the strings contains spaces, comma's or quotes it will be enclosed by double quotes. Any double quotes in a string will be doubled. For instance the following strings:

```
Comma,string
Quote"string
Space string
NormalSttring
```

is converted to

```
"Comma,string","Quote""String","Space string",NormalString
```

Conversely, when setting the `CommaText` property, the text will be parsed according to the rules outlined above, and the strings will be set accordingly. Note that spaces will in this context be regarded as string separators, unless the string as a whole is contained in double quotes. Spaces that occur next to a delimiter will be ignored. The following string:

```
"Comma,string" , "Quote""String",Space string,, NormalString
```

Will be converted to

```
Comma,String
Quote"String
Space
String

NormalString
```

This is a special case of the `DelimitedText` (194) property where the quote character is always the double quote, and the delimiter is always the colon.

See also: `TStrings.Text` (388), `TStrings.SetText` (382)

## 2.65.40 TStrings.Count

**Synopsis:** Number of strings in the list.

**Declaration:** `Property Count : Integer`

**Visibility:** public

**Access:** Read

**Description:** `Count` is the current number of strings in the list. `TStrings` does not implement this property; descendent classes should override the property read handler to return the correct value.

Strings in the list are always uniquely identified by their `Index`; the index of a string is zero-based, i.e. it's supported range is 0 to `Count-1`. trying to access a string with an index larger than or equal to `Count` will result in an error. Code that iterates over the list in a stringlist should always take into account the zero-based character of the list index.

See also: `TStrings.Strings` (388), `TStrings.Objects` (387), `TStrings.Capacity` (385)

### 2.65.41 TStrings.Names

**Synopsis:** Name parts of the name-value pairs in the list.

**Declaration:** `Property Names[Index: Integer]: String`

**Visibility:** public

**Access:** Read

**Description:** `Names` provides indexed access to the names of the name-value pairs in the list. It returns the name part of the `Index`-th string in the list.

**Remark:** The index is not an index based on the number of name-value pairs in the list. It is the name part of the name-value pair a string `Index` in the list. If the string at position `Index` is not a name-value pair (i.e. does not contain the equal sign (=)), then an empty name is returned.

See also: `TStrings.Values` (387), `TStrings.IndexOfName` (379)

### 2.65.42 TStrings.Objects

**Synopsis:** Indexed access to the objects associated with the strings in the list.

**Declaration:** `Property Objects[Index: Integer]: TObject`

**Visibility:** public

**Access:** Read,Write

**Description:** `Objects` provides indexed access to the objects associated to the strings in the list. `Index` is a zero-based index and must be in the range of 0 to `Count-1`.

Setting the `objects` property will not free the previously associated object, if there was one. The caller is responsible for freeing the object that was previously associated to the string.

`TStrings` does not implement any storage for objects. Reading the `Objects` property will always return `Nil`. Setting the property will have no effect. It is the responsibility of the descendent classes to provide storage for the associated objects.

**Errors:** If an `Index` outside the valid range is specified, an `EStringListError` (226) exception will be raised.

See also: `TStrings.Strings` (388), `TStrings.IndexOfObject` (379), `TStrings.Names` (387), `TStrings.Values` (387)

### 2.65.43 TStrings.Values

**Synopsis:** Value parts of the name-value pairs in the list.

**Declaration:** `Property Values[Name: String]: String`

**Visibility:** public

**Access:** Read,Write

**Description:** `Values` represents the value parts of the name-value pairs in the list.

When reading this property, if there is a name-value pair in the list of strings that has name part `Name`, then the corresponding value is returned. If there is no such pair, an empty string is returned.

When writing this value, first it is checked whether there exists a name-value pair in the list with name `Name`. If such a pair is found, its value part is overwritten with the specified value. If no such pair is found, a new name-value pair is added with the specified `Name` and value.

**Remark:**

1. Names are compared case-insensitively.
2. Any character, including whitespace, up till the first equal (=) sign in a string is considered part of the name.

See also: `TStrings.Names` (387), `TStrings.Strings` (388), `TStrings.Objects` (387)

### 2.65.44 TStrings.Strings

**Synopsis:** Indexed access to the strings in the list.

**Declaration:** `Property Strings[Index: Integer]: String; default`

**Visibility:** public

**Access:** Read, Write

**Description:** `Strings` is the default property of `TStrings`. It provides indexed read-write access to the list of strings. Reading it will return the string at position `Index` in the list. Writing it will set the string at position `Index`.

`Index` is the position of the string in the list. It is zero-based, i.e. valued values range from 0 (the first string in the list) till `Count-1` (the last string in the list). When browsing through the strings in the list, this fact must be taken into account.

To access the objects associated with the strings in the list, use the `TStrings.Objects` (387) property. The name parts of name-value pairs can be accessed with the `TStrings.Names` (387) property, and the values can be set or read through the `TStrings.Values` (387) property.

Searching through the list can be done using the `TStrings.IndexOf` (379) method.

**Errors:** If `Index` is outside the allowed range, an `EStringListError` (226) exception is raised.

See also: `TStrings.Count` (386), `TStrings.Objects` (387), `TStrings.Names` (387), `TStrings.Values` (387), `TStrings.IndexOf` (379)

### 2.65.45 TStrings.Text

**Synopsis:** Contents of the list as one big string.

**Declaration:** `Property Text : String`

**Visibility:** public

**Access:** Read, Write

**Description:** `Text` returns, when read, the contents of the stringlist as one big string consisting of all strings in the list, separated by an end-of-line marker. When this property is set, the string will be cut into smaller strings, based on the positions of end-of-line markers in the string. Any previous content of the stringlist will be lost.

**Remark:** If any of the strings in the list contains an end-of-line marker, then the resulting string will appear to contain more strings than actually present in the list. To avoid this ambiguity, use the `TStrings.CommaText` (385) property instead.

See also: `TStrings.Strings` (388), `TStrings.Count` (386), `TStrings.CommaText` (385)

### 2.65.46 TStrings.StringsAdapter

Synopsis: Not implemented in Free Pascal.

Declaration: `Property StringsAdapter : IStringsAdapter`

Visibility: `public`

Access: Read,Write

Description: Not implemented in Free Pascal.

## 2.66 TStringsEnumerator

### 2.66.1 Description

`TStringsEnumerator` implements the `#rtl.system.IEnumerator` (1406) interface for the `TStrings` (373) class, so the `TStrings` class can be used in a `for ... in` loop. It is returned by the `TStrings.GetEnumerator` (378) method of `TStrings`.

### 2.66.2 Method overview

Page	Property	Description
<a href="#">389</a>	Create	Initialize a new instance of <code>TStringsEnumerator</code>
<a href="#">389</a>	GetCurrent	Return the current pointer in the list
<a href="#">390</a>	MoveNext	Move the position of the enumerator to the next position in the list.

### 2.66.3 Property overview

Page	Property	Access	Description
<a href="#">390</a>	Current	r	Current pointer in the list

### 2.66.4 TStringsEnumerator.Create

Synopsis: Initialize a new instance of `TStringsEnumerator`

Declaration: `constructor Create(AStrings: TStrings)`

Visibility: `public`

Description: `Create` initializes a new instance of `TStringsEnumerator` and keeps a reference to the stringlist `AStrings` that will be enumerated.

See also: `TStrings` (373)

### 2.66.5 TStringsEnumerator.GetCurrent

Synopsis: Return the current pointer in the list

Declaration: `function GetCurrent : String`

Visibility: `public`

Description: `GetCurrent` returns the current string item in the enumerator.

Errors: No checking is done on the validity of the current position.

See also: `TStringsEnumerator.MoveNext` (390), `TStringsItem` (194)

### 2.66.6 TStringsEnumerator.MoveNext

Synopsis: Move the position of the enumerator to the next position in the list.

Declaration: `function MoveNext : Boolean`

Visibility: `public`

Description: `MoveNext` puts the pointer on the next item in the stringlist, and returns `True` if this succeeded, or `False` if the pointer is past the last element in the list.

Errors: Note that if `False` is returned, calling `GetCurrent` will result in an exception.

See also: `TStringsEnumerator.GetCurrent` (389)

### 2.66.7 TStringsEnumerator.Current

Synopsis: Current pointer in the list

Declaration: `Property Current : String`

Visibility: `public`

Access: `Read`

Description: `Current` redefines `GetCurrent` (389) as a property.

See also: `TStringsEnumerator.GetCurrent` (389)

## 2.67 TStringStream

### 2.67.1 Description

`TStringStream` stores its data in an `ansistring`. The contents of this string is available as the `DataString` (392) property. It also introduces some methods to read or write parts of the stringstream's data as a string.

The main purpose of a `TStringStream` is to be able to treat a string as a stream from which can be read.

### 2.67.2 Method overview

Page	Property	Description
<a href="#">391</a>	<code>Create</code>	Creates a new stringstream and sets its initial content.
<a href="#">391</a>	<code>Read</code>	Reads from the stream.
<a href="#">391</a>	<code>ReadString</code>	Reads a string of length <code>Count</code>
<a href="#">391</a>	<code>Seek</code>	Sets the position in the stream.
<a href="#">392</a>	<code>Write</code>	<code>Write</code> overrides the <code>TStream.Write</code> (356) method.
<a href="#">392</a>	<code>WriteString</code>	<code>WriteString</code> writes a string to the stream.

### 2.67.3 Property overview

Page	Property	Access	Description
<a href="#">392</a>	<code>DataString</code>	<code>r</code>	Contains the contents of the stream in string form



### 2.67.4 TStringStream.Create

Synopsis: Creates a new stringstream and sets its initial content.

Declaration: `constructor Create(const AString: String)`

Visibility: public

Description: `Create` creates a new `TStringStream` instance and sets its initial content to `AString`. The position is still 0 but the size of the stream will equal the length of the string.

See also: `TStringStream.DataString` (392)

### 2.67.5 TStringStream.Read

Synopsis: Reads from the stream.

Declaration: `function Read(var Buffer; Count: LongInt) : LongInt; Override`

Visibility: public

Description: `Read` overrides the `Read` (356) from `TStream` (355). It tries to read `Count` bytes into `Buffer`. It returns the number of bytes actually read. The position of the stream is advanced with the number of bytes actually read; When the reading has reached the end of the `DataStream` (392), then the reading stops, i.e. it is not possible to read beyond the end of the `datastring`.

See also: `TStream.Read` (356), `TStringStream.Write` (392), `TStringStream.DataString` (392)

### 2.67.6 TStringStream.ReadString

Synopsis: Reads a string of length `Count`

Declaration: `function ReadString(Count: LongInt) : String`

Visibility: public

Description: `ReadString` reads `Count` bytes from the stream and returns the read bytes as a string. If less than `Count` bytes were available, the string has as many characters as bytes could be read.

The `ReadString` method is a wrapper around the `Read` (391) method. It does not do the same string as the `TStream.ReadAnsiString` (362) method, which first reads a length integer to determine the length of the string to be read.

See also: `TStringStream.Read` (391), `TStream.ReadAnsiString` (362)

### 2.67.7 TStringStream.Seek

Synopsis: Sets the position in the stream.

Declaration: `function Seek(Offset: LongInt; Origin: Word) : LongInt; Override`

Visibility: public

Description: `Seek` implements the abstract `Seek` (356) method.

### 2.67.8 TStringStream.Write

Synopsis: `Write` overrides the `TStream.Write` (356) method.

Declaration: `function Write(const Buffer; Count: LongInt) : LongInt; Override`

Visibility: `public`

Description: `Write` overrides the `TStream.Write` (356) method.

### 2.67.9 TStringStream.WriteString

Synopsis: `WriteString` writes a string to the stream.

Declaration: `procedure WriteString(const AString: String)`

Visibility: `public`

Description: `WriteString` writes a string to the stream.

### 2.67.10 TStringStream.DataString

Synopsis: Contains the contents of the stream in string form

Declaration: `Property DataString : String`

Visibility: `public`

Access: `Read`

Description: Contains the contents of the stream in string form

## 2.68 TTextObjectWriter

### 2.68.1 Description

Not yet implemented.

## 2.69 TThread

### 2.69.1 Description

The `TThread` class encapsulates the native thread support of the operating system. To create a thread, declare a descendent of the `TThread` object and override the `Execute` (392) method. In this method, the `tthread`'s code should be executed. To run a thread, create an instance of the `tthread` descendent, and call its `execute` method.

### 2.69.2 Method overview

Page	Property	Description
<a href="#">393</a>	AfterConstruction	Code to be executed after construction but before execute.
<a href="#">393</a>	Create	Creates a new thread.
<a href="#">393</a>	Destroy	Destroys the thread object.
<a href="#">394</a>	Resume	Resumes the thread's execution.
<a href="#">394</a>	Start	Starts a thread thread that was created in a suspended state.
<a href="#">394</a>	Suspend	Suspends the thread's execution.
<a href="#">394</a>	Terminate	Signals the thread it should terminate.
<a href="#">394</a>	WaitFor	Waits for the thread to terminate and returns the exit status.

### 2.69.3 Property overview

Page	Property	Access	Description
<a href="#">396</a>	FatalException	r	Exception that occurred during thread execution
<a href="#">395</a>	FreeOnTerminate	rw	Indicates whether the thread should free itself when it stops executing.
<a href="#">395</a>	Handle	r	Returns the thread handle.
<a href="#">396</a>	OnTerminate	rw	Event called when the thread terminates.
<a href="#">395</a>	Priority	rw	Returns the thread priority.
<a href="#">395</a>	Suspended	rw	Indicates whether the thread is suspended.
<a href="#">395</a>	ThreadID	r	Returns the thread ID.

### 2.69.4 TThread.Create

Synopsis: Creates a new thread.

Declaration: `constructor Create(CreateSuspended: Boolean; const StackSize: SizeUInt)`

Visibility: `public`

Description: Creates a new thread.

### 2.69.5 TThread.Destroy

Synopsis: Destroys the thread object.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: Destroys the thread object.

### 2.69.6 TThread.AfterConstruction

Synopsis: Code to be executed after construction but before execute.

Declaration: `procedure AfterConstruction; Override`

Visibility: `public`

Description: `AfterConstruction` is overridden in `TThread` but currently does not do anything useful.

### 2.69.7 TThread.Start

Synopsis: Starts a thread thread that was created in a suspended state.

Declaration: `procedure Start`

Visibility: `public`

Description: The effect of this method is currently the same as calling `TThread.Resume` after creating a thread in a suspended state. This method was added for Delphi-compatibility, where it was introduced after `TThread.Suspend` and `TThread.Resume` were deprecated.

See also: `TThread.Create` ([393](#))

### 2.69.8 TThread.Resume

Synopsis: Resumes the thread's execution.

Declaration: `procedure Resume`

Visibility: `public`

Description: Resumes the thread's execution.

See also: `TThread.Start` ([394](#)), `TThread.Suspend` ([394](#))

### 2.69.9 TThread.Suspend

Synopsis: Suspends the thread's execution.

Declaration: `procedure Suspend`

Visibility: `public`

Description: On non-Windows platforms, a thread can only suspend itself. Other threads can wake up a suspended thread by calling `TThread.Resume`.

See also: `TThread.Resume` ([394](#))

### 2.69.10 TThread.Terminate

Synopsis: Signals the thread it should terminate.

Declaration: `procedure Terminate`

Visibility: `public`

Description: Signals the thread it should terminate.

### 2.69.11 TThread.WaitFor

Synopsis: Waits for the thread to terminate and returns the exit status.

Declaration: `function WaitFor : Integer`

Visibility: `public`

Description: Waits for the thread to terminate and returns the exit status.

### 2.69.12 TThread.FreeOnTerminate

Synopsis: Indicates whether the thread should free itself when it stops executing.

Declaration: `Property FreeOnTerminate : Boolean`

Visibility: `public`

Access: `Read,Write`

Description: Indicates whether the thread should free itself when it stops executing.

### 2.69.13 TThread.Handle

Synopsis: Returns the thread handle.

Declaration: `Property Handle : TThreadID`

Visibility: `public`

Access: `Read`

Description: Returns the thread handle.

### 2.69.14 TThread.Priority

Synopsis: Returns the thread priority.

Declaration: `Property Priority : TThreadPriority`

Visibility: `public`

Access: `Read,Write`

Description: Returns the thread priority.

### 2.69.15 TThread.Suspended

Synopsis: Indicates whether the thread is suspended.

Declaration: `Property Suspended : Boolean`

Visibility: `public`

Access: `Read,Write`

Description: Indicates whether the thread is suspended.

### 2.69.16 TThread.ThreadID

Synopsis: Returns the thread ID.

Declaration: `Property ThreadID : TThreadID`

Visibility: `public`

Access: `Read`

Description: Returns the thread ID.

### 2.69.17 TThread.OnTerminate

Synopsis: Event called when the thread terminates.

Declaration: `Property OnTerminate : TNotifyEvent`

Visibility: `public`

Access: `Read, Write`

Description: Event called when the thread terminates.

### 2.69.18 TThread.FatalException

Synopsis: Exception that occurred during thread execution

Declaration: `Property FatalException : TObject`

Visibility: `public`

Access: `Read`

Description: `FatalException` contains the exception that occurred during the thread's execution.

## 2.70 TThreadList

### 2.70.1 Description

`TThreadList` is a thread-safe `TList` (319) implementation. Unlike `TList`, it can be accessed read-write by multiple threads: the list implementation will take care of locking the list when adding or removing items from the list.

### 2.70.2 Method overview

Page	Property	Description
<a href="#">397</a>	<code>Add</code>	Adds an element to the list.
<a href="#">397</a>	<code>Clear</code>	Removes all elements from the list.
<a href="#">396</a>	<code>Create</code>	Creates a new thread-safe list.
<a href="#">397</a>	<code>Destroy</code>	Destroys the list instance.
<a href="#">397</a>	<code>LockList</code>	Locks the list for exclusive access.
<a href="#">398</a>	<code>Remove</code>	Removes an item from the list.
<a href="#">398</a>	<code>UnlockList</code>	Unlocks the list after it was locked.

### 2.70.3 Property overview

Page	Property	Access	Description
<a href="#">398</a>	<code>Duplicates</code>	<code>rw</code>	Describes what to do with duplicates

### 2.70.4 TThreadList.Create

Synopsis: Creates a new thread-safe list.

Declaration: `constructor Create`

Visibility: `public`

**Description:** `Create` instantiates a new `TThreadList` instance. It initializes a critical section and an internal list object.

See also: `TThreadList.Destroy` (397)

### 2.70.5 `TThreadList.Destroy`

**Synopsis:** Destroys the list instance.

**Declaration:** `destructor Destroy; Override`

**Visibility:** `public`

**Description:** `Destroy` finalizes the critical section, clears the internal list object and calls the inherited destructor.

See also: `TThreadList.Create` (396)

### 2.70.6 `TThreadList.Add`

**Synopsis:** Adds an element to the list.

**Declaration:** `procedure Add(Item: Pointer)`

**Visibility:** `public`

**Description:** `Add` attempts to lock the list and adds the pointer `Item` to the list. After the pointer was added, the list is unlocked again.

See also: `TThreadList.LockList` (397), `TThreadList.Clear` (397), `TThreadList.Remove` (398), `TThreadList.UnlockList` (398)

### 2.70.7 `TThreadList.Clear`

**Synopsis:** Removes all elements from the list.

**Declaration:** `procedure Clear`

**Visibility:** `public`

**Description:** `Clear` attempts to lock the list and then clears the list; all items are removed from the list. After the list is cleared, it is again unlocked.

See also: `TThreadList.LockList` (397), `TThreadList.Add` (397), `TThreadList.Remove` (398), `TThreadList.UnlockList` (398)

### 2.70.8 `TThreadList.LockList`

**Synopsis:** Locks the list for exclusive access.

**Declaration:** `function LockList : TList`

**Visibility:** `public`

**Description:** `LockList` locks the list for exclusive access. Locklist uses an internal critical section, so all rules for multiple locking of critical sections apply to locklist/unlocklist as well.

See also: `TThreadList.Clear` (397), `TThreadList.Add` (397), `TThreadList.Remove` (398), `TThreadList.UnlockList` (398)

### 2.70.9 TThreadList.Remove

Synopsis: Removes an item from the list.

Declaration: `procedure Remove (Item: Pointer)`

Visibility: `public`

Description: `Remove` attempts to lock the list and then removes `Item` from the list. After the item is removed, the list is again unlocked.

See also: `TThreadList.LockList` (397), `TThreadList.Add` (397), `TThreadList.Clear` (397), `TThreadList.UnlockList` (398)

### 2.70.10 TThreadList.UnlockList

Synopsis: Unlocks the list after it was locked.

Declaration: `procedure UnlockList`

Visibility: `public`

Description: `UnlockList` unlocks the list when it was locked for exclusive access. `UnlockList` and `LockList` use an internal critical section, so all rules for multiple locking/unlocking of critical sections apply.

See also: `TThreadList.Clear` (397), `TThreadList.Add` (397), `TThreadList.Remove` (398), `TThreadList.LockList` (397)

### 2.70.11 TThreadList.Duplicates

Synopsis: Describes what to do with duplicates

Declaration: `Property Duplicates : TDuplicates`

Visibility: `public`

Access: `Read, Write`

Description: `Duplicates` describes what the threadlist should do when a duplicate pointer is added to the list. It is identical in behaviour to the `Duplicates` (372) property of `TStringList` (368).

See also: `TDuplicates` (199)

## 2.71 TWriter

### 2.71.1 Description

Object to write component data to an arbitrary format.



### 2.71.2 Method overview

Page	Property	Description
<a href="#">399</a>	Create	Creates a new Writer with a stream and bufsize.
<a href="#">400</a>	DefineBinaryProperty	Callback used when defining and streaming custom properties.
<a href="#">400</a>	DefineProperty	Callback used when defining and streaming custom properties.
<a href="#">400</a>	Destroy	Destroys the writer instance.
<a href="#">400</a>	Write	Write raw data to stream
<a href="#">400</a>	WriteBoolean	Write boolean value to the stream.
<a href="#">401</a>	WriteChar	Write a character to the stream.
<a href="#">401</a>	WriteCollection	Write a collection to the stream.
<a href="#">401</a>	WriteComponent	Stream a component to the stream.
<a href="#">402</a>	WriteCurrency	Write a currency value to the stream
<a href="#">402</a>	WriteDate	Write a date to the stream.
<a href="#">401</a>	WriteDescendent	Write a descendent component to the stream.
<a href="#">401</a>	WriteFloat	Write a float to the stream.
<a href="#">402</a>	WriteIdent	Write an identifier to the stream.
<a href="#">402</a>	WriteInteger	Write an integer to the stream.
<a href="#">403</a>	WriteListBegin	Write a start-of-list marker to the stream.
<a href="#">403</a>	WriteListEnd	Write an end-of-list marker to the stream.
<a href="#">403</a>	WriteRootComponent	Write a root component to the stream.
<a href="#">403</a>	WriteSet	Write a set value to the stream
<a href="#">402</a>	WriteSingle	Write a single-type real to the stream.
<a href="#">403</a>	WriteString	Write a string to the stream.
<a href="#">404</a>	WriteUnicodeString	Write a unicode string to the stream.
<a href="#">404</a>	WriteVariant	Write a variant to the stream
<a href="#">401</a>	WriteWideChar	Write widechar to stream
<a href="#">404</a>	WriteWideString	Write a widestring value to the stream

### 2.71.3 Property overview

Page	Property	Access	Description
<a href="#">405</a>	Driver	r	Driver used when writing to the stream.
<a href="#">404</a>	OnFindAncestor	rw	Event occurring when an ancestor component must be found.
<a href="#">405</a>	OnWriteMethodProperty	rw	Handler from writing method properties.
<a href="#">405</a>	OnWriteStringProperty	rw	Event handler for translating strings written to stream.
<a href="#">405</a>	PropertyPath	r	Path to the property that is currently being written
<a href="#">404</a>	RootAncestor	rw	Ancestor of root component.

### 2.71.4 TWriter.Create

Synopsis: Creates a new Writer with a stream and bufsize.

Declaration: `constructor Create(ADriver: TAbstractObjectWriter)`  
`constructor Create(Stream: TStream; BufSize: Integer)`

Visibility: `public`

Description: Creates a new Writer with a stream and bufsize.

### 2.71.5 TWriter.Destroy

Synopsis: Destroys the writer instance.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: Destroys the writer instance.

### 2.71.6 TWriter.DefineProperty

Synopsis: Callback used when defining and streaming custom properties.

Declaration: `procedure DefineProperty(const Name: String; ReadData: TReaderProc;  
AWriteData: TWriterProc; HasData: Boolean)  
; Override`

Visibility: `public`

Description: Callback used when defining and streaming custom properties.

### 2.71.7 TWriter.DefineBinaryProperty

Synopsis: Callback used when defining and streaming custom properties.

Declaration: `procedure DefineBinaryProperty(const Name: String; ReadData: TStreamProc;  
AWriteData: TStreamProc; HasData: Boolean)  
; Override`

Visibility: `public`

Description: Callback used when defining and streaming custom properties.

### 2.71.8 TWriter.Write

Synopsis: Write raw data to stream

Declaration: `procedure Write(const Buffer; Count: LongInt); Virtual`

Visibility: `public`

Description: `Write` is introduced for Delphi compatibility to write raw data to the component stream. This should not be used in new production code as it will totally mess up the streaming.

See also: `TBinaryObjectWriter.Write` ([262](#)), `TAbstractObjectWriter.Write` ([244](#))

### 2.71.9 TWriter.WriteBoolean

Synopsis: Write boolean value to the stream.

Declaration: `procedure WriteBoolean(Value: Boolean)`

Visibility: `public`

Description: Write boolean value to the stream.

### 2.71.10 TWriter.WriteCollection

Synopsis: Write a collection to the stream.

Declaration: `procedure WriteCollection(Value: TCollection)`

Visibility: `public`

Description: Write a collection to the stream.

### 2.71.11 TWriter.WriteComponent

Synopsis: Stream a component to the stream.

Declaration: `procedure WriteComponent(Component: TComponent)`

Visibility: `public`

Description: Stream a component to the stream.

### 2.71.12 TWriter.WriteChar

Synopsis: Write a character to the stream.

Declaration: `procedure WriteChar(Value: Char)`

Visibility: `public`

Description: Write a character to the stream.

### 2.71.13 TWriter.WriteWideChar

Synopsis: Write widechar to stream

Declaration: `procedure WriteWideChar(Value: WideChar)`

Visibility: `public`

Description: `WriteWideChar` writes a widechar to the stream. This actually writes a widestring of length 1.

See also: `TReader.ReadWideChar` ([345](#)), `TWriter.WriteWideString` ([404](#))

### 2.71.14 TWriter.WriteDescendent

Synopsis: Write a descendent component to the stream.

Declaration: `procedure WriteDescendent(ARoot: TComponent; AAncestor: TComponent)`

Visibility: `public`

Description: Write a descendent component to the stream.

### 2.71.15 TWriter.WriteFloat

Synopsis: Write a float to the stream.

Declaration: `procedure WriteFloat(const Value: Extended)`

Visibility: `public`

Description: Write a float to the stream.

### 2.71.16 TWriter.WriteSingle

Synopsis: Write a single-type real to the stream.

Declaration: `procedure WriteSingle(const Value: Single)`

Visibility: `public`

Description: Write a single-type real to the stream.

### 2.71.17 TWriter.WriteDate

Synopsis: Write a date to the stream.

Declaration: `procedure WriteDate(const Value: TDateTime)`

Visibility: `public`

Description: Write a date to the stream.

### 2.71.18 TWriter.WriteCurrency

Synopsis: Write a currency value to the stream

Declaration: `procedure WriteCurrency(const Value: Currency)`

Visibility: `public`

Description: `WriteCurrency` writes a currency typed value to the stream. This method does nothing except call the driver method of the driver being used.

See also: `TReader.ReadCurrency` ([346](#))

### 2.71.19 TWriter.WriteIdent

Synopsis: Write an identifier to the stream.

Declaration: `procedure WriteIdent(const Ident: String)`

Visibility: `public`

Description: Write an identifier to the stream.

### 2.71.20 TWriter.WriteInteger

Synopsis: Write an integer to the stream.

Declaration: `procedure WriteInteger(Value: LongInt); Overload`  
`procedure WriteInteger(Value: Int64); Overload`

Visibility: `public`

Description: Write an integer to the stream.

### 2.71.21 TWriter.WriteSet

Synopsis: Write a set value to the stream

Declaration: `procedure WriteSet (Value: LongInt; SetType: Pointer)`

Visibility: `public`

Description: `WriteSet` writes a set `Value` consisting of elements with type `EnumType`. The set must be encoded as an integer where each element is encoded in a bit of the integer. Thus, at most an enumerated type with 32 elements can be written with this method.

Errors: No checking is performed on the validity of `EnumType`. It is assumed to be a valid `PTypeInfo` pointer.

See also: `TReader.ReadSet` ([347](#))

### 2.71.22 TWriter.WriteListBegin

Synopsis: Write a start-of-list marker to the stream.

Declaration: `procedure WriteListBegin`

Visibility: `public`

Description: Write a start-of-list marker to the stream.

### 2.71.23 TWriter.WriteListEnd

Synopsis: Write an end-of-list marker to the stream.

Declaration: `procedure WriteListEnd`

Visibility: `public`

Description: Write an end-of-list marker to the stream.

### 2.71.24 TWriter.WriteRootComponent

Synopsis: Write a root component to the stream.

Declaration: `procedure WriteRootComponent (ARoot: TComponent)`

Visibility: `public`

Description: Write a root component to the stream.

### 2.71.25 TWriter.WriteString

Synopsis: Write a string to the stream.

Declaration: `procedure WriteString (const Value: String)`

Visibility: `public`

Description: Write a string to the stream.

**2.71.26 TWriter.WriteString**

Synopsis: Write a widestring value to the stream

Declaration: `procedure WriteWideString(const Value: WideString)`

Visibility: public

Description: `WriteWideString` writes a currency typed value to the stream. This method does nothing except call the driver method of the driver being used.

See also: `TReader.ReadWideString` ([348](#))

**2.71.27 TWriter.WriteString**

Synopsis: Write a unicode string to the stream.

Declaration: `procedure WriteUnicodeString(const Value: UnicodeString)`

Visibility: public

Description: `WriteUnicodeString` writes `Value`, a `UnicodeString` string to the stream. It simply passes the string on to the `WriteUnicodeString` method of the writer driver class.

See also: `TBinaryObjectWriter.WriteUnicodeString` ([264](#)), `TReader.ReadUnicodeString` ([348](#))

**2.71.28 TWriter.WriteVariant**

Synopsis: Write a variant to the stream

Declaration: `procedure WriteVariant(const VarValue: Variant)`

Visibility: public

Description: `WriteVariant` writes `Value`, a simple variant, to the stream. It simply passes the string on to the `WriteVariant` method of the writer driver class.

See also: `TBinaryObjectWriter.WriteVariant` ([264](#)), `TReader.ReadVariant` ([348](#))

**2.71.29 TWriter.RootAncestor**

Synopsis: Ancestor of root component.

Declaration: `Property RootAncestor : TComponent`

Visibility: public

Access: Read, Write

Description: Ancestor of root component.

**2.71.30 TWriter.OnFindAncestor**

Synopsis: Event occurring when an ancestor component must be found.

Declaration: `Property OnFindAncestor : TFindAncestorEvent`

Visibility: public

Access: Read, Write

Description: Event occurring when an ancestor component must be found.

**2.71.31 TWriter.OnWriteMethodProperty**

Synopsis: Handler from writing method properties.

Declaration: `Property OnWriteMethodProperty : TWriteMethodPropertyEvent`

Visibility: `public`

Access: `Read, Write`

Description: `OnWriteMethodProperty` can be set by an IDE or some streaming mechanism which handles dummy values for method properties; It can be used to write a real value to the stream which will be interpreted correctly when the stream is read. See `TWriteMethodPropertyEvent` (207) for a description of the arguments.

See also: `TWriteMethodPropertyEvent` (207), `TReader.OnSetMethodProperty` (350)

**2.71.32 TWriter.OnWriteStringProperty**

Synopsis: Event handler for translating strings written to stream.

Declaration: `Property OnWriteStringProperty : TReadWriteStringPropertyEvent`

Visibility: `public`

Access: `Read, Write`

Description: `OnWriteStringProperty` is called whenever a string property is written to the stream. It can be used e.g. by a translation mechanism to translate the strings on the fly, when a form is written. See `TReadWriteStringPropertyEvent` (204) for a description of the various parameters.

See also: `TReader.OnPropertyNotFound` (350), `TReader.OnSetMethodProperty` (350), `TReadWriteStringPropertyEvent` (204)

**2.71.33 TWriter.Driver**

Synopsis: Driver used when writing to the stream.

Declaration: `Property Driver : TAbstractObjectWriter`

Visibility: `public`

Access: `Read`

Description: Driver used when writing to the stream.

**2.71.34 TWriter.PropertyPath**

Synopsis: Path to the property that is currently being written

Declaration: `Property PropertyPath : String`

Visibility: `public`

Access: `Read`

Description: `PropertyPath` is set to the property name of the class currently being written to stream. This is only done when `TPersistent` (338) descendent class properties are written.

## Chapter 3

# Reference for unit 'clocale'

### 3.1 Overview

The `clocale` offers no API by itself: it just initializes the internationalization settings of the `sysutils` (1426) unit with the values provided by the C library found on most Unix or Linux systems that are POSIX compliant.

The `clocale` should simply be included in the `uses` clause of the program, preferably as one of the first units, and the initialization section of the unit will do all the work.

Note that including this unit, links your program to the C library of the system.

It makes no sense to use this unit on a non-posix system: Windows, OS/2 or DOS - therefore it should always be between an `ifdef` statement:

```
program myprogram;

uses
  {$ifdef unix}clocale{$endif},
  classes, sysutils;
```



## Chapter 4

# Reference for unit 'cmem'

### 4.1 Overview

The `cmem` memory manager sets the system units memory manager to a C-based memory manager: all memory management calls are shunted through to the C memory manager, using `Malloc` ([408](#)), `Free` ([407](#)) and `ReAlloc` ([408](#)). For this reason, the `cmem` unit should be the first unit of the uses clause of the program.

The unit also offers the C memory calls directly as external declarations from the C library, but it is recommended to use the normal FPC routines for this.

Obviously, including this unit links your program to the C library.

### 4.2 Constants, types and variables

#### 4.2.1 Constants

`LibName = 'c'`

`LibName` is the name of the library that is actually used. On most systems, this is simply "libc.so".

### 4.3 Procedures and functions

#### 4.3.1 CAlloc

Synopsis: Allocate memory based on item size and count

Declaration: `function CAlloc(unitSize: ptruint; UnitCount: ptruint) : pointer`

Visibility: default

Description: `CAlloc` allocates memory to hold `UnitCount` units of size `UnitSize` each. The memory is one block of memory. It returns a pointer to the newly allocated memory block.

See also: `Malloc` ([408](#)), `Free` ([407](#)), `Realloc` ([408](#))

#### 4.3.2 Free

Synopsis: Free a previously allocated block

**Declaration:** `procedure Free(P: pointer)`

**Visibility:** `default`

**Description:** `Free` returns the memory block pointed to by `P` to the system. After `Free` was called, the pointer `P` is no longer valid.

**See also:** `Malloc` (408), `ReAlloc` (408)

### 4.3.3 Malloc

**Synopsis:** `Malloc` external declaration.

**Declaration:** `function Malloc(Size: ptruint) : Pointer`

**Visibility:** `default`

**Description:** `Malloc` is the external declaration of the C library's `malloc` call. It accepts a size parameter, and returns a pointer to a memory block of the requested size or `Nil` if no more memory could be allocated.

**See also:** `Free` (407), `ReAlloc` (408)

### 4.3.4 ReAlloc

**Synopsis:** `ReAlloc` re-allocates a memory block

**Declaration:** `function ReAlloc(P: Pointer; Size: ptruint) : pointer`

**Visibility:** `default`

**Description:** `ReAlloc` re-allocates a block of memory pointed to by `p`. The new block will have size `Size`, and as much data as was available or as much data as fits is copied from the old to the new location.

**See also:** `Malloc` (408), `Free` (407)

## Chapter 5

# Reference for unit 'Crt'

### 5.1 Overview

This chapter describes the CRT unit for Free Pascal, both under dos linux and Windows. The unit was first written for dos by Florian klaempfl. The unit was ported to linux by Mark May and enhanced by Michael Van Canneyt and Peter Vreman. It works on the linux console, and in xterm and rxvt windows under X-Windows. The functionality for both is the same, except that under linux the use of an early implementation (versions 0.9.1 and earlier of the compiler) the crt unit automatically cleared the screen at program startup.

There are some caveats when using the CRT unit:

- Programs using the CRT unit will *not* be usable when input/output is being redirected on the command-line.
- For similar reasons they are not usable as CGI-scripts for use with a webserver.
- The use of the CRT unit and the graph unit may not always be supported.
- The CRT unit is not thread safe.
- On linux or other unix OSes , executing other programs that expect special terminal behaviour (using one of the special functions in the linux unit) will not work. The terminal is set in RAW mode, which will destroy most terminal emulation settings.

### 5.2 Constants, types and variables

#### 5.2.1 Constants

`Black = 0`

Black color attribute

`Blink = 128`

Blink attribute

`Blue = 1`

**Blue color attribute**

Brown = 6

**Brown color attribute**

BW40 = 0

40 columns black and white screen mode.

BW80 = 2

80 columns black and white screen mode.

C40 = CO40

40 columns color screen mode.

C80 = CO80

80 columns color screen mode.

CO40 = 1

40 columns color screen mode.

CO80 = 3

80 columns color screen mode.

ConsoleMaxX = 1024

ConsoleMaxY = 1024

Cyan = 3

**Cyan color attribute**

DarkGray = 8

**Dark gray color attribute**

Flushing = false

Font8x8 = 256

**Internal ROM font mode**

Green = 2

Green color attribute

LightBlue = 9

Light Blue color attribute

LightCyan = 11

Light cyan color attribute

LightGray = 7

Light gray color attribute

LightGreen = 10

Light green color attribute

LightMagenta = 13

Light magenta color attribute

LightRed = 12

Light red color attribute

Magenta = 5

Magenta color attribute

Mono = 7

Monochrome screen mode (hercules screens)

Red = 4

Red color attribute

ScreenHeight : LongInt = 25

Current screen height.

ScreenWidth : LongInt = 80

Current screen width

White = 15

White color attribute

Yellow = 14

Yellow color attribute

### 5.2.2 Types

```
PConsoleBuf = ^TConsoleBuf
```

```
TCharAttr = packed record
  ch : Char;
  attr : Byte;
end
```

```
TConsoleBuf = Array[0..ConsoleMaxX*ConsoleMaxY-1] of TCharAttr
```

```
tcrtcoord = 1..255
```

`tcrtcoord` is a subrange type for denoting CRT coordinates. It supports coordinates ranging from 1 to 255. Using this type together with range-checking turned on can be used to debug CRT code.

### 5.2.3 Variables

```
CheckBreak : Boolean
```

Check for CTRL-Break keystroke. Not used.

```
CheckEOF : Boolean
```

Check for EOF on standard input. Not used.

```
CheckSnow : Boolean
```

Check snow on CGA screens. Not used.

```
ConsoleBuf : PConsoleBuf
```

```
DirectVideo : Boolean
```

The `DirectVideo` variable controls the writing to the screen. If it is `True`, the the cursor is set via direct port access. If `False`, then the BIOS is used. This is defined under dos only.

```
LastMode : Word = 3
```

The `Lastmode` variable tells you which mode was last selected for the screen. It is defined on DOS only.

```
TextAttr : Byte = $07
```

The `TextAttr` variable controls the attributes with which characters are written to screen.

```
WindMax : Word = $184f
```

The upper byte of `WindMax` contains the Y coordinate while the lower byte contains the X coordinate. The use of this variable is deprecated, use `WindMaxX` and `WindMaxY` instead.

`WindMaxX : DWord`

X coordinate of lower right corner of the defined window

`WindMaxY : DWord`

Y coordinate of lower right corner of the defined window

`WindMin : Word = $0`

The upper byte of `WindMin` contains the Y coordinate while the lower byte contains the X coordinate. The use of this variable is deprecated, use `WindMinX` and `WindMinY` instead.

`WindMinX : DWord`

X coordinate of upper left corner of the defined window

`WindMinY : DWord`

Y coordinate of upper left corner of the defined window

## 5.3 Procedures and functions

### 5.3.1 AssignCrt

Synopsis: Assign file to CRT.

Declaration: `procedure AssignCrt (var F: Text)`

Visibility: default

Description: `AssignCrt` Assigns a file `F` to the console. Everything written to the file `F` goes to the console instead. If the console contains a window, everything is written to the window instead.

Errors: None.

See also: [Window \(424\)](#)

**Listing:** `./crtex/ex1.pp`

---

```
Program Example1;
uses Crt;

{ Program to demonstrate the AssignCrt function. }

var
  F : Text;
begin
  AssignCrt(F);
  Rewrite(F); { Don't forget to open for output! }
  WriteLn(F, 'This is written to the Assigned File');
  Close(F);
end.
```

---

### 5.3.2 ClrEol

Synopsis: Clear from cursor position till end of line.

Declaration: `procedure ClrEol`

Visibility: default

Description: `ClrEol` clears the current line, starting from the cursor position, to the end of the window. The cursor doesn't move

Errors: None.

See also: `DelLine` ([416](#)), `InsLine` ([418](#)), `ClrScr` ([414](#))

**Listing:** `./crtex/ex9.pp`

---

```

Program Example9;
uses Crt;

{ Program to demonstrate the ClrEol function. }
var
  I,J : integer;

begin
  For I:=1 to 15 do
    For J:=1 to 80 do
      begin
        gotoxy(j,i);
        Write(j mod 10);
      end;
  Window(5,5,75,12);
  Write('This line will be cleared from',
    ' here till the right of the window');
  GotoXY(27,WhereY);
  ReadKey;
  ClrEol;
  WriteLn;
end.

```

---

### 5.3.3 ClrScr

Synopsis: Clear current window.

Declaration: `procedure ClrScr`

Visibility: default

Description: `ClrScr` clears the current window (using the current colors), and sets the cursor in the top left corner of the current window.

Errors: None.

See also: `Window` ([424](#))

**Listing:** `./crtex/ex8.pp`



---

```
Program Example8;  
uses Crt;  
  
{ Program to demonstrate the ClrScr function. }  
  
begin  
  WriteLn('Press any key to clear the screen');  
  ReadKey;  
  ClrScr;  
  WriteLn('Have fun with the cleared screen');  
end.
```

---

### 5.3.4 cursorbig

Synopsis: Show big cursor

Declaration: `procedure cursorbig`

Visibility: default

Description: `CursorBig` makes the cursor a big rectangle. Not implemented on unixes.

Errors: None.

See also: `CursorOn` ([415](#)), `CursorOff` ([415](#))

### 5.3.5 cursoroff

Synopsis: Hide cursor

Declaration: `procedure cursoroff`

Visibility: default

Description: `CursorOff` switches the cursor off (i.e. the cursor is no longer visible). Not implemented on unixes.

Errors: None.

See also: `CursorOn` ([415](#)), `CursorBig` ([415](#))

### 5.3.6 cursoron

Synopsis: Display cursor

Declaration: `procedure cursoron`

Visibility: default

Description: `CursorOn` switches the cursor on. Not implemented on unixes.

Errors: None.

See also: `CursorBig` ([415](#)), `CursorOff` ([415](#))

### 5.3.7 Delay

Synopsis: Delay program execution.

Declaration: `procedure Delay (MS: Word)`

Visibility: default

Description: `Delay` waits a specified number of milliseconds. The number of specified seconds is an approximation, and may be off a lot, if system load is high.

Errors: None

See also: `Sound` ([421](#)), `NoSound` ([420](#))

**Listing:** `./crtex/ex15.pp`

---

```

Program Example15;
uses Crt;

{ Program to demonstrate the Delay function. }
var
  i : longint;
begin
  WriteLn( 'Counting Down' );
  for i:=10 downto 1 do
    begin
      WriteLn(i);
      Delay(1000); { Wait one second }
    end;
  WriteLn( 'BOOM!!! ' );
end.

```

---

### 5.3.8 DelLine

Synopsis: Delete line at cursor position.

Declaration: `procedure DelLine`

Visibility: default

Description: `DelLine` removes the current line. Lines following the current line are scrolled 1 line up, and an empty line is inserted at the bottom of the current window. The cursor doesn't move.

Errors: None.

See also: `ClrEol` ([414](#)), `InsLine` ([418](#)), `ClrScr` ([414](#))

**Listing:** `./crtex/ex11.pp`

---

```

Program Example10;
uses Crt;

{ Program to demonstrate the InsLine function. }

begin
  ClrScr;
  WriteLn;
  WriteLn( 'Line 1 ' );

```

---

---

```

WriteLn('Line 2');
WriteLn('Line 2');
WriteLn('Line 3');
WriteLn;
WriteLn('Oops, Line 2 is listed twice,',
        ' let''s delete the line at the cursor postion');
GotoXY(1,3);
ReadKey;
DelLine;
GotoXY(1,10);
end.

```

---

### 5.3.9 GotoXY

Synopsis: Set cursor position on screen.

Declaration: `procedure GotoXY(X: tcrtcoord; Y: tcrtcoord)`

Visibility: default

Description: `GotoXY` positions the cursor at  $(X, Y)$ ,  $X$  in horizontal,  $Y$  in vertical direction relative to the origin of the current window. The origin is located at  $(1, 1)$ , the upper-left corner of the window.

Errors: None.

See also: [WhereX \(423\)](#), [WhereY \(423\)](#), [Window \(424\)](#)

**Listing:** `./crtex/ex6.pp`

---

```

Program Example6;
uses Crt;

{ Program to demonstrate the GotoXY function. }

begin
  ClrScr;
  GotoXY(10,10);
  Write('10,10');
  GotoXY(70,20);
  Write('70,20');
  GotoXY(1,22);
end.

```

---

### 5.3.10 HighVideo

Synopsis: Switch to highlighted text mode

Declaration: `procedure HighVideo`

Visibility: default

Description: `HighVideo` switches the output to highlighted text. (It sets the high intensity bit of the video attribute)

Errors: None.

See also: [TextColor \(422\)](#), [TextBackground \(421\)](#), [LowVideo \(419\)](#), [NormVideo \(419\)](#)

**Listing:** ./crtex/ex14.pp

---

```

Program Example14;
uses Crt;

{ Program to demonstrate the LowVideo, HighVideo, NormVideo functions. }

begin
  LowVideo;
  WriteLn( 'This is written with LowVideo' );
  HighVideo;
  WriteLn( 'This is written with HighVideo' );
  NormVideo;
  WriteLn( 'This is written with NormVideo' );
end.

```

---

### 5.3.11 InsLine

Synopsis: Insert an empty line at cursor position

Declaration: `procedure InsLine`

Visibility: default

Description: `InsLine` inserts an empty line at the current cursor position. Lines following the current line are scrolled 1 line down, causing the last line to disappear from the window. The cursor doesn't move.

Errors: None.

See also: `ClrEol` ([414](#)), `DelLine` ([416](#)), `ClrScr` ([414](#))

**Listing:** ./crtex/ex10.pp

---

```

Program Example10;
uses Crt;

{ Program to demonstrate the InsLine function. }

begin
  ClrScr;
  WriteLn;
  WriteLn( 'Line 1 ' );
  WriteLn( 'Line 3 ' );
  WriteLn;
  WriteLn( 'Oops, forgot Line 2, let's insert at the cursor postion' );
  GotoXY(1,3);
  ReadKey;
  InsLine;
  Write( 'Line 2 ' );
  GotoXY(1,10);
end.

```

---

### 5.3.12 KeyPressed

Synopsis: Check if there is a keypress in the keybuffer

Declaration: `function KeyPressed : Boolean`

Visibility: default

**Description:** `KeyPressed` scans the keyboard buffer and sees if a key has been pressed. If this is the case, `True` is returned. If not, `False` is returned. The `Shift`, `Alt`, `Ctrl` keys are not reported. The key is not removed from the buffer, and can hence still be read after the `KeyPressed` function has been called.

Errors: None.

See also: `ReadKey` ([420](#))

**Listing:** `./crtex/ex2.pp`

---

```
Program Example2;
uses Crt;

{ Program to demonstrate the KeyPressed function. }

begin
  WriteLn('Waiting until a key is pressed');
  repeat
    until KeyPressed;
  { The key is not Read,
    so it should also be outputted at the commandline }
end.
```

---

### 5.3.13 LowVideo

**Synopsis:** Switch to low intensity colors.

**Declaration:** `procedure LowVideo`

Visibility: default

**Description:** `LowVideo` switches the output to non-highlighted text. (It clears the high intensity bit of the video attribute)

For an example, see `HighVideo` ([417](#))

Errors: None.

See also: `TextColor` ([422](#)), `TextBackground` ([421](#)), `HighVideo` ([417](#)), `NormVideo` ([419](#))

### 5.3.14 NormVideo

**Synopsis:** Return to normal (startup) modus

**Declaration:** `procedure NormVideo`

Visibility: default

**Description:** `NormVideo` switches the output to the defaults, read at startup. (The defaults are read from the cursor position at startup)

For an example, see `HighVideo` ([417](#))

Errors: None.

See also: `TextColor` ([422](#)), `TextBackground` ([421](#)), `LowVideo` ([419](#)), `HighVideo` ([417](#))

### 5.3.15 NoSound

Synopsis: Stop system speaker

Declaration: `procedure NoSound`

Visibility: default

Description: `NoSound` stops the speaker sound. This call is not supported on all operating systems.

Errors: None.

See also: `Sound` ([421](#))

**Listing:** `./crtex/ex16.pp`

---

```

Program Example16;
uses Crt;

{ Program to demonstrate the Sound and NoSound function. }

var
  i : longint;
begin
  WriteLn('You will hear some tones from your speaker');
  while (i < 15000) do
    begin
      inc(i, 500);
      Sound(i);
      Delay(100);
    end;
  WriteLn('Quiet now!');
  NoSound; { Stop noise }
end.
```

---

### 5.3.16 ReadKey

Synopsis: Read key from keybuffer

Declaration: `function ReadKey : Char`

Visibility: default

Description: `ReadKey` reads 1 key from the keyboard buffer, and returns this. If an extended or function key has been pressed, then the zero ASCII code is returned. You can then read the scan code of the key with a second `ReadKey` call.

Key mappings under Linux can cause the wrong key to be reported by `ReadKey`, so caution is needed when using `ReadKey`.

Errors: None.

See also: `KeyPressed` ([418](#))

**Listing:** `./crtex/ex3.pp`

---

```

Program Example3;
uses Crt;

{ Program to demonstrate the ReadKey function. }
```

---

---

```

var
  ch : char;
begin
  writeln( 'Press Left/Right , Esc=Quit' );
  repeat
    ch:=ReadKey;
    case ch of
      #0 : begin
        ch:=ReadKey; {Read ScanCode}
        case ch of
          #75 : WriteLn( 'Left' );
          #77 : WriteLn( 'Right' );
        end;
      end;
      #27 : WriteLn( 'ESC' );
    end;
  until ch=#27 {Esc}
end.

```

---

### 5.3.17 Sound

Synopsis: Sound system speaker

Declaration: `procedure Sound(Hz: Word)`

Visibility: default

Description: `Sound` sounds the speaker at a frequency of `hz`. Under Windows, a system sound is played and the frequency parameter is ignored. On other operating systems, this routine may not be implemented.

Errors: None.

See also: `NoSound` ([420](#))

### 5.3.18 TextBackground

Synopsis: Set text background

Declaration: `procedure TextBackground(Color: Byte)`

Visibility: default

Description: `TextBackground` sets the background color to `CL`. `CL` can be one of the predefined color constants.

Errors: None.

See also: `TextColor` ([422](#)), `HighVideo` ([417](#)), `LowVideo` ([419](#)), `NormVideo` ([419](#))

**Listing:** `./crtex/ex13.pp`

---

```

Program Example13;
uses Crt;

```

```

{ Program to demonstrate the TextBackground function. }

```

```

begin

```

---

```

    TextColor(White);
    WriteLn('This is written in with the default background color');
    TextBackground(Green);
    WriteLn('This is written in with a Green background');
    TextBackground(Brown);
    WriteLn('This is written in with a Brown background');
    TextBackground(Black);
    WriteLn('Back with a black background');
end.

```

---

### 5.3.19 TextColor

Synopsis: Set text color

Declaration: `procedure TextColor(Color: Byte)`

Visibility: default

Description: `TextColor` sets the foreground color to CL. CL can be one of the predefined color constants.

Errors: None.

See also: `TextBackground` ([421](#)), `HighVideo` ([417](#)), `LowVideo` ([419](#)), `NormVideo` ([419](#))

**Listing:** `./crtex/ex12.pp`

---

```

Program Example12;
uses Crt;

{ Program to demonstrate the TextColor function. }

begin
    WriteLn('This is written in the default color');
    TextColor(Red);
    WriteLn('This is written in Red');
    TextColor(White);
    WriteLn('This is written in White');
    TextColor(LightBlue);
    WriteLn('This is written in Light Blue');
end.

```

---

### 5.3.20 TextMode

Synopsis: Set screen mode.

Declaration: `procedure TextMode(Mode: Word)`

Visibility: default

Description: `TextMode` sets the textmode of the screen (i.e. the number of lines and columns of the screen). The lower byte is use to set the VGA text mode.

This procedure is only implemented on dos.

Errors: None.

See also: `Window` ([424](#))



### 5.3.21 WhereX

Synopsis: Return X (horizontal) cursor position

Declaration: `function WhereX : tcrtcoord`

Visibility: default

Description: `WhereX` returns the current X-coordinate of the cursor, relative to the current window. The origin is (1, 1), in the upper-left corner of the window.

Errors: None.

See also: `GotoXY` (417), `WhereY` (423), `Window` (424)

**Listing:** `./crtex/ex7.pp`

---

```
Program Example7;  
uses Crt;  
  
{ Program to demonstrate the WhereX and WhereY functions. }  
  
begin  
  WriteLn( 'Cursor postion: X= ', WhereX, ' Y= ', WhereY );  
end.
```

---

### 5.3.22 WhereY

Synopsis: Return Y (vertical) cursor position

Declaration: `function WhereY : tcrtcoord`

Visibility: default

Description: `WhereY` returns the current Y-coordinate of the cursor, relative to the current window. The origin is (1, 1), in the upper-left corner of the window.

Errors: None.

See also: `GotoXY` (417), `WhereX` (423), `Window` (424)

**Listing:** `./crtex/ex7.pp`

---

```
Program Example7;  
uses Crt;  
  
{ Program to demonstrate the WhereX and WhereY functions. }  
  
begin  
  WriteLn( 'Cursor postion: X= ', WhereX, ' Y= ', WhereY );  
end.
```

---

### 5.3.23 Window

Synopsis: Create new window on screen.

Declaration: `procedure Window(X1: Byte;Y1: Byte;X2: Byte;Y2: Byte)`

Visibility: default

Description: `Window` creates a window on the screen, to which output will be sent.  $(X1, Y1)$  are the coordinates of the upper left corner of the window,  $(X2, Y2)$  are the coordinates of the bottom right corner of the window. These coordinates are relative to the entire screen, with the top left corner equal to  $(1, 1)$ . Further coordinate operations, except for the next `Window` call, are relative to the window's top left corner.

Errors: None.

See also: `GotoXY` ([417](#)), `WhereX` ([423](#)), `WhereY` ([423](#)), `ClrScr` ([414](#))

**Listing:** `./crtex/ex5.pp`

---

```

Program Example5;
uses Crt;

{ Program to demonstrate the Window function. }

begin
  ClrScr;
  WriteLn('Creating a window from 30,10 to 50,20');
  Window(30,10,50,20);
  WriteLn('We are now writing in this small window we just created, we '+
    'can''t get outside it when writing long lines like this one');
  Write('Press any key to clear the window');
  ReadKey;
  ClrScr;
  Write('The window is cleared, press any key to restore to fullscreen');
  ReadKey;
  { Full Screen is 80x25 }
  Window(1,1,80,25);
  Clrscr;
  WriteLn('Back in Full Screen');
end.

```

---

## Chapter 6

# Reference for unit 'cthreads'

### 6.1 Overview

The `CThreads` unit initializes the system unit's thread management routines with an implementation based on the POSIX thread managing routines in the C library. This assures that C libraries that are thread-aware still work if they are linked to by a FPC program.

It doesn't offer any API by itself: the initialization section of the unit just initializes the `ThreadManager` record in the `System` ([1209](#)) unit. This is done using the `SetCThreadManager` ([425](#)) call

The `cthreads` unit simply needs to be included in the `uses` clause of the program, preferably the very first unit, and the initialization section of the unit will do all the work.

Note that including this unit links your program to the C library of the system.

It makes no sense to use this unit on a non-posix system: Windows, OS/2 or DOS, therefor it should always be between an `ifdef` statement:

```
program myprogram;

uses
  {$ifdef unix}cthreads{$endif},
  classes, sysutils;
```

The Lazarus IDE inserts this conditional automatically for each new started program.

### 6.2 Procedures and functions

#### 6.2.1 SetCThreadManager

**Synopsis:** Sets the thread manager to the C thread manager

**Declaration:** `procedure SetCThreadManager`

**Visibility:** `default`

**Description:** `SetCThreadManager` actually sets the thread manager to the C thread manager. It can be called to re-set the thread manager if the thread manager was set to some other thread manager during the life-time of the program.

## Chapter 7

# Reference for unit 'ctypes'

### 7.1 Used units

Table 7.1: Used units by unit 'ctypes'

Name	Page
unixtype	<a href="#">1679</a>

### 7.2 Overview

The `ctypes` unit contains the definitions of commonly found C types. It can be used when interfaces to C libraries need to be defined. The types here are correct on all platforms, 32 or 64 bit.

The main advantage of using this file is to make sure that all C header import units use the same definitions for basic C types.

The `h2pas` program can include the `ctypes` unit automatically in the units it generates. The `-C` command-line switch can be used for this.

### 7.3 Constants, types and variables

#### 7.3.1 Types

`cbool = UnixType.cbool`

C boolean (longbool)

`cchar = UnixType.cchar`

C character type (No signedness specification, 8 bit integer)

`cdouble = UnixType.cdouble`

Double precision floating point type (double)

`cfloat = UnixType.cfloat`

Single precision floating point type (single)

`cint = UnixType.cint`

C integer (commonly 32 bit)

`cint16 = UnixType.cint16`

16-bit signed integer.

`cint32 = UnixType.cint32`

32-bit signed integer (commonly: int)

`cint64 = UnixType.cint64`

64-bit integer

`cint8 = UnixType.cint8`

8-bit signed integer

`clong = UnixType.clong`

long integer (32/64 bit, depending on CPU register size)

`clongdouble = packed Array[0..15] of Byte`

Long precision floating point type (extended/double, depending on CPU)

`clonglong = UnixType.clonglong`

Long (64-bit) integer

`coff_t = UnixType.TOff`

Generic type to indicate offset

`cschar = UnixType.cschar`

C signed character type (8 bit signed integer)

`cshort = UnixType.cshort`

Short integer (16 bit)

`csigned = UnixType.csigned`

Signed integer (commonly 32 bit)

`csint = UnixType.csint`

Signed integer (commonly 32 bit)

`csize_t = UnixType.size_t`

Generic type to contain a size of all kinds of structures

`cslong = UnixType.cslong`

Signed long integer (32/64 bit, depending on CPU register size)

`cslonglong = UnixType.cslonglong`

Signed long (64-bit) integer

`csshort = UnixType.csshort`

Short signed integer (16 bit)

`cuchar = UnixType.cuchar`

C unsigned character type (8 bit unsigned integer).

`cuint = UnixType.cuint`

Unsigned integer (commonly 32 bit)

`cuint16 = UnixType.cuint16`

16-bit unsigned integer.

`cuint32 = UnixType.cuint32`

32-bit unsigned integer

`cuint64 = UnixType.cuint64`

Unsigned 64-bit integer

`cuint8 = UnixType.cuint8`

8-bit unsigned integer

`culong = UnixType.culong`

Unsigned long integer (32/64 bit, depending on CPU register size)

`culonglong = UnixType.culonglong`

Unsigned long (64-bit) integer

`cunsigned = UnixType.cunsigned`

Unsigned integer (commonly 32 bit)

`cushort = UnixType.cushort`

Short unsigned integer (16 bit)

`pcbool = UnixType.pcbbool`

Pointer to `cbool` (426) type.

`pcchar = UnixType.pcchar`

Pointer to `cchar` (426) type.

`pcdouble = UnixType.pcdouble`

Pointer to `cdouble` (426) type.

`pcfloat = UnixType.pcfloating`

Pointer to `cfloat` (427) type.

`pcint = UnixType.pcint`

Pointer to `cint` (427) type.

`pcint16 = UnixType.pcint16`

Pointer to `cint16` (427) type.

`pcint32 = UnixType.pcint32`

Pointer to `cint32` (427) type.

`pcint64 = UnixType.pcint64`

Pointer to `cint64` (427) type.

`pcint8 = UnixType.pcint8`

Pointer to `cint8` (427) type.

`pclong = UnixType.pclong`

Pointer to `clong` (427) type.

`Pclongdouble = ^clongdouble`

Pointer to `clongdouble` (427) type.

`pclonglong = UnixType.pclonglong`

Pointer to `clonglong` (427) type.

`pcschar = UnixType.pcschar`

Pointer to `cschar` (427) type.

`pcshort = UnixType.pcshort`

Pointer to `cshort` (427) type.

`pcsigned = UnixType.pcsigned`

Pointer to `csigned` (427) type.

`pcsint = UnixType.pcsint`

Pointer to `csint` (428) type.

`pcsize_t = UnixType.psize_t`

Pointer to generic size type

`pcslong = UnixType.pcslong`

Pointer to `clong` (428) type.

`pcslonglong = UnixType.pcslonglong`

Pointer to `cslonglong` (428) type.

`pcsshort = UnixType.pcsshort`

Pointer to `csshort` (428) type.

`pcuchar = UnixType.pcuchar`

Pointer to `cuchar` (428) type.

`pcuint = UnixType.pcuint`

Pointer to `cuint` (428) type.

`pcuint16 = UnixType.pcuint16`

Pointer to `cuint16` (428) type.

`pcuint32 = UnixType.pcuint32`

Pointer to `cuint32` (428) type.



```
pcuint64 = UnixType.pcuint64
```

Pointer to `cuint64` (428) type.

```
pcuint8 = UnixType.pcuint8
```

Pointer to `cuint8` (428) type.

```
pculong = UnixType.pculong
```

Pointer to `culong` (428) type.

```
pculonglong = UnixType.pculonglong
```

Pointer to `culonglong` (428) type.

```
pcunsigned = UnixType.punsigned
```

Pointer to `cunsigned` (429) type.

```
pcushort = UnixType.pcushort
```

Pointer to `cushort` (429) type.

## 7.4 Procedures and functions

### 7.4.1 operator `*(clongdouble, Double): Double`

Synopsis: Implement multiplication of `clongdouble` and `double`.

Declaration: 

```
operator operator *(clongdouble, Double): Double(const c: clongdouble;
                                                    const e: Double)
                : Double
```

Visibility: default

Description: This operator allows to multiply a `double` typed value with a `clongdouble` typed value. the result is a `double` typed value.

### 7.4.2 operator `*(Double, clongdouble): Double`

Synopsis: Implement multiplication of `double` and `clongdouble`.

Declaration: 

```
operator operator *(Double, clongdouble): Double(const e: Double;
                                                    const c: clongdouble)
                : Double
```

Visibility: default

Description: This operator allows to multiply a `clongdouble` typed value with a `double` typed value. The result is a `double` typed value.

Errors:

### 7.4.3 operator +(clongdouble, Double): Double

Synopsis:

Declaration: `operator operator +(clongdouble, Double): Double(const c: clongdouble;  
const e: Double)  
: Double`

Visibility: default

Description: This operator allows to add `clongdouble` and `double` typed values. The result is a `double` typed value.

### 7.4.4 operator +(Double, clongdouble): Double

Synopsis: Implement addition of `clongdouble` and `double`.

Declaration: `operator operator +(Double, clongdouble): Double(const e: Double;  
const c: clongdouble)  
: Double`

Visibility: default

Description: This operator allows to add `double` and `clongdouble` typed values. The result is a `double` typed value.

### 7.4.5 operator -(clongdouble, Double): Double

Synopsis: Implement subtraction of `double` and `clongdouble`.

Declaration: `operator operator -(clongdouble, Double): Double(const c: clongdouble;  
const e: Double)  
: Double`

Visibility: default

Description: This operator allows to subtract a `double` typed value from a `clongdouble` typed value. The result is a `double` typed value.

### 7.4.6 operator -(Double, clongdouble): Double

Synopsis: Implement subtraction of `clongdouble` and `double`.

Declaration: `operator operator -(Double, clongdouble): Double(const e: Double;  
const c: clongdouble)  
: Double`

Visibility: default

Description: This operator allows to subtract a `clongdouble` typed value from a `double` typed value. The result is a `double` typed value.

**7.4.7 operator /(clongdouble, Double): Double**

Synopsis: Implement division of double and clongdouble.

Declaration: `operator operator /(clongdouble, Double): Double(const c: clongdouble;  
const e: Double)  
: Double`

Visibility: default

Description: This operator allows to divide a clongdouble typed value by a double typed value. the result is a double typed value.

Errors:

**7.4.8 operator /(Double, clongdouble): Double**

Synopsis: Implement division of clongdouble and double.

Declaration: `operator operator /(Double, clongdouble): Double(const e: Double;  
const c: clongdouble)  
: Double`

Visibility: default

Description: This operator allows to divide a double typed value by a clongdouble typed value. the result is a double typed value.

**7.4.9 operator :=(clongdouble): double**

Synopsis: Implement assignment of a clongdouble to a double type.

Declaration: `operator operator :=(clongdouble): double(const v: clongdouble) : double`

Visibility: default

Description: This operator allows to assign a clongdouble to a Double type.

**7.4.10 operator :=(double): clongdouble**

Synopsis: Implement assignment of a double to a clongdouble type.

Declaration: `operator operator :=(double): clongdouble(const v: double) : clongdouble`

Visibility: default

Description: This operator allows to assign a double to a clongdouble type.

**7.4.11 operator <(clongdouble, Double): Boolean**

Synopsis: Implement less than comparison between double and clongdouble.

Declaration: `operator operator <(clongdouble, Double): Boolean(const c: clongdouble;  
const e: Double)  
: Boolean`

Visibility: default

Description: This operator compares the values of a clongdouble typed value and a double typed value, and returns True if the clongdouble value is less than the double value.

**7.4.12 operator <(Double, clongdouble): Boolean**

Synopsis: Implement less than comparison between `clongdouble` and `double`.

Declaration: 

```
operator operator <(Double, clongdouble): Boolean(const e: Double;
                                                    const c: clongdouble)
                                                    : Boolean
```

Visibility: default

Description: This operator compares the values of a `double` typed value and a `clongdouble` typed value, and returns `True` if the `double` value is less than the `clongdouble` value.

**7.4.13 operator <=(clongdouble, Double): Boolean**

Synopsis: Implement greater than or equal comparison between `double` and `clongdouble`.

Declaration: 

```
operator operator <=(clongdouble, Double): Boolean(const c: clongdouble;
                                                    const e: Double)
                                                    : Boolean
```

Visibility: default

Description: This operator compares the values of a `clongdouble` typed value and a `double` typed value, and returns `True` if the `clongdouble` value is less than or equal to the `double` value.

**7.4.14 operator <=(Double, clongdouble): Boolean**

Synopsis: Implement less than or equal comparison between `clongdouble` and `double`.

Declaration: 

```
operator operator <=(Double, clongdouble): Boolean(const e: Double;
                                                    const c: clongdouble)
                                                    : Boolean
```

Visibility: default

Description: This operator compares the values of a `double` typed value and a `clongdouble` typed value, and returns `True` if the `double` value is less than or equal to the `clongdouble` value.

**7.4.15 operator =(clongdouble, Double): Boolean**

Synopsis: Implement equality of `clongdouble` and `double`.

Declaration: 

```
operator operator =(clongdouble, Double): Boolean(const c: clongdouble;
                                                    const e: Double)
                                                    : Boolean
```

Visibility: default

Description: This operator compares the values of a `double` typed value and a `clongdouble` typed value, and returns `True` if the values are equal (only `double` precision is used).

**7.4.16 operator ==(Double, clongdouble): Boolean**

Synopsis: Implement equality of double and clongdouble.

Declaration: `operator operator ==(Double, clongdouble): Boolean(const e: Double;  
const c: clongdouble)  
: Boolean`

Visibility: default

Description: This operator compares the values of a `clongdouble` typed value and a `double` typed value, and returns `True` if the values are equal (only double precision is used).

**7.4.17 operator >(clongdouble, Double): Boolean**

Synopsis: Implement greater than comparison between double and clongdouble.

Declaration: `operator operator >(clongdouble, Double): Boolean(const c: clongdouble;  
const e: Double)  
: Boolean`

Visibility: default

Description: This operator compares the values of a `clongdouble` typed value and a `double` typed value, and returns `True` if the `clongdouble` value is greater than the `double` value.

**7.4.18 operator >(Double, clongdouble): Boolean**

Synopsis: Implement greater than comparison between clongdouble and double.

Declaration: `operator operator >(Double, clongdouble): Boolean(const e: Double;  
const c: clongdouble)  
: Boolean`

Visibility: default

Description: This operator compares the values of a `double` typed value and a `clongdouble` typed value, and returns `True` if the `double` value is greater than the `clongdouble` value.

**7.4.19 operator >=(clongdouble, Double): Boolean**

Synopsis: Implement greater than or equal comparison between double and clongdouble.

Declaration: `operator operator >=(clongdouble, Double): Boolean(const c: clongdouble;  
const e: Double)  
: Boolean`

Visibility: default

Description: This operator compares the values of a `clongdouble` typed value and a `double` typed value, and returns `True` if the `clongdouble` value is greater than or equal to the `double` value.

### 7.4.20 operator >=(Double, clongdouble): Boolean

Synopsis: Implement greater than or equal comparison between `clongdouble` and `double`.

Declaration: 

```
operator operator >=(Double, clongdouble): Boolean(const e: Double;  
                                                    const c: clongdouble)  
                                                    : Boolean
```

Visibility: default

Description: This operator compares the values of a `double` typed value and a `clongdouble` typed value, and returns `True` if the `double` value is greater than or equal to the `clongdouble` value.

## Chapter 8

# Reference for unit 'cwstring'

### 8.1 Overview

The `cstring` unit offers no API by itself: it just initializes the widestring manager record of the system (1209) unit with an implementation that uses collation and conversion routines which are provided by the C library found on most Unix or Linux systems that are POSIX compliant.

The `cstring` should simply be included in the uses clause of the program, preferably as one of the first units, and the initialization section of the unit will do all the work.

Note that including this unit links your program to the C library of the system.

It makes no sense to use this unit on a non-posix system: Windows, OS/2 or DOS, therefor it should always be between an `ifdef` statement:

```
program myprogram;

uses
  {$ifdef unix}cstring, {$endif}
  classes, sysutils;
```

### 8.2 Procedures and functions

#### 8.2.1 SetCWidestringManager

**Synopsis:** Set the Widestring manager of the system unit to the C version

**Declaration:** `procedure SetCWidestringManager`

**Visibility:** `default`

**Description:** `SetCWidestringManager` actually sets the widestring manager record of the system unit. It is called automatically by the initialization section of the unit.

## Chapter 9

# Reference for unit 'dateutils'

### 9.1 Used units

Table 9.1: Used units by unit 'dateutils'

Name	Page
math	<a href="#">736</a>
sysutils	<a href="#">1426</a>
types	<a href="#">1587</a>

### 9.2 Overview

`DateUtils` contains a large number of date/time manipulation routines, all based on the `TDateTime` type. There are routines for date/time math, for comparing dates and times, for composing dates and decomposing dates in their constituent parts.

### 9.3 Constants, types and variables

#### 9.3.1 Constants

`ApproxDaysPerMonth : Double = 30.4375`

Average number of days in a month, measured over a year. Used in `MonthsBetween` ([484](#)).

`ApproxDaysPerYear : Double = 365.25`

Average number of days in a year, measured over 4 years. Used in `YearsBetween` ([525](#)).

`DayFriday = 5`

ISO day number for Friday

`DayMonday = 1`



ISO day number for Monday

DaySaturday = 6

ISO day number for Saturday

DaysPerWeek = 7

Number of days in a week.

DaysPerYear : Array[Boolean] of Word = (365, 366)

Array with number of days in a year. The boolean index indicates whether it is a leap year or not.

DaySunday = 7

ISO day number for Sunday

DayThursday = 4

ISO day number for Thursday

DayTuesday = 2

ISO day number for Tuesday

DayWednesday = 3

ISO day number for Wednesday

MonthsPerYear = 12

Number of months in a year

OneHour = 1/HoursPerDay

One hour as a fraction of a day (suitable for TDateTime)

OneMillisecond = 1/MSecsPerDay

One millisecond as a fraction of a day (suitable for TDateTime)

OneMinute = 1/MinsPerDay

One minute as a fraction of a day (suitable for TDateTime)

OneSecond = 1/SecsPerDay

One second as a fraction of a day (suitable for TDateTime)

RecodeLeaveFieldAsIs = High(Word)

Bitmask deciding what to do with each TDateTime field in recode routines

`WeeksPerFortnight = 2`

Number of weeks in fortnight

`YearsPerCentury = 100`

Number of years in a century

`YearsPerDecade = 10`

Number of years in a decade

`YearsPerMillennium = 1000`

Number of years in a millenium

## 9.4 Procedures and functions

### 9.4.1 CompareDate

Synopsis: Compare 2 dates, disregarding the time of day

Declaration: `function CompareDate(const A: TDateTime;const B: TDateTime)  
: TValueRelationship`

Visibility: default

Description: `CompareDate` compares the date parts of two timestamps A and B and returns the following results:

< 0 if the day part of A is earlier than the day part of B.

0 if A and B are the on same day (times may differ) .

> 0 if the day part of A is later than the day part of B.

See also: `CompareTime` ([442](#)), `CompareDateTime` ([441](#)), `SameDate` ([494](#)), `SameTime` ([496](#)), `SameDateTime` ([495](#))

**Listing:** `./datutex/ex99.pp`

---

**Program** `Example99;`

`{ This program demonstrates the CompareDate function }`

**Uses** `SysUtils , DateUtils ;`

**Const**

`Fmt = 'dddd dd mmm yyyy ' ;`

**Procedure** `Test(D1,D2 : TDateTime);`

**Var**

`Cmp : Integer;`



---

```

Procedure Test(D1,D2 : TDateTime);

Var
  Cmp : Integer;

begin
  Write(FormatDateTime(Fmt,D1), ' is ');
  Cmp:=CompareDateTime(D1,D2);
  If Cmp<0 then
    write('earlier than ')
  else if Cmp>0 then
    Write('later than ')
  else
    Write('equal to ');
  WriteIn(FormatDateTime(Fmt,D2));
end;

Var
  D,N : TDateTime;

Begin
  D:=Today;
  N:=Now;
  Test(D,D);
  Test(N,N);
  Test(D+1,D);
  Test(D-1,D);
  Test(D+OneSecond,D);
  Test(D-OneSecond,D);
  Test(N+OneSecond,N);
  Test(N-OneSecond,N);
End.

```

---

### 9.4.3 CompareTime

**Synopsis:** Compares two times of the day, disregarding the date part.

**Declaration:** `function CompareTime(const A: TDateTime;const B: TDateTime)  
: TValueRelationship`

**Visibility:** default

**Description:** `CompareTime` compares the time parts of two timestamps A and B and returns the following results:

< 0 if the time part of A is earlier than the time part of B.

0 if A and B have the same time part (dates may differ) .

> 0 if the time part of A is later than the time part of B.

See also: `CompareDateTime` (441), `CompareDate` (440), `SameDate` (494), `SameTime` (496), `SameDateTime` (495)

**Listing:** ./datutex/ex100.pp

---

```

Program Example100;

{ This program demonstrates the CompareTime function }

Uses SysUtils, DateUtils;

Const
    Fmt = 'dddd dd mmmm yyyy hh:nn:ss.zzz';

Procedure Test(D1,D2 : TDateTime);

Var
    Cmp : Integer;

begin
    Write(FormatDateTime(Fmt,D1), ' has ');
    Cmp:=CompareDateTime(D1,D2);
    If Cmp<0 then
        write('earlier time than ')
    else if Cmp>0 then
        Write('later time than ')
    else
        Write('equal time with ');
    WriteIn(FormatDateTime(Fmt,D2));
end;

Var
    D,N : TDateTime;

Begin
    D:=Today;
    N:=Now;
    Test(D,D);
    Test(N,N);
    Test(N+1,N);
    Test(N-1,N);
    Test(N+OneSecond,N);
    Test(N-OneSecond,N);
End.

```

---

#### 9.4.4 DateOf

**Synopsis:** Extract the date part from a DateTime indication.

**Declaration:** `function DateOf(const AValue: TDateTime) : TDateTime`

**Visibility:** default

**Description:** DateOf extracts the date part from AValue and returns the result.

Since the TDateTime is actually a double with the date part encoded in the integer part, this operation corresponds to a call to Trunc.

See also: TimeOf ([505](#)), YearOf ([524](#)), MonthOf ([484](#)), DayOf ([445](#)), HourOf ([460](#)), MinuteOf ([480](#)), SecondOf ([497](#)), MilliSecondOf ([476](#))

**Listing:** ./datutex/ex1.pp

---

**Program** Example1;

*{ This program demonstrates the DateOf function }*

**Uses** SysUtils, DateUtils;

**Begin**

    WriteLn( 'Date is: ', DateTimeToStr(DateOf(Now)));

**End.**

---

### 9.4.5 DateTimeToDosDateTime

**Synopsis:** Convert TDateTime format to DOS date/time format

**Declaration:** function DateTimeToDosDateTime(const AValue: TDateTime) : LongInt

**Visibility:** default

**Description:** DateTimeToDosDatetime takes Value, a TDateTime formatted timestamp, and recodes it to a MS-DOS encoded date/time value. This is a longint with the date/time encoded in the bits as:

**0-4**Seconds divided by 2

**5-10**Minutes

**11-15**Hours

**16-20**Day

**21-24**Month

**25-31**Years since 1980

See also: DosDateTimeToDateTime ([453](#))

### 9.4.6 DateTimeToJulianDate

**Synopsis:** Converts a TDateTime value to a Julian date representation

**Declaration:** function DateTimeToJulianDate(const AValue: TDateTime) : Double

**Visibility:** default

**Description:** DateTimeToJulianDate converts the AValue date/time indication to a julian (as opposed to Gregorian) date.

See also: JulianDateToDateTime ([475](#)), TryJulianDateToDateTime ([510](#)), DateTimeToModifiedJulianDate ([445](#)), TryModifiedJulianDateToDateTime ([510](#))

### 9.4.7 DateTimeToMac

**Synopsis:** Convert a TDateTime timestamp to a Mac timestamp

**Declaration:** function DateTimeToMac(const AValue: TDateTime) : Int64

**Visibility:** default

**Description:** DateTimeToMac converts the TDateTime value AValue to a valid Mac timestamp indication and returns the result.

Errors: None.

See also: [UnixTimeStampToMac \(512\)](#), [MacToDateTime \(475\)](#), [MacTimeStampToUnix \(475\)](#)

### 9.4.8 DateTimeToModifiedJulianDate

Synopsis: Convert a `TDateTime` value to a modified Julian date representation

Declaration: `function DateTimeToModifiedJulianDate(const AValue: TDateTime) : Double`

Visibility: default

Description: Not yet implemented.

Errors: Currently, trying to use this function will raise an exception.

See also: [DateTimeToJulianDate \(444\)](#), [JulianDateToDateTime \(475\)](#), [TryJulianDateToDateTime \(510\)](#), [TryModifiedJulianDateToDateTime \(510\)](#)

### 9.4.9 DateTimeToUnix

Synopsis: Convert a `TDateTime` value to Unix epoch time

Declaration: `function DateTimeToUnix(const AValue: TDateTime) : Int64`

Visibility: default

Description: `DateTimeToUnix` converts a `TDateTime` value to a epoch time (i.e. the time elapsed since 1/1/1970).

See also: [UnixToDateTime \(512\)](#)

### 9.4.10 DayOf

Synopsis: Extract the day (of month) part from a `DateTime` value

Declaration: `function DayOf(const AValue: TDateTime) : Word`

Visibility: default

Description: `DayOf` returns the day of the month part of the `AValue` date/time indication. It is a number between 1 and 31.

For an example, see [YearOf \(524\)](#)

See also: [YearOf \(524\)](#), [WeekOf \(512\)](#), [MonthOf \(484\)](#), [HourOf \(460\)](#), [MinuteOf \(480\)](#), [SecondOf \(497\)](#), [MilliSecondOf \(476\)](#)

### 9.4.11 DayOfTheMonth

Synopsis: Extract the day (of month) part of a `DateTime` value

Declaration: `function DayOfTheMonth(const AValue: TDateTime) : Word`

Visibility: default

**Description:** `DayOfTheMonth` returns the number of days that have passed since the start of the month till the moment indicated by `AValue`. This is a one-based number, i.e. the first day of the month will return 1.

For an example, see the `WeekOfTheMonth` (512) function.

See also: `DayOfTheYear` (446), `WeekOfTheMonth` (512), `HourOfTheMonth` (461), `MinuteOfTheMonth` (481), `SecondOfTheMonth` (498), `MilliSecondOfTheMonth` (477)

### 9.4.12 DayOfTheWeek

**Synopsis:** Extracts the day of the week from a `DateTime` value

**Declaration:** `function DayOfTheWeek(const AValue: TDateTime) : Word`

**Visibility:** default

**Description:** `DayOfTheWeek` returns the number of days that have passed since the start of the week till the moment indicated by `AValue`. This is a one-based number, i.e. the first day of the week will return 1.

See also: `DayOfTheYear` (446), `DayOfTheMonth` (445), `HourOfTheWeek` (461), `MinuteOfTheWeek` (481), `SecondOfTheWeek` (498), `MilliSecondOfTheWeek` (478)

**Listing:** `./datutex/ex42.pp`

---

**Program** Example42;

*{ This program demonstrates the WeekOfTheMonth function }*

**Uses** SysUtils, DateUtils;

**Var**

N : TDateTime;

**Begin**

N:=Now;

WriteLn('Day of the Week : ', DayOfTheWeek(N));

WriteLn('Hour of the Week : ', HourOfTheWeek(N));

WriteLn('Minute of the Week : ', MinuteOfTheWeek(N));

WriteLn('Second of the Week : ', SecondOfTheWeek(N));

WriteLn('MilliSecond of the Week : ',  
MilliSecondOfTheWeek(N));

**End.**

---

### 9.4.13 DayOfTheYear

**Synopsis:** Extracts the day of the year from a `TDateTime` value

**Declaration:** `function DayOfTheYear(const AValue: TDateTime) : Word`

**Visibility:** default

**Description:** `DayOfTheYear` returns the number of days that have passed since the start of the year till the moment indicated by `AValue`. This is a one-based number, i.e. January 1 will return 1.

For an example, see the `WeekOfTheYear` (513) function.

See also: `WeekOfTheYear` (513), `HourOfTheYear` (462), `MinuteOfTheYear` (482), `SecondOfTheYear` (499), `MilliSecondOfTheYear` (478)



### 9.4.14 DaysBetween

Synopsis: Number of whole days between two DateTime values.

Declaration: `function DaysBetween(const ANow: TDateTime;const AThen: TDateTime)  
: Integer`

Visibility: default

Description: `DaysBetween` returns the number of whole days between `ANow` and `AThen`. This means the fractional part of a day (hours, minutes, etc.) is dropped.

See also: `YearsBetween` (525), `MonthsBetween` (484), `WeeksBetween` (514), `HoursBetween` (462), `MinutesBetween` (482), `SecondsBetween` (499), `MillisecondsBetween` (478)

**Listing:** `./datutex/ex58.pp`

---

**Program** Example58;

*{ This program demonstrates the DaysBetween function }*

**Uses** SysUtils, DateUtils;

**Procedure** Test(ANow, AThen : TDateTime);

**begin**

  Write( 'Number of days between ' );

  Write( DateTimeToStr(AThen), ' and ', DateTimeToStr(ANow) );

  WriteLn( ' : ', DaysBetween(ANow, AThen) );

**end**;

**Var**

  D1, D2 : TDateTime;

**Begin**

  D1 := Now;

  D2 := Today - 23/24;

  Test(D1, D2);

  D2 := Today - 1;

  Test(D1, D2);

  D2 := Today - 25/24;

  Test(D1, D2);

  D2 := Today - 26/24;

  Test(D1, D2);

  D2 := Today - 5.4;

  Test(D1, D2);

  D2 := Today - 2.5;

  Test(D1, D2);

**End.**

---

### 9.4.15 DaysInAMonth

Synopsis: Number of days in a month of a certain year.

Declaration: `function DaysInAMonth(const AYear: Word;const AMonth: Word) : Word`

Visibility: default

**Description:** `DaysInMonth` returns the number of days in the month `AMonth` in the year `AYear`. The return value takes leap years into account.

See also: [WeeksInAYear \(515\)](#), [WeeksInYear \(515\)](#), [DaysInYear \(449\)](#), [DaysInAYear \(448\)](#), [DaysInMonth \(449\)](#)

**Listing:** `./datutex/ex17.pp`

---

**Program** `Example17;`

*{ This program demonstrates the DaysInAMonth function }*

**Uses** `SysUtils, DateUtils;`

**Var**

`Y,M : Word;`

**Begin**

`For Y:=1992 to 2010 do`

`For M:=1 to 12 do`

`WriteLn(LongMonthNames[m], ' ', Y, ' has ', DaysInAMonth(Y,M), ' days. ');`

**End.**

---

#### 9.4.16 DaysInAYear

**Synopsis:** Number of days in a particular year.

**Declaration:** `function DaysInAYear(const AYear: Word) : Word`

**Visibility:** `default`

**Description:** `DaysInAYear` returns the number of weeks in the year `AYear`. The return value is either 365 or 366.

See also: [WeeksInAYear \(515\)](#), [WeeksInYear \(515\)](#), [DaysInYear \(449\)](#), [DaysInMonth \(449\)](#), [DaysInAMonth \(447\)](#)

**Listing:** `./datutex/ex15.pp`

---

**Program** `Example15;`

*{ This program demonstrates the DaysInAYear function }*

**Uses** `SysUtils, DateUtils;`

**Var**

`Y : Word;`

**Begin**

`For Y:=1992 to 2010 do`

`WriteLn(Y, ' has ', DaysInAYear(Y), ' days. ');`

**End.**

---

### 9.4.17 DaysInMonth

Synopsis: Return the number of days in the month in which a date occurs.

Declaration: `function DaysInMonth(const AValue: TDateTime) : Word`

Visibility: default

Description: `DaysInMonth` returns the number of days in the month in which `AValue` falls. The return value takes leap years into account.

See also: [WeeksInAYear \(515\)](#), [WeeksInYear \(515\)](#), [DaysInYear \(449\)](#), [DaysInAYear \(448\)](#), [DaysInAMonth \(447\)](#)

**Listing:** `./datutex/ex16.pp`

---

**Program** Example16;

*{ This program demonstrates the DaysInMonth function }*

**Uses** SysUtils, DateUtils;

**Var**

Y,M : Word;

**Begin**

For Y:=1992 to 2010 do

For M:=1 to 12 do

WriteLn(LongMonthNames[m], ' ', Y, ' has ', DaysInMonth(EncodeDate(Y,M,1)), ' days.');

**End.**

---

### 9.4.18 DaysInYear

Synopsis: Return the number of days in the year in which a date occurs.

Declaration: `function DaysInYear(const AValue: TDateTime) : Word`

Visibility: default

Description: `daysInYear` returns the number of days in the year part of `AValue`. The return value is either 365 or 366.

See also: [WeeksInAYear \(515\)](#), [WeeksInYear \(515\)](#), [DaysInAYear \(448\)](#), [DaysInMonth \(449\)](#), [DaysInAMonth \(447\)](#)

**Listing:** `./datutex/ex14.pp`

---

**Program** Example14;

*{ This program demonstrates the DaysInYear function }*

**Uses** SysUtils, DateUtils;

**Var**

Y : Word;

**Begin**

For Y:=1992 to 2010 do

WriteLn(Y, ' has ', DaysInYear(EncodeDate(Y,1,1)), ' days.');

**End.**

---

### 9.4.19 DaySpan

**Synopsis:** Calculate the approximate number of days between two `DateTime` values.

**Declaration:** `function DaySpan(const ANow: TDateTime;const AThen: TDateTime) : Double`

**Visibility:** default

**Description:** `DaySpan` returns the number of Days between `ANow` and `AThen`, including any fractional parts of a Day.

See also: `YearSpan` (526), `MonthSpan` (485), `WeekSpan` (516), `HourSpan` (463), `MinuteSpan` (483), `SecondSpan` (500), `MillisecondSpan` (479), `DaysBetween` (447)

**Listing:** `./datutex/ex66.pp`

---

**Program** Example66;

*{ This program demonstrates the DaySpan function }*

**Uses** SysUtils, DateUtils;

**Procedure** Test(ANow, AThen : TDateTime);

**begin**

  Write( 'Number of days between ' );

  Write( `DateTimeToStr`(AThen), ' and ', `DateTimeToStr`(ANow) );

  WriteLn( ' : ', DaySpan(ANow, AThen) );

**end;**

**Var**

  D1, D2 : TDateTime;

**Begin**

  D1 := `Now`;

  D2 := `Today` - 23/24;

  Test(D1, D2);

  D2 := `Today` - 1;

  Test(D1, D2);

  D2 := `Today` - 25/24;

  Test(D1, D2);

  D2 := `Today` - 26/24;

  Test(D1, D2);

  D2 := `Today` - 5.4;

  Test(D1, D2);

  D2 := `Today` - 2.5;

  Test(D1, D2);

**End.**

---

### 9.4.20 DecodeDateDay

**Synopsis:** Decode a `DateTime` value in year and year of day.

**Declaration:** `procedure DecodeDateDay(const AValue: TDateTime;out AYear: Word;  
                                  out ADayOfYear: Word)`

**Visibility:** default

**Description:** `DecodeDateDay` decomposes the date indication in `AValue` and returns the various components in `AYear`, `ADayOfYear`.

See also: `EncodeDateTime` (454), `EncodeDateMonthWeek` (454), `EncodeDateWeek` (455), `EncodeDateDay` (454), `DecodeDateTime` (452), `DecodeDateWeek` (452), `DecodeDateMonthWeek` (451)

**Listing:** `./datutex/ex83.pp`

---

**Program** `Example83`;

*{ This program demonstrates the DecodeDateDay function }*

**Uses** `SysUtils`, `DateUtils`;

**Var**

`Y, DoY` : `Word`;  
`TS` : `TDateTime`;

**Begin**

`DecodeDateDay(Now, Y, DoY)`;  
`TS := EncodeDateDay(Y, DoY)`;  
`WriteLn('Today is : ', DateToStr(TS))`;

**End.**

---

### 9.4.21 DecodeDateMonthWeek

**Synopsis:** Decode a `DateTime` value in a month, week of month and day of week

**Declaration:** `procedure DecodeDateMonthWeek(const AValue: TDateTime; out AYear: Word;  
out AMonth: Word; out AWeekOfMonth: Word;  
out ADayOfWeek: Word)`

**Visibility:** `default`

**Description:** `DecodeDateMonthWeek` decomposes the date indication in `AValue` and returns the various components in `AYear`, `AMonth`, `AWeekOfMonth` and `ADayOfWeek`.

See also: `EncodeDateTime` (454), `EncodeDateMonthWeek` (454), `EncodeDateWeek` (455), `EncodeDateDay` (454), `DecodeDateTime` (452), `DecodeDateWeek` (452), `DecodeDateDay` (450)

**Listing:** `./datutex/ex85.pp`

---

**Program** `Example85`;

*{ This program demonstrates the DecodeDateMonthWeek function }*

**Uses** `SysUtils`, `DateUtils`;

**Var**

`Y, M, WoM, DoW` : `Word`;  
`TS` : `TDateTime`;

**Begin**

`DecodeDateMonthWeek(Now, Y, M, WoM, DoW)`;  
`TS := EncodeDateMonthWeek(Y, M, WoM, DoW)`;  
`WriteLn('Today is : ', DateToStr(TS))`;

**End.**

---

### 9.4.22 DecodeDateTime

Synopsis: Decode a datetime value in a date and time value

Declaration: `procedure DecodeDateTime(const AValue: TDateTime; out AYear: Word;  
out AMonth: Word; out ADay: Word; out AHour: Word;  
out AMinute: Word; out ASecond: Word;  
out AMilliSecond: Word)`

Visibility: default

Description: `DecodeDateTime` decomposes the date/time indication in `AValue` and returns the various components in `AYear`, `AMonth`, `ADay`, `AHour`, `AMinute`, `ASecond`, `AMilliSecond`

See also: `EncodeDateTime` (454), `EncodeDateMonthWeek` (454), `EncodeDateWeek` (455), `EncodeDateDay` (454), `DecodeDateWeek` (452), `DecodeDateDay` (450), `DecodeDateMonthWeek` (451)

**Listing:** `./datutex/ex79.pp`

---

**Program** `Example79`;

*{ This program demonstrates the DecodeDateTime function }*

**Uses** `SysUtils`, `DateUtils`;

**Var**

`Y, Mo, D, H, Mi, S, MS : Word;`  
`TS : TDateTime;`

**Begin**

`DecodeDateTime(Now, Y, Mo, D, H, Mi, S, MS);`  
`TS := EncodeDateTime(Y, Mo, D, H, Mi, S, MS);`  
`WriteLn('Now is : ', DateTimeToStr(TS));`

**End.**

---

### 9.4.23 DecodeDateWeek

Synopsis: Decode a `DateTime` value in a week of year and day of week.

Declaration: `procedure DecodeDateWeek(const AValue: TDateTime; out AYear: Word;  
out AWeekOfYear: Word; out ADayOfWeek: Word)`

Visibility: default

Description: `DecodeDateWeek` decomposes the date indication in `AValue` and returns the various components in `AYear`, `AWeekOfYear`, `ADayOfWeek`.

See also: `EncodeDateTime` (454), `EncodeDateMonthWeek` (454), `EncodeDateWeek` (455), `EncodeDateDay` (454), `DecodeDateTime` (452), `DecodeDateDay` (450), `DecodeDateMonthWeek` (451)

**Listing:** `./datutex/ex81.pp`

---

**Program** `Example81`;

*{ This program demonstrates the DecodeDateWeek function }*

**Uses** `SysUtils`, `DateUtils`;

---

```

Var
  Y,W,Dow : Word;
  TS : TDateTime;

Begin
  DecodeDateWeek(Now,Y,W,Dow);
  TS:=EncodeDateWeek(Y,W,Dow);
  WriteIn('Today is : ',DateToStr(TS));
End.

```

---

#### 9.4.24 DecodeDayOfWeekInMonth

Synopsis: Decode a DateTime value in year, month, day of week parts

Declaration: `procedure DecodeDayOfWeekInMonth(const AValue: TDateTime;`  
   `out AYear: Word;out AMonth: Word;`  
   `out ANthDayOfWeek: Word;`  
   `out ADayOfWeek: Word)`

Visibility: default

Description: `DecodeDayOfWeekInMonth` decodes the date `AValue` in a `AYear`, `AMonth`, `ADayOfWeek` and `ANthDayOfWeek`. (This is the N-th time that this weekday occurs in the month, e.g. the third saturday of the month.)

See also: `NthDayOfWeek` ([486](#)), `EncodeDateMonthWeek` ([454](#)), `#rtl.sysutils.DayOfWeek` ([1474](#)), `EncodeDayOfWeekInMonth` ([455](#)), `TryEncodeDayOfWeekInMonth` ([509](#))

**Listing:** `./datutex/ex105.pp`

---

**Program** `Example105;`

*{ This program demonstrates the DecodeDayOfWeekInMonth function }*

**Uses** `SysUtils, DateUtils;`

```

Var
  Y,M,NDoW,DoW : Word;
  D : TDateTime;
Begin
  DecodeDayOfWeekInMonth(Date,Y,M,NDoW,DoW);
  D:=EncodeDayOfWeekInMonth(Y,M,NDoW,DoW);
  Write(DateToStr(D),' is the ',NDoW,'-th ');
  WriteIn(formatDateTime('dddd',D),' of the month. ');
End.

```

---

#### 9.4.25 DosDateTimeToDateTime

Synopsis: Convert DOS date/time format to TDateTime format

Declaration: `function DosDateTimeToDateTime(AValue: LongInt) : TDateTime`

Visibility: default

Description: `DosDateTimeToDateTime` takes a DOS encoded date/time `AValue` and recodes it as a `TDateTime` value.

The bit encoding of the DOS date/time is explained in the `DateTimeToDosDateTime` ([444](#)) function.

See also: [DateTimeToDosDateTime \(444\)](#)

### 9.4.26 EncodeDateDay

**Synopsis:** Encodes a year and day of year to a `DateTime` value

**Declaration:** `function EncodeDateDay(const AYear: Word;const ADayOfYear: Word)  
: TDateTime`

**Visibility:** default

**Description:** `EncodeDateDay` encodes the values `AYear` and `ADayOfYear` to a date value and returns this value.

For an example, see [DecodeDateDay \(450\)](#).

**Errors:** If any of the arguments is not valid, then an `EConvertError` exception is raised.

See also: [EncodeDateMonthWeek \(454\)](#), [DecodeDateDay \(450\)](#), [EncodeDateTime \(454\)](#), [EncodeDateWeek \(455\)](#), [TryEncodeDateTime \(508\)](#), [TryEncodeDateMonthWeek \(507\)](#), [TryEncodeDateWeek \(509\)](#)

### 9.4.27 EncodeDateMonthWeek

**Synopsis:** Encodes a year, month, week of month and day of week to a `DateTime` value

**Declaration:** `function EncodeDateMonthWeek(const AYear: Word;const AMonth: Word;  
const AWeekOfMonth: Word;  
const ADayOfWeek: Word) : TDateTime`

**Visibility:** default

**Description:** `EncodeDateMonthWeek` encodes the values `AYear`, `AMonth`, `WeekOfMonth`, `ADayOfWeek`, to a date value and returns this value.

For an example, see [DecodeDateMonthWeek \(451\)](#).

**Errors:** If any of the arguments is not valid, then an `EConvertError` exception is raised.

See also: [DecodeDateMonthWeek \(451\)](#), [EncodeDateTime \(454\)](#), [EncodeDateWeek \(455\)](#), [EncodeDateDay \(454\)](#), [TryEncodeDateTime \(508\)](#), [TryEncodeDateWeek \(509\)](#), [TryEncodeDateMonthWeek \(507\)](#), [TryEncodeDateDay \(507\)](#), [NthDayOfWeek \(486\)](#)

### 9.4.28 EncodeDateTime

**Synopsis:** Encodes a `DateTime` value from all its parts

**Declaration:** `function EncodeDateTime(const AYear: Word;const AMonth: Word;  
const ADay: Word;const AHour: Word;  
const AMinute: Word;const ASecond: Word;  
const AMilliSecond: Word) : TDateTime`

**Visibility:** default

**Description:** `EncodeDateTime` encodes the values `AYear`, `AMonth`, `ADay`, `AHour`, `AMinute`, `ASecond` and `AMilliSecond` to a date/time value and returns this value.

For an example, see [DecodeDateTime \(452\)](#).

**Errors:** If any of the arguments is not valid, then an `EConvertError` exception is raised.



See also: [DecodeDateTime \(452\)](#), [EncodeDateMonthWeek \(454\)](#), [EncodeDateWeek \(455\)](#), [EncodeDateDay \(454\)](#), [TryEncodeDateTime \(508\)](#), [TryEncodeDateWeek \(509\)](#), [TryEncodeDateDay \(507\)](#), [TryEncodeDateMonthWeek \(507\)](#)

### 9.4.29 EncodeDateWeek

**Synopsis:** Encode a `TDateTime` value from a year, week and day of week triplet

**Declaration:**

```
function EncodeDateWeek(const AYear: Word;const AWeekOfYear: Word;
                        const ADayOfWeek: Word) : TDateTime
function EncodeDateWeek(const AYear: Word;const AWeekOfYear: Word)
                        : TDateTime
```

**Visibility:** default

**Description:** `EncodeDateWeek` encodes the values `AYear`, `AWeekOfYear` and `ADayOfWeek` to a date value and returns this value.

For an example, see [DecodeDateWeek \(452\)](#).

**Errors:** If any of the arguments is not valid, then an `EConvertError` exception is raised.

See also: [EncodeDateMonthWeek \(454\)](#), [DecodeDateWeek \(452\)](#), [EncodeDateTime \(454\)](#), [EncodeDateDay \(454\)](#), [TryEncodeDateTime \(508\)](#), [TryEncodeDateWeek \(509\)](#), [TryEncodeDateMonthWeek \(507\)](#)

### 9.4.30 EncodeDayOfWeekInMonth

**Synopsis:** Encodes a year, month, week, day of week specification to a `TDateTime` value

**Declaration:**

```
function EncodeDayOfWeekInMonth(const AYear: Word;const AMonth: Word;
                                const ANthDayOfWeek: Word;
                                const ADayOfWeek: Word) : TDateTime
```

**Visibility:** default

**Description:** `EncodeDayOfWeekInMonth` encodes `AYear`, `AMonth`, `ADayOfWeek` and `ANthDayOfWeek` to a valid date stamp and returns the result.

`ANthDayOfWeek` is the N-th time that this weekday occurs in the month, e.g. the third saturday of the month.

For an example, see [DecodeDayOfWeekInMonth \(453\)](#).

**Errors:** If any of the values is not in range, then an `EConvertError` exception will be raised.

See also: [NthDayOfWeek \(486\)](#), [EncodeDateMonthWeek \(454\)](#), [#rtl.sysutils.DayOfWeek \(1474\)](#), [DecodeDayOfWeekInMonth \(453\)](#), [TryEncodeDayOfWeekInMonth \(509\)](#)

### 9.4.31 EndOfADay

**Synopsis:** Calculates a `DateTime` value representing the end of a specified day

**Declaration:**

```
function EndOfADay(const AYear: Word;const AMonth: Word;
                  const ADay: Word) : TDateTime; Overload
function EndOfADay(const AYear: Word;const ADayOfYear: Word) : TDateTime
                  ; Overload
```

**Visibility:** default

**Description:** `EndOfDay` returns a `TDateTime` value with the date/time indication of the last moment (23:59:59.999) of the day given by `AYear`, `AMonth`, `ADay`.

The day may also be indicated with a `AYear`, `ADayOfYear` pair.

See also: `StartOfDay` (503), `StartOfDay` (501), `StartOfTheWeek` (504), `StartOfAWeek` (502), `StartOfAMonth` (502), `StartOfTheMonth` (504), `EndOfTheWeek` (459), `EndOfAWeek` (457), `EndOfTheYear` (460), `EndOfAYear` (457), `EndOfTheMonth` (458), `EndOfAMonth` (456), `EndOfTheDay` (458)

**Listing:** `./datutex/ex39.pp`

---

**Program** `Example39`;

*{ This program demonstrates the EndOfDay function }*

**Uses** `SysUtils`, `DateUtils`;

**Const**

`Fmt = ' "End of the day : "dd mmm yyyy hh:nn:ss ';`

**Var**

`Y,M,D : Word;`

**Begin**

`Y:=YearOf(Today);`

`M:=MonthOf(Today);`

`D:=DayOf(Today);`

`WriteLn(FormatDateTime(Fmt,EndOfDay(Y,M,D)));`

`DecodeDateDay(Today,Y,D);`

`WriteLn(FormatDateTime(Fmt,EndOfDay(Y,D)));`

**End.**

---

### 9.4.32 EndOfAMonth

**Synopsis:** Calculate a datetime value representing the last day of the indicated month

**Declaration:** `function EndOfAMonth(const AYear: Word;const AMonth: Word) : TDateTime`

**Visibility:** `default`

**Description:** `EndOfAMonth` returns a `TDateTime` value with the date of the last day of the month indicated by the `AYear`, `AMonth` pair.

See also: `StartOfTheMonth` (504), `StartOfAMonth` (502), `EndOfTheMonth` (458), `EndOfTheYear` (460), `EndOfAYear` (457), `StartOfAWeek` (502), `StartOfTheWeek` (504)

**Listing:** `./datutex/ex31.pp`

---

**Program** `Example31`;

*{ This program demonstrates the EndOfAMonth function }*

**Uses** `SysUtils`, `DateUtils`;

**Const**

`Fmt = ' "Last day of this month : "dd mmm yyyy ';`

**Var**

`Y,M : Word;`

**Begin**

```
Y:=YearOf(Today);
M:=MonthOf(Today);
WriteIn(FormatDateTime(Fmt,EndOfAMonth(Y,M)));
End.
```

---

### 9.4.33 EndOfAWeek

Synopsis: Return the last moment of day of the week, given a year and a week in the year.

**Declaration:** `function EndOfAWeek(const AYear: Word;const AWeekOfYear: Word;const ADayOfWeek: Word) : TDateTime`  
`function EndOfAWeek(const AYear: Word;const AWeekOfYear: Word): TDateTime`

Visibility: default

**Description:** `EndOfAWeek` returns a `TDateTime` value with the date of the last moment (23:59:59:999) on the indicated day of the week indicated by the `AYear`, `AWeek`, `ADayOfWeek` values.

The default value for `ADayOfWeek` is 7.

See also: `StartOfTheWeek` (504), `EndOfTheWeek` (459), `EndOfAWeek` (457), `StartOfAMonth` (502), `EndOfTheYear` (460), `EndOfAYear` (457), `EndOfTheMonth` (458), `EndOfAMonth` (456)

**Listing:** `./datutex/ex35.pp`

---

**Program** Example35;

*{ This program demonstrates the EndOfAWeek function }*

**Uses** SysUtils, DateUtils;

**Const**

```
Fmt = 'Last day of this week : "dd mmm yyyy hh:nn:ss';
Fmt2 = 'Last-1 day of this week : "dd mmm yyyy hh:nn:ss';
```

**Var**

```
Y,W : Word;
```

**Begin**

```
Y:=YearOf(Today);
W:=WeekOf(Today);
WriteIn(FormatDateTime(Fmt,EndOfAWeek(Y,W)));
WriteIn(FormatDateTime(Fmt2,EndOfAWeek(Y,W,6)));
End.
```

---

### 9.4.34 EndOfAYear

Synopsis: Calculate a `DateTime` value representing the last day of a year

**Declaration:** `function EndOfAYear(const AYear: Word) : TDateTime`

Visibility: default

**Description:** `StartOfYear` returns a `TDateTime` value with the date of the last day of the year `AYear` (December 31).

See also: `StartOfYear` ([505](#)), `EndOfYear` ([460](#)), `EndOfYear` ([457](#)), `EndOfMonth` ([458](#)), `EndOfMonth` ([456](#)), `StartOfWeek` ([502](#)), `StartOfWeek` ([504](#))

**Listing:** `./datutex/ex27.pp`

---

**Program** `Example27`;

*{ This program demonstrates the EndOfYear function }*

**Uses** `SysUtils`, `DateUtils`;

**Const**

`Fmt = 'Last day of this year : "dd mmm yyyy' ;`

**Begin**

`WriteLn (FormatDateTime (Fmt, EndOfYear (YearOf (Today)))) ;`

**End.**

---

### 9.4.35 EndOfDay

**Synopsis:** Calculate a datetime value that represents the end of a given day.

**Declaration:** `function EndOfDay(const AValue: TDateTime) : TDateTime`

**Visibility:** `default`

**Description:** `EndOfDay` extracts the date part of `AValue` and returns a `TDateTime` value with the date/-time indication of the last moment (23:59:59.999) of this day.

See also: `StartOfDay` ([503](#)), `StartOfDay` ([501](#)), `StartOfWeek` ([504](#)), `StartOfWeek` ([502](#)), `StartOfMonth` ([502](#)), `StartOfMonth` ([504](#)), `EndOfWeek` ([459](#)), `EndOfWeek` ([457](#)), `EndOfYear` ([460](#)), `EndOfYear` ([457](#)), `EndOfMonth` ([458](#)), `EndOfMonth` ([456](#)), `EndOfDay` ([455](#))

**Listing:** `./datutex/ex37.pp`

---

**Program** `Example37`;

*{ This program demonstrates the EndOfDay function }*

**Uses** `SysUtils`, `DateUtils`;

**Const**

`Fmt = 'End of the day : "dd mmm yyyy hh:nn:ss' ;`

**Begin**

`WriteLn (FormatDateTime (Fmt, EndOfDay (Today))) ;`

**End.**

---

### 9.4.36 EndOfMonth

**Synopsis:** Calculate a `DateTime` value representing the last day of the month, given a day in that month.

**Declaration:** `function EndOfTheMonth(const AValue: TDateTime) : TDateTime`

**Visibility:** default

**Description:** `EndOfTheMonth` extracts the year and month parts of `AValue` and returns a `TDateTime` value with the date of the first day of that year and month as the `EndOfAMonth` (456) function.

See also: `StartOfAMonth` (502), `StartOfTheMonth` (504), `EndOfAMonth` (456), `EndOfTheYear` (460), `EndOfAYear` (457), `StartOfAWeek` (502), `StartOfTheWeek` (504)

**Listing:** `./datutex/ex29.pp`

---

**Program** Example29;

*{ This program demonstrates the EndOfTheMonth function }*

**Uses** SysUtils, DateUtils;

**Const**

Fmt = ' "last day of this month : "dd mmm yyyy ';

**Begin**

WriteLn (FormatDateTime (Fmt, EndOfTheMonth (Today)));

**End.**

---

### 9.4.37 EndOfTheWeek

**Synopsis:** Calculate a `DateTime` value which represents the end of a week, given a date in that week.

**Declaration:** `function EndOfTheWeek(const AValue: TDateTime) : TDateTime`

**Visibility:** default

**Description:** `EndOfTheWeek` extracts the year and week parts of `AValue` and returns a `TDateTime` value with the date of the last day of that week as the `EndOfAWeek` (457) function.

See also: `StartOfAWeek` (502), `StartOfTheWeek` (504), `EndOfAWeek` (457), `StartOfAMonth` (502), `EndOfTheYear` (460), `EndOfAYear` (457), `EndOfTheMonth` (458), `EndOfAMonth` (456)

**Listing:** `./datutex/ex33.pp`

---

**Program** Example33;

*{ This program demonstrates the EndOfTheWeek function }*

**Uses** SysUtils, DateUtils;

**Const**

Fmt = ' "last day of this week : "dd mmm yyyy ';

**Begin**

WriteLn (FormatDateTime (Fmt, EndOfTheWeek (Today)));

**End.**

---

### 9.4.38 EndOfTheYear

**Synopsis:** Calculate a `DateTime` value representing the last day of a year, given a date in that year.

**Declaration:** `function EndOfTheYear(const AValue: TDateTime) : TDateTime`

**Visibility:** default

**Description:** `EndOfTheYear` extracts the year part of `AValue` and returns a `TDateTime` value with the date of the last day of that year (December 31), as the `EndOfAYear` (457) function.

**See also:** `StartOfAYear` (503), `StartOfTheYear` (505), `EndOfTheMonth` (458), `EndOfAMonth` (456), `StartOfAWeek` (502), `StartOfTheWeek` (504), `EndOfAYear` (457)

**Listing:** `./datutex/ex25.pp`

---

**Program** `Example25`;

*{ This program demonstrates the EndOfTheYear function }*

**Uses** `SysUtils`, `DateUtils`;

**Const**

`Fmt = ' "Last day of this year : "dd mmm yyyy ';`

**Begin**

`WriteLn (FormatDateTime (Fmt, EndOfTheYear (Today) ));`

**End.**

---

### 9.4.39 HourOf

**Synopsis:** Extract the hour part from a `DateTime` value.

**Declaration:** `function HourOf(const AValue: TDateTime) : Word`

**Visibility:** default

**Description:** `HourOf` returns the hour of the day part of the `AValue` date/time indication. It is a number between 0 and 23.

For an example, see `YearOf` (524)

**See also:** `YearOf` (524), `WeekOf` (512), `MonthOf` (484), `DayOf` (445), `MinuteOf` (480), `SecondOf` (497), `MilliSecondOf` (476)

### 9.4.40 HourOfTheDay

**Synopsis:** Calculate the hour of a given `DateTime` value

**Declaration:** `function HourOfTheDay(const AValue: TDateTime) : Word`

**Visibility:** default

**Description:** `HourOfTheDay` returns the number of hours that have passed since the start of the day till the moment indicated by `AValue`. This is a zero-based number, i.e. 00:59:59 will return 0.

**See also:** `HourOfTheYear` (462), `HourOfTheMonth` (461), `HourOfTheWeek` (461), `MinuteOfTheDay` (480), `SecondOfTheDay` (497), `MilliSecondOfTheDay` (476)

**Listing:** ./datutex/ex43.pp

**Program** Example43;

*{ This program demonstrates the HourOfDay function }*

**Uses** SysUtils , DateUtils ;

**Var**

N : TDateTime ;

**Begin**

N:=Now;

WriteLn( 'Hour of the Day : ', HourOfDay(N));

WriteLn( 'Minute of the Day : ', MinuteOfDay(N));

WriteLn( 'Second of the Day : ', SecondOfDay(N));

WriteLn( 'MilliSecond of the Day : ',  
MilliSecondOfDay(N));

**End.**

#### 9.4.41 HourOfTheMonth

**Synopsis:** Calculate the number of hours passed since the start of the month.

**Declaration:** function HourOfTheMonth(const AValue: TDateTime) : Word

**Visibility:** default

**Description:** HourOfTheMonth returns the number of hours that have passed since the start of the month till the moment indicated by AValue. This is a zero-based number, i.e. 00:59:59 on the first day of the month will return 0.

For an example, see the WeekOfTheMonth (512) function.

See also: WeekOfTheMonth (512), DayOfTheMonth (445), MinuteOfTheMonth (481), SecondOfTheMonth (498), MilliSecondOfTheMonth (477)

#### 9.4.42 HourOfTheWeek

**Synopsis:** Calculate the number of hours elapsed since the start of the week.

**Declaration:** function HourOfTheWeek(const AValue: TDateTime) : Word

**Visibility:** default

**Description:** HourOfTheWeek returns the number of hours that have passed since the start of the Week till the moment indicated by AValue. This is a zero-based number, i.e. 00:59:59 on the first day of the week will return 0.

For an example, see the DayOfTheWeek (446) function.

See also: HourOfTheYear (462), HourOfTheMonth (461), HourOfDay (460), DayOfTheWeek (446), MinuteOfTheWeek (481), SecondOfTheWeek (498), MilliSecondOfTheWeek (478)

### 9.4.43 HourOfTheYear

**Synopsis:** Calculate the number of hours passed since the start of the year.

**Declaration:** `function HourOfTheYear(const AValue: TDateTime) : Word`

**Visibility:** default

**Description:** `HourOfTheYear` returns the number of hours that have passed since the start of the year (January 1, 00:00:00) till the moment indicated by `AValue`. This is a zero-based number, i.e. January 1 00:59:59 will return 0.

For an example, see the `WeekOfTheYear` (513) function.

See also: `WeekOfTheYear` (513), `DayOfTheYear` (446), `MinuteOfTheYear` (482), `SecondOfTheYear` (499), `MilliSecondOfTheYear` (478)

### 9.4.44 HoursBetween

**Synopsis:** Calculate the number of whole hours between two `DateTime` values.

**Declaration:** `function HoursBetween(const ANow: TDateTime; const AThen: TDateTime) : Int64`

**Visibility:** default

**Description:** `HoursBetween` returns the number of whole hours between `ANow` and `AThen`. This means the fractional part of an hour (minutes, seconds etc.) is dropped.

See also: `YearsBetween` (525), `MonthsBetween` (484), `WeeksBetween` (514), `DaysBetween` (447), `MinutesBetween` (482), `SecondsBetween` (499), `MillisecondsBetween` (478)

**Listing:** `./datutex/ex59.pp`

---

**Program** Example59;

*{ This program demonstrates the HoursBetween function }*

**Uses** SysUtils, DateUtils;

**Procedure** Test(ANow, AThen : TDateTime);

**begin**

  Write('Number of hours between ');  
  Write(DateTimeToStr(AThen), ' and ', DateTimeToStr(ANow));  
  WriteLn(' : ', HoursBetween(ANow, AThen));  
**end**;

**Var**

  D1, D2 : TDateTime;

**Begin**

  D1:=Now;  
  D2:=D1-(59\*OneMinute);  
  Test(D1, D2);  
  D2:=D1-(61\*OneMinute);  
  Test(D1, D2);  
  D2:=D1-(122\*OneMinute);  
  Test(D1, D2);  
  D2:=D1-(306\*OneMinute);



```

    Test(D1,D2);
    D2:=D1-(5.4*OneHour);
    Test(D1,D2);
    D2:=D1-(2.5*OneHour);
    Test(D1,D2);
End.

```

---

### 9.4.45 HourSpan

**Synopsis:** Calculate the approximate number of hours between two `DateTime` values.

**Declaration:** `function HourSpan(const ANow: TDateTime;const AThen: TDateTime) : Double`

**Visibility:** default

**Description:** `HourSpan` returns the number of Hours between `ANow` and `AThen`, including any fractional parts of a Hour.

See also: `YearSpan` (526), `MonthSpan` (485), `WeekSpan` (516), `DaySpan` (450), `MinuteSpan` (483), `SecondSpan` (500), `MilliSecondSpan` (479), `HoursBetween` (462)

**Listing:** `./datutex/ex67.pp`

---

**Program** Example67;

*{ This program demonstrates the HourSpan function }*

**Uses** SysUtils, DateUtils;

**Procedure** Test(ANow, AThen : TDateTime);

**begin**

```

    Write('Number of hours between ');
    Write(DateTimeToStr(AThen), ' and ', DateTimeToStr(ANow));
    Writeln(' : ', HourSpan(ANow, AThen));
end;

```

**Var**

D1,D2 : TDateTime;

**Begin**

```

    D1:=Now;
    D2:=D1-(59*OneMinute);
    Test(D1,D2);
    D2:=D1-(61*OneMinute);
    Test(D1,D2);
    D2:=D1-(122*OneMinute);
    Test(D1,D2);
    D2:=D1-(306*OneMinute);
    Test(D1,D2);
    D2:=D1-(5.4*OneHour);
    Test(D1,D2);
    D2:=D1-(2.5*OneHour);
    Test(D1,D2);
End.

```

---

### 9.4.46 IncDay

**Synopsis:** Increase a DateTime value with a number of days.

**Declaration:** `function IncDay(const AValue: TDateTime;const ANumberOfDays: Integer)  
: TDateTime  
function IncDay(const AValue: TDateTime) : TDateTime`

**Visibility:** default

**Description:** IncDay adds ANumberOfDays days to AValue and returns the resulting date/time. ANumberOfDays can be positive or negative.

**See also:** IncYear (467), #rtl.sysutils.IncMonth (1520), IncWeek (466), IncHour (464), IncMinute (465), IncSecond (466), IncMilliSecond (465)

**Listing:** ./datutex/ex74.pp

---

**Program** Example74;

*{ This program demonstrates the IncDay function }*

**Uses** SysUtils, DateUtils;

**Begin**

**WriteIn**( 'One Day from today is ', **DateToStr**(IncDay(Today,1)));

**WriteIn**( 'One Day ago from today is ', **DateToStr**(IncDay(Today,-1)));

**End.**

---

### 9.4.47 IncHour

**Synopsis:** Increase a DateTime value with a number of hours.

**Declaration:** `function IncHour(const AValue: TDateTime;const ANumberOfHours: Int64)  
: TDateTime  
function IncHour(const AValue: TDateTime) : TDateTime`

**Visibility:** default

**Description:** IncHour adds ANumberOfHours hours to AValue and returns the resulting date/time. ANumberOfHours can be positive or negative.

**See also:** IncYear (467), #rtl.sysutils.IncMonth (1520), IncWeek (466), IncDay (464), IncMinute (465), IncSecond (466), IncMilliSecond (465)

**Listing:** ./datutex/ex75.pp

---

**Program** Example75

;

*{ This program demonstrates the IncHour function }*

**Uses** SysUtils, DateUtils;

**Begin**

**WriteIn**( 'One Hour from now is ', **DateTimeToStr**(IncHour(**Now**,1)));

**WriteIn**( 'One Hour ago from now is ', **DateTimeToStr**(IncHour(**Now**,-1)));

**End.**

---

### 9.4.48 IncMilliSecond

Synopsis: Increase a DateTime value with a number of milliseconds.

Declaration: `function IncMilliSecond(const AValue: TDateTime;  
const ANumberOfMilliseconds: Int64) : TDateTime  
function IncMilliSecond(const AValue: TDateTime) : TDateTime`

Visibility: default

Description: `IncMilliSecond` adds `ANumberOfMilliseconds` milliseconds to `AValue` and returns the resulting date/time. `ANumberOfMilliseconds` can be positive or negative.

See also: `IncYear` (467), `#rtl.sysutils.IncMonth` (1520), `IncWeek` (466), `IncDay` (464), `IncHour` (464), `IncSecond` (466), `IncMilliSecond` (465)

**Listing:** `./datutex/ex78.pp`

---

**Program** `Example78;`

`{ This program demonstrates the IncMilliSecond function }`

**Uses** `SysUtils, DateUtils;`

**Begin**

`WriteLn('One MilliSecond from now is ', TimeToStr(IncMilliSecond(Now, 1)));  
WriteLn('One MilliSecond ago from now is ', TimeToStr(IncMilliSecond(Now, -1)));  
End.`

---

### 9.4.49 IncMinute

Synopsis: Increase a DateTime value with a number of minutes.

Declaration: `function IncMinute(const AValue: TDateTime;  
const ANumberOfMinutes: Int64) : TDateTime  
function IncMinute(const AValue: TDateTime) : TDateTime`

Visibility: default

Description: `IncMinute` adds `ANumberOfMinutes` minutes to `AValue` and returns the resulting date/time. `ANumberOfMinutes` can be positive or negative.

See also: `IncYear` (467), `#rtl.sysutils.IncMonth` (1520), `IncWeek` (466), `IncDay` (464), `IncHour` (464), `IncSecond` (466), `IncMilliSecond` (465)

**Listing:** `./datutex/ex76.pp`

---

**Program** `Example76;`

`{ This program demonstrates the IncMinute function }`

**Uses** `SysUtils, DateUtils;`

**Begin**

`WriteLn('One Minute from now is ', TimeToStr(IncMinute(Time, 1)));  
WriteLn('One Minute ago from now is ', TimeToStr(IncMinute(Time, -1)));  
End.`

---

### 9.4.50 IncSecond

Synopsis: Increase a DateTime value with a number of seconds.

Declaration: `function IncSecond(const AValue: TDateTime;  
const ANumberOfSeconds: Int64) : TDateTime  
function IncSecond(const AValue: TDateTime) : TDateTime`

Visibility: default

Description: `IncSecond` adds `ANumberOfSeconds` seconds to `AValue` and returns the resulting date/time. `ANumberOfSeconds` can be positive or negative.

See also: `IncYear` (467), `#rtl.sysutils.IncMonth` (1520), `IncWeek` (466), `IncDay` (464), `IncHour` (464), `IncSecond` (466), `IncMilliSecond` (465)

**Listing:** `./datutex/ex77.pp`

---

**Program** `Example77;`

`{ This program demonstrates the IncSecond function }`

**Uses** `SysUtils, DateUtils;`

**Begin**

`WriteLn('One Second from now is ', TimeToStr(IncSecond(Time, 1)));`

`WriteLn('One Second ago from now is ', TimeToStr(IncSecond(Time, -1)));`

**End.**

---

### 9.4.51 IncWeek

Synopsis: Increase a DateTime value with a number of weeks.

Declaration: `function IncWeek(const AValue: TDateTime; const ANumberOfWeeks: Integer)  
: TDateTime  
function IncWeek(const AValue: TDateTime) : TDateTime`

Visibility: default

Description: `IncWeek` adds `ANumberOfWeeks` weeks to `AValue` and returns the resulting date/time. `ANumberOfWeeks` can be positive or negative.

See also: `IncYear` (467), `#rtl.sysutils.IncMonth` (1520), `IncDay` (464), `IncHour` (464), `IncMinute` (465), `IncSecond` (466), `IncMilliSecond` (465)

**Listing:** `./datutex/ex73.pp`

---

**Program** `Example73;`

`{ This program demonstrates the IncWeek function }`

**Uses** `SysUtils, DateUtils;`

**Begin**

`WriteLn('One Week from today is ', DateToStr(IncWeek(Today, 1)));`

`WriteLn('One Week ago from today is ', DateToStr(IncWeek(Today, -1)));`

**End.**

---

### 9.4.52 IncYear

**Synopsis:** Increase a `DateTime` value with a number of years.

**Declaration:** `function IncYear(const AValue: TDateTime; const ANumberOfYears: Integer) : TDateTime`  
`function IncYear(const AValue: TDateTime) : TDateTime`

**Visibility:** default

**Description:** `IncYear` adds `ANumberOfYears` years to `AValue` and returns the resulting date/time. `ANumberOfYears` can be positive or negative.

See also: `#rtl.sysutils.IncMonth` (1520), `IncWeek` (466), `IncDay` (464), `IncHour` (464), `IncMinute` (465), `IncSecond` (466), `IncMilliSecond` (465)

**Listing:** `./datutex/ex71.pp`

---

**Program** `Example71`;

*{ This program demonstrates the IncYear function }*

**Uses** `SysUtils`, `DateUtils`;

**Begin**

`WriteLn('One year from today is ', DateToStr(IncYear(Today, 1)));`

`WriteLn('One year ago from today is ', DateToStr(IncYear(Today, -1)));`

**End.**

---

### 9.4.53 InvalidDateDayError

**Synopsis:** Raise an `EConvertError` exception when a day is not a valid day of a year.

**Declaration:** `procedure InvalidDateDayError(const AYear: Word; const ADayOfYear: Word)`

**Visibility:** default

**Description:** `InvalidDateDayError` raises an `EConvertError` (1572) exception and formats the error message with an appropriate description made up from the parts `AYear` and `ADayOfYear`.

Normally this function should not be needed, the conversion routines call it when they have received invalid arguments.

See also: `InvalidDateWeekError` (468), `InvalidDateTimeError` (468), `InvalidDateMonthWeekError` (467), `InvalidDayOfWeekInMonthError` (469)

### 9.4.54 InvalidDateMonthWeekError

**Synopsis:** Raise an `EConvertError` exception when a `Year, Month, WeekOfMonth, DayOfWeek` is invalid.

**Declaration:** `procedure InvalidDateMonthWeekError(const AYear: Word;`  
`const AMonth: Word;`  
`const AWeekOfMonth: Word;`  
`const ADayOfWeek: Word)`

**Visibility:** default

**Description:** `InvalidDateMonthWeekError` raises an `EConvertError` (1572) exception and formats the error message with an appropriate description made up from the parts `AYear`, `Amonth`, `AWeekOfMonth` and `ADayOfWeek`.

Normally this function should not be needed, the conversion routines call it when they have received invalid arguments.

See also: `InvalidDateWeekError` (468), `InvalidDateTimeError` (468), `InvalidDateDayError` (467), `InvalidDay-Of-WeekInMonthError` (469)

### 9.4.55 InvalidDateTimeError

**Synopsis:** Raise an `EConvertError` about an invalid date-time specification.

**Declaration:**

```
procedure InvalidDateTimeError(const AYear: Word;const AMonth: Word;
                               const ADay: Word;const AHour: Word;
                               const AMinute: Word;const ASecond: Word;
                               const AMilliSecond: Word;
                               const ABaseDate: TDateTime)
procedure InvalidDateTimeError(const AYear: Word;const AMonth: Word;
                               const ADay: Word;const AHour: Word;
                               const AMinute: Word;const ASecond: Word;
                               const AMilliSecond: Word)
```

**Visibility:** default

**Description:** `InvalidDateTimeError` raises an `EConvertError` (1572) exception and formats the error message with an appropriate description made up from the parts `AYear`, `AMonth`, `ADay`, `AHour`, `AMinute`, `ASecond` and `AMilliSecond`.

Normally this function should not be needed, the conversion routines call it when they have received invalid arguments.

See also: `InvalidDateWeekError` (468), `InvalidDateDayError` (467), `InvalidDateMonthWeekError` (467), `InvalidDayOf-WeekInMonthError` (469)

### 9.4.56 InvalidDateWeekError

**Synopsis:** Raise an `EConvertError` with an invalid Year, WeekOfyear and DayOfWeek specification

**Declaration:**

```
procedure InvalidDateWeekError(const AYear: Word;
                               const AWeekOfYear: Word;
                               const ADayOfWeek: Word)
```

**Visibility:** default

**Description:** `InvalidDateWeekError` raises an `EConvertError` (1572) exception and formats the error message with an appropriate description made up from the parts `AYear`, `AWeek`, `ADayOfWeek`

Normally this function should not be needed, the conversion routines call it when they have received invalid arguments.

See also: `InvalidDateTimeError` (468), `InvalidDateDayError` (467), `InvalidDateMonthWeekError` (467), `InvalidDayOf-WeekInMonthError` (469)

### 9.4.57 InvalidDayOfWeekInMonthError

**Synopsis:** Raise an `EConvertError` exception when a `Year,Month,NthDayOfWeek,DayOfWeek` is invalid.

**Declaration:** `procedure InvalidDayOfWeekInMonthError(const AYear: Word;  
const AMonth: Word;  
const ANthDayOfWeek: Word;  
const ADayOfWeek: Word)`

**Visibility:** `default`

**Description:** `InvalidDayOfWeekInMonthError` raises an `EConvertError` (1572) exception and formats the error message with an appropriate description made up from the parts `AYear`, `AMonth`, `ANthDayOfWeek` and `ADayOfWeek`.

Normally this function should not be needed, the conversion routines call it when they have received invalid arguments.

See also: `InvalidDateWeekError` (468), `InvalidDateTimeError` (468), `InvalidDateDayError` (467), `InvalidDate-MonthWeekError` (467)

### 9.4.58 IsInLeapYear

**Synopsis:** Determine whether a date is in a leap year.

**Declaration:** `function IsInLeapYear(const AValue: TDateTime) : Boolean`

**Visibility:** `default`

**Description:** `IsInLeapYear` returns `True` if the year part of `AValue` is leap year, or `False` if not.

See also: `YearOf` (524), `IsPM` (469), `IsToday` (470), `IsSameDay` (470)

**Listing:** `./datutex/ex3.pp`

---

**Program** `Example3;`

*{ This program demonstrates the IsInLeapYear function }*

**Uses** `SysUtils, DateUtils;`

**Begin**

`WriteLn('Current year is leap year: ', IsInLeapYear(Date));`

**End.**

---

### 9.4.59 IsPM

**Synopsis:** Determine whether a time is PM or AM.

**Declaration:** `function IsPM(const AValue: TDateTime) : Boolean`

**Visibility:** `default`

**Description:** `IsPM` returns `True` if the time part of `AValue` is later then 12:00 (PM, or afternoon).

See also: `YearOf` (524), `IsInLeapYear` (469), `IsToday` (470), `IsSameDay` (470)

**Listing:** `./datutex/ex4.pp`

---

```

Program Example4;

{ This program demonstrates the IsPM function }

Uses SysUtils, DateUtils;

Begin
    WriteLn('Current time is PM : ', IsPM(Now));
End.

```

---

### 9.4.60 IsSameDay

Synopsis: Check if two date/time indications are the same day.

Declaration: `function IsSameDay(const AValue: TDateTime; const ABasis: TDateTime) : Boolean`

Visibility: default

Description: `IsSameDay` checks whether `AValue` and `ABasis` have the same date part, and returns `True` if they do, `False` if not.

See also: Today (506), Yesterday (527), Tomorrow (506), IsToday (470)

**Listing:** ./datutex/ex21.pp

---

```

Program Example21;

{ This program demonstrates the IsSameDay function }

Uses SysUtils, DateUtils;

Var
    I : Integer;
    D : TDateTime;

Begin
    For I:=1 to 3 do
        begin
            D:=Today+Random(3)-1;
            Write(FormatDateTime('dd mmm yyyy "is today : "', D));
            WriteLn(IsSameDay(D, Today));
        end;
End.

```

---

### 9.4.61 IsToday

Synopsis: Check whether a given date is today.

Declaration: `function IsToday(const AValue: TDateTime) : Boolean`

Visibility: default

Description: `IsToday` returns `True` if `AValue` is today's date, and `False` otherwise.

See also: Today (506), Yesterday (527), Tomorrow (506), IsSameDay (470)



**Listing:** ./datutex/ex20.pp

---

**Program** Example20;

*{ This program demonstrates the IsToday function }*

**Uses** SysUtils, DateUtils;

**Begin**

```
WriteLn('Today      : ', IsToday(Today));
WriteLn('Tomorrow   : ', IsToday(Tomorrow));
WriteLn('Yesterday  : ', IsToday(Yesterday));
```

**End.**

---

### 9.4.62 IsValidDate

**Synopsis:** Check whether a set of values is a valid date indication.

**Declaration:** function IsValidDate(const AYear: Word; const AMonth: Word;  
const ADay: Word) : Boolean

**Visibility:** default

**Description:** IsValidDate returns True when the values AYear, AMonth, ADay form a valid date indication. If one of the values is not valid (e.g. the day is invalid or does not exist in that particular month), False is returned.

AYear must be in the range 1..9999 to be valid.

See also: IsValidTime ([475](#)), IsValidDateTime ([473](#)), IsValidDateDay ([471](#)), IsValidDateWeek ([474](#)), IsValidDateMonthWeek ([472](#))

**Listing:** ./datutex/ex5.pp

---

**Program** Example5;

*{ This program demonstrates the IsValidDate function }*

**Uses** SysUtils, DateUtils;

**Var**

```
Y,M,D : Word;
```

**Begin**

```
For Y:=2000 to 2004 do
  For M:=1 to 12 do
    For D:=1 to 31 do
      If Not IsValidDate(Y,M,D) then
        WriteLn(D, ' is not a valid day in ', Y, '/', M);
```

**End.**

---

### 9.4.63 IsValidDateDay

**Synopsis:** Check whether a given year/day of year combination is a valid date.

**Declaration:** function IsValidDateDay(const AYear: Word; const ADayOfYear: Word)  
: Boolean

Visibility: default

**Description:** `IsValidDateDay` returns `True` if `AYear` and `ADayOfYear` form a valid date indication, or `False` otherwise.

`AYear` must be in the range 1..9999 to be valid.

The `ADayOfYear` value is checked to see whether it falls within the valid range of dates for `AYear`.

See also: `IsValidDate` (471), `IsValidTime` (475), `IsValidDateTime` (473), `IsValidDateWeek` (474), `IsValidDateMonthWeek` (472)

**Listing:** `./datutex/ex9.pp`

---

**Program** `Example9`;

*{ This program demonstrates the IsValidDateDay function }*

**Uses** `SysUtils`, `DateUtils`;

**Var**

`Y` : `Word`;

**Begin**

**For** `Y:=1996 to 2004 do`

**if** `IsValidDateDay(Y,366) then`

**WriteLn**(`Y, ' is a leap year'`);

**End.**

---

#### 9.4.64 IsValidDateMonthWeek

**Synopsis:** Check whether a given year/month/week/day of the week combination is a valid day

**Declaration:** `function IsValidDateMonthWeek(const AYear: Word;const AMonth: Word;  
const AWeekOfMonth: Word;  
const ADayOfWeek: Word) : Boolean`

Visibility: default

**Description:** `IsValidDateMonthWeek` returns `True` if `AYear`, `AMonth`, `AWeekOfMonth` and `ADayOfWeek` form a valid date indication, or `False` otherwise.

`AYear` must be in the range 1..9999 to be valid.

The `AWeekOfMonth`, `ADayOfWeek` values are checked to see whether the combination falls within the valid range of weeks for the `AYear`, `AMonth` combination.

See also: `IsValidDate` (471), `IsValidTime` (475), `IsValidDateTime` (473), `IsValidDateDay` (471), `IsValidDateWeek` (474)

**Listing:** `./datutex/ex11.pp`

---

**Program** `Example11`;

*{ This program demonstrates the IsValidDateMonthWeek function }*

**Uses** `SysUtils`, `DateUtils`;

**Var**

`Y,W,D` : `Word`;

```

    B : Boolean;

Begin
  For Y:=2000 to 2004 do
    begin
      B:=True;
      For W:=4 to 6 do
        For D:=1 to 7 do
          If B then
            begin
              B:=IsValidDateMonthWeek(Y,12,W,D);
            end
          If Not B then
            if (D=1) then
              Writeln('December ',Y,' has exactly ',W,' weeks. ');
            else
              Writeln('December ',Y,' has ',W,' weeks and ',D-1,' days. ');
            end;
          end;
        end;
      end;
    end;
  End.

```

---

#### 9.4.65 IsValidDateTime

Synopsis: Check whether a set of values is a valid date and time indication.

Declaration: `function IsValidDateTime(const AYear: Word;const AMonth: Word;  
const ADay: Word;const AHour: Word;  
const AMinute: Word;const ASecond: Word;  
const AMilliSecond: Word) : Boolean`

Visibility: default

Description: `IsValidTime` returns `True` when the values `AYear`, `AMonth`, `ADay`, `AHour`, `AMinute`, `ASecond` and `AMilliSecond` form a valid date and time indication. If one of the values is not valid (e.g. the seconds are larger than 60), `False` is returned.

`AYear` must be in the range 1..9999 to be valid.

See also: `IsValidDate` ([471](#)), `IsValidTime` ([475](#)), `IsValidDateDay` ([471](#)), `IsValidDateWeek` ([474](#)), `IsValidDateMonthWeek` ([472](#))

**Listing:** `./datutex/ex7.pp`

---

**Program** Example7;

*{ This program demonstrates the IsValidDateTime function }*

**Uses** SysUtils, DateUtils;

**Var**

```

Y,Mo,D : Word;
H,M,S,MS : Word;
I : Integer;

```

**Begin**

```

  For I:=1 to 10 do
    begin
      Y:=2000+Random(5);
      Mo:=Random(15);

```

```

D:=Random(40);
H:=Random(32);
M:=Random(90);
S:=Random(90);
MS:=Random(1500);
If Not IsValidDateTime(Y,Mo,D,H,M,S,MS) then
  WriteLn(Y,'-',Mo,'-',D,' ',H,':',M,':',S,'.',MS,' is not a valid date/time. ');
end;
End.

```

---

### 9.4.66 IsValidDateWeek

**Synopsis:** Check whether a given year/week/day of the week combination is a valid day.

**Declaration:** function IsValidDateWeek(const AYear: Word;const AWeekOfYear: Word;  
const ADayOfWeek: Word) : Boolean

**Visibility:** default

**Description:** IsValidDateWeek returns True if AYear, AWeekOfYear and ADayOfWeek form a valid date indication, or False otherwise.

AYear must be in the range 1..9999 to be valid.

The ADayOfWeek,ADayOfWeek values are checked to see whether the combination falls within the valid range of weeks for AYear.

See also: IsValidDate (471), IsValidTime (475), IsValidDateTime (473), IsValidDateDay (471), IsValidDate-MonthWeek (472)

**Listing:** ./datutex/ex10.pp

---

**Program** Example10;

*{ This program demonstrates the IsValidDateWeek function }*

**Uses** SysUtils, DateUtils;

**Var**

Y,W,D : Word;  
B : Boolean;

**Begin**

```

For Y:=2000 to 2004 do
  begin
    B:=True;
    For W:=51 to 54 do
      For D:=1 to 7 do
        If B then
          begin
            B:=IsValidDateWeek(Y,W,D);
            If Not B then
              if (D=1) then
                WriteLn(Y,' has exactly ',W,' weeks. ');
              else
                WriteLn(Y,' has ',W,' weeks and ',D-1,' days. ');
            end;
          end;
        end;
      end;
    end;
  end;
end;

```

**End.**

---

### 9.4.67 IsValidTime

Synopsis: Check whether a set of values is a valid time indication.

Declaration: `function IsValidTime(const AHour: Word;const AMinute: Word;  
const ASecond: Word;const AMilliSecond: Word)  
: Boolean`

Visibility: default

Description: Check whether a set of values is a valid time indication.

### 9.4.68 JulianDateToDateTime

Synopsis: Convert a Julian date representation to a TDateTime value.

Declaration: `function JulianDateToDateTime(const AValue: Double) : TDateTime`

Visibility: default

Description: `JulianDateToDateTime` converts the Julian `AValue` date/time indication to a regular `TDateTime` date/time indication.

See also: `DateTimeToJulianDate` ([444](#)), `TryJulianDateToDateTime` ([510](#)), `DateTimeToModifiedJulianDate` ([445](#)), `TryModifiedJulianDateToDateTime` ([510](#))

### 9.4.69 MacTimeStampToUnix

Synopsis: Convert a Mac timestamp to a Unix timestamp

Declaration: `function MacTimeStampToUnix(const AValue: Int64) : Int64`

Visibility: default

Description: `MacTimeStampToUnix` converts the Mac timestamp indication in `AValue` to a unix timestamp indication (epoch time)

Errors: None.

See also: `UnixTimeStampToMac` ([512](#)), `DateTimeToMac` ([444](#)), `MacToDateTime` ([475](#))

### 9.4.70 MacToDateTime

Synopsis: Convert a Mac timestamp to a TDateTime timestamp

Declaration: `function MacToDateTime(const AValue: Int64) : TDateTime`

Visibility: default

Description: `MacToDateTime` converts the Mac timestamp indication in `AValue` to a valid `TDateTime` indication.

Errors: None.

See also: `UnixTimeStampToMac` ([512](#)), `DateTimeToMac` ([444](#)), `MacTimeStampToUnix` ([475](#))

### 9.4.71 MilliSecondOf

Synopsis: Extract the millisecond part from a DateTime value.

Declaration: `function MilliSecondOf(const AValue: TDateTime) : Word`

Visibility: default

Description: `MilliSecondOf` returns the second of the minute part of the `AValue` date/time indication. It is a number between 0 and 999.

For an example, see `YearOf` (524)

See also: `YearOf` (524), `WeekOf` (512), `MonthOf` (484), `DayOf` (445), `HourOf` (460), `MinuteOf` (480), `MilliSecondOf` (476)

### 9.4.72 MilliSecondOfTheDay

Synopsis: Calculate the number of milliseconds elapsed since the start of the day

Declaration: `function MilliSecondOfTheDay(const AValue: TDateTime) : LongWord`

Visibility: default

Description: `MilliSecondOfTheDay` returns the number of milliseconds that have passed since the start of the Day (00:00:00.000) till the moment indicated by `AValue`. This is a zero-based number, i.e. 00:00:00.000 will return 0.

For an example, see the `HourOfTheDay` (460) function.

See also: `MilliSecondOfTheYear` (478), `MilliSecondOfTheMonth` (477), `MilliSecondOfTheWeek` (478), `MilliSecondOfTheHour` (476), `MilliSecondOfTheMinute` (476), `MilliSecondOfTheSecond` (477), `HourOfTheDay` (460), `MinuteOfTheDay` (480), `SecondOfTheDay` (497)

### 9.4.73 MilliSecondOfTheHour

Synopsis: Calculate the number of milliseconds elapsed since the start of the hour

Declaration: `function MilliSecondOfTheHour(const AValue: TDateTime) : LongWord`

Visibility: default

Description: `MilliSecondOfTheHour` returns the number of milliseconds that have passed since the start of the Hour (HH:00:00.000) till the moment indicated by `AValue`. This is a zero-based number, i.e. HH:00:00.000 will return 0.

For an example, see the `MinuteOfTheHour` (480) function.

See also: `MilliSecondOfTheYear` (478), `MilliSecondOfTheMonth` (477), `MilliSecondOfTheWeek` (478), `MilliSecondOfTheDay` (476), `MilliSecondOfTheMinute` (476), `MilliSecondOfTheSecond` (477), `MinuteOfTheHour` (480), `SecondOfTheHour` (497)

### 9.4.74 MilliSecondOfTheMinute

Synopsis: Calculate the number of milliseconds elapsed since the start of the minute

Declaration: `function MilliSecondOfTheMinute(const AValue: TDateTime) : LongWord`

Visibility: default

**Description:** `MilliSecondOfTheMinute` returns the number of milliseconds that have passed since the start of the Minute (HH:MM:00.000) till the moment indicated by `AValue`. This is a zero-based number, i.e. HH:MM:00.000 will return 0.

For an example, see the `SecondOfTheMinute` (498) function.

See also: `MilliSecondOfTheYear` (478), `MilliSecondOfTheMonth` (477), `MilliSecondOfTheWeek` (478), `MilliSecondOfTheDay` (476), `MilliSecondOfTheHour` (476), `MilliSecondOfTheMinute` (476), `MilliSecondOfTheSecond` (477), `SecondOfTheMinute` (498)

### 9.4.75 MilliSecondOfTheMonth

**Synopsis:** Calculate number of milliseconds elapsed since the start of the month.

**Declaration:** `function MilliSecondOfTheMonth(const AValue: TDateTime) : LongWord`

**Visibility:** default

**Description:** `MilliSecondOfTheMonth` returns the number of milliseconds that have passed since the start of the month (00:00:00.000) till the moment indicated by `AValue`. This is a zero-based number, i.e. 00:00:00.000 on the first of the month will return 0.

For an example, see the `WeekOfTheMonth` (512) function.

See also: `WeekOfTheMonth` (512), `DayOfTheMonth` (445), `HourOfTheMonth` (461), `MinuteOfTheMonth` (481), `SecondOfTheMonth` (498), `MilliSecondOfTheMonth` (477)

### 9.4.76 MilliSecondOfTheSecond

**Synopsis:** Calculate the number of milliseconds elapsed since the start of the second

**Declaration:** `function MilliSecondOfTheSecond(const AValue: TDateTime) : Word`

**Visibility:** default

**Description:** `MilliSecondOfTheSecond` returns the number of milliseconds that have passed since the start of the second (HH:MM:SS.000) till the moment indicated by `AValue`. This is a zero-based number, i.e. HH:MM:SS.000 will return 0.

See also: `MilliSecondOfTheYear` (478), `MilliSecondOfTheMonth` (477), `MilliSecondOfTheWeek` (478), `MilliSecondOfTheDay` (476), `MilliSecondOfTheHour` (476), `MilliSecondOfTheMinute` (476), `SecondOfTheMinute` (498)

**Listing:** `./datutex/ex46.pp`

---

**Program** Example46;

*{ This program demonstrates the MilliSecondOfTheSecond function }*

**Uses** SysUtils, DateUtils;

**Var**

N : TDateTime;

**Begin**

N:=Now;

WriteLn('MilliSecond of the Second : ',  
MilliSecondOfTheSecond(N));

**End.**

---

### 9.4.77 MilliSecondOfTheWeek

**Synopsis:** Calculate the number of milliseconds elapsed since the start of the week

**Declaration:** `function MilliSecondOfTheWeek(const AValue: TDateTime) : LongWord`

**Visibility:** default

**Description:** `MilliSecondOfTheWeek` returns the number of milliseconds that have passed since the start of the Week (00:00:00.000) till the moment indicated by `AValue`. This is a zero-based number, i.e. 00:00:00.000 on the first of the Week will return 0.

For an example, see the `DayOfTheWeek` (446) function.

See also: `MilliSecondOfTheYear` (478), `MilliSecondOfTheMonth` (477), `MilliSecondOfTheDay` (476), `MilliSecondOfTheHour` (476), `MilliSecondOfTheMinute` (476), `MilliSecondOfTheSecond` (477), `DayOfTheWeek` (446), `HourOfTheWeek` (461), `MinuteOfTheWeek` (481), `SecondOfTheWeek` (498)

### 9.4.78 MilliSecondOfTheYear

**Synopsis:** Calculate the number of milliseconds elapsed since the start of the year.

**Declaration:** `function MilliSecondOfTheYear(const AValue: TDateTime) : Int64`

**Visibility:** default

**Description:** `MilliSecondOfTheYear` returns the number of milliseconds that have passed since the start of the year (January 1, 00:00:00.000) till the moment indicated by `AValue`. This is a zero-based number, i.e. January 1 00:00:00.000 will return 0.

For an example, see the `WeekOfTheYear` (513) function.

See also: `WeekOfTheYear` (513), `DayOfTheYear` (446), `HourOfTheYear` (462), `MinuteOfTheYear` (482), `SecondOfTheYear` (499), `MilliSecondOfTheYear` (478)

### 9.4.79 MilliSecondsBetween

**Synopsis:** Calculate the number of whole milliseconds between two `DateTime` values.

**Declaration:** `function MilliSecondsBetween(const ANow: TDateTime;  
const AThen: TDateTime) : Int64`

**Visibility:** default

**Description:** `MilliSecondsBetween` returns the number of whole milliseconds between `ANow` and `AThen`. This means a fractional part of a millisecond is dropped.

See also: `YearsBetween` (525), `MonthsBetween` (484), `WeeksBetween` (514), `DaysBetween` (447), `HoursBetween` (462), `MinutesBetween` (482), `SecondsBetween` (499)

**Listing:** `./datutex/ex62.pp`

---

**Program** Example62;

*{ This program demonstrates the MilliSecondsBetween function }*

**Uses** SysUtils, DateUtils;

**Procedure** Test(ANow, AThen : TDateTime);



---

```

begin
  Write( 'Number of milliseconds between ');
  Write( TimeToStr(AThen), ' and ', TimeToStr(ANow));
  WriteLn( ' : ', MilliSecondsBetween(ANow, AThen));
end;

Var
  D1, D2 : TDateTime;

Begin
  D1:=Now;
  D2:=D1-(0.9*OneMilliSecond);
  Test(D1,D2);
  D2:=D1-(1.0*OneMilliSecond);
  Test(D1,D2);
  D2:=D1-(1.1*OneMilliSecond);
  Test(D1,D2);
  D2:=D1-(2.5*OneMilliSecond);
  Test(D1,D2);
End.

```

---

### 9.4.80 MilliSecondSpan

Synopsis: Calculate the approximate number of milliseconds between two DateTime values.

Declaration: `function MilliSecondSpan(const ANow: TDateTime; const AThen: TDateTime) : Double`

Visibility: default

Description: `MilliSecondSpan` returns the number of milliseconds between `ANow` and `AThen`. Since millisecond is the smallest fraction of a `TDateTime` indication, the returned number will always be an integer value.

See also: `YearSpan` ([526](#)), `MonthSpan` ([485](#)), `WeekSpan` ([516](#)), `DaySpan` ([450](#)), `HourSpan` ([463](#)), `MinuteSpan` ([483](#)), `SecondSpan` ([500](#)), `MilliSecondsBetween` ([478](#))

**Listing:** `./datutex/ex70.pp`

---

**Program** `Example70`;

*{ This program demonstrates the MilliSecondSpan function }*

**Uses** `SysUtils, DateUtils`;

**Procedure** `Test(ANow, AThen : TDateTime)`;

```

begin
  Write( 'Number of milliseconds between ');
  Write( TimeToStr(AThen), ' and ', TimeToStr(ANow));
  WriteLn( ' : ', MilliSecondSpan(ANow, AThen));
end;

```

```

Var
  D1, D2 : TDateTime;

```

**Begin**

---

```

D1:=Now;
D2:=D1-(0.9*OneMilliSecond);
Test(D1,D2);
D2:=D1-(1.0*OneMilliSecond);
Test(D1,D2);
D2:=D1-(1.1*OneMilliSecond);
Test(D1,D2);
D2:=D1-(2.5*OneMilliSecond);
Test(D1,D2);
End.

```

---

### 9.4.81 MinuteOf

**Synopsis:** Extract the minute part from a `DateTime` value.

**Declaration:** `function MinuteOf(const AValue: TDateTime) : Word`

**Visibility:** default

**Description:** `MinuteOf` returns the minute of the hour part of the `AValue` date/time indication. It is a number between 0 and 59.

For an example, see `YearOf` ([524](#))

See also: `YearOf` ([524](#)), `WeekOf` ([512](#)), `MonthOf` ([484](#)), `DayOf` ([445](#)), `HourOf` ([460](#)), `SecondOf` ([497](#)), `MilliSecondOf` ([476](#))

### 9.4.82 MinuteOfTheDay

**Synopsis:** Calculate the number of minutes elapsed since the start of the day

**Declaration:** `function MinuteOfTheDay(const AValue: TDateTime) : Word`

**Visibility:** default

**Description:** `MinuteOfTheDay` returns the number of minutes that have passed since the start of the Day (00:00:00) till the moment indicated by `AValue`. This is a zero-based number, i.e. 00:00:59 will return 0.

For an example, see the `HourOfTheDay` ([460](#)) function.

See also: `MinuteOfTheYear` ([482](#)), `MinuteOfTheMonth` ([481](#)), `MinuteOfTheWeek` ([481](#)), `MinuteOfTheHour` ([480](#)), `HourOfTheDay` ([460](#)), `SecondOfTheDay` ([497](#)), `MilliSecondOfTheDay` ([476](#))

### 9.4.83 MinuteOfTheHour

**Synopsis:** Calculate the number of minutes elapsed since the start of the hour

**Declaration:** `function MinuteOfTheHour(const AValue: TDateTime) : Word`

**Visibility:** default

**Description:** `MinuteOfTheHour` returns the number of minutes that have passed since the start of the Hour (HH:00:00) till the moment indicated by `AValue`. This is a zero-based number, i.e. HH:00:59 will return 0.

See also: `MinuteOfTheYear` ([482](#)), `MinuteOfTheMonth` ([481](#)), `MinuteOfTheWeek` ([481](#)), `MinuteOfTheDay` ([480](#)), `SecondOfTheHour` ([497](#)), `MilliSecondOfTheHour` ([476](#))

**Listing:** ./datutex/ex44.pp

**Program** Example44;

*{ This program demonstrates the MinuteOfTheHour function }*

**Uses** SysUtils, DateUtils;

**Var**

N : TDateTime;

**Begin**

N:=Now;

WriteLn('Minute of the Hour : ', MinuteOfTheHour(N));

WriteLn('Second of the Hour : ', SecondOfTheHour(N));

WriteLn('MilliSecond of the Hour : ',  
MilliSecondOfTheHour(N));

**End.**

#### 9.4.84 MinuteOfTheMonth

**Synopsis:** Calculate number of minutes elapsed since the start of the month.

**Declaration:** function MinuteOfTheMonth(const AValue: TDateTime) : Word

**Visibility:** default

**Description:** MinuteOfTheMonth returns the number of minutes that have passed since the start of the Month (00:00:00) till the moment indicated by AValue. This is a zero-based number, i.e. 00:00:59 on the first day of the month will return 0.

For an example, see the WeekOfTheMonth (512) function.

See also: WeekOfTheMonth (512), DayOfTheMonth (445), HourOfTheMonth (461), MinuteOfTheMonth (481), SecondOfTheMonth (498), MilliSecondOfTheMonth (477)

#### 9.4.85 MinuteOfTheWeek

**Synopsis:** Calculate the number of minutes elapsed since the start of the week

**Declaration:** function MinuteOfTheWeek(const AValue: TDateTime) : Word

**Visibility:** default

**Description:** MinuteOfTheWeek returns the number of minutes that have passed since the start of the week (00:00:00) till the moment indicated by AValue. This is a zero-based number, i.e. 00:00:59 on the first day of the week will return 0.

For an example, see the DayOfTheWeek (446) function.

See also: MinuteOfTheYear (482), MinuteOfTheMonth (481), MinuteOfTheDay (480), MinuteOfTheHour (480), DayOfTheWeek (446), HourOfTheWeek (461), SecondOfTheWeek (498), MilliSecondOfTheWeek (478)

### 9.4.86 MinuteOfTheYear

**Synopsis:** Calculate the number of minutes elapsed since the start of the year

**Declaration:** `function MinuteOfTheYear(const AValue: TDateTime) : LongWord`

**Visibility:** default

**Description:** `MinuteOfTheYear` returns the number of minutes that have passed since the start of the year (January 1, 00:00:00) till the moment indicated by `AValue`. This is a zero-based number, i.e. January 1 00:00:59 will return 0.

For an example, see the `WeekOfTheYear` (513) function.

See also: `WeekOfTheYear` (513), `DayOfTheYear` (446), `HourOfTheYear` (462), `MinuteOfTheYear` (482), `SecondOfTheYear` (499), `MilliSecondOfTheYear` (478)

### 9.4.87 MinutesBetween

**Synopsis:** Calculate the number of whole minutes between two `DateTime` values.

**Declaration:** `function MinutesBetween(const ANow: TDateTime; const AThen: TDateTime) : Int64`

**Visibility:** default

**Description:** `MinutesBetween` returns the number of whole minutes between `ANow` and `AThen`. This means the fractional part of a minute (seconds, milliseconds etc.) is dropped.

See also: `YearsBetween` (525), `MonthsBetween` (484), `WeeksBetween` (514), `DaysBetween` (447), `HoursBetween` (462), `SecondsBetween` (499), `MillisecondsBetween` (478)

**Listing:** `./datutex/ex60.pp`

---

**Program** Example60;

*{ This program demonstrates the MinutesBetween function }*

**Uses** SysUtils, DateUtils;

**Procedure** Test(ANow, AThen : TDateTime);

**begin**

  Write('Number of minutes between ');  
  Write(TimeToStr(AThen), ' and ', TimeToStr(ANow));  
  WriteLn(' : ', MinutesBetween(ANow, AThen));  
**end;**

**Var**

  D1, D2 : TDateTime;

**Begin**

  D1:=Now;  
  D2:=D1-(59\*OneSecond);  
  Test(D1, D2);  
  D2:=D1-(61\*OneSecond);  
  Test(D1, D2);  
  D2:=D1-(122\*OneSecond);  
  Test(D1, D2);  
  D2:=D1-(306\*OneSecond);

---

```

Test(D1,D2);
D2:=D1-(5.4*OneMinute);
Test(D1,D2);
D2:=D1-(2.5*OneMinute);
Test(D1,D2);
End.

```

---

### 9.4.88 MinuteSpan

**Synopsis:** Calculate the approximate number of minutes between two DateTime values.

**Declaration:** `function MinuteSpan(const ANow: TDateTime;const AThen: TDateTime)  
: Double`

**Visibility:** default

**Description:** MinuteSpan returns the number of minutes between ANow and AThen, including any fractional parts of a minute.

See also: YearSpan (526), MonthSpan (485), WeekSpan (516), DaySpan (450), HourSpan (463), SecondSpan (500), MilliSecondSpan (479), MinutesBetween (482)

**Listing:** ./datutex/ex68.pp

---

**Program** Example68;

*{ This program demonstrates the MinuteSpan function }*

**Uses** SysUtils, DateUtils;

**Procedure** Test(ANow, AThen : TDateTime);

**begin**

```

Write('Number of minutes between ');
Write(TimeToStr(AThen), ' and ', TimeToStr(ANow));
WriteLn(' : ', MinuteSpan(ANow, AThen));
end;

```

**Var**

```

D1,D2 : TDateTime;

```

**Begin**

```

D1:=Now;
D2:=D1-(59*OneSecond);
Test(D1,D2);
D2:=D1-(61*OneSecond);
Test(D1,D2);
D2:=D1-(122*OneSecond);
Test(D1,D2);
D2:=D1-(306*OneSecond);
Test(D1,D2);
D2:=D1-(5.4*OneMinute);
Test(D1,D2);
D2:=D1-(2.5*OneMinute);
Test(D1,D2);

```

**End.**

---

### 9.4.89 ModifiedJulianDateToDateTime

**Synopsis:** Convert a modified Julian date representation to a `TDateTime` value.

**Declaration:** `function ModifiedJulianDateToDateTime(const AValue: Double) : TDateTime`

**Visibility:** default

**Description:** Not yet implemented.

**Errors:** Currently, trying to use this function will raise an exception.

**See also:** `DateTimeToJulianDate` (444), `JulianDateToDateTime` (475), `TryJulianDateToDateTime` (510), `DateTimeToModifiedJulianDate` (445), `TryModifiedJulianDateToDateTime` (510)

### 9.4.90 MonthOf

**Synopsis:** Extract the month from a given date.

**Declaration:** `function MonthOf(const AValue: TDateTime) : Word`

**Visibility:** default

**Description:** `MonthOf` returns the month part of the `AValue` date/time indication. It is a number between 1 and 12.

For an example, see `YearOf` (524)

**See also:** `YearOf` (524), `DayOf` (445), `WeekOf` (512), `HourOf` (460), `MinuteOf` (480), `SecondOf` (497), `MilliSecondOf` (476)

### 9.4.91 MonthOfTheYear

**Synopsis:** Extract the month of a `DateTime` indication.

**Declaration:** `function MonthOfTheYear(const AValue: TDateTime) : Word`

**Visibility:** default

**Description:** `MonthOfTheYear` extracts the month part of `AValue` and returns it. It is an alias for `MonthOf` (484), and is provided for completeness only, corresponding to the other `PartOfTheYear` functions.

For an example, see the `WeekOfTheYear` (513) function.

**See also:** `MonthOf` (484), `WeekOfTheYear` (513), `DayOfTheYear` (446), `HourOfTheYear` (462), `MinuteOfTheYear` (482), `SecondOfTheYear` (499), `MilliSecondOfTheYear` (478)

### 9.4.92 MonthsBetween

**Synopsis:** Calculate the number of whole months between two `DateTime` values

**Declaration:** `function MonthsBetween(const ANow: TDateTime; const AThen: TDateTime) : Integer`

**Visibility:** default

**Description:** `MonthsBetween` returns the number of whole months between `ANow` and `AThen`. This number is an approximation, based on an average number of days of 30.4375 per month (average over 4 years). This means the fractional part of a month is dropped.

See also: [YearsBetween \(525\)](#), [WeeksBetween \(514\)](#), [DaysBetween \(447\)](#), [HoursBetween \(462\)](#), [MinutesBetween \(482\)](#), [SecondsBetween \(499\)](#), [MilliSecondsBetween \(478\)](#)

**Listing:** ./datutex/ex56.pp

**Program** Example56;

```
{ This program demonstrates the MonthsBetween function }
```

**Uses** SysUtils , DateUtils ;

```
Procedure Test (ANow, AThen : TDateTime);
```

**begin**

```
Write( 'Number of months between ');
Write(DateToStr(AThen), ' and ', DateToStr(ANow));
WriteLn( ' : ', MonthsBetween(ANow, AThen));
end;
```

## Var

D1 , D2 : TDateTime ;

## Begin

```
D1:= Today ;
D2:= Today - 364;
Test (D1, D2);
D2:= Today - 365;
Test (D1, D2);
D2:= Today - 366;
Test (D1, D2);
D2:= Today - 390;
Test (D1, D2);
D2:= Today - 368;
Test (D1, D2);
D2:= Today - 1000;
Test (D1, D2);
```

**End .**

### 9.4.93 MonthSpan

**Synopsis:** Calculate the approximate number of months between two DateTime values.

```
Declaration: function MonthSpan(const ANow: TDateTime;const AThen: TDateTime)
                        : Double
```

Visibility: default

**Description:** MonthSpan returns the number of month between ANow and AThen, including any fractional parts of a month. This number is an approximation, based on an average number of days of 30.4375 per month (average over 4 years).

See also: [YearSpan \(526\)](#), [WeekSpan \(516\)](#), [DaySpan \(450\)](#), [HourSpan \(463\)](#), [MinuteSpan \(483\)](#), [SecondSpan \(500\)](#), [MilliSecondSpan \(479\)](#), [MonthsBetween \(484\)](#)

**Listing:** ./datutex/ex64.pp

---

**Program** Example64;

*{ This program demonstrates the MonthSpan function }*

**Uses** SysUtils, DateUtils;

**Procedure** Test(ANow, AThen : TDateTime);

**begin**

**Write**( 'Number of months between ');

**Write**( **DateToStr**(AThen), ' and ', **DateToStr**(ANow));

**WriteLn**( ' : ', MonthSpan(ANow, AThen));

**end**;

**Var**

    D1, D2 : TDateTime;

**Begin**

    D1 := Today;

    D2 := Today - 364;

    Test(D1, D2);

    D2 := Today - 365;

    Test(D1, D2);

    D2 := Today - 366;

    Test(D1, D2);

    D2 := Today - 390;

    Test(D1, D2);

    D2 := Today - 368;

    Test(D1, D2);

    D2 := Today - 1000;

    Test(D1, D2);

**End.**

---

### 9.4.94 NthDayOfWeek

**Synopsis:** Calculate which occurrence of weekday in the month a given day represents

**Declaration:** `function NthDayOfWeek(const AValue: TDateTime) : Word`

**Visibility:** default

**Description:** `NthDayOfWeek` returns the occurrence of the weekday of `AValue` in the month. This is the N-th time that this weekday occurs in the month (e.g. the third saturday of the month).

**See also:** `EncodeDateMonthWeek` ([454](#)), `#rtl.sysutils.DayOfWeek` ([1474](#)), `DecodeDayOfWeekInMonth` ([453](#)), `EncodeDayOfWeekInMonth` ([455](#)), `TryEncodeDayOfWeekInMonth` ([509](#))

**Listing:** `./datutex/ex104.pp`

---

**Program** Example104;

*{ This program demonstrates the NthDayOfWeek function }*

**Uses** SysUtils, DateUtils;

**Begin**

**Write**( 'Today is the ', NthDayOfWeek(Today), '-th ');



```

WriteIn(formatdateTime('dddd',Today), ' of the month. ');
End.

```

---

### 9.4.95 PreviousDayOfWeek

**Synopsis:** Given a day of the week, return the previous day of the week.

**Declaration:** `function PreviousDayOfWeek(DayOfWeek: Word) : Word`

**Visibility:** default

**Description:** `PreviousDayOfWeek` returns the previous day of the week. If the current day is the first day of the week (1) then the last day will be returned (7).

**Remark:** Note that the days of the week are in ISO notation, i.e. 1-based.

See also: Yesterday ([527](#))

**Listing:** `./datutex/ex22.pp`

---

**Program** Example22;

*{ This program demonstrates the PreviousDayOfWeek function }*

**Uses** SysUtils, DateUtils;

**Var**

D : Word;

**Begin**

For D:=1 to 7 do

WriteIn('Previous day of ',D,' is : ',PreviousDayOfWeek(D));

**End.**

---

### 9.4.96 RecodeDate

**Synopsis:** Replace date part of a `TDateTime` value with another date.

**Declaration:** `function RecodeDate(const AValue: TDateTime;const AYear: Word;  
const AMonth: Word;const ADay: Word) : TDateTime`

**Visibility:** default

**Description:** `RecodeDate` replaces the date part of the timestamp `AValue` with the date specified in `AYear`, `AMonth`, `ADay`. All other parts (the time part) of the date/time stamp are left untouched.

**Errors:** If one of the `AYear`, `AMonth`, `ADay` values is not within a valid range then an `EConvertError` exception is raised.

See also: `RecodeYear` ([493](#)), `RecodeMonth` ([491](#)), `RecodeDay` ([489](#)), `RecodeHour` ([489](#)), `RecodeMinute` ([491](#)), `RecodeSecond` ([492](#)), `RecodeDate` ([487](#)), `RecodeTime` ([493](#)), `RecodeDateTime` ([488](#))

**Listing:** `./datutex/ex94.pp`

---

**Program** Example94;

*{ This program demonstrates the RecodeDate function }*

**Uses** SysUtils, DateUtils;

**Const**

Fmt = 'dddd dd mmmm yyyy hh:nn:ss';

**Var**

S : AnsiString;

**Begin**

S := **FormatDateTime**(Fmt, RecodeDate(**Now**, 2001, 1, 1));

**WriteLn**('This moment on the first of the millenium : ', S);

**End.**

---

### 9.4.97 RecodeDateTime

**Synopsis:** Replace selected parts of a TDateTime value with other values

**Declaration:** function RecodeDateTime(const AValue: TDateTime; const AYear: Word;  
const AMonth: Word; const ADay: Word;  
const AHour: Word; const AMinute: Word;  
const ASecond: Word; const AMilliSecond: Word)  
: TDateTime

**Visibility:** default

**Description:** RecodeDateTime replaces selected parts of the timestamp AValue with the date/time values specified in AYear, AMonth, ADay, AHour, AMinute, ASecond and AMilliSecond. If any of these values equals the pre-defined constant RecodeLeaveFieldAsIs (440), then the corresponding part of the date/time stamp is left untouched.

**Errors:** If one of the values AYear, AMonth, ADay, AHour, AMinute, ASecond, AMilliSecond is not within a valid range (RecodeLeaveFieldAsIs excepted) then an EConvertError exception is raised.

**See also:** RecodeYear (493), RecodeMonth (491), RecodeDay (489), RecodeHour (489), RecodeMinute (491), RecodeSecond (492), RecodeMilliSecond (490), RecodeDate (487), RecodeTime (493), TryRecodeDateTime (511)

**Listing:** ./datutex/ex96.pp

---

**Program** Example96;

*{ This program demonstrates the RecodeDateTime function }*

**Uses** SysUtils, DateUtils;

**Const**

Fmt = 'dddd dd mmmm yyyy hh:nn:ss';

**Var**

S : AnsiString;

D : TDateTime;

**Begin**

```
D:=Now;
D:=RecodeDateTime(D,2000,2,RecodeLeaveFieldAsIs,0,0,0,0);
S:=FormatDateTime(Fmt,D);
WriteIn('This moment in february 2000 : ',S);
End.
```

---

### 9.4.98 RecodeDay

**Synopsis:** Replace day part of a TDateTime value with another day.

**Declaration:** function RecodeDay(const AValue: TDateTime;const ADay: Word) : TDateTime

**Visibility:** default

**Description:** RecodeDay replaces the Day part of the timestamp AValue with ADay. All other parts of the date/time stamp are left untouched.

**Errors:** If the ADay value is not within a valid range (1 till the number of days in the month) then an EConvertError exception is raised.

**See also:** RecodeYear ([493](#)), RecodeMonth ([491](#)), RecodeHour ([489](#)), RecodeMinute ([491](#)), RecodeSecond ([492](#)), RecodeMilliSecond ([490](#)), RecodeDate ([487](#)), RecodeTime ([493](#)), RecodeDateTime ([488](#))

**Listing:** ./datutex/ex89.pp

---

**Program** Example89;

```
{ This program demonstrates the RecodeDay function }
```

**Uses** SysUtils, DateUtils;

**Const**

```
Fmt = 'dddd dd mmm yyyy hh:nn:ss';
```

**Var**

```
S : AnsiString;
```

**Begin**

```
S:=FormatDateTime(Fmt,RecodeDay(Now,1));
WriteIn('This moment on the first of the month : ',S);
End.
```

---

### 9.4.99 RecodeHour

**Synopsis:** Replace hours part of a TDateTime value with another hour.

**Declaration:** function RecodeHour(const AValue: TDateTime;const AHour: Word) : TDateTime

**Visibility:** default

**Description:** RecodeHour replaces the Hour part of the timestamp AValue with AHour. All other parts of the date/time stamp are left untouched.

**Errors:** If the AHour value is not within a valid range (0..23) then an EConvertError exception is raised.

See also: [RecodeYear \(493\)](#), [RecodeMonth \(491\)](#), [RecodeDay \(489\)](#), [RecodeMinute \(491\)](#), [RecodeSecond \(492\)](#), [RecodeMilliSecond \(490\)](#), [RecodeDate \(487\)](#), [RecodeTime \(493\)](#), [RecodeDateTime \(488\)](#)

**Listing:** ./datutex/ex90.pp

---

**Program** Example90;

*{ This program demonstrates the RecodeHour function }*

**Uses** SysUtils, DateUtils;

**Const**

Fmt = 'dddd dd mmm yyyy hh:nn:ss';

**Var**

S : AnsiString;

**Begin**

S := **FormatDateTime**(Fmt, RecodeHour(**Now**, 0));

**WriteIn**('Today, in the first hour : ', S);

**End.**

---

### 9.4.100 RecodeMilliSecond

**Synopsis:** Replace milliseconds part of a TDateTime value with another millisecond.

**Declaration:** function RecodeMilliSecond(const AValue: TDateTime;  
const AMilliSecond: Word) : TDateTime

**Visibility:** default

**Description:** RecodeMilliSecond replaces the millisecond part of the timestamp AValue with AMilliSecond. All other parts of the date/time stamp are left untouched.

**Errors:** If the AMilliSecond value is not within a valid range (0..999) then an EConvertError exception is raised.

See also: [RecodeYear \(493\)](#), [RecodeMonth \(491\)](#), [RecodeDay \(489\)](#), [RecodeHour \(489\)](#), [RecodeMinute \(491\)](#), [RecodeSecond \(492\)](#), [RecodeDate \(487\)](#), [RecodeTime \(493\)](#), [RecodeDateTime \(488\)](#)

**Listing:** ./datutex/ex93.pp

---

**Program** Example93;

*{ This program demonstrates the RecodeMilliSecond function }*

**Uses** SysUtils, DateUtils;

**Const**

Fmt = 'dddd dd mmm yyyy hh:nn:ss.zzz';

**Var**

S : AnsiString;

**Begin**

S := **FormatDateTime**(Fmt, RecodeMilliSecond(**Now**, 0));

**WriteIn**('This moment, milliseconds stripped : ', S);

**End.**

---

### 9.4.101 RecodeMinute

**Synopsis:** Replace minutse part of a TDateTime value with another minute.

**Declaration:** `function RecodeMinute(const AValue: TDateTime;const AMinute: Word)  
: TDateTime`

**Visibility:** default

**Description:** `RecodeMinute` replaces the Minute part of the timestamp `AValue` with `AMinute`. All other parts of the date/time stamp are left untouched.

**Errors:** If the `AMinute` value is not within a valid range (0..59) then an `EConvertError` exception is raised.

**See also:** [RecodeYear \(493\)](#), [RecodeMonth \(491\)](#), [RecodeDay \(489\)](#), [RecodeHour \(489\)](#), [RecodeSecond \(492\)](#), [RecodeMilliSecond \(490\)](#), [RecodeDate \(487\)](#), [RecodeTime \(493\)](#), [RecodeDateTime \(488\)](#)

**Listing:** `./datutex/ex91.pp`

---

**Program** Example91 ;

*{ This program demonstrates the RecodeMinute function }*

**Uses** SysUtils , DateUtils ;

**Const**

    Fmt = 'dddd dd mmm yyyy hh:nn:ss' ;

**Var**

    S : AnsiString ;

**Begin**

    S:=**FormatDateTime**(Fmt,RecodeMinute(**Now**,0));

**WriteIn**('This moment in the first minute of the hour: ',S);

**End.**

---

### 9.4.102 RecodeMonth

**Synopsis:** Replace month part of a TDateTime value with another month.

**Declaration:** `function RecodeMonth(const AValue: TDateTime;const AMonth: Word)  
: TDateTime`

**Visibility:** default

**Description:** `RecodeMonth` replaces the Month part of the timestamp `AValue` with `AMonth`. All other parts of the date/time stamp are left untouched.

**Errors:** If the `AMonth` value is not within a valid range (1..12) then an `EConvertError` exception is raised.

**See also:** [RecodeYear \(493\)](#), [RecodeDay \(489\)](#), [RecodeHour \(489\)](#), [RecodeMinute \(491\)](#), [RecodeSecond \(492\)](#), [RecodeMilliSecond \(490\)](#), [RecodeDate \(487\)](#), [RecodeTime \(493\)](#), [RecodeDateTime \(488\)](#)

**Listing:** `./datutex/ex88.pp`

---

**Program** Example88;

*{ This program demonstrates the RecodeMonth function }*

**Uses** SysUtils, DateUtils;

**Const**

Fmt = 'dddd dd mmm yyyy hh:nn:ss';

**Var**

S : AnsiString;

**Begin**

S := **FormatDateTime**(Fmt, RecodeMonth(**Now**, 5));

**WriteIn**('This moment in May : ', S);

**End.**

---

### 9.4.103 RecodeSecond

**Synopsis:** Replace seconds part of a TDateTime value with another second.

**Declaration:** function RecodeSecond(const AValue: TDateTime; const ASecond: Word)  
: TDateTime

**Visibility:** default

**Description:** RecodeSecond replaces the Second part of the timestamp AValue with ASecond. All other parts of the date/time stamp are left untouched.

**Errors:** If the ASecond value is not within a valid range (0..59) then an EConvertError exception is raised.

**See also:** RecodeYear ([493](#)), RecodeMonth ([491](#)), RecodeDay ([489](#)), RecodeHour ([489](#)), RecodeMinute ([491](#)), RecodeMilliSecond ([490](#)), RecodeDate ([487](#)), RecodeTime ([493](#)), RecodeDateTime ([488](#))

**Listing:** ./datutex/ex92.pp

---

**Program** Example92;

*{ This program demonstrates the RecodeSecond function }*

**Uses** SysUtils, DateUtils;

**Const**

Fmt = 'dddd dd mmm yyyy hh:nn:ss';

**Var**

S : AnsiString;

**Begin**

S := **FormatDateTime**(Fmt, RecodeSecond(**Now**, 0));

**WriteIn**('This moment, seconds stripped : ', S);

**End.**

---

### 9.4.104 RecodeTime

**Synopsis:** Replace time part of a `TDateTime` value with another time.

**Declaration:** `function RecodeTime(const AValue: TDateTime; const AHour: Word;  
const AMinute: Word; const ASecond: Word;  
const AMilliSecond: Word) : TDateTime`

**Visibility:** default

**Description:** `RecodeTime` replaces the time part of the timestamp `AValue` with the date specified in `AHour`, `AMinute`, `ASecond` and `AMilliSecond`. All other parts (the date part) of the date/time stamp are left untouched.

**Errors:** If one of the values `AHour`, `AMinute`, `ASecond` or `AMilliSecond` is not within a valid range then an `EConvertError` exception is raised.

**See also:** `RecodeYear` (493), `RecodeMonth` (491), `RecodeDay` (489), `RecodeHour` (489), `RecodeMinute` (491), `RecodeSecond` (492), `RecodeMilliSecond` (490), `RecodeDate` (487), `RecodeDateTime` (488)

**Listing:** `./datutex/ex95.pp`

---

**Program** Example95;

*{ This program demonstrates the RecodeTime function }*

**Uses** SysUtils, DateUtils;

**Const**

    Fmt = 'dddd dd mmm yyyy hh:nn:ss';

**Var**

    S : AnsiString;

**Begin**

    S := **FormatDateTime**(Fmt, **RecodeTime**(**Now**, 8, 0, 0, 0));

**WriteIn**( 'Today, 8 AM : ', S);

**End.**

---

### 9.4.105 RecodeYear

**Synopsis:** Replace year part of a `TDateTime` value with another year.

**Declaration:** `function RecodeYear(const AValue: TDateTime; const AYear: Word)  
: TDateTime`

**Visibility:** default

**Description:** `RecodeYear` replaces the year part of the timestamp `AValue` with `AYear`. All other parts of the date/time stamp are left untouched.

**Errors:** If the `AYear` value is not within a valid range (1..9999) then an `EConvertError` exception is raised.

**See also:** `RecodeMonth` (491), `RecodeDay` (489), `RecodeHour` (489), `RecodeMinute` (491), `RecodeSecond` (492), `RecodeMilliSecond` (490), `RecodeDate` (487), `RecodeTime` (493), `RecodeDateTime` (488)

**Listing:** `./datutex/ex87.pp`

---

```

Program Example87;

{ This program demonstrates the RecodeYear function }

Uses SysUtils, DateUtils;

Const
    Fmt = 'dddd dd mmmm yyyy hh:nn:ss';

Var
    S : AnsiString;

Begin
    S:=FormatDateTime(Fmt, RecodeYear(Now, 1999));
    WriteLn('This moment in 1999 : ', S);
End.

```

---

#### 9.4.106 SameDate

**Synopsis:** Check whether two TDateTime values have the same date part.

**Declaration:** `function SameDate(const A: TDateTime; const B: TDateTime) : Boolean`

**Visibility:** default

**Description:** SameDate compares the date parts of two timestamps A and B and returns True if they are equal, False if they are not.

The function simply checks whether CompareDate (440) returns zero.

**See also:** CompareDateTime (441), CompareDate (440), CompareTime (442), SameDateTime (495), SameTime (496)

**Listing:** ./datutex/ex102.pp

---

```

Program Example102;

{ This program demonstrates the SameDate function }

Uses SysUtils, DateUtils;

Const
    Fmt = 'dddd dd mmmm yyyy hh:nn:ss.zzz';

Procedure Test(D1, D2 : TDateTime);

begin
    Write(FormatDateTime(Fmt, D1), ' is the same date as ');
    WriteLn(FormatDateTime(Fmt, D2), ' : ', SameDate(D1, D2));
end;

Var
    D, N : TDateTime;

Begin
    D:=Today;
    N:=Now;

```



---

```

Test(D,D);
Test(N,N);
Test(N+1,N);
Test(N-1,N);
Test(N+OneSecond,N);
Test(N-OneSecond,N);
End.

```

---

### 9.4.107 SameDateTime

**Synopsis:** Check whether two TDateTime values have the same date and time parts.

**Declaration:** `function SameDateTime(const A: TDateTime;const B: TDateTime) : Boolean`

**Visibility:** default

**Description:** SameDateTime compares the date/time parts of two timestamps A and B and returns True if they are equal, False if they are not.

The function simply checks whether CompareDateTime (441) returns zero.

See also: CompareDateTime (441), CompareDate (440), CompareTime (442), SameDate (494), SameTime (496)

**Listing:** ./datutex/ex101.pp

---

**Program** Example101;

*{ This program demonstrates the SameDateTime function }*

**Uses** SysUtils, DateUtils;

**Const**

Fmt = 'dddd dd mmm yyyy hh:nn:ss.zzz';

**Procedure** Test(D1,D2 : TDateTime);

**begin**

Write(FormatDateTime(Fmt,D1),' is the same datetime as ');

WriteIn(FormatDateTime(Fmt,D2),' : ',SameDateTime(D1,D2));

**end;**

**Var**

D,N : TDateTime;

**Begin**

D:=Today;

N:=Now;

Test(D,D);

Test(N,N);

Test(N+1,N);

Test(N-1,N);

Test(N+OneSecond,N);

Test(N-OneSecond,N);

**End.**

---

**9.4.108 SameTime**

Synopsis: Check whether two `TDateTime` values have the same time part.

Declaration: `function SameTime(const A: TDateTime; const B: TDateTime) : Boolean`

Visibility: default

Description: `SameTime` compares the time parts of two timestamps `A` and `B` and returns `True` if they are equal, `False` if they are not.

The function simply checks whether `CompareTime` (442) returns zero.

See also: `CompareDateTime` (441), `CompareDate` (440), `CompareTime` (442), `SameDateTime` (495), `SameDate` (494)

**Listing:** `./datutex/ex103.pp`

---

**Program** `Example102;`

*{ This program demonstrates the SameTime function }*

**Uses** `SysUtils, DateUtils;`

**Const**

`Fmt = 'dddd dd mmmm yyyy hh:nn:ss.zzz';`

**Procedure** `Test(D1, D2 : TDateTime);`

**begin**

`Write(FormatDateTime(Fmt, D1), ' is the same time as ');`

`WriteLn(FormatDateTime(Fmt, D2), ' : ', SameTime(D1, D2));`

**end;**

**Var**

`D, N : TDateTime;`

**Begin**

`D := Today;`

`N := Now;`

`Test(D, D);`

`Test(N, N);`

`Test(N+1, N);`

`Test(N-1, N);`

`Test(N+OneSecond, N);`

`Test(N-OneSecond, N);`

**End.**

---

**9.4.109 ScanDateTime**

Synopsis: Scans a string for a `DateTime` pattern and returns the date/time

Declaration: `function ScanDateTime(const Pattern: String; const s: String;  
const fmt: TFormatSettings; startpos: Integer)  
: tdatetime; Overload`  
`function ScanDateTime(const Pattern: String; const s: String;  
startpos: Integer) : tdatetime; Overload`

Visibility: default

**Description:** `ScanDateTime` scans string `S` for the date/time pattern `Pattern`, starting at position `StartPos` (default 1). Optionally, the format settings `fmt` can be specified.

In effect, this function does the opposite of what `FormatDateTime` (1510) does. The `Pattern` variable must contain a valid date/time pattern: note that not all possible `formatdatetime` patterns can be recognized, e.g., `hn` cannot be detected properly.

**Errors:** In case of an error, a `EConvertError` (1572) exception is raised.

See also: `#rtl.sysutils.FormatDateTime` (1510)

### 9.4.110 SecondOf

**Synopsis:** Extract the second part from a `DateTime` value.

**Declaration:** `function SecondOf(const AValue: TDateTime) : Word`

**Visibility:** default

**Description:** `SecondOf` returns the second of the minute part of the `AValue` date/time indication. It is a number between 0 and 59.

For an example, see `YearOf` (524)

See also: `YearOf` (524), `WeekOf` (512), `MonthOf` (484), `DayOf` (445), `HourOf` (460), `MinuteOf` (480), `MilliSecondOf` (476)

### 9.4.111 SecondOfDay

**Synopsis:** Calculate the number of seconds elapsed since the start of the day

**Declaration:** `function SecondOfDay(const AValue: TDateTime) : LongWord`

**Visibility:** default

**Description:** `SecondOfDay` returns the number of seconds that have passed since the start of the Day (00:00:00) till the moment indicated by `AValue`. This is a zero-based number, i.e. 00:00:00.999 return 0.

For an example, see the `HourOfDay` (460) function.

See also: `SecondOfYear` (499), `SecondOfMonth` (498), `SecondOfWeek` (498), `SecondOfTheHour` (497), `SecondOfTheMinute` (498), `HourOfDay` (460), `MinuteOfDay` (480), `MilliSecondOfDay` (476)

### 9.4.112 SecondOfTheHour

**Synopsis:** Calculate the number of seconds elapsed since the start of the hour

**Declaration:** `function SecondOfTheHour(const AValue: TDateTime) : Word`

**Visibility:** default

**Description:** `SecondOfTheHour` returns the number of seconds that have passed since the start of the Hour (HH:00:00) till the moment indicated by `AValue`. This is a zero-based number, i.e. HH:00:00.999 return 0.

For an example, see the `MinuteOfTheHour` (480) function.

See also: `SecondOfYear` (499), `SecondOfMonth` (498), `SecondOfWeek` (498), `SecondOfDay` (497), `SecondOfTheMinute` (498), `MinuteOfTheHour` (480), `MilliSecondOfTheHour` (476)

### 9.4.113 SecondOfTheMinute

**Synopsis:** Calculate the number of seconds elapsed since the start of the minute

**Declaration:** `function SecondOfTheMinute(const AValue: TDateTime) : Word`

**Visibility:** default

**Description:** `SecondOfTheMinute` returns the number of seconds that have passed since the start of the minute (HH:MM:00) till the moment indicated by `AValue`. This is a zero-based number, i.e. HH:MM:00.999 return 0.

See also: `SecondOfTheYear` (499), `SecondOfTheMonth` (498), `SecondOfTheWeek` (498), `SecondOfTheDay` (497), `SecondOfTheHour` (497), `MilliSecondOfTheMinute` (476)

**Listing:** `./datutex/ex45.pp`

---

**Program** Example45;

*{ This program demonstrates the SecondOfTheMinute function }*

**Uses** SysUtils, DateUtils;

**Var**

N : TDateTime;

**Begin**

N:=Now;

WriteLn('Second of the Minute : ',SecondOfTheMinute(N));

WriteLn('MilliSecond of the Minute : ',  
MilliSecondOfTheMinute(N));

**End.**

---

### 9.4.114 SecondOfTheMonth

**Synopsis:** Calculate number of seconds elapsed since the start of the month.

**Declaration:** `function SecondOfTheMonth(const AValue: TDateTime) : LongWord`

**Visibility:** default

**Description:** `SecondOfTheMonth` returns the number of seconds that have passed since the start of the month (00:00:00) till the moment indicated by `AValue`. This is a zero-based number, i.e. 00:00:00.999 on the first day of the month will return 0.

For an example, see the `WeekOfTheMonth` (512) function.

See also: `WeekOfTheMonth` (512), `DayOfTheMonth` (445), `HourOfTheMonth` (461), `MinuteOfTheMonth` (481), `MilliSecondOfTheMonth` (477)

### 9.4.115 SecondOfTheWeek

**Synopsis:** Calculate the number of seconds elapsed since the start of the week

**Declaration:** `function SecondOfTheWeek(const AValue: TDateTime) : LongWord`

**Visibility:** default

**Description:** `SecondOfTheWeek` returns the number of seconds that have passed since the start of the week (00:00:00) till the moment indicated by `AValue`. This is a zero-based number, i.e. 00:00:00.999 on the first day of the week will return 0.

For an example, see the `DayOfTheWeek` (446) function.

See also: `SecondOfTheYear` (499), `SecondOfTheMonth` (498), `SecondOfTheDay` (497), `SecondOfTheHour` (497), `SecondOfTheMinute` (498), `DayOfTheWeek` (446), `HourOfTheWeek` (461), `MinuteOfTheWeek` (481), `MilliSecondOfTheWeek` (478)

### 9.4.116 `SecondOfTheYear`

**Synopsis:** Calculate the number of seconds elapsed since the start of the year.

**Declaration:** `function SecondOfTheYear(const AValue: TDateTime) : LongWord`

**Visibility:** default

**Description:** `SecondOfTheYear` returns the number of seconds that have passed since the start of the year (January 1, 00:00:00) till the moment indicated by `AValue`. This is a zero-based number, i.e. January 1 00:00:00.999 will return 0.

For an example, see the `WeekOfTheYear` (513) function.

See also: `WeekOfTheYear` (513), `DayOfTheYear` (446), `HourOfTheYear` (462), `MinuteOfTheYear` (482), `SecondOfTheYear` (499), `MilliSecondOfTheYear` (478)

### 9.4.117 `SecondsBetween`

**Synopsis:** Calculate the number of whole seconds between two `DateTime` values.

**Declaration:** `function SecondsBetween(const ANow: TDateTime; const AThen: TDateTime) : Int64`

**Visibility:** default

**Description:** `SecondsBetween` returns the number of whole seconds between `ANow` and `AThen`. This means the fractional part of a second (milliseconds etc.) is dropped.

See also: `YearsBetween` (525), `MonthsBetween` (484), `WeeksBetween` (514), `DaysBetween` (447), `HoursBetween` (462), `MinutesBetween` (482), `MilliSecondsBetween` (478)

**Listing:** `./datutex/ex61.pp`

---

**Program** `Example61` ;

*{ This program demonstrates the SecondsBetween function }*

**Uses** `SysUtils` , `DateUtils` ;

**Procedure** `Test` (`ANow`, `AThen` : `TDateTime`) ;

**begin**

**Write** ( 'Number of seconds between ' );  
    **Write** (`TimeToStr` (`AThen`) , ' and ' , `TimeToStr` (`ANow`) );  
    **WriteLn** ( ' : ' , `SecondsBetween` (`ANow`, `AThen`) );  
**end** ;

**Var**

```

Begin
  D1:=Now;
  D2:=D1-(999*OneMilliSecond);
  Test(D1,D2);
  D2:=D1-(1001*OneMilliSecond);
  Test(D1,D2);
  D2:=D1-(2001*OneMilliSecond);
  Test(D1,D2);
  D2:=D1-(5001*OneMilliSecond);
  Test(D1,D2);
  D2:=D1-(5.4*OneSecond);
  Test(D1,D2);
  D2:=D1-(2.5*OneSecond);
  Test(D1,D2);
End.

```

```

Write ('Number of seconds between ');
Write (TimeToStr(AThen), ' and ', TimeToStr(ANow));
WriteLn (' : ', SecondSpan(ANow, AThen));
end;

```

D1,D2 : TDateTime;

```
D1:=Now;  
D2:=D1-(999*OneMilliSecond);  
Test(D1,D2);  
D2:=D1-(1001*OneMilliSecond);
```

```

Test(D1,D2);
D2:=D1-(2001*OneMilliSecond);
Test(D1,D2);
D2:=D1-(5001*OneMilliSecond);
Test(D1,D2);
D2:=D1-(5.4*OneSecond);
Test(D1,D2);
D2:=D1-(2.5*OneSecond);
Test(D1,D2);
End.

```

---

### 9.4.119 StartOfDay

**Synopsis:** Return the start of a day as a DateTime value, given a day indication

**Declaration:**

```

function StartOfDay(const AYear: Word;const AMonth: Word;
                    const ADay: Word) : TDateTime; Overload
function StartOfDay(const AYear: Word;const ADayOfYear: Word)
                    : TDateTime; Overload

```

**Visibility:** default

**Description:** StartOfDay returns a TDateTime value with the date/time indication of the start (0:0:0.000) of the day given by AYear, AMonth, ADay.

The day may also be indicated with a AYear, ADayOfYear pair.

See also: StartOfDay (503), StartOfTheWeek (504), StartOfAWeek (502), StartOfAMonth (502), StartOfTheMonth (504), EndOfTheWeek (459), EndOfAWeek (457), EndOfTheYear (460), EndOfAYear (457), EndOfTheMonth (458), EndOfAMonth (456), EndOfTheDay (458), EndOfDay (455)

**Listing:** ./datutex/ex38.pp

---

**Program** Example38;

*{ This program demonstrates the StartOfDay function }*

**Uses** SysUtils, DateUtils;

**Const**

Fmt = ' "Start of the day : "dd mmm yyyy hh:nn:ss ';

**Var**

Y,M,D : Word;

**Begin**

Y:=YearOf(Today);

M:=MonthOf(Today);

D:=DayOf(Today);

WriteLn(FormatDateTime(Fmt, StartOfDay(Y,M,D)));

DecodeDateDay(Today,Y,D);

WriteLn(FormatDateTime(Fmt, StartOfDay(Y,D)));

**End.**

---

### 9.4.120 StartOfAMonth

Synopsis: Return first date of month, given a year/month pair.

Declaration: `function StartOfAMonth(const AYear: Word;const AMonth: Word) : TDateTime`

Visibility: default

Description: `StartOfAMonth` returns a `TDateTime` value with the date of the first day of the month indicated by the `AYear`, `AMonth` pair.

See also: `StartOfTheMonth` (504), `EndOfTheMonth` (458), `EndOfAMonth` (456), `EndOfTheYear` (460), `EndOfAYear` (457), `StartOfAWeek` (502), `StartOfTheWeek` (504)

**Listing:** `./datutex/ex30.pp`

---

**Program** Example30;

*{ This program demonstrates the StartOfAMonth function }*

**Uses** SysUtils, DateUtils;

**Const**

    Fmt = ' "First day of this month : "dd mmm yyyy ';

**Var**

    Y,M : Word;

**Begin**

    Y:=YearOf(Today);

    M:=MonthOf(Today);

    WriteLn(FormatDateTime(Fmt, StartOfAMonth(Y,M)));

**End.**

---

### 9.4.121 StartOfAWeek

Synopsis: Return a day of the week, given a year, week and day in the week.

Declaration: `function StartOfAWeek(const AYear: Word;const AWeekOfYear: Word;  
                                  const ADayOfWeek: Word) : TDateTime`  
`function StartOfAWeek(const AYear: Word;const AWeekOfYear: Word)  
                      : TDateTime`

Visibility: default

Description: `StartOfAWeek` returns a `TDateTime` value with the date of the indicated day of the week indicated by the `AYear`, `AWeek`, `ADayOfWeek` values.

The default value for `ADayOfWeek` is 1.

See also: `StartOfTheWeek` (504), `EndOfTheWeek` (459), `EndOfAWeek` (457), `StartOfAMonth` (502), `EndOfTheYear` (460), `EndOfAYear` (457), `EndOfTheMonth` (458), `EndOfAMonth` (456)

**Listing:** `./datutex/ex34.pp`

---

**Program** Example34;

*{ This program demonstrates the StartOfAWeek function }*

**Uses** SysUtils, DateUtils;



**Const**

```
Fmt = '"First day of this week : "dd mmm yyyy hh:nn:ss';
Fmt2 = '"Second day of this week : "dd mmm yyyy hh:nn:ss';
```

**Var**

```
Y,W : Word;
```

**Begin**

```
Y:=YearOf(Today);
W:=WeekOf(Today);
WriteIn(FormatDateTime(Fmt, StartOfAWeek(Y,W)));
WriteIn(FormatDateTime(Fmt2, StartOfAWeek(Y,W,2)));
```

```
End.
```

---

**9.4.122 StartOfAYear**

Synopsis: Return the first day of a given year.

Declaration: `function StartOfAYear(const AYear: Word) : TDateTime`

Visibility: default

Description: `StartOfAYear` returns a `TDateTime` value with the date of the first day of the year `AYear` (January 1).

See also: `StartOfTheYear` ([505](#)), `EndOfTheYear` ([460](#)), `EndOfAYear` ([457](#)), `EndOfTheMonth` ([458](#)), `EndOfA-Month` ([456](#)), `StartOfAWeek` ([502](#)), `StartOfTheWeek` ([504](#))

**Listing:** `./datutex/ex26.pp`

---

**Program** Example26;

```
{ This program demonstrates the StartOfAYear function }
```

**Uses** SysUtils, DateUtils;

**Const**

```
Fmt = '"First day of this year : "dd mmm yyyy';
```

**Begin**

```
WriteIn(FormatDateTime(Fmt, StartOfAYear(YearOf(Today))));
```

```
End.
```

---

**9.4.123 StartOfTheDay**

Synopsis: Calculate the start of the day as a `DateTime` value, given a moment in the day.

Declaration: `function StartOfTheDay(const AValue: TDateTime) : TDateTime`

Visibility: default

Description: `StartOfTheDay` extracts the date part of `AValue` and returns a `TDateTime` value with the date/time indication of the start (0:0:0.000) of this day.

See also: [StartOfADay \(501\)](#), [StartOfTheWeek \(504\)](#), [StartOfAWeek \(502\)](#), [StartOfAMonth \(502\)](#), [StartOfTheMonth \(504\)](#), [EndOfTheWeek \(459\)](#), [EndOfAWeek \(457\)](#), [EndOfTheYear \(460\)](#), [EndOfAYear \(457\)](#), [EndOfTheMonth \(458\)](#), [EndOfAMonth \(456\)](#), [EndOftheDay \(458\)](#), [EndOfADay \(455\)](#)

**Listing:** ./datutex/ex36.pp

---

**Program** Example36;

*{ This program demonstrates the StartOfTheDay function }*

**Uses** SysUtils, DateUtils;

**Const**

Fmt = 'Start of the day : "dd mmm yyyy hh:nn:ss';

**Begin**

WriteIn (FormatDateTime (Fmt, StartOfTheDay (Today)));

**End.**

---

#### 9.4.124 StartOfTheMonth

Synopsis: Calculate the first day of the month, given a date in that month.

**Declaration:** function StartOfTheMonth(const AValue: TDateTime) : TDateTime

Visibility: default

**Description:** StartOfTheMonth extracts the year and month parts of AValue and returns a TDateTime value with the date of the first day of that year and month as the StartOfAMonth ([502](#)) function.

See also: [StartOfAMonth \(502\)](#), [EndOfTheYear \(460\)](#), [EndOfAYear \(457\)](#), [EndOfTheMonth \(458\)](#), [EndOfAMonth \(456\)](#), [StartOfAWeek \(502\)](#), [StartOfTheWeek \(504\)](#)

**Listing:** ./datutex/ex28.pp

---

**Program** Example28;

*{ This program demonstrates the StartOfTheMonth function }*

**Uses** SysUtils, DateUtils;

**Const**

Fmt = 'First day of this month : "dd mmm yyyy';

**Begin**

WriteIn (FormatDateTime (Fmt, StartOfTheMonth (Today)));

**End.**

---

#### 9.4.125 StartOfTheWeek

Synopsis: Return the first day of the week, given a date.

**Declaration:** function StartOfTheWeek(const AValue: TDateTime) : TDateTime

Visibility: default

**Description:** `StartOfTheWeek` extracts the year and week parts of `AValue` and returns a `TDateTime` value with the date of the first day of that week as the `StartOfAWeek` (502) function.

See also: `StartOfAWeek` (502), `EndOfTheWeek` (459), `EndOfAWeek` (457), `StartOfAMonth` (502), `EndOfTheYear` (460), `EndOfAYear` (457), `EndOfTheMonth` (458), `EndOfAMonth` (456)

**Listing:** `./datutex/ex32.pp`

---

**Program** `Example32`;

*{ This program demonstrates the StartOfTheWeek function }*

**Uses** `SysUtils`, `DateUtils`;

**Const**

`Fmt = ' "First day of this week : "dd mmm yyyy ';`

**Begin**

`WriteLn (FormatDateTime (Fmt, StartOfTheWeek (Today)));`

**End.**

---

### 9.4.126 StartOfTheYear

**Synopsis:** Return the first day of the year, given a date in this year.

**Declaration:** `function StartOfTheYear(const AValue: TDateTime) : TDateTime`

**Visibility:** `default`

**Description:** `StartOfTheYear` extracts the year part of `AValue` and returns a `TDateTime` value with the date of the first day of that year (January 1), as the `StartOfAYear` (503) function.

See also: `StartOfAYear` (503), `EndOfTheYear` (460), `EndOfAYear` (457)

**Listing:** `./datutex/ex24.pp`

---

**Program** `Example24`;

*{ This program demonstrates the StartOfTheYear function }*

**Uses** `SysUtils`, `DateUtils`;

**Const**

`Fmt = ' "First day of this year : "dd mmm yyyy ';`

**Begin**

`WriteLn (FormatDateTime (Fmt, StartOfTheYear (Today)));`

**End.**

---

### 9.4.127 TimeOf

**Synopsis:** Extract the time part from a `DateTime` indication.

**Declaration:** `function TimeOf(const AValue: TDateTime) : TDateTime`

**Visibility:** `default`

**Description:** `TimeOf` extracts the time part from `AValue` and returns the result.

Since the `TDateTime` is actually a double with the time part encoded in the fractional part, this operation corresponds to a call to `Frac`.

See also: `DateOf` ([443](#)), `YearOf` ([524](#)), `MonthOf` ([484](#)), `DayOf` ([445](#)), `HourOf` ([460](#)), `MinuteOf` ([480](#)), `SecondOf` ([497](#)), `MilliSecondOf` ([476](#))

**Listing:** `./datutex/ex2.pp`

---

**Program** `Example2`;

*{ This program demonstrates the TimeOf function }*

**Uses** `SysUtils`, `DateUtils`;

**Begin**

`WriteLn('Time is : ', TimeToStr(TimeOf(Now)));`  
**End.**

---

### 9.4.128 Today

**Synopsis:** Return the current date

**Declaration:** `function Today : TDateTime`

**Visibility:** `default`

**Description:** `Today` is an alias for the `Date` ([1470](#)) function in the `sysutils` ([1426](#)) unit.

For an example, see `Yesterday` ([527](#))

See also: `#rtl.sysutils.Date` ([1470](#)), `Yesterday` ([527](#)), `Tomorrow` ([506](#))

### 9.4.129 Tomorrow

**Synopsis:** Return the next day

**Declaration:** `function Tomorrow : TDateTime`

**Visibility:** `default`

**Description:** `Tomorrow` returns tomorrow's date. `Tomorrow` is determined from the system clock, i.e. it is `Today` ([506](#)) +1.

See also: `Today` ([506](#)), `Yesterday` ([527](#))

**Listing:** `./datutex/ex19.pp`

---

**Program** `Example19`;

*{ This program demonstrates the Tomorrow function }*

**Uses** `SysUtils`, `DateUtils`;

**Begin**

`WriteLn(FormatDateTime('"Today is" dd mmm yyyy', Today));`  
`WriteLn(FormatDateTime('"Tomorrow will be" dd mmm yyyy', Tomorrow));`  
**End.**

---

**9.4.130 TryEncodeDateDay**

Synopsis: Encode a year and day of year to a TDateTime value

Declaration: `function TryEncodeDateDay(const AYear: Word;const ADayOfYear: Word;  
out AValue: TDateTime) : Boolean`

Visibility: default

Description: TryEncodeDateDay encodes the values AYear and ADayOfYear to a date value and returns this value in AValue.

If the encoding was successful, True is returned. False is returned if any of the arguments is not valid.

See also: EncodeDateDay (454), EncodeDateTime (454), EncodeDateMonthWeek (454), EncodeDateWeek (455), TryEncodeDateTime (508), TryEncodeDateMonthWeek (507), TryEncodeDateWeek (509)

**Listing:** ./datutex/ex84.pp

---

**Program** Example84;

*{ This program demonstrates the TryEncodeDateDay function }*

**Uses** SysUtils, DateUtils;

**Var**

Y, DoY : Word;  
TS : TDateTime;

**Begin**

DecodeDateDay(**Now**, Y, DoY);  
**If** TryEncodeDateDay(Y, DoY, TS) **then**  
    **WriteLn**( 'Today is : ', **DateToStr**(TS))  
**else**  
    **WriteLn**( 'Wrong year/day of year indication');

**End.**

---

**9.4.131 TryEncodeDateMonthWeek**

Synopsis: Encode a year, month, week of month and day of week to a TDateTime value

Declaration: `function TryEncodeDateMonthWeek(const AYear: Word;const AMonth: Word;  
const AWeekOfMonth: Word;  
const ADayOfWeek: Word;  
out AValue: TDateTime) : Boolean`

Visibility: default

Description: TryEncodeDateMonthWeek encodes the values AYear, AMonth, AWeekOfMonth, ADayOfWeek, to a date value and returns this value in AValue.

If the encoding was successful, True is returned, False if any of the arguments is not valid.

See also: DecodeDateMonthWeek (451), EncodeDateTime (454), EncodeDateWeek (455), EncodeDateDay (454), EncodeDateMonthWeek (454), TryEncodeDateTime (508), TryEncodeDateWeek (509), TryEncodeDateDay (507), NthDayOfWeek (486)

**Listing:** ./datutex/ex86.pp

---

**Program** Example86;

*{ This program demonstrates the TryEncodeDateMonthWeek function }*

**Uses** SysUtils , DateUtils ;

**Var**

Y,M,WoM,Dow : Word;  
TS : TDateTime;

**Begin**

DecodeDateMonthWeek(**Now**,Y,M,WoM,Dow);  
**If** TryEncodeDateMonthWeek(Y,M,WoM,Dow,TS) **then**  
    **WriteLn**( 'Today is : ',**DateToStr**(TS))  
**else**  
    **WriteLn**( 'Invalid year/month/week/dow indication ');

**End.**

---

### 9.4.132 TryEncodeDateTime

**Synopsis:** Encode a Year, Month, Day, Hour, minute, seconds, milliseconds tuple to a TDateTime value

**Declaration:** function TryEncodeDateTime(const AYear: Word;const AMonth: Word;  
  const ADay: Word;const AHour: Word;  
  const AMinute: Word;const ASecond: Word;  
  const AMilliSecond: Word;  
  out AValue: TDateTime) : Boolean

**Visibility:** default

**Description:** EncodeDateTime encodes the values AYearAMonth, ADay,AHour, AMinute,ASecond and AMilliSecond to a date/time value and returns this value in AValue.

If the date was encoded successfully, True is returned, False is returned if one of the arguments is not valid.

**See also:** EncodeDateTime (454), EncodeDateMonthWeek (454), EncodeDateWeek (455), EncodeDateDay (454), TryEncodeDateDay (507), TryEncodeDateWeek (509), TryEncodeDateMonthWeek (507)

**Listing:** ./datutex/ex80.pp

---

**Program** Example79;

*{ This program demonstrates the TryEncodeDateTime function }*

**Uses** SysUtils , DateUtils ;

**Var**

Y,Mo,D,H,Mi,S,MS : Word;  
TS : TDateTime;

**Begin**

DecodeDateTime(**Now**,Y,Mo,D,H,Mi,S,MS);  
**If** TryEncodeDateTime(Y,Mo,D,H,Mi,S,MS,TS) **then**  
    **WriteLn**( 'Now is : ',**DateTimeToStr**(TS))  
**else**  
    **WriteLn**( 'Wrong date/time indication ');

---

End.

---

### 9.4.133 TryEncodeDateWeek

Synopsis: Encode a year, week and day of week triplet to a TDateTime value

Declaration: 

```
function TryEncodeDateWeek(const AYear: Word;const AWeekOfYear: Word;
                           out AValue: TDateTime;const ADayOfWeek: Word)
                           : Boolean
function TryEncodeDateWeek(const AYear: Word;const AWeekOfYear: Word;
                           out AValue: TDateTime) : Boolean
```

Visibility: default

Description: TryEncodeDateWeek encodes the values AYear, AWeekOfYear and ADayOfWeek to a date value and returns this value in AValue.

If the encoding was successful, True is returned. False is returned if any of the arguments is not valid.

See also: EncodeDateMonthWeek (454), EncodeDateWeek (455), EncodeDateTime (454), EncodeDateDay (454), TryEncodeDateTime (508), TryEncodeDateMonthWeek (507), TryEncodeDateDay (507)

Listing: ./datutex/ex82.pp

---

Program Example82;

*{ This program demonstrates the TryEncodeDateWeek function }*

Uses SysUtils , DateUtils ;

Var

Y,W,Dow : Word;  
TS : TDateTime;

Begin

DecodeDateWeek(**Now**,Y,W,Dow);  
**If** TryEncodeDateWeek(Y,W,TS,Dow) **then**  
    **WriteLn**('Today is : ',DateToStr(TS))  
**else**  
    **WriteLn**('Invalid date/week indication');

End.

---

### 9.4.134 TryEncodeDayOfWeekInMonth

Synopsis: Encode a year, month, week, day of week triplet to a TDateTime value

Declaration: 

```
function TryEncodeDayOfWeekInMonth(const AYear: Word;const AMonth: Word;
                                   const ANthDayOfWeek: Word;
                                   const ADayOfWeek: Word;
                                   out AValue: TDateTime) : Boolean
```

Visibility: default

**Description:** `EncodeDayOfWeekInMonth` encodes `AYear`, `AMonth`, `ADayOfWeek` and `ANthDayOfWeek` to a valid date stamp and returns the result in `AValue`.

`ANthDayOfWeek` is the N-th time that this weekday occurs in the month, e.g. the third saturday of the month.

The function returns `True` if the encoding was succesful, `False` if any of the values is not in range.

See also: `NthDayOfWeek` (486), `EncodeDateMonthWeek` (454), `#rtl.sysutils.DayOfWeek` (1474), `DecodeDayOfWeekInMonth` (453), `EncodeDayOfWeekInMonth` (455)

**Listing:** `./datutex/ex106.pp`

**Program** `Example105`;

*{ This program demonstrates the DecodeDayOfWeekInMonth function }*

**Uses** `SysUtils`, `DateUtils`;

**Var**

`Y,M,NDoW,DoW` : `Word`;

`D` : `TDateTime`;

**Begin**

`DecodeDayOfWeekInMonth (Date , Y,M,NDoW,DoW) ;`

**If** `TryEncodeDayOfWeekInMonth (Y,M,NDoW,DoW,D)` **then**

**begin**

`Write (DateToStr(D), ' is the ',NDoW, '-th ');`

`WriteLn (formatdateTime( 'dddd',D), ' of the month. ');`

**end**

**else**

`WriteLn( 'Invalid year/month/NthDayOfWeek combination ');`

**End.**

### 9.4.135 TryJulianDateToDateTime

**Synopsis:** Convert a Julian date representation to a `TDateTime` value.

**Declaration:** `function TryJulianDateToDateTime(const AValue: Double;`  
`out ADateTime: TDateTime) : Boolean`

**Visibility:** `default`

**Description:** Try to convert a Julian date to a regular `TDateTime` date/time representation.

See also: `DateTimeToJulianDate` (444), `JulianDateToDateTime` (475), `DateTimeToModifiedJulianDate` (445), `TryModifiedJulianDateToDateTime` (510)

### 9.4.136 TryModifiedJulianDateToDateTime

**Synopsis:** Convert a modified Julian date representation to a `TDateTime` value.

**Declaration:** `function TryModifiedJulianDateToDateTime(const AValue: Double;`  
`out ADateTime: TDateTime)`  
`: Boolean`

**Visibility:** `default`

**Description:** Not yet implemented.



Errors: Currently, trying to use this function will raise an exception.

See also: [DateTimeToJulianDate \(444\)](#), [JulianDateToDateTime \(475\)](#), [TryJulianDateToDateTime \(510\)](#), [DateTimeToModifiedJulianDate \(445\)](#), [ModifiedJulianDateToDateTime \(484\)](#)

### 9.4.137 TryRecodeDateTime

Synopsis: Replace selected parts of a TDateTime value with other values

Declaration: 

```
function TryRecodeDateTime(const AValue: TDateTime;const AYear: Word;
                           const AMonth: Word;const ADay: Word;
                           const AHour: Word;const AMinute: Word;
                           const ASecond: Word;const AMilliSecond: Word;
                           out AResult: TDateTime) : Boolean
```

Visibility: default

Description: TryRecodeDateTime replaces selected parts of the timestamp AValue with the date/time values specified in AYear, AMonth, ADay, AHour, AMinute, ASecond and AMilliSecond. If any of these values equals the pre-defined constant RecodeLeaveFieldAsIs (440), then the corresponding part of the date/time stamp is left untouched.

The resulting date/time is returned in AValue.

The function returns True if the encoding was succesful. It returns False if one of the values AYear, AMonth, ADay, AHour, AMinute, ASecondAMilliSecond is not within a valid range.

See also: [RecodeYear \(493\)](#), [RecodeMonth \(491\)](#), [RecodeDay \(489\)](#), [RecodeHour \(489\)](#), [RecodeMinute \(491\)](#), [RecodeSecond \(492\)](#), [RecodeMilliSecond \(490\)](#), [RecodeDate \(487\)](#), [RecodeTime \(493\)](#), [RecodeDateTime \(488\)](#)

**Listing:** ./datutex/ex97.pp

---

**Program** Example97;

*{ This program demonstrates the TryRecodeDateTime function }*

**Uses** SysUtils, DateUtils;

**Const**

    Fmt = 'dddd dd mmm yyyy hh:nn:ss';

**Var**

    S : AnsiString;

    D : TDateTime;

**Begin**

**If** TryRecodeDateTime(**Now**,2000,2,RecodeLeaveFieldAsIs,0,0,0,0,D) **then**  
        **begin**  
            S:=**FormatDateTime**(Fmt,D);  
            **WriteLn**('This moment in februari 2000 : ',S);  
            **end**  
        **else**  
            **WriteLn**('This moment did/does not exist in februari 2000');

**End.**

---

### 9.4.138 UnixTimeStampToMac

**Synopsis:** Convert Unix Timestamp to a Mac Timestamp

**Declaration:** `function UnixTimeStampToMac(const AValue: Int64) : Int64`

**Visibility:** default

**Description:** `UnixTimeStampToMac` converts the unix epoch time in `AValue` to a valid Mac timestamp indication and returns the result.

**Errors:** None.

**See also:** `DateTimeToMac` (444), `MacToDateTime` (475), `MacTimeStampToUnix` (475)

### 9.4.139 UnixToDateTime

**Synopsis:** Convert Unix epoch time to a `TDateTime` value

**Declaration:** `function UnixToDateTime(const AValue: Int64) : TDateTime`

**Visibility:** default

**Description:** `UnixToDateTime` converts epoch time (time elapsed since 1/1/1970) to a `TDateTime` value.

**See also:** `DateTimeToUnix` (445)

### 9.4.140 WeekOf

**Synopsis:** Extract week (of the year) from a given date.

**Declaration:** `function WeekOf(const AValue: TDateTime) : Word`

**Visibility:** default

**Description:** `WeekOf` returns the week-of-the-year part of the `AValue` date/time indication. It is a number between 1 and 53.

For an example, see `YearOf` (524)

**See also:** `YearOf` (524), `DayOf` (445), `MonthOf` (484), `HourOf` (460), `MinuteOf` (480), `SecondOf` (497), `MilliSecondOf` (476)

### 9.4.141 WeekOfTheMonth

**Synopsis:** Extract the week of the month (and optionally month and year) from a `DateTime` value

**Declaration:** `function WeekOfTheMonth(const AValue: TDateTime) : Word; Overload`  
`function WeekOfTheMonth(const AValue: TDateTime; out AYear: Word;`  
`out AMonth: Word) : Word; Overload`

**Visibility:** default

**Description:** `WeekOfTheMonth` extracts the week of the month from `AValue` and returns it, and optionally returns the year and month as well (in `AYear`, `AMonth` respectively).

**Remark:** Note that weeks are numbered from 1 using the ISO 8601 standard, and the day of the week as well. This means that the year and month may not be the same as the year part of the date, since the week may start in the previous year as the first week of the year is the week with at least 4 days in it.

See also: [WeekOfTheYear \(513\)](#), [DayOfTheMonth \(445\)](#), [HourOfTheMonth \(461\)](#), [MinuteOfTheMonth \(481\)](#), [SecondOfTheMonth \(498\)](#), [MilliSecondOfTheMonth \(477\)](#)

**Listing:** ./datutex/ex41.pp

---

**Program** Example41 ;

*{ This program demonstrates the WeekOfTheMonth function }*

**Uses** SysUtils , DateUtils ;

**Var**

N : TDateTime ;

**Begin**

N:=Now;

WriteLn ( 'Week of the Month : ', WeekOfTheMonth(N));

WriteLn ( 'Day of the Month : ', DayOfTheMonth(N));

WriteLn ( 'Hour of the Month : ', HourOfTheMonth(N));

WriteLn ( 'Minute of the Month : ', MinuteOfTheMonth(N));

WriteLn ( 'Second of the Month : ', SecondOfTheMonth(N));

WriteLn ( 'MilliSecond of the Month : ',  
MilliSecondOfTheMonth(N));

**End.**

---

#### 9.4.142 WeekOfTheYear

**Synopsis:** Extract the week of the year (and optionally year) of a DateTime indication.

**Declaration:** function WeekOfTheYear(const AValue: TDateTime) : Word; Overload  
function WeekOfTheYear(const AValue: TDateTime;out AYear: Word) : Word  
; Overload

**Visibility:** default

**Description:** WeekOfTheYear extracts the week of the year from AValue and returns it, and optionally returns the year as well. It returns the same value as WeekOf ([512](#)).

**Remark:** Note that weeks are numbered from 1 using the ISO 8601 standard, and the day of the week as well. This means that the year may not be the same as the year part of the date, since the week may start in the previous year as the first week of the year is the week with at least 4 days in it.

See also: [WeekOf \(512\)](#), [MonthOfTheYear \(484\)](#), [DayOfTheYear \(446\)](#), [HourOfTheYear \(462\)](#), [MinuteOfTheYear \(482\)](#), [SecondOfTheYear \(499\)](#), [MilliSecondOfTheYear \(478\)](#)

**Listing:** ./datutex/ex40.pp

---

**Program** Example40 ;

*{ This program demonstrates the WeekOfTheYear function }*

**Uses** SysUtils , DateUtils ;

**Var**

N : TDateTime ;

**Begin**

N:=Now;

---

```

WriteLn ( 'Month of the year      : ', MonthOfTheYear(N));
WriteLn ( 'Week of the year       : ', WeekOfTheYear(N));
WriteLn ( 'Day of the year        : ', DayOfTheYear(N));
WriteLn ( 'Hour of the year       : ', HourOfTheYear(N));
WriteLn ( 'Minute of the year     : ', MinuteOfTheYear(N));
WriteLn ( 'Second of the year    : ', SecondOfTheYear(N));
WriteLn ( 'MilliSecond of the year : ',
          MilliSecondOfTheYear(N));
End.

```

---

### 9.4.143 WeeksBetween

**Synopsis:** Calculate the number of whole weeks between two `DateTime` values

**Declaration:** `function WeeksBetween(const ANow: TDateTime; const AThen: TDateTime) : Integer`

**Visibility:** default

**Description:** `WeeksBetween` returns the number of whole weeks between `ANow` and `AThen`. This means the fractional part of a Week is dropped.

See also: `YearsBetween` (525), `MonthsBetween` (484), `DaysBetween` (447), `HoursBetween` (462), `MinutesBetween` (482), `SecondsBetween` (499), `MillisecondsBetween` (478)

**Listing:** `./datutex/ex57.pp`

---

**Program** Example57;

*{ This program demonstrates the WeeksBetween function }*

**Uses** SysUtils, DateUtils;

**Procedure** Test(ANow, AThen : TDateTime);

**begin**

```

  Write ( 'Number of weeks between ');
  Write (DateToStr(AThen), ' and ', DateToStr(ANow));
  WriteLn ( ' : ', WeeksBetween(ANow, AThen));

```

**end;**

**Var**

```

  D1, D2 : TDateTime;

```

**Begin**

```

  D1 := Today;
  D2 := Today - 7;
  Test(D1, D2);
  D2 := Today - 8;
  Test(D1, D2);
  D2 := Today - 14;
  Test(D1, D2);
  D2 := Today - 35;
  Test(D1, D2);
  D2 := Today - 36;
  Test(D1, D2);
  D2 := Today - 17;

```

```
Test(D1,D2);
End.
```

---

### 9.4.144 WeeksInAYear

Synopsis: Return the number of weeks in a given year

Declaration: `function WeeksInAYear(const AYear: Word) : Word`

Visibility: default

Description: `WeeksInAYear` returns the number of weeks in the year `AYear`. The return value is either 52 or 53.

**Remark:** The first week of the year is determined according to the ISO 8601 standard: It is the first week that has at least 4 days in it, i.e. it includes a thursday.

See also: `WeeksInYear` ([515](#)), `DaysInYear` ([449](#)), `DaysInAYear` ([448](#)), `DaysInMonth` ([449](#)), `DaysInAMonth` ([447](#))

**Listing:** `./datutex/ex13.pp`

---

**Program** `Example13;`

*{ This program demonstrates the WeeksInAYear function }*

**Uses** `SysUtils, DateUtils;`

**Var**  
`Y : Word;`

**Begin**  
`For Y:=1992 to 2010 do`  
`Writeln(Y, ' has ', WeeksInAYear(Y), ' weeks. ');`  
**End.**

---

### 9.4.145 WeeksInYear

Synopsis: return the number of weeks in the year, given a date

Declaration: `function WeeksInYear(const AValue: TDateTime) : Word`

Visibility: default

Description: `WeeksInYear` returns the number of weeks in the year part of `AValue`. The return value is either 52 or 53.

**Remark:** The first week of the year is determined according to the ISO 8601 standard: It is the first week that has at least 4 days in it, i.e. it includes a thursday.

See also: `WeeksInAYear` ([515](#)), `DaysInYear` ([449](#)), `DaysInAYear` ([448](#)), `DaysInMonth` ([449](#)), `DaysInAMonth` ([447](#))

**Listing:** `./datutex/ex12.pp`

---

```

Program Example12;

{ This program demonstrates the WeeksInYear function }

Uses SysUtils, DateUtils;

Var
  Y : Word;

Begin
  For Y:=1992 to 2010 do
    WriteLn(Y, ' has ', WeeksInYear(EncodeDate(Y,2,1)), ' weeks. ');
End.

```

---

### 9.4.146 WeekSpan

**Synopsis:** Calculate the approximate number of weeks between two `DateTime` values.

**Declaration:** `function WeekSpan(const ANow: TDateTime; const AThen: TDateTime) : Double`

**Visibility:** default

**Description:** `WeekSpan` returns the number of weeks between `ANow` and `AThen`, including any fractional parts of a week.

See also: `YearSpan` ([526](#)), `MonthSpan` ([485](#)), `DaySpan` ([450](#)), `HourSpan` ([463](#)), `MinuteSpan` ([483](#)), `SecondSpan` ([500](#)), `MilliSecondSpan` ([479](#)), `WeeksBetween` ([514](#))

**Listing:** `./datutex/ex65.pp`

---

```

Program Example57;

{ This program demonstrates the WeekSpan function }

Uses SysUtils, DateUtils;

Procedure Test(ANow, AThen : TDateTime);

begin
  Write( 'Number of weeks between ');
  Write( DateToStr(AThen), ' and ', DateToStr(ANow));
  WriteLn( ' : ', WeekSpan(ANow, AThen));
end;

Var
  D1, D2 : TDateTime;

Begin
  D1:=Today;
  D2:=Today-7;
  Test(D1,D2);
  D2:=Today-8;
  Test(D1,D2);
  D2:=Today-14;
  Test(D1,D2);
  D2:=Today-35;
  Test(D1,D2);

```

```

D2:=Today-36;
Test(D1,D2);
D2:=Today-17;
Test(D1,D2);
End.

```

---

### 9.4.147 WithinPastDays

**Synopsis:** Check whether two datetimes are only a number of days apart

**Declaration:** `function WithinPastDays(const ANow: TDateTime; const AThen: TDateTime;  
const ADays: Integer) : Boolean`

**Visibility:** default

**Description:** `WithinPastDays` compares the timestamps `ANow` and `AThen` and returns `True` if the difference between them is at most `ADays` days apart, or `False` if they are further apart.

**Remark:** Since this function uses the `DaysBetween` (447) function to calculate the difference in days, this means that fractional days do not count, and the fractional part is simply dropped, so for two dates actually 2 and a half days apart, the result will also be `True`

See also: `WithinPastYears` (523), `WithinPastMonths` (520), `WithinPastWeeks` (522), `WithinPastHours` (518), `WithinPastMinutes` (520), `WithinPastSeconds` (521), `WithinPastMilliseconds` (519)

**Listing:** `./datutex/ex50.pp`

---

**Program** Example50;

*{ This program demonstrates the WithinPastDays function }*

**Uses** SysUtils, DateUtils;

**Procedure** Test(ANow, AThen : TDateTime; ADays : Integer);

**begin**

Write(DateTimeToStr(AThen), ' and ', DateTimeToStr(ANow));

Write(' are within ', ADays, ' days: ');

WriteLn(WithinPastDays(ANow, AThen, ADays));

**end;**

**Var**

D1, D2 : TDateTime;

**Begin**

D1:=Now;

D2:=Today-23/24;

Test(D1,D2,1);

D2:=Today-1;

Test(D1,D2,1);

D2:=Today-25/24;

Test(D1,D2,1);

D2:=Today-26/24;

Test(D1,D2,5);

D2:=Today-5.4;

Test(D1,D2,5);

D2:=Today-2.5;

Test(D1,D2,1);

```

    Test(D1,D2,2);
    Test(D1,D2,3);
End.

```

---

### 9.4.148 WithinPastHours

**Synopsis:** Check whether two datetimes are only a number of hours apart

**Declaration:** `function WithinPastHours(const ANow: TDateTime;const AThen: TDateTime;  
const AHours: Int64) : Boolean`

**Visibility:** default

**Description:** `WithinPastHours` compares the timestamps `ANow` and `AThen` and returns `True` if the difference between them is at most `AHours` hours apart, or `False` if they are further apart.

**Remark:** Since this function uses the `HoursBetween` (462) function to calculate the difference in Hours, this means that fractional hours do not count, and the fractional part is simply dropped, so for two dates actually 2 and a half hours apart, the result will also be `True`

See also: `WithinPastYears` (523), `WithinPastMonths` (520), `WithinPastWeeks` (522), `WithinPastDays` (517), `WithinPastMinutes` (520), `WithinPastSeconds` (521), `WithinPastMilliseconds` (519)

**Listing:** `./datutex/ex51.pp`

---

**Program** Example51 ;

*{ This program demonstrates the WithinPastHours function }*

**Uses** SysUtils , DateUtils ;

**Procedure** Test(ANow,AThen : TDateTime; AHours : Integer);

**begin**

**Write**( **DateTimeToStr**(AThen), ' and ', **DateTimeToStr**(ANow));

**Write**( ' are within ',AHours, ' hours: ' );

**WriteLn**( **WithinPastHours**(ANow,AThen,AHours));

**end**;

**Var**

    D1,D2 : TDateTime;

**Begin**

    D1:=**Now**;

    D2:=D1-(59\*OneMinute);

    Test(D1,D2,1);

    D2:=D1-(61\*OneMinute);

    Test(D1,D2,1);

    D2:=D1-(122\*OneMinute);

    Test(D1,D2,1);

    D2:=D1-(306\*OneMinute);

    Test(D1,D2,5);

    D2:=D1-(5.4\*OneHour);

    Test(D1,D2,5);

    D2:=D1-(2.5\*OneHour);

    Test(D1,D2,1);

    Test(D1,D2,2);

    Test(D1,D2,3);



---

End.

---

### 9.4.149 WithinPastMilliseconds

**Synopsis:** Check whether two datetimes are only a number of milliseconds apart

**Declaration:** `function WithinPastMilliseconds(const ANow: TDateTime;  
const AThen: TDateTime;  
const AMilliSeconds: Int64) : Boolean`

**Visibility:** default

**Description:** `WithinPastMilliseconds` compares the timestamps `ANow` and `AThen` and returns `True` if the difference between them is at most `AMilliSeconds` milliseconds apart, or `False` if they are further apart.

**Remark:** Since this function uses the `MillisecondsBetween` (478) function to calculate the difference in milliseconds, this means that fractional milliseconds do not count, and the fractional part is simply dropped, so for two dates actually 2 and a half milliseconds apart, the result will also be `True`

See also: `WithinPastYears` (523), `WithinPastMonths` (520), `WithinPastWeeks` (522), `WithinPastDays` (517), `WithinPastHours` (518), `WithinPastMinutes` (520), `WithinPastSeconds` (521)

**Listing:** `./datutex/ex54.pp`

---

**Program** Example54;

*{ This program demonstrates the WithinPastMilliseconds function }*

**Uses** SysUtils, DateUtils;

**Procedure** Test(ANow, AThen : TDateTime; AMilliSeconds : Integer);

**begin**  
  Write( **TimeToStr**(AThen), ' and ', **TimeToStr**(ANow));  
  Write( ' are within ', AMilliSeconds, ' milliseconds: ');  
  WriteLn( WithinPastMilliseconds(ANow, AThen, AMilliSeconds));  
**end**;

**Var**  
  D1, D2 : TDateTime;

**Begin**  
  D1:=**Now**;  
  D2:=D1-(0.9\*OneMilliSecond);  
  Test(D1,D2,1);  
  D2:=D1-(1.0\*OneMilliSecond);  
  Test(D1,D2,1);  
  D2:=D1-(1.1\*OneMilliSecond);  
  Test(D1,D2,1);  
  D2:=D1-(2.5\*OneMilliSecond);  
  Test(D1,D2,1);  
  Test(D1,D2,2);  
  Test(D1,D2,3);

**End.**

---

### 9.4.150 WithinPastMinutes

**Synopsis:** Check whether two datetimes are only a number of minutes apart

**Declaration:** `function WithinPastMinutes(const ANow: TDateTime; const AThen: TDateTime;  
const AMinutes: Int64) : Boolean`

**Visibility:** default

**Description:** `WithinPastMinutes` compares the timestamps `ANow` and `AThen` and returns `True` if the difference between them is at most `AMinutes` minutes apart, or `False` if they are further apart.

**Remark:** Since this function uses the `MinutesBetween` (482) function to calculate the difference in Minutes, this means that fractional minutes do not count, and the fractional part is simply dropped, so for two dates actually 2 and a half minutes apart, the result will also be `True`

See also: `WithinPastYears` (523), `WithinPastMonths` (520), `WithinPastWeeks` (522), `WithinPastDays` (517), `WithinPastHours` (518), `WithinPastSeconds` (521), `WithinPastMilliseconds` (519)

**Listing:** `./datutex/ex52.pp`

---

**Program** `Example52;`

*{ This program demonstrates the WithinPastMinutes function }*

**Uses** `SysUtils, DateUtils;`

**Procedure** `Test(ANow, AThen : TDateTime; AMinutes : Integer);`

**begin**

`Write(DateTimeToStr(AThen), ' and ', DateTimeToStr(ANow));`

`Write(' are within ', AMinutes, ' Minutes: ');`

`WriteLn(WithinPastMinutes(ANow, AThen, AMinutes));`

**end;**

**Var**

`D1, D2 : TDateTime;`

**Begin**

`D1:=Now;`

`D2:=D1-(59*OneSecond);`

`Test(D1, D2, 1);`

`D2:=D1-(61*OneSecond);`

`Test(D1, D2, 1);`

`D2:=D1-(122*OneSecond);`

`Test(D1, D2, 1);`

`D2:=D1-(306*OneSecond);`

`Test(D1, D2, 5);`

`D2:=D1-(5.4*OneMinute);`

`Test(D1, D2, 5);`

`D2:=D1-(2.5*OneMinute);`

`Test(D1, D2, 1);`

`Test(D1, D2, 2);`

`Test(D1, D2, 3);`

**End.**

---

### 9.4.151 WithinPastMonths

**Synopsis:** Check whether two datetimes are only a number of months apart

**Declaration:** `function WithinPastMonths(const ANow: TDateTime; const AThen: TDateTime;  
const AMonths: Integer) : Boolean`

Visibility: default

**Description:** `WithinPastMonths` compares the timestamps `ANow` and `AThen` and returns `True` if the difference between them is at most `AMonths` months apart, or `False` if they are further apart.

**Remark:** Since this function uses the `MonthsBetween` (484) function to calculate the difference in Months, this means that fractional months do not count, and the fractional part is simply dropped, so for two dates actually 2 and a half months apart, the result will also be `True`

See also: `WithinPastYears` (523), `WithinPastWeeks` (522), `WithinPastDays` (517), `WithinPastHours` (518), `WithinPastMinutes` (520), `WithinPastSeconds` (521), `WithinPastMilliseconds` (519)

**Listing:** `./datutex/ex48.pp`

---

**Program** Example48;

*{ This program demonstrates the WithinPastMonths function }*

**Uses** SysUtils, DateUtils;

**Procedure** Test(ANow, AThen : TDateTime; AMonths : Integer);

**begin**

**Write**(**DateToStr**(AThen), ' and ', **DateToStr**(ANow));

**Write**(' are within ', AMonths, ' months: ');

**WriteLn**(WithinPastMonths(ANow, AThen, AMonths));

**end**;

**Var**

    D1, D2 : TDateTime;

**Begin**

    D1 := Today;

    D2 := Today - 364;

    Test(D1, D2, 12);

    D2 := Today - 365;

    Test(D1, D2, 12);

    D2 := Today - 366;

    Test(D1, D2, 12);

    D2 := Today - 390;

    Test(D1, D2, 12);

    D2 := Today - 368;

    Test(D1, D2, 11);

    D2 := Today - 1000;

    Test(D1, D2, 31);

    Test(D1, D2, 32);

    Test(D1, D2, 33);

**End.**

---

### 9.4.152 WithinPastSeconds

Synopsis: Check whether two datetimes are only a number of seconds apart

**Declaration:** `function WithinPastSeconds(const ANow: TDateTime; const AThen: TDateTime;  
const ASeconds: Int64) : Boolean`

Visibility: default

**Description:** `WithinPastSeconds` compares the timestamps `ANow` and `AThen` and returns `True` if the difference between them is at most `ASeconds` seconds apart, or `False` if they are further apart.

**Remark:** Since this function uses the `SecondsBetween` (499) function to calculate the difference in seconds, this means that fractional seconds do not count, and the fractional part is simply dropped, so for two dates actually 2 and a half seconds apart, the result will also be `True`

See also: `WithinPastYears` (523), `WithinPastMonths` (520), `WithinPastWeeks` (522), `WithinPastDays` (517), `WithinPastHours` (518), `WithinPastMinutes` (520), `WithinPastMilliseconds` (519)

**Listing:** `./datutex/ex53.pp`

**Program** `Example53`;

*{ This program demonstrates the WithinPastSeconds function }*

**Uses** `SysUtils`, `DateUtils`;

**Procedure** `Test(ANow,AThen : TDateTime; ASeconds : Integer);`

**begin**

`Write(DateTimeToStr(AThen), ' and ', DateTimeToStr(ANow));`

`Write(' are within ',ASeconds,' seconds: ');`

`WriteLn(WithinPastSeconds(ANow,AThen,ASeconds));`

**end**;

**Var**

`D1,D2 : TDateTime;`

**Begin**

`D1:=Now;`

`D2:=D1-(999*OneMilliSecond);`

`Test(D1,D2,1);`

`D2:=D1-(1001*OneMilliSecond);`

`Test(D1,D2,1);`

`D2:=D1-(2001*OneMilliSecond);`

`Test(D1,D2,1);`

`D2:=D1-(5001*OneMilliSecond);`

`Test(D1,D2,5);`

`D2:=D1-(5.4*OneSecond);`

`Test(D1,D2,5);`

`D2:=D1-(2.5*OneSecond);`

`Test(D1,D2,1);`

`Test(D1,D2,2);`

`Test(D1,D2,3);`

**End.**

### 9.4.153 WithinPastWeeks

**Synopsis:** Check whether two datetimes are only a number of weeks apart

**Declaration:** `function WithinPastWeeks(const ANow: TDateTime;const AThen: TDateTime;  
const AWeeks: Integer) : Boolean`

Visibility: default

**Description:** `WithinPastWeeks` compares the timestamps `ANow` and `AThen` and returns `True` if the difference between them is at most `AWeeks` weeks apart, or `False` if they are further apart.

**Remark:** Since this function uses the `WeeksBetween` (514) function to calculate the difference in Weeks, this means that fractional Weeks do not count, and the fractional part is simply dropped, so for two dates actually 2 and a half weeks apart, the result will also be `True`

See also: `WithinPastYears` (523), `WithinPastMonths` (520), `WithinPastDays` (517), `WithinPastHours` (518), `WithinPastMinutes` (520), `WithinPastSeconds` (521), `WithinPastMilliseconds` (519)

**Listing:** `./datutex/ex49.pp`

---

**Program** `Example49`;

*{ This program demonstrates the WithinPastWeeks function }*

**Uses** `SysUtils`, `DateUtils`;

**Procedure** `Test(ANow, AThen : TDateTime; AWeeks : Integer);`

```
begin
  Write( DateToStr(AThen), ' and ', DateToStr(ANow));
  Write( ' are within ', AWeeks, ' weeks: ');
  WriteLn( WithinPastWeeks(ANow, AThen, AWeeks));
end;
```

**Var**  
     `D1, D2 : TDateTime;`

```
Begin
  D1:=Today;
  D2:=Today-7;
  Test(D1,D2,1);
  D2:=Today-8;
  Test(D1,D2,1);
  D2:=Today-14;
  Test(D1,D2,1);
  D2:=Today-35;
  Test(D1,D2,5);
  D2:=Today-36;
  Test(D1,D2,5);
  D2:=Today-17;
  Test(D1,D2,1);
  Test(D1,D2,2);
  Test(D1,D2,3);
```

**End.**

---

### 9.4.154 WithinPastYears

**Synopsis:** Check whether two datetimes are only a number of years apart

**Declaration:** `function WithinPastYears(const ANow: TDateTime; const AThen: TDateTime; const AYears: Integer) : Boolean`

**Visibility:** `default`

**Description:** `WithinPastYears` compares the timestamps `ANow` and `AThen` and returns `True` if the difference between them is at most `AYears` years apart, or `False` if they are further apart.

**Remark:** Since this function uses the `YearsBetween` (525) function to calculate the difference in years, this means that fractional years do not count, and the fractional part is simply dropped, so for two dates actually 2 and a half years apart, the result will also be `True`

See also: `WithinPastMonths` (520), `WithinPastWeeks` (522), `WithinPastDays` (517), `WithinPastHours` (518), `WithinPastMinutes` (520), `WithinPastSeconds` (521), `WithinPastMilliseconds` (519)

**Listing:** ./datutex/ex47.pp

---

**Program** Example47;

*{ This program demonstrates the WithinPastYears function }*

**Uses** SysUtils, DateUtils;

**Procedure** Test(ANow, AThen : TDateTime; AYears : Integer);

**begin**

**Write**(**DateToStr**(AThen), ' and ', **DateToStr**(ANow));

**Write**(' are within ', AYears, ' years: ');

**WriteLn**(**WithinPastYears**(ANow, AThen, AYears));

**end**;

**Var**

    D1, D2 : TDateTime;

**Begin**

    D1 := Today;

    D2 := Today - 364;

    Test(D1, D2, 1);

    D2 := Today - 365;

    Test(D1, D2, 1);

    D2 := Today - 366;

    Test(D1, D2, 1);

    D2 := Today - 390;

    Test(D1, D2, 1);

    D2 := Today - 368;

    Test(D1, D2, 1);

    D2 := Today - 1000;

    Test(D1, D2, 1);

    Test(D1, D2, 2);

    Test(D1, D2, 3);

**End.**

---

### 9.4.155 YearOf

**Synopsis:** Extract the year from a given date.

**Declaration:** `function YearOf(const AValue: TDateTime) : Word`

**Visibility:** default

**Description:** `YearOf` returns the year part of the `AValue` date/time indication. It is a number between 1 and 9999.

See also: `MonthOf` (484), `DayOf` (445), `WeekOf` (512), `HourOf` (460), `MinuteOf` (480), `SecondOf` (497), `MilliSecondOf` (476)

**Listing:** ./datutex/ex23.pp

**Program** Example23;

*{ This program demonstrates the YearOf function }*

**Uses** SysUtils, DateUtils;

**Var**

D : TDateTime;

**Begin**

D:=Now;

WriteLn('Year : ', YearOf(D));

WriteLn('Month : ', MonthOf(D));

WriteLn('Day : ', DayOf(D));

WriteLn('Week : ', WeekOf(D));

WriteLn('Hour : ', HourOf(D));

WriteLn('Minute : ', MinuteOf(D));

WriteLn('Second : ', SecondOf(D));

WriteLn('MilliSecond : ', MilliSecondOf(D));

**End.**

### 9.4.156 YearsBetween

**Synopsis:** Calculate the number of whole years between two DateTime values

**Declaration:** function YearsBetween(const ANow: TDateTime; const AThen: TDateTime)  
: Integer

**Visibility:** default

**Description:** YearsBetween returns the number of whole years between ANow and AThen. This number is an approximation, based on an average number of days of 365.25 per year (average over 4 years). This means the fractional part of a year is dropped.

See also: MonthsBetween ([484](#)), WeeksBetween ([514](#)), DaysBetween ([447](#)), HoursBetween ([462](#)), MinutesBetween ([482](#)), SecondsBetween ([499](#)), MilliSecondsBetween ([478](#)), YearSpan ([526](#))

**Listing:** ./datutex/ex55.pp

**Program** Example55;

*{ This program demonstrates the YearsBetween function }*

**Uses** SysUtils, DateUtils;

**Procedure** Test(ANow, AThen : TDateTime);

**begin**

Write('Number of years between ');

Write(DateToStr(AThen), ' and ', DateToStr(ANow));

WriteLn(' : ', YearsBetween(ANow, AThen));

**end;**

**Var**

D1, D2 : TDateTime;

**Begin**

```

D1:=Today;
D2:=Today-364;
Test(D1,D2);
D2:=Today-365;
Test(D1,D2);
D2:=Today-366;
Test(D1,D2);
D2:=Today-390;
Test(D1,D2);
D2:=Today-368;
Test(D1,D2);
D2:=Today-1000;
Test(D1,D2);

```

**End.****9.4.157 YearSpan**

**Synopsis:** Calculate the approximate number of years between two DateTime values.

**Declaration:** `function YearSpan(const ANow: TDateTime;const AThen: TDateTime) : Double`

**Visibility:** default

**Description:** YearSpan returns the number of years between ANow and AThen, including any fractional parts of a year. This number is an approximation, based on an average number of days of 365.25 per year (average over 4 years).

See also: MonthSpan ([485](#)), WeekSpan ([516](#)), DaySpan ([450](#)), HourSpan ([463](#)), MinuteSpan ([483](#)), SecondSpan ([500](#)), MilliSecondSpan ([479](#)), YearsBetween ([525](#))

**Listing:** ./datutex/ex63.pp

**Program** Example63;

*{ This program demonstrates the YearSpan function }*

**Uses** SysUtils, DateUtils;

**Procedure** Test(ANow, AThen : TDateTime);

**begin**

```

Write('Number of years between ');
Write(DateToStr(AThen), ' and ', DateToStr(ANow));
WriteLn(' : ', YearSpan(ANow, AThen));
end;

```

**Var**

```

D1, D2 : TDateTime;

```

**Begin**

```

D1:=Today;
D2:=Today-364;
Test(D1,D2);
D2:=Today-365;
Test(D1,D2);
D2:=Today-366;

```



---

```

Test(D1,D2);
D2:=Today-390;
Test(D1,D2);
D2:=Today-368;
Test(D1,D2);
D2:=Today-1000;
Test(D1,D2);
End.

```

---

### 9.4.158 Yesterday

Synopsis: Return the previous day.

Declaration: `function Yesterday : TDateTime`

Visibility: default

Description: `Yesterday` returns yesterday's date. Yesterday is determined from the system clock, i.e. it is `Today` (506) -1.

See also: `Today` (506), `Tomorrow` (506)

**Listing:** `./datutex/ex18.pp`

---

**Program** Example18;

*{ This program demonstrates the Yesterday function }*

**Uses** SysUtils, DateUtils;

**Begin**

```

  WriteLn(FormatDateTime('"Today is " dd mmm yyyy ',Today));
  WriteLn(FormatDateTime('"Yesterday was " dd mmm yyyy ',Yesterday));
End.

```

---

## Chapter 10

# Reference for unit 'Dos'

### 10.1 Used units

Table 10.1: Used units by unit 'Dos'

Name	Page
baseunix	<a href="#">528</a>

### 10.2 Overview

The DOS unit gives access to some operating system calls related to files, the file system, date and time. Except for the PalmOS target, this unit is available to all supported platforms.

The unit was first written for dos by Florian Klaempfl. It was ported to linux by Mark May and enhanced by Michael Van Canneyt. The Amiga version was ported by Nils Sjöholm.

Under non-DOS systems, some of the functionality is lost, as it is either impossible or meaningless to implement it. Other than that, the functionality is the same for all operating systems.

Because the DOS unit is a Turbo Pascal compatibility unit, it is no longer actively developed: the interface is frozen and it is maintained only for the purpose of porting Turbo Pascal programs. For new development, it is recommended to use the sysutils ([1426](#)) unit instead.

### 10.3 System information

Functions for retrieving and setting general system information such as date and time.

### 10.4 Process handling

Functions to handle process information and starting new processes.

Table 10.2:

Name	Description
DosVersion (537)	Get OS version
GetCBreak (543)	Get setting of control-break handling flag
GetDate (543)	Get system date
GetIntVec (546)	Get interrupt vector status
GetTime (547)	Get system time
GetVerify (548)	Get verify flag
Intr (548)	Execute an interrupt
Keep (548)	Keep process in memory and exit
MSDos (549)	Execute MS-dos function call
PackTime (549)	Pack time for file time
SetCBreak (550)	Set control-break handling flag
SetDate (550)	Set system date
SetIntVec (551)	Set interrupt vectors
SetTime (552)	Set system time
SetVerify (552)	Set verify flag
SwapVectors (552)	Swap interrupt vectors
UnPackTime (553)	Unpack file time

Table 10.3:

Name	Description
DosExitCode (537)	Exit code of last executed program
EnvCount (538)	Return number of environment variables
EnvStr (539)	Return environment string pair
Exec (539)	Execute program
GetEnv (544)	Return specified environment string

## 10.5 Directory and disk handling

Routines to handle disk information.

Table 10.4:

Name	Description
AddDisk (535)	Add disk to list of disks (UNIX only)
DiskFree (535)	Return size of free disk space
DiskSize (536)	Return total disk size

## 10.6 File handling

Routines to handle files on disk.

Table 10.5:

Name	Description
FExpand (539)	Expand filename to full path
FindClose (540)	Close finfirst/findnext session
FindFirst (540)	Start find of file
FindNext (541)	Find next file
FSearch (541)	Search for file in a path
FSplit (542)	Split filename in parts
GetFAttr (544)	Return file attributes
GetFTime (545)	Return file time
GetLongName (546)	Convert short filename to long filename (DOS only)
GetShortName (547)	Convert long filename to short filename (DOS only)
SetFAttr (550)	Set file attributes
SetFTime (551)	Set file time

## 10.7 File open mode constants.

These constants are used in the `Mode` field of the `TextRec` record. Gives information on the file-mode of the text I/O. For their definitions consult the following table:

Table 10.6: Possible mode constants

Constant	Description	Value
<code>fmclosed</code>	File is closed	<code>\$D7B0</code>
<code>fminput</code>	File is read only	<code>\$D7B1</code>
<code>fmoutput</code>	File is write only	<code>\$D7B2</code>
<code>fminout</code>	File is read and write	<code>\$D7B3</code>

## 10.8 File attributes

The File Attribute constants are used in `FindFirst` (540), `FindNext` (541) to determine what type of special file to search for in addition to normal files. These flags are also used in the `SetFAttr` (550) and `GetFAttr` (544) routines to set and retrieve attributes of files. For their definitions consult `fileattributes` (530).

Table 10.7: Possible file attributes

Constant	Description	Value
<code>readonly</code>	Read-Only file attribute	<code>\$01</code>
<code>hidden</code>	Hidden file attribute	<code>\$02</code>
<code>sysfile</code>	System file attribute	<code>\$04</code>
<code>volumeid</code>	Volumd ID file attribute	<code>\$08</code>
<code>directory</code>	Directory file attribute	<code>\$10</code>
<code>archive</code>	Archive file attribute	<code>\$20</code>
<code>anyfile</code>	Match any file attribute	<code>\$3F</code>

## 10.9 Constants, types and variables

### 10.9.1 Constants

`anyfile = $3F`

Match any file attribute

`archive = $20`

Archive file attribute

`directory = $10`

Directory file attribute

`fauxiliary = $0010`

CPU auxiliary flag. Not used.

`fcarry = $0001`

CPU carry flag. Not used.

`FileNameLen = 255`

Maximum length of a filename

`filerecnamelength = 255`

Maximum length of FileName part in FileRec ([533](#))

`fmclosed = $D7B0`

File is closed

`fminout = $D7B3`

File is read and write

`fminput = $D7B1`

File is read only

`fmoutput = $D7B2`

File is write only

`foverflow = $0800`

CPU overflow flag. Not used.

`fparity = $0004`

CPU parity flag. Not used.

`fsign = $0080`

CPU sign flag. Not used.

`fzero = $0040`

CPU zero flag. Not used.

`hidden = $02`

Hidden file attribute

`readonly = $01`

Read-Only file attribute

`sysfile = $04`

System file attribute

`TextRecBufSize = 256`

Size of default buffer in TextRec ([534](#))

`TextRecNameLength = 256`

Maximum length of filename in TextRec ([534](#))

`volumeid = $08`

Volume ID file attribute

## 10.9.2 Types

`ComStr =`

Command-line string type

`DateTime = packed record`

`Year : Word;`

`Month : Word;`

`Day : Word;`

`Hour : Word;`

`Min : Word;`

`Sec : Word;`

`end`

The `DateTime` type is used in `PackTime` (549) and `UnPackTime` (553) for setting/reading file times with `GetFTime` (545) and `SetFTime` (551).

`DirStr =`

Full directory string type.

`ExtStr =`

Filename extension string type.

```
FileRec = packed record
  Handle : THandle;
  Mode : LongInt;
  RecSize : SizeInt;
  _private : Array[1..3*SizeOf(SizeInt)+5*SizeOf(pointer)] of Byte;
  UserData : Array[1..32] of Byte;
  name : Array[0..filerecnamelength] of Char;
end
```

`FileRec` is used for internal representation of typed and untyped files.

`NameStr =`

Fill filename string type.

`PathStr =`

Full File path string type.

```
Registers = packed record
end
```

This structure is only defined on a i386 compatible 32-bit platform, and is not used anywhere: it is defined for Turbo Pascal backwards compatibility only.

```
SearchRec = packed record
  SearchPos : TOff;
  SearchNum : LongInt;
  DirPtr : Pointer;
  SearchType : Byte;
  SearchAttr : Byte;
  Mode : Word;
  Fill : Array[1..1] of Byte;
  Attr : Byte;
  Time : LongInt;
  Size : LongInt;
  Reserved : Word;
  Name : String;
  SearchSpec : String;
  NamePos : Word;
end
```

`SearchRec` is filled by the `FindFirst` (540) call and can be used in subsequent `FindNext` (541) calls to search for files. The structure of this record depends on the platform. Only the following fields are present on all platforms:

**Attr** File attributes.

**Time** File modification time.

**Size** File size

**Name** File name (name part only, no path)

**Mode** File access mode (linux only)

`TextBuf = Array[0..TextRecBufSize-1] of Char`

Type for default buffer in `TextRec` (534)

```
TextRec = packed record
  Handle : THandle;
  Mode : LongInt;
  bufsize : SizeInt;
  _private : SizeInt;
  bufpos : SizeInt;
  bufend : SizeInt;
  bufptr : ^TextBuf;
  openfunc : pointer;
  inoutfunc : pointer;
  flushfunc : pointer;
  closefunc : pointer;
  UserData : Array[1..32] of Byte;
  name : Array[0..textrecnamelength-1] of Char;
  LineEnd : TLineEndStr;
  buffer : TextBuf;
end
```

`TextRec` describes the internal working of a Text file.

Remark that this is not binary compatible with the Turbo Pascal definition of `TextRec`, since the sizes of the different fields are different.

`TLineEndStr =`

`TLineEndStr` is used in the `TextRec` (534) record to indicate the end-of-line sequence for a text file.

### 10.9.3 Variables

`DosError : Integer`

The `DosError` variable is used by the procedures in the `dos` unit to report errors. It can have the following values :

Other values are possible, but are not documented.



Table 10.8: Dos error codes

Value	Meaning
2	File not found.
3	Path not found.
5	Access denied.
6	Invalid handle.
8	Not enough memory.
10	Invalid environment.
11	Invalid format.
18	No more files.

## 10.10 Procedures and functions

### 10.10.1 AddDisk

**Synopsis:** Add disk definition to list if drives (Unix only)

**Declaration:** `function AddDisk(const path: String) : Byte`

**Visibility:** default

**Description:** `AddDisk` adds a filename `S` to the internal list of disks. It is implemented for systems which do not use DOS type drive letters. This list is used to determine which disks to use in the `DiskFree` (535) and `DiskSize` (536) calls. The `DiskFree` (535) and `DiskSize` (536) functions need a file on the specified drive, since this is required for the `statfs` system call. The names are added sequentially. The dos initialization code presets the first three disks to:

- `'.'` for the current drive,
- `'/fd0/.'` for the first floppy-drive (linux only).
- `'/fd1/.'` for the second floppy-drive (linux only).
- `''` for the first hard disk.

The first call to `AddDisk` will therefore add a name for the second harddisk, The second call for the third drive, and so on until 23 drives have been added (corresponding to drives `'D:'` to `'Z:'`)

**Errors:** None

**See also:** `DiskFree` (535), `DiskSize` (536)

### 10.10.2 DiskFree

**Synopsis:** Get free size on Disk.

**Declaration:** `function DiskFree(drive: Byte) : Int64`

**Visibility:** default

**Description:** `DiskFree` returns the number of free bytes on a disk. The parameter `Drive` indicates which disk should be checked. This parameter is 1 for floppy `a:`, 2 for floppy `b:`, etc. A value of 0 returns the free space on the current drive.

**Remark:** For Unices: The `diskfree` and `disksize` functions need a file on the specified drive, since this is required for the `statfs` system call. These filenames are set in the initialization of the dos unit, and have been preset to :

- `'.'` for the current drive,
- `'/fd0/.'` for the first floppy-drive (linux only).
- `'/fd1/.'` for the second floppy-drive (linux only).
- `''` for the first hard disk.

There is room for 1-26 drives. You can add a drive with the [AddDisk \(535\)](#) procedure. These settings can be coded in `dos.pp`, in the initialization part.

Errors: -1 when a failure occurs, or an invalid drive number is given.

See also: [DiskSize \(536\)](#), [AddDisk \(535\)](#)

**Listing:** `./dosex/ex6.pp`

---

```

Program Example6;
uses Dos;

{ Program to demonstrate the DiskSize and DiskFree function. }

begin
  WriteLn('This partition size has ', DiskSize(0), ' bytes');
  WriteLn('Currently ', DiskFree(0), ' bytes are free');
end.

```

---

### 10.10.3 DiskSize

Synopsis: Get total size of disk.

Declaration: `function DiskSize(drive: Byte) : Int64`

Visibility: default

Description: `DiskSize` returns the total size (in bytes) of a disk. The parameter `Drive` indicates which disk should be checked. This parameter is 1 for floppy a:, 2 for floppy b:, etc. A value of 0 returns the size of the current drive.

**Remark:** For unix only: The `diskfree` and `disksize` functions need a file on the specified drive, since this is required for the `statfs` system call. These filenames are set in the initialization of the `dos` unit, and have been preset to :

- `'.'` for the current drive,
- `'/fd0/.'` for the first floppy-drive (linux only).
- `'/fd1/.'` for the second floppy-drive (linux only).
- `''` for the first hard disk.

There is room for 1-26 drives. You can add a drive with the [AddDisk \(535\)](#) procedure. These settings can be coded in `dos.pp`, in the initialization part.

For an example, see [DiskFree \(535\)](#).

Errors: -1 when a failure occurs, or an invalid drive number is given.

See also: [DiskFree \(535\)](#), [AddDisk \(535\)](#)

### 10.10.4 DosExitCode

Synopsis: Exit code of last executed program.

Declaration: `function DosExitCode : Word`

Visibility: default

Description: `DosExitCode` contains (in the low byte) the exit-code of a program executed with the `Exec` call.

Errors: None.

See also: `Exec` ([539](#))

**Listing:** `./dosex/ex5.pp`

---

```

Program Example5;
uses Dos;

{ Program to demonstrate the Exec and DosExitCode function. }

begin
{$IFDEF Unix}
  WriteLn('Executing /bin/ls -la');
  Exec('/bin/ls', '-la');
{$ELSE}
  WriteLn('Executing Dir');
  Exec(GetEnv('COMSPEC'), '/C dir');
{$ENDIF}
  WriteLn('Program returned with ExitCode ', Lo(DosExitCode));
end.

```

---

### 10.10.5 DosVersion

Synopsis: Current OS version

Declaration: `function DosVersion : Word`

Visibility: default

Description: `DosVersion` returns the operating system or kernel version. The low byte contains the major version number, while the high byte contains the minor version number.

**Remark:** On systems where versions consists of more then two numbers, only the first two numbers will be returned. For example Linux version 2.1.76 will give you `DosVersion` 2.1. Some operating systems, such as FreeBSD, do not have system calls to return the kernel version, in that case a value of 0 will be returned.

Errors: None.

**Listing:** `./dosex/ex1.pp`

---

```

Program Example1;
uses Dos;

{ Program to demonstrate the DosVersion function. }

var
  OS      : string[32];

```

---

---

```

    Version : word;
begin
{$IFDEF LINUX}
    OS:= 'Linux';
{$ENDIF}
{$IFDEF FreeBSD}
    OS:= 'FreeBSD';
{$endif}
{$IFDEF NetBSD}
    OS:= 'NetBSD';
{$endif}
{$IFDEF Solaris}
    OS:= 'Solaris';
{$endif}
{$IFDEF QNX}
    OS:= 'QNX';
{$endif}

{$IFDEF DOS}
    OS:= 'Dos';
{$ENDIF}
    Version:=DosVersion;
    WriteLn('Current ',OS,' version is ',Lo(Version),'. ',Hi(Version));
end.

```

---

### 10.10.6 DTTToUnixDate

Synopsis: Convert a DateTime to unix timestamp

Declaration: `function DTTToUnixDate(DT: DateTime) : LongInt`

Visibility: default

Description: `DTTToUnixDate` converts the `DateTime` value in `DT` to a unix timestamp. It is an internal function, implemented on Unix platforms, and should not be used.

Errors: None.

See also: `UnixDateToDT` ([553](#)), `PackTime` ([549](#)), `UnpackTime` ([553](#)), `GetTime` ([547](#)), `SetTime` ([552](#))

### 10.10.7 EnvCount

Synopsis: Return the number of environment variables

Declaration: `function EnvCount : LongInt`

Visibility: default

Description: `EnvCount` returns the number of environment variables.

Errors: None.

See also: `EnvStr` ([539](#)), `GetEnv` ([544](#))

### 10.10.8 EnvStr

Synopsis: Return environment variable by index

Declaration: `function EnvStr(Index: LongInt) : String`

Visibility: default

Description: `EnvStr` returns the `Index`-th Name=Value pair from the list of environment variables. The index of the first pair is zero.

Errors: The length is limited to 255 characters.

See also: `EnvCount` ([538](#)), `GetEnv` ([544](#))

**Listing:** `./dosex/ex13.pp`

---

**Program** `Example13;`  
**uses** `Dos;`

*{ Program to demonstrate the EnvCount and EnvStr function. }*

```
var
  i : Longint;
begin
  WriteLn('Current Environment is:');
  for i:=1 to EnvCount do
    WriteLn(EnvStr(i));
end.
```

---

### 10.10.9 Exec

Synopsis: Execute another program, and wait for it to finish.

Declaration: `procedure Exec(const path: PathStr; const comline: ComStr)`

Visibility: default

Description: `Exec` executes the program in `Path`, with the options given by `ComLine`. The program name should *not* appear again in `ComLine`, it is specified in `Path`. `Comline` contains only the parameters that are passed to the program.

After the program has terminated, the procedure returns. The Exit value of the program can be consulted with the `DosExitCode` function.

For an example, see `DosExitCode` ([537](#))

Errors: Errors are reported in `DosError`.

See also: `DosExitCode` ([537](#))

### 10.10.10 FExpand

Synopsis: Expand a relative path to an absolute path

Declaration: `function FExpand(const path: PathStr) : PathStr`

Visibility: default

**Description:** `FExpand` takes its argument and expands it to a complete filename, i.e. a filename starting from the root directory of the current drive, prepended with the drive-letter or volume name (when supported).

**Remark:** On case sensitive file systems (such as unix and linux), the resulting name is left as it is, otherwise it is converted to uppercase.

Errors: `FSplit` (542)

**Listing:** `./dosex/ex11.pp`

---

```

Program Example11;
uses Dos;

{ Program to demonstrate the FExpand function. }

begin
  WriteLn('Expanded Name of this program is ',FExpand(ParamStr(0)));
end.
```

---

### 10.10.11 FindClose

**Synopsis:** Dispose resources allocated by a `FindFirst` (540)/`FindNext` (541) sequence.

**Declaration:** `procedure FindClose(var f: SearchRec)`

**Visibility:** default

**Description:** `FindClose` frees any resources associated with the search record `F`.

This call is needed to free any internal resources allocated by the `FindFirst` (540) or `FindNext` (541) calls.

The unix implementation of the dos unit therefore keeps a table of open directories, and when the table is full, closes one of the directories, and reopens another. This system is adequate but slow if you use a lot of `searchrecs`.

So, to speed up the `findfirst/findnext` system, the `FindClose` call was implemented. When you don't need a `searchrec` any more, you can tell this to the dos unit by issuing a `FindClose` call. The directory which is kept open for this `searchrec` is then closed, and the table slot freed.

**Remark:** It is recommended to use the linux call `Glob` when looking for files on linux.

Errors: Errors are reported in `DosError`.

See also: `FindFirst` (540), `FindNext` (541)

### 10.10.12 FindFirst

**Synopsis:** Start search for one or more files.

**Declaration:** `procedure FindFirst(const path: PathStr;attr: Word;var f: SearchRec)`

**Visibility:** default

**Description:** `FindFirst` searches the file specified in `Path`. Normal files, as well as all special files which have the attributes specified in `Attr` will be returned.

It returns a `SearchRec` record for further searching in `F`. `Path` can contain the wildcard characters `?` (matches any single character) and `*` (matches 0 ore more arbitrary characters). In this case

`FindFirst` will return the first file which matches the specified criteria. If `DosError` is different from zero, no file(s) matching the criteria was(were) found.

**Remark:** On os/2, you cannot issue two different `FindFirst` calls. That is, you must close any previous search operation with `FindClose` (540) before starting a new one. Failure to do so will end in a Run-Time Error 6 (Invalid file handle)

Errors: Errors are reported in `DosError`.

See also: `FindNext` (541), `FindClose` (540)

**Listing:** ./dosex/ex7.pp

---

```

Program Example7;
uses Dos;

{ Program to demonstrate the FindFirst and FindNext function. }

var
  Dir : SearchRec;
begin
  FindFirst( '*.*', archive, Dir);
  WriteLn( 'FileName'+Space(32), 'FileSize':9);
  while (DosError=0) do
    begin
      WriteLn( Dir.Name+Space(40-Length(Dir.Name)), Dir.Size:9);
      FindNext(Dir);
    end;
  FindClose(Dir);
end.
```

---

### 10.10.13 FindNext

Synopsis: Find next matching file after `FindFirst` (540)

Declaration: `procedure FindNext (var f: SearchRec)`

Visibility: default

Description: `FindNext` takes as an argument a `SearchRec` from a previous `FindNext` call, or a `FindFirst` call, and tries to find another file which matches the criteria, specified in the `FindFirst` call. If `DosError` is different from zero, no more files matching the criteria were found.

For an example, see `FindFirst` (540).

Errors: `DosError` is used to report errors.

See also: `FindFirst` (540), `FindClose` (540)

### 10.10.14 FSearch

Synopsis: Search a file in searchpath

Declaration: `function FSearch (path: PathStr; dirlist: String) : PathStr`

Visibility: default

**Description:** `FSearch` searches the file `Path` in all directories listed in `DirList`. The full name of the found file is returned. `DirList` must be a list of directories, separated by semi-colons. When no file is found, an empty string is returned.

**Remark:** On unix systems, `DirList` can also be separated by colons, as is customary on those environments.

Errors: None.

See also: `FExpand` ([539](#))

**Listing:** `./dosex/ex10.pp`

---

```

program Example10;

uses Dos;

{ Program to demonstrate the FSearch function. }

var s:pathstr;

begin
  s:=FSearch(ParamStr(1),GetEnv('PATH'));
  if s='' then
    WriteLn(ParamStr(1),' not Found in PATH')
  else
    WriteLn(ParamStr(1),' Found in PATH at ',s);
end.

```

---

### 10.10.15 FSplit

**Synopsis:** Split a full-path filename in parts.

**Declaration:** `procedure FSplit(path: PathStr; var dir: DirStr; var name: NameStr; var ext: ExtStr)`

Visibility: default

**Description:** `FSplit` splits a full file name into 3 parts : A Path, a Name and an extension (in ext.) The extension is taken to be all letters after the *last* dot (.). For dos, however, an exception is made when `LFNSupport=False`, then the extension is defined as all characters after the *first* dot.

Errors: None.

See also: `FSearch` ([541](#))

**Listing:** `./dosex/ex12.pp`

---

```

program Example12;

uses Dos;

{ Program to demonstrate the FSplit function. }

var dir:dirstr;
    name:namestr;
    ext:extstr;

begin

```



---

```

FSplit(ParamStr(1),dir,name,ext);
WriteLn('Splitted ',ParamStr(1),' in:');
WriteLn('Path      : ',dir);
WriteLn('Name       : ',name);
WriteLn('Extension : ',ext);
end.

```

---

### 10.10.16 GetCBreak

Synopsis: Get control-Break flag

Declaration: `procedure GetCBreak(var breakvalue: Boolean)`

Visibility: default

Description: `GetCBreak` gets the status of CTRL-Break checking under dos and Amiga. When `BreakValue` is `false`, then dos only checks for the CTRL-Break key-press when I/O is performed. When it is set to `True`, then a check is done at every system call.

**Remark:** Under non-dos and non-Amiga operating systems, `BreakValue` always returns `True`.

Errors: None

See also: `SetCBreak` ([550](#))

### 10.10.17 GetDate

Synopsis: Get the current date

Declaration: `procedure GetDate(var year: Word;var month: Word;var mday: Word;  
var wday: Word)`

Visibility: default

Description: `GetDate` returns the system's date. `Year` is a number in the range 1980..2099. `mday` is the day of the month, `wday` is the day of the week, starting with Sunday as day 0.

Errors: None.

See also: `GetTime` ([547](#)), `SetDate` ([550](#))

**Listing:** `./dosex/ex2.pp`

---

**Program** Example2;

**uses** Dos;

*{ Program to demonstrate the GetDate function. }*

**const**

DayStr:array[0..6] of string[3]=('Sun','Mon','Tue','Wed','Thu','Fri','Sat');

MonthStr:array[1..12] of string[3]=('Jan','Feb','Mar','Apr','May','Jun',  
'Jul','Aug','Sep','Oct','Nov','Dec');

**var**

Year,Month,Day,WDay : word;

**begin**

GetDate(Year,Month,Day,WDay);

**WriteLn**('Current date');

**WriteLn**(DayStr[WDay],', ',',Day,', ',MonthStr[Month],', ',Year,', ');

**end.**

---

### 10.10.18 GetEnv

Synopsis: Get environment variable by name.

Declaration: `function GetEnv(envvar: String) : String`

Visibility: default

Description: `Getenv` returns the value of the environment variable `EnvVar`. When there is no environment variable `EnvVar` defined, an empty string is returned.

**Remark:** Under some operating systems (such as unix), case is important when looking for `EnvVar`.

Errors: None.

See also: `EnvCount` (538), `EnvStr` (539)

**Listing:** `./dosex/ex14.pp`

---

```

Program Example14;
uses Dos;

{ Program to demonstrate the GetEnv function. }

begin
  WriteLn('Current PATH is ',GetEnv('PATH'));
end

```

---

### 10.10.19 GetFAttr

Synopsis: Get file attributes

Declaration: `procedure GetFAttr(var f;var attr: Word)`

Visibility: default

Description: `GetFAttr` returns the file attributes of the file-variable `f`. `F` can be a untyped or typed file, or of type `Text`. `f` must have been assigned, but not opened. The attributes can be examined with the following constants :

- `ReadOnly`
- `Hidden`
- `SysFile`
- `VolumeId`
- `Directory`
- `Archive`

Under linux, supported attributes are:

- `Directory`
- `ReadOnly` if the current process doesn't have access to the file.
- `Hidden` for files whose name starts with a dot ( `'.'` ).

Errors: Errors are reported in `DosError`

See also: `SetFAttr` (550)

**Listing:** ./dosex/ex8.pp

---

```

Program Example8;
uses Dos;

{ Program to demonstrate the GetFAttr function. }

var
  Attr : Word;
  f     : File;
begin
  Assign(f, ParamStr(1));
  GetFAttr(f, Attr);
  WriteLn('File ', ParamStr(1), ' has attribute ', Attr);
  if (Attr and archive) <> 0 then WriteLn(' - Archive ');
  if (Attr and directory) <> 0 then WriteLn(' - Directory ');
  if (Attr and readonly) <> 0 then WriteLn(' - Read-Only ');
  if (Attr and sysfile) <> 0 then WriteLn(' - System ');
  if (Attr and hidden) <> 0 then WriteLn(' - Hidden ');
end.

```

---

**10.10.20 GetFTime**

Synopsis: Get file last modification time.

Declaration: `procedure GetFTime(var f; var time: LongInt)`

Visibility: default

Description: GetFTime returns the modification time of a file. This time is encoded and must be decoded with UnPackTime. F must be a file type, which has been assigned, and opened.

Errors: Errors are reported in DosError

See also: SetFTime ([551](#)), PackTime ([549](#)), UnPackTime ([553](#))

**Listing:** ./dosex/ex9.pp

---

```

Program Example9;
uses Dos;

{ Program to demonstrate the GetFTime function. }

Function L0(w: word): string;
var
  s : string;
begin
  Str(w, s);
  if w < 10 then
    L0 := '0' + s
  else
    L0 := s;
end;

var
  f     : File;
  Time : Longint;
  DT    : DateTime;

```

---

---

```

begin
  if Paramcount>0 then
    Assign(f, ParamStr(1))
  else
    Assign(f, 'ex9.pp' );
  Reset(f);
  GetFTime(f, Time);
  Close(f);
  UnPackTime(Time, DT);
  Write ('File ', ParamStr(1), ' is last modified on ');
  WriteLn (L0(DT.Month), '-', L0(DT.Day), '-', DT.Year,
           ' at ', L0(DT.Hour), ': ', L0(DT.Min));
end.

```

---

### 10.10.21 GetIntVec

Synopsis: Get interrupt vector

Declaration: `procedure GetIntVec(intno: Byte; var vector: pointer)`

Visibility: default

Description: `GetIntVec` returns the address of interrupt vector `IntNo`.

**Remark:** This call does nothing, it is present for compatibility only. Modern systems do not allow low level access to the hardware.

Errors: None.

See also: `SetIntVec` ([551](#))

### 10.10.22 GetLongName

Synopsis: Get the long filename of a DOS 8.3 filename.

Declaration: `function GetLongName(var p: String) : Boolean`

Visibility: default

Description: This function is only implemented in the GO32V2 and Win32 versions of Free Pascal.

`GetLongName` changes the filename `p` to a long filename if the API call to do this is successful. The resulting string is the long file name corresponding to the short filename `p`.

The function returns `True` if the API call was successful, `False` otherwise.

This function should only be necessary when using the DOS extender under Windows 95 and higher.

Errors: If the API call was not successful, `False` is returned.

See also: `GetShortName` ([547](#))

### 10.10.23 GetMsCount

Synopsis: Number of milliseconds since a starting point.

Declaration: `function GetMsCount : Int64`

Visibility: default

**Description:** `GetMSCount` returns a number of milliseconds elapsed since a certain moment in time. This moment in time is implementation dependent. This function is used for timing purposes: Subtracting the results of 2 subsequent calls to this function returns the number of milliseconds elapsed between the two calls.

This call is not very reliable, it is recommended to use some system specific calls for timings.

See also: `GetTime` ([547](#))

#### 10.10.24 GetShortName

**Synopsis:** Get the short (8.3) filename of a long filename.

**Declaration:** `function GetShortName(var p: String) : Boolean`

**Visibility:** default

**Description:** This function is only implemented in the GO32V2 and Win32 versions of Free Pascal.

`GetShortName` changes the filename `p` to a short filename if the API call to do this is successful. The resulting string is the short file name corresponding to the long filename `p`.

The function returns `True` if the API call was successful, `False` otherwise.

This function should only be necessary when using the DOS extender under Windows 95 and higher.

**Errors:** If the API call was not successful, `False` is returned.

See also: `GetLongName` ([546](#))

#### 10.10.25 GetTime

**Synopsis:** Return the current time

**Declaration:** `procedure GetTime(var hour: Word; var minute: Word; var second: Word; var sec100: Word)`

**Visibility:** default

**Description:** `GetTime` returns the system's time. `Hour` is on a 24-hour time scale. `sec100` is in hundredth of a second.

**Remark:** Certain operating systems (such as Amiga), always set the `sec100` field to zero.

**Errors:** None.

See also: `GetDate` ([543](#)), `SetTime` ([552](#))

**Listing:** `./dosex/ex3.pp`

---

```

Program Example3;
uses Dos;

{ Program to demonstrate the GetTime function. }

Function L0(w: word): string;
var
  s : string;
begin
  Str(w,s);
  if w<10 then

```

---

```

    L0:= '0'+s
  else
    L0:=s;
end;

var
  Hour,Min,Sec,HSec : word;
begin
  GetTime(Hour,Min,Sec,HSec);
  WriteLn('Current time ');
  WriteLn(L0(Hour),':',L0(Min),':',L0(Sec));
end.

```

---

### 10.10.26 GetVerify

Synopsis: Get verify flag

Declaration: `procedure GetVerify(var verify: Boolean)`

Visibility: default

Description: `GetVerify` returns the status of the verify flag under dos. When `Verify` is `True`, then dos checks data which are written to disk, by reading them after writing. If `Verify` is `False`, then data written to disk are not verified.

**Remark:** Under non-dos systems (excluding os/2 applications running under vanilla DOS), `Verify` is always `True`.

Errors: None.

See also: `SetVerify` ([552](#))

### 10.10.27 Intr

Synopsis: Execute interrupt

Declaration: `procedure Intr(intno: Byte;var regs: Registers)`

Visibility: default

Description: `Intr` executes a software interrupt number `IntNo` (must be between 0 and 255), with processor registers set to `Regs`. After the interrupt call returned, the processor registers are saved in `Regs`.

**Remark:** Under non-dos operating systems, this call does nothing.

Errors: None.

See also: `MSDos` ([549](#))

### 10.10.28 Keep

Synopsis: Terminate and stay resident.

Declaration: `procedure Keep(exitcode: Word)`

Visibility: default

**Description:** `Keep` terminates the program, but stays in memory. This is used for TSR (Terminate Stay Resident) programs which catch some interrupt. `ExitCode` is the same parameter as the `Halt` function takes.

**Remark:** This call does nothing, it is present for compatibility only.

Errors: None.

### 10.10.29 MSDos

**Synopsis:** Execute MS-DOS system call

**Declaration:** `procedure MSDos (var regs: Registers)`

**Visibility:** default

**Description:** `MSDos` executes an operating system call. This is the same as doing a `Intr` call with the interrupt number for an os call.

**Remark:** Under non-dos operating systems, this call does nothing. On DOS systems, this calls interrupt \$21.

Errors: None.

See also: `Intr` ([548](#))

### 10.10.30 PackTime

**Synopsis:** Pack `DateTime` value to a packed-time format.

**Declaration:** `procedure PackTime (var t: DateTime; var p: LongInt)`

**Visibility:** default

**Description:** `UnPackTime` converts the date and time specified in `T` to a packed-time format which can be fed to `SetFTime`.

Errors: None.

See also: `SetFTime` ([551](#)), `FindFirst` ([540](#)), `FindNext` ([541](#)), `UnPackTime` ([553](#))

**Listing:** `./dosex/ex4.pp`

---

**Program** `Example4`;  
**uses** `Dos`;

*{ Program to demonstrate the PackTime and UnPackTime functions. }*

```
var
  DT    : DateTime;
  Time  : longint;
begin
  with DT do
    begin
      Year:=2008;
      Month:=11;
      Day:=11;
      Hour:=11;
      Min:=11;
      Sec:=11;
    end;
    PackTime(DT, Time);
```

---

```

WriteLn( 'Packed Time : ',Time);
UnPackTime( Time,DT);
WriteLn( 'Unpacked Again: ');
with DT do
begin
  WriteLn( 'Year  ',Year);
  WriteLn( 'Month ',Month);
  WriteLn( 'Day   ',Day);
  WriteLn( 'Hour  ',Hour);
  WriteLn( 'Min   ',Min);
  WriteLn( 'Sec   ',Sec);
end;
end.

```

---

### 10.10.31 SetCBreak

Synopsis: Set Control-Break flag status

Declaration: `procedure SetCBreak(breakvalue: Boolean)`

Visibility: default

Description: `SetCBreak` sets the status of CTRL-Break checking. When `BreakValue` is false, then dos only checks for the CTRL-Break key-press when I/O is performed. When it is set to `True`, then a check is done at every system call.

**Remark:** Under non-dos and non-Amiga operating systems, this call does nothing.

Errors: None.

See also: `GetCBreak` ([543](#))

### 10.10.32 SetDate

Synopsis: Set system date

Declaration: `procedure SetDate(year: Word;month: Word;day: Word)`

Visibility: default

Description: `SetDate` sets the system's internal date. `Year` is a number between 1980 and 2099.

**Remark:** On a unix machine, there must be root privileges, otherwise this routine will do nothing. On other unix systems, this call currently does nothing.

Errors: None.

See also: `GetDate` ([543](#)), `SetTime` ([552](#))

### 10.10.33 SetFAttr

Synopsis: Set file attributes

Declaration: `procedure SetFAttr(var f;attr: Word)`

Visibility: default



**Description:** `SetFAttr` sets the file attributes of the file-variable `F`. `F` can be a untyped or typed file, or of type `Text`. `F` must have been assigned, but not opened. The attributes can be a sum of the following constants:

- `ReadOnly`
- `Hidden`
- `SysFile`
- `VolumeId`
- `Directory`
- `Archive`

**Remark:** Under unix like systems (such as linux and BeOS) the call exists, but is not implemented, i.e. it does nothing.

Errors: Errors are reported in `DosError`.

See also: `GetFAttr` ([544](#))

### 10.10.34 SetFTime

Synopsis: Set file modification time.

**Declaration:** `procedure SetFTime(var f; time: LongInt)`

Visibility: default

**Description:** `SetFTime` sets the modification time of a file, this time is encoded and must be encoded with `PackTime`. `F` must be a file type, which has been assigned, and opened.

**Remark:** Under unix like systems (such as linux and BeOS) the call exists, but is not implemented, i.e. it does nothing.

Errors: Errors are reported in `DosError`

See also: `GetFTime` ([545](#)), `PackTime` ([549](#)), `UnPackTime` ([553](#))

### 10.10.35 SetIntVec

Synopsis: Set interrupt vector

**Declaration:** `procedure SetIntVec(intno: Byte; vector: pointer)`

Visibility: default

**Description:** `SetIntVec` sets interrupt vector `IntNo` to `Vector`. `Vector` should point to an interrupt procedure.

**Remark:** This call does nothing, it is present for compatibility only.

Errors: None.

See also: `GetIntVec` ([546](#))

### 10.10.36 SetTime

Synopsis: Set system time

Declaration: `procedure SetTime(hour: Word; minute: Word; second: Word; sec100: Word)`

Visibility: default

Description: `SetTime` sets the system's internal clock. The `Hour` parameter is on a 24-hour time scale.

**Remark:** On a linux machine, there must be root privileges, otherwise this routine will do nothing. On other unix systems, this call currently does nothing.

Errors: None.

See also: `GetTime` ([547](#)), `SetDate` ([550](#))

### 10.10.37 SetVerify

Synopsis: Set verify flag

Declaration: `procedure SetVerify(verify: Boolean)`

Visibility: default

Description: `SetVerify` sets the status of the verify flag under dos. When `Verify` is `True`, then dos checks data which are written to disk, by reading them after writing. If `Verify` is `False`, then data written to disk are not verified.

**Remark:** Under non-dos operating systems (excluding os/2 applications running under vanilla dos), `Verify` is always `True`.

Errors: None.

See also: `SetVerify` ([552](#))

### 10.10.38 SwapVectors

Synopsis: Swap interrupt vectors

Declaration: `procedure SwapVectors`

Visibility: default

Description: `SwapVectors` swaps the contents of the internal table of interrupt vectors with the current contents of the interrupt vectors. This is called typically in before and after an `Exec` call.

**Remark:** Under certain operating systems, this routine may be implemented as an empty stub.

Errors: None.

See also: `Exec` ([539](#)), `SetIntVec` ([551](#))

### 10.10.39 UnixDateToDt

Synopsis: Convert a unix timestamp to a DateTime record

Declaration: `procedure UnixDateToDt (SecsPast: LongInt; var Dt: DateTime)`

Visibility: default

Description: `DTToUnixDate` converts the unix timestamp value in `SecsPast` to a `DateTime` representation in `DT`. It is an internal function, implemented on Unix platforms, and should not be used.

Errors: None.

See also: `DTToUnixDate` (538), `PackTime` (549), `UnpackTime` (553), `GetTime` (547), `SetTime` (552)

### 10.10.40 UnpackTime

Synopsis: Unpack packed file time to a DateTime value

Declaration: `procedure UnpackTime (p: LongInt; var t: DateTime)`

Visibility: default

Description: `UnPackTime` converts the file-modification time in `p` to a `DateTime` record. The file-modification time can be returned by `GetFTime`, `FindFirst` or `FindNext` calls.

For an example, see `PackTime` (549).

Errors: None.

See also: `GetFTime` (545), `FindFirst` (540), `FindNext` (541), `PackTime` (549)

### 10.10.41 weekday

Synopsis: Return the day of the week

Declaration: `function weekday (y: LongInt; m: LongInt; d: LongInt) : LongInt`

Visibility: default

Description: `WeekDay` returns the day of the week on which the day `Y/M/D` falls. Sunday is represented by 0, Saturday is 6.

Errors: On error, -1 is returned.

See also: `PackTime` (549), `UnpackTime` (553), `GetTime` (547), `SetTime` (552)

# Chapter 11

## Reference for unit 'dxeload'

### 11.1 Overview

The `dxeload` unit was implemented by Pierre Mueller for dos, it allows to load a DXE file (an object file with 1 entry point) into memory and return a pointer to the entry point.

It exists only for dos.

### 11.2 Procedures and functions

#### 11.2.1 `dxeload`

Synopsis: Load DXE file in memory

Declaration: `function dxeload(filename: String) : pointer`

Visibility: default

Description: `dxeload` loads the contents of the file `filename` into memory. It performs the necessary relocations in the object code, and returns then a pointer to the entry point of the code.

For an example, see the `emu387` ([558](#)) unit in the RTL.

Errors: If an error occurs during the load or relocations, `Nil` is returned.

## Chapter 12

# Reference for unit 'dynlibs'

### 12.1 Overview

The `Dynlibs` unit provides support for dynamically loading shared libraries. It is available only on those platforms that support shared libraries. The functionality available here may only be a part of the functionality available on each separate platform, in the interest of portability.

On unix platforms, using this unit will cause the program to be linked to the C library, as most shared libraries are implemented in C and the dynamical linker too.

### 12.2 Constants, types and variables

#### 12.2.1 Constants

```
NilHandle = TLibHandle(0)
```

Correctly typed Nil handle - returned on error by `LoadLibrary` ([556](#))

```
SharedSuffix = 'so'
```

`SharedSuffix` contains the extension of a shared library (dynamically loadable library) on the current platform. It does not contain the . (dot) character. This can be used to determine the name of a shared library in a platform independent way.

#### 12.2.2 Types

```
HModule = TLibHandle
```

Alias for `TLibHandle` ([555](#)) type.

```
TLibHandle = PtrInt
```

`TLibHandle` should be considered an opaque type. It is defined differently on various platforms. The definition shown here depends on the platform for which the documentation was generated.

## 12.3 Procedures and functions

### 12.3.1 FreeLibrary

Synopsis: For compatibility with Delphi/Windows: Unload a library

Declaration: `function FreeLibrary(Lib: TLibHandle) : Boolean`

Visibility: default

Description: `FreeLibrary` provides the same functionality as `UnloadLibrary` (557), and is provided for compatibility with Delphi.

See also: `UnloadLibrary` (557)

### 12.3.2 GetProcAddress

Synopsis: For compatibility with Delphi/Windows: Get the address of a procedure

Declaration: `function GetProcAddress(Lib: TLibHandle; ProcName: AnsiString) : Pointer`

Visibility: default

Description: `GetProcAddress` provides the same functionality as `GetProcedureAddress` (556), and is provided for compatibility with Delphi.

See also: `GetProcedureAddress` (556)

### 12.3.3 GetProcedureAddress

Synopsis: Get the address of a procedure or symbol in a dynamic library.

Declaration: `function GetProcedureAddress(Lib: TLibHandle; ProcName: AnsiString)  
: Pointer`

Visibility: default

Description: `GetProcedureAddress` returns a pointer to the location in memory of the symbol `ProcName` in the dynamically loaded library specified by its handle `lib`. If the symbol cannot be found or the handle is invalid, `Nil` is returned.

On Windows, only an exported procedure or function can be searched this way. On Unix platforms the location of any exported symbol can be retrieved this way.

Errors: If the symbol cannot be found, `Nil` is returned.

See also: `LoadLibrary` (556), `UnLoadLibrary` (557)

### 12.3.4 LoadLibrary

Synopsis: Load a dynamic library and return a handle to it.

Declaration: `function LoadLibrary(Name: AnsiString) : TLibHandle`

Visibility: default

**Description:** `LoadLibrary` loads a dynamic library in file `Name` and returns a handle to it. If the library cannot be loaded, `NilHandle` (555) is returned.

No assumptions should be made about the location of the loaded library if a relative pathname is specified. The behaviour is dependent on the platform. Therefore it is best to specify an absolute pathname if possible.

**Errors:** On error, `NilHandle` (555) is returned.

**See also:** `UnloadLibrary` (557), `GetProcAddress` (556)

### 12.3.5 SafeLoadLibrary

**Synopsis:** Saves the control word and loads a library

**Declaration:** `function SafeLoadLibrary(Name: AnsiString) : TLibHandle`

**Visibility:** default

**Description:** `SafeLoadLibrary` saves the FPU control word, and calls `LoadLibrary` (556) with library name `Name`. After that function has returned, the FPU control word is saved again. (only on Intel i386 CPUs).

**See also:** `LoadLibrary` (556)

### 12.3.6 UnloadLibrary

**Synopsis:** Unload a previously loaded library

**Declaration:** `function UnloadLibrary(Lib: TLibHandle) : Boolean`

**Visibility:** default

**Description:** `UnloadLibrary` unloads a previously loaded library (specified by the handle `lib`). The call returns `True` if succesful, `False` otherwisa.

**Errors:** On error, `False` is returned.

**See also:** `LoadLibrary` (556), `GetProcAddress` (556)

## Chapter 13

# Reference for unit 'emu387'

### 13.1 Overview

The `emu387` unit was written by Pierre Mueller for dos. It sets up the coprocessor emulation for FPC under dos. It is not necessary to use this unit on other OS platforms because they either simply do not run on a machine without coprocessor, or they provide the coprocessor emulation themselves.

It shouldn't be necessary to use the function in this unit, it should be enough to place this unit in the `uses` clause of your program to enable the coprocessor emulation under dos. The unit initialization code will try and load the coprocessor emulation code and initialize it.

### 13.2 Procedures and functions

#### 13.2.1 `npxsetup`

**Synopsis:** Set up coprocessor emulation.

**Declaration:** `procedure npxsetup(prog_name: String)`

**Visibility:** `default`

**Description:** `npxsetup` checks whether a coprocessor is found. If not, it loads the file `wmemu387.dxe` into memory and initializes the code in it.

If the environment variable `387` is set to `N`, then the emulation will be loaded, even if there is a coprocessor present. If the variable doesn't exist, or is set to any other value, the unit will try to detect the presence of a coprocessor unit.

The function searches the file `wmemu387.dxe` in the following way:

- 1.If the environment variable `EMU387` is set, then it is assumed to point at the `wmemu387.dxe` file.
- 2.if the environment variable `EMU387` does not exist, then the function will take the path part of `prog_name` and look in that directory for the file `wmemu387.dxe`.

It should never be necessary to call this function, because the initialization code of the unit contains a call to the function with as an argument `paramstr(0)`. This means that you should deliver the file `wmemu387.dxe` together with your program.

**Errors:** If there is an error, an error message is printed to standard error, and the program is halted, since any floating-point code is bound to fail anyhow.



## Chapter 14

# Reference for unit 'exeinfo'

### 14.1 Overview

The `exeinfo` unit implements some cross-platform routines to examine the contents of an executable: information about sections, mapping addresses to loaded modules etc.

It is mainly used by the `lineinfo` ([713](#)) and `Infodwrf` ([735](#)) unit to examine the binary for debug info.

### 14.2 Constants, types and variables

#### 14.2.1 Types

```
TExeFile = record
  f : File;
  size : Int64;
  isopen : Boolean;
  nsects : LongInt;
  sechdrofs : ptruint;
  secstrofs : ptruint;
  processaddress : ptruint;
  FunctionRelative : Boolean;
  ImgOffset : ptruint;
  filename : String;
  buf : Array[0..4095] of Byte;
  bufsize : LongInt;
  bufcnt : LongInt;
end
```

`TExeFile` is a record used in the various calls of this unit. It contains a file descriptor, and various fields that describe the executable.

The structure of `TExeFile` is opaque, that is, one shouldn't rely on the exactness of this structure, it may change any time in the future.

## 14.3 Procedures and functions

### 14.3.1 CloseExeFile

Synopsis: Close a previously opened file.

Declaration: `function CloseExeFile(var e: TExeFile) : Boolean`

Visibility: default

Description: `CloseExeFile` closes an executable file image previously opened with `OpenExeFile` (560), and represented by `e`.

The function returns `True` if the file was closed succesfully, or `False` if something went wrong.

Errors: In case of an error, `False` is returned.

See also: `OpenExeFile` (560)

### 14.3.2 FindExeSection

Synopsis: Find a section in the binary image.

Declaration: `function FindExeSection(var e: TExeFile; const secname: String;  
var secofs: LongInt; var seclen: LongInt)  
: Boolean`

Visibility: default

Description: `FindExeSection` examines the binary that was opened with `OpenExeFile` (560) (represented by `e`) and searches for the section named `secname`. If found, the section offset is returned in `secofs` and the section length (in bytes) is returned in `seclen`.

The function returns `True` if the section was found, `False` if not.

See also: `OpenExeFile` (560)

### 14.3.3 GetModuleByAddr

Synopsis: Return the module name by address

Declaration: `procedure GetModuleByAddr(addr: pointer; var baseaddr: pointer;  
var filename: String)`

Visibility: default

Description: `GetModuleByAddr` returns the name of the module that contains address `addr`. If succesful, it returns `True` and returns the filename in `FileName` and the base address at which it is loaded in `BaseAddr`.

### 14.3.4 OpenExeFile

Synopsis: Open an executable file

Declaration: `function OpenExeFile(var e: TExeFile; const fn: String) : Boolean`

Visibility: default

**Description:** `OpenExeFile` opens the executable file `fn` and initializes the structure `e` for subsequent calls to routines in the `exeinfo` unit.

The function returns `True` if the file was opened successfully, `false` otherwise.

See also: `FindExeSection` ([560](#)), `CloseExeFile` ([560](#)), `ReadDebugLink` ([561](#))

### 14.3.5 ReadDebugLink

**Synopsis:** Read the location of a debug info filename

**Declaration:** `function ReadDebugLink (var e: TExeFile; var dbgfn: String) : Boolean`

**Visibility:** `default`

**Description:** `ReadDebugLink` examines the `.gnu_debuglink` section to see if the debug information is stored in an external file. If so, then the name of the file with the debug information is returned in the `dbgfn` parameter.

The function returns `false` if there is no external debug information file, or if the file with debug information does not exist. It is searched next to the binary file or in the current directory.

See also: `OpenExeFile` ([560](#)), `CloseExeFile` ([560](#))

## Chapter 15

# Reference for unit 'getopts'

### 15.1 Overview

This document describes the GETOPTS unit for Free Pascal. It was written for linux by Michael Van Canneyt. It now also works for all supported platforms.

The getopts unit provides a mechanism to handle command-line options in a structured way, much like the GNU getopts mechanism. It allows you to define the valid options for your program, and the unit will then parse the command-line options for you, and inform you of any errors.

### 15.2 Constants, types and variables

#### 15.2.1 Constants

`EndOfOptions = #255`

Returned by `getopt` ([564](#)), `getlongopts` ([564](#)) to indicate that there are no more options.

`No_Argument = 0`

Specifies that a long option does not take an argument.

`Optional_Argument = 2`

Specifies that a long option optionally takes an argument.

`OptSpecifier : Set of Char = ['-']`

Character indicating an option on the command-line.

`Required_Argument = 1`

Specifies that a long option needs an argument.

Table 15.1: Enumeration values for type Orderings

Value	Explanation
permute	Change command-line options.
require_order	Don't touch the ordering of the command-line options
return_in_order	Return options in the correct order.

### 15.2.2 Types

```
Orderings = (require_order, permute, return_in_order)
```

Command-line ordering options.

```
POption = ^TOption
```

Pointer to TOption (563) record.

```
TOption = record
  Name : String;
  Has_arg : Integer;
  Flag : PChar;
  Value : Char;
end
```

The TOption type is used to communicate the long options to GetLongOpts (564). The Name field is the name of the option. Has\_arg specifies if the option wants an argument, Flag is a pointer to a char, which is set to Value, if it is non-nil.

### 15.2.3 Variables

```
OptArg : String
```

Set to the argument of an option, if the option needs one.

```
OptErr : Boolean
```

Indicates whether getopt() prints error messages.

```
OptInd : LongInt
```

when all options have been processed, optind is the index of the first non-option parameter. This is a read-only variable. Note that it can become equal to paramcount+1.

```
OptOpt : Char
```

In case of an error, contains the character causing the error.

## 15.3 Procedures and functions

### 15.3.1 GetLongOpts

**Synopsis:** Return next long option.

**Declaration:** `function GetLongOpts (ShortOpts: String; LongOpts: POption;  
var Longind: LongInt) : Char`

**Visibility:** default

**Description:** Returns the next option found on the command-line, taking into account long options as well. If no more options are found, returns `EndOfOptions`. If the option requires an argument, it is returned in the `OptArg` variable.

`ShortOptions` is a string containing all possible one-letter options. (see [Getopt \(564\)](#) for its description and use) `LongOpts` is a pointer to the first element of an array of `Option` records, the last of which needs a name of zero length.

The function tries to match the names even partially (i.e. `-app` will match e.g. the append option), but will report an error in case of ambiguity. If the option needs an argument, set `Has_arg` to `Required_argument`, if the option optionally has an argument, set `Has_arg` to `Optional_argument`. If the option needs no argument, set `Has_arg` to zero.

Required arguments can be specified in two ways :

1. Pasted to the option : `-option=value`
2. As a separate argument : `-option value`

Optional arguments can only be specified through the first method.

**Errors:** see [Getopt \(564\)](#).

See also: [Getopt \(564\)](#)

### 15.3.2 GetOpt

**Synopsis:** Get next short option.

**Declaration:** `function GetOpt (ShortOpts: String) : Char`

**Visibility:** default

**Description:** Returns the next option found on the command-line. If no more options are found, returns `EndOfOptions`. If the option requires an argument, it is returned in the `OptArg` variable.

`ShortOptions` is a string containing all possible one-letter options. If a letter is followed by a colon (:), then that option needs an argument. If a letter is followed by 2 colons, the option has an optional argument. If the first character of `shortoptions` is a '+' then options following a non-option are regarded as non-options (standard Unix behavior). If it is a '-', then all non-options are treated as arguments of a option with character #0. This is useful for applications that require their options in the exact order as they appear on the command-line. If the first character of `shortoptions` is none of the above, options and non-options are permuted, so all non-options are behind all options. This allows options and non-options to be in random order on the command line.

**Errors:** Errors are reported through giving back a '?' character. `OptOpt` then gives the character which caused the error. If `OptErr` is `True` then `getopt` prints an error-message to `stdout`.

See also: [GetLongOpts \(564\)](#)

**Listing:** ./optex/optex.pp

---

```

program testopt;

{ Program to depmonstrate the getopt function. }

{
  Valid calls to this program are
  optex --verbose --add me --delete you
  optex --append --create child
  optex -ab -c me -d you
  and so on
}
uses getopt;

var c : char;
    optionindex : Longint;
    theopts : array[1..7] of TOption;

begin
  with theopts[1] do
    begin
      name := 'add';
      has_arg := 1;
      flag := nil;
      value := #0;
    end;
  with theopts[2] do
    begin
      name := 'append';
      has_arg := 0;
      flag := nil;
      value := #0;
    end;
  with theopts[3] do
    begin
      name := 'delete';
      has_arg := 1;
      flag := nil;
      value := #0;
    end;
  with theopts[4] do
    begin
      name := 'verbose';
      has_arg := 0;
      flag := nil;
      value := #0;
    end;
  with theopts[5] do
    begin
      name := 'create';
      has_arg := 1;
      flag := nil;
      value := 'c';
    end;
  with theopts[6] do
    begin
      name := 'file';
      has_arg := 1;

```

---

```

    flag:=nil;
    value:=#0;
end;
with theopts[7] do
    begin
        name:='';
        has_arg:=0;
        flag:=nil;
    end;
c:=#0;
repeat
    c:=getlongopts('abc:d:012',@theo[1],optionindex);
    case c of
        '1','2','3','4','5','6','7','8','9' :
            begin
                writeln('Got optind : ',c)
            end;
        #0 : begin
                write('Long option : ',theo[optionindex].name);
                if theopts[optionindex].has_arg>0 then
                    writeln(' With value : ',optarg)
                else
                    writeln
                end;
            'a' : writeln('Option a. ');
            'b' : writeln('Option b. ');
            'c' : writeln('Option c : ',optarg);
            'd' : writeln('Option d : ',optarg);
            '?' : writeln('Error with opt : ',optopt);
        end; { case }
    until c=endofoptions;
    if optind<=paramcount then
        begin
            write('Non options : ');
            while optind<=paramcount do
                begin
                    write(paramstr(optind),' ');
                    inc(optind)
                end;
            writeln
        end
    end.
end.

```

---



## Chapter 16

# Reference for unit 'go32'

### 16.1 Overview

This document describes the GO32 unit for the Free Pascal compiler under dos. It was donated by Thomas Schatzl (tom\_at\_work@geocities.com), for which my thanks. This unit was first written for dos by Florian Klaempfl.

Only the GO32V2 DPMI mode is discussed by me here due to the fact that new applications shouldn't be created with the older GO32V1 model. The go32v2 version is much more advanced and better. Additionally a lot of functions only work in DPMI mode anyway. I hope the following explanations and introductions aren't too confusing at all. If you notice an error or bug send it to the FPC mailing list or directly to me. So let's get started and happy and error free coding I wish you.... Thomas Schatzl, 25. August 1998

### 16.2 Real mode callbacks

The callback mechanism can be thought of as the converse of calling a real mode procedure (i.e. interrupt), which allows your program to pass information to a real mode program, or obtain services from it in a manner that's transparent to the real mode program. In order to make a real mode callback available, you must first get the real mode callback address of your procedure and the selector and offset of a register data structure. This real mode callback address (this is a segment:offset address) can be passed to a real mode program via a software interrupt, a dos memory block or any other convenient mechanism. When the real mode program calls the callback (via a far call), the DPMI host saves the registers contents in the supplied register data structure, switches into protected mode, and enters the callback routine with the following settings:

- interrupts disabled
- %CS : %EIP = 48 bit pointer specified in the original call to `get_rm_callback` ([585](#))
- %DS : %ESI = 48 bit pointer to real mode SS : SP
- %ES : %EDI = 48 bit pointer of real mode register data structure.
- %SS : %ESP = locked protected mode stack
- All other registers undefined

The callback procedure can then extract its parameters from the real mode register data structure and/or copy parameters from the real mode stack to the protected mode stack. Recall that the segment

register fields of the real mode register data structure contain segment or paragraph addresses that are not valid in protected mode. Far pointers passed in the real mode register data structure must be translated to virtual addresses before they can be used with a protected mode program. The callback procedure exits by executing an IRET with the address of the real mode register data structure in `%ES:%EDI`, passing information back to the real mode caller by modifying the contents of the real mode register data structure and/or manipulating the contents of the real mode stack. The callback procedure is responsible for setting the proper address for resumption of real mode execution into the real mode register data structure; typically, this is accomplished by extracting the return address from the real mode stack and placing it into the `%CS:%EIP` fields of the real mode register data structure. After the IRET, the DPMI host switches the CPU back into real mode, loads ALL registers with the contents of the real mode register data structure, and finally returns control to the real mode program. All variables and code touched by the callback procedure MUST be locked to prevent page faults.

See also: [get\\_rm\\_callback \(585\)](#), [free\\_rm\\_callback \(581\)](#), [lock\\_code \(594\)](#), [lock\\_data \(594\)](#)

### 16.3 Executing software interrupts

Simply execute a `realintr()` call with the desired interrupt number and the supplied register data structure. But some of these interrupts require you to supply them a pointer to a buffer where they can store data to or obtain data from in memory. These interrupts are real mode functions and so they only can access the first Mb of linear address space, not FPC's data segment. For this reason FPC supplies a pre-initialized dos memory location within the GO32 unit. This buffer is internally used for dos functions too and so it's contents may change when calling other procedures. It's size can be obtained with [tb\\_size \(603\)](#) and it's linear address via [transfer\\_buffer \(603\)](#). Another way is to allocate a completely new dos memory area via the [global\\_dos\\_alloc \(591\)](#) function for your use and supply its real mode address.

See also: [tb\\_size \(603\)](#), [transfer\\_buffer \(603\)](#), [global\\_dos\\_alloc \(591\)](#), [global\\_dos\\_free \(592\)](#), [realintr \(596\)](#)

### 16.4 Software interrupts

Ordinarily, a handler installed with [set\\_pm\\_interrupt \(600\)](#) only services software interrupts that are executed in protected mode; real mode software interrupts can be redirected by [set\\_rm\\_interrupt \(601\)](#).

See also: [set\\_rm\\_interrupt \(601\)](#), [get\\_rm\\_interrupt \(588\)](#), [set\\_pm\\_interrupt \(600\)](#), [get\\_pm\\_interrupt \(585\)](#), [lock\\_data \(594\)](#), [lock\\_code \(594\)](#), [enable \(580\)](#), [disable \(578\)](#), [outportb \(595\)](#)

### 16.5 Hardware interrupts

Hardware interrupts are generated by hardware devices when something unusual happens; this could be a keypress or a mouse move or any other action. This is done to minimize CPU time, else the CPU would have to check all installed hardware for data in a big loop (this method is called 'polling') and this would take much time. A standard IBM-PC has two interrupt controllers, that are responsible for these hardware interrupts: both allow up to 8 different interrupt sources (IRQs, interrupt requests). The second controller is connected to the first through IRQ 2 for compatibility reasons, e.g. if controller 1 gets an IRQ 2, he hands the IRQ over to controller 2. Because of this up to 15 different hardware interrupt sources can be handled. IRQ 0 through IRQ 7 are mapped to interrupts 8h to Fh and the second controller (IRQ 8 to 15) is mapped to interrupt 70h to 77h. All of the code and

data touched by these handlers **MUST** be locked (via the various locking functions) to avoid page faults at interrupt time. Because hardware interrupts are called (as in real mode) with interrupts disabled, the handler has to enable them before it returns to normal program execution. Additionally a hardware interrupt must send an EOI (end of interrupt) command to the responsible controller; this is accomplished by sending the value 20h to port 20h (for the first controller) or A0h (for the second controller). The following example shows how to redirect the keyboard interrupt.

## 16.6 Disabling interrupts

The GO32 unit provides the two procedures `disable()` and `enable()` to disable and enable all interrupts.

## 16.7 Creating your own interrupt handlers

Interrupt redirection with FPC pascal is done via the `set_pm_interrupt()` for protected mode interrupts or via the `set_rm_interrupt()` for real mode interrupts.

## 16.8 Protected mode interrupts vs. Real mode interrupts

As mentioned before, there's a distinction between real mode interrupts and protected mode interrupts; the latter are protected mode programs, while the former must be real mode programs. To call a protected mode interrupt handler, an assembly `'int'` call must be issued, while the other is called via the `realintr()` or `intr()` function. Consequently, a real mode interrupt then must either reside in dos memory (<1MB) or the application must allocate a real mode callback address via the `get_rm_callback()` function.

## 16.9 Handling interrupts with DPMI

The interrupt functions are real-mode procedures; they normally can't be called in protected mode without the risk of an protection fault. So the DPMI host creates an interrupt descriptor table for the application. Initially all software interrupts (except for int 31h, 2Fh and 21h function 4Ch) or external hardware interrupts are simply directed to a handler that reflects the interrupt in real-mode, i.e. the DPMI host's default handlers switch the CPU to real-mode, issue the interrupt and switch back to protected mode. The contents of general registers and flags are passed to the real mode handler and the modified registers and flags are returned to the protected mode handler. Segment registers and stack pointer are not passed between modes.

## 16.10 Interrupt redirection

Interrupts are program interruption requests, which in one or another way get to the processor; there's a distinction between software and hardware interrupts. The former are explicitly called by an `'int'` instruction and are a bit comparable to normal functions. Hardware interrupts come from external devices like the keyboard or mouse. Functions that handle hardware interrupts are called handlers.

## 16.11 Processor access

These are some functions to access various segment registers (`%cs`, `%ds`, `%ss`) which makes your work a bit easier.

See also: `get_cs` (581), `get_ds` (582), `get_ss` (590)

## 16.12 I/O port access

The I/O port access is done via the various `inportb` (592), `outportb` (595) functions which are available. Additionally Free Pascal supports the Turbo Pascal `PORT[]`-arrays but it is by no means recommended to use them, because they're only for compatibility purposes.

See also: `outportb` (595), `inportb` (592)

## 16.13 dos memory access

Dos memory is accessed by the predefined `dosmemselector` selector; the GO32 unit additionally provides some functions to help you with standard tasks, like copying memory from heap to dos memory and the likes. Because of this it is strongly recommended to use them, but you are still free to use the provided standard memory accessing functions which use 48 bit pointers. The third, but only thought for compatibility purposes, is using the `mem[]`-arrays. These arrays map the whole 1 Mb dos space. They shouldn't be used within new programs. To convert a segment:offset real mode address to a protected mode linear address you have to multiply the segment by 16 and add its offset. This linear address can be used in combination with the `DOSMEMSELECTOR` variable.

See also: `dosmemget` (572), `dosmemput` (572), `dosmemmove` (572), `dosmemfillchar` (571), `dosmemfillword` (571), `seg_move` (599), `seg_fillchar` (598), `seg_fillword` (599)

## 16.14 FPC specialities

The `%ds` and `%es` selector MUST always contain the same value or some system routines may crash when called. The `%fs` selector is preloaded with the `DOSMEMSELECTOR` variable at startup, and it MUST be restored after use, because again FPC relies on this for some functions. Luckily we asm programmers can still use the `%gs` selector for our own purposes, but for how long ?

See also: `get_cs` (581), `get_ds` (582), `get_ss` (590), `allocate_ldt_descriptors` (575), `free_ldt_descriptor` (580), `segment_to_descriptor` (597), `get_next_selector_increment_value` (584), `get_segment_base_address` (589), `set_segment_base_address` (602), `set_segment_limit` (602), `create_code_segment_alias_descriptor` (578)

## 16.15 Selectors and descriptors

Descriptors are a bit like real mode segments; they describe (as the name implies) a memory area in protected mode. A descriptor contains information about segment length, its base address and the attributes of it (i.e. type, access rights, ...). These descriptors are stored internally in a so-called descriptor table, which is basically an array of such descriptors. Selectors are roughly an index into this table. Because these 'segments' can be up to 4 GB in size, 32 bits aren't sufficient anymore

to describe a single memory location like in real mode. 48 bits are now needed to do this, a 32 bit address and a 16 bit sized selector. The GO32 unit provides the tseginfo record to store such a pointer. But due to the fact that most of the time data is stored and accessed in the %ds selector, FPC assumes that all pointers point to a memory location of this selector. So a single pointer is still only 32 bits in size. This value represents the offset from the data segment base address to this memory location.

## 16.16 What is DPMI

The dos Protected Mode Interface helps you with various aspects of protected mode programming. These are roughly divided into descriptor handling, access to dos memory, management of interrupts and exceptions, calls to real mode functions and other stuff. Additionally it automatically provides swapping to disk for memory intensive applications. A DPMI host (either a Windows dos box or CWSDPMI.EXE) provides these functions for your programs.

## 16.17 Constants, types and variables

### 16.17.1 Constants

```
auxcarryflag = $010
```

Check for auxiliary carry flag in trealregs ([574](#))

```
carryflag = $001
```

Check for carry flag in trealregs ([574](#))

```
directionflag = $400
```

Check for direction flag in trealregs ([574](#))

```
dosmemfillchar : procedure(seg: Word;ofs: Word;count: LongInt;c: Char) = @dpmi_dosmem
```

Sets a region of dos memory to a specific byte value.

Parameters:

**seg** real mode segment.

**ofs** real mode offset.

**count** number of bytes to set.

**c** value to set memory to.

Notes: No range check is performed.

```
dosmemfillword : procedure(seg: Word;ofs: Word;count: LongInt;w: Word) = @dpmi_dosmem
```

Sets a region of dos memory to a specific word value.

Parameters:

**seg** real mode segment.

**ofs** real mode offset.

**count** number of words to set.

**w** value to set memory to.

Notes: No range check is performed.

```
dosmemget : procedure(seg: Word;ofs: Word;var data;count: LongInt) = @dpmi_dosmemget
```

Copies data from the dos memory onto the heap.

Parameters:

**seg** source real mode segment.

**ofs** source real mode offset.

**data** destination.

**count** number of bytes to copy.

Notes: No range checking is performed.

For an example, see `global_dos_alloc` ([591](#)).

```
dosmemmove : procedure(sseg: Word;sofs: Word;dseg: Word;dofs: Word;count: LongInt) =
```

Copies count bytes of data between two dos real mode memory locations.

Parameters:

**sseg** source real mode segment.

**sofs** source real mode offset.

**dseg** destination real mode segment.

**dofs** destination real mode offset.

**count** number of bytes to copy.

Notes: No range check is performed in any way.

```
dosmemput : procedure(seg: Word;ofs: Word;var data;count: LongInt) = @dpmi_dosmemput
```

Copies heap data to dos real mode memory.

Parameters:

**seg** destination real mode segment.

**ofs** destination real mode offset.

**data** source.

**count** number of bytes to copy.

Notes: No range checking is performed.

For an example, see `global_dos_alloc` (591).

```
interruptflag = $200
```

Check for interrupt flag in `trealregs` (574)

```
overflowflag = $800
```

Check for overflow flag in `trealregs` (574)

```
parityflag = $004
```

Check for parity flag in `trealregs` (574)

```
rm_dpml = 4
```

`get_run_mode` (589) return value: DPMI (e.g. dos box or 386Max)

```
rm_raw = 1
```

`get_run_mode` (589) return value: raw (without HIMEM)

```
rm_unknown = 0
```

`get_run_mode` (589) return value: Unknown runmode

```
rm_vcpi = 3
```

`get_run_mode` (589) return value: VCPI (with HIMEM and EMM386)

```
rm_xms = 2
```

`get_run_mode` (589) return value: XMS (with HIMEM, without EMM386)

```
signflag = $080
```

Check for sign flag in `trealregs` (574)

```
trapflag = $100
```

Check for trap flag in `trealregs` (574)

```
zeroflag = $040
```

Check for zero flag in `trealregs` (574)

### 16.17.2 Types

```
registers = trealregs
```

Alias for `trealregs` (574)

```
tmeminfo = record
  available_memory : LongInt;
  available_pages : LongInt;
  available_lockable_pages : LongInt;
  linear_space : LongInt;
  unlocked_pages : LongInt;
  available_physical_pages : LongInt;
  total_physical_pages : LongInt;
  free_linear_space : LongInt;
  max_pages_in_paging_file : LongInt;
  reserved0 : LongInt;
  reserved1 : LongInt;
  reserved2 : LongInt;
end
```

`tmeminfo` Holds information about the memory allocation, etc.

**NOTE:** The value of a field is -1 (0ffffffh) if the value is unknown, it's only guaranteed, that `available_memory` contains a valid value. The size of the pages can be determined by the `get_page_size()` function.

```
trealregs = record
end
```

The `trealregs` type contains the data structure to pass register values to a interrupt handler or real mode callback.

```
tseginfo = record
  offset : pointer;
  segment : Word;
end
```

This record is used to store a full 48-bit pointer. This may be either a protected mode selector:offset address or in real mode a segment:offset address, depending on application.

See also: Selectors and descriptors, dos memory access, Interrupt redirection

### 16.17.3 Variables

```
dosmemselector : Word
```

Selector to the dos memory. The whole dos memory is automatically mapped to this single descriptor at startup. This selector is the recommended way to access dos memory.

```
int31error : Word
```

This variable holds the result of a DPMI interrupt call. Any nonzero value must be treated as a critical failure.



## 16.18 Procedures and functions

### 16.18.1 allocate\_ldt\_descriptors

Synopsis: Allocate a number of descriptors

Declaration: `function allocate_ldt_descriptors(count: Word) : Word`

Visibility: default

Description: Allocates a number of new descriptors.

Parameters:

**count:** \ specifies the number of requested unique descriptors.

Return value: The base selector.

**Remark:** Notes: The descriptors allocated must be initialized by the application with other function calls. This function returns descriptors with a limit and size value set to zero. If more than one descriptor was requested, the function returns a base selector referencing the first of a contiguous array of descriptors. The selector values for subsequent descriptors in the array can be calculated by adding the value returned by the `get_next_selector_increment_value` (584) function.

Errors: Check the `int31error` (574) variable.

See also: `free_ldt_descriptor` (580), `get_next_selector_increment_value` (584), `segment_to_descriptor` (597), `create_code_segment_alias_descriptor` (578), `set_segment_limit` (602), `set_segment_base_address` (602)

**Listing:** `./go32ex/seldes.pp`

---

```
{ $mode delphi }
uses
    crt ,
    go32;

const
    maxx = 80;
    maxy = 25;
    bytespercell = 2;
    screensize = maxx * maxy * bytespercell;

    linB8000 = $B800 * 16;

type
    string80 = string[80];

var
    text_save : array[0..screensize-1] of byte;
    text_oldx , text_oldy : Word;

    text_sel : Word;

procedure status(s : string80);
begin
    gotoxy(1 , 1); clreol; write(s); readkey;
end;

procedure selinfo(sel : Word);
```

```

begin
  gotoxy(1, 24);
  clreol; writeln('Descriptor base address : $',
    hexstr(get_segment_base_address(sel), 8));
  clreol; write('Descriptor limit : ', get_segment_limit(sel));
end;

function makechar(ch : char; color : byte) : Word;
begin
  result := byte(ch) or (color shl 8);
end;

begin
  seg_move(dosmemselector, linB8000, get_ds, longint(@text_save),
    screensize);
  text_oldx := wherex; text_oldy := wherey;
  seg_fillword(dosmemselector, linB8000, screensize div 2,
    makechar(' ', Black or (Black shl 4)));
  status('Creating selector ''text_sel'' to a part of ' +
    'text screen memory');
  text_sel := allocate_ldt_descriptors(1);
  set_segment_base_address(text_sel,
    linB8000 + bytespercell * maxx * 1);
  set_segment_limit(text_sel, screensize - 1 - bytespercell *
    maxx * 3);
  selinfo(text_sel);

  status('and clearing entire memory selected by ''text_sel'' +
    ' descriptor');
  seg_fillword(text_sel, 0, (get_segment_limit(text_sel)+1) div 2,
    makechar(' ', LightBlue shl 4));

  status('Notice that only the memory described by the ' +
    ' descriptor changed, nothing else');

  status('Now reducing it''s limit and base and setting it''s ' +
    'described memory');
  set_segment_base_address(text_sel,
    get_segment_base_address(text_sel) + bytespercell * maxx);
  set_segment_limit(text_sel,
    get_segment_limit(text_sel) - bytespercell * maxx * 2);
  selinfo(text_sel);
  status('Notice that the base addr increased by one line but ' +
    'the limit decreased by 2 lines');
  status('This should give you the hint that the limit is ' +
    'relative to the base');
  seg_fillword(text_sel, 0, (get_segment_limit(text_sel)+1) div 2,
    makechar(#176, LightMagenta or Brown shl 4));

  status('Now let''s get crazy and copy 10 lines of data from ' +
    'the previously saved screen');
  seg_move(get_ds, longint(@text_save), text_sel,
    maxx * bytespercell * 2, maxx * bytespercell * 10);

  status('At last freeing the descriptor and restoring the old ' +
    ' screen contents..');
  status('I hope this little program may give you some hints on ' +
    'working with descriptors');

```

---

```

    free_ldt_descriptor(text_sel);
    seg_move(get_ds, longint(@text_save), dosmemselector,
            linB8000, screensize);
    gotoxy(text_oldx, text_oldy);
end.

```

---

### 16.18.2 allocate\_memory\_block

Synopsis: Allocate a block of linear memory

Declaration: `function allocate_memory_block(size: LongInt) : LongInt`

Visibility: default

Description: Allocates a block of linear memory.

Parameters:

**size:**Size of requested linear memory block in bytes.

Returned values: blockhandle - the memory handle to this memory block. Linear address of the requested memory.

**Remark:** *warning* According to my DPMI docs this function is not implemented correctly. Normally you should also get a blockhandle to this block after successful operation. This handle can then be used to free the memory block afterwards or use this handle for other purposes. Since the function isn't implemented correctly, and doesn't return a blockhandle, the block can't be deallocated and is hence unusable ! This function doesn't allocate any descriptors for this block, it's the applications responsibility to allocate and initialize for accessing this memory.

Errors: Check the int31error ([574](#)) variable.

See also: `free_memory_block` ([581](#))

### 16.18.3 copyfromdos

Synopsis: Copy data from DOS to to heap

Declaration: `procedure copyfromdos(var addr; len: LongInt)`

Visibility: default

Description: Copies data from the pre-allocated dos memory transfer buffer to the heap.

Parameters:

**addr**data to copy to.

**len**number of bytes to copy to heap.

Notes: Can only be used in conjunction with the dos memory transfer buffer.

Errors: Check the int31error ([574](#)) variable.

See also: `tb_size` ([603](#)), `transfer_buffer` ([603](#)), `copytodos` ([578](#))

### 16.18.4 copytodos

Synopsis: Copy data from heap to DOS memory

Declaration: `procedure copytodos(var addr; len: LongInt)`

Visibility: default

Description: Copies data from heap to the pre-allocated dos memory buffer.

Parameters:

**addr** data to copy from.

**len** number of bytes to copy to dos memory buffer.

Notes: This function fails if you try to copy more bytes than the transfer buffer is in size. It can only be used in conjunction with the transfer buffer.

Errors: Check the `int31error` ([574](#)) variable.

See also: `tb_size` ([603](#)), `transfer_buffer` ([603](#)), `copyfromdos` ([577](#))

### 16.18.5 create\_code\_segment\_alias\_descriptor

Synopsis: Create new descriptor from existing descriptor

Declaration: `function create_code_segment_alias_descriptor(seg: Word) : Word`

Visibility: default

Description: Creates a new descriptor that has the same base and limit as the specified descriptor.

Parameters:

**seg** Descriptor.

Return values: The data selector (alias).

Notes: In effect, the function returns a copy of the descriptor. The descriptor alias returned by this function will not track changes to the original descriptor. In other words, if an alias is created with this function, and the base or limit of the original segment is then changed, the two descriptors will no longer map the same memory.

Errors: Check the `int31error` ([574](#)) variable.

See also: `allocate_ldt_descriptors` ([575](#)), `set_segment_limit` ([602](#)), `set_segment_base_address` ([602](#))

### 16.18.6 disable

Synopsis: Disable hardware interrupts

Declaration: `procedure disable`

Visibility: default

Description: Disables all hardware interrupts by execution a CLI instruction.

Errors: None.

See also: `enable` ([580](#))

### 16.18.7 dpmi\_dosmemfillchar

Synopsis: Fill DOS memory with a character

Declaration: `procedure dpmi_dosmemfillchar(seg: Word; ofs: Word; count: LongInt;  
c: Char)`

Visibility: default

Description: `dpmi_dosmemfillchar` fills the DOS memory region indicated by `seg,ofs` with `count` characters `c`.

See also: `dpmi_dosmempout` (580), `dpmi_dosmemget` (579), `dpmi_dosmemmove` (579), `dpmi_dosmemfillword` (579)

### 16.18.8 dpmi\_dosmemfillword

Synopsis: Fill DOS memory with a word value

Declaration: `procedure dpmi_dosmemfillword(seg: Word; ofs: Word; count: LongInt;  
w: Word)`

Visibility: default

Description: `dpmi_dosmemfillword` fills the DOS memory region indicated by `seg,ofs` with `count` words `w`.

See also: `dpmi_dosmempout` (580), `dpmi_dosmemget` (579), `dpmi_dosmemfillchar` (579), `dpmi_dosmemmove` (579)

### 16.18.9 dpmi\_dosmemget

Synopsis: Move data from DOS memory to DPMI memory

Declaration: `procedure dpmi_dosmemget(seg: Word; ofs: Word; var data; count: LongInt)`

Visibility: default

Description: `dpmi_dosmempout` moves `count` bytes of data from the DOS memory location indicated by `seg` and `ofs` to DPMI memory indicated by `data`.

See also: `dpmi_dosmempout` (580), `dpmi_dosmemmove` (579), `dpmi_dosmemfillchar` (579), `dpmi_dosmemfillword` (579)

### 16.18.10 dpmi\_dosmemmove

Synopsis: Move DOS memory

Declaration: `procedure dpmi_dosmemmove(sseg: Word; sofs: Word; dseg: Word; dofs: Word;  
count: LongInt)`

Visibility: default

Description: `dpmi_dosmemmove` moves `count` bytes from DOS memory `sseg,sofs` to `dseg,dofs`.

See also: `dpmi_dosmempout` (580), `dpmi_dosmemget` (579), `dpmi_dosmemfillchar` (579), `dpmi_dosmemfillword` (579)

**16.18.11 dpmi\_dosmempu**

Synopsis: Move data from DPMI memory to DOS memory.

Declaration: `procedure dpmi_dosmempu (seg: Word; ofs: Word; var data; count: LongInt)`

Visibility: default

Description: `dpmi_dosmempu` moves `count` bytes of data from `data` to the DOS memory location indicated by `seg` and `ofs`.

See also: `dpmi_dosmemget` (579), `dpmi_dosmemmove` (579), `dpmi_dosmemfillchar` (579), `dpmi_dosmemfillword` (579)

**16.18.12 enable**

Synopsis: Enable hardware interrupts

Declaration: `procedure enable`

Visibility: default

Description: Enables all hardware interrupts by executing a STI instruction.

Errors: None.

See also: `disable` (578)

**16.18.13 free\_ldt\_descriptor**

Synopsis: Free a descriptor

Declaration: `function free_ldt_descriptor (d: Word) : Boolean`

Visibility: default

Description: Frees a previously allocated descriptor.

Parameters:

**des** The descriptor to be freed.

Return value: `True` if successful, `False` otherwise. Notes: After this call this selector is invalid and must not be used for any memory operations anymore. Each descriptor allocated with `allocate_ldt_descriptors` (575) must be freed individually with this function, even if it was previously allocated as a part of a contiguous array of descriptors.

For an example, see `allocate_ldt_descriptors` (575).

Errors: Check the `int31error` (574) variable.

See also: `allocate_ldt_descriptors` (575), `get_next_selector_increment_value` (584)

**16.18.14 free\_memory\_block**

Synopsis: Free allocated memory block

Declaration: `function free_memory_block(blockhandle: LongInt) : Boolean`

Visibility: default

Description: Frees a previously allocated memory block.

Parameters:

**blockhandle** the handle to the memory area to free.

Return value: `True` if successful, `false` otherwise. Notes: Frees memory that was previously allocated with `allocate_memory_block` (577) . This function doesn't free any descriptors mapped to this block, it's the application's responsibility.

Errors: Check `int31error` (574) variable.

See also: `allocate_memory_block` (577)

**16.18.15 free\_rm\_callback**

Synopsis: Release real mode callback.

Declaration: `function free_rm_callback(var intaddr: tseginfo) : Boolean`

Visibility: default

Description: Releases a real mode callback address that was previously allocated with the `get_rm_callback` (585) function.

Parameters:

**intaddr** real mode address buffer returned by `get_rm_callback` (585) .

Return values: `True` if successful, `False` if not

For an example, see `get_rm_callback` (585).

Errors: Check the `int31error` (574) variable.

See also: `set_rm_interrupt` (601), `get_rm_callback` (585)

**16.18.16 get\_cs**

Synopsis: Get CS selector

Declaration: `function get_cs : Word`

Visibility: default

Description: Returns the cs selector.

Return value: The content of the cs segment register.

For an example, see `set_pm_interrupt` (600).

Errors: None.

See also: `get_ds` (582), `get_ss` (590)

### 16.18.17 `get_descriptor_access_right`

Synopsis: Get descriptor's access rights

Declaration: `function get_descriptor_access_right(d: Word) : LongInt`

Visibility: default

Description: Gets the access rights of a descriptor.

Parameters:

`d` selector to descriptor.

Return value: Access rights bit field.

Errors: Check the `int31error` (574) variable.

See also: `set_descriptor_access_right` (600)

### 16.18.18 `get_ds`

Synopsis: Get DS Selector

Declaration: `function get_ds : Word`

Visibility: default

Description: Returns the ds selector.

Return values: The content of the ds segment register.

Errors: None.

See also: `get_cs` (581), `get_ss` (590)

### 16.18.19 `get_exception_handler`

Synopsis: Return current exception handler

Declaration: `function get_exception_handler(e: Byte; var intaddr: tseginfo) : Boolean`

Visibility: default

Description: `get_exception_handler` returns the exception handler for exception `E` in `intaddr`. It returns `True` if the call was successful, `False` if not.

See also: `set_exception_handler` (600), `get_pm_exception_handler` (585)

### 16.18.20 `get_linear_addr`

Synopsis: Convert physical to linear address

Declaration: `function get_linear_addr(phys_addr: LongInt; size: LongInt) : LongInt`

Visibility: default

Description: Converts a physical address into a linear address.

Parameters:



**phys\_addr** physical address of device.

**size** Size of region to map in bytes.

Return value: Linear address that can be used to access the physical memory. Notes: It's the applications responsibility to allocate and set up a descriptor for access to the memory. This function shouldn't be used to map real mode addresses.

Errors: Check the `int31error` (574) variable.

See also: `allocate_ldt_descriptors` (575), `set_segment_limit` (602), `set_segment_base_address` (602)

### 16.18.21 get\_meminfo

Synopsis: Return information on the available memory

Declaration: `function get_meminfo(var meminfo: tmeminfo) : Boolean`

Visibility: default

Description: Returns information about the amount of available physical memory, linear address space, and disk space for page swapping.

Parameters:

**meminfo** buffer to fill memory information into.

Return values: Due to an implementation bug this function always returns `False`, but it always succeeds.

**Remark:** Notes: Only the first field of the returned structure is guaranteed to contain a valid value. Any fields that are not supported by the DPMI host will be set by the host to `-1` (`0FFFFFFFFH`) to indicate that the information is not available. The size of the pages used by the DPMI host can be obtained with the `get_page_size` (584) function.

Errors: Check the `int31error` (574) variable.

See also: `get_page_size` (584)

**Listing:** `./go32ex/meminfo.pp`

---

```

uses
    go32;

var
    meminfo : tmeminfo;

begin
    get_meminfo(meminfo);
    if (int31error <> 0) then begin
        Writeln('Error getting DPMI memory information... Halting');
        Writeln('DPMI error number : ', int31error);
    end else begin
        with meminfo do begin
            Writeln('Largest available free block : ',
                available_memory div 1024, ' kbytes');
            if (available_pages <> -1) then
                Writeln('Maximum available unlocked pages : ',
                    available_pages);
            if (available_lockable_pages <> -1) then

```

---

```

        Writeln('Maximum lockable available pages : ',
                available_lockable_pages);
    if (linear_space <> -1) then
        Writeln('Linear address space size : ',
                linear_space*get_page_size div 1024, ' kbytes');
    if (unlocked_pages <> -1) then
        Writeln('Total number of unlocked pages : ',
                unlocked_pages);
    if (available_physical_pages <> -1) then
        Writeln('Total number of free pages : ',
                available_physical_pages);
    if (total_physical_pages <> -1) then
        Writeln('Total number of physical pages : ',
                total_physical_pages);
    if (free_linear_space <> -1) then
        Writeln('Free linear address space : ',
                free_linear_space*get_page_size div 1024,
                ' kbytes');
    if (max_pages_in_paging_file <> -1) then
        Writeln('Maximum size of paging file : ',
                max_pages_in_paging_file*get_page_size div 1024,
                ' kbytes');
    end;
end;
end.

```

---

### 16.18.22 get\_next\_selector\_increment\_value

Synopsis: Return selector increment value

Declaration: function get\_next\_selector\_increment\_value : Word

Visibility: default

Description: Returns the selector increment value when allocating multiple subsequent descriptors via allocate\_ldt\_descriptors (575).

Return value: Selector increment value.

**Remark:** Notes: Because allocate\_ldt\_descriptors (575) only returns the selector for the first descriptor and so the value returned by this function can be used to calculate the selectors for subsequent descriptors in the array.

Errors: Check the int31error (574) variable.

See also: allocate\_ldt\_descriptors (575), free\_ldt\_descriptor (580)

### 16.18.23 get\_page\_size

Synopsis: Return the page size

Declaration: function get\_page\_size : LongInt

Visibility: default

Description: Returns the size of a single memory page.

Return value: Size of a single page in bytes.

**Remark:** The returned size is typically 4096 bytes.

For an example, see `get_meminfo` (583).

Errors: Check the `int31error` (574) variable.

See also: `get_meminfo` (583)

#### 16.18.24 `get_pm_exception_handler`

Synopsis: Get protected mode exception handler

Declaration: `function get_pm_exception_handler(e: Byte; var intaddr: tseginfo) : Boolean`

Visibility: default

Description: `get_pm_exception_handler` returns the protected mode exception handler for exception `E` in `intaddr`. It returns `True` if the call was successful, `False` if not.

See also: `get_exception_handler` (582), `set_pm_exception_handler` (600)

#### 16.18.25 `get_pm_interrupt`

Synopsis: Return protected mode interrupt handler

Declaration: `function get_pm_interrupt(vector: Byte; var intaddr: tseginfo) : Boolean`

Visibility: default

Description: Returns the address of a current protected mode interrupt handler.

Parameters:

**vector** interrupt handler number you want the address to.

**intaddr** buffer to store address.

Return values: `True` if successful, `False` if not.

**Remark:** The returned address is a protected mode selector:offset address.

For an example, see `set_pm_interrupt` (600).

Errors: Check the `int31error` (574) variable.

See also: `set_pm_interrupt` (600), `set_rm_interrupt` (601), `get_rm_interrupt` (588)

#### 16.18.26 `get_rm_callback`

Synopsis: Return real mode callback

Declaration: `function get_rm_callback(pm_func: pointer; const reg: trealregs; var rmcb: tseginfo) : Boolean`

Visibility: default

Description: Returns a unique real mode `segment : offset` address, known as a "real mode callback," that will transfer control from real mode to a protected mode procedure.

Parameters:

**pm\_funcpointer** to the protected mode callback function.

**regs** supplied registers structure.

**rmcbbuffer** to real mode address of callback function.

Return values: `True` if successful, otherwise `False`.

**Remark:** Callback addresses obtained with this function can be passed by a protected mode program for example to an interrupt handler, device driver, or TSR, so that the real mode program can call procedures within the protected mode program or notify the protected mode program of an event. The contents of the supplied `regs` structure is not valid after function call, but only at the time of the actual callback.

Errors: Check the `int31error` (574) variable.

See also: `free_rm_callback` (581)

**Listing:** `./go32ex/callback.pp`

---

```
{ $ASMMODE ATT }
{ $MODE FPC }

uses
    crt ,
    go32;

const
    mouseint = $33;

var
    mouse_regs      : trealregs; external name '___v2prt0_rmcb_regs';
    mouse_seginfo   : tseginfo;

var
    mouse_numbuttons : longint;

    mouse_action : word;
    mouse_x, mouse_y : Word;
    mouse_b : Word;

    userproc_installed : Longbool;
    userproc_length : Longint;
    userproc_proc : pointer;

procedure callback_handler; assembler;
asm
    pushw %ds
    pushl %eax
    movw %es, %ax
    movw %ax, %ds

    cmpl $1, USERPROC_INSTALLED
    jne .LNoCallback
    pushal
    movw DOSmemSELECTOR, %ax
    movw %ax, %fs
    call *USERPROC_PROC
    popal
.LNoCallback:
```

```

    popl %eax
    popw %ds

    pushl %eax
    movl (%esi), %eax
    movl %eax, %es: 42(%edi)
    addw $4, %es:46(%edi)
    popl %eax
    iret
end;
procedure mouse_dummy; begin end;

procedure textuserproc;
begin
    mouse_b := mouse_regs.bx;
    mouse_x := (mouse_regs.cx shr 3) + 1;
    mouse_y := (mouse_regs.dx shr 3) + 1;
end;

procedure install_mouse(userproc : pointer; userproclen : longint);
var r : trealregs;
begin
    r.eax := $0; realintr(mouseint, r);
    if (r.eax <> $FFFF) then begin
        Writeln('No Microsoft compatible mouse found');
        Writeln('A Microsoft compatible mouse driver is necessary ',
            'to run this example');
        halt;
    end;
    if (r.bx = $ffff) then mouse_numbuttons := 2
    else mouse_numbuttons := r.bx;
    Writeln(mouse_numbuttons, ' button Microsoft compatible mouse ',
        ' found. ');
    if (userproc <> nil) then begin
        userproc_proc := userproc;
        userproc_installed := true;
        userproc_length := userproclen;
        lock_code(userproc_proc, userproc_length);
    end else begin
        userproc_proc := nil;
        userproc_length := 0;
        userproc_installed := false;
    end;
    lock_data(mouse_x, sizeof(mouse_x));
    lock_data(mouse_y, sizeof(mouse_y));
    lock_data(mouse_b, sizeof(mouse_b));
    lock_data(mouse_action, sizeof(mouse_action));

    lock_data(userproc_installed, sizeof(userproc_installed));
    lock_data(userproc_proc, sizeof(userproc_proc));

    lock_data(mouse_regs, sizeof(mouse_regs));
    lock_data(mouse_seginfo, sizeof(mouse_seginfo));
    lock_code(@callback_handler,
        longint(@mouse_dummy) - longint(@callback_handler));
    get_rm_callback(@callback_handler, mouse_regs, mouse_seginfo);
    r.eax := $0c; r.ecx := $7f;

```

---

```

    r.edx := longint(mouse_seginfo.offset);
    r.es := mouse_seginfo.segment;
    realintr(mouseint, r);
    r.eax := $01;
    realintr(mouseint, r);
end;

procedure remove_mouse;
var
    r : trealregs;
begin
    r.eax := $02; realintr(mouseint, r);
    r.eax := $0c; r.ecx := 0; r.edx := 0; r.es := 0;
    realintr(mouseint, r);
    free_rm_callback(mouse_seginfo);
    if (userproc_installed) then begin
        unlock_code(userproc_proc, userproc_length);
        userproc_proc := nil;
        userproc_length := 0;
        userproc_installed := false;
    end;
    unlock_data(mouse_x, sizeof(mouse_x));
    unlock_data(mouse_y, sizeof(mouse_y));
    unlock_data(mouse_b, sizeof(mouse_b));
    unlock_data(mouse_action, sizeof(mouse_action));

    unlock_data(userproc_proc, sizeof(userproc_proc));
    unlock_data(userproc_installed, sizeof(userproc_installed));

    unlock_data(mouse_regs, sizeof(mouse_regs));
    unlock_data(mouse_seginfo, sizeof(mouse_seginfo));
    unlock_code(@callback_handler,
        longint(@mouse_dummy) - longint(@callback_handler));
    fillchar(mouse_seginfo, sizeof(mouse_seginfo), 0);
end;

begin
    install_mouse(@textuserproc, 400);
    Writeln('Press any key to exit...');
    while (not keypressed) do begin
        gotoxy(1, wherey);
        write('MouseX : ', mouse_x:2, ' MouseY : ', mouse_y:2,
            ' Buttons : ', mouse_b:2);
    end;
    remove_mouse;
end.

```

---

### 16.18.27 get\_rm\_interrupt

Synopsis: Get real mode interrupt vector

Declaration: `function get_rm_interrupt(vector: Byte; var intaddr: tseginfo) : Boolean`

Visibility: default

Description: Returns the contents of the current machine's real mode interrupt vector for the specified interrupt.

Parameters:

**vector** interrupt vector number.

**intaddr** buffer to store real mode segment : offset address.

Return values: True if successful, False otherwise.

**Remark:** The returned address is a real mode segment address, which isn't valid in protected mode.

Errors: Check the `int31error` (574) variable.

See also: `set_rm_interrupt` (601), `set_pm_interrupt` (600), `get_pm_interrupt` (585)

### 16.18.28 get\_run\_mode

Synopsis: Return current run mode

Declaration: `function get_run_mode : Word`

Visibility: default

Description: Returns the current mode your application runs with.

Return values: One of the constants used by this function.

Errors: None.

See also: `get_run_mode` (589)

**Listing:** `./go32ex/getrunmd.pp`

---

```

uses
    go32;

begin
    case (get_run_mode) of
        rm_unknown :
            WriteLn('Unknown environment found');
        rm_raw :
            WriteLn('You are currently running in raw mode ',
                    '(without HIMEM)');
        rm_xms :
            WriteLn('You are currently using HIMEM.SYS only');
        rm_vcpi :
            WriteLn('VCPI server detected. You''re using HIMEM and ',
                    'EMM386');
        rm_dpml :
            WriteLn('DPML detected. You''re using a DPML host like ',
                    'a windows DOS box or CWSDPML');
    end;
end.
```

---

### 16.18.29 get\_segment\_base\_address

Synopsis: Return base address from descriptor table

Declaration: `function get_segment_base_address(d: Word) : LongInt`

Visibility: default

**Description:** Returns the 32-bit linear base address from the descriptor table for the specified segment.

**Parameters:**

**dselector** of the descriptor you want the base address of.

**Return values:** Linear base address of specified descriptor.

For an example, see `allocate_ldt_descriptors` (575).

**Errors:** Check the `int31error` (574) variable.

**See also:** `allocate_ldt_descriptors` (575), `set_segment_base_address` (602), `allocate_ldt_descriptors` (575), `set_segment_limit` (602), `get_segment_limit` (590)

### 16.18.30 `get_segment_limit`

**Synopsis:** Return segment limite from descriptor

**Declaration:** `function get_segment_limit(d: Word) : LongInt`

**Visibility:** default

**Description:** Returns a descriptors segment limit.

**Parameters:**

**dselector.**

**Return value:** Limit of the descriptor in bytes.

**Errors:** Returns zero if descriptor is invalid.

**See also:** `allocate_ldt_descriptors` (575), `set_segment_limit` (602), `set_segment_base_address` (602), `get_segment_base_address` (589)

### 16.18.31 `get_ss`

**Synopsis:** Return SS selector

**Declaration:** `function get_ss : Word`

**Visibility:** default

**Description:** Returns the ss selector.

**Return values:** The content of the ss segment register.

**Errors:** None.

**See also:** `get_ds` (582), `get_cs` (581)



**16.18.32 global\_dos\_alloc**

Synopsis: Allocate DOS real mode memory

Declaration: `function global_dos_alloc(bytes: LongInt) : LongInt`

Visibility: default

Description: Allocates a block of dos real mode memory.

Parameters:

**bytesize** of requested real mode memory.

Return values: The low word of the returned value contains the selector to the allocated dos memory block, the high word the corresponding real mode segment value. The offset value is always zero. This function allocates memory from dos memory pool, i.e. memory below the 1 MB boundary that is controlled by dos. Such memory blocks are typically used to exchange data with real mode programs, TSRs, or device drivers. The function returns both the real mode segment base address of the block and one descriptor that can be used by protected mode applications to access the block. This function should only be used for temporary buffers to get real mode information (e.g. interrupts that need a data structure in ES:(E)DI), because every single block needs a unique selector. The returned selector should only be freed by a `global_dos_free` (592) call.

Errors: Check the `int31error` (574) variable.

See also: `global_dos_free` (592)

**Listing:** `./go32ex/buffer.pp`

---

```

uses
    go32;

procedure dosalloc(var selector : word;
    var segment : word; size : longint);
var
    res : longint;
begin
    res := global_dos_alloc(size);
    selector := word(res);
    segment := word(res shr 16);
end;

procedure dosfree(selector : word);
begin
    global_dos_free(selector);
end;

type
    VBEInfoBuf = packed record
        Signature : array[0..3] of char;
        Version : Word;
        reserved : array[0..505] of byte;
    end;

var
    selector ,
    segment : Word;

    r : trealregs;

```

```

infobuf : VBEInfoBuf;

begin
  fillchar(r, sizeof(r), 0);
  fillchar(infobuf, sizeof(VBEInfoBuf), 0);
  dosalloc(selector, segment, sizeof(VBEInfoBuf));
  if (int31error <> 0) then begin
    Writeln('Error while allocating real mode memory, halting');
    halt;
  end;
  infobuf.Signature := 'VBE2';
  dosmemput(segment, 0, infobuf, sizeof(infobuf));
  r.ax := $4f00; r.es := segment;
  realintr($10, r);
  dosmemget(segment, 0, infobuf, sizeof(infobuf));
  dosfree(selector);
  if (r.ax <> $4f) then begin
    Writeln('VBE BIOS extension not available, function call ',
            'failed');
    halt;
  end;
  if (infobuf.signature[0] = 'V') and
    (infobuf.signature[1] = 'E') and
    (infobuf.signature[2] = 'S') and
    (infobuf.signature[3] = 'A') then begin
    Writeln('VBE version ', hi(infobuf.version), '.',
            lo(infobuf.version), ' detected');
  end;
end.

```

---

### 16.18.33 global\_dos\_free

Synopsis: Free DOS memory block

Declaration: `function global_dos_free(selector: Word) : Boolean`

Visibility: default

Description: Frees a previously allocated dos memory block.

Parameters:

**selector** selector to the dos memory block.

Return value: True if successful, False otherwise.

**Remark:** The descriptor allocated for the memory block is automatically freed and hence invalid for further use. This function should only be used for memory allocated by `global_dos_alloc` (591).

For an example, see `global_dos_alloc` (591).

Errors: Check the `int31error` (574) variable.

See also: `global_dos_alloc` (591)

### 16.18.34 inportb

Synopsis: Read byte from I/O port

**Declaration:** `function inportb(port: Word) : Byte`

**Visibility:** default

**Description:** Reads 1 byte from the selected I/O port.

**Parameters:**

**port** the I/O port number which is read.

**Return values:** Current I/O port value.

**Errors:** None.

See also: `outportb` ([595](#)), `inportw` ([593](#)), `inportl` ([593](#))

### 16.18.35 inportl

**Synopsis:** Read longint from I/O port

**Declaration:** `function inportl(port: Word) : LongInt`

**Visibility:** default

**Description:** Reads 1 longint from the selected I/O port.

**Parameters:**

**port** the I/O port number which is read.

**Return values:** Current I/O port value.

**Errors:** None.

See also: `outportb` ([595](#)), `inportb` ([592](#)), `inportw` ([593](#))

### 16.18.36 inportw

**Synopsis:** Read word from I/O port

**Declaration:** `function inportw(port: Word) : Word`

**Visibility:** default

**Description:** Reads 1 word from the selected I/O port.

**Parameters:**

**port** the I/O port number which is read.

**Return values:** Current I/O port value.

**Errors:** None.

See also: `outportw` ([596](#)), `inportb` ([592](#)), `inportl` ([593](#))

**16.18.37 lock\_code**

Synopsis: Lock code memory range

Declaration: `function lock_code(functionaddr: pointer;size: LongInt) : Boolean`

Visibility: default

Description: Locks a memory range which is in the code segment selector.

Parameters:

**functionaddr** address of the function to be locked.

**size** size in bytes to be locked.

Return values: `True` if successful, `False` otherwise.

For an example, see `get_rm_callback` (585).

Errors: Check the `int31error` (574) variable.

See also: `lock_linear_region` (594), `lock_data` (594), `unlock_linear_region` (604), `unlock_data` (604), `unlock_code` (604)

**16.18.38 lock\_data**

Synopsis: Lock data memory range

Declaration: `function lock_data(var data;size: LongInt) : Boolean`

Visibility: default

Description: Locks a memory range which resides in the data segment selector.

Parameters:

**data** address of data to be locked.

**size** length of data to be locked.

Return values: `True` if successful, `False` otherwise.

For an example, see `get_rm_callback` (585).

Errors: Check the `int31error` (574) variable.

See also: `lock_linear_region` (594), `lock_code` (594), `unlock_linear_region` (604), `unlock_data` (604), `unlock_code` (604)

**16.18.39 lock\_linear\_region**

Synopsis: Lock linear memory region

Declaration: `function lock_linear_region(linearaddr: LongInt;size: LongInt) : Boolean`

Visibility: default

Description: Locks a memory region to prevent swapping of it.

Parameters:

**linearaddr** the linear address of the memory are to be locked.

**size** size in bytes to be locked.

Return value: True if successful, False otherwise.

Errors: Check the `int31error` (574) variable.

See also: `lock_data` (594), `lock_code` (594), `unlock_linear_region` (604), `unlock_data` (604), `unlock_code` (604)

#### 16.18.40 map\_device\_in\_memory\_block

Synopsis: Map a device into program's memory space

Declaration: `function map_device_in_memory_block(handle: LongInt; offset: LongInt; pagecount: LongInt; device: LongInt) : Boolean`

Visibility: default

Description: `map_device_in_memory_block` allows to map a device in memory. This function is a direct call of the extender. For more information about it's arguments, see the extender documentation.

#### 16.18.41 outportb

Synopsis: Write byte to I/O port

Declaration: `procedure outportb(port: Word; data: Byte)`

Visibility: default

Description: Sends 1 byte of data to the specified I/O port.

Parameters:

**port** the I/O port number to send data to.

**data** value sent to I/O port.

Return values: None.

Errors: None.

See also: `inportb` (592), `outportl` (596), `outportw` (596)

**Listing:** `./go32ex/outport.pp`

---

```
uses
    crt ,
    go32;

begin
    outportb($61, $ff);
    delay(50);
    outportb($61, $0);
end.
```

---

**16.18.42 outportl**

Synopsis: Write longint to I/O port

Declaration: `procedure outportl(port: Word; data: LongInt)`

Visibility: default

Description: Sends 1 longint of data to the specified I/O port.

Parameters:

**port** the I/O port number to send data to.

**data** value sent to I/O port.

Return values: None.

For an example, see [outportb \(595\)](#).

Errors: None.

See also: [inportl \(593\)](#), [outportw \(596\)](#), [outportb \(595\)](#)

**16.18.43 outportw**

Synopsis: Write word to I/O port

Declaration: `procedure outportw(port: Word; data: Word)`

Visibility: default

Description: Sends 1 word of data to the specified I/O port.

Parameters:

**port** the I/O port number to send data to.

**data** value sent to I/O port.

Return values: None.

For an example, see [outportb \(595\)](#).

Errors: None.

See also: [inportw \(593\)](#), [outportl \(596\)](#), [outportb \(595\)](#)

**16.18.44 realintr**

Synopsis: Simulate interrupt

Declaration: `function realintr(intnr: Word; var regs: trealregs) : Boolean`

Visibility: default

Description: Simulates an interrupt in real mode.

Parameters:

**intnr** interrupt number to issue in real mode.

**regs** registers data structure.

Return values: The supplied registers data structure contains the values that were returned by the real mode interrupt. `True` if successful, `False` if not.

**Remark:** The function transfers control to the address specified by the real mode interrupt vector of `intr`. The real mode handler must return by executing an `IRET`.

Errors: Check the `int31error` (574) variable.

**Listing:** `./go32ex/flags.pp`

---

```

uses
    go32;

var
    r : trealregs;

begin
    r.ax := $5300;
    r.bx := 0;
    realintr($15, r);
    if ((r.flags and carryflag)=0) then begin
        WriteLn('APM v', (r.ah and $f), '.',
                (r.al shr 4), (r.al and $f), ' detected');
    end else
        WriteLn('APM not present');
end.

```

---

#### 16.18.45 request\_linear\_region

Synopsis: Request linear address region.

Declaration: `function request_linear_region(linearaddr: LongInt; size: LongInt; var blockhandle: LongInt) : Boolean`

Visibility: default

Description: `request_linear_region` requests a linear range of addresses of size `Size`, starting at `linearaddr`. If successful, `True` is returned, and a handle to the address region is returned in `blockhandle`.

Errors: On error, `False` is returned.

#### 16.18.46 segment\_to\_descriptor

Synopsis: Map segment address to descriptor

Declaration: `function segment_to_descriptor(seg: Word) : Word`

Visibility: default

Description: Maps a real mode segment (paragraph) address onto an descriptor that can be used by a protected mode program to access the same memory.

Parameters:

**seg** the real mode segment you want the descriptor to.

Return values: Descriptor to real mode segment address.

**Remark:** The returned descriptors limit will be set to 64 kB. Multiple calls to this function with the same segment address will return the same selector. Descriptors created by this function can never be modified or freed. Programs which need to examine various real mode addresses using the same selector should use the function `allocate_ldt_descriptors` (575) and change the base address as necessary.

For an example, see `seg_fillchar` (598).

Errors: Check the `int31error` (574) variable.

See also: `allocate_ldt_descriptors` (575), `free_ldt_descriptor` (580), `set_segment_base_address` (602)

### 16.18.47 `seg_fillchar`

Synopsis: Fill segment with byte value

Declaration: `procedure seg_fillchar(seg: Word; ofs: LongInt; count: LongInt; c: Char)`

Visibility: default

Description: Sets a memory area to a specific value.

Parameters:

**seg** selector to memory area.

**ofs** offset to memory.

**count** number of bytes to set.

**c** byte data which is set.

Return values: None.

Notes: No range check is done in any way.

Errors: None.

See also: `seg_move` (599), `seg_fillword` (599), `dosmemfillchar` (571), `dosmemfillword` (571), `dosmemget` (572), `dosmemput` (572), `dosmemmove` (572)

**Listing:** `./go32ex/vgasel.pp`

---

```

uses
    go32;

var
    vgasel : Word;
    r : trealregs;

begin
    r.eax := $13; realintr($10, r);
    vgasel := segment_to_descriptor($A000);
    seg_fillchar(vgasel, 0, 64000, #15);
    readln;
    r.eax := $3; realintr($10, r);
end.

```

---



**16.18.48 seg\_fillword**

Synopsis: Fill segment with word value

Declaration: `procedure seg_fillword(seg: Word; ofs: LongInt; count: LongInt; w: Word)`

Visibility: default

Description: Sets a memory area to a specific value.

Parameters:

**seg** selector to memory area.

**ofs** offset to memory.

**count** number of words to set.

**w** word data which is set.

Return values: None.

Notes: No range check is done in any way.

For an example, see `allocate_ldt_descriptors` (575).

Errors: None.

See also: `seg_move` (599), `seg_fillchar` (598), `dosmemfillchar` (571), `dosmemfillword` (571), `dosmemget` (572), `dosmemput` (572), `dosmemmove` (572)

**16.18.49 seg\_move**

Synopsis: Move data between 2 locations

Declaration: `procedure seg_move(sseg: Word; source: LongInt; dseg: Word; dest: LongInt; count: LongInt)`

Visibility: default

Description: Copies data between two memory locations.

Parameters:

**sseg** source selector.

**source** source offset.

**dseg** destination selector.

**dest** destination offset.

**count** size in bytes to copy.

Return values: None.

**Remark:** Overlapping is only checked if the source selector is equal to the destination selector. No range check is done.

For an example, see `allocate_ldt_descriptors` (575).

Errors: None.

See also: `seg_fillchar` (598), `seg_fillword` (599), `dosmemfillchar` (571), `dosmemfillword` (571), `dosmemget` (572), `dosmemput` (572), `dosmemmove` (572)

### 16.18.50 set\_descriptor\_access\_right

Synopsis: Set access rights to memory descriptor

Declaration: `function set_descriptor_access_right(d: Word;w: Word) : LongInt`

Visibility: default

Description: `set_descriptor_access_right` sets the access rights for descriptor `d` to `w`

### 16.18.51 set\_exception\_handler

Synopsis: Set exception handler

Declaration: `function set_exception_handler(e: Byte;const intaddr: tseginfo)  
: Boolean`

Visibility: default

Description: `set_exception_handler` sets the exception handler for exception `E` to `intaddr`. It returns `True` if the call was successful, `False` if not.

See also: `get_exception_handler` ([582](#)), `set_pm_exception_handler` ([600](#))

### 16.18.52 set\_pm\_exception\_handler

Synopsis: Set protected mode exception handler

Declaration: `function set_pm_exception_handler(e: Byte;const intaddr: tseginfo)  
: Boolean`

Visibility: default

Description: `set_pm_exception_handler` sets the protected mode exception handler for exception `E` to `intaddr`. It returns `True` if the call was successful, `False` if not.

See also: `set_exception_handler` ([600](#)), `get_pm_exception_handler` ([585](#))

### 16.18.53 set\_pm\_interrupt

Synopsis: Set protected mode interrupt handler

Declaration: `function set_pm_interrupt(vector: Byte;const intaddr: tseginfo)  
: Boolean`

Visibility: default

Description: Sets the address of the protected mode handler for an interrupt.

Parameters:

**vector** number of protected mode interrupt to set.

**intaddr** selector:offset address to the interrupt vector.

Return values: `True` if successful, `False` otherwise.

**Remark:** The address supplied must be a valid `selector:offset` protected mode address.

Errors: Check the `int31error` ([574](#)) variable.

See also: [get\\_pm\\_interrupt \(585\)](#), [set\\_rm\\_interrupt \(601\)](#), [get\\_rm\\_interrupt \(588\)](#)

**Listing:** ./go32ex/intpm.pp

```

uses
    crt ,
    go32;

const
    int1c = $1c;

var
    oldint1c : tseginfo;
    newint1c : tseginfo;

    int1c_counter : Longint;

    int1c_ds : Word; external name '___v2prt0_ds_alias';

procedure int1c_handler; assembler;
asm
    cli
    pushw %ds
    pushw %ax
    movw %cs:int1c_ds, %ax
    movw %ax, %ds
    incl int1c_counter
    popw %ax
    popw %ds
    sti
    iret
end;

var i : Longint;

begin
    newint1c.offset := @int1c_handler;
    newint1c.segment := get_cs;
    get_pm_interrupt(int1c, oldint1c);
    WriteLn('-- Press any key to exit --');
    set_pm_interrupt(int1c, newint1c);
    while (not keypressed) do begin
        gotoxy(1, wherey);
        write('Number of interrupts occurred : ', int1c_counter);
    end;
    set_pm_interrupt(int1c, oldint1c);
end.

```

### 16.18.54 set\_rm\_interrupt

## Synopsis: Set real mode interrupt handler

```
Declaration: function set_rm_interrupt(vector: Byte;const intaddr: tseginfo)
                                         : Boolean
```

Visibility: default

Description: Sets a real mode interrupt handler.

Parameters:

**vector** the interrupt vector number to set.

**intaddr** address of new interrupt vector.

Return values: `True` if successful, otherwise `False`.

**Remark:** The address supplied MUST be a real mode segment address, not a `selector:offset` address. So the interrupt handler must either reside in dos memory (below 1 Mb boundary) or the application must allocate a real mode callback address with `get_rm_callback` (585).

Errors: Check the `int31error` (574) variable.

See also: `get_rm_interrupt` (588), `set_pm_interrupt` (600), `get_pm_interrupt` (585), `get_rm_callback` (585)

### 16.18.55 set\_segment\_base\_address

Synopsis: Set descriptor's base address

Declaration: `function set_segment_base_address(d: Word; s: LongInt) : Boolean`

Visibility: default

Description: Sets the 32-bit linear base address of a descriptor.

Parameters:

**d** selector.

**s** new base address of the descriptor.

Errors: Check the `int31error` (574) variable.

See also: `allocate_ldt_descriptors` (575), `get_segment_base_address` (589), `allocate_ldt_descriptors` (575), `set_segment_limit` (602), `get_segment_base_address` (589), `get_segment_limit` (590)

### 16.18.56 set\_segment\_limit

Synopsis: Set descriptor limit

Declaration: `function set_segment_limit(d: Word; s: LongInt) : Boolean`

Visibility: default

Description: Sets the limit of a descriptor.

Parameters:

**d** selector.

**s** new limit of the descriptor.

Return values: Returns `True` if successful, else `False`.

**Remark:** The new limit specified must be the byte length of the segment - 1. Segment limits bigger than or equal to 1MB must be page aligned, they must have the lower 12 bits set.

For an example, see `allocate_ldt_descriptors` (575).

Errors: Check the `int31error` (574) variable.

See also: `allocate_ldt_descriptors` (575), `set_segment_base_address` (602), `get_segment_limit` (590), `set_segment_limit` (602)

### 16.18.57 `tb_offset`

Synopsis: Return DOS transfer buffer offset

Declaration: `function tb_offset : LongInt`

Visibility: default

Description: `tb_offset` returns the DOS transfer buffer segment.

See also: `transfer_buffer` (603), `tb_segment` (603), `tb_size` (603)

### 16.18.58 `tb_segment`

Synopsis: Return DOS transfer buffer segment

Declaration: `function tb_segment : LongInt`

Visibility: default

Description: `tb_segment` returns the DOS transfer buffer segment.

See also: `transfer_buffer` (603), `tb_offset` (603), `tb_size` (603)

### 16.18.59 `tb_size`

Synopsis: Return DOS transfer memory buffer size

Declaration: `function tb_size : LongInt`

Visibility: default

Description: Returns the size of the pre-allocated dos memory buffer.

Return values: The size of the pre-allocated dos memory buffer. This block always seems to be 16k in size, but don't rely on this.

Errors: None.

See also: `transfer_buffer` (603), `copyfromdos` (577), `copytodos` (578)

### 16.18.60 `transfer_buffer`

Synopsis: Return offset of DOS transfer buffer

Declaration: `function transfer_buffer : LongInt`

Visibility: default

Description: `transfer_buffer` returns the offset of the transfer buffer.

Errors: None.

See also: `tb_size` (603)

### 16.18.61 unlock\_code

Synopsis: Unlock code segment

Declaration: `function unlock_code(functionaddr: pointer;size: LongInt) : Boolean`

Visibility: default

Description: Unlocks a memory range which resides in the code segment selector.

Parameters:

**functionaddr** address of function to be unlocked.

**size** size bytes to be unlocked.

Return value: `True` if successful, `False` otherwise.

For an example, see `get_rm_callback` (585).

Errors: Check the `int31error` (574) variable.

See also: `unlock_linear_region` (604), `unlock_data` (604), `lock_linear_region` (594), `lock_data` (594), `lock_code` (594)

### 16.18.62 unlock\_data

Synopsis: Unlock data segment

Declaration: `function unlock_data(var data;size: LongInt) : Boolean`

Visibility: default

Description: Unlocks a memory range which resides in the data segment selector.

Parameters:

**data** address of memory to be unlocked.

**size** size bytes to be unlocked.

Return values: `True` if successful, `False` otherwise.

For an example, see `get_rm_callback` (585).

Errors: Check the `int31error` (574) variable.

See also: `unlock_linear_region` (604), `unlock_code` (604), `lock_linear_region` (594), `lock_data` (594), `lock_code` (594)

### 16.18.63 unlock\_linear\_region

Synopsis: Unlock linear memory region

Declaration: `function unlock_linear_region(linearaddr: LongInt;size: LongInt)  
: Boolean`

Visibility: default

Description: Unlocks a previously locked linear region range to allow it to be swapped out again if needed.

Parameters:

**linearaddr** linear address of the memory to be unlocked.

**size**size bytes to be unlocked.

Return values: `True` if successful, `False` otherwise.

Errors: Check the `int31error` (574) variable.

See also: `unlock_data` (604), `unlock_code` (604), `lock_linear_region` (594), `lock_data` (594), `lock_code` (594)

## Chapter 17

# Reference for unit 'gpm'

### 17.1 Used units

Table 17.1: Used units by unit 'gpm'

Name	Page
baseUnix	<a href="#">606</a>

### 17.2 Overview

The GPM unit implements an interface to `libgpm`, the console program for mouse handling. This unit was created by Peter Vreman, and is only available on linux.

When this unit is used, your program is linked to the C libraries, so you must take care of the C library version. Also, it will only work with version 1.17 or higher of the `libgpm` library.

### 17.3 Constants, types and variables

#### 17.3.1 Constants

`GPM_BOT` = 2

Bottom of area.

`GPM_B_LEFT` = 4

Left mouse button identifier.

`GPM_B_MIDDLE` = 2

Middle mouse button identifier.

`GPM_B_RIGHT` = 1



Right mouse button identifier.

GPM\_DOUBLE = 32

Mouse double click event.

GPM\_DOWN = 4

Mouse button down event.

GPM\_DRAG = 2

Mouse drag event.

GPM\_ENTER = 512

Enter area event.

GPM\_HARD = 256

?

GPM\_LEAVE = 1024

Leave area event.

GPM\_LEFT = 4

Left side of area.

GPM\_MAGIC = \$47706D4C

Constant identifying GPM in gpm\_Open ([614](#)).

GPM\_MFLAG = 128

Motion flag.

GPM\_MOVE = 1

Mouse move event.

GPM\_NODE\_CTL = GPM\_NODE\_DEV

Control socket

GPM\_NODE\_DEV = '/dev/gpmctl'

Device socket filename

GPM\_NODE\_DIR = \_PATH\_VARRUN

Where to write socket.

`GPM_NODE_DIR_MODE = 0775`

Mode of socket.

`GPM_NODE_FIFO = '/dev/gpmdata'`

FIFO name

`GPM_NODE_PID = '/var/run/gpm.pid'`

Name of PID file.

`GPM_RGT = 8`

Right side of area.

`GPM_SINGLE = 16`

Mouse single click event.

`GPM_TOP = 1`

Top of area.

`GPM_TRIPLE = 64`

Mouse triple click event.

`GPM_UP = 8`

Mouse button up event.

`_PATH_DEV = '/dev/'`

Location of `/dev` directory.

`_PATH_VARRUN = '/var/run/'`

Location of run PID files directory.

### 17.3.2 Types

`Pgpmconnect = Pgpm_connect`

Pointer to `TGpmConnect` (610) record.

`Pgpmevent = Pgpm_event`

Pointer to TGpmEvent (610) record

```
Pgpmroi = Pgpm_roi
```

Pointer to TGpmRoi (610) record.

```
Pgpm_connect = ^TGpm_connect
```

Pointer to TGpm\_Connect (610) record.

```
Pgpm_event = ^Tgpm_event
```

Pointer to TGpm\_Event (610) record

```
Pgpm_roi = ^Tgpm_roi
```

Pointer to Tgpm\_roi (610) record.

```
Tgpmconnect = Tgpm_connect
```

Alias for TGpm\_Connect (610) record.

```
TGpmEtype = LongInt
```

Type for event type.

```
Tgpmevent = Tgpm_event
```

Alias for TGPM\_EVent (610) record

```
TGpmHandler = function(var event: Tgpmevent; clientdata: pointer)
                  : LongInt of object
```

Mouse event handler callback.

```
TGpmMargin = LongInt
```

Type to hold area margin.

```
Tgpmroi = Tgpm_roi
```

Alias for TGpm\_roi (610)Record

```
Tgpm_connect = packed record
  eventMask : Word;
  defaultMask : Word;
  minMod : Word;
  maxMod : Word;
  pid : LongInt;
  vc : LongInt;
end
```

GPM server connection information.

```
Tgpm_event = packed record
  buttons : Byte;
  modifiers : Byte;
  vc : Word;
  dx : Word;
  dy : Word;
  x : Word;
  y : Word;
  EventType : TGpmEtype;
  clicks : LongInt;
  margin : TGpmMargin;
  wdx : Word;
  wdy : Word;
end
```

Tgpm\_event describes the events that are reported by GPM.

```
Tgpm_roi = packed record
  xmin : Integer;
  xmax : Integer;
  ymin : Integer;
  ymax : Integer;
  minmod : Word;
  maxmod : Word;
  eventmask : Word;
  owned : Word;
  handler : TGpmHandler;
  clientdata : pointer;
  prev : Pgpm_roi;
  next : Pgpm_roi;
end
```

Record used to define regions of interest.

### 17.3.3 Variables

```
gpm_current_roi : Pgpm_roi
```

Internal gpm library variable. Do not use.

```
gpm_handler : TGpmHandler
```

Internal gpm library variable. Do not use.

```
gpm_roi : Pgpm_roi
```

Internal gpm library variable. Do not use.

```
gpm_roi_data : pointer
```

Internal gpm library variable. Do not use.

`gpm_roi_handler` : `TGpmHandler`

Internal gpm library variable. Do not use.

## 17.4 Procedures and functions

### 17.4.1 `Gpm_AnyDouble`

Synopsis: Check whether event has double click event.

Declaration: `function Gpm_AnyDouble(EventType: LongInt) : Boolean`

Visibility: default

Description: `Gpm_AnyDouble` returns `True` if `EventType` contains the `GPM_DOUBLE` flag, `False` otherwise.

Errors: None.

See also: `Gpm_StrictSingle` (616), `Gpm_AnySingle` (611), `Gpm_StrictDouble` (616), `Gpm_StrictTriple` (616), `Gpm_AnyTriple` (611)

### 17.4.2 `Gpm_AnySingle`

Synopsis: Check whether event has a single click event.

Declaration: `function Gpm_AnySingle(EventType: LongInt) : Boolean`

Visibility: default

Description: `Gpm_AnySingle` returns `True` if `EventType` contains the `GPM_SINGLE` flag, `False` otherwise.

Errors: None.

See also: `Gpm_StrictSingle` (616), `Gpm_AnyDouble` (611), `Gpm_StrictDouble` (616), `Gpm_StrictTriple` (616), `Gpm_AnyTriple` (611)

### 17.4.3 `Gpm_AnyTriple`

Synopsis: Check whether event has a triple click event.

Declaration: `function Gpm_AnyTriple(EventType: LongInt) : Boolean`

Visibility: default

Description: `Gpm_AnySingle` returns `True` if `EventType` contains the `GPM_TRIPLE` flag, `False` otherwise.

Errors: None.

See also: `Gpm_StrictSingle` (616), `Gpm_AnyDouble` (611), `Gpm_StrictDouble` (616), `Gpm_StrictTriple` (616), `Gpm_AnySingle` (611)

#### 17.4.4 gpm\_close

Synopsis: Close connection to GPM server.

Declaration: `function gpm_close : LongInt`

Visibility: default

Description: `Gpm_Close` closes the current connection, and pops the connection stack; this means that the previous connection becomes active again.

The function returns -1 if the current connection is not the last one, and it returns 0 if the current connection is the last one.

for an example, see `Gpm_GetEvent` (612).

Errors: None.

See also: `Gpm_Open` (614)

#### 17.4.5 gpm\_fitvalues

Synopsis: Change coordinates to fit physical screen.

Declaration: `function gpm_fitvalues(var x: LongInt;var y: LongInt) : LongInt`

Visibility: default

Description: `Gpm_fitValues` changes `x` and `y` so they fit in the visible screen. The actual mouse pointer is not affected by this function.

Errors: None.

See also: `Gpm_FitValuesM` (612)

#### 17.4.6 gpm\_fitvaluesM

Synopsis: Change coordinates to fit margin.

Declaration: `function gpm_fitvaluesM(var x: LongInt;var y: LongInt;margin: LongInt) : LongInt`

Visibility: default

Description: `Gpm_FitValuesM` changes `x` and `y` so they fit in the margin indicated by `margin`. If `margin` is -1, then the values are fitted to the screen. The actual mouse pointer is not affected by this function.

Errors: None.

See also: `Gpm_FitValues` (612)

#### 17.4.7 gpm\_getevent

Synopsis: Get event from event queue.

Declaration: `function gpm_getevent(var event: Tgpm_event) : LongInt`

Visibility: default

**Description:** `Gpm_GetEvent` Reads an event from the file descriptor `gpm_fd`. This file is only for internal use and should never be called by a client application.

It returns 1 on succes, and -1 on failue.

**Errors:** On error, -1 is returned.

See also: `Gpm_GetSnapshot` (614)

**Listing:** `./gpmex/gpmex.pp`

---

```

program gpmex;

{
  Example program to demonstrate the use of the gpm unit.
}

uses gpm;

var
  connect : TGPMConnect;
  event : tgpmevent;

begin
  connect.EventMask:=GPM_MOVE or GPM_DRAG or GPM_DOWN or GPM_UP;
  connect.DefaultMask:=0;
  connect.MinMod:=0;
  connect.MaxMod:=0;
  if Gpm_Open(connect,0)=-1 then
    begin
      Writeln('No mouse handler present. ');
      Halt(1);
    end;
  Writeln('Click right button to end. ');
  Repeat
    gpm_getevent(Event);
    With Event do
      begin
        Write('Pos = ( ',X,', ',Y,', ') Buttons : ( ');
        if (buttons and Gpm_b_left)<>0 then
          write('left ');
        if (buttons and Gpm_b_right)<>0 then
          write('right ');
        if (buttons and Gpm_b_middle)<>0 then
          Write('middle ');
        Write(') Event : ');
        Case EventType and $F of
          GPM_MOVE: write('Move');
          GPM_DRAG: write('Drag');
          GPM_DOWN: write('Down');
          GPM_UP: write('Up');
        end;
        Writeln;
      end;
    Until (Event.Buttons and gpm_b_right)<>0;
    gpm_close;
  end.

```

---

### 17.4.8 gpm\_getsnapshot

Synopsis: Return servers' current image of mouse state.

Declaration: `function gpm_getsnapshot (eptr: Pgpmevent) : LongInt`  
`function gpm_getsnapshot (var eptr: Tgpmevent) : LongInt`

Visibility: default

Description: `Gpm_GetSnapshot` returns the picture that the server has of the current situation in `Event`. This call will not read the current situation from the mouse file descriptor, but returns a buffered version.

The function returns the number of mouse buttons, or -1 if this information is not available.

Errors: None.

See also: `Gpm_GetEvent` (612)

### 17.4.9 gpm\_lowerroi

Synopsis: Lower a region of interest in the stack.

Declaration: `function gpm_lowerroi (which: Pgpm_roi; after: Pgpm_roi) : Pgpm_roi`

Visibility: default

Description: `Gpm_LowerRoi` lowers the region of interest `which` after `after`. If `after` is `Nil`, the region of interest is moved to the bottom of the stack.

The return value is the new top of the region-of-interest stack.

Errors: None.

See also: `Gpm_RaiseRoi` (615), `Gpm_PopRoi` (615), `Gpm_PushRoi` (615)

### 17.4.10 gpm\_open

Synopsis: Open connection to GPM server.

Declaration: `function gpm_open (var conn: Tgpm_connect; flag: LongInt) : LongInt`

Visibility: default

Description: `Gpm_Open` opens a new connection to the mouse server. The connection is described by the fields of the `conn` record of type `TGPMConnect` (610).

if `Flag` is 0, then the application only receives events that come from its own terminal device. If it is negative it will receive all events. If the value is positive then it is considered a console number to which to connect.

The return value is -1 on error, or the file descriptor used to communicate with the client. Under an X-Term the return value is -2.

for an example, see `Gpm_GetEvent` (612).

Errors: On Error, the return value is -1.

See also: `Gpm_Open` (614)



### 17.4.11 gpm\_poproi

Synopsis: Pop region of interest from the stack.

Declaration: `function gpm_poproi(which: Pgpm_roi) : Pgpm_roi`

Visibility: default

Description: `Gpm_PopRoi` pops the topmost region of interest from the stack. It returns the next element on the stack, or `Nil` if the current element was the last one.

Errors: None.

See also: `Gpm_RaiseRoi` (615), `Gpm_LowerRoi` (614), `Gpm_PushRoi` (615)

### 17.4.12 gpm\_pushroi

Synopsis: Push region of interest on the stack.

Declaration: `function gpm_pushroi(x1: LongInt; y1: LongInt; x2: LongInt; y2: LongInt; mask: LongInt; fun: TGpmHandler; xtradata: pointer) : Pgpm_roi`

Visibility: default

Description: `Gpm_PushRoi` puts a new *region of interest* on the stack. The region of interest is defined by a rectangle described by the corners (X1, Y1) and (X2, Y2).

The mask describes which events the handler {fun} will handle; `ExtraData` will be put in the `xtradata` field of the {TGPM\_Roi} record passed to the fun handler.

Errors: None.

See also: `Gpm_RaiseRoi` (615), `Gpm_PopRoi` (615), `Gpm_LowerRoi` (614)

### 17.4.13 gpm\_raiseroi

Synopsis: Raise region of interest in the stack.

Declaration: `function gpm_raiseroi(which: Pgpm_roi; before: Pgpm_roi) : Pgpm_roi`

Visibility: default

Description: `Gpm_RaiseRoi` raises the *region of interest* which till it is on top of region before. If before is nil then the region is put on top of the stack. The returned value is the top of the stack.

Errors: None.

See also: `Gpm_PushRoi` (615), `Gpm_PopRoi` (615), `Gpm_LowerRoi` (614)

### 17.4.14 gpm\_repeat

Synopsis: Check for presence of mouse event.

Declaration: `function gpm_repeat(millisec: LongInt) : LongInt`

Visibility: default

Description: `Gpm_Repeat` returns 1 if no mouse event arrives in the next `millisec` milliseconds, it returns 0 otherwise.

Errors: None.

See also: [Gpm\\_GetEvent \(612\)](#)

### 17.4.15 Gpm\_StrictDouble

Synopsis: Check whether event contains only a double-click event.

Declaration: `function Gpm_StrictDouble(EventType: LongInt) : Boolean`

Visibility: default

Description: `Gpm_StrictDouble` returns `true` if `EventType` contains only a doubleclick event, `False` otherwise.

Errors: None.

See also: [Gpm\\_StrictSingle \(616\)](#), [Gpm\\_AnyTriple \(611\)](#), [Gpm\\_AnyDouble \(611\)](#), [Gpm\\_StrictTriple \(616\)](#), [Gpm\\_AnySingle \(611\)](#)

### 17.4.16 Gpm\_StrictSingle

Synopsis: Check whether event contains only a single-click event.

Declaration: `function Gpm_StrictSingle(EventType: LongInt) : Boolean`

Visibility: default

Description: `Gpm_StrictSingle` returns `True` if `EventType` contains only a singleclick event, `False` otherwise.

Errors: None.

See also: [Gpm\\_AnyTriple \(611\)](#), [Gpm\\_StrictDouble \(616\)](#), [Gpm\\_AnyDouble \(611\)](#), [Gpm\\_StrictTriple \(616\)](#), [Gpm\\_AnySingle \(611\)](#)

### 17.4.17 Gpm\_StrictTriple

Synopsis: Check whether event contains only a triple-click event.

Declaration: `function Gpm_StrictTriple(EventType: LongInt) : Boolean`

Visibility: default

Description: `Gpm_StrictTriple` returns `true` if `EventType` contains only a triple click event, `False` otherwise.

Errors: None.

See also: [Gpm\\_AnyTriple \(611\)](#), [Gpm\\_StrictDouble \(616\)](#), [Gpm\\_AnyDouble \(611\)](#), [Gpm\\_StrictSingle \(616\)](#), [Gpm\\_AnySingle \(611\)](#)

## Chapter 18

# Reference for unit 'Graph'

### 18.1 Overview

This document describes the `GRAPH` unit for Free Pascal, for all platforms. The unit was first written for dos by Florian Klaempfl, but was later completely rewritten by Carl-Eric Codere to be completely portable. The unit is provided for compatibility only: It is recommended to use more modern graphical systems. The graph unit will allow to recompile old programs. They will work to some extent, but if the application has heavy graphical needs, it's recommended to use another set of graphical routines, suited to the platform the program should work on.

### 18.2 Categorized functions: Text and font handling

Functions to set texts on the screen.

Table 18.1:

Name	Description
<code>GetTextSettings</code> ( <a href="#">652</a> )	Get current text settings
<code>InstallUserFont</code> ( <a href="#">655</a> )	Install a new font
<code>OutText</code> ( <a href="#">656</a> )	Write text at current cursor position
<code>OutTextXY</code> ( <a href="#">643</a> )	Write text at coordinates X,Y
<code>RegisterBGIFont</code> ( <a href="#">658</a> )	Register a new font
<code>SetTextJustify</code> ( <a href="#">661</a> )	Set text justification
<code>SetTextStyle</code> ( <a href="#">662</a> )	Set text style
<code>SetUserCharSize</code> ( <a href="#">662</a> )	Set text size
<code>TextHeight</code> ( <a href="#">663</a> )	Calculate height of text
<code>TextWidth</code> ( <a href="#">663</a> )	Calculate width of text

### 18.3 Categorized functions: Filled drawings

Functions for drawing filled regions.

Table 18.2:

Name	Description
Bar3D (645)	Draw a filled 3D-style bar
Bar (645)	Draw a filled rectangle
FloodFill (647)	Fill starting from coordinate
FillEllipse (646)	Draw a filled ellipse
FillPoly (647)	Draw a filled polygone
GetFillPattern (649)	Get current fill pattern
GetFillSettings (649)	Get current fill settings
SetFillPattern (659)	Set current fill pattern
SetFillStyle (660)	Set current fill settings

## 18.4 Categorized functions: Drawing primitives

Functions for simple drawing.

Table 18.3:

Name	Description
Arc (644)	Draw an arc
Circle (642)	Draw a complete circle
DrawPoly (646)	Draw a polygone with N points
Ellipse (646)	Draw an ellipse
GetArcCoords (647)	Get arc coordinates
GetLineSettings (650)	Get current line drawing settings
Line (643)	Draw line between 2 points
LineRel (655)	Draw line relative to current position
LineTo (656)	Draw line from current position to absolute position
MoveRel (656)	Move cursor relative to current position
MoveTo (656)	Move cursor to absolute position
PieSlice (657)	Draw a pie slice
PutPixel (644)	Draw 1 pixel
Rectangle (657)	Draw a non-filled rectangle
Sector (658)	Draw a sector
SetLineStyle (660)	Set current line drawing style

## 18.5 Categorized functions: Color management

All functions related to color management.

## 18.6 Categorized functions: Screen management

General drawing screen management functions.

Table 18.4:

Name	Description
GetBkColor (648)	Get current background color
GetColor (648)	Get current foreground color
GetDefaultPalette (648)	Get default palette entries
GetMaxColor (650)	Get maximum valid color
GetPaletteSize (652)	Get size of palette for current mode
GetPixel (643)	Get color of selected pixel
GetPalette (652)	Get palette entry
SetAllPalette (644)	Set all colors in palette
SetBkColor (659)	Set background color
SetColor (659)	Set foreground color
SetPalette (661)	Set palette entry
SetRGBPalette (644)	Set palette entry with RGB values

Table 18.5:

Name	Description
ClearViewPort (642)	Clear the current viewport
GetImage (642)	Copy image from screen to memory
GetMaxX (651)	Get maximum X coordinate
GetMaxY (651)	Get maximum Y coordinate
GetX (653)	Get current X position
GetY (653)	Get current Y position
ImageSize (643)	Get size of selected image
GetViewSettings (652)	Get current viewport settings
PutImage (643)	Copy image from memory to screen
SetActivePage (644)	Set active video page
SetAspectRatio (658)	Set aspect ratio for drawing routines
SetViewPort (663)	Set current viewport
SetVisualPage (644)	Set visual page
SetWriteMode (663)	Set write mode for screen operations

## 18.7 Categorized functions: Initialization

Initialization of the graphics screen.

## 18.8 Target specific issues: Linux

There are several issues on Linux that need to be taken care of:

The Linux version of the Graph unit uses the `libvga` library. This library works on the console, not under X.

If you get an error similar to

```
/usr/bin/ld: cannot find -lvga
```

This can mean one of two things: either `libvga` and its development package is not installed properly, or the directory where it is installed is not in the linker path.

Table 18.6:

Name	Description
ClearDevice (645)	Empty the graphics screen
CloseGraph (645)	Finish drawing session, return to text mode
DetectGraph (646)	Detect graphical modes
GetAspectRatio (648)	Get aspect ratio of screen
GetModeRange (651)	Get range of valid modes for current driver
GraphDefaults (653)	Set defaults
GetDriverName (649)	Return name of graphical driver
GetGraphMode (650)	Return current or last used graphics mode
GetMaxMode (650)	Get maximum mode for current driver
GetModeName (651)	Get name of current mode
GraphErrorMsg (653)	String representation of graphical error
GraphResult (654)	Result of last drawing operation
InitGraph (654)	Initialize graphics drivers
InstallUserDriver (655)	Install a new driver
RegisterBGIDriver (657)	Register a new driver
RestoreCRTMode (658)	Go back to text mode
SetGraphMode (660)	Set graphical mode

To remedy the former, you should install both the `libvga` package and `libvga-devel` package (or compile and install from scratch).

To remedy the latter, you should add the path to the compiler command-line using the `-F1` option.

Programs using `libvga` need root privileges to run. You can make them `setuid` root with the following command:

```
chown root.root myprogram
chmod u+s myprogram
```

The `libvga` library will give up the root privileges after it is initialized.

there is an experimental version of the Graphics library available that uses GGI to do all the drawing, but it is not well tested. It's called `ggigraph` and is distributed in source form only.

Do not use the CRT unit together with the Graph unit: the console may end up in an unusable state. Instead, the `ncurses` unit may function fine.

## 18.9 Target specific issues: DOS

VESA modes (i.e., anything but 320x200x256 and 640x480x16) do not work under most installations of Windows NT, Windows 2000 and Windows XP. They also do not work for some people under Windows 98 and Windows ME, depending on their graphics drivers. However, the graph unit cannot detect this, because no errors are returned from the system. In such cases, the screen simply turns black, or will show garbage.

Nothing can be done about this, the reason is missing or buggy support in the graphics drivers of the operating system.

## 18.10 A word about mode selection

The graph unit was implemented for compatibility with the old Turbo Pascal graph unit. For this reason, the mode constants as they were defined in the Turbo Pascal graph unit are retained.

However, since

1. Video cards have evolved very much
2. Free Pascal runs on multiple platforms

it was decided to implement new mode and graphic driver constants, which are more independent of the specific platform the program runs on.

In this section we give a short explanation of the new mode system. the following drivers were defined:

```
D1bit = 11;
D2bit = 12;
D4bit = 13;
D6bit = 14; { 64 colors Half-brite mode - Amiga }
D8bit = 15;
D12bit = 16; { 4096 color modes HAM mode - Amiga }
D15bit = 17;
D16bit = 18;
D24bit = 19; { not yet supported }
D32bit = 20; { not yet supported }
D64bit = 21; { not yet supported }

lowNewDriver = 11;
highNewDriver = 21;
```

Each of these drivers specifies a desired color-depth.

The following modes have been defined:

```
detectMode = 30000;
m320x200 = 30001;
m320x256 = 30002; { amiga resolution (PAL) }
m320x400 = 30003; { amiga/atari resolution }
m512x384 = 30004; { mac resolution }
m640x200 = 30005; { vga resolution }
m640x256 = 30006; { amiga resolution (PAL) }
m640x350 = 30007; { vga resolution }
m640x400 = 30008;
m640x480 = 30009;
m800x600 = 30010;
m832x624 = 30011; { mac resolution }
m1024x768 = 30012;
m1280x1024 = 30013;
m1600x1200 = 30014;
m2048x1536 = 30015;

lowNewMode = 30001;
highNewMode = 30015;
```

These modes start at 30000 because Borland specified that the mode number should be ascending with increasing X resolution, and the new constants shouldn't interfere with the old ones.

The above constants can be used to set a certain color depth and resolution, as demonstrated in the below example.

If other modes than the ones above are supported by the graphics card, you will not be able to select them with this mechanism.

For this reason, there is also a 'dynamic' mode number, which is assigned at run-time. This number increases with increasing X resolution. It can be queried with the `getmoderange` call. This call will return the range of modes which are valid for a certain graphics driver. The numbers are guaranteed to be consecutive, and can be used to search for a certain resolution, as in the second example below.

Thus, the `getmoderange` function can be used to detect all available modes and drivers, as in the third example below:

## 18.11 Requirements

The unit `Graph` exports functions and procedures for graphical output. It requires at least a VGA-compatible Card or a VGA-Card with software-driver (min. **512Kb** video memory).

## 18.12 Constants, types and variables

### 18.12.1 Constants

`AndPut = 3`

Draw operation: use AND

`AnsiToASCIITransTable : TCharsetTransTable = (#$00, #$01, #$02, #$03, #$04, #$05, #$06, #$07, ...)`

Default ansi transliteration table.

`BkSlashFill = 5`

Fill style: Diagonal (backslash) lines

`black = 0`

Color code: black.

`blue = 1`

Color code: blue

`BoldFont = 10`

Font number: Bold font.

`BottomText = 0`



Vertical text alignment: Align text to bottom

```
brown = 6
```

Color code: brown

```
CenterLn = 2
```

Line style: centered line

```
CenterText = 1
```

Horizontal text alignment: Center text

```
ClipOff = false
```

Viewport clipping off

```
ClipOn = true
```

Viewport clipping on

```
CloseDotFill = 11
```

Fill style: Closely spaced dotted lines

```
CopyPut = 0
```

Draw operation: use Copy

```
CurrentDriver = -128
```

Currently used driver

```
cyan = 3
```

Color code: Cyan

```
D12bit = 16
```

Mode: Depth 12 bit

```
D15bit = 17
```

Mode: Depth 15 bit

```
D16bit = 18
```

Mode: Depth 16 bit

```
D1bit = 11
```

**Mode: Depth 1 bit**

D24bit = 19

**Mode: Depth 24 bit**

D2bit = 12

**Mode: Depth 2 bit**

D32bit = 20

**Mode: Depth 32 bit**

D4bit = 13

**Mode: Depth 4 bit**

D64bit = 21

**Mode: Depth 64 bit**

D6bit = 14

**Mode: Depth 6 bit**

D8bit = 15

**Mode: Depth 8 bit**

darkgray = 8

**Color code: Dark gray**

DashedLn = 3

**Line style: dashed line**

Default = 0

**Default mode**

DefaultFont = 0

**Font number: Normal font**

Detect = 0

**Mode: Detect mode.**

detectMode = 30000

Mode: Autodetect optimal mode

DottedLn = 1

Line style: Dotted line

DrawTextBackground : Boolean = false

Should the background of texts be drawn or should it be left untouched ?

EGABlack = 0

Color code: EGA Black

EGABlue = 1

Color code: EGA blue

EGABrown = 20

Color code: EGA brown

EGACyan = 3

Color code: EGA cyan

EGADarkgray = 56

Color code: EGA dark gray

EGAGreen = 2

Color code: EGA green

EGALightblue = 57

Color code: EGA Light blue

EGALightcyan = 59

Color code: EGA Light cyan

EGALightgray = 7

Color code: EGA Light gray

EGALightgreen = 58

Color code: EGA Light green

EGALightmagenta = 61



Mode: Resolution 1024x768, 32K colors

G1024x768x64K = 24

Mode: Resolution 1024x768, 64K colors

G1152x864x16 = 38

Mode: Resolution 1152x864, 16 colors

G1152x864x16M = 42

Mode: Resolution 1152x864, 16M colors

G1152x864x16M32 = 43

Mode: Resolution 1152x864, 16M 32-bit colors

G1152x864x256 = 39

Mode: Resolution 1152x864, 256 colors

G1152x864x32K = 40

Mode: Resolution 1152x864, 32K colors

G1152x864x64K = 41

Mode: Resolution 1152x864, 64K colors

G1280x1024x16 = 31

Mode: Resolution 1280x1024, 16 colors

G1280x1024x16M = 28

Mode: Resolution 1280x1024, 16M colors

G1280x1024x16M32 = 37

Mode: Resolution 1280x1024, 16M 32-bit colors

G1280x1024x256 = 13

Mode: Resolution 1280x1024, 256 colors

G1280x1024x32K = 26

Mode: Resolution 1280x1024, 32K colors

G1280x1024x64K = 27

Mode: Resolution 1280x1024, 64K colors

G1600x1200x16 = 44

Mode: Resolution 1600x1200, 16 colors

G1600x1200x16M = 48

Mode: Resolution 1600x1200, 16M colors

G1600x1200x16M32 = 49

Mode: Resolution 1600x1200, 16M 32-bit colors

G1600x1200x256 = 45

Mode: Resolution 1600x1200, 256 colors

G1600x1200x32K = 46

Mode: Resolution 1600x1200, 32K colors

G1600x1200x64K = 47

Mode: Resolution 1600x1200, 64K colors

G320x200x16 = 1

Mode: Resolution 320x200, 16 colors

G320x200x16M = 16

Mode: Resolution 320x200, 16M colors

G320x200x16M32 = 33

Mode: Resolution 320x200, 16M 32-bit colors

G320x200x256 = 5

Mode: Resolution 320x200, 256 colors

G320x200x32K = 14

Mode: Resolution 320x200, 32K colors

G320x200x64K = 15

Mode: Resolution 320x200, 64K colors

G320x240x256 = 6

Mode: Resolution 320x240, 256 colors

G320x400x256 = 7

Mode: Resolution 320x400, 256 colors

G360x480x256 = 8

Mode: Resolution 360x480, 256 colors

G640x200x16 = 2

Mode: Resolution x, colors

G640x350x16 = 3

Mode: Resolution x, colors

G640x480x16 = 4

Mode: Resolution x, colors

G640x480x16M = 19

Mode: Resolution 640x480, 16M colors

G640x480x16M32 = 34

Mode: Resolution 640x480, 16M 32-bit colors

G640x480x2 = 9

Mode: Resolution 640x480, 2 colors

G640x480x256 = 10

Mode: Resolution 640x480, 256 colors

G640x480x32K = 17

Mode: Resolution 640x480, 32K colors

G640x480x64K = 18

Mode: Resolution 640x480, 64K colors

G720x348x2 = 32

Mode: Resolution 720x348, 2 colors

G800x600x16 = 29

Mode: Resolution 800x600, 16 colors

G800x600x16M = 22

Mode: Resolution 800x600, 16M colors

G800x600x16M32 = 35

Mode: Resolution 800x600, 16M 32-bit colors

G800x600x256 = 11

Mode: Resolution 800x600, 256 colors

G800x600x32K = 20

Mode: Resolution 800x600, 32K colors

G800x600x64K = 21

Mode: Resolution 800x600, 64K colors

GothicFont = 4

Font number: Gothic font

GraphStringTransTable : PCharsetTransTable = nil

Table used when transliterating strings.

green = 2

Color code: green

grError = -11

Error: Unknown error.

grFileNotFound = -3

Error: File for driver not found.

grFontNotFound = -8

Error: font description file not found.

grInvalidDriver = -4

Error: Invalid driver specified

grInvalidFont = -13



Error: Invalid font description

`grInvalidFontNum = -14`

Error: Invalid font number

`grInvalidMode = -10`

Error: Invalid mode specified.

`grInvalidVersion = -18`

Error: Invalid version.

`grIOerror = -12`

Error: Unspecified Input/Output error.

`grNoFloodMem = -7`

Error: Could not allocate memory for flood operation.

`grNoFontMem = -9`

Error: Not enough memory to load font.

`grNoInitGraph = -1`

Error: Graphical system not initialized

`grNoLoadMem = -5`

Error: Memory error.

`grNoScanMem = -6`

Error: Could not allocate memory for scan

`grNotDetected = -2`

Error: Graphics device not detected.

`grOk = 0`

Graphical operation went OK.

`HatchFill = 7`

Fill style: Hatch lines

`HercMono = 7`

Mode: Hercules, mono color

HercMonoHi = 0

Mode: Hercules card, monochrome, high resolution

highNewDriver = 21

Mode: highest number for new driver

highNewMode = 30015

Mode: Highest possible value of the new modes.

HorizDir = 0

Text write direction: Horizontal

InterleaveFill = 9

Fill style: Interleaving lines

LCOMFont = 8

Font number: ?

LeftText = 0

Horizontal text alignment: Align text left

lightblue = 9

Color code: Light blue

lightcyan = 11

Color code: Light cyan

lightgray = 7

Color code: Light gray

lightgreen = 10

Color code: Light green

lightmagenta = 13

Color code: Light magenta

lightred = 12

Color code: Light red

LineFill = 2

Fill style: Fill using horizontal lines

lowNewDriver = 11

Mode: lowest number for new driver

lowNewMode = 30001

Mode: Lowest possible value of the new modes.

LowRes = 1

Mode: Low resolution.

LtBkSlashFill = 6

Fill style: Light diagonal (backslash) lines

LtSlashFill = 3

Fill style: Light diagonal (slash) lines

m1024x768 = 30012

Mode: Resolution 1024x768

m1280x1024 = 30013

Mode: Resolution 1280x1024

m1600x1200 = 30014

Mode: Resolution 1600x1200

m2048x1536 = 30015

Mode: Resolution 2048x1536

m320x200 = 30001

Mode: Resolution 320x200

m320x256 = 30002

Mode: Resolution 320x256

m320x400 = 30003

**Mode: Resolution 320x400**

m512x384 = 30004

**Mode: Resolution 512x384**

m640x200 = 30005

**Mode: Resolution 640x200**

m640x256 = 30006

**Mode: Resolution 640x256**

m640x350 = 30007

**Mode: Resolution 640x350**

m640x400 = 30008

**Mode: Resolution 640x400**

m640x480 = 30009

**Mode: Resolution 640x480**

m800x600 = 30010

**Mode: Resolution 800x600**

m832x624 = 30011

**Mode: Resolution 832x624**

magenta = 5

**Color code: Magenta**

MaxColors = 255

**Max amount of colors in a palette**

maxsmallint = high(smallint)

**Maximum value for smallint type**

NormalPut = 0

**Draw operation: Use Normal (copy) operation**

NormWidth = 1

Line width: Normal width

`NotPut = 4`

Draw operation: use NOT

`OrPut = 2`

Draw operation: use OR

`red = 4`

Color code: Red

`resolutions : Array[lowNewMode..highNewMode] of TResolutionRec = ((x:320;y:200),(x:3`

Array with actual resolutions of the new modes

`RightText = 2`

Horizontal text alignment: Align text right

`SansSerifFont = 3`

Font number: Sans Serif font

`ScriptFont = 5`

Font number: Script font

`SimpleFont = 6`

Font number: Simple font

`SlashFill = 4`

Fill style: Diagonal (slash) lines

`SmallFont = 2`

Font number: Small font

`SolidFill = 1`

Fill style: Solid fill.

`SolidLn = 0`

Line style: Solid line

`ThickWidth = 3`

Line width: double width

`TopOff = false`

Top off

`TopOn = true`

Top on

`TopText = 2`

Vertical text alignment: Align text to top

`TriplexFont = 1`

Font number: Triplex font

`TSCRFont = 7`

Font number: Terminal font

`UserBitLn = 4`

Line style: User defined

`UserCharSize = 0`

User character size

`UserFill = 12`

Fill style: User-defined fill.

`VertDir = 1`

Text write direction: Vertical

`VESA = 10`

Mode: VESA graphics adaptor.

`VGA = 9`

Mode: VGA graphics adaptor.

`VGAHi = 2`

Mode: VGA high resolution (640x480)

`VGALo = 0`

Mode: VGA low resolution (640x200)

VGAMed = 1

Mode: VGA medium resolution (640x350)

white = 15

Color code: White

WideDotFill = 10

Fill style: Widely spaced dotted lines

XHatchFill = 8

Fill style: Heavy hatch lines

XORPut = 1

Draw operation: use XOR

yellow = 14

Color code: Yellow

### 18.12.2 Types

```
ArcCoordsType = record
  x : SmallInt;
  y : SmallInt;
  xstart : SmallInt;
  ystart : SmallInt;
  xend : SmallInt;
  yend : SmallInt;
end
```

Describe the last arc which was drawn on screen

```
CircleProc = procedure(X: SmallInt;Y: SmallInt;Radius: Word)
```

Standard circle drawing routine prototype.

```
clrviewproc = procedure
```

Standard clearviewport routine prototype

```
defpixelproc = procedure(X: SmallInt;Y: SmallInt)
```

This is the standard putpixel routine used by all function drawing routines, it will use the viewport settings, as well as clip, and use the current foreground color to plot the desired pixel.

```
ellipseproc = procedure(X: SmallInt;Y: SmallInt;XRadius: Word;
                        YRadius: Word;stAngle: Word;EndAngle: Word;
                        fp: patternlineproc)
```

Standard ellipse drawing routine prototype.

```
FillPatternType = Array[1..8] of Byte
```

Bit pattern used when drawing lines. Set bits are drawn.

```
FillSettingsType = record
    pattern : Word;
    color : Word;
end
```

Record describing fill mode

```
getimageproc = procedure(X1: SmallInt;Y1: SmallInt;X2: SmallInt;
                        Y2: SmallInt;var Bitmap)
```

Standard GetImage (642) procedure prototype.

```
getpixelproc = function(X: SmallInt;Y: SmallInt) : Word
```

Standard pixel fetching routine prototype

```
getrgbpaletteproc = procedure(ColorNum: SmallInt;var RedValue: SmallInt;
                        var GreenValue: SmallInt;
                        var BlueValue: SmallInt)
```

This routine prototype is a hook for GetRGBPalette (643)

```
getscanlineproc = procedure(X1: SmallInt;X2: SmallInt;Y: SmallInt;
                        var data)
```

This routine is used for FloodFill (647) It returns an entire screen scan line with a word for each pixel in the scanline. Also handy for GetImage.

```
graphfreememprc = procedure(var P: Pointer;size: Word)
```

Procedure prototype, used when heap memory is freed by the graph routines.

```
graphgetmemprc = procedure(var P: pointer;size: Word)
```

Procedure prototype, used when heap memory is needed by the graph routines.

```
graph_float = single
```



The platform's preferred floating point size for fast graph operations

```
hlineproc = procedure(x: SmallInt;x2: SmallInt;y: SmallInt)
```

Standard procedure prototype to draw a single horizontal line

```
imagesizeproc = function(X1: SmallInt;Y1: SmallInt;X2: SmallInt;
                        Y2: SmallInt) : LongInt
```

Standard ImageSize (643) calculation procedure prototype.

```
initmodeproc = procedure
```

Standard routine prototype to initialize a mode.

```
lineproc = procedure(X1: SmallInt;Y1: SmallInt;X2: SmallInt;
                    Y2: SmallInt)
```

Standard line drawing routine prototype.

```
LineStyleType = record
  linestyle : Word;
  pattern : Word;
  thickness : Word;
end
```

Record describing current line drawing mode

```
OutTextXYProc = procedure(x: SmallInt;y: SmallInt;
                        const TextString: String)
```

This routine prototype is a hook for OutTextXY (643)

```
PaletteType = record
  Size : LongInt;
  Colors : Array[0..MaxColors] of RGBRec;
end
```

Record describing palette.

```
patternlineproc = procedure(x1: SmallInt;x2: SmallInt;y: SmallInt)
```

Standard procedure prototype to draw a patterned line

```
PCharsetTransTable = ^TCharsetTransTable
```

Pointer to TCharsetTransTable (641) array.

```
PModeInfo = ^TModeInfo
```

Pointer to TModeInfo (642) record

```
PointType = record
  x : SmallInt;
  y : SmallInt;
end
```

Record describing a point in a 2 dimensional plane

```
putimageproc = procedure(X: SmallInt;Y: SmallInt;var Bitmap;
                        BitBlt: Word)
```

Standard PutImage (643) procedure prototype.

```
putpixelproc = procedure(X: SmallInt;Y: SmallInt;Color: Word)
```

Standard pixel drawing routine prototype

```
restorestateproc = procedure
```

Standard routine prototype to restore the graphical state at a closegraph call.

```
RGBRec = packed record
  Red : SmallInt;
  Green : SmallInt;
  Blue : SmallInt;
end
```

Record describing palette RGB color

```
savestateproc = procedure
```

Standard routine prototype to save the graphical state before a mode is set.

```
setactivepageproc = procedure(page: Word)
```

Standard SetActivePage (644) procedure prototype.

```
SetAllPaletteProc = procedure(const Palette: PaletteType)
```

This routine prototype is a hook for SetAllPalette (644)

```
setrgbpaletteproc = procedure(ColorNum: SmallInt;RedValue: SmallInt;
                        GreenValue: SmallInt;BlueValue: SmallInt)
```

This routine prototype is a hook for SetRGBPalette (644)

```
setvisualpageproc = procedure(page: Word)
```

Standard SetVisualPage (644) procedure prototype.

TCharsetTransTable = Array[Char] of Char

Character transliteration table, with entries for 256 characters

```
TextSettingsType = record
  font : Word;
  direction : Word;
  charsize : Word;
  horiz : Word;
  vert : Word;
end
```

Record describing how texts are drawn.

```
TModeInfo = record
  DriverNumber : SmallInt;
  ModeNumber : SmallInt;
  internModeNumber : SmallInt;
  MaxColor : LongInt;
  PaletteSize : LongInt;
  XAspect : Word;
  YAspect : Word;
  MaxX : Word;
  MaxY : Word;
  DirectColor : Boolean;
  Hardwarepages : Byte;
  ModeName : String;
  DirectPutPixel : defpixelproc;
  GetPixel : getpixelproc;
  PutPixel : putpixelproc;
  SetRGBPalette : setrgbpaletteproc;
  GetRGBPalette : getrgbpaletteproc;
  SetAllPalette : SetAllPaletteProc;
  SetVisualPage : setvisualpageproc;
  SetActivePage : setactivepageproc;
  ClearViewPort : clrviewproc;
  PutImage : putimageproc;
  GetImage : getimageproc;
  ImageSize : imagesizeproc;
  GetScanLine : getscanlineproc;
  Line : lineproc;
  InternalEllipse : ellipseproc;
  PatternLine : patternlineproc;
  HLine : hlineproc;
  VLine : vlineproc;
  Circle : CircleProc;
  InitMode : initmodeproc;
  OutTextXY : OutTextXYProc;
  next : PModeInfo;
end
```

Record describing a graphical mode.

```
TNewModeInfo = record
  modeInfo : Array[lowNewDriver..highNewDriver] of PModeInfo;
  loHiModeNr : Array[lowNewDriver..highNewDriver] of ;
end
```

Mode information for new modes.a

```
TResolutionRec = record
  x : LongInt;
  y : LongInt;
end
```

Record describing resolution

```
ViewPortType = record
  x1 : SmallInt;
  y1 : SmallInt;
  x2 : SmallInt;
  y2 : SmallInt;
  Clip : Boolean;
end
```

Record describing a viewport

```
vlineproc = procedure(x: SmallInt;y: SmallInt;y2: SmallInt)
```

Standard procedure prototype to draw a single vertical line

### 18.12.3 Variables

Circle : CircleProc

Circle draws a complete circle with center at (X, Y), radius radius.

ClearViewPort : clrviewproc

Clears the current viewport. The current background color is used as filling color. The pointer is set at (0, 0).

DirectPutPixel : defpixelproc

Hook to directly draw a pixel on the screen.

GetImage : getimageproc

GetImage Places a copy of the screen area (X1, Y1) to X2, Y2 in BitMap

GetPixel : getpixelproc

GetPixel returns the color of the point at (X, Y)

GetRGBPalette : getrgbpaletteproc

Hook to set a RGB palette entries.

GetScanLine : getscanlineproc

Hook to get a scan line from the screen.

GraphFreeMemPtr : graphfreememprc

Hook to free heap memory.

GraphGetMemPtr : graphgetmemprc

Hook to get heap memory

HLine : hlineproc

Hook to draw a solid horizontal line

ImageSize : imagesizeproc

ImageSize returns the number of bytes needed to store the image in the rectangle defined by (X1, Y1) and (X2, Y2).

InternalEllipse : ellipseproc

Hook to draw an ellipse

Line : lineproc

Line draws a line starting from (X1, Y1 to (X2, Y2), in the current line style and color. The current position is put to (X2, Y2)

OutTextXY : OutTextXYProc

OutText puts TextString on the screen, at position (X, Y), using the current font and text settings. The current position is moved to the end of the text.

PatternLine : patternlineproc

Hook to draw a patterned line

PutImage : putimageproc

PutImage Places the bitmap in Bitmap on the screen at (X1, Y1). How determines how the bitmap will be placed on the screen. Possible values are :

- CopyPut
- XORPut
- ORPut
- AndPut
- NotPut

PutPixel : putpixelproc

Puts a point at (X, Y) using color Color

RestoreVideoState : restorestateproc

Hook to restore a saved video mode

SaveVideoState : savestateproc

Hook to save the current video state

SetActivePage : setactivepageproc

Sets Page as the active page for all graphical output.

SetAllPalette : SetAllPaletteProc

Sets the current palette to Palette. Palette is an untyped variable, usually pointing to a record of type PaletteType

SetRGBPalette : setrgbpaletteproc

SetRGBPalette sets the ColorNr-th entry in the palette to the color with RGB-values Red, Green Blue.

SetVisualPage : setvisualpageproc

SetVisualPage sets the video page to page number Page.

VLine : vlineproc

Hook to draw a solid vertical line

## 18.13 Procedures and functions

### 18.13.1 Arc

Synopsis: Draw part of a circle

Declaration: `procedure Arc(X: SmallInt; Y: SmallInt; StAngle: Word; EndAngle: Word; Radius: Word)`

Visibility: default

Description: Arc draws part of a circle with center at (X, Y), radius radius, starting from angle start, stopping at angle stop. These angles are measured counterclockwise.

Errors: None.

See also: Circle ([642](#)), Ellipse ([646](#)), GetArcCoords ([647](#)), PieSlice ([657](#)), Sector ([658](#))

### 18.13.2 Bar

Synopsis: Draw filled rectangle

Declaration: `procedure Bar(x1: SmallInt; y1: SmallInt; x2: SmallInt; y2: SmallInt)`

Visibility: default

Description: Draws a rectangle with corners at (X1, Y1) and (X2, Y2) and fills it with the current color and fill-style.

Errors: None.

See also: Bar3D ([645](#)), Rectangle ([657](#))

### 18.13.3 Bar3D

Synopsis: Draw filled 3-dimensional rectangle

Declaration: `procedure Bar3D(x1: SmallInt; y1: SmallInt; x2: SmallInt; y2: SmallInt;  
depth: Word; top: Boolean)`

Visibility: default

Description: Bar3d draws a 3-dimensional Bar with corners at (X1, Y1) and (X2, Y2) and fills it with the current color and fill-style. Depth specifies the number of pixels used to show the depth of the bar.

If Top is true; then a 3-dimensional top is drawn.

Errors: None.

See also: Bar ([645](#)), Rectangle ([657](#))

### 18.13.4 ClearDevice

Synopsis: Clear the complete screen

Declaration: `procedure ClearDevice`

Visibility: default

Description: Clears the graphical screen (with the current background color), and sets the pointer at (0, 0).

Errors: None.

See also: ClearViewPort ([642](#)), SetBkColor ([659](#))

### 18.13.5 Closegraph

Synopsis: Close graphical system.

Declaration: `procedure Closegraph`

Visibility: default

Description: Closes the graphical system, and restores the screen modus which was active before the graphical modus was activated.

Errors: None.

See also: InitGraph ([654](#))

### 18.13.6 DetectGraph

Synopsis: Detect correct graphical driver to use

Declaration: `procedure DetectGraph(var GraphDriver: SmallInt; var GraphMode: SmallInt)`

Visibility: default

Description: `DetectGraph` checks the hardware in the PC and determines the driver and screen-modus to be used. These are returned in `Driver` and `Modus`, and can be fed to `InitGraph`. See the `InitGraph` for a list of drivers and modi.

Errors: None.

See also: `InitGraph` ([654](#))

### 18.13.7 DrawPoly

Synopsis: Draw a polygone

Declaration: `procedure DrawPoly(NumPoints: Word; var polypoints)`

Visibility: default

Description: `DrawPoly` draws a polygone with `NumberOfPoints` corner points, using the current color and line-style. `PolyPoints` is an array of type `PointType` ([640](#)).

Errors: None.

See also: `Bar` ([645](#)), `Bar3D` ([645](#)), `Rectangle` ([657](#))

### 18.13.8 Ellipse

Synopsis: Draw an ellipse

Declaration: `procedure Ellipse(X: SmallInt; Y: SmallInt; stAngle: Word; EndAngle: Word; XRadius: Word; YRadius: Word)`

Visibility: default

Description: `Ellipse` draws part of an ellipse with center at `(X, Y)`. `XRadius` and `Yradius` are the horizontal and vertical radii of the ellipse. `Start` and `Stop` are the starting and stopping angles of the part of the ellipse. They are measured counterclockwise from the X-axis (3 o'clock is equal to 0 degrees). Only positive angles can be specified.

Errors: None.

See also: `Arc` ([644](#)), `Circle` ([642](#)), `FillEllipse` ([646](#))

### 18.13.9 FillEllipse

Synopsis: Draw and fill an ellipse

Declaration: `procedure FillEllipse(X: SmallInt; Y: SmallInt; XRadius: Word; YRadius: Word)`

Visibility: default



**Description:** `Ellipse` draws an ellipse with center at  $(X, Y)$ . `XRadiu`s and `Yradiu`s are the horizontal and vertical radii of the ellipse. The ellipse is filled with the current color and fill-style.

**Errors:** None.

**See also:** `Arc` ([644](#)), `Circle` ([642](#)), `GetArcCoords` ([647](#)), `PieSlice` ([657](#)), `Sector` ([658](#))

### 18.13.10 FillPoly

**Synopsis:** Draw, close and fill a polygone

**Declaration:** `procedure FillPoly (NumPoints: Word; var PolyPoints)`

**Visibility:** default

**Description:** `FillPoly` draws a polygone with `NumberOfPoints` corner points and fills it using the current color and line-style. `PolyPoints` is an array of type `PointType`.

**Errors:** None.

**See also:** `Bar` ([645](#)), `Bar3D` ([645](#)), `Rectangle` ([657](#))

### 18.13.11 FloodFill

**Synopsis:** Fill an area with a given color

**Declaration:** `procedure FloodFill (x: SmallInt; y: SmallInt; Border: Word)`

**Visibility:** default

**Description:** Fills the area containing the point  $(X, Y)$ , bounded by the color `BorderColor`.

**Errors:** None

**See also:** `SetColor` ([659](#)), `SetBkColor` ([659](#))

### 18.13.12 GetArcCoords

**Synopsis:** Return coordinates of last drawn arc or ellipse.

**Declaration:** `procedure GetArcCoords (var ArcCoords: ArcCoordsType)`

**Visibility:** default

**Description:** `GetArcCoords` returns the coordinates of the latest `Arc` or `Ellipse` call.

**Errors:** None.

**See also:** `Arc` ([644](#)), `Ellipse` ([646](#))

### 18.13.13 GetAspectRatio

Synopsis: Return screen resolution

Declaration: `procedure GetAspectRatio (var Xasp: Word; var Yasp: Word)`

Visibility: default

Description: `GetAspectRatio` determines the effective resolution of the screen. The aspect ration can then be calculated as  $Xasp/Yasp$ .

Errors: None.

See also: `InitGraph` ([654](#)), `SetAspectRatio` ([658](#))

### 18.13.14 GetBkColor

Synopsis: Return current background color

Declaration: `function GetBkColor : Word`

Visibility: default

Description: `GetBkColor` returns the current background color (the palette entry).

Errors: None.

See also: `GetColor` ([648](#)), `SetBkColor` ([659](#))

### 18.13.15 GetColor

Synopsis: Return current drawing color

Declaration: `function GetColor : Word`

Visibility: default

Description: `GetColor` returns the current drawing color (the palette entry).

Errors: None.

See also: `GetColor` ([648](#)), `SetBkColor` ([659](#))

### 18.13.16 GetDefaultPalette

Synopsis: Return default palette

Declaration: `procedure GetDefaultPalette (var Palette: PaletteType)`

Visibility: default

Description: `GetDefaultPalette` returns the current palette in `Palette`.

Errors: None.

See also: `GetColor` ([648](#)), `GetBkColor` ([648](#))

### 18.13.17 GetDirectVideo

Synopsis: Determine whether direct video mode is active.

Declaration: `function GetDirectVideo : Boolean`

Visibility: default

Description: Determine whether direct video mode is active.

Errors:

### 18.13.18 GetDriverName

Synopsis: Return current driver name

Declaration: `function GetDriverName : String`

Visibility: default

Description: `GetDriverName` returns a string containing the name of the current driver.

Errors: None.

See also: `GetModeName` ([651](#)), `InitGraph` ([654](#))

### 18.13.19 GetFillPattern

Synopsis: Return current fill pattern

Declaration: `procedure GetFillPattern(var FillPattern: FillPatternType)`

Visibility: default

Description: `GetFillPattern` returns an array with the current fill-pattern in `FillPattern`

Errors: None

See also: `SetFillPattern` ([659](#))

### 18.13.20 GetFillSettings

Synopsis: Return current fill settings

Declaration: `procedure GetFillSettings(var Fillinfo: FillSettingsType)`

Visibility: default

Description: `GetFillSettings` returns the current fill-settings in `FillInfo`

Errors: None.

See also: `SetFillPattern` ([659](#))

### 18.13.21 GetGraphMode

Synopsis: Get current graphical modus

Declaration: `function GetGraphMode : SmallInt`

Visibility: default

Description: `GetGraphMode` returns the current graphical modus

Errors: None.

See also: `InitGraph` ([654](#))

### 18.13.22 GetLineSettings

Synopsis: Get current line drawing settings

Declaration: `procedure GetLineSettings (var ActiveLineInfo: LineSettingsType)`

Visibility: default

Description: `GetLineSettings` returns the current Line settings in `LineInfo`

Errors: None.

See also: `SetLineStyle` ([660](#))

### 18.13.23 GetMaxColor

Synopsis: return maximum number of colors

Declaration: `function GetMaxColor : Word`

Visibility: default

Description: `GetMaxColor` returns the maximum color-number which can be set with `SetColor`. Contrary to Turbo Pascal, this color isn't always guaranteed to be white (for instance in 256+ color modes).

Errors: None.

See also: `SetColor` ([659](#)), `GetPaletteSize` ([652](#))

### 18.13.24 GetMaxMode

Synopsis: Return biggest mode for the current driver

Declaration: `function GetMaxMode : SmallInt`

Visibility: default

Description: `GetMaxMode` returns the highest modus for the current driver.

Errors: None.

See also: `InitGraph` ([654](#))

### 18.13.25 GetMaxX

Synopsis: Return maximal X coordinate

Declaration: `function GetMaxX : SmallInt`

Visibility: default

Description: `GetMaxX` returns the maximum horizontal screen length

Errors: None.

See also: `GetMaxY` ([651](#))

### 18.13.26 GetMaxY

Synopsis: Return maximal Y coordinate

Declaration: `function GetMaxY : SmallInt`

Visibility: default

Description: `GetMaxY` returns the maximum number of screen lines

Errors: None.

See also: `GetMaxX` ([651](#))

### 18.13.27 GetModeName

Synopsis: Return description a modus

Declaration: `function GetModeName (ModeNumber: SmallInt) : String`

Visibility: default

Description: `GetModeName` Returns a string with the name of modus `Modus`

Errors: None.

See also: `GetDriverName` ([649](#)), `InitGraph` ([654](#))

### 18.13.28 GetModeRange

Synopsis: Return lowest and highest modus of current driver

Declaration: `procedure GetModeRange (GraphDriver: SmallInt; var LoMode: SmallInt;  
var HiMode: SmallInt)`

Visibility: default

Description: `GetModeRange` returns the Lowest and Highest modus of the currently installed driver. If no modes are supported for this driver, `HiModus` will be -1.

Errors: None.

See also: `InitGraph` ([654](#))

### 18.13.29 GetPalette

Synopsis: Return current palette

Declaration: `procedure GetPalette (var Palette: PaletteType)`

Visibility: default

Description: `GetPalette` returns in `Palette` the current palette.

Errors: None.

See also: `GetPaletteSize` ([652](#)), `SetPalette` ([661](#))

### 18.13.30 GetPaletteSize

Synopsis: Return maximal number of entries in current palette

Declaration: `function GetPaletteSize : SmallInt`

Visibility: default

Description: `GetPaletteSize` returns the maximum number of entries in the current palette.

Errors: None.

See also: `GetPalette` ([652](#)), `SetPalette` ([661](#))

### 18.13.31 GetTextSettings

Synopsis: Return current text style

Declaration: `procedure GetTextSettings (var TextInfo: TextSettingsType)`

Visibility: default

Description: `GetTextSettings` returns the current text style settings : The font, direction, size and placement as set with `SetTextStyle` and `SetTextJustify`

Errors: None.

See also: `SetTextStyle` ([662](#)), `SetTextJustify` ([661](#))

### 18.13.32 GetViewSettings

Synopsis: Return current viewport

Declaration: `procedure GetViewSettings (var viewport: ViewPortType)`

Visibility: default

Description: `GetViewSettings` returns the current viewport and clipping settings in `ViewPort`.

Errors: None.

See also: `SetViewPort` ([663](#))

### 18.13.33 GetX

Synopsis: Return current cursor X position

Declaration: `function GetX : SmallInt`

Visibility: default

Description: `GetX` returns the X-coordinate of the current position of the graphical pointer

Errors: None.

See also: `GetY` ([653](#))

### 18.13.34 GetY

Synopsis: Return current cursor Y position

Declaration: `function GetY : SmallInt`

Visibility: default

Description: `GetY` returns the Y-coordinate of the current position of the graphical pointer

Errors: None.

See also: `GetX` ([653](#))

### 18.13.35 GraphDefaults

Synopsis: Reset graphical mode to defaults

Declaration: `procedure GraphDefaults`

Visibility: default

Description: `GraphDefaults` resets all settings for viewport, palette, foreground and background pattern, line-style and pattern, filling style, filling color and pattern, font, text-placement and text size.

Errors: None.

See also: `SetViewPort` ([663](#)), `SetFillStyle` ([660](#)), `SetColor` ([659](#)), `SetBkColor` ([659](#)), `SetLineStyle` ([660](#))

### 18.13.36 GraphErrorMsg

Synopsis: Return a description of an error

Declaration: `function GraphErrorMsg(ErrorCode: SmallInt) : String`

Visibility: default

Description: `GraphErrorMsg` returns a string describing the error `Errorcode`. This string can be used to let the user know what went wrong.

Errors: None.

See also: `GraphResult` ([654](#))

**18.13.37 GraphResult**

Synopsis: Result of last graphical operation

Declaration: `function GraphResult : SmallInt`

Visibility: default

Description: `GraphResult` returns an error-code for the last graphical operation. If the returned value is zero, all went well. A value different from zero means an error has occurred. besides all operations which draw something on the screen, the following procedures also can produce a `GraphResult` different from zero:

- `InstallUserFont` ([655](#))
- `SetLineStyle` ([660](#))
- `SetWriteMode` ([663](#))
- `SetFillStyle` ([660](#))
- `SetTextJustify` ([661](#))
- `SetGraphMode` ([660](#))
- `SetTextStyle` ([662](#))

Errors: None.

See also: `GraphErrorMsg` ([653](#))

**18.13.38 InitGraph**

Synopsis: Initialize graphical system

Declaration: `procedure InitGraph(var GraphDriver: SmallInt; var GraphMode: SmallInt; const PathToDriver: String)`

Visibility: default

Description: `InitGraph` initializes the graph package. `GraphDriver` has two valid values: `GraphDriver=0` which performs an auto detect and initializes the highest possible mode with the most colors. 1024x768x64K is the highest possible resolution supported by the driver, if you need a higher resolution, you must edit `MODES.PPI`. If you need another mode, then set `GraphDriver` to a value different from zero and `graphmode` to the mode you wish (VESA modes where 640x480x256 is 101h etc.). `PathToDriver` is only needed, if you use the BGI fonts from Borland. Free Pascal does not offer BGI fonts like Borland, these must be obtained separately.

Example code:

```
var
  gd,gm : integer;
  PathToDriver : string;
begin
  gd:=detect; { highest possible resolution }
  gm:=0; { not needed, auto detection }
  PathToDriver:='C:\PP\BGI'; { path to BGI fonts,
                                drivers aren't needed }
  InitGraph(gd,gm,PathToDriver);
  if GraphResult<>grok then
    halt; ..... { whatever you need }
  CloseGraph; { restores the old graphics mode }
end.
```



Errors: None.

See also: Modes ([621](#)), DetectGraph ([646](#)), CloseGraph ([645](#)), GraphResult ([654](#))

### 18.13.39 InstallUserDriver

Synopsis: Install a user driver

Declaration: `function InstallUserDriver (Name: String; AutoDetectPtr: Pointer)  
: SmallInt`

Visibility: default

Description: `InstallUserDriver` adds the device-driver `DriverPath` to the list of .BGI drivers. `AutoDetectPtr` is a pointer to a possible auto-detect function.

Errors: None.

See also: `InitGraph` ([654](#)), `InstallUserFont` ([655](#))

### 18.13.40 InstallUserFont

Synopsis: Install a user-defined font

Declaration: `function InstallUserFont (const FontFileName: String) : SmallInt`

Visibility: default

Description: `InstallUserFont` adds the font in `FontPath` to the list of fonts of the .BGI system.

Errors: None.

See also: `InitGraph` ([654](#)), `InstallUserDriver` ([655](#))

### 18.13.41 LineRel

Synopsis: Draw a line starting from current position in given direction

Declaration: `procedure LineRel (Dx: SmallInt; Dy: SmallInt)`

Visibility: default

Description: `LineRel` draws a line starting from the current pointer position to the point  $(DX, DY)$ , `\textbf{relative}` to the current position, in the current line style and color. The Current Position is set to the endpoint of the line.

Errors: None.

See also: `Line` ([643](#)), `LineTo` ([656](#))

### 18.13.42 LineTo

Synopsis: Draw a line starting from current position to a given point

Declaration: `procedure LineTo(X: SmallInt;Y: SmallInt)`

Visibility: default

Description: `LineTo` draws a line starting from the current pointer position to the point  $(DX, DY, \text{\textbf{relative}})$  to the current position, in the current line style and color. The Current position is set to the end of the line.

Errors: None.

See also: `LineRel` ([655](#)), `Line` ([643](#))

### 18.13.43 MoveRel

Synopsis: Move cursor relative to current position

Declaration: `procedure MoveRel(Dx: SmallInt;Dy: SmallInt)`

Visibility: default

Description: `MoveRel` moves the pointer to the point  $(DX, DY)$ , relative to the current pointer position

Errors: None.

See also: `MoveTo` ([656](#))

### 18.13.44 MoveTo

Synopsis: Move cursor to absolute position.

Declaration: `procedure MoveTo(X: SmallInt;Y: SmallInt)`

Visibility: default

Description: `MoveTo` moves the pointer to the point  $(X, Y)$ .

Errors: None.

See also: `MoveRel` ([656](#))

### 18.13.45 OutText

Synopsis: Write text on the screen at the current location.

Declaration: `procedure OutText(const TextString: String)`

Visibility: default

Description: `OutText` puts `TextString` on the screen, at the current pointer position, using the current font and text settings. The current position is moved to the end of the text.

Errors: None.

See also: `OutTextXY` ([643](#))

### 18.13.46 PieSlice

Synopsis: Draw a pie-slice

Declaration: `procedure PieSlice(X: SmallInt; Y: SmallInt; stangle: SmallInt;  
                                  endAngle: SmallInt; Radius: Word)`

Visibility: default

Description: `PieSlice` draws and fills a sector of a circle with center (X, Y) and radius Radius, starting at angle Start and ending at angle Stop.

Errors: None.

See also: Arc ([644](#)), Circle ([642](#)), Sector ([658](#))

### 18.13.47 queryadapterinfo

Synopsis: Function called to retrieve the current video adapter settings.

Declaration: `function queryadapterinfo : PModeInfo`

Visibility: default

### 18.13.48 Rectangle

Synopsis: Draw a rectangle on the screen.

Declaration: `procedure Rectangle(x1: SmallInt; y1: SmallInt; x2: SmallInt; y2: SmallInt)`

Visibility: default

Description: Draws a rectangle with corners at (X1, Y1) and (X2, Y2), using the current color and style.

Errors: None.

See also: Bar ([645](#)), Bar3D ([645](#))

### 18.13.49 RegisterBGIDriver

Synopsis: Register a new BGI driver.

Declaration: `function RegisterBGIDriver(driver: pointer) : SmallInt`

Visibility: default

Description: Registers a user-defined BGI driver

Errors: None.

See also: `InstallUserDriver` ([655](#)), `RegisterBGIFont` ([658](#))

### 18.13.50 RegisterBGIfont

Synopsis: Register a new BGI font

Declaration: `function RegisterBGIfont (font: pointer) : SmallInt`

Visibility: default

Description: Registers a user-defined BGI driver

Errors: None.

See also: `InstallUserFont` ([655](#)), `RegisterBGIDriver` ([657](#))

### 18.13.51 RestoreCrtMode

Synopsis: Restore text screen

Declaration: `procedure RestoreCrtMode`

Visibility: default

Description: Restores the screen modus which was active before the graphical modus was started.

To get back to the graph mode you were last in, you can use `SetGraphMode (GetGraphMode)`

Errors: None.

See also: `InitGraph` ([654](#))

### 18.13.52 Sector

Synopsis: Draw and fill a sector of an ellipse

Declaration: `procedure Sector (x: SmallInt; y: SmallInt; StAngle: Word; EndAngle: Word;  
                                  XRadius: Word; YRadius: Word)`

Visibility: default

Description: `Sector` draws and fills a sector of an ellipse with center (X, Y) and radii XRadius and YRadius, starting at angle Start and ending at angle Stop.

Errors: None.

See also: `Arc` ([644](#)), `Circle` ([642](#)), `PieSlice` ([657](#))

### 18.13.53 SetAspectRatio

Synopsis: Set aspect ration of the screen

Declaration: `procedure SetAspectRatio (Xasp: Word; Yasp: Word)`

Visibility: default

Description: Sets the aspect ratio of the current screen to Xasp/Yasp.

Errors: None

See also: `InitGraph` ([654](#)), `GetAspectRatio` ([648](#))

#### 18.13.54 SetBkColor

Synopsis: Set background drawing color

Declaration: `procedure SetBkColor (ColorNum: Word)`

Visibility: default

Description: Sets the background color to `Color`.

Errors: None.

See also: `GetBkColor` (648), `SetColor` (659), `SetWriteMode` (663)

#### 18.13.55 SetColor

Synopsis: Set foreground drawing color

Declaration: `procedure SetColor (Color: Word)`

Visibility: default

Description: Sets the foreground color to `Color`.

Errors: None.

See also: `GetColor` (648), `SetBkColor` (659), `SetWriteMode` (663)

#### 18.13.56 SetDirectVideo

Synopsis: Attempt to enter direct video mode.

Declaration: `procedure SetDirectVideo (DirectAccess: Boolean)`

Visibility: default

Description: `SetDirectVideo` attempts to enter direct video mode. In that mode, everything is drawn straight in the video buffer.

#### 18.13.57 SetFillPattern

Synopsis: Set drawing fill pattern

Declaration: `procedure SetFillPattern (Pattern: FillPatternType; Color: Word)`

Visibility: default

Description: `SetFillPattern` sets the current fill-pattern to `FillPattern`, and the filling color to `Color`. The pattern is an 8x8 raster, corresponding to the 64 bits in `FillPattern`.

Errors: None

See also: `GetFillPattern` (649), `SetFillStyle` (660), `SetWriteMode` (663)

### 18.13.58 SetFillStyle

Synopsis: Set drawing fill style

Declaration: `procedure SetFillStyle (Pattern: Word; Color: Word)`

Visibility: default

Description: `SetFillStyle` sets the filling pattern and color to one of the predefined filling patterns. `Pattern` can be one of the following predefined constants :

**EmptyFill** Uses backgroundcolor.

**SolidFill** Uses filling color

**LineFill** Fills with horizontal lines.

**ltSlashFill** Fills with lines from left-under to top-right.

**SlashFill** Idem as previous, thick lines.

**BkSlashFill** Fills with thick lines from left-Top to bottom-right.

**LtBkSlashFill** Idem as previous, normal lines.

**HatchFill** Fills with a hatch-like pattern.

**XHatchFill** Fills with a hatch pattern, rotated 45 degrees.

**InterLeaveFill**

**WideDotFill** Fills with dots, wide spacing.

**CloseDotFill** Fills with dots, narrow spacing.

**UserFill** Fills with a user-defined pattern.

Errors: None.

See also: `SetFillPattern` ([659](#)), `SetWriteMode` ([663](#))

### 18.13.59 SetGraphMode

Synopsis: Set graphical mode

Declaration: `procedure SetGraphMode (Mode: SmallInt)`

Visibility: default

Description: `SetGraphMode` sets the graphical mode and clears the screen.

Errors: None.

See also: `InitGraph` ([654](#))

### 18.13.60 SetLineStyle

Synopsis: Set line drawing style

Declaration: `procedure SetLineStyle (LineStyle: Word; Pattern: Word; Thickness: Word)`

Visibility: default

Description: `SetLineStyle` sets the drawing style for lines. You can specify a `LineStyle` which is one of the following pre-defined constants:

**SolidIn** Draws a solid line.

**DottedIn** Draws a dotted line.

**CenterIn** Draws a non-broken centered line.

**DashedIn** Draws a dashed line.

**UserBitIn** Draws a User-defined bit pattern.

If **UserBitIn** is specified then **Pattern** contains the bit pattern. In all another cases, **Pattern** is ignored. The parameter **Width** indicates how thick the line should be. You can specify one of the following pre-defined constants:

**NormWidth** Normal line width

**ThickWidth** Double line width

Errors: None.

See also: [GetLineSettings \(650\)](#), [SetWriteMode \(663\)](#)

### 18.13.61 SetPalette

Synopsis: Set palette entry using color constant

Declaration: `procedure SetPalette (ColorNum: Word; Color: ShortInt)`

Visibility: default

Description: **SetPalette** changes the **ColorNr**-th entry in the palette to **NewColor**

Errors: None.

See also: [SetAllPalette \(644\)](#), [SetRGBPalette \(644\)](#)

### 18.13.62 SetTextJustify

Synopsis: Set text placement style

Declaration: `procedure SetTextJustify (horiz: Word; vert: Word)`

Visibility: default

Description: **SetTextJustify** controls the placement of new text, relative to the (graphical) cursor position. **Horizontal** controls horizontal placement, and can be one of the following pre-defined constants:

**LeftText** Text is set left of the pointer.

**CenterText** Text is set centered horizontally on the pointer.

**RightText** Text is set to the right of the pointer.

**Vertical** controls the vertical placement of the text, relative to the (graphical) cursor position. Its value can be one of the following pre-defined constants :

**BottomText** Text is placed under the pointer.

**CenterText** Text is placed centered vertically on the pointer.

**TopText** Text is placed above the pointer.

Errors: None.

See also: [OutText \(656\)](#), [OutTextXY \(643\)](#)

### 18.13.63 SetTextStyle

Synopsis: Set text style

Declaration: `procedure SetTextStyle(font: Word; direction: Word; charsize: Word)`

Visibility: default

Description: `SetTextStyle` controls the style of text to be put on the screen. pre-defined constants for `Font` are:

**DefaultFont**The default font

**TriplexFont**A special font

**SmallFont**A smaller font

**SansSerifFont**A sans-serif font (like Arial)

**GothicFont**A gothic font

**ScriptFont**A script font

**SimpleFont**A simple font

**TSCRFont**Terminal screen font

**LCOMFont?**

**EuroFont?**

**BoldFont**A bold typeface font

Pre-defined constants for `Direction` are :

**HorizDir**Write horizontal

**VertDir**Write vertical

Errors: None.

See also: `GetTextSettings` ([652](#))

### 18.13.64 SetUserCharSize

Synopsis: Set user character size for vector font

Declaration: `procedure SetUserCharSize(Multx: Word; Divx: Word; Multy: Word; Divy: Word)`

Visibility: default

Description: Sets the width and height of vector-fonts. The horizontal size is given by `Xasp1/Xasp2`, and the vertical size by `Yasp1/Yasp2`.

Errors: None.

See also: `SetTextStyle` ([662](#))



**18.13.65 SetViewPort**

Synopsis: Set the graphical drawing window

Declaration: `procedure SetViewPort (X1: SmallInt; Y1: SmallInt; X2: SmallInt;  
Y2: SmallInt; Clip: Boolean)`

Visibility: default

Description: Sets the current graphical viewport (window) to the rectangle defined by the top-left corner (X1, Y1) and the bottom-right corner (X2, Y2). If Clip is true, anything drawn outside the viewport (window) will be clipped (i.e. not drawn). Coordinates specified after this call are relative to the top-left corner of the viewport.

Errors: None.

See also: `GetViewSettings` ([652](#))

**18.13.66 SetWriteMode**

Synopsis: Specify binary operation to perform when drawing on screen

Declaration: `procedure SetWriteMode (WriteMode: SmallInt)`

Visibility: default

Description: `SetWriteMode` controls the drawing of lines on the screen. It controls the binary operation used when drawing lines on the screen. Mode can be one of the following pre-defined constants:

**CopyPutDraw** as specified using current bitmask and color

**XORPutDraw** XOR-ing current bitmask and color

Errors: None.

See also: `SetColor` ([659](#)), `SetBkColor` ([659](#)), `SetLineStyle` ([660](#)), `SetFillStyle` ([660](#))

**18.13.67 TextHeight**

Synopsis: Return height (in pixels) of the given string

Declaration: `function TextHeight (const TextString: String) : Word`

Visibility: default

Description: `TextHeight` returns the height (in pixels) of the string S in the current font and text-size.

Errors: None.

See also: `TextWidth` ([663](#))

**18.13.68 TextWidth**

Synopsis: Return width (in pixels) of the given string

Declaration: `function TextWidth (const TextString: String) : Word`

Visibility: default

Description: `TextWidth` returns the width (in pixels) of the string S in the current font and text-size.

Errors: None.

See also: TextHeight ([663](#))

## Chapter 19

# Reference for unit 'heaptrc'

### 19.1 Overview

This document describes the HEAPTRC unit for Free Pascal. It was written by Pierre Muller. It is system independent, and works on all supported systems.

The HEAPTRC unit can be used to debug your memory allocation/deallocation. It keeps track of the calls to `getmem/freemem`, and, implicitly, of `New/Dispose` statements.

When the program exits, or when you request it explicitly. It displays the total memory used, and then dumps a list of blocks that were allocated but not freed. It also displays where the memory was allocated.

If there are any inconsistencies, such as memory blocks being allocated or freed twice, or a memory block that is released but with wrong size, this will be displayed also.

The information that is stored/displayed can be customized using some constants.

### 19.2 Controlling HeapTrc with environment variables

The `HeapTrc` unit can be controlled with the `HEAPTRC` environment variable. The contents of this variable controls the initial setting of some constants in the unit. `HEAPTRC` consists of one or more of the following strings, separated by spaces:

**keepreleased** If this string occurs, then the `KeepReleased` (667) variable is set to `True`

**disabled** If this string occurs, then the `UseHeapTrace` (667) variable is set to `False` and the heap trace is disabled. It does not make sense to combine this value with other values.

**nohalt** If this string occurs, then the `HaltOnError` (666) variable is set to `False`, so the program continues executing even in case of a heap error.

**log=filename** If this string occurs, then the output of `heaptrc` is sent to the specified `Filename`. (see also `SetHeapTraceOutput` (669))

The following are valid values for the `HEAPTRC` variable:

```
HEAPTRC=disabled
HEAPTRC="keepreleased log=heap.log"
HEAPTRC="log=myheap.log nohalt"
```

Note that these strings are case sensitive, and the name of the variable too.

## 19.3 HeapTrc Usage

All that you need to do is to include `heaptrc` in the `uses` clause of your program. Make sure that it is the first unit in the clause, otherwise memory allocated in initialization code of units that precede the `heaptrc` unit will not be accounted for, causing an incorrect memory usage report.

If you use the `-gh` switch, the compiler will insert the unit by itself, so you don't have to include it in your `uses` clause.

The below example shows how to use the `heaptrc` unit.

This is the memory dump shown when running this program in a standard way:

```
Marked memory at 0040FA50 invalid
Wrong size : 128 allocated 64 freed
  0x00408708
  0x0040CB49
  0x0040C481
Call trace for block 0x0040FA50 size 128
  0x0040CB3D
  0x0040C481
```

If you use the `lineinfo` unit (or use the `-gl` switch) as well, then `heaptrc` will also give you the filenames and line-numbers of the procedures in the backtrace:

```
Marked memory at 00410DA0 invalid
Wrong size : 128 allocated 64 freed
  0x004094B8
  0x0040D8F9  main,   line 25 of heapex.pp
  0x0040D231
Call trace for block 0x00410DA0 size 128
  0x0040D8ED  main,   line 23 of heapex.pp
  0x0040D231
```

If lines without filename/line-number occur, this means there is a unit which has no debug info included.

## 19.4 Constants, types and variables

### 19.4.1 Constants

```
add_tail : Boolean = true
```

If `add\_tail` is `True` (the default) then a check is also performed on the memory location just behind the allocated memory.

```
HaltOnError : Boolean = true
```

If `HaltOnError` is set to `True` then an illegal call to `FreeMem` will cause the memory manager to execute a `halt (1)` instruction, causing a memory dump. By Default it is set to `True`.

```
HaltOnNotReleased : Boolean = false
```

`HaltOnNotReleased` can be set to `True` to make the `DumpHeap` (667) procedure halt (exit code 203) the program if any memory was not released when the dump is made. If it is `False` (the default) then `DumpHeap` just returns.

```
keepreleased : Boolean = false
```

If `keepreleased` is set to `true`, then a list of freed memory blocks is kept. This is useful if you suspect that the same memory block is released twice. However, this option is very memory intensive, so use it sparingly, and only when it's really necessary.

```
quicktrace : Boolean = true
```

`Quicktrace` determines whether the memory manager checks whether a block that is about to be released is allocated correctly. This is a rather time consuming search, and slows program execution significantly, so by default it is set to `True`.

```
tracesize = 8
```

`Tracesize` specifies how many levels of calls are displayed of the call stack during the memory dump. If you specify `keepreleased:=True` then half the `TraceSize` is reserved for the `GetMem` call stack, and the other half is reserved for the `FreeMem` call stack. For example, the default value of 8 will cause eight levels of call frames to be dumped for the `getmem` call if `keepreleased` is `False`. If `KeepReleased` is `true`, then 4 levels of call frames will be dumped for the `GetMem` call and 4 frames will be dumped for the `FreeMem` call. If you want to change this value, you must recode the `heaptrc` unit.

```
usecrc : Boolean = true
```

If `usecrc` is `True` (the default) then a crc check is performed on locations before and after the allocated memory. This is useful to detect memory overwrites.

```
useheaptrace : Boolean = true
```

This variable must be set at program startup, through the help of an environment variable.

## 19.4.2 Types

```
tDisplayExtraInfoProc = procedure(var ptext: text;p: pointer)
```

The `TDisplayExtraInfoType` is a procedural type used in the `SetHeapExtraInfo` (668) call to display a memory location which was previously filled with `TFillExtraInfoProc` (667)

```
tFillExtraInfoProc = procedure(p: pointer)
```

The `TFillExtraInfoProc` is a procedural type used in the `SetHeapExtraInfo` (668) call to fill a memory location with extra data for displaying.

## 19.5 Procedures and functions

### 19.5.1 DumpHeap

Synopsis: Dump memory usage report to stderr.

**Declaration:** `procedure DumpHeap`

**Visibility:** `default`

**Description:** `DumpHeap` dumps to standard output a summary of memory usage. It is called automatically by the `heaptrc` unit when your program exits (by installing an exit procedure), but it can be called at any time.

**Errors:** None.

**See also:** `MarkHeap` ([665](#))

### 19.5.2 SetHeapExtraInfo

**Synopsis:** Store extra information in blocks.

**Declaration:** `procedure SetHeapExtraInfo(size: ptruint; fillproc: tFillExtraInfoProc;  
displayproc: tdisplayextrainfoProc)`

**Visibility:** `default`

**Description:** You can use `SetHeapExtraInfo` to store extra info in the blocks that the `heaptrc` unit reserves when tracing `getmem` calls. `Size` indicates the size (in bytes) that the trace mechanism should reserve for your extra information. For each call to `getmem`, `FillProc` will be called, and passed a pointer to the memory reserved.

When dumping the memory summary, the extra info is shown by calling `displayproc` and passing it the memory location which was filled by `fillproc`. It should write the information in readable form to the text file provided in the call to `displayproc`

**Errors:** You can only call `SetHeapExtraInfo` if no memory has been allocated yet. If memory was already allocated prior to the call to `SetHeapExtraInfo`, then an error will be displayed on standard error output, and a `DumpHeap` ([667](#)) is executed.

**See also:** `DumpHeap` ([667](#)), `SetHeapTraceOutput` ([669](#))

**Listing:** `./heapex/setinfo.pp`

---

**Program** `heapex`;

*{ Program used to demonstrate the usage of heaptrc unit }*

**Uses** `heaptrc`;

**Var** `P1 : ^Longint;  
P2 : Pointer;  
I : longint;  
Marker : Longint;`

**Procedure** `SetMarker (P : pointer);`

**Type** `PLongint = ^Longint;`

**begin**  
    `PLongint(P)^:=Marker;`  
**end**;

**Procedure** `Part1;`

---

```

begin
  // Blocks allocated here are marked with $FFAAFFAA = -5570646
  Marker := $FFAAFFAA;
  New(P1);
  New(P1);
  Dispose(P1);
  For I:=1 to 10 do
    begin
      GetMem (P2,128);
      If (I mod 2) = 0 Then FreeMem(P2,128);
    end;
  GetMem(P2,128);
end;

Procedure Part2;

begin
  // Blocks allocated here are marked with $FAFAFAFA = -84215046
  Marker := $FAFAFAFA;
  New(P1);
  New(P1);
  Dispose(P1);
  For I:=1 to 10 do
    begin
      GetMem (P2,128);
      If (I mod 2) = 0 Then FreeMem(P2,128);
    end;
  GetMem(P2,128);
end;

begin
  SetExtraInfo (SizeOf(Marker), @SetMarker);
  Writeln ( 'Part 1 ');
  part1;
  Writeln ( 'Part 2 ');
  part2;
end.

```

---

### 19.5.3 SetHeapTraceOutput

Synopsis: Specify filename for heap trace output.

Declaration: `procedure SetHeapTraceOutput(const name: String)`

Visibility: default

Description: `SetHeapTraceOutput` sets the filename into which heap trace info will be written. By default information is written to standard output, this function allows you to redirect the information to a file with full filename `name`.

Errors: If the file cannot be written to, errors will occur when writing the trace.

See also: `SetHeapExtraInfo` ([668](#))

## Chapter 20

# Reference for unit 'ipc'

### 20.1 Used units

Table 20.1: Used units by unit 'ipc'

Name	Page
BaseUnix	<a href="#">670</a>
UnixType	<a href="#">670</a>

### 20.2 Overview

This document describes the IPC unit for Free Pascal. It was written for linux by Michael Van Canneyt. It gives all the functionality of System V Inter-Process Communication: shared memory, semaphores and messages. It works only on the linux operating system.

Many constants here are provided for completeness only, and should under normal circumstances not be used by the programmer.

### 20.3 Constants, types and variables

#### 20.3.1 Constants

`IPC_CREAT = 1sh19`

Create if key is nonexistent

`IPC_EXCL = 2sh19`

fail if key exists

`IPC_INFO = 3`

For ipcs call



IPC\_NOWAIT = 4sh19

return error on wait

IPC\_RMID = 0

Remove resource

IPC\_SET = 1

set ipc\_perm options

IPC\_STAT = 2

get ipc\_perm options

MSGMAX = 4056

Internal Message control code. Do not use

MSGMNB = 16384

Internal Message control code. Do not use

MSGMNI = 128

Internal Message control code. Do not use

MSG\_EXCEPT = 2sh112

Internal Message control code. Do not use

MSG\_NOERROR = 1sh112

Internal Message control code. Do not use

SEM\_GETALL = 13

Semaphore operation: Get all semaphore values

SEM\_GETNCNT = 14

Semaphore operation: Get number of processes waiting for resource.

SEM\_GETPID = 11

Semaphore operation: Get process ID of last operation.

SEM\_GETVAL = 12

Semaphore operation: Get current value of semaphore

SEM\_GETZCNT = 15

Semaphore operation: Get number of processes waiting for semaphores to reach zero

SEM\_SEMMNI = 128

Semaphore operation: ?

SEM\_SEMMNS = (SEM\_SEMMNI\*SEM\_SEMMSL)

Semaphore operation: ?

SEM\_SEMMSL = 32

Semaphore operation: ?

SEM\_SEMOPM = 32

Semaphore operation: ?

SEM\_SEVMX = 32767

Semaphore operation: ?

SEM\_SETALL = 17

Semaphore operation: Set all semaphore values

SEM\_SETVAL = 16

Semaphore operation: Set semaphore value

SEM\_UNDO = \$1000

Constant for use in semop (686)

SHM\_LOCK = 11

This constant is used in the shmctl (688) call.

SHM\_R = 4shl6

This constant is used in the shmctl (688) call.

SHM\_RDONLY = 1shl12

This constant is used in the shmctl (688) call.

SHM\_REMAP = 4shl12

This constant is used in the shmctl (688) call.

```
SHM_RND = 2shl12
```

This constant is used in the shmctl (688) call.

```
SHM_UNLOCK = 12
```

This constant is used in the shmctl (688) call.

```
SHM_W = 2shl6
```

This constant is used in the shmctl (688) call.

### 20.3.2 Types

```
key_t = TKey
```

Alias for TKey (674) type

```
msglen_t = culong
```

Message length type

```
msgqnum_t = culong
```

Message queue number type

```
PIPC_Perm = ^TIPC_Perm
```

Pointer to TIPC\_Perm (674) record.

```
PMSG = ^TMSG
```

Pointer to TMSG (674) record

```
PMSGbuf = ^TMSGbuf
```

Pointer to TMsgBuf (675) record

```
PMSGinfo = ^TMSGinfo
```

Pointer to TMSGinfo (675) record

```
PMSQid_ds = ^TMSQid_ds
```

Pointer to TMSQid\_ds (675)

```
PSEMBuf = ^TSEMBuf
```

Pointer to Tsembuf (675) record.

```
PSEMid_ds = ^TSEMid_ds
```

Pointer to TSEMid\_ds (676) record.

```
PSEMinfo = ^TSEMinfo
```

Pointer to TSEMinfo (676) record.

```
PSEMun = ^TSEMun
```

Pointer to TSEMun (676) record

```
PShmid_DS = ^TShmid_ds
```

Pointer to TSHMid\_ds (676) record.

```
PSHMinfo = ^TSHMinfo
```

```
TIPC_Perm = record
  key : TKey;
  uid : uid_t;
  gid : gid_t;
  cuid : uid_t;
  cgid : gid_t;
  mode : mode_t;
  seq : cushort;
end
```

TIPC\_Perm is used in all IPC systems to specify the permissions. It should never be used directly.

```
TKey = cint
```

Type returned by the ftok (677) key generating function.

```
TMSG = record
  msg_next : PMSG;
  msg_type : LongInt;
  msg_spot : PChar;
  msg_stime : LongInt;
  msg_ts : Integer;
end
```

Record used in the handling of message queues. Do not use directly.

```
TMSGbuf = record
  mtype : clong;
  mtext : Array[0..0] of Char;
end
```

The TMSGbuf record is a record containing the data of a record. you should never use this record directly, instead you should make your own record that follows the structure of the TMSGbuf record, but that has a size that is big enough to accomodate your messages. The `mtype` field should always be present, and should always be filled.

```
TMSGinfo = record
  msgpool : cint;
  msgmap : cint;
  msgmax : cint;
  msgmnb : cint;
  msgmni : cint;
  msgssz : cint;
  msgtql : cint;
  msgseg : cushort;
end
```

Internal message system record. Do not use directly.

```
TMSQid_ds = record
  msg_perm : TIPC_Perm;
  msg_first : PMSG;
  msg_last : PMSG;
  msg_stime : time_t;
  msg_rtime : time_t;
  msg_ctime : time_t;
  msg_cbytes : Word;
  msg_qnum : Word;
  msg_qbytes : Word;
  msg_lspid : ipc_pid_t;
  msg_lrpid : ipc_pid_t;
end
```

This record should never be used directly, it is an internal kernel record. It's fields may change at any time.

```
TSEMbuf = record
  sem_num : cushort;
  sem_op : cshort;
  sem_flg : cshort;
end
```

The TSEMbuf record is used in the `semop` (686) call, and is used to specify which operations you want to do.

```
TSEMid_ds = record
  sem_perm : TIPC_Perm;
  sem_otime : time_t;
  sem_ctime : time_t;
  sem_base : pointer;
  sem_pending : pointer;
```

```

    sem_pending_last : pointer;
    undo : pointer;
    sem_nsems : cushort;
end

```

Structure returned by the `semctl` (681) call, contains all data of a semaphore

```

TSEMinfo = record
    semmap : cint;
    semmni : cint;
    semmns : cint;
    semmnu : cint;
    semmsl : cint;
    semopm : cint;
    semume : cint;
    semusz : cint;
    semvmx : cint;
    semaem : cint;
end

```

Internal semaphore system record. Do not use.

```

TSEMun = record
end

```

Record used in `semctl` (681) call.

```

TShmid_ds = record
    shm_perm : TIPC_Perm;
    shm_segsz : cint;
    shm_atime : time_t;
    shm_dtime : time_t;
    shm_ctime : time_t;
    shm_cpid : ipc_pid_t;
    shm_lpid : ipc_pid_t;
    shm_nattch : Word;
    shm_npages : Word;
    shm_pages : pointer;
    attaches : pointer;
end

```

Record used in the `shmctl` (688) call to set or retrieve settings for shared memory.

```

TSHMinfo = record
    shmmax : cint;
    shmmni : cint;
    shmmni : cint;
    shmseg : cint;
    shmall : cint;
end

```

Record used by the shared memory system, Do not use directly.

## 20.4 Procedures and functions

### 20.4.1 ftok

Synopsis: Create token from filename

Declaration: `function ftok(Path: pchar; ID: cint) : TKey`

Visibility: default

Description: `ftok` returns a key that can be used in a `semget` (686) `shmget` (690) or `msgget` (680) call to access a new or existing IPC resource.

`Path` is the name of a file in the file system, `ID` is a character of your choice. The `ftok` call does the same as it's C counterpart, so a pascal program and a C program will access the same resource if they use the same `Path` and `ID`

For an example, see `msgctl` (677), `semctl` (681) or `shmctl` (688).

Errors: `ftok` returns -1 if the file in `Path` doesn't exist.

See also: `semget` (686), `shmget` (690), `msgget` (680)

### 20.4.2 msgctl

Synopsis: Perform various operations on a message queue

Declaration: `function msgctl(msqid: cint; cmd: cint; buf: PMSQid_ds) : cint`

Visibility: default

Description: `msgctl` performs various operations on the message queue with id `ID`. Which operation is performed, depends on the `cmd` parameter, which can have one of the following values:

**IPC\_STAT** In this case, the `msgctl` call fills the `TMSQid_ds` structure with information about the message queue.

**IPC\_SET** In this case, the `msgctl` call sets the permissions of the queue as specified in the `ipc_perm` record inside `buf`.

**IPC\_RMID** If this is specified, the message queue will be removed from the system.

`buf` contains the data that are needed by the call. It can be `Nil` in case the message queue should be removed.

The function returns `True` if successful, `False` otherwise.

Errors: On error, `False` is returned, and `IPCError` is set accordingly.

See also: `msgget` (680), `msgsnd` (681), `msgrcv` (680)

**Listing:** `./ipcex/msgtool.pp`

---

**program** `msgtool`;

**Uses** `ipc`, `baseunix`;

**Type**

```

PMyMsgBuf = ^TMyMsgBuf;
TMyMsgBuf = record
  mtype : Longint;
  mtext : string[255];
end;

Procedure DoError (Const Msg : string);

begin
  Writeln (msg, ' returned an error : ',fpgeterrno);
  halt(1);
end;

Procedure SendMessage (Id : Longint;
  Var Buf : TMyMsgBuf;
  MType : Longint;
  Const MText : String);

begin
  Writeln ( 'Sending message. ');
  Buf.mtype:=mtype;
  Buf.Mtext:=mtext;
  If msgsnd(Id ,PMsgBuf(@Buf),256,0)=-1 then
    DoError( 'msgsnd ');
end;

Procedure ReadMessage (ID : Longint;
  Var Buf : TMyMsgBuf;
  MType : longint);

begin
  Writeln ( 'Reading message. ');
  Buf.MType:=MType;
  If msgrcv(ID ,PMSGBuf(@Buf),256,mtype,0)<>-1 then
    Writeln ( 'Type : ',buf.mtype, ' Text : ',buf.mtext)
  else
    DoError ( 'msgrcv ');
end;

Procedure RemoveQueue ( ID : Longint);

begin
  If msgctl (id ,IPC_RMID,Nil)<>-1 then
    Writeln ( 'Removed Queue with id ',Id);
end;

Procedure ChangeQueueMode (ID,mode : longint);

Var QueueDS : TMSQid_ds;

begin
  If msgctl (Id ,IPC_STAT,@QueueDS)=-1 then
    DoError ( 'msgctl : stat ');
  Writeln ( 'Old permissions : ',QueueDS.msg_perm.mode);
  QueueDS.msg_perm.mode:=Mode;
  if msgctl (ID ,IPC_SET,@QueueDS)=0 then
    Writeln ( 'New permissions : ',QueueDS.msg_perm.mode)
  else

```



---

```

    DoError ( 'msgctl : IPC_SET');
end;

procedure usage;

begin
    Writeln ( 'Usage : msgtool s(end)    <type> <text> (max 255 characters) ');
    Writeln ( '                      r(eceive) <type> ');
    Writeln ( '                      d(etele) ');
    Writeln ( '                      m(ode) <decimal mode> ');
    halt(1);
end;

Function StrToInt (S : String): longint;

Var M : longint;
    C : Integer;

begin
    val (S,M,C);
    If C<>0 Then DoError ( 'StrToInt : '+S);
    StrToInt:=M;
end;

Var
    Key : TKey;
    ID : longint;
    Buf : TMyMsgBuf;

const ipckey = '. '#0;

begin
    If Paramcount<1 then Usage;
    key := Ftok (@ipckey[1], ord( 'M' ));
    ID:=msgget(key,IPC_CREAT or 438);
    If ID<0 then DoError ( 'MsgGet');
    Case upCase(Paramstr(1)[1]) of
        'S' : If ParamCount<>3 then
            Usage
        else
            SendMessage ( id , Buf , StrToInt (Paramstr(2)) , paramstr(3));
        'R' : If ParamCount<>2 then
            Usage
        else
            ReadMessage ( id , buf , strtoint (Paramstr(2)));
        'D' : If ParamCount<>1 then
            Usage
        else
            RemoveQueue ( ID );
        'M' : If ParamCount<>2 then
            Usage
        else
            ChangeQueueMode ( id , strtoint (paramstr(2)));
    else
        Usage
    end;
end.

```

---

### 20.4.3 msgget

**Synopsis:** Return message queue ID, possibly creating the queue

**Declaration:** `function msgget(key: TKey;msgflg: cint) : cint`

**Visibility:** default

**Description:** `msgget` returns the ID of the message queue described by `key`. Depending on the flags in `msgflg`, a new queue is created.

`msgflg` can have one or more of the following values (combined by ORs):

**IPC\_CREAT**The queue is created if it doesn't already exist.

**IPC\_EXCL**If used in combination with `IPC_CREAT`, causes the call to fail if the queue already exists. It cannot be used by itself.

Optionally, the flags can be ORed with a permission mode, which is the same mode that can be used in the file system.

For an example, see `msgctl` (677).

**Errors:** On error, -1 is returned, and `IPCError` is set.

See also: `ftok` (677), `msgsnd` (681), `msgrcv` (680), `msgctl` (677)

### 20.4.4 msgrcv

**Synopsis:** Retrieve a message from the queue

**Declaration:** `function msgrcv(msqid: cint;msgp: PMSGbuf;msgsz: size_t;msgtyp: cint;msgflg: cint) : cint`

**Visibility:** default

**Description:** `msgrcv` retrieves a message of type `msgtyp` from the message queue with ID `msqid`. `msgtyp` corresponds to the `mtype` field of the `TMSGbuf` record. The message is stored in the `MSGbuf` structure pointed to by `msgp`.

The `msgflg` parameter can be used to control the behaviour of the `msgrcv` call. It consists of an ORed combination of the following flags:

**0**No special meaning.

**IPC\_NOWAIT**If no messages are available, then the call returns immediately, with the `ENOMSG` error.

**MSG\_NOERROR**If the message size is wrong (too large), no error is generated, instead the message is truncated. Normally, in such cases, the call returns an error (`E2BIG`)

The function returns `True` if the message was received correctly, `False` otherwise.

For an example, see `msgctl` (677).

**Errors:** In case of error, `False` is returned, and `IPCError` is set.

See also: `msgget` (680), `msgsnd` (681), `msgctl` (677)

### 20.4.5 msgsnd

**Synopsis:** Send a message to the message queue

**Declaration:** `function msgsnd(msqid: cint;msgp: PMSGbuf;msgsz: size_t;msgflg: cint)  
: cint`

**Visibility:** default

**Description:** `msgsnd` sends a message to a message queue with ID `msqid`. `msgp` is a pointer to a message buffer, that should be based on the `TMsgBuf` type. `msgsz` is the size of the message (NOT of the message buffer record !)

The `msgflg` can have a combination of the following values (ORed together):

**0**No special meaning. The message will be written to the queue. If the queue is full, then the process is blocked.

**IPC\_NOWAIT**If the queue is full, then no message is written, and the call returns immediately.

The function returns `True` if the message was sent successfully, `False` otherwise.

For an example, see `msgctl` (677).

**Errors:** In case of error, the call returns `False`, and `IPCError` is set.

See also: `msgget` (680), `msgrcv` (680), `msgctl` (677)

### 20.4.6 semctl

**Synopsis:** Perform various control operations on a semaphore set

**Declaration:** `function semctl(semid: cint;semnum: cint;cmd: cint;var arg: TSEMun)  
: cint`

**Visibility:** default

**Description:** `semctl` performs various operations on the semaphore `semnum` with semaphore set id `ID`.

The `arg` parameter supplies the data needed for each call. This is a variant record that should be filled differently, according to the command:

```
Type
TSEMun = record
  case longint of
    0 : ( val : longint );
    1 : ( buf : PSEMid_ds );
    2 : ( arr : PWord );
    3 : ( padbuf : PSEminfo );
    4 : ( padpad : pointer );
  end;
```

Which operation is performed, depends on the `cmd` parameter, which can have one of the following values:

**IPC\_STAT**In this case, the `arg` record should have its `buf` field set to the address of a `TSEMid_ds` record. The `semctl` call fills this `TSEMid_ds` structure with information about the semaphore set.

**IPC\_SET**In this case, the `arg` record should have its `buf` field set to the address of a `TSEMid_ds` record. The `semctl` call sets the permissions of the queue as specified in the `ipc_perm` record.

**IPC\_RMID**If this is specified, the semaphore set is removed from the system.

**GETALL**In this case, the `arr` field of `arg` should point to a memory area where the values of the semaphores will be stored. The size of this memory area is `\var{SizeOf(Word)* Number of semaphores in the set}`. This call will then fill the memory array with all the values of the semaphores.

**GETNCNT**This will fill the `val` field of the `arg` union with the number of processes waiting for resources.

**GETPID**`semctl` returns the process ID of the process that performed the last `semop` (686) call.

**GETVAL**`semctl` returns the value of the semaphore with number `semnum`.

**GETZCNT**`semctl` returns the number of processes waiting for semaphores that reach value zero.

**SETALL**In this case, the `arr` field of `arg` should point to a memory area where the values of the semaphores will be retrieved from. The size of this memory area is `\var{SizeOf(Word)* Number of semaphores in the set}`. This call will then set the values of the semaphores from the memory array.

**SETVAL**This will set the value of semaphore `semnum` to the value in the `val` field of the `arg` parameter.

The function returns -1 on error.

Errors: The function returns -1 on error, and `IPCError` is set accordingly.

See also: `semget` (686), `semop` (686)

**Listing:** `./ipccex/semtool.pp`

---

**Program** `semtool`;

*{ Program to demonstrat the use of semaphores }*

**Uses** `ipc,baseunix`;

**Const** `MaxSemValue = 5`;

**Procedure** `DoError (Const Msg : String)`;

```
begin
  Writeln ( 'Error : ',msg, ' Code : ',fpgeterrno);
  Halt(1);
end;
```

**Function** `getsemval (ID,Member : longint) : longint`;

**Var** `S : TSEMun`;

```
begin
  GetSemVal:= SemCtl(id ,member,SEM_GETVAL,S);
end;
```

**Procedure** `DispVal (ID,member : longint)`;

```
begin
  writeln ( 'Value for member ',member, ' is ',GetSemVal(ID,Member));
```

```

end;

Function GetMemberCount (ID : Longint) : longint;

Var opts : TSEMun;
    semds : TSEMid_ds;

begin
    opts.buf:=@semds;
    If semctl(Id,0,IPC_STAT,opts)<>-1 then
        GetMemberCount:=semds.sem_nsems
    else
        GetMemberCount:=-1;
end;

Function OpenSem (Key : TKey) : Longint;

begin
    OpenSem:=semget(Key,0,438);
    If OpenSem=-1 then
        DoError ('OpenSem');
end;

Function CreateSem (Key : TKey; Members : Longint) : Longint;

Var Count : Longint;
    Semopts : TSemun;

begin
    // the semmsl constant seems kernel specific
    { If members>semmsl then
        DoError ('Sorry, maximum number of semaphores in set exceeded');
    }
    WriteLn ('Trying to create a new semaphore set with ',members,' members. ');
    CreateSem:=semget(key,members,IPC_CREAT or IPC_Excl or 438);
    If CreateSem=-1 then
        DoError ('Semaphore set already exists. ');
    Semopts.val:=MaxSemValue; { Initial value of semaphores }
    For Count:=0 to Members-1 do
        semctl(CreateSem,count,SEM_SETVAL,semopts);
end;

Procedure lockSem (ID,Member: Longint);

Var lock : TSEMbuf;

begin
    With lock do
        begin
            sem_num:=0;
            sem_op:=-1;
            sem_flg:=IPC_NOWAIT;
        end;
        if (member<0) or (member>GetMemberCount(ID)-1) then
            DoError ('semaphore member out of range ');
        if getsemval(ID,member)=0 then
            DoError ('Semaphore resources exhausted (no lock) ');
        lock.sem_num:=member;

```

```

Writeln ( 'Attempting to lock member ',member, ' of semaphore ',ID );
if semop( Id ,@lock,1)=-1 then
    DoError ( 'Lock failed ' )
else
    Writeln ( 'Semaphore resources decremented by one ' );
    dispval( ID ,Member );
end;

Procedure UnlockSem ( ID ,Member: Longint );

Var Unlock : TSEMbuf;

begin
    With Unlock do
        begin
            sem_num:=0;
            sem_op:=1;
            sem_flg:=IPC_NOWAIT;
        end;
        if ( member<0 ) or ( member>GetMemberCount( ID )-1 ) then
            DoError ( 'semaphore member out of range ' );
        if getsemval( ID ,member)=MaxSemValue then
            DoError ( 'Semaphore not locked ' );
        Unlock.sem_num:=member;
        Writeln ( 'Attempting to unlock member ',member, ' of semaphore ',ID );
        if semop( Id ,@unlock,1)=-1 then
            DoError ( 'Unlock failed ' )
        else
            Writeln ( 'Semaphore resources incremented by one ' );
            dispval( ID ,Member );
        end;

Procedure RemoveSem ( ID : longint );

var S : TSemun;

begin
    If semctl( Id ,0 ,IPC_RMID ,s)<>-1 then
        Writeln ( 'Semaphore removed ' )
    else
        DoError ( 'Couldn't remove semaphore ' );
end;

Procedure ChangeMode ( ID ,Mode : longint );

Var rc : longint;
    opts : TSEMun;
    semds : TSEMid_ds;

begin
    opts.buf:=@semds;
    If not semctl ( Id ,0 ,IPC_STAT ,opts)<>-1 then
        DoError ( 'Couldn't stat semaphore ' );
    Writeln ( 'Old permissions were : ',semds.sem_perm.mode );
    semds.sem_perm.mode:=mode;
    If semctl( id ,0 ,IPC_SET ,opts)<>-1 then
        Writeln ( 'Set permissions to ',mode)

```

```

    else
        DoError ( 'Couldn't set permissions' );
end;

Procedure PrintSem ( ID : longint );

Var I, cnt : longint;

begin
    cnt:=getmembercount(ID);
    Writeln ( 'Semaphore ', ID, ' has ', cnt, ' Members' );
    For I:=0 to cnt-1 Do
        DispVal(id, i);
end;

Procedure USage;

begin
    Writeln ( 'Usage : semtool c(reate) <count>' );
    Writeln ( '          l(ock) <member>' );
    Writeln ( '          u(nlock) <member>' );
    Writeln ( '          d(elete)' );
    Writeln ( '          m(ode) <mode>' );
    halt(1);
end;

Function StrToInt ( S : String ): longint;

Var M : longint;
    C : Integer;

begin
    val ( S,M,C );
    If C<>0 Then DoError ( 'StrToInt : '+S );
    StrToInt:=M;
end;

Var Key : TKey;
    ID : Longint;

const ipckey='.#0;

begin
    If ParamCount<1 then USage;
    key:=ftok ( @ipckey[1],ORD( 's' ));
    Case UpCase(Paramstr(1)[1]) of
        'C' : begin
            if paramcount<>2 then usage;
            CreateSem ( key, strtoint ( paramstr (2) ));
            end;
        'L' : begin
            if paramcount<>2 then usage;
            ID:=OpenSem ( key );
            LockSem ( ID, strtoint ( paramstr (2) ));
            end;
        'U' : begin
            if paramcount<>2 then usage;

```

---

```

        ID:=OpenSem ( key );
        UnLockSem ( ID , strtoint ( paramstr ( 2 ) ) );
        end;
'M' : begin
        if paramcount<>2 then usage;
        ID:=OpenSem ( key );
        ChangeMode ( ID , strtoint ( paramstr ( 2 ) ) );
        end;
'D' : Begin
        ID:=OpenSem ( Key );
        RemoveSem ( Id );
        end;
'P' : begin
        ID:=OpenSem ( Key );
        PrintSem ( Id );
        end;
else
    Usage
end;
end.

```

---

### 20.4.7 semget

**Synopsis:** Return the ID of a semaphore set, possibly creating the set

**Declaration:** `function semget (key: TKey; nsems: cint; semflg: cint) : cint`

**Visibility:** default

**Description:** `msgget` returns the ID of the semaphore set described by `key`. Depending on the flags in `semflg`, a new queue is created.

`semflg` can have one or more of the following values (combined by ORs):

**IPC\_CREAT** The queue is created if it doesn't already exist.

**IPC\_EXCL** If used in combination with `IPC_CREAT`, causes the call to fail if the set already exists. It cannot be used by itself.

Optionally, the flags can be ORed with a permission mode, which is the same mode that can be used in the file system.

if a new set of semaphores is created, then there will be `nsems` semaphores in it.

**Errors:** On error, -1 is returned, and `IPCError` is set.

See also: `ftok` ([677](#)), `semop` ([686](#)), `semctl` ([681](#))

### 20.4.8 semop

**Synopsis:** Perform semaphore operation.

**Declaration:** `function semop (semid: cint; sops: PSEMbuf; nsops: cuint) : cint`

**Visibility:** default

**Description:** `semop` performs a set of operations on a message queue. `sops` points to an array of type `TSEMbuf`. The array should contain `nsops` elements.

The fields of the `TSEMbuf` ([675](#)) structure



```
TSEMBuf = record
    sem_num : word;
    sem_op  : integer;
    sem_flg : integer;
```

should be filled as follows:

**sem\_num**The number of the semaphore in the set on which the operation must be performed.

**sem\_op**The operation to be performed. The operation depends on the sign of `sem_op`: A positive number is simply added to the current value of the semaphore. If 0 (zero) is specified, then the process is suspended until the specified semaphore reaches zero. If a negative number is specified, it is subtracted from the current value of the semaphore. If the value would become negative then the process is suspended until the value becomes big enough, unless `IPC_NOWAIT` is specified in the `sem_flg`.

**sem\_flg**Optional flags: if `IPC_NOWAIT` is specified, then the calling process will never be suspended.

The function returns `True` if the operations were successful, `False` otherwise.

Errors: In case of error, `False` is returned, and `IPCError` is set.

See also: `semget` (686), `semctl` (681)

## 20.4.9 shmat

Synopsis: Attach a shared memory block.

Declaration: `function shmat(shmid: cint; shmaddr: pointer; shmflg: cint) : pointer`

Visibility: default

Description: `shmat` attaches a shared memory block with identified `shmid` to the current process. The function returns a pointer to the shared memory block.

If `shmaddr` is `Nil`, then the system chooses a free unmapped memory region, as high up in memory space as possible.

If `shmaddr` is non-nil, and `SHM_RND` is in `shmflg`, then the returned address is `shmaddr`, rounded down to `SHMLBA`. If `SHM_RND` is not specified, then `shmaddr` must be a page-aligned address.

The parameter `shmflg` can be used to control the behaviour of the `shmat` call. It consists of a ORed combination of the following constants:

**SHM\_RND**The suggested address in `shmaddr` is rounded down to `SHMLBA`.

**SHM\_RDONLY**the shared memory is attached for read access only. Otherwise the memory is attached for read-write. The process then needs read-write permissions to access the shared memory.

For an example, see `shmctl` (688).

Errors: If an error occurs, -1 is returned, and `IPCError` is set.

See also: `shmget` (690), `shmdt` (690), `shmctl` (688)

### 20.4.10 shmctl

**Synopsis:** Perform control operations on a shared memory block.

**Declaration:** `function shmctl(shmid: cint;cmd: cint;buf: PShmid_DS) : cint`

**Visibility:** default

**Description:** `shmctl` performs various operations on the shared memory block identified by identifier `shmid`.

The `buf` parameter points to a `TSHMid_ds` record. The `cmd` parameter is used to pass which operation is to be performed. It can have one of the following values :

**IPC\_STAT**`shmctl` fills the `TSHMid_ds` record that `buf` points to with the available information about the shared memory block.

**IPC\_SET**applies the values in the `ipc_perm` record that `buf` points to, to the shared memory block.

**IPC\_RMID**the shared memory block is destroyed (after all processes to which the block is attached, have detached from it).

If successful, the function returns `True`, `False` otherwise.

**Errors:** If an error occurs, the function returns `False`, and `IPCError` is set.

See also: `shmget` ([690](#)), `shmat` ([687](#)), `shmdt` ([690](#))

**Listing:** `./ipccex/shmtool.pp`

---

```

Program shmtool;

uses ipc , strings , Baseunix;

Const SegSize = 100;

var key : Tkey;
    shmid,cntr : longint;
    segptr : pchar;

Procedure USage;

begin
  Writeln ( 'Usage : shmtool w(rite) text' );
  writeln ( '                r(ead)' );
  writeln ( '                d(elete)' );
  writeln ( '                m(ode change) mode' );
  halt (1);
end;

Procedure Writeshm (ID : Longint; ptr : pchar; S : string);

begin
  strcpy ( ptr, S );
end;

Procedure Readshm(ID : longint; ptr : pchar);

begin
  Writeln ( 'Read : ', ptr );
end;

```

```

Procedure removeshm (ID : Longint);

begin
    shmctl (ID,IPC_RMID,Nil);
    writeln ( 'Shared memory marked for deletion' );
end;

Procedure CHangeMode (ID : longint; mode : String);

Var m : word;
    code : integer;
    data : TSHMid_ds;

begin
    val (mode,m,code);
    if code<>0 then
        usage;
    if shmctl (shmid,IPC_STAT,@data)=-1 then
        begin
            writeln ( 'Error : shmctl : ',fpgeterrno);
            halt(1);
        end;
    writeln ( 'Old permissions : ',data.shm_perm.mode);
    data.shm_perm.mode:=m;
    if shmctl (shmid,IPC_SET,@data)=-1 then
        begin
            writeln ( 'Error : shmctl : ',fpgeterrno);
            halt(1);
        end;
    writeln ( 'New permissions : ',data.shm_perm.mode);
end;

const ftokpath = '.'#0;

begin
    if paramcount<1 then usage;
    key := ftok (pchar(@ftokpath[1]),ord('S'));
    shmid := shmget(key,segsz,IPC_CREAT or IPC_EXCL or 438);
    if shmid=-1 then
        begin
            writeln ( 'Shared memory exists. Opening as client' );
            shmid := shmget(key,segsz,0);
            if shmid = -1 then
                begin
                    writeln ( 'shmget : Error ! ',fpgeterrno);
                    halt(1);
                end
            end
        else
            writeln ( 'Creating new shared memory segment.' );
            segptr:=shmat(shmid,Nil,0);
            if longint(segptr)=-1 then
                begin
                    writeln ( 'Shmat : error ! ',fpgeterrno);
                    halt(1);
                end;
            case upcase(paramstr(1)[1]) of

```

---

```

    'W' : writeshm ( shmId , segptr , paramstr (2));
    'R' : readshm ( shmId , segptr );
    'D' : removeshm (shmId);
    'M' : changemode ( shmId , paramstr (2));
else
    begin
        writeln ( paramstr (1));
        usage;
    end;
end;
end.

```

---

### 20.4.11 shmdt

Synopsis: Detach shared memory block.

Declaration: `function shmdt (shmaddr: pointer) : cint`

Visibility: default

Description: `shmdt` detaches the shared memory at address `shmaddr`. This shared memory block is unavailable to the current process, until it is attached again by a call to `shmat` (687).

The function returns `True` if the memory block was detached successfully, `False` otherwise.

Errors: On error, `False` is returned, and `IPCError` is set.

See also: `shmget` (690), `shmat` (687), `shmctl` (688)

### 20.4.12 shmget

Synopsis: Return the ID of a shared memory block, possibly creating it

Declaration: `function shmget (key: TKey; size: size_t; flag: cint) : cint`

Visibility: default

Description: `shmget` returns the ID of a shared memory block, described by `key`. Depending on the flags in `flag`, a new memory block is created.

`flag` can have one or more of the following values (combined by ORs):

**IPC\_CREAT** The queue is created if it doesn't already exist.

**IPC\_EXCL** If used in combination with `IPC_CREAT`, causes the call to fail if the queue already exists. It cannot be used by itself.

Optionally, the flags can be ORed with a permission mode, which is the same mode that can be used in the file system.

if a new memory block is created, then it will have size `Size` bytes in it.

Errors: On error, -1 is returned, and `IPCError` is set.

## Chapter 21

# Reference for unit 'keyboard'

### 21.1 Overview

The Keyboard unit implements a keyboard access layer which is system independent. It can be used to poll the keyboard state and wait for certain events. Waiting for a keyboard event can be done with the `GetKeyEvent` (701) function, which will return a driver-dependent key event. This key event can be translated to a interpretable event by the `TranslateKeyEvent` (710) function. The result of this function can be used in the other event examining functions.

A custom keyboard driver can be installed using the `SetKeyboardDriver` (709) function. The current keyboard driver can be retrieved using the `GetKeyboardDriver` (701) function. The last section of this chapter demonstrates how to make a keyboard driver.

### 21.2 Unix specific notes

On Unix, applications run on a "terminal", and the application writes to the screen and reads from the keyboard by communicating with the terminal. Unix keyboard handling is mostly backward compatible with the DEC vt100 and vt220 terminals from tens of years ago. The vt100 and vt220 had very different keyboards than today's PC's and this is where the problems start. To make it worse the protocol of both terminals has not been very well designed.

Because of this, the keyboard unit on Unix operating systems does a best effort to provide keyboard functionality. An implementation with full keyboard facilities like on other operating systems is not possible.

The exception is the Linux kernel. The terminal emulation of the Linux kernel is from a PC keyboard viewpoint hopeless as well, but unlike other terminal emulators it is configurable. On the Linux console, the Free Pascal keyboard unit tries to implement full functionality.

Users of applications using the keyboard unit should expect the following:

- Full functionality on the Linux console. It must be the bare console, SSH into another machine will kill the full functionality.
- Limited functionality otherwise.

Notes about Linux full functionality:

- The keyboard is reprogrammed. If the keyboard is for whatever reason not restored in its original state, please load your keymap to reinitialize it.

- Alt+function keys generate keycodes for those keys. To switch virtual consoles, use ctrl+alt+function key.
- Unlike what you're used to with other Unix software, escape works as you intuitively expect, it generates the keycode for an escape key **without a delay**.

The limited functionality does include these quirks:

- Escape must be pressed two times before it has effect.
- On the Linux console, when the users runs the program by logging into another machine:
  - Shift+F1 and Shift+F12 will generate keycodes for F11 and F12.
  - Shift+arrow keys, shift+ins, shift+del, shift+home, shift+end do not work. The same is true about the control and alt combinations.
  - Alt+function keys will switch virtual consoles instead of generating the right key sequences.
  - Ctrl+function keys will generate the keycodes for the function keys without ctrl
- In Xterm:
  - Shift+insert pastes the x clipboard, no keycode will be generated.
- In Konsole:
  - Shift+insert pastes the x clipboard, no keycode will be generated.
  - Shift+arrow keys doesn't work, nor does ctrl+arrow keys

If you have a non-standard terminal, some keys may not work at all. When in limited functionality mode, the user can work around using an escape prefix:

- Esc+1 = F1, Esc+2 = F2.
- Esc before another key is equal to alt+key.

In such cases, if the terminal does output an escape sequence for those keys, please submit a bug report so we can add them.

## 21.3 Writing a keyboard driver

Writing a keyboard driver means that hooks must be created for most of the keyboard unit functions. The `TKeyboardDriver` record contains a field for each of the possible hooks:

```
TKeyboardDriver = Record
  InitDriver : Procedure;
  DoneDriver : Procedure;
  GetKeyEvent : Function : TKeyEvent;
  PollKeyEvent : Function : TKeyEvent;
  GetShiftState : Function : Byte;
  TranslateKeyEvent : Function (KeyEvent: TKeyEvent): TKeyEvent;
  TranslateKeyEventUnicode: Function (KeyEvent: TKeyEvent): TKeyEvent;
end;
```

The meaning of these hooks is explained below:

**InitDriver** Called to initialize and enable the driver. Guaranteed to be called only once. This should initialize all needed things for the driver.

**DoneDriver** Called to disable and clean up the driver. Guaranteed to be called after a call to `initDriver`. This should clean up all things initialized by `InitDriver`.

**GetKeyEvent** Called by `GetKeyEvent` (701). Must wait for and return the next key event. It should NOT store keys.

**PollKeyEvent** Called by `PollKeyEvent` (706). It must return the next key event if there is one. Should not store keys.

**GetShiftState** Called by `PollShiftStateEvent` (707). Must return the current shift state.

**TranslateKeyEvent** Should translate a raw key event to a correct key event, i.e. should fill in the `shiftstate` and convert function key scancodes to function key keycodes. If the `TranslateKeyEvent` is not filled in, a default translation function will be called which converts the known scancodes from the tables in the previous section to a correct keyevent.

**TranslateKeyEventUnicode** Should translate a key event to a unicode key representation.

Strictly speaking, only the `GetKeyEvent` and `PollKeyEvent` hooks must be implemented for the driver to function correctly.

The example unit demonstrates how a keyboard driver can be installed. It takes the installed driver, and hooks into the `GetKeyEvent` function to register and log the key events in a file. This driver can work on top of any other driver, as long as it is inserted in the `uses` clause *after* the real driver unit, and the real driver unit should set the driver record in its initialization section.

Note that with a simple extension of this unit could be used to make a driver that is capable of recording and storing a set of keyboard strokes, and replaying them at a later time, so a 'keyboard macro' capable driver. This driver could sit on top of any other driver.

## 21.4 Keyboard scan codes

Special physical keys are encoded with the DOS scan codes for these keys in the second byte of the `TKeyEvent` (698) type. A complete list of scan codes can be found in the below table. This is the list of keys that is used by the default key event translation mechanism. When writing a keyboard driver, either these constants should be returned by the various key event functions, or the `TranslateKeyEvent` hook should be implemented by the driver.

A list of scan codes for special keys and combinations with the SHIFT, ALT and CTRL keys can be found in the following table: They are for quick reference only.

## 21.5 Constants, types and variables

### 21.5.1 Constants

`AltPrefix : Byte = 0`

Keycode for alternate prefix key for Alt key. Unix Only

`CtrlPrefix : Byte = 0`

Keycode for alternate prefix key for Ctrl key. Unix only

```
errKbdBase = 1010
```

Base of keyboard routine error reporting constants.

```
errKbdInitError = errKbdBase+0
```

Failed to initialize keyboard driver

```
errKbdNotImplemented = errKbdBase+1
```

Keyboard driver not implemented.

```
kbAlt = 8
```

Alt key modifier

```
kbASCII = $00
```

Ascii code key event

```
kbCtrl = 4
```

Control key modifier

```
kbdApps = $FF17
```

Application key (popup-menu) pressed.

```
kbdDelete = $FF2A
```

Delete key pressed

```
kbdDown = $FF27
```

Arrow down key pressed

```
kbdEnd = $FF26
```

End key pressed

```
kbdF1 = $FF01
```

F1 function key pressed.

```
kbdF10 = $FF0A
```

F10 function key pressed.

```
kbdF11 = $FF0B
```



F12 function key pressed.

kbdF12 = \$FF0C

F12 function key pressed.

kbdF13 = \$FF0D

F13 function key pressed.

kbdF14 = \$FF0E

F14 function key pressed.

kbdF15 = \$FF0F

F15 function key pressed.

kbdF16 = \$FF10

F16 function key pressed.

kbdF17 = \$FF11

F17 function key pressed.

kbdF18 = \$FF12

F18 function key pressed.

kbdF19 = \$FF13

F19 function key pressed.

kbdF2 = \$FF02

F2 function key pressed.

kbdF20 = \$FF14

F20 function key pressed.

kbdF3 = \$FF03

F3 function key pressed.

kbdF4 = \$FF04

F4 function key pressed.

kbdF5 = \$FF05

F5 function key pressed.

kbdF6 = \$FF06

F6 function key pressed.

kbdF7 = \$FF07

F7 function key pressed.

kbdF8 = \$FF08

F8 function key pressed.

kbdF9 = \$FF09

F9 function key pressed.

kbdHome = \$FF20

Home key pressed

kbdInsert = \$FF29

Insert key pressed

kbdLeft = \$FF23

Arrow left key pressed

kbdLWin = \$FF15

Left windows key pressed.

kbdMiddle = \$FF24

Middle key pad key pressed (numerical 5)

kbdPgDn = \$FF28

Page down key pressed

kbdPgUp = \$FF22

Page Up key pressed

kbdRight = \$FF25

Arrow right key pressed

kbdRWin = \$FF16

Right windows key pressed.

`kbdUp = $FF21`

Arrow up key pressed

`kbFnKey = $02`

function key pressed.

`kbLeftShift = 1`

Left shift key modifier

`kbPhys = $03`

Physical key code event

`kbReleased = $04`

Key release event

`kbRightShift = 2`

Right shift key modifier

`kbShift = kbLeftShift or kbRightShift`

Shift key modifier

`kbUnicode = $01`

Unicode code key event

`SAnd : String = 'AND'`

This constant is used as the 'And' word in key descriptions. This constant is used by the key event description routines. It can be changed to localize the key descriptions when needed.

`ShiftPrefix : Byte = 0`

Keycode for alternate prefix key for Shift key. Unix Only

`SKeyPad : Array[0..($FF2F-kbdHome)] of String = ('Home', 'Up', 'PgUp', 'Left', 'Middle',`

This constant describes all keypad keys. This constant is used by the key event description routines. It can be changed to localize the key descriptions when needed.

`SLeftRight : Array[1..2] of String = ('LEFT', 'RIGHT')`

This constant contains strings to describe left and right keys. This constant is used by the key event description routines. It can be changed to localize the key descriptions when needed.

```
SScanCode : String = 'Key with scancode '
```

This constant contains a string to denote a scancode key event. This constant is used by the key event description routines. It can be changed to localize the key descriptions when needed.

```
SShift : Array[1..3] of String = ('SHIFT', 'CTRL', 'ALT')
```

This constant describes the various modifier keys. This constant is used by the key event description routines. It can be changed to localize the key descriptions when needed.

```
SUnicodeChar : String = 'Unicode character '
```

This constant contains a string to denote a unicode key event. This constant is used by the key event description routines. It can be changed to localize the key descriptions when needed.

```
SUnknownFunctionKey : String = 'Unknown function key : '
```

This constant contains a string to denote that an unknown function key was found. This constant is used by the key event description routines. It can be changed to localize the key descriptions when needed.

## 21.5.2 Types

```
PTreeElement = ^TTreeElement
```

Pointer to TTreeElement ([699](#)) record

```
TKeyboardDriver = record
  InitDriver : procedure;
  DoneDriver : procedure;
  GetKeyEvent : function : TKeyEvent;
  PollKeyEvent : function : TKeyEvent;
  GetShiftState : function : Byte;
  TranslateKeyEvent : function(KeyEvent: TKeyEvent) : TKeyEvent;
  TranslateKeyEventUniCode : function(KeyEvent: TKeyEvent) : TKeyEvent;
end
```

The TKeyboardDriver record can be used to install a custom keyboard driver with the SetKeyboardDriver ([709](#)) function.

The various fields correspond to the different functions of the keyboard unit interface. For more information about this record see kbddriver ([692](#))

```
TKeyEvent = Cardinal
```

The TKeyEvent type is the base type for all keyboard events.

The key stroke is encoded in the 4 bytes of the TKeyEvent type. The various fields of the key stroke encoding can be obtained by typecasting the TKeyEvent type to the TKeyEventRecord ([699](#)) type.

```
TKeyRecord = packed record
  KeyCode : Word;
  ShiftState : Byte;
  Flags : Byte;
end
```

The structure of a TKeyRecord structure is explained in the following table:

The shift-state can be checked using the various shift-state constants, and the flags in the last byte can be checked using one of the kbASCII, kbUnicode, kbFnKey, kbPhys, kbReleased constants.

If there are two keys returning the same char-code, there's no way to find out which one was pressed (Gray+ and Simple+). If it needs to be known which was pressed, the untranslated keycodes must be used, but these are system dependent. System dependent constants may be defined to cover those, with possibly having the same name (but different value).

```
Tprocedure = procedure
```

Procedure prototype

```
TTreeElement = record
  Next : PTreeElement;
  Parent : PTreeElement;
  Child : PTreeElement;
  CanBeTerminal : Boolean;
  char : Byte;
  ScanValue : Byte;
  CharValue : Byte;
  SpecialHandler : Tprocedure;
end
```

TTreeElement is used to describe key scancode sequences, and is used to handle special key combinations in AddSpecialSequence (699) on unix platforms. There should be no need to handle records of this type.

## 21.6 Procedures and functions

### 21.6.1 AddSequence

Declaration: procedure AddSequence(const St: String; AChar: Byte; AScan: Byte)

Visibility: default

### 21.6.2 AddSpecialSequence

Synopsis: Add a handler for a special key sequence

Declaration: function AddSpecialSequence(const St: String; Proc: Tprocedure)  
: PTreeElement

Visibility: default

**Description:** `AddSpecialSequence` adds a sequence of key combinations to the keyboard handler. When the key combination specified in `st` is encountered, then `Proc` will be executed. The function returns the element in the special key sequence handling tree which handles `st`.

See also: `AddSequence` ([699](#))

### 21.6.3 DoneKeyboard

**Synopsis:** Deactivate keyboard driver.

**Declaration:** `procedure DoneKeyboard`

**Visibility:** `default`

**Description:** `DoneKeyboard` de-initializes the keyboard interface if the keyboard driver is active. If the keyboard driver is not active, the function does nothing.

This will cause the keyboard driver to clear up any allocated memory, or restores the console or terminal the program was running in to its initial state before the call to `InitKeyBoard` ([705](#)). This function should be called on program exit. Failing to do so may leave the terminal or console window in an unusable state. Its exact action depends on the platform on which the program is running.

On Unix the default keyboard driver restores the line ending of `system.output` to `#10`.

For an example, see most other functions.

**Errors:** None.

See also: `InitKeyBoard` ([705](#))

### 21.6.4 FindSequence

**Declaration:** `function FindSequence(const St: String; var AChar: Byte; var Ascan: Byte) : Boolean`

**Visibility:** `default`

### 21.6.5 FunctionKeyName

**Synopsis:** Return string representation of a function key code.

**Declaration:** `function FunctionKeyName(KeyCode: Word) : String`

**Visibility:** `default`

**Description:** `FunctionKeyName` returns a string representation of the function key with code `KeyCode`. This can be an actual function key, or one of the cursor movement keys.

**Errors:** In case `KeyCode` does not contain a function code, the `SUnknownFunctionKey` string is returned, appended with the `KeyCode`.

See also: `ShiftStateToString` ([710](#)), `KeyEventToString` ([706](#))

**Listing:** `./kbdex/ex8.pp`

---

```

Program Example8;

{ Program to demonstrate the FunctionKeyName function. }

Uses keyboard;

Var
  K : TKeyEvent;

begin
  InitKeyboard;
  WriteLn('Press function keys, press "q" to end. ');
  Repeat
    K:=GetKeyEvent;
    K:=TranslateKeyEvent(K);
    If IsFunctionKey(k) then
      begin
        Write('Got function key : ');
        WriteLn(FunctionKeyName(TkeyRecord(K).KeyCode));
      end;
    Until (GetKeyEventChar(K)= 'q ');
  DoneKeyboard;
end.

```

---

### 21.6.6 GetKeyboardDriver

**Synopsis:** Return the current keyboard driver record.

**Declaration:** `procedure GetKeyboardDriver(var Driver: TKeyboardDriver)`

**Visibility:** default

**Description:** `GetKeyboardDriver` returns in `Driver` the currently active keyboard driver. This function can be used to enhance an existing keyboarddriver.

For more information on getting and setting the keyboard driver `kbddriver` ([692](#)).

**Errors:** None.

**See also:** `SetKeyboardDriver` ([709](#))

### 21.6.7 GetKeyEvent

**Synopsis:** Get the next raw key event, wait if needed.

**Declaration:** `function GetKeyEvent : TKeyEvent`

**Visibility:** default

**Description:** `GetKeyEvent` returns the last keyevent if it is available, or waits for one if none is available. A non-blocking version is available in `PollKeyEvent` ([706](#)).

The returned key is encoded as a `TKeyEvent` type variable, and is normally the physical key scan code, (the scan code is driver dependent) which can be translated with one of the translation functions `TranslateKeyEvent` ([710](#)) or `TranslateKeyEventUnicode` ([710](#)). See the types section for a description of how the key is described.

**Errors:** If no key became available (e.g. when the driver does not support it), 0 is returned.

See also: [PutKeyEvent \(708\)](#), [PollKeyEvent \(706\)](#), [TranslateKeyEvent \(710\)](#), [TranslateKeyEventUnicode \(710\)](#)

**Listing:** ./kbdex/ex1.pp

---

```

program example1;

{ This program demonstrates the GetKeyEvent function }

uses keyboard;

Var
  K : TKeyEvent;

begin
  InitKeyBoard;
  Writeln('Press keys, press "q" to end. ');
  Repeat
    K:=GetKeyEvent;
    K:=TranslateKeyEvent(K);
    Write('Got key event with ');
    Case GetKeyEventFlags(K) of
      kbASCII    : Writeln('ASCII key ');
      kbUnicode  : Writeln('Unicode key ');
      kbFnKey    : Writeln('Function key ');
      kbPhys     : Writeln('Physical key ');
      kbReleased : Writeln('Released key event ');
    end;
    Writeln('Got key : ', KeyEventToString(K));
  Until (GetKeyEventChar(K)='q');
  DoneKeyBoard;
end.
```

---

### 21.6.8 GetKeyEventChar

**Synopsis:** Get the character key part of a key event.

**Declaration:** `function GetKeyEventChar(KeyEvent: TKeyEvent) : Char`

**Visibility:** default

**Description:** `GetKeyEventChar` returns the charcode part of the given `KeyEvent`, if it contains a translated character key keycode. The charcode is simply the ascii code of the character key that was pressed.

It returns the null character if the key was not a character key, but e.g. a function key.

For an example, see [GetKeyEvent \(701\)](#)

**Errors:** None.

See also: [GetKeyEventUnicode \(704\)](#), [GetKeyEventShiftState \(704\)](#), [GetKeyEventFlags \(703\)](#), [GetKeyEventCode \(702\)](#), [GetKeyEvent \(701\)](#)

### 21.6.9 GetKeyEventCode

**Synopsis:** Translate function key part of a key event code.

**Declaration:** `function GetKeyEventCode(KeyEvent: TKeyEvent) : Word`



Visibility: default

**Description:** `GetKeyEventCode` returns the translated function keycode part of the given `KeyEvent`, if it contains a translated function key.

If the key pressed was not a function key, the null character is returned.

Errors: None.

See also: `GetKeyEventUnicode` (704), `GetKeyEventShiftState` (704), `GetKeyEventFlags` (703), `GetKeyEventChar` (702), `GetKeyEvent` (701)

**Listing:** `./kbdex/ex2.pp`

---

**Program** `Example2`;

*{ Program to demonstrate the GetKeyEventCode function. }*

**Uses** `keyboard`;

**Var**

`K : TKeyEvent`;

**begin**

`InitKeyBoard`;

**WriteIn** ( 'Press function keys , or press "q" to end.' );

**Repeat**

`K:=GetKeyEvent`;

`K:=TranslateKeyEvent(K)`;

**If** ( `GetKeyEventFlags(K)<>KbfnKey` ) **then**

**WriteIn** ( 'Not a function key' )

**else**

**begin**

**Write** ( 'Got key ( ', `GetKeyEventCode(K)` );

**WriteIn** ( ' ) : ', `KeyEventToString(K)` );

**end**;

**Until** ( `GetKeyEventChar(K)= 'q'` );

`DoneKeyboard`;

**end.**

---

### 21.6.10 GetKeyEventFlags

**Synopsis:** Extract the flags from a key event.

**Declaration:** `function GetKeyEventFlags(KeyEvent: TKeyEvent) : Byte`

Visibility: default

**Description:** `GetKeyEventFlags` returns the flags part of the given `KeyEvent`.

For an example, see `GetKeyEvent` (701)

Errors: None.

See also: `GetKeyEventUnicode` (704), `GetKeyEventShiftState` (704), `GetKeyEventCode` (702), `GetKeyEventChar` (702), `GetKeyEvent` (701)

### 21.6.11 GetKeyEventShiftState

Synopsis: Return the current state of the shift keys.

Declaration: `function GetKeyEventShiftState(KeyEvent: TKeyEvent) : Byte`

Visibility: default

Description: `GetKeyEventShiftState` returns the shift-state values of the given `KeyEvent`. This can be used to detect which of the modifier keys `Shift`, `Alt` or `Ctrl` were pressed. If none were pressed, zero is returned.

Note that this function does not always return expected results; In a unix X-Term, the modifier keys do not always work.

Errors: None.

See also: `GetKeyEventUniCode` (704), `GetKeyEventFlags` (703), `GetKeyEventCode` (702), `GetKeyEventChar` (702), `GetKeyEvent` (701)

**Listing:** `./kbdex/ex3.pp`

---

**Program** `Example3`;

*{ Program to demonstrate the GetKeyEventShiftState function. }*

**Uses** `keyboard`;

**Var**

`K : TKeyEvent;`  
`S : Byte;`

**begin**

`InitKeyBoard`;

**Write** (`'Press keys combined with CTRL/SHIFT/ALT'`);

**WriteLn** (`', or press "q" to end.'`);

**Repeat**

`K:=GetKeyEvent`;

`K:=TranslateKeyEvent(K)`;

`S:=GetKeyEventShiftState(K)`;

**If** (`S=0`) **then**

`WriteLn('No special keys pressed')`

**else**

**begin**

`WriteLn('Detected special keys : ',ShiftStateToString(K,False));`

`WriteLn('Got key : ',KeyEventToString(K));`

**end**;

**Until** (`GetKeyEventChar(K)='q'`);

`DoneKeyboard`;

**end.**

---

### 21.6.12 GetKeyEventUniCode

Synopsis: Return the unicode key event.

Declaration: `function GetKeyEventUniCode(KeyEvent: TKeyEvent) : Word`

Visibility: default

**Description:** `GetKeyEventUnicode` returns the unicode part of the given `KeyEvent` if it contains a translated unicode character.

**Errors:** None.

**See also:** `GetKeyEventShiftState` (704), `GetKeyEventFlags` (703), `GetKeyEventCode` (702), `GetKeyEventChar` (702), `GetKeyEvent` (701)

### 21.6.13 InitKeyboard

**Synopsis:** Initialize the keyboard driver.

**Declaration:** `procedure InitKeyboard`

**Visibility:** default

**Description:** `InitKeyboard` initializes the keyboard driver. If the driver is already active, it does nothing. When the driver is initialized, it will do everything necessary to ensure the functioning of the keyboard, including allocating memory, initializing the terminal etc.

This function should be called once, before using any of the keyboard functions. When it is called, the `DoneKeyboard` (700) function should also be called before exiting the program or changing the keyboard driver with `SetKeyboardDriver` (709).

On Unix, the default keyboard driver sets terminal in raw mode. In raw mode the line feed behaves as an actual linefeed, i.e. the cursor is moved down one line. while the x coordinate does not change. To compensate, the default keyboard sets driver line ending of `system.output` to `#13#10`.

For an example, see most other functions.

**Errors:** None.

**See also:** `DoneKeyboard` (700), `SetKeyboardDriver` (709)

### 21.6.14 IsFunctionKey

**Synopsis:** Check whether a given event is a function key event.

**Declaration:** `function IsFunctionKey (KeyEvent: TKeyEvent) : Boolean`

**Visibility:** default

**Description:** `IsFunctionKey` returns `True` if the given key event in `KeyEvent` was a function key or not.

**Errors:** None.

**See also:** `GetKeyEvent` (701)

**Listing:** `./kbdex/ex7.pp`

---

```

program example1 ;

{ This program demonstrates the GetKeyEvent function }

uses keyboard ;

Var
  K : TKeyEvent ;

begin
```

---

```

InitKeyBoard ;
WriteIn( 'Press keys , press "q" to end.' );
Repeat
  K:=GetKeyEvent ;
  K:=TranslateKeyEvent (K);
  If IsFunctionKey(K) then
    WriteIn( 'Got function key : ', KeyEventToString (K))
  else
    WriteIn( 'not a function key.' );
  Until ( GetKeyEventChar (K)= 'q' );
DoneKeyBoard ;
end .

```

---

### 21.6.15 KeyEventToString

Synopsis: Return a string describing the key event.

Declaration: `function KeyEventToString(KeyEvent: TKeyEvent) : String`

Visibility: default

Description: `KeyEventToString` translates the key event in `KeyEvent` to a human-readable description of the pressed key. It will use the constants described in the constants section to do so.

For an example, see most other functions.

Errors: If an unknown key is passed, the scancode is returned, prefixed with the `SScanCode` string.

See also: `FunctionKeyName` ([700](#)), `ShiftStateToString` ([710](#))

### 21.6.16 KeyPressed

Synopsis: Check event queue for key press

Declaration: `function KeyPressed : Boolean`

Visibility: default

Description: `KeyPressed` checks the keyboard event queue to see whether a key event is present, and returns `True` if a key event is available. This function simply calls `PollKeyEvent` ([706](#)) and checks for a valid result.

Errors: None.

See also: `PollKeyEvent` ([706](#)), `GetKeyEvent` ([701](#))

### 21.6.17 PollKeyEvent

Synopsis: Get next key event, but does not wait.

Declaration: `function PollKeyEvent : TKeyEvent`

Visibility: default

Description: `PollKeyEvent` checks whether a key event is available, and returns it if one is found. If no event is pending, it returns 0.

Note that this does not remove the key from the pending keys. The key should still be retrieved from the pending key events list with the `GetKeyEvent` ([701](#)) function.

Errors: None.

See also: PutKeyEvent (708), GetKeyEvent (701)

**Listing:** ./kbdex/ex4.pp

---

```

program example4;

{ This program demonstrates the PollKeyEvent function }

uses keyboard;

Var
  K : TKeyEvent;

begin
  InitKeyBoard;
  WriteLn('Press keys, press "q" to end. ');
  Repeat
    K:=PollKeyEvent;
    If k<>0 then
      begin
        K:=GetKeyEvent;
        K:=TranslateKeyEvent(K);
        writeln;
        WriteLn('Got key : ',KeyEventToString(K));
      end
    else
      write(' ');
    Until (GetKeyEventChar(K)= 'q ');
  DoneKeyBoard;
end.

```

---

### 21.6.18 PollShiftStateEvent

Synopsis: Check current shift state.

Declaration: `function PollShiftStateEvent : TKeyEvent`

Visibility: default

Description: `PollShiftStateEvent` returns the current shiftstate in a keyevent. This will return 0 if there is no key event pending.

Errors: None.

See also: PollKeyEvent (706), GetKeyEvent (701)

**Listing:** ./kbdex/ex6.pp

---

```

program example6;

{ This program demonstrates the PollShiftStateEvent function }

uses keyboard;

Var
  K : TKeyEvent;

```

---

```

begin
  InitKeyBoard;
  WriteLn('Press keys, press "q" to end. ');
  Repeat
    K:=PollKeyEvent;
    If k<>0 then
      begin
        K:=PollShiftStateEvent;
        WriteLn('Got shift state : ', ShiftStateToString(K, False));
        // Consume the key.
        K:=GetKeyEvent;
        K:=TranslateKeyEvent(K);
      end
    { else
      write(' '). };
    Until (GetKeyEventChar(K)='q');
  DoneKeyBoard;
end.

```

---

### 21.6.19 PutKeyEvent

Synopsis: Put a key event in the event queue.

Declaration: `procedure PutKeyEvent (KeyEvent: TKeyEvent)`

Visibility: default

Description: `PutKeyEvent` adds the given `KeyEvent` to the input queue. Please note that depending on the implementation this can hold only one value, i.e. when calling `PutKeyEvent` multiple times, only the last pushed key will be remembered.

Errors: None

See also: `PollKeyEvent` ([706](#)), `GetKeyEvent` ([701](#))

**Listing:** `./kbdex/ex5.pp`

---

```

program example5;

{ This program demonstrates the PutKeyEvent function }

uses keyboard;

Var
  K, k2 : TKeyEvent;

begin
  InitKeyBoard;
  WriteLn('Press keys, press "q" to end. ');
  K2:=0;
  Repeat
    K:=GetKeyEvent;
    If k<>0 then
      begin
        if (k2 mod 2)=0 then
          K2:=K+1
        else

```

---

```

        K2:=0;
        K:=TranslateKeyEvent(K);
        WriteLn('Got key : ',KeyEventToString(K));
        if (K2<>0) then
            begin
                PutKeyEvent(k2);
                K2:=TranslateKeyEvent(K2);
                WriteLn('Put key : ',KeyEventToString(K2))
            end
        end
    Until (GetKeyEventChar(K)= 'q ');
    DoneKeyBoard;
end.
```

---

### 21.6.20 RawReadKey

Declaration: function RawReadKey : Char

Visibility: default

### 21.6.21 RawReadString

Declaration: function RawReadString : String

Visibility: default

### 21.6.22 RestoreStartMode

Declaration: procedure RestoreStartMode

Visibility: default

### 21.6.23 SetKeyboardDriver

Synopsis: Set a new keyboard driver.

Declaration: function SetKeyboardDriver(const Driver: TKeyboardDriver) : Boolean

Visibility: default

Description: SetKeyBoardDriver sets the keyboard driver to Driver, if the current keyboard driver is not yet initialized. If the current keyboard driver is initialized, then SetKeyboardDriver does nothing. Before setting the driver, the currently active driver should be disabled with a call to DoneKeyboard ([700](#)).

The function returns True if the driver was set, False if not.

For more information on setting the keyboard driver, see kbddriver ([692](#)).

Errors: None.

See also: GetKeyboardDriver ([701](#)), DoneKeyboard ([700](#))

### 21.6.24 ShiftStateToString

Synopsis: Return description of key event shift state

Declaration: `function ShiftStateToString(KeyEvent: TKeyEvent; UseLeftRight: Boolean) : String`

Visibility: default

Description: `ShiftStateToString` returns a string description of the shift state of the key event `KeyEvent`. This can be an empty string.

The shift state is described using the strings in the `SShift` constant.

For an example, see `PollShiftStateEvent` (707).

Errors: None.

See also: `FunctionKeyName` (700), `KeyEventToString` (706)

### 21.6.25 TranslateKeyEvent

Synopsis: Translate raw event to ascii key event

Declaration: `function TranslateKeyEvent(KeyEvent: TKeyEvent) : TKeyEvent`

Visibility: default

Description: `TranslateKeyEvent` performs ASCII translation of the `KeyEvent`. It translates a physical key to a function key if the key is a function key, and translates the physical key to the ordinal of the ascii character if there is an equivalent character key.

For an example, see `GetKeyEvent` (701)

Errors: None.

See also: `TranslateKeyEventUnicode` (710)

### 21.6.26 TranslateKeyEventUnicode

Synopsis: Translate raw event to UNICODE key event

Declaration: `function TranslateKeyEventUnicode(KeyEvent: TKeyEvent) : TKeyEvent`

Visibility: default

Description: `TranslateKeyEventUnicode` performs Unicode translation of the `KeyEvent`. It is not yet implemented for all platforms.

Errors: If the function is not yet implemented, then the `ErrorCode` of the `system` unit will be set to `errKbdNotImplemented`

See also: `TranslateKeyEvent` (710)



Table 21.1: Key Scancodes

Code	Key	Code	Key	Code	Key
00	NoKey	3D	F3	70	ALT-F9
01	ALT-Esc	3E	F4	71	ALT-F10
02	ALT-Space	3F	F5	72	CTRL-PrtSc
04	CTRL-Ins	40	F6	73	CTRL-Left
05	SHIFT-Ins	41	F7	74	CTRL-Right
06	CTRL-Del	42	F8	75	CTRL-end
07	SHIFT-Del	43	F9	76	CTRL-PgDn
08	ALT-Back	44	F10	77	CTRL-Home
09	ALT-SHIFT-Back	47	Home	78	ALT-1
0F	SHIFT-Tab	48	Up	79	ALT-2
10	ALT-Q	49	PgUp	7A	ALT-3
11	ALT-W	4B	Left	7B	ALT-4
12	ALT-E	4C	Center	7C	ALT-5
13	ALT-R	4D	Right	7D	ALT-6
14	ALT-T	4E	ALT-GrayPlus	7E	ALT-7
15	ALT-Y	4F	end	7F	ALT-8
16	ALT-U	50	Down	80	ALT-9
17	ALT-I	51	PgDn	81	ALT-0
18	ALT-O	52	Ins	82	ALT-Minus
19	ALT-P	53	Del	83	ALT-Equal
1A	ALT-LftBrack	54	SHIFT-F1	84	CTRL-PgUp
1B	ALT-RgtBrack	55	SHIFT-F2	85	F11
1E	ALT-A	56	SHIFT-F3	86	F12
1F	ALT-S	57	SHIFT-F4	87	SHIFT-F11
20	ALT-D	58	SHIFT-F5	88	SHIFT-F12
21	ALT-F	59	SHIFT-F6	89	CTRL-F11
22	ALT-G	5A	SHIFT-F7	8A	CTRL-F12
23	ALT-H	5B	SHIFT-F8	8B	ALT-F11
24	ALT-J	5C	SHIFT-F9	8C	ALT-F12
25	ALT-K	5D	SHIFT-F10	8D	CTRL-Up
26	ALT-L	5E	CTRL-F1	8E	CTRL-Minus
27	ALT-SemiCol	5F	CTRL-F2	8F	CTRL-Center
28	ALT-Quote	60	CTRL-F3	90	CTRL-GreyPlus
29	ALT-OpQuote	61	CTRL-F4	91	CTRL-Down
2B	ALT-BkSlash	62	CTRL-F5	94	CTRL-Tab
2C	ALT-Z	63	CTRL-F6	97	ALT-Home
2D	ALT-X	64	CTRL-F7	98	ALT-Up
2E	ALT-C	65	CTRL-F8	99	ALT-PgUp
2F	ALT-V	66	CTRL-F9	9B	ALT-Left
30	ALT-B	67	CTRL-F10	9D	ALT-Right
31	ALT-N	68	ALT-F1	9F	ALT-end
32	ALT-M	69	ALT-F2	A0	ALT-Down
33	ALT-Comma	6A	ALT-F3	A1	ALT-PgDn
34	ALT-Period	6B	ALT-F4	A2	ALT-Ins
35	ALT-Slash	6C	ALT-F5	A3	ALT-Del
37	ALT-GreyAst	6D	ALT-F6	A5	ALT-Tab
3B	F1	6E	ALT-F7		
3C	F2	6F	ALT-F8		

Table 21.2: Special keys scan codes

Key	Code	SHIFT-Key	CTRL-Key	Alt-Key
NoKey	00			
F1	3B	54	5E	68
F2	3C	55	5F	69
F3	3D	56	60	6A
F4	3E	57	61	6B
F5	3F	58	62	6C
F6	40	59	63	6D
F7	41	5A	64	6E
F8	42	5A	65	6F
F9	43	5B	66	70
F10	44	5C	67	71
F11	85	87	89	8B
F12	86	88	8A	8C
Home	47		77	97
Up	48		8D	98
PgUp	49		84	99
Left	4B		73	9B
Center	4C		8F	
Right	4D		74	9D
end	4F		75	9F
Down	50		91	A0
PgDn	51		76	A1
Ins	52	05	04	A2
Del	53	07	06	A3
Tab	8	0F	94	A5
GreyPlus			90	4E

Table 21.3: Structure of TKeyRecord

Field	Meaning
KeyCode	Depending on <code>flags</code> either the physical representation of a key (under DOS scancode, ascii code pair), or the t
ShiftState	Shift-state when this key was pressed (or shortly after)
Flags	Determine how to interpret <code>KeyCode</code>

## Chapter 22

# Reference for unit 'lineinfo'

### 22.1 Overview

The `lineinfo` provides a routine that reads the debug information of an executable (if any exists) and returns source code information about this address. It works with `Stabs` debug information. Note that this unit is not thread-safe, and that its behaviour is undefined if multiple threads try to write a backtrace at the same time.

For DWARF debug information, the `Infodwrf` ([735](#)) unit must be used.

### 22.2 Procedures and functions

#### 22.2.1 GetLineInfo

**Synopsis:** Return source line information about an address.

**Declaration:**

```
function GetLineInfo(addr: ptruint; var func: String; var source: String;
                    var line: LongInt) : Boolean
```

**Visibility:** default

**Description:** `GetLineInfo` returns source line information about the address `addr`. It searches this information in the stabs debugging information found in the binary: If the file was compiled without debug information, nothing will be returned. Upon succesful retrieval of the debug information, `True` is returned, and the `func` parameter is filled with the name of the function in which the address is located. The `source` parameter contains the name of the file in which the function was implemented, and `line` contains the line number in the source file for `addr`.

**Errors:** If no debug information is found, `False` is returned.

## Chapter 23

# Reference for unit 'Linux'

### 23.1 Used units

Table 23.1: Used units by unit 'Linux'

Name	Page
BaseUnix	<a href="#">101</a>
unixtype	<a href="#">1679</a>

### 23.2 Overview

The linux unit contains linux specific operating system calls.

The platform independent functionality of the FPC 1.0.X version of the linux unit has been split out over the unix ([1642](#)), baseunix ([101](#)) and unixutil ([1693](#)) units.

The X86-specific parts have been moved to the X86 ([1723](#)) unit.

People wanting to use the old version (FPC 1.0.X and before) of the linux can use the oldlinux ([989](#)) unit instead.

### 23.3 Constants, types and variables

#### 23.3.1 Constants

`CAP_AUDIT_CONTROL = 30`

Allow manipulation of kernel auditing features

`CAP_AUDIT_WRITE = 29`

Allow writing to kernel audit log

`CAP_CHOWN = 0`

Perform chown operation

`CAP_DAC_OVERRIDE = 1`

Bypass file operation (rwx) checks

`CAP_DAC_READ_SEARCH = 2`

Bypass file read-only operation checks

`CAP_FOWNER = 3`

Bypass owner ID checks

`CAP_FSETID = 4`

Do not clear SUID/GUID bits on modified files

`CAP_FS_MASK = 0xf`

?

`CAP_IPC_LOCK = 14`

Allow memory locking calls

`CAP_IPC_OWNER = 15`

Bypass permission checks on IPC operations

`CAP_KILL = 5`

Bypass permission checks for sending signals

`CAP_LEASE = 28`

Allow file leases

`CAP_LINUX_IMMUTABLE = 9`

Allow setting ext2 file attributes

`CAP_MKNOD = 27`

Allow creation of special files through mknod calls

`CAP_NET_ADMIN = 12`

Allow network operations (e.g. setting socket options)

`CAP_NET_BIND_SERVICE = 10`

Allow binding to ports less than 1024

`CAP_NET_BROADCAST = 11`

Allow socket broadcast operations

`CAP_NET_RAW = 13`

Allow use of RAW and PACKET sockets

`CAP_SETGID = 6`

Allow GID manipulations

`CAP_SETPCAP = 8`

Allow to set other process' capabilities

`CAP_SETUID = 7`

Allow process ID manipulations

`CAP_SYS_ADMIN = 21`

Allow various system administration calls

`CAP_SYS_BOOT = 22`

Allow reboot calls

`CAP_SYS_CHROOT = 18`

Allow chroot calls.

`CAP_SYS_MODULE = 16`

Allow loading/unloading of kernel modules

`CAP_SYS_NICE = 23`

Allowing raising process and thread priorities

`CAP_SYS_PACCT = 20`

Allow acct calls

`CAP_SYS_PTRACE = 19`

Allow ptrace calls

`CAP_SYS_RAWIO = 17`

Allow raw I/O port operations

`CAP_SYS_RESOURCE = 24`

Allow use of special resources or raising of resource limits

`CAP_SYS_TIME = 25`

Allow system or real-time clock modification

`CAP_SYS_TTY_CONFIG = 26`

Allow vhangup calls

`CLONE_CHILD_CLEAR_TID = $00200000`

Clone option: Erase child thread ID in child memory space when child exits.

`CLONE_CHILD_SETTID = $01000000`

Clone option: Store child thread ID in child memory.

`CLONE_DETACHED = $00400000`

Clone option: Start clone detached.

`CLONE_FILES = $00000400`

Clone (729) option: open files shared between processes

`CLONE_FS = $00000200`

Clone (729) option: fs info shared between processes

`CLONE_NEWNS = $00020000`

Clone options: Start child in new (filesystem) namespace.

`CLONE_PARENT = $00008000`

Clone options: Set child parent to parent of calling process.

`CLONE_PARENT_SETTID = $00100000`

Clone option: Store child thread ID in memory in both parent and child.

`CLONE_PID = $00001000`

Clone (729) option: PID shared between processes

`CLONE_PTRACE = $00002000`

Clone options: if parent is traced, trace child also

`CLONE_SETTLS = $00080000`

Clone option: The `newtls` parameter is the TLS descriptor of the child

`CLONE_SIGHAND = $00000800`

Clone (729) option: signal handlers shared between processes

`CLONE_STOPPED = $02000000`

Clone option: Start child in stopped state.

`CLONE_SYSVSEM = $00040000`

Clone option: Caller and child share the same semaphore undo values

`CLONE_THREAD = $00010000`

Clone options: Set child in thread group of calling process.

`CLONE_UNTRACED = $00800000`

Clone option: Do not allow a `ptrace` call on this clone.

`CLONE_VFORK = $00004000`

Clone options: suspend parent till child execs

`CLONE_VM = $00000100`

Clone (729) option: VM shared between processes

`CSIGNAL = $000000ff`

Clone (729) option: Signal mask to be sent at exit

`EPOLLERR = $08`

`event_wait` error condition on file descriptor

`EPOLLET = $80000000`

Set `event_wait` edge trigger behaviour on file descriptor

`EPOLLHUP = $10`

`event_wait` hang up event

`EPOLLIN = $01`



event\_wait input file descriptor ready event

EPOLLONESHOT = \$40000000

Set single-shot behaviour on epoll\_wait.

EPOLLOUT = \$04

event\_wait output file descriptor ready event

EPOLLPRI = \$02

event\_wait high priority data available on input file descriptor

EPOLL\_CTL\_ADD = 1

Add filedescriptor to list of events

EPOLL\_CTL\_DEL = 2

Delete event for filedescriptor

EPOLL\_CTL\_MOD = 3

Modify event for filedescriptor

FUTEX\_CMP\_REQUEUE = 4

Futex option: requeue waiting processes on other futex, but check it's value first

FUTEX\_FD = 2

Futex option: Associate file descriptor with futex.

FUTEX\_LOCK\_PI = 6

Futex option: Undocumented

FUTEX\_OP\_ADD = 1

Futex operation: Undocumented

FUTEX\_OP\_ANDN = 3

Futex operation: Undocumented

FUTEX\_OP\_CMP\_EQ = 0

Futex operation: Undocumented

FUTEX\_OP\_CMP\_GE = 5

Futex operation: Undocumented

FUTEX\_OP\_CMP\_GT = 4

Futex operation: Undocumented

FUTEX\_OP\_CMP\_LE = 3

Futex operation: Undocumented

FUTEX\_OP\_CMP\_LT = 2

Futex operation: Undocumented

FUTEX\_OP\_CMP\_NE = 1

Futex operation: Undocumented

FUTEX\_OP\_OPARG\_SHIFT = 8

Futex operation: Undocumented

FUTEX\_OP\_OR = 2

Futex operation: Undocumented

FUTEX\_OP\_SET = 0

Futex operation: Undocumented

FUTEX\_OP\_XOR = 4

Futex operation: Undocumented

FUTEX\_REQUEUE = 3

Futex option: requeue waiting processes on other futex.

FUTEX\_TRYLOCK\_PI = 8

Futex option: Undocumented

FUTEX\_UNLOCK\_PI = 7

Futex option: Undocumented

FUTEX\_WAIT = 0

Futex option: Wait on futex till wake call arrives.

FUTEX\_WAKE = 1

Futex option: wakes any waiting processes on this futex

`FUTEX_WAKE_OP = 5`

Futex option: Undocumented

`GIO_CMAP = $4B70`

IOCTL: Get colour palette on VGA+

`GIO_FONT = $4B60`

IOCTL: Get font in expanded form.

`GIO_FONTX = $4B6B`

IOCTL: Get font in `consolefontdesc` record.

`GIO_SCRNMAP = $4B40`

IOCTL: get screen mapping from kernel

`GIO_UNIMAP = $4B66`

IOCTL: get unicode-to-font mapping from kernel

`GIO_UNISCRNMAP = $4B69`

IOCTL: get full Unicode screen mapping

`KB_101 = 2`

IOCTL: Keyboard types: 101 keys

`KB_84 = 1`

IOCTL: Keyboard types: 84 keys

`KB_OTHER = 3`

IOCTL: Keyboard types: other type

`KDADDIO = $4B34`

IOCTL: add i/o port as valid

`KDDELIO = $4B35`

IOCTL: delete i/o port as valid

`KDDISABIO = $4B37`

**IOCTL: disable i/o to video board**

KDENABIO = \$4B36

**IOCTL: enable i/o to video board**

KDFONTOP = \$4B72

**IOCTL: font operations**

KDGETKEYCODE = \$4B4C

**IOCTL: read kernel keycode table entry**

KDGETLED = \$4B31

**IOCTL: return current led state**

KDGETMODE = \$4B3B

**IOCTL: get current mode**

KDGKBDIACR = \$4B4A

**IOCTL: read kernel accent table**

KDGKBTYPE = \$4B33

**IOCTL: get keyboard type**

KDMAPDISP = \$4B3C

**IOCTL: map display into address space**

KDMKTONE = \$4B30

**IOCTL: generate tone**

KDSETKEYCODE = \$4B4D

**IOCTL: write kernel keycode table entry**

KDSETLED = \$4B32

**IOCTL: set led state**

KDSETMODE = \$4B3A

**IOCTL: set text/graphics mode**

KDSIGACCEPT = \$4B4E

**IOCTL: accept kbd generated signals**

KDSKBDIACR = \$4B4B

**IOCTL: write kernel accent table**

KDUNMAPDISP = \$4B3D

**IOCTL: unmap display from address space**

KD\_GRAPHICS = 1

**IOCTL: Tty modes: graphics mode**

KD\_TEXT = 0

**IOCTL: Tty modes: Text mode**

KD\_TEXT0 = 2

**IOCTL: Tty modes: Text mode (obsolete)**

KD\_TEXT1 = 3

**IOCTL: Tty modes: Text mode (obsolete)**

KIOCSOUND = \$4B2F

**IOCTL: start/stop sound generation (0 for off)**

LED\_CAP = 4

**IOCTL: LED\_CAP : caps lock led**

LED\_NUM = 2

**IOCTL: LED\_SCR : Num lock led**

LED\_SCR = 1

**IOCTL: LED\_SCR : scroll lock led**

LINUX\_CAPABILITY\_VERSION = \$19980330

**Current capability version in use by kernel**

MAP\_DENYWRITE = \$800

**Read-only**

MAP\_EXECUTABLE = \$1000

Memory area is marked as executable

MAP\_GROWSDOWN = \$100

Memory map grows down, like stack

MAP\_LOCKED = \$2000

Memory pages are locked

MAP\_NORESERVE = \$4000

Do not check for reservations

MODIFY\_LDT\_CONTENTS\_CODE = 2

Modify\_ldt option: Undocumented

MODIFY\_LDT\_CONTENTS\_DATA = 0

Modify\_ldt option: Undocumented

MODIFY\_LDT\_CONTENTS\_STACK = 1

Modify\_ldt option: Undocumented

PIO\_CMAP = \$4B71

IOCTL: Set colour palette on VGA+

PIO\_FONT = \$4B61

IOCTL: Use font in expanded form.

PIO\_FONTRESET = \$4B6D

IOCTL: Reset to default font

PIO\_FONTX = \$4B6C

IOCTL: Set font in consolefontdesc record.

PIO\_SCRNMAP = \$4B41

IOCTL: put screen mapping table in kernel

PIO\_UNIMAP = \$4B67

IOCTL: put unicode-to-font mapping in kernel

PIO\_UNIMAPCLR = \$4B68

**IOCTL:** clear table, possibly advise hash algorithm

`PIO_UNISCRNMAP = $4B6A`

**IOCTL:** set full Unicode screen mapping

`POLLMSG = $0400`

**Unused in linux**

`POLLRDHUP = $2000`

**Peer Shutdown/closed writing half of connection**

`POLLREMOVE = $1000`

**Undocumented linux extension of Poll**

`SPLICE_F_GIFT = 8`

**Pages spliced in are a gift**

`SPLICE_F_MORE = 4`

**Expect more data**

`SPLICE_F_MOVE = 1`

**Move pages instead of copying**

`SPLICE_F_NONBLOCK = 2`

**Don't block on pipe splicing operations**

`SYNC_FILE_RANGE_WAIT_AFTER = 4`

**Wait upon write-out of specified pages in the range after performing any write.**

`SYNC_FILE_RANGE_WAIT_BEFORE = 1`

**Wait for write-out of previously-submitted specified pages before writing more data.**

`SYNC_FILE_RANGE_WRITE = 2`

**Initiate write of all dirty pages in the specified range.**

`UD_CONTENTS_CODE = MODIFY_LDT_CONTENTS_CODE shl1`

**TLS segment descriptor: Undocumented**

`UD_CONTENTS_DATA = MODIFY_LDT_CONTENTS_DATA shl1`

TLS segment descriptor: Undocumented

```
UD_CONTENTS_STACK = MODIFY_LDT_CONTENTS_STACK shl1
```

TLS segment descriptor: Undocumented

```
UD_LIMIT_IN_PAGES = $10
```

TLS segment descriptor: Undocumented

```
UD_LM = $80
```

TLS segment descriptor: Undocumented

```
UD_READ_EXEC_ONLY = $08
```

TLS segment descriptor: Undocumented

```
UD_SEG_32BIT = $01
```

TLS segment descriptor : Undocumented

```
UD_SEG_NOT_PRESENT = $20
```

TLS segment descriptor: Undocumented

```
UD_USEABLE = $40
```

TLS segment descriptor: Undocumented

### 23.3.2 Types

```
EPoll_Data = record
end
```

Data structure used in EPOLL IOCTL call.

```
EPoll_Event = record
    Events : cuint32;
    Data : TEPoll_Data;
end
```

Structure used in epoll\_ctl ([731](#)) call.

```
PEPoll_Data = ^EPoll_Data
```

Pointer to EPoll\_Data ([726](#)) record

```
PEpoll_Event = ^EPoll_Event
```



Pointer to EPoll\_Event (726) type

PSysInfo = ^TSysInfo

Pointer to TSysInfo (727) record.

Puser\_cap\_data = ^user\_cap\_data

Pointer to user\_cap\_data (728) record

Puser\_cap\_header = ^user\_cap\_header

Pointer to user\_cap\_header (728) record

PUser\_Desc = ^user\_desc

PUser\_Desc is a pointer to the user\_desc (728) type.

TCloneFunc = function(args: pointer) : LongInt of object

Clone function prototype.

TEPoll\_Data = EPoll\_Data

Alias for EPoll\_Data (726) type

TEPoll\_Event = EPoll\_Event

Alias for EPoll\_Event (726) type

```
TSysInfo = record
  uptime : clong;
  loads : Array[0..2] of culong;
  totalram : culong;
  freeram : culong;
  sharedram : culong;
  bufferram : culong;
  totalswap : culong;
  freeswap : culong;
  procs : cushort;
  pad : cushort;
  totalhigh : culong;
  freehigh : culong;
  mem_unit : cuint;
  _f : Array[0..19-2*sizeof(clong)-sizeof(cint)] of cchar;
end
```

Record with system information, used by the SysInfo (733) call.

TUser\_Desc = user\_desc

TUser\_Desc is an alias for the user\_desc (728) type.

```
user_cap_data = packed record
  effective : cardinal;
  permitted : cardinal;
  inheritable : cardinal;
end
```

user\_cap\_data describes the set of capabilities for the indicated thread.

```
user_cap_header = packed record
  version : cardinal;
  pid : cardinal;
end
```

user\_cap\_header describes the root user capabilities for the current thread, as set by getcap (714) and setcap (714)

```
user_desc = packed record
  entry_number : cint;
  base_addr : cuint;
  limit : cuint;
  flags : cuint;
end
```

user\_desc is the TLS (Thread Local Storage) segment descriptor used in the Clone call. It should not be used, as it contains highly kernel-specific data.

## 23.4 Procedures and functions

### 23.4.1 capget

**Synopsis:** Return the capabilities for the indicated thread

**Declaration:** `function capget(header: Puser_cap_header; data: Puser_cap_data) : cint`

**Visibility:** default

**Description:** capget returns the capabilities of the indicated thread in header. The thread is identified by the process ID, or -1 for all caller (and child) process ID's.

Refer to the linux man pages (7 capabilities) for more info.

**Errors:** On success, zero is returned, on error -1 is returned, and fperno is set to the error.

See also: capset (729)

### 23.4.2 capset

Synopsis: Set the capabilities for the indicated thread

Declaration: `function capset(header: Puser_cap_header; data: Puser_cap_data) : cint`

Visibility: default

Description: `capset` sets the capabilities of the indicated thread in `header`. The thread is identified by the process ID, or -1 for all caller (and child) process ID's.

Refer to the linux man pages (7 capabilities) for more info.

Errors: On success, zero is returned, on error -1 is returned, and `fperrno` is set to the error.

See also: `capget` ([728](#))

### 23.4.3 clone

Synopsis: Clone current process (create new thread)

Declaration: `function clone(func: TCloneFunc; sp: pointer; flags: LongInt; args: pointer) : LongInt`

Visibility: default

Description: `Clone` creates a child process which is a copy of the parent process, just like `FpFork` ([151](#)) does. In difference with `Fork`, however, the child process shares some parts of it's execution context with its parent, so it is suitable for the implementation of threads: many instances of a program that share the same memory.

When the child process is created, it starts executing the function `Func`, and passes it `Args`. The return value of `Func` is either the explicit return value of the function, or the exit code of the child process.

The `sp` pointer points to the memory reserved as stack space for the child process. This address should be the top of the memory block to be used as stack.

The `Flags` determine the behaviour of the `Clone` call. The low byte of the `Flags` contains the number of the signal that will be sent to the parent when the child dies. This may be bitwise OR'ed with the following constants:

**CLONE\_VM**Parent and child share the same memory space, including memory (un)mapped with subsequent `mmap` calls.

**CLONE\_FS**Parent and child have the same view of the filesystem; the `chroot`, `chdir` and `umask` calls affect both processes.

**CLONE\_FILES**the file descriptor table of parent and child is shared.

**CLONE\_SIGHAND**the parent and child share the same table of signal handlers. The signal masks are different, though.

**CLONE\_PID**Parent and child have the same process ID.

`Clone` returns the process ID in the parent process, and -1 if an error occurred.

Errors: On error, -1 is returned to the parent, and no child is created.

**sys\_eagain**Too many processes are running.

**sys\_enomem**Not enough memory to create child process.

See also: `#rtl.baseunix.FpFork` ([151](#))

**Listing:** ./linuxex/ex71.pp

---

```

program TestC{!one};

{$ifdef Linux}
// close is very Linux specific. 1.9.x threading is done via pthreads.

uses
    Linux , Errors , crt;

const
    Ready : Boolean = false;
    aChar : Char    = 'a';

function CloneProc( Arg: Pointer ): LongInt; Cdecl;
begin
    WriteLn('Hello from the clone ',PChar(Arg));
    repeat
        Write(aChar);
        Select(0,0,0,0,600);
    until Ready;
    WriteLn('Clone finished. ');
    CloneProc := 1;
end;

var
    PID : LongInt;

procedure MainProc;
begin
    WriteLn('cloned process PID: ', PID );
    WriteLn('Press <ESC> to kill ... ');
    repeat
        Write('. ');
        Select(0,0,0,0,300);
        if KeyPressed then
            case ReadKey of
                #27: Ready := true;
                'a': aChar := 'A';
                'A': aChar := 'a';
                'b': aChar := 'b';
                'B': aChar := 'B';
            end;
        until Ready;
    WriteLn('Ready. ');
end;

const
    StackSize = 16384;
    theFlags = CLONE_VM+CLONE_FS+CLONE_FILES+CLONE_SIGHAND;
    aMsg      : PChar = 'Oops !';

var
    theStack : Pointer;
    ExitStat : LongInt;

begin
    GetMem(theStack, StackSize);
    PID := Clone(@CloneProc,

```

---

```

        Pointer ( LongInt(theStack)+StackSize),
        theFlags,
        aMsg);
if PID < 0 then
    WriteLn('Error : ', LinuxError, ' when cloning.')
else
    begin
        MainProc;
        case WaitPID(0,@ExitStat,Wait_Untraced or wait_clone) of
            -1: WriteLn('error:',LinuxError,'; ',StrError(LinuxError));
            0: WriteLn('error:',LinuxError,'; ',StrError(LinuxError));
        else
            WriteLn('Clone exited with: ',ExitStat shr 8);
        end;
    end;
    FreeMem( theStack, StackSize );
{$else}
begin
{$endif}
end.

```

---

#### 23.4.4 epoll\_create

Synopsis: Create new epoll file descriptor

Declaration: `function epoll_create(size: cint) : cint`

Visibility: default

Description: `epoll_create` creates a new epoll file descriptor. The `size` argument indicates to the kernel approximately how many structures should be allocated, but is by no means an upper limit.

On success, a file descriptor is returned that can be used in subsequent `epoll_ctl` (731) or `epoll_wait` (732) calls, and should be closed using the `fpClose` (145) call.

Errors: On error, -1 is returned, and `errno` (101) is set.

See also: `epoll_ctl` (731), `epoll_wait` (732), `#rtl.baseunix.fpClose` (145)

#### 23.4.5 epoll\_ctl

Synopsis: Modify an epoll file descriptor

Declaration: `function epoll_ctl(epfd: cint;op: cint;fd: cint;event: PEpoll_Event) : cint`

Visibility: default

Description: `epoll_ctl` performs the `op` operation on epoll file descriptor `epfd`. The operation will be monitored on file descriptor `fd`, and is optionally controlled by `event`.

`op` can be one of the following values:

**EPOLL\_CTL\_ADD**Add filedescriptor to list of events

**EPOLL\_CTL\_MOD**Modify event for filedescriptor

**EPOLL\_CTL\_DEL**Delete event for filedescriptor

The `events` field in `event_data` is a bitmask of one or more of the following values:

**EPOLLIN**The file is ready for read operations

**EPOLLOUT**The file is ready for write operations.

**EPOLLPRI**Urgent data is available for read operations.

**EPOLLERR**An error condition is signaled on the file descriptor.

**EPOLLHUP**A Hang up happened on the file descriptor.

**EPOLLET**Set the Edge Triggered behaviour for the file descriptor.

**EPOLLONESHOT**Set One-Shot behaviour for the file descriptor. The event will be triggered only once.

Errors: On error -1 is returned, and `errno` is set accordingly.

See also: `epoll_create` (731), `epoll_wait` (732), `#rtl.baseunix.fpClose` (145)

### 23.4.6 `epoll_wait`

Synopsis: Wait for an event on an `epoll` file descriptor.

Declaration: `function epoll_wait(epfd: cint; events: PEPoll_Event; maxevents: cint; timeout: cint) : cint`

Visibility: default

Description: `epoll_wait` waits for `timeout` milliseconds for an event to occur on `epoll` file descriptor `epfd`. If `timeout` is -1, it waits indefinitely, if `timeout` is zero, it does not wait, but returns immediately, even if no events were detected.

On return, data for at most `maxevents` will be returned in the memory pointed to by `events`. The function returns the number of file descriptors for which events were reported. This can be zero if the timeout was reached.

Errors: On error -1 is returned, and `errno` is set accordingly.

See also: `epoll_create` (731), `epoll_ctl` (731), `#rtl.baseunix.fpClose` (145)

### 23.4.7 `fdatasync`

Synopsis: Synchronize the data in memory with the data on storage device

Declaration: `function fdatasync(fd: cint) : cint`

Visibility: default

Description: `fdatasync` does the same as `ffsync` but does not flush the metadata, unless it is vital to the correct reading/writing of the file. In practice, this means that unless the file size changed, the file metadata will not be synced.

See also: `#rtl.unix.fsync` (1670)

### 23.4.8 `futex_op`

Synopsis: Futex operation:

Declaration: `function futex_op(op: cint; oparg: cint; cmp: cint; cmparg: cint) : cint`

Visibility: default

Description: `FUTEX_OP` Performs an operation on a futex:

```
FUTEX_OP := ((op and $F) shl 28) or
             ((cmp and $F) shl 24) or
             ((oparg and $FFF) shl 12)
             or (cmparg and $FFF);
```

### 23.4.9 sync\_file\_range

Synopsis: Force committing of data to disk

Declaration: `function sync_file_range(fd: cint; offset: off64_t; nbytes: off64_t; flags: cuint) : cint`

Visibility: default

Description: `sync_file_range` forces the linux kernel to write any data pages of a specified file (file descriptor `fd`) to disk. The range of the file is specified by the offset `offset` and the number of bytes `nbytes`. `Options` is an OR-ed combination of

**SYNC\_FILE\_RANGE\_WAIT\_BEFORE** Wait for write-out of previously-submitted specified pages before writing more data.

**SYNC\_FILE\_RANGE\_WRITE** Initiate write of all dirty pages in the specified range.

**SYNC\_FILE\_RANGE\_WAIT\_AFTER** Wait upon write-out of specified pages in the range after performing any write.

If none is specified, the operation does nothing.

Errors: On return -1 is returned and `fperno` is set to the actual error code. See the linux man page for more on the error codes.

See also: `fdatsync` ([732](#))

### 23.4.10 Sysinfo

Synopsis: Return kernel system information

Declaration: `function Sysinfo(Info: PSysInfo) : cint`

Visibility: default

Description: `SysInfo` returns system information in `Info`. Returned information in `Info` includes:

**uptime** Number of seconds since boot.

**loads** 1, 5 and 15 minute load averages.

**totalram** total amount of main memory.

**freeram** amount of free memory.

**sharedram** amount of shared memory.

**bufferram** amount of memory used by buffers.

**totalswap** total amount of swap space.

**freeswap** amount of free swap space.

**procs** number of current processes.

Errors: None.

See also: `#rtl.baseunix.fpUname` ([189](#))

**Listing:** `./linuxex/ex64.pp`

---

**program** Example64;

*{ Example to demonstrate the SysInfo function.  
Sysinfo is Linux-only. }*

*{ \$ifdef Linux }*

**Uses** Linux;

**Function** Mb(L : Longint) : longint;

**begin**

    Mb:=L **div** (1024\*1024);

**end**;

**Var** Info : TSysInfo;

    D,M,Secs,H : longint;

*{ \$endif }*

**begin**

*{ \$ifdef Linux }*

**If Not** SysInfo(Info) **then**

**Halt**(1);

**With** Info **do**

**begin**

            D:=Uptime **div** (3600\*24);

            UpTime:=UpTime **mod** (3600\*24);

            h:=uptime **div** 3600;

            uptime:=uptime **mod** 3600;

            m:=uptime **div** 60;

            secs:=uptime **mod** 60;

**Writeln**('Uptime : ',d,'days, ',h,' hours, ',m,' min, ',secs,' s.');

**Writeln**('Loads : ',Loads[1],'/ ',Loads[2],'/ ',Loads[3]);

**Writeln**('Total Ram : ',Mb(totalram),'Mb.');

**Writeln**('Free Ram : ',Mb(freeram),'Mb.');

**Writeln**('Shared Ram : ',Mb(sharedram),'Mb.');

**Writeln**('Buffer Ram : ',Mb(bufferram),'Mb.');

**Writeln**('Total Swap : ',Mb(totalswap),'Mb.');

**Writeln**('Free Swap : ',Mb(freeswap),'Mb.');

**end**;

*{ \$endif }*

**end**.

---



## Chapter 24

# Reference for unit 'Infodwrf'

### 24.1 Overview

The `Infodwrf` provides a routine that reads the debug information of an executable (if any exists) and returns source code information about this address. It works with DWARF debug information. Note that this unit is not thread-safe, and that its behaviour is undefined if multiple threads try to write a backtrace at the same time.

For stabs debug information, the `lineinfo` ([713](#)) unit must be used.

### 24.2 Procedures and functions

#### 24.2.1 GetLineInfo

**Synopsis:** Return source line information about an address.

**Declaration:**

```
function GetLineInfo(addr: ptruint; var func: String; var source: String;
                    var line: LongInt) : Boolean
```

**Visibility:** default

**Description:** `GetLineInfo` returns source line information about the address `addr`. It searches this information in the DWARF debugging information found in the binary: If the file was compiled without debug information, nothing will be returned. Upon successful retrieval of the debug information, `True` is returned, and the `func` parameter is filled with the name of the function in which the address is located. The `source` parameter contains the name of the file in which the function was implemented, and `line` contains the line number in the source file for `addr`.

**Errors:** If no debug information is found, `False` is returned.

## Chapter 25

# Reference for unit 'math'

### 25.1 Used units

Table 25.1: Used units by unit 'math'

Name	Page
sysutils	<a href="#">1426</a>

### 25.2 Overview

This document describes the `math` unit. The `math` unit was initially written by Florian Klaempfl. It provides mathematical functions which aren't covered by the system unit.

This chapter starts out with a definition of all types and constants that are defined, after which an overview is presented of the available functions, grouped by category, and the last part contains a complete explanation of each function.

The following things must be taken into account when using this unit:

1. This unit is compiled in Object Pascal mode so all `integers` are 32 bit.
2. Some overloaded functions exist for data arrays of integers and floats. When using the address operator (`@`) to pass an array of data to such a function, make sure the address is typecasted to the right type, or turn on the 'typed address operator' feature. failing to do so, will cause the compiler not be able to decide which function you want to call.

Table 25.2:

Name	Description
hypot (754)	Hypotenuse of triangle
norm (765)	Euclidian norm

Table 25.3:

Name	Description
mean (761)	Mean of values
meanandstddev (762)	Mean and standard deviation of values
momentskewkurtosis (765)	Moments, skew and kurtosis
popnstddev (766)	Population standard deviation
popnvariance (767)	Population variance
randg (770)	Gaussian distributed random value
stddev (774)	Standard deviation
sum (775)	Sum of values
sumofsquares (776)	Sum of squared values
sumsandsquares (777)	Sum of values and squared values
totalvariance (778)	Total variance of values
variance (779)	variance of values

### 25.3 Geometrical functions

### 25.4 Statistical functions

### 25.5 Number converting

### 25.6 Exponential and logarithmic functions

### 25.7 Hyperbolic functions

### 25.8 Trigonometric functions

### 25.9 Angle unit conversion

Routines to convert angles between different angle units.

### 25.10 Min/max determination

Functions to determine the minimum or maximum of numbers:

Table 25.4:

Name	Description
<code>ceil</code> (746)	Round to infinity
<code>floor</code> (751)	Round to minus infinity
<code>frexp</code> (751)	Return mantissa and exponent

Table 25.5:

Name	Description
<code>intpower</code> (755)	Raise float to integer power
<code>ldexp</code> (756)	Calculate $2^x \times \text{float}$
<code>lnxp1</code> (757)	calculate $\log(x+1)$
<code>log10</code> (757)	calculate 10-base log
<code>log2</code> (758)	calculate 2-base log
<code>logn</code> (758)	calculate N-base log
<code>power</code> (768)	raise float to arbitrary power

## 25.11 Constants, types and variables

### 25.11.1 Constants

`EqualsValue` = 0

Values are the same

`GreaterThanValue` = `High(TValueRelationship)`

First values is greater than second value

`Infinity` = `1.0/0.0`

Value is infinity

`LessThanValue` = `Low(TValueRelationship)`

First value is less than second value

`MaxExtended` = `1.1e+4932`

Maximum value of extended type

`MaxFloat` = `MaxExtended`

Maximum value of float type

`MinExtended` = `3.4e-4932`

Minimum value (closest to zero) of extended type

Table 25.6:

Name	Description
<code>arcosh</code> (743)	calculate reverse hyperbolic cosine
<code>arsinh</code> (745)	calculate reverse hyperbolic sine
<code>artanh</code> (745)	calculate reverse hyperbolic tangent
<code>cosh</code> (747)	calculate hyperbolic cosine
<code>sinh</code> (774)	calculate hyperbolic sine
<code>tanh</code> (778)	calculate hyperbolic tangent

Table 25.7:

Name	Description
<code>arccos</code> (742)	calculate reverse cosine
<code>arcsin</code> (743)	calculate reverse sine
<code>arctan2</code> (744)	calculate reverse tangent
<code>cotan</code> (748)	calculate cotangent
<code>sincos</code> (773)	calculate sine and cosine
<code>tan</code> (777)	calculate tangent

`MinFloat = MinExtended`

Minimum value (closest to zero) of float type

`NaN = 0.0/0.0`

Value is Not a Number

`NegativeValue = Low(TValueSign)`

Value is negative

`NegInfinity = -1.0/0.0`

Value is negative (minus) infinity

`PositiveValue = High(TValueSign)`

Value is positive

`ZeroValue = 0`

Value is zero

## 25.11.2 Types

`float = extended`

Table 25.8:

Name	Description
cycletorad (749)	convert cycles to radians
degtograd (749)	convert degrees to grads
degtorad (750)	convert degrees to radians
gradtodeg (752)	convert grads to degrees
gradtorad (753)	convert grads to radians
radto cycle (768)	convert radians to cycles
radtodeg (769)	convert radians to degrees
radto grad (769)	convert radians to grads

Table 25.9:

Name	Description
max (759)	Maximum of 2 values
maxIntValue (759)	Maximum of an array of integer values
maxvalue (760)	Maximum of an array of values
min (762)	Minimum of 2 values
minIntValue (763)	Minimum of an array of integer values
minvalue (764)	Minimum of an array of values

All calculations are done with the Float type. This allows to recompile the unit with a different float type to obtain a desired precision. The pointer type PFloat (740) is used in functions that accept an array of values of arbitrary length.

```
PFloat = ^float
```

Pointer to Float (740) type.

```
PInteger = ObjPas.PInteger
```

Pointer to integer type

```
TFPUException = (exInvalidOp,exDenormalized,exZeroDivide,exOverflow,
exUnderflow,exPrecision)
```

Table 25.10: Enumeration values for type TFPUEXception

Value	Explanation
exDenormalized	
exInvalidOp	Invalid operation error
exOverflow	Float overflow error
exPrecision	Precision error
exUnderflow	Float underflow error
exZeroDivide	Division by zero error.

Type describing Floating Point processor exceptions.

TFPUExceptionMask= Set of (exDenormalized,exInvalidOp,exOverflow,  
exPrecision,exUnderflow,exZeroDivide)

Type to set the Floating Point Unit exception mask.

TFPUPrecisionMode = (pmSingle,pmReserved,pmDouble,pmExtended)

Table 25.11: Enumeration values for type TFPUPrecisionMode

Value	Explanation
pmDouble	Double-type precision
pmExtended	Extended-type precision
pmReserved	?
pmSingle	Single-type precision

Type describing the default precision for the Floating Point processor.

TFPURoundingMode = (rmNearest,rmDown,rmUp,rmTruncate)

Table 25.12: Enumeration values for type TFPURoundingMode

Value	Explanation
rmDown	Round to biggest integer smaller than value.
rmNearest	Round to nearest integer value
rmTruncate	Cut off fractional part.
rmUp	Round to smallest integer larger than value.

Type describing the rounding mode for the Floating Point processor.

tpaymenttime = (ptendofperiod,ptstartofperiod)

Table 25.13: Enumeration values for type tpaymenttime

Value	Explanation
ptendofperiod	End of period.
ptstartofperiod	Start of period.

Type used in financial (interest) calculations.

TRoundToRange = -37..37

TRoundToRange is the range of valid digits to be used in the RoundTo (771) function.

TValueRelationship = -1..1

Type to describe relational order between values

TValueSign = -1..1

Type indicating sign of a valuea

## 25.12 Procedures and functions

### 25.12.1 arccos

Synopsis: Return inverse cosine

Declaration: `function arccos(x: float) : float`

Visibility: default

Description: `Arccos` returns the inverse cosine of its argument `x`. The argument `x` should lie between -1 and 1 (borders included).

Errors: If the argument `x` is not in the allowed range, an `EInvalidArgument` exception is raised.

See also: `arcsin` (743), `arcosh` (743), `arsinh` (745), `artanh` (745)

**Listing:** `./mathex/ex1.pp`

---

**Program** `Example1`;

*{ Program to demonstrate the arccos function. }*

**Uses** `math`;

**Procedure** `WriteRadDeg(X : float)`;

**begin**

`WriteLn(X:8:5, ' rad = ', radtodeg(x):8:5, ' degrees.')`  
**end**;

**begin**

`WriteRadDeg ( arccos (1));`  
`WriteRadDeg ( arccos (sqrt (3)/2));`  
`WriteRadDeg ( arccos (sqrt (2)/2));`  
`WriteRadDeg ( arccos (1/2));`  
`WriteRadDeg ( arccos (0));`  
`WriteRadDeg ( arccos (-1));`

**end.**

---

### 25.12.2 arcosh

Synopsis: Return inverse hyperbolic cosine

Declaration: `function arcosh(x: float) : float`

Visibility: default

Description: `arcosh` returns the inverse hyperbolic cosine of its argument `x`.

This function is an alias for `arcosh` (743), provided for Delphi compatibility.

See also: `arcosh` (743)



### 25.12.3 arcosh

Synopsis: Return inverse hyperbolic cosine

Declaration: `function arcosh(x: float) : float`

Visibility: default

Description: `Arcosh` returns the inverse hyperbolic cosine of its argument `x`. The argument `x` should be larger than 1. The `arccosh` variant of this function is supplied for Delphi compatibility.

Errors: If the argument `x` is not in the allowed range, an `EInvalidArgument` exception is raised.

See also: `cosh` (747), `sinh` (774), `arcsin` (743), `arsinh` (745), `artanh` (745), `tanh` (778)

**Listing:** `./mathex/ex3.pp`

---

**Program** Example3;

*{ Program to demonstrate the arcosh function. }*

**Uses** math;

**begin**

**WriteLn**(arcosh(1));

**WriteLn**(arcosh(2));

**end.**

---

### 25.12.4 arcsin

Synopsis: Return inverse sine

Declaration: `function arcsin(x: float) : float`

Visibility: default

Description: `Arcsin` returns the inverse sine of its argument `x`. The argument `x` should lie between -1 and 1.

Errors: If the argument `x` is not in the allowed range, an `EInvalidArgument` exception is raised.

See also: `arccos` (742), `arcosh` (743), `arsinh` (745), `artanh` (745)

**Listing:** `./mathex/ex2.pp`

---

**Program** Example1;

*{ Program to demonstrate the arcsin function. }*

**Uses** math;

**Procedure** WriteRadDeg(X : float);

**begin**

**WriteLn**(X:8:5, ' rad = ', radtodeg(x):8:5, ' degrees.')

**end;**

**begin**

    WriteRadDeg ( arcsin(1));

    WriteRadDeg ( arcsin(**sqrt**(3)/2));

---

```

WriteRadDeg ( arcsin (sqrt (2)/2));
WriteRadDeg ( arcsin (1/2));
WriteRadDeg ( arcsin (0));
WriteRadDeg ( arcsin (-1));
end.

```

---

### 25.12.5 arcsinh

Synopsis: Return inverse hyperbolic sine

Declaration: `function arcsinh(x: float) : float`

Visibility: default

Description: `arcsinh` returns the inverse hyperbolic sine of its argument `x`.

This function is an alias for `arsinh` (745), provided for Delphi compatibility.

See also: `arsinh` (745)

### 25.12.6 arctan2

Synopsis: Return arctangent of (y/x)

Declaration: `function arctan2(y: float;x: float) : float`

Visibility: default

Description: `arctan2` calculates `arctan(y/x)`, and returns an angle in the correct quadrant. The returned angle will be in the range  $-\pi$  to  $\pi$  radians. The values of `x` and `y` must be between  $-2^{64}$  and  $2^{64}$ , moreover `x` should be different from zero. On Intel systems this function is implemented with the native intel `fpatan` instruction.

Errors: If `x` is zero, an overflow error will occur.

See also: `arccos` (742), `arcosh` (743), `arsinh` (745), `artanh` (745)

**Listing:** `./mathex/ex6.pp`

---

**Program** Example6;

*{ Program to demonstrate the arctan2 function. }*

**Uses** math;

**Procedure** WriteRadDeg(X : float);

**begin**

**WriteLn**(X:8:5, ' rad = ', radtodeg(x):8:5, ' degrees.')

**end**;

**begin**

**WriteRadDeg** ( arctan2 (2,1));

**end**.

---

### 25.12.7 arctanh

Synopsis: Return inverse hyperbolic tangent

Declaration: `function arctanh(x: float) : float`

Visibility: default

Description: `arcsinh` returns the inverse hyperbolic tangent of its argument `x`.

This function is an alias for `artanh` (745), provided for Delphi compatibility.

See also: `artanh` (745)

### 25.12.8 arsinh

Synopsis: Return inverse hyperbolic sine

Declaration: `function arsinh(x: float) : float`

Visibility: default

Description: `arsinh` returns the inverse hyperbolic sine of its argument `x`. The `arcsinh` variant of this function is supplied for Delphi compatibility.

Errors: None.

See also: `arcosh` (743), `arccos` (742), `arcsin` (743), `artanh` (745)

**Listing:** `./mathex/ex4.pp`

---

**Program** `Example4`;

*{ Program to demonstrate the arsinh function. }*

**Uses** `math`;

**begin**

**WriteLn**(`arsinh(0)`);

**WriteLn**(`arsinh(1)`);

**end**.

---

### 25.12.9 artanh

Synopsis: Return inverse hyperbolic tangent

Declaration: `function artanh(x: float) : float`

Visibility: default

Description: `artanh` returns the inverse hyperbolic tangent of its argument `x`, where `x` should lie in the interval `[-1,1]`, borders included. The `arctanh` variant of this function is supplied for Delphi compatibility.

Errors: In case `x` is not in the interval `[-1,1]`, an `EInvalidArgument` exception is raised.

See also: `arcosh` (743), `arccos` (742), `arcsin` (743), `artanh` (745)

**Listing:** `./mathex/ex5.pp`

---

```

Program Example5;

{ Program to demonstrate the artanh function. }

Uses math;

begin
  WriteLn(artanh(0));
  WriteLn(artanh(0.5));
end.

```

---

### 25.12.10 ceil

Synopsis: Return the lowest integer number greater than or equal to argument

Declaration: `function ceil(x: float) : Integer`

Visibility: default

Description: `Ceil` returns the lowest integer number greater than or equal to `x`. The absolute value of `x` should be less than `maxint`.

Errors: If the absolute value of `x` is larger than `maxint`, an overflow error will occur.

See also: `floor` ([751](#))

**Listing:** `./mathex/ex7.pp`

---

```

Program Example7;

{ Program to demonstrate the Ceil function. }

Uses math;

begin
  WriteLn(Ceil(-3.7)); // should be -3
  WriteLn(Ceil(3.7)); // should be 4
  WriteLn(Ceil(-4.0)); // should be -4
end.

```

---

### 25.12.11 ClearExceptions

Synopsis: Clear Floating Point Unit exceptions

Declaration: `procedure ClearExceptions(RaisePending: Boolean)`

Visibility: default

Description: Clear Floating Point Unit exceptions

### 25.12.12 CompareValue

Synopsis: Compare 2 values

**Declaration:**

```
function CompareValue(const A: Integer;const B: Integer)
    : TValueRelationship
function CompareValue(const A: Int64;const B: Int64)
    : TValueRelationship
function CompareValue(const A: QWord;const B: QWord)
    : TValueRelationship
function CompareValue(const A: Extended;const B: Extended;
    delta: Extended) : TValueRelationship
```

**Visibility:** default

**Description:** CompareValue compares 2 integer or floating point values A and B and returns one of the following values:

```
-1if A<B
0if A=B
-1if A>B
```

See also: TValueRelationship ([741](#))

### 25.12.13 cosecant

**Synopsis:** Calculate cosecant

**Declaration:** `function cosecant(x: float) : float`

**Visibility:** default

**Description:** cosecant calculates the cosecant ( $1/\sin(x)$ ) of its argument x.

**Errors:** If 0 or 180 degrees is specified, an exception will be raised.

See also: secant ([772](#))

### 25.12.14 cosh

**Synopsis:** Return hyperbolic cosine

**Declaration:** `function cosh(x: float) : float`

**Visibility:** default

**Description:** Cosh returns the hyperbolic cosine of it's argument {x}.

**Errors:** None.

See also: arcosh ([743](#)), sinh ([774](#)), arsinh ([745](#))

**Listing:** ./mathex/ex8.pp

---

**Program** Example8;

```
{ Program to demonstrate the cosh function. }
```

**Uses** math;

**begin**

```
    WriteLn(Cosh(0));
```

```
    WriteLn(Cosh(1));
```

```
end.
```

---

**25.12.15 cot**

Synopsis: Alias for `Cotan`

Declaration: `function cot(x: float) : float`

Visibility: default

Description: `cot` is an alias for the `cotan` (748) function.

See also: `cotan` (748)

**25.12.16 cotan**

Synopsis: Return cotangent

Declaration: `function cotan(x: float) : float`

Visibility: default

Description: `Cotan` returns the cotangent of it's argument `x`. The argument `x` must be in radians. `x` should be different from zero.

Errors: If `x` is zero then a overflow error will occur.

See also: `tanh` (778)

**Listing:** `./mathex/ex9.pp`

---

**Program** `Example9`;

*{ Program to demonstrate the cotan function. }*

**Uses** `math`;

**begin**

`writeln(cotan(pi/2));`

`Writeln(cotan(pi/3));`

`Writeln(cotan(pi/4));`

**end.**

---

**25.12.17 csc**

Synopsis: Alias for `cosecant`

Declaration: `function csc(x: float) : float`

Visibility: default

Description: `csc` is an alias for the `cosecant` (747) function.

See also: `cosecant` (747)

**25.12.18 cycletorad**

Synopsis: Convert cycle angle to radians angle

Declaration: `function cycletorad(cycle: float) : float`

Visibility: default

Description: `Cycletorad` transforms it's argument `cycle` (an angle expressed in cycles) to radians. (1 cycle is  $2\pi$  radians).

Errors: None.

See also: `degtograd` ([749](#)), `degtorad` ([750](#)), `radtodeg` ([769](#)), `radtograd` ([769](#)), `radto cycle` ([768](#))

**Listing:** `./mathex/ex10.pp`

---

**Program** `Example10;`

*{ Program to demonstrate the cycletorad function. }*

**Uses** `math;`

**begin**

`writeln(cos(cycletorad(1/6))); // Should print 1/2`

`writeln(cos(cycletorad(1/8))); // should be sqrt(2)/2`

**end.**

---

**25.12.19 degtograd**

Synopsis: Convert degree angle to grads angle

Declaration: `function degtograd(deg: float) : float`

Visibility: default

Description: `Degtograd` transforms it's argument `deg` (an angle in degrees) to grads. (90 degrees is 100 grad.)

Errors: None.

See also: `cycletorad` ([749](#)), `degtorad` ([750](#)), `radtodeg` ([769](#)), `radtograd` ([769](#)), `radto cycle` ([768](#))

**Listing:** `./mathex/ex11.pp`

---

**Program** `Example11;`

*{ Program to demonstrate the degtograd function. }*

**Uses** `math;`

**begin**

`writeln(degtograd(90));`

`writeln(degtograd(180));`

`writeln(degtograd(270))`

**end.**

---

**25.12.20 degtorad**

Synopsis: Convert degree angle to radians angle.

Declaration: `function degtorad(deg: float) : float`

Visibility: default

Description: Degtorad converts it's argument deg (an angle in degrees) to radians. (pi radians is 180 degrees)

Errors: None.

See also: [cycletorad \(749\)](#), [degtograd \(749\)](#), [radtodeg \(769\)](#), [radtograd \(769\)](#), [radto cycle \(768\)](#)

**Listing:** ./mathex/ex12.pp

---

**Program** Example12;

*{ Program to demonstrate the degtorad function. }*

**Uses** math;

```
begin
  writeln(degtorad(45));
  writeln(degtorad(90));
  writeln(degtorad(180));
  writeln(degtorad(270));
  writeln(degtorad(360));
end.
```

---

**25.12.21 DivMod**

Synopsis: Return DIV and MOD of arguments

Declaration: `procedure DivMod(Dividend: Integer; Divisor: Word; var Result: Word; var Remainder: Word)`  
`procedure DivMod(Dividend: Integer; Divisor: Word; var Result: SmallInt; var Remainder: SmallInt)`  
`procedure DivMod(Dividend: DWord; Divisor: DWord; var Result: DWord; var Remainder: DWord)`  
`procedure DivMod(Dividend: Integer; Divisor: Integer; var Result: Integer; var Remainder: Integer)`

Visibility: default

Description: DivMod returns Dividend DIV Divisor in Result, and Dividend MOD Divisor in Remainder

**25.12.22 EnsureRange**

Synopsis: Change value to it falls in specified range.

Declaration: `function EnsureRange(const AValue: Integer; const AMin: Integer; const AMax: Integer) : Integer; Overload`  
`function EnsureRange(const AValue: Int64; const AMin: Int64; const AMax: Int64) : Int64; Overload`



Visibility: default

Description: `EnsureRange` returns `Value` if `AValue` is in the range `AMin..AMax`. It returns `AMin` if the value is less than `AMin`, or `AMax` if the value is larger than `AMax`.

See also: `InRange` ([754](#))

### 25.12.23 floor

Synopsis: Return the largest integer smaller than or equal to argument

Declaration: `function floor(x: float) : Integer`

Visibility: default

Description: `Floor` returns the largest integer smaller than or equal to `x`. The absolute value of `x` should be less than `maxint`.

Errors: If `x` is larger than `maxint`, an overflow will occur.

See also: `ceil` ([746](#))

**Listing:** `./mathex/ex13.pp`

---

**Program** `Example13;`

*{ Program to demonstrate the floor function. }*

**Uses** `math;`

**begin**

`WriteLn (Ceil (-3.7)); // should be -4`

`WriteLn (Ceil (3.7)); // should be 3`

`WriteLn (Ceil (-4.0)); // should be -4`

**end.**

---

### 25.12.24 Frexp

Synopsis: Return mantissa and exponent.

Declaration: `procedure Frexp(X: float; var Mantissa: float; var Exponent: Integer)`

Visibility: default

Description: `Frexp` returns the mantissa and exponent of it's argument `x` in mantissa and exponent.

Errors: None

**Listing:** `./mathex/ex14.pp`

---

**Program** `Example14;`

*{ Program to demonstrate the frexp function. }*

**Uses** `math;`

**Procedure** `dofrexp(Const X : extended);`

---

```

var man : extended;
    exp: longint;

begin
    man:=0;
    exp:=0;
    frexp(x,man,exp);
    write(x,' has ');
    WriteLn('mantissa ',man,' and exponent ',exp);
end;

begin
//    dofexp(1.00);
    dofexp(1.02e-1);
    dofexp(1.03e-2);
    dofexp(1.02e1);
    dofexp(1.03e2);
end.

```

---

### 25.12.25 GetExceptionMask

Synopsis: Get the Floating Point Unit exception mask.

Declaration: function GetExceptionMask : TFPUExceptionMask

Visibility: default

Description: Get the Floating Point Unit exception mask.

### 25.12.26 GetPrecisionMode

Synopsis: Return the Floating Point Unit precision mode.

Declaration: function GetPrecisionMode : TFPUPrecisionMode

Visibility: default

Description: Return the Floating Point Unit precision mode.

### 25.12.27 GetRoundMode

Synopsis: Return the Floating Point Unit rounding mode.

Declaration: function GetRoundMode : TFPURoundingMode

Visibility: default

Description: Return the Floating Point Unit rounding mode.

### 25.12.28 gradtodeg

Synopsis: Convert grads angle to degrees angle

Declaration: function gradtodeg(grad: float) : float

Visibility: default

Description: `Gradtodeg` converts its argument `grad` (an angle in grads) to degrees. (100 grad is 90 degrees)

Errors: None.

See also: `cycletorad` (749), `degtograd` (749), `radtodeg` (769), `radtograd` (769), `radto cycle` (768), `gradtorad` (753)

**Listing:** `./mathex/ex15.pp`

---

**Program** `Example15;`

*{ Program to demonstrate the `gradtodeg` function. }*

**Uses** `math;`

```
begin
  writeln (gradtodeg (100));
  writeln (gradtodeg (200));
  writeln (gradtodeg (300));
end.
```

---

### 25.12.29 `gradtorad`

Synopsis: Convert grads angle to radians angle

Declaration: `function gradtorad(grad: float) : float`

Visibility: default

Description: `Gradtorad` converts its argument `grad` (an angle in grads) to radians. (200 grad is pi degrees).

Errors: None.

See also: `cycletorad` (749), `degtograd` (749), `radtodeg` (769), `radtograd` (769), `radto cycle` (768), `gradtodeg` (752)

**Listing:** `./mathex/ex16.pp`

---

**Program** `Example16;`

*{ Program to demonstrate the `gradtorad` function. }*

**Uses** `math;`

```
begin
  writeln (gradtorad (100));
  writeln (gradtorad (200));
  writeln (gradtorad (300));
end.
```

---

### 25.12.30 hypot

Synopsis: Return hypotenuse of triangle

Declaration: `function hypot(x: float;y: float) : float`

Visibility: default

Description: `Hypot` returns the hypotenuse of the triangle where the sides adjacent to the square angle have lengths `x` and `y`. The function uses Pythagoras' rule for this.

Errors: None.

**Listing:** `./mathex/ex17.pp`

---

**Program** `Example17;`

`{ Program to demonstrate the hypot function. }`

**Uses** `math;`

**begin**

`WriteLn(hypot(3,4)); // should be 5`  
**end.**

---

### 25.12.31 ifthen

Synopsis: Return one of two values, depending on a boolean condition

Declaration: `function ifthen(val: Boolean;const iftrue: Integer;  
                          const iffalse: Integer) : Integer; Overload`  
`function ifthen(val: Boolean;const iftrue: Int64;const iffalse: Int64)  
                  : Int64; Overload`  
`function ifthen(val: Boolean;const iftrue: double;const iffalse: double)  
                  : double; Overload`

Visibility: default

Description: `ifthen` returns `iftrue` if `val` is `True`, and `iffalse` if `val` is `False`.

This function can be used in expressions.

### 25.12.32 InRange

Synopsis: Check whether value is in range.

Declaration: `function InRange(const AValue: Integer;const AMin: Integer;  
                          const AMax: Integer) : Boolean; Overload`  
`function InRange(const AValue: Int64;const AMin: Int64;  
                  const AMax: Int64) : Boolean; Overload`

Visibility: default

Description: `InRange` returns `True` if `AValue` is in the range `AMin..AMax`. It returns `False` if `Value` lies outside the specified range.

See also: `EnsureRange` ([750](#))

### 25.12.33 intpower

Synopsis: Return integer power.

Declaration: `function intpower(base: float; const exponent: Integer) : float`

Visibility: default

Description: `Intpower` returns `base` to the power `exponent`, where `exponent` is an integer value.

Errors: If `base` is zero and the exponent is negative, then an overflow error will occur.

See also: `power` ([768](#))

**Listing:** `./mathex/ex18.pp`

---

**Program** `Example18;`

*{ Program to demonstrate the intpower function. }*

**Uses** `math;`

**Procedure** `DoIntpower (X : extended; Pow : Integer);`

**begin**

`writeln (X:8:4, '^', Pow:2, ' = ', intpower(X,pow):8:4);`  
**end;**

**begin**

`dointpower (0.0,0);`  
`dointpower (1.0,0);`  
`dointpower (2.0,5);`  
`dointpower (4.0,3);`  
`dointpower (2.0,-1);`  
`dointpower (2.0,-2);`  
`dointpower (-2.0,4);`  
`dointpower (-4.0,3);`

**end.**

---

### 25.12.34 IsInfinite

Synopsis: Check whether value is infinite

Declaration: `function IsInfinite(const d: Double) : Boolean`

Visibility: default

Description: `IsInfinite` returns `True` if the double `d` contains the infinite value.

See also: `IsZero` ([756](#)), `IsInfinite` ([755](#))

### 25.12.35 IsNan

Synopsis: Check whether value is Not a Number

Declaration: `function IsNan(const d: Double) : Boolean; Overload`

Visibility: default

**Description:** `IsNan` returns `True` if the double `d` contains Not A Number (a value which cannot be represented correctly in double format).

See also: `IsZero` (756), `IsInfinite` (755)

### 25.12.36 `IsZero`

**Synopsis:** Check whether value is zero

**Declaration:**

```
function IsZero(const A: Single;Epsilon: Single) : Boolean;  Overload
function IsZero(const A: Single) : Boolean;  Overload
function IsZero(const A: Extended;Epsilon: Extended) : Boolean
          ;  Overload
function IsZero(const A: Extended) : Boolean;  Overload
```

**Visibility:** default

**Description:** `IsZero` checks whether the float value `A` is zero, up to a precision of `Epsilon`. It returns `True` if `Abs(A)` is less than `Epsilon`.

The default value for `Epsilon` depends on the type of the argument: it is 1E-4 for `Single`, 1E-12 for `Double` and 1E-16 for `extended`.

See also: `IsNan` (755), `IsInfinite` (755), `SameValue` (771)

### 25.12.37 `ldexp`

**Synopsis:** Return (2 to the power `p`) times `x`

**Declaration:**

```
function ldexp(x: float;const p: Integer) : float
```

**Visibility:** default

**Description:** `Ldexp` returns (2 to the power `p`) times `x`.

**Errors:** None.

See also: `lnxp1` (757), `log10` (757), `log2` (758), `logn` (758)

**Listing:** `./mathex/ex19.pp`

---

**Program** `Example19`;

*{ Program to demonstrate the `ldexp` function. }*

**Uses** `math`;

**begin**

**writeln** (`ldexp` (2,4):8:4);

**writeln** (`ldexp` (0.5,3):8:4);

**end.**

---

**25.12.38 lnxp1**

Synopsis: Return natural logarithm of 1+X

Declaration: `function lnxp1(x: float) : float`

Visibility: default

Description: `Lnxp1` returns the natural logarithm of 1+X. The result is more precise for small values of x. x should be larger than -1.

Errors: If  $x \leq -1$  then an `EInvalidArgument` exception will be raised.

See also: `ldexp` (756), `log10` (757), `log2` (758), `logn` (758)

**Listing:** `./mathex/ex20.pp`

---

**Program** `Example20`;

*{ Program to demonstrate the lnxp1 function. }*

**Uses** `math`;

```
begin
  writeln(lnxp1(0));
  writeln(lnxp1(0.5));
  writeln(lnxp1(1));
end.
```

---

**25.12.39 log10**

Synopsis: Return 10-Based logarithm.

Declaration: `function log10(x: float) : float`

Visibility: default

Description: `Log10` returns the 10-base logarithm of X.

Errors: If x is less than or equal to 0 an 'invalid fpu operation' error will occur.

See also: `ldexp` (756), `lnxp1` (757), `log2` (758), `logn` (758)

**Listing:** `./mathex/ex21.pp`

---

**Program** `Example21`;

*{ Program to demonstrate the log10 function. }*

**Uses** `math`;

```
begin
  Writeln(Log10(10):8:4);
  Writeln(Log10(100):8:4);
  Writeln(Log10(1000):8:4);
  Writeln(Log10(1):8:4);
  Writeln(Log10(0.1):8:4);
  Writeln(Log10(0.01):8:4);
  Writeln(Log10(0.001):8:4);
end.
```

---

**25.12.40 log2**

Synopsis: Return 2-based logarithm

Declaration: `function log2(x: float) : float`

Visibility: default

Description: Log2 returns the 2-base logarithm of X.

Errors: If  $x$  is less than or equal to 0 an 'invalid fpu operation' error will occur.

See also: `ldexp` (756), `lnxp1` (757), `log10` (757), `logn` (758)

**Listing:** `./mathex/ex22.pp`

---

**Program** Example22;

*{ Program to demonstrate the log2 function. }*

**Uses** math;

**begin**

```

  WriteLn(Log2(2):8:4);
  WriteLn(Log2(4):8:4);
  WriteLn(Log2(8):8:4);
  WriteLn(Log2(1):8:4);
  WriteLn(Log2(0.5):8:4);
  WriteLn(Log2(0.25):8:4);
  WriteLn(Log2(0.125):8:4);

```

**end.**

---

**25.12.41 logn**

Synopsis: Return N-based logarithm.

Declaration: `function logn(n: float;x: float) : float`

Visibility: default

Description: Logn returns the n-base logarithm of X.

Errors: If  $x$  is less than or equal to 0 an 'invalid fpu operation' error will occur.

See also: `ldexp` (756), `lnxp1` (757), `log10` (757), `log2` (758)

**Listing:** `./mathex/ex23.pp`

---

**Program** Example23;

*{ Program to demonstrate the logn function. }*

**Uses** math;

**begin**

```

  WriteLn(Logn(3,4):8:4);
  WriteLn(Logn(2,4):8:4);
  WriteLn(Logn(6,9):8:4);
  WriteLn(Logn(exp(1),exp(1)):8:4);

```



---

```

Writeln (Logn (0.5 , 1):8:4);
Writeln (Logn (0.25 , 3):8:4);
Writeln (Logn (0.125 , 5):8:4);
end.

```

---

### 25.12.42 Max

Synopsis: Return largest of 2 values

Declaration: `function Max(a: Integer;b: Integer) : Integer; Overload`  
`function Max(a: Int64;b: Int64) : Int64; Overload`  
`function Max(a: Extended;b: Extended) : Extended; Overload`

Visibility: default

Description: Max returns the maximum of Int1 and Int2.

Errors: None.

See also: min ([762](#)), maxIntValue ([759](#)), maxvalue ([760](#))

**Listing:** ./mathex/ex24.pp

---

**Program** Example24 ;

*{ Program to demonstrate the max function. }*

**Uses** math ;

**Var**

A,B : Cardinal ;

**begin**

A:=1;b:=2;

**writeln** (max(a,b));

**end.**

---

### 25.12.43 MaxIntValue

Synopsis: Return largest element in integer array

Declaration: `function MaxIntValue(const Data: Array of Integer) : Integer`

Visibility: default

Description: MaxIntValue returns the largest integer out of the Data array.

This function is provided for Delphi compatibility, use the maxvalue ([760](#)) function instead.

Errors: None.

See also: maxvalue ([760](#)), minvalue ([764](#)), minIntValue ([763](#))

**Listing:** ./mathex/ex25.pp

---

```

Program Example25;

{ Program to demonstrate the MaxIntValue function. }

{ Make sure integer is 32 bit }
{$mode objfpc}

Uses math;

Type
  TExArray = Array[1..100] of Integer;

Var
  I : Integer;
  ExArray : TExArray;

begin
  Randomize;
  for I:=low(exarray) to high(exarray) do
    ExArray[I]:=Random(I)-Random(100);
  WriteLn(MaxIntValue(ExArray));
end.

```

---

### 25.12.44 maxvalue

Synopsis: Return largest value in array

**Declaration:** function maxvalue(const data: Array of Extended) : Extended  
 function maxvalue(const data: PExtended;const N: Integer) : Extended  
 function maxvalue(const data: Array of Integer) : Integer  
 function maxvalue(const data: PInteger;const N: Integer) : Integer

Visibility: default

**Description:** Maxvalue returns the largest value in the data array with integer or float values. The return value has the same type as the elements of the array.

The third and fourth forms accept a pointer to an array of N integer or float values.

Errors: None.

See also: maxIntValue ([759](#)), minvalue ([764](#)), minIntValue ([763](#))

**Listing:** ./mathex/ex26.pp

---

```

program Example26;

{ Program to demonstrate the MaxValue function. }

{ Make sure integer is 32 bit }
{$mode objfpc}

uses math;

var i:1..100;
    f_array:array[1..100] of Float;
    i_array:array[1..100] of Integer;

```

```

    Pf_array : Pfloat;
    Pi_array : Pinteger;

begin
    randomize;

    Pf_array := @f_array[1];
    Pi_array := @i_array[1];

    for i:=low(f_array) to high(f_array) do
        f_array[i] := (random-random)*100;
    for i:=low(i_array) to high(i_array) do
        i_array[i] := random(l)-random(100);

    Writeln('Max Float      : ',MaxValue(f_array):8:4);
    Writeln('Max Float    (b) : ',MaxValue(Pf_array,100):8:4);
    Writeln('Max Integer    : ',MaxValue(i_array):8);
    Writeln('Max Integer (b) : ',MaxValue(Pi_array,100):8);
end.

```

---

### 25.12.45 mean

Synopsis: Return mean value of array

Declaration: `function mean(const data: Array of Extended) : float`  
`function mean(const data: PExtended;const N: LongInt) : float`

Visibility: default

Description: `Mean` returns the average value of `data`. The second form accepts a pointer to an array of `N` values.

Errors: None.

See also: `meanandstddev` ([762](#)), `momentaskewkurtosis` ([765](#)), `sum` ([775](#))

**Listing:** `./mathex/ex27.pp`

---

**Program** Example27;

*{ Program to demonstrate the Mean function. }*

**Uses** math;

**Type**

`TExArray = Array[1..100] of Float;`

**Var**

`l : Integer;`  
`ExArray : TExArray;`

**begin**

**Randomize;**

**for** `l:=low(ExArray) to high(ExArray) do`

`ExArray[i] := (Random-Random)*100;`

**Writeln** ('Max : ',MaxValue(ExArray):8:4);

**Writeln** ('Min : ',MinValue(ExArray):8:4);

**Writeln** ('Mean : ',Mean(ExArray):8:4);

**Writeln** ('Mean (b) : ',Mean(@ExArray[1],100):8:4);

---

end.

---

### 25.12.46 meanandstddev

Synopsis: Return mean and standard deviation of array

**Declaration:** `procedure meanandstddev(const data: Array of Extended; var mean: float;  
var stddev: float)  
procedure meanandstddev(const data: PExtended; const N: LongInt;  
var mean: float; var stddev: float)`

Visibility: default

**Description:** `meanandstddev` calculates the mean and standard deviation of data and returns the result in `mean` and `stddev`, respectively. `Stddev` is zero if there is only one value. The second form accepts a pointer to an array of `N` values.

Errors: None.

See also: `mean` (761), `sum` (775), `sumofsquares` (776), `momentskewkurtosis` (765)

**Listing:** `./mathex/ex28.pp`

---

**Program** `Example28;`

*{ Program to demonstrate the Meanandstddev function. }*

**Uses** `math;`

**Type**

`TExArray = Array[1..100] of Extended;`

**Var**

`I : Integer;  
ExArray : TExArray;  
Mean, stddev : Extended;`

**begin**

`Randomize;  
for I:=low(ExArray) to high(ExArray) do  
ExArray[I]:= (Random-Random)*100;  
MeanAndStdDev(ExArray, Mean, StdDev);  
WriteLn('Mean : ', Mean:8:4);  
WriteLn('StdDev : ', StdDev:8:4);  
MeanAndStdDev(@ExArray[1], 100, Mean, StdDev);  
WriteLn('Mean (b) : ', Mean:8:4);  
WriteLn('StdDev (b) : ', StdDev:8:4);`

`end.`

---

### 25.12.47 Min

Synopsis: Return smallest of two values.

**Declaration:** `function Min(a: Integer; b: Integer) : Integer; Overload  
function Min(a: Int64; b: Int64) : Int64; Overload  
function Min(a: Extended; b: Extended) : Extended; Overload`

Visibility: default

Description: `min` returns the smallest value of `Int1` and `Int2`;

Errors: None.

See also: `max` ([759](#))

**Listing:** `./mathex/ex29.pp`

---

```
Program Example29;

{ Program to demonstrate the min function. }

Uses math;

Var
  A,B : Cardinal;

begin
  A:=1;b:=2;
  writeln(min(a,b));
end.
```

---

### 25.12.48 MinIntValue

Synopsis: Return smallest value in integer array

Declaration: `function MinIntValue(const Data: Array of Integer) : Integer`

Visibility: default

Description: `MinIntvalue` returns the smallest value in the `Data` array.

This function is provided for Delphi compatibility, use `minvalue` instead.

Errors: None

See also: `minvalue` ([764](#)), `maxIntValue` ([759](#)), `maxvalue` ([760](#))

**Listing:** `./mathex/ex30.pp`

---

```
Program Example30;

{ Program to demonstrate the MinIntValue function. }

{ Make sore integer is 32 bit}
{$mode objfpc}

Uses math;

Type
  TExArray = Array[1..100] of Integer;

Var
  I : Integer;
  ExArray : TExArray;

begin
```

---

```

Randomize;
for i:=low(ExArray) to high(ExArray) do
  ExArray[i]:=Random(i)-Random(100);
WriteLn(MinIntValue(ExArray));
end.

```

---

### 25.12.49 minvalue

Synopsis: Return smallest value in array

Declaration: `function minvalue(const data: Array of Extended) : Extended`  
`function minvalue(const data: PExtended;const N: Integer) : Extended`  
`function minvalue(const data: Array of Integer) : Integer`  
`function MinValue(const Data: PInteger;const N: Integer) : Integer`

Visibility: default

Description: `Minvalue` returns the smallest value in the data array with integer or float values. The return value has the same type as the elements of the array.

The third and fourth forms accept a pointer to an array of N integer or float values.

Errors: None.

See also: `maxIntValue` (759), `maxvalue` (760), `minIntValue` (763)

Listing: `./mathex/ex31.pp`

---

**program** Example31;

*{ Program to demonstrate the MinValue function. }*

*{ Make sure integer is 32 bit }*  
*{ \$mode objfpc }*

**uses** math;

**var** i:1..100;  
 f\_array:array[1..100] of Float;  
 i\_array:array[1..100] of Integer;  
 Pf\_array:Pfloat;  
 Pi\_array:Pinteger;

**begin**

**randomize**;

  Pf\_array:=@f\_array[1];

  Pi\_array:=@i\_array[1];

**for** i:=low(f\_array) **to** high(f\_array) **do**

    f\_array[i]:=(random-random)\*100;

**for** i:=low(i\_array) **to** high(i\_array) **do**

    i\_array[i]:=random(i)-random(100);

**WriteLn**( 'Min Float : ',MinValue(f\_array):8:4);

**WriteLn**( 'Min Float (b) : ',MinValue(Pf\_array,100):8:4);

**WriteLn**( 'Min Integer : ',MinValue(i\_array):8);

**WriteLn**( 'Min Integer (b) : ',MinValue(Pi\_array,100):8);

**end.**

---

**25.12.50 momentskewkurtosis**

Synopsis: Return 4 first moments of distribution

Declaration: `procedure momentskewkurtosis(const data: Array of Extended;`  
   `out m1: float;out m2: float;out m3: float;`  
   `out m4: float;out skew: float;`  
   `out kurtosis: float)`  
           `procedure momentskewkurtosis(const data: PExtended;const N: Integer;`  
   `out m1: float;out m2: float;out m3: float;`  
   `out m4: float;out skew: float;`  
   `out kurtosis: float)`

Visibility: default

Description: `momentskewkurtosis` calculates the 4 first moments of the distribution of values in `data` and returns them in `m1,m2,m3` and `m4`, as well as the `skew` and `kurtosis`.

Errors: None.

See also: `mean` (761), `meanandstddev` (762)

**Listing:** `./mathex/ex32.pp`

---

```

program Example32;

{ Program to demonstrate the momentskewkurtosis function. }

uses math;

var distarray: array[1..1000] of float;
    l: longint;
    m1,m2,m3,m4,skew,kurtosis: float;

begin
  randomize;
  for l:=low(distarray) to high(distarray) do
    distarray[l]:=random;
  momentskewkurtosis(DistArray,m1,m2,m3,m4,skew,kurtosis);

  Writeln ( '1st moment : ',m1:8:6);
  Writeln ( '2nd moment : ',m2:8:6);
  Writeln ( '3rd moment : ',m3:8:6);
  Writeln ( '4th moment : ',m4:8:6);
  Writeln ( 'Skew       : ',skew:8:6);
  Writeln ( 'kurtosis    : ',kurtosis:8:6);
end.
```

---

**25.12.51 norm**

Synopsis: Return Euclidian norm

Declaration: `function norm(const data: Array of Extended) : float`  
           `function norm(const data: PExtended;const N: Integer) : float`

Visibility: default

**Description:** `Norm` calculates the Euclidian norm of the array of data. This equals `sqrt (sumofsquares (data))`.

The second form accepts a pointer to an array of N values.

**Errors:** None.

See also: `sumofsquares` ([776](#))

**Listing:** `./mathex/ex33.pp`

---

```

program Example33;

  { Program to demonstrate the norm function. }

uses math;

var v:array[1..10] of Float;
    l:1..10;

begin
  for l:=low(v) to high(v) do
    v[l]:=random;
    writeln(norm(v));
end.

```

---

### 25.12.52 operator **\*\***(float, float): float

**Declaration:** `operator operator **(float, float): float(bas: float;expo: float)`  
`: float`

**Visibility:** default

### 25.12.53 operator **\*\***(Int64, Int64): Int64

**Declaration:** `operator operator **(Int64, Int64): Int64(bas: Int64;expo: Int64)`  
`: Int64`

**Visibility:** default

### 25.12.54 popnstddev

**Synopsis:** Return population variance

**Declaration:** `function popnstddev(const data: Array of Extended) : float`  
`function popnstddev(const data: PExtended;const N: Integer) : float`

**Visibility:** default

**Description:** `Popnstddev` returns the square root of the population variance of the values in the `Data` array. It returns zero if there is only one value.

The second form of this function accepts a pointer to an array of N values.

**Errors:** None.

See also: `popnvariance` ([767](#)), `mean` ([761](#)), `meanandstddev` ([762](#)), `stddev` ([774](#)), `momentskewkurtosis` ([765](#))



**Listing:** ./mathex/ex35.pp

---

**Program** Example35;

*{ Program to demonstrate the PopnStdDev function. }*

**Uses** Math;

**Type**

TExArray = **Array**[1..100] **of** Float;

**Var**

I : Integer;

ExArray : TExArray;

**begin**

Randomize;

**for** I:=**low**(ExArray) **to high**(ExArray) **do**

ExArray[I]:= (**Random**-**Random**)\*100;

WriteIn('Max : ',MaxValue(ExArray):8:4);

WriteIn('Min : ',MinValue(ExArray):8:4);

WriteIn('Pop. stddev. : ',PopnStdDev(ExArray):8:4);

WriteIn('Pop. stddev. (b) : ',PopnStdDev(@ExArray[1],100):8:4);

**end.**

---

### 25.12.55 popnvariance

Synopsis: Return population variance

**Declaration:** function popnvariance(const data: PExtended; const N: Integer) : float  
 function popnvariance(const data: Array of Extended) : float

Visibility: default

**Description:** Popnvariance the population variance of the values in the Data array. It returns zero if there is only one value.

The second form of this function accepts a pointer to an array of N values.

Errors: None.

See also: popnstddev ([766](#)), mean ([761](#)), meanandstddev ([762](#)), stddev ([774](#)), momentskewkurtosis ([765](#))

**Listing:** ./mathex/ex36.pp

---

**Program** Example36;

*{ Program to demonstrate the PopnVariance function. }*

**Uses** math;

**Var**

I : Integer;

ExArray : **Array**[1..100] **of** Float;

**begin**

Randomize;

**for** I:=**low**(ExArray) **to high**(ExArray) **do**

ExArray[I]:= (**Random**-**Random**)\*100;

---

```

WriteIn ( 'Max           : ',MaxValue ( ExArray ):8:4 );
WriteIn ( 'Min           : ',MinValue ( ExArray ):8:4 );
WriteIn ( 'Pop. var.     : ',PopnVariance ( ExArray ):8:4 );
WriteIn ( 'Pop. var. (b) : ',PopnVariance ( @ExArray [ 1 ],100 ):8:4 );
end.

```

---

### 25.12.56 power

Synopsis: Return real power.

Declaration: `function power (base: float;exponent: float) : float`

Visibility: default

Description: `power` raises `base` to the power `power`. This is equivalent to `exp (power*ln (base) )`. Therefore `base` should be non-negative.

Errors: None.

See also: `intpower` ([755](#))

**Listing:** `./mathex/ex34.pp`

---

**Program** Example34;

*{ Program to demonstrate the power function. }*

**Uses** Math;

**procedure** dopower(x,y : float);

```

begin
  writeln (x:8:6, '^',y:8:6, ' = ',power(x,y):8:6)
end;

```

```

begin
  dopower(2,2);
  dopower(2,-2);
  dopower(2,0.0);
end.

```

---

### 25.12.57 radtocycle

Synopsis: Convert radians angle to cycle angle

Declaration: `function radtocycle(rad: float) : float`

Visibility: default

Description: `Radtocycle` converts its argument `rad` (an angle expressed in radians) to an angle in cycles.  
(1 cycle equals  $2\pi$  radians)

Errors: None.

See also: `degtograd` ([749](#)), `degtorad` ([750](#)), `radtodeg` ([769](#)), `radtograd` ([769](#)), `cycletorad` ([749](#))

**Listing:** ./mathex/ex37.pp

**Program** Example37;

*{ Program to demonstrate the radtocycle function. }*

**Uses** math;

**begin**  
     **writeln**(radtocycle(2\***pi**):8:6);  
     **writeln**(radtocycle(**pi**):8:6);  
     **writeln**(radtocycle(**pi**/2):8:6);  
**end.**

### 25.12.58 radtodeg

Synopsis: Convert radians angle to degrees angle

Declaration: `function radtodeg(rad: float) : float`

Visibility: default

Description: `Radtodeg` converts its argument `rad` (an angle expressed in radians) to an angle in degrees. (180 degrees equals  $\pi$  radians)

Errors: None.

See also: `degtograd` (749), `degtorad` (750), `radtocycle` (768), `radtograd` (769), `cycletorad` (749)

**Listing:** ./mathex/ex38.pp

**Program** Example38;

*{ Program to demonstrate the radtodeg function. }*

**Uses** math;

**begin**  
     **writeln**(radtodeg(2\***pi**):8:6);  
     **writeln**(radtodeg(**pi**):8:6);  
     **writeln**(radtodeg(**pi**/2):8:6);  
**end.**

### 25.12.59 radtograd

Synopsis: Convert radians angle to grads angle

Declaration: `function radtograd(rad: float) : float`

Visibility: default

Description: `Radtodeg` converts its argument `rad` (an angle expressed in radians) to an angle in grads. (200 grads equals  $\pi$  radians)

Errors: None.

See also: `degtograd` (749), `degtorad` (750), `radtocycle` (768), `radtodeg` (769), `cycletorad` (749)

**Listing:** ./mathex/ex39.pp

---

**Program** Example39;

*{ Program to demonstrate the radto grad function. }*

**Uses** math;

**begin**  
     **writeln**(radto grad(2\***pi**):8:6);  
     **writeln**(radto grad(**pi**):8:6);  
     **writeln**(radto grad(**pi**/2):8:6);  
**end.**

---

### 25.12.60 randg

Synopsis: Return gaussian distributed random number.

Declaration: `function randg(mean: float; stddev: float) : float`

Visibility: default

Description: `randg` returns a random number which - when produced in large quantities - has a Gaussian distribution with mean `mean` and standard deviation `stddev`.

Errors: None.

See also: `mean` ([761](#)), `stddev` ([774](#)), `meanandstddev` ([762](#))

**Listing:** ./mathex/ex40.pp

---

**Program** Example40;

*{ Program to demonstrate the randg function. }*

**Uses** Math;

**Var**  
     I : Integer;  
     ExArray : **Array**[1..10000] of Float;;  
     Mean, stddev : Float;  
  
**begin**  
     **Randomize**;  
     **for** I := **low**(ExArray) **to high**(ExArray) **do**  
         ExArray[I] := Randg(1, 0.2);  
     MeanAndStdDev(ExArray, Mean, StdDev);  
     **Writeln**( 'Mean : ', Mean:8:4);  
     **Writeln**( 'StdDev : ', StdDev:8:4);  
**end.**

---

### 25.12.61 RandomFrom

Synopsis: Return a random element of an array of numbers

Visibility: default

See also: `#rtl.system.Random` (1359), `RandomRange` (771)

**Synopsis:** Return a random number in a range

Visibility: default

See also: `#rtl.system.Random` (1359), `RandomFrom` (770)

**Synopsis:** Round to the specified number of digits

Visibility: default

See also: [TRoundToRange \(741\)](#), [SimpleRoundTo \(773\)](#)

Synopsis: Check whether 2 float values are the same

Visibility: default

If unspecified, the default value for `Epsilon` is 0.0.

See also: [MinFloat \(739\)](#), [IsZero \(756\)](#)

### 25.12.65 **sec**

Synopsis: Alias for `secant`

Declaration: `function sec(x: float) : float`

Visibility: default

Description: `sec` is an alias for the `secant` ([772](#)) function.

See also: `secant` ([772](#))

### 25.12.66 **secant**

Synopsis: Calculate `secant`

Declaration: `function secant(x: float) : float`

Visibility: default

Description: `Secant` calculates the `secant` ( $1/\cos(x)$ ) of its argument `x`.

Errors: If 90 or 270 degrees is specified, an exception will be raised.

See also: `cosecant` ([747](#))

### 25.12.67 **SetExceptionMask**

Synopsis: Set the Floating Point Unit exception mask.

Declaration: `function SetExceptionMask(const Mask: TFPUEExceptionMask)  
: TFPUEExceptionMask`

Visibility: default

Description: Set the Floating Point Unit exception mask.

### 25.12.68 **SetPrecisionMode**

Synopsis: Set the Floating Point Unit precision mode.

Declaration: `function SetPrecisionMode(const Precision: TFPUPrecisionMode)  
: TFPUPrecisionMode`

Visibility: default

Description: Set the Floating Point Unit precision mode.

### 25.12.69 **SetRoundMode**

Synopsis: Set the Floating Point Unit rounding mode.

Declaration: `function SetRoundMode(const RoundMode: TFPURoundingMode)  
: TFPURoundingMode`

Visibility: default

Description: Set the Floating Point Unit rounding mode.

### 25.12.70 Sign

Synopsis: Return sign of argument

Declaration: `function Sign(const AValue: Integer) : TValueSign; Overload`  
`function Sign(const AValue: Int64) : TValueSign; Overload`  
`function Sign(const AValue: Double) : TValueSign; Overload`  
`function Sign(const AValue: Extended) : TValueSign; Overload`

Visibility: default

Description: `Sign` returns the sign of it's argument, which can be an Integer, 64 bit integer, or a double. The returned value is an integer which is -1, 0 or 1, and can be used to do further calculations with.

### 25.12.71 SimpleRoundTo

Synopsis: Round to the specified number of digits (rounding up if needed)

Declaration: `function SimpleRoundTo(const AValue: Extended;`  
`const Digits: TRoundToRange) : Extended`

Visibility: default

Description: `SimpleRoundTo` rounds the specified float `AValue` to the specified number of digits, but rounds up, and returns the result. This result is accurate to "10 to the power Digits". It uses the standard `Round` function for this.

See also: `TRoundToRange` ([741](#)), `RoundTo` ([771](#))

### 25.12.72 sincos

Synopsis: Return sine and cosine of argument

Declaration: `procedure sincos(theta: float; out sinus: float; out cosinus: float)`

Visibility: default

Description: `Sincos` calculates the sine and cosine of the angle `theta`, and returns the result in `sinus` and `cosinus`.

On Intel hardware, This calculation will be faster than making 2 calls to calculate the sine and cosine separately.

Errors: None.

See also: `arcsin` ([743](#)), `arccos` ([742](#))

**Listing:** `./mathex/ex41.pp`

---

**Program** `Example41;`

*{ Program to demonstrate the sincos function. }*

**Uses** `math;`

**Procedure** `dosincos(Angle : Float);`

**Var**

`Sine, Cosine : Float;`

---

```

begin
  sincos(angle,sine,cosine);
  Write('Angle : ',Angle:8:6);
  Write(' Sine : ',sine:8:6);
  Write(' Cosine : ',cosine:8:6);
end;

begin
  dosincos(pi);
  dosincos(pi/2);
  dosincos(pi/3);
  dosincos(pi/4);
  dosincos(pi/6);
end.

```

---

### 25.12.73 sinh

Synopsis: Return hyperbolic sine

Declaration: `function sinh(x: float) : float`

Visibility: default

Description: `Sinh` returns the hyperbolic sine of its argument `x`.

Errors:

See also: `cosh` (747), `arsinh` (745), `tanh` (778), `artanh` (745)

**Listing:** `./mathex/ex42.pp`

---

**Program** Example42;

*{ Program to demonstrate the sinh function. }*

**Uses** math;

```

begin
  writeln(sinh(0));
  writeln(sinh(1));
  writeln(sinh(-1));
end.

```

---

### 25.12.74 stddev

Synopsis: Return standard deviation of data

Declaration: `function stddev(const data: Array of Extended) : float`  
`function stddev(const data: PExtended;const N: Integer) : float`

Visibility: default

Description: `Stddev` returns the standard deviation of the values in `Data`. It returns zero if there is only one value.

The second form of the function accepts a pointer to an array of `N` values.



Errors: None.

See also: mean ([761](#)), meanandstddev ([762](#)), variance ([779](#)), totalvariance ([778](#))

**Listing:** ./mathex/ex43.pp

---

**Program** Example40;

*{ Program to demonstrate the stddev function. }*

**Uses** Math;

**Var**

  I : Integer;  
  ExArray : **Array**[1..10000] of Float;

**begin**

**Randomize**;

**for** I:=**low**(ExArray) **to high**(ExArray) **do**

    ExArray[I]:=Randg(1,0.2);

**WriteIn**( 'StdDev       : ', StdDev(ExArray):8:4);

**WriteIn**( 'StdDev (b) : ', StdDev(@ExArray[0],10000):8:4);

**end.**

---

### 25.12.75 sum

Synopsis: Return sum of values

**Declaration:** function sum(const data: Array of Extended) : float  
                  function sum(const data: PExtended;const N: LongInt) : float

Visibility: default

**Description:** Sum returns the sum of the values in the data array.

The second form of the function accepts a pointer to an array of N values.

Errors: None.

See also: sumofsquares ([776](#)), sumsandsquares ([777](#)), totalvariance ([778](#)), variance ([779](#))

**Listing:** ./mathex/ex44.pp

---

**Program** Example44;

*{ Program to demonstrate the Sum function. }*

**Uses** math;

**Var**

  I : 1..100;  
  ExArray : **Array**[1..100] of Float;

**begin**

**Randomize**;

**for** I:=**low**(ExArray) **to high**(ExArray) **do**

    ExArray[I]:=(**Random-Random**)\*100;

**WriteIn**( 'Max       : ', MaxValue(ExArray):8:4);

---

```

Writeln ( 'Min      : ', MinValue ( ExArray ) : 8 : 4 );
Writeln ( 'Sum      : ', Sum ( ExArray ) : 8 : 4 );
Writeln ( 'Sum (b) : ', Sum (@ExArray[1], 100) : 8 : 4 );
end.

```

---

### 25.12.76 sumInt

Synopsis: Return the sum of an array of integers

Declaration: `function sumInt(const data: PInt64; const N: LongInt) : Int64`  
`function sumInt(const data: Array of Int64) : Int64`

Visibility: default

Description: `SumInt` returns the sum of the `N` integers in the `Data` array, where this can be an open array or a pointer to an array.

Errors: An overflow may occur.

### 25.12.77 sumofsquares

Synopsis: Return sum of squares of values

Declaration: `function sumofsquares(const data: Array of Extended) : float`  
`function sumofsquares(const data: PExtended; const N: Integer) : float`

Visibility: default

Description: `Sumofsquares` returns the sum of the squares of the values in the `data` array.

The second form of the function accepts a pointer to an array of `N` values.

Errors: None.

See also: `sum` (775), `sumsandsquares` (777), `totalvariance` (778), `variance` (779)

**Listing:** `./mathex/ex45.pp`

---

**Program** Example45;

*{ Program to demonstrate the SumOfSquares function. }*

**Uses** math;

**Var**

`I : 1..100;`  
`ExArray : Array[1..100] of Float;`

**begin**

`Randomize;`

`for I := low(ExArray) to high(ExArray) do`

`ExArray[I] := (Random - Random) * 100;`

`Writeln` ( 'Max : ', MaxValue ( ExArray ) : 8 : 4 );

`Writeln` ( 'Min : ', MinValue ( ExArray ) : 8 : 4 );

`Writeln` ( 'Sum squares : ', SumOfSquares ( ExArray ) : 8 : 4 );

`Writeln` ( 'Sum squares (b) : ', SumOfSquares (@ExArray[1], 100) : 8 : 4 );

**end.**

---

**25.12.78 sumsandsquares**

Synopsis: Return sum and sum of squares of values.

Declaration: `procedure sumsandsquares(const data: Array of Extended; var sum: float;  
var sumofsquares: float)  
procedure sumsandsquares(const data: PExtended; const N: Integer;  
var sum: float; var sumofsquares: float)`

Visibility: default

Description: `sumsandsquares` calculates the sum of the values and the sum of the squares of the values in the `data` array and returns the results in `sum` and `sumofsquares`.

The second form of the function accepts a pointer to an array of `N` values.

Errors: None.

See also: `sum` (775), `sumofsquares` (776), `totalvariance` (778), `variance` (779)

**Listing:** `./mathex/ex46.pp`

**Program** Example45;

*{ Program to demonstrate the SumOfSquares function. }*

**Uses** math;

**Var**

`l : 1..100;  
ExArray : Array[1..100] of Float  
s,ss : float;`

**begin**

`Randomize;  
for l:=low(ExArray) to high(ExArray) do  
ExArray[l]:=(Random-Random)*100;  
WriteLn('Max : ',MaxValue(ExArray):8:4);  
WriteLn('Min : ',MinValue(ExArray):8:4);  
SumsAndSquares(ExArray,S,SS);  
WriteLn('Sum : ',S:8:4);  
WriteLn('Sum squares : ',SS:8:4);  
SumsAndSquares(@ExArray[1],100,S,SS);  
WriteLn('Sum (b) : ',S:8:4);  
WriteLn('Sum squares (b) : ',SS:8:4);`

**end.**

**25.12.79 tan**

Synopsis: Return tangent

Declaration: `function tan(x: float) : float`

Visibility: default

Description: `Tan` returns the tangent of `x`. The argument `x` must be in radians.

Errors: If `x` (normalized) is `pi/2` or `3pi/2` then an overflow will occur.

See also: `tanh` (778), `arcsin` (743), `sincos` (773), `arccos` (742)

**Listing:** ./mathex/ex47.pp

---

**Program** Example47;

*{ Program to demonstrate the Tan function. }*

**Uses** math;

**Procedure** DoTan(Angle : Float);

**begin**

**Write**( 'Angle : ', RadToDeg(Angle):8:6);

**WriteLn**( ' Tangent : ', Tan(Angle):8:6);

**end**;

**begin**

    DoTan(0);

    DoTan(**Pi**);

    DoTan(**Pi**/3);

    DoTan(**Pi**/4);

    DoTan(**Pi**/6);

**end**.

---

### 25.12.80 tanh

Synopsis: Return hyperbolic tangent

Declaration: `function tanh(x: float) : float`

Visibility: default

Description: Tanh returns the hyperbolic tangent of x.

Errors: None.

See also: arcsin ([743](#)), sincos ([773](#)), arccos ([742](#))

**Listing:** ./mathex/ex48.pp

---

**Program** Example48;

*{ Program to demonstrate the Tanh function. }*

**Uses** math;

**begin**

**writeln**(tanh(0));

**writeln**(tanh(1));

**writeln**(tanh(-1));

**end**.

---

### 25.12.81 totalvariance

Synopsis: Return total variance of values

Declaration: `function totalvariance(const data: Array of Extended) : float`

`function totalvariance(const data: PExtended; const N: Integer) : float`

Visibility: default

**Description:** `TotalVariance` returns the total variance of the values in the `data` array. It returns zero if there is only one value.

The second form of the function accepts a pointer to an array of `N` values.

Errors: None.

See also: `variance` (779), `stddev` (774), `mean` (761)

**Listing:** `./mathex/ex49.pp`

---

**Program** `Example49`;

*{ Program to demonstrate the TotalVariance function. }*

**Uses** `math`;

**Type**

`TExArray = Array[1..100] of Float`;

**Var**

`I : Integer`;

`ExArray : TExArray`;

`TV : float`;

**begin**

`Randomize`;

**for** `I:=1 to 100 do`

`ExArray[I] := (Random-Random)*100`;

`TV := TotalVariance(ExArray)`;

`WriteIn('Total variance : ',TV:8:4)`;

`TV := TotalVariance(@ExArray[1],100)`;

`WriteIn('Total Variance (b) : ',TV:8:4)`;

**end.**

---

### 25.12.82 variance

Synopsis: Return variance of values

**Declaration:** `function variance(const data: Array of Extended) : float`  
`function variance(const data: PExtended;const N: Integer) : float`

Visibility: default

**Description:** `Variance` returns the variance of the values in the `data` array. It returns zero if there is only one value.

The second form of the function accepts a pointer to an array of `N` values.

Errors: None.

See also: `totalvariance` (778), `stddev` (774), `mean` (761)

**Listing:** `./mathex/ex50.pp`

---

**Program** Example50;

*{ Program to demonstrate the Variance function. }*

**Uses** math;

**Var**

  I : 1..100;

  ExArray : **Array**[1..100] **of** Float;

  V : float;

**begin**

**Randomize**;

**for** I:=**low**(ExArray) **to high**(ExArray) **do**

    ExArray[I]:=(**Random-Random**)\*100;

  V:=Variance(ExArray);

**WriteIn**( 'Variance       : ',V:8:4);

  V:=Variance(@ExArray[1],100);

**WriteIn**( 'Variance (b) : ',V:8:4);

**end.**

---

## 25.13 EInvalidArgument

### 25.13.1 Description

Exception raised when invalid arguments are passed to a function.

## Chapter 26

# Reference for unit 'matrix'

### 26.1 Overview

The unit `matrix` is a unit that provides objects for the common two, three and four dimensional vectors matrixes. These vectors and matrixes are very common in computer graphics and are often implemented from scratch by programmers while every implementation provides exactly the same functionality.

It makes therefore sense to provide this functionality in the runtime library. This eliminates the need for programmers to reinvent the wheel and also allows libraries that use matrix operations to become more compatible.

The matrix unit does not provide n-dimensional matrixes. The functionality needs of a general matrix unit varies from application to application; one can think of reduced memory usage tricks for matrixes that only have data around the diagonal etc., desire for parallelization etc. etc. It is believed that programmers that do use n-dimensional matrices would not necessarily benefit from such a unit in the runtime library.

Design goals:

- Provide common dimensions, two three and four.
- Provide multiple floating point precisions, single, double, extended.
- Simple trivial binary representation; it is possible to typecast vectors into other implementations that use the same trivial representation.
- No dynamic memory management in the background. It must be possible to write expressions like `matrix A * B * C` without worrying about memory management.

Design decisions:

- Class object model is ruled out. The objects object model, without virtual methods, is suitable.
- Operator overloading is a good way to allow programmers to write matrix expressions.
- 3 dimensions \* 3 precision means 9 vector and 9 matrix objects. Macro's have been used in the source to take care of this.

## 26.2 Constants, types and variables

### 26.2.1 Types

```
Tmatrix2_double_data = Array[0..1,0..1] of double
```

This is the matrix internal data for a matrix. It uses a simple array structure so data from other libraries that define their own matrix type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tmatrix2_extended_data = Array[0..1,0..1] of extended
```

This is the matrix internal data for a matrix. It uses a simple array structure so data from other libraries that define their own matrix type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tmatrix2_single_data = Array[0..1,0..1] of single
```

This is the matrix internal data for a matrix. It uses a simple array structure so data from other libraries that define their own matrix type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tmatrix3_double_data = Array[0..2,0..2] of double
```

This is the matrix internal data for a matrix. It uses a simple array structure so data from other libraries that define their own matrix type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tmatrix3_extended_data = Array[0..2,0..2] of extended
```

This is the matrix internal data for a matrix. It uses a simple array structure so data from other libraries that define their own matrix type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tmatrix3_single_data = Array[0..2,0..2] of single
```

This is the matrix internal data for a matrix. It uses a simple array structure so data from other libraries that define their own matrix type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tmatrix4_double_data = Array[0..3,0..3] of double
```

This is the matrix internal data for a matrix. It uses a simple array structure so data from other libraries that define their own matrix type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.



```
Tmatrix4_extended_data = Array[0..3,0..3] of extended
```

This is the matrix internal data for a matrix. It uses a simple array structure so data from other libraries that define their own matrix type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tmatrix4_single_data = Array[0..3,0..3] of single
```

This is the matrix internal data for a matrix. It uses a simple array structure so data from other libraries that define their own matrix type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tvector2_double_data = Array[0..1] of double
```

This is the vector internal data for a vector. It uses a simple array structure so data from other libraries that define their own vector type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tvector2_extended_data = Array[0..1] of extended
```

This is the vector internal data for a vector. It uses a simple array structure so data from other libraries that define their own vector type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tvector2_single_data = Array[0..1] of single
```

This is the vector internal data for a vector. It uses a simple array structure so data from other libraries that define their own vector type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tvector3_double_data = Array[0..2] of double
```

This is the vector internal data for a vector. It uses a simple array structure so data from other libraries that define their own vector type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tvector3_extended_data = Array[0..2] of extended
```

This is the vector internal data for a vector. It uses a simple array structure so data from other libraries that define their own vector type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tvector3_single_data = Array[0..2] of single
```

This is the vector internal data for a vector. It uses a simple array structure so data from other libraries that define their own vector type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tvector4_double_data = Array[0..3] of double
```

This is the vector internal data for a vector. It uses a simple array structure so data from other libraries that define their own vector type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tvector4_extended_data = Array[0..3] of extended
```

This is the vector internal data for a vector. It uses a simple array structure so data from other libraries that define their own vector type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tvector4_single_data = Array[0..3] of single
```

This is the vector internal data for a vector. It uses a simple array structure so data from other libraries that define their own vector type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

## 26.3 Procedures and functions

### 26.3.1 operator \*(Tmatrix2\_double, double): Tmatrix2\_double

Synopsis: Multiply a two-dimensional double precision matrix by a scalar

Declaration: `operator operator *(Tmatrix2_double, double): Tmatrix2_double`

```
(const m: Tmatrix2_double,
const x: double)
: Tmatrix2_double
```

Visibility: default

Description: This operator allows you to multiply a matrix with a scalar. All elements in the matrix are multiplied by the scalar, the result is returned as a new matrix.

### 26.3.2 operator \*(Tmatrix2\_double, Tmatrix2\_double): Tmatrix2\_double

Synopsis: Give product of two two-dimensional double precision matrices

Declaration: `operator operator *(Tmatrix2_double, Tmatrix2_double): Tmatrix2_double`

```
(const m1: Tmatrix2_double,
const m2: Tmatrix2_double)
: Tmatrix2_double
```

Visibility: default

Description: This operator allows you to multiply two two-dimensional single precision matrices. A new matrix is returned which is the product of both matrices. The product is calculated using the well known matrix multiplication algorithm.

**26.3.3 operator\*(Tmatrix2\_double, Tvector2\_double): Tvector2\_double**

Synopsis: Give product of a two-dimensional double precision matrix and vector

Declaration: `operator operator *(Tmatrix2_double, Tvector2_double): Tvector2_double`

```
(const m: Tmatrix2_double,
const v: Tvector2_double)
: Tvector2_double
```

Visibility: default

Description: This operator allows you to multiply a two-dimensional double precision matrices with a two dimensional double precision vector. A new vector is returned which is the product of the matrix and the vector. The product is calculated using the well known matrix-vector multiplication algorithm.

**26.3.4 operator\*(Tmatrix2\_extended, extended): Tmatrix2\_extended**

Synopsis: Multiply a two-dimensional extended precision matrix by a scalar

Declaration: `operator operator *(Tmatrix2_extended, extended): Tmatrix2_extended`

```
(const m: Tmatrix2_extended,
const x: extended)
: Tmatrix2_extended
```

Visibility: default

Description: This operator allows you to multiply a matrix with a scalar. All elements in the matrix are multiplied by the scalar, the result is returned as a new matrix.

**26.3.5 operator\*(Tmatrix2\_extended, Tmatrix2\_extended): Tmatrix2\_extended**

Synopsis: Give product of two two-dimensional extended precision matrices

Declaration:

```
operator operator *(
(const m1: Tmatrix2_extended,
const m2: Tmatrix2_extended)
: Tmatrix2_extended
```

Visibility: default

Description: This operator allows you to multiply two two-dimensional single precision matrices. A new matrix is returned which is the product of both matrices. The product is calculated using the well known matrix multiplication algorithm.

**26.3.6 operator\*(Tmatrix2\_extended, Tvector2\_extended): Tvector2\_extended**

Synopsis: Give product of a two-dimensional extended precision matrix and vector

Declaration:

```
operator operator *(
(const m: Tmatrix2_extended,
const v: Tvector2_extended)
: Tvector2_extended
```

Visibility: default

**Description:** This operator allows you to multiply a two-dimensional extended precision matrices with a two dimensional extended precision vector. A new vector is returned which is the product of the matrix and the vector. The product is calculated using the well known matrix-vector multiplication algorithm.

### 26.3.7 operator \*(Tmatrix2\_single, single): Tmatrix2\_single

**Synopsis:** Multiply a two-dimensional single precision matrix by a scalar

**Declaration:** `operator operator *(Tmatrix2_single, single): Tmatrix2_single`

```
(const m: Tmatrix2_single)
const x: single)
: Tmatrix2_single
```

**Visibility:** default

**Description:** This operator allows you to multiply a matrix with a scalar. All elements in the matrix are multiplied by the scalar, the result is returned as a new matrix.

### 26.3.8 operator \*(Tmatrix2\_single, Tmatrix2\_single): Tmatrix2\_single

**Synopsis:** Give product of two two-dimensional single precision matrices

**Declaration:** `operator operator *(Tmatrix2_single, Tmatrix2_single): Tmatrix2_single`

```
(const m1: Tmatrix2_single)
const m2: Tmatrix2_single)
: Tmatrix2_single
```

**Visibility:** default

**Description:** This operator allows you to multiply two two-dimensional single precision matrices. A new matrix is returned which is the product of both matrices. The product is calculated using the well known matrix multiplication algorithm.

### 26.3.9 operator \*(Tmatrix2\_single, Tvector2\_single): Tvector2\_single

**Synopsis:** Give product of a two-dimensional single precision matrix and vector

**Declaration:** `operator operator *(Tmatrix2_single, Tvector2_single): Tvector2_single`

```
(const m: Tmatrix2_single)
const v: Tvector2_single)
: Tvector2_single
```

**Visibility:** default

**Description:** This operator allows you to multiply a two-dimensional single precision matrices with a two dimensional single precision vector. A new vector is returned which is the product of the matrix and the vector. The product is calculated using the well known matrix-vector multiplication algorithm.

### 26.3.10 operator \*(Tmatrix3\_double, double): Tmatrix3\_double

**Synopsis:** Multiply a three-dimensional double precision matrix by a scalar

**Declaration:** `operator operator *(Tmatrix3_double, double): Tmatrix3_double`

```
(const m: Tmatrix3_double)
const x: double)
: Tmatrix3_double
```

Visibility: default

Description: This operator allows you to multiply a matrix with a scalar. All elements in the matrix are multiplied by the scalar, the result is returned as a new matrix.

### 26.3.11 operator\*(Tmatrix3\_double, Tmatrix3\_double): Tmatrix3\_double

Synopsis: Give product of two three-dimensional double precision matrices

Declaration: `operator operator *(Tmatrix3_double, Tmatrix3_double): Tmatrix3_double`

```
(const m1: Tmatrix3_double,
const m2: Tmatrix3_double)
: Tmatrix3_double
```

Visibility: default

Description: This operator allows you to multiply two two-dimensional single precision matrices. A new matrix is returned which is the product of both matrices. The product is calculated using the well known matrix multiplication algorithm.

### 26.3.12 operator\*(Tmatrix3\_double, Tvector3\_double): Tvector3\_double

Synopsis: Give product of a three-dimensional double precision matrix and vector

Declaration: `operator operator *(Tmatrix3_double, Tvector3_double): Tvector3_double`

```
(const m: Tmatrix3_double,
const v: Tvector3_double)
: Tvector3_double
```

Visibility: default

Description: This operator allows you to multiply a three-dimensional double precision matrices with a three dimensional double precision vector. A new vector is returned which is the product of the matrix and the vector. The product is calculated using the well known matrix-vector multiplication algorithm.

### 26.3.13 operator\*(Tmatrix3\_extended, extended): Tmatrix3\_extended

Synopsis: Multiply a three-dimensional extended precision matrix by a scalar

Declaration: `operator operator *(Tmatrix3_extended, extended): Tmatrix3_extended`

```
(const m: Tmatrix3_extended,
const x: extended)
: Tmatrix3_extended
```

Visibility: default

Description: This operator allows you to multiply a matrix with a scalar. All elements in the matrix are multiplied by the scalar, the result is returned as a new matrix.

### 26.3.14 operator\*(Tmatrix3\_extended, Tmatrix3\_extended): Tmatrix3\_extended

Synopsis: Give product of two three-dimensional extended precision matrices

Declaration:

```
operator
(const m
const m2
: Tmatr
```

Visibility: default

Description: This operator allows you to multiply two two-dimensional single precision matrices. A new matrix is returned which is the product of both matrices. The product is calculated using the well known matrix multiplication algorithm.

### 26.3.15 operator\*(Tmatrix3\_extended, Tvector3\_extended): Tvector3\_extended

Synopsis: Give product of a three-dimendional extended precision matrix and vector

Declaration:

```
operator
(const m
const v:
: Tvect
```

Visibility: default

Description: This operator allows you to multiply a three-dimensional extended precision matrices with a three dimensional extended precision vector. A new vector is returned which is the product of the matrix and the vector. The product is calculated using the well known matrix-vector multiplication algorithm.

### 26.3.16 operator\*(Tmatrix3\_single, single): Tmatrix3\_single

Synopsis: Multiply a three-dimensional single precision matrix by a scalar

Declaration: `operator operator *(Tmatrix3_single, single): Tmatrix3_single`

```
(const m: Tmatrix3_sing
const x: single)
: Tmatrix3_single
```

Visibility: default

Description: This operator allows you to multiply a matrix with a scalar. All elements in the matrix are multiplied by the scalar, the result is returned as a new matrix.

### 26.3.17 operator\*(Tmatrix3\_single, Tmatrix3\_single): Tmatrix3\_single

Synopsis: Give product of two three-dimensional single precision matrices

Declaration: `operator operator *(Tmatrix3_single, Tmatrix3_single): Tmatrix3_single`

```
(const m1: Tma
const m2: Tmat
: Tmatrix3_si
```

Visibility: default

Description: This operator allows you to multiply two two-dimensional single precision matrices. A new matrix is returned which is the product of both matrices. The product is calculated using the well known matrix multiplication algorithm.

**26.3.18 operator\*(Tmatrix3\_single, Tvector3\_single): Tvector3\_single**

Synopsis: Give product of a three-dimendional single precision matrix and vector

Declaration: `operator operator *(Tmatrix3_single, Tvector3_single): Tvector3_single`

```
(const m: Tmat
const v: Tvect
: Tvector3_si
```

Visibility: default

Description: This operator allows you to multiply a three-dimensional single precision matrices with a three dimensional single precision vector. A new vector is returned which is the product of the matrix and the vector. The product is calculated using the well known matrix-vector multiplication algorithm.

**26.3.19 operator\*(Tmatrix4\_double, double): Tmatrix4\_double**

Synopsis: Multiply a four-dimensional double precision matrix by a scalar

Declaration: `operator operator *(Tmatrix4_double, double): Tmatrix4_double`

```
(const m: Tmatrix4_doub
const x: double)
: Tmatrix4_double
```

Visibility: default

Description: This operator allows you to multiply a matrix with a scalar. All elements in the matrix are multiplied by the scalar, the result is returned as a new matrix.

**26.3.20 operator\*(Tmatrix4\_double, Tmatrix4\_double): Tmatrix4\_double**

Synopsis: Give product of two four-dimensional double precision matrices

Declaration: `operator operator *(Tmatrix4_double, Tmatrix4_double): Tmatrix4_double`

```
(const m1: Tmat
const m2: Tmat
: Tmatrix4_do
```

Visibility: default

Description: This operator allows you to multiply two two-dimensional single precision matrices. A new matrix is returned which is the product of both matrices. The product is calculated using the well known matrix multiplication algorithm.

**26.3.21 operator\*(Tmatrix4\_double, Tvector4\_double): Tvector4\_double**

Synopsis: Give product of a four-dimendional double precision matrix and vector

Declaration: `operator operator *(Tmatrix4_double, Tvector4_double): Tvector4_double`

```
(const m: Tmat
const v: Tvect
: Tvector4_do
```

Visibility: default

Description: This operator allows you to multiply a four-dimensional double precision matrices with a four dimensional double precision vector. A new vector is returned which is the product of the matrix and the vector. The product is calculated using the well known matrix-vector multiplication algorithm.

**26.3.22 operator\*(Tmatrix4\_extended, extended): Tmatrix4\_extended**

Synopsis: Multiply a four-dimensional extended precision matrix by a scalar

Declaration: `operator operator *(Tmatrix4_extended, extended): Tmatrix4_extended`

```
(const m: Tmatrix4_extended,
const x: extended)
: Tmatrix4_extended
```

Visibility: default

Description: This operator allows you to multiply a matrix with a scalar. All elements in the matrix are multiplied by the scalar, the result is returned as a new matrix.

**26.3.23 operator\*(Tmatrix4\_extended, Tmatrix4\_extended): Tmatrix4\_extended**

Synopsis: Give product of two four-dimensional extended precision matrices

Declaration:

```
operator operator *(Tmatrix4_extended, Tmatrix4_extended)
: Tmatrix4_extended
```

Visibility: default

Description: This operator allows you to multiply two two-dimensional single precision matrices. A new matrix is returned which is the product of both matrices. The product is calculated using the well known matrix multiplication algorithm.

**26.3.24 operator\*(Tmatrix4\_extended, Tvector4\_extended): Tvector4\_extended**

Synopsis: Give product of a four-dimendional extended precision matrix and vector

Declaration:

```
operator operator *(Tmatrix4_extended, Tvector4_extended)
: Tvector4_extended
```

Visibility: default

Description: This operator allows you to multiply a four-dimensional extended precision matrices with a four dimensional extended precision vector. A new vector is returned which is the product of the matrix and the vector. The product is calculated using the well known matrix-vector multiplication algorithm.

**26.3.25 operator\*(Tmatrix4\_single, single): Tmatrix4\_single**

Synopsis: Multiply a four-dimensional single precision matrix by a scalar

Declaration: `operator operator *(Tmatrix4_single, single): Tmatrix4_single`

```
(const m: Tmatrix4_single,
const x: single)
: Tmatrix4_single
```

Visibility: default



Description: This operator allows you to multiply a matrix with a scalar. All elements in the matrix are multiplied by the scalar, the result is returned as a new matrix.

### 26.3.26 operator \*(Tmatrix4\_single, Tmatrix4\_single): Tmatrix4\_single

Synopsis: Give product of two four-dimensional single precision matrices

Declaration: `operator operator *(Tmatrix4_single, Tmatrix4_single): Tmatrix4_single`

```
(const m1: Tmatrix4_single,
const m2: Tmatrix4_single)
: Tmatrix4_single
```

Visibility: default

Description: This operator allows you to multiply two two-dimensional single precision matrices. A new matrix is returned which is the product of both matrices. The product is calculated using the well known matrix multiplication algorithm.

### 26.3.27 operator \*(Tmatrix4\_single, Tvector4\_single): Tvector4\_single

Synopsis: Give product of a four-dimensional single precision matrix and vector

Declaration: `operator operator *(Tmatrix4_single, Tvector4_single): Tvector4_single`

```
(const m: Tmatrix4_single,
const v: Tvector4_single)
: Tvector4_single
```

Visibility: default

Description: This operator allows you to multiply a four-dimensional single precision matrices with a four dimensional single precision vector. A new vector is returned which is the product of the matrix and the vector. The product is calculated using the well known matrix-vector multiplication algorithm.

### 26.3.28 operator \*(Tvector2\_double, double): Tvector2\_double

Synopsis: Multiply a two-dimensional double precision vector by a scalar

Declaration: `operator operator *(Tvector2_double, double): Tvector2_double`

```
(const x: Tvector2_double,
y: double)
: Tvector2_double
```

Visibility: default

Description: This operator allows you to multiply a vector by a scalar value. Each vector element is multiplied by the scalar value; the result is returned as a new vector.

### 26.3.29 operator \*(Tvector2\_double, Tvector2\_double): Tvector2\_double

Synopsis: Multiply two vectors element wise

Declaration: `operator operator *(Tvector2_double, Tvector2_double): Tvector2_double`

```
(const x: Tvector2_double,
const y: Tvector2_double)
: Tvector2_double
```

Visibility: default

Description: This operator returns a vector that contains the element by element multiplication of the two multiplied vectors.

### 26.3.30 operator \*(Tvector2\_extended, extended): Tvector2\_extended

Synopsis: Multiply a two-dimensional extended precision vector by a scalar

Declaration: `operator operator *(Tvector2_extended, extended): Tvector2_extended`

```
(const x: Tvector2_extended,
y: extended)
: Tvector2_extended
```

Visibility: default

Description: This operator allows you to multiply a vector by a scalar value. Each vector element is multiplied by the scalar value; the result is returned as a new vector.

### 26.3.31 operator \*(Tvector2\_extended, Tvector2\_extended): Tvector2\_extended

Synopsis: Multiply two vectors element wise

Declaration:

```
operator operator *(Tvector2_extended, Tvector2_extended): Tvector2_extended
(const x: Tvector2_extended,
const y: Tvector2_extended)
: Tvector2_extended
```

Visibility: default

Description: This operator returns a vector that contains the element by element multiplication of the two multiplied vectors.

### 26.3.32 operator \*(Tvector2\_single, single): Tvector2\_single

Synopsis: Multiply a two-dimensional single precision vector by a scalar

Declaration: `operator operator *(Tvector2_single, single): Tvector2_single`

```
(const x: Tvector2_single,
y: single)
: Tvector2_single
```

Visibility: default

Description: This operator allows you to multiply a vector by a scalar value. Each vector element is multiplied by the scalar value; the result is returned as a new vector.

### 26.3.33 operator \*(Tvector2\_single, Tvector2\_single): Tvector2\_single

Synopsis: Multiply two vectors element wise

Declaration: `operator operator *(Tvector2_single, Tvector2_single): Tvector2_single`

```
(const x: Tvector2_single,
const y: Tvector2_single)
: Tvector2_single
```

Visibility: default

Description: This operator returns a vector that contains the element by element multiplication of the two multiplied vectors.

### 26.3.34 operator \*(Tvector3\_double, double): Tvector3\_double

Synopsis: Multiply a three-dimensional double precision vector by a scalar

Declaration: `operator operator *(Tvector3_double, double): Tvector3_double`  
`(const x: Tvector3_double, y: double): Tvector3_double`

Visibility: default

Description: This operator allows you to multiply a vector by a scalar value. Each vector element is multiplied by the scalar value; the result is returned as a new vector.

### 26.3.35 operator \*(Tvector3\_double, Tvector3\_double): Tvector3\_double

Synopsis: Multiply two vectors element wise

Declaration: `operator operator *(Tvector3_double, Tvector3_double): Tvector3_double`  
`(const x: Tvector3_double, const y: Tvector3_double): Tvector3_double`

Visibility: default

Description: This operator returns a vector that contains the element by element multiplication of the two multiplied vectors.

### 26.3.36 operator \*(Tvector3\_extended, extended): Tvector3\_extended

Synopsis: Multiply a three-dimensional extended precision vector by a scalar

Declaration: `operator operator *(Tvector3_extended, extended): Tvector3_extended`  
`(const x: Tvector3_extended, y: extended): Tvector3_extended`

Visibility: default

Description: This operator allows you to multiply a vector by a scalar value. Each vector element is multiplied by the scalar value; the result is returned as a new vector.

### 26.3.37 operator \*(Tvector3\_extended, Tvector3\_extended): Tvector3\_extended

Synopsis: Multiply two vectors element wise

Declaration: `operator operator *(Tvector3_extended, Tvector3_extended): Tvector3_extended`  
`(const x: Tvector3_extended, const y: Tvector3_extended): Tvector3_extended`

Visibility: default

Description: This operator returns a vector that contains the element by element multiplication of the two multiplied vectors.

### 26.3.38 operator \*(Tvector3\_single, single): Tvector3\_single

Synopsis: Multiply a three-dimensional single precision vector by a scalar

Declaration: `operator operator *(Tvector3_single, single): Tvector3_single`

```
(const x: Tvector3_single,
 y: single)
: Tvector3_single
```

Visibility: default

Description: This operator allows you to multiply a vector by a scalar value. Each vector element is multiplied by the scalar value; the result is returned as a new vector.

### 26.3.39 operator \*(Tvector3\_single, Tvector3\_single): Tvector3\_single

Synopsis: Multiply two vectors element wise

Declaration: `operator operator *(Tvector3_single, Tvector3_single): Tvector3_single`

```
(const x: Tvector3_single,
 const y: Tvector3_single)
: Tvector3_single
```

Visibility: default

Description: This operator returns a vector that contains the element by element multiplication of the two multiplied vectors.

### 26.3.40 operator \*(Tvector4\_double, double): Tvector4\_double

Synopsis: Multiply a four-dimensional double precision vector by a scalar

Declaration: `operator operator *(Tvector4_double, double): Tvector4_double`

```
(const x: Tvector4_double,
 y: double)
: Tvector4_double
```

Visibility: default

Description: This operator allows you to multiply a vector by a scalar value. Each vector element is multiplied by the scalar value; the result is returned as a new vector.

### 26.3.41 operator \*(Tvector4\_double, Tvector4\_double): Tvector4\_double

Synopsis: Multiply two vectors element wise

Declaration: `operator operator *(Tvector4_double, Tvector4_double): Tvector4_double`

```
(const x: Tvector4_double,
 const y: Tvector4_double)
: Tvector4_double
```

Visibility: default

Description: This operator returns a vector that contains the element by element multiplication of the two multiplied vectors.

### 26.3.42 operator \*(Tvector4\_extended, extended): Tvector4\_extended

Synopsis: Multiply a four-dimensional extended precision vector by a scalar

Declaration: `operator operator *(Tvector4_extended, extended): Tvector4_extended`

```
(const x: Tvector4_extended,
y: extended)
: Tvector4_extended
```

Visibility: default

Description: This operator allows you to multiply a vector by a scalar value. Each vector element is multiplied by the scalar value; the result is returned as a new vector.

### 26.3.43 operator \*(Tvector4\_extended, Tvector4\_extended): Tvector4\_extended

Synopsis: Multiply two vectors element wise

Declaration:

```
operator operator *(Tvector4_extended, Tvector4_extended): Tvector4_extended
(const x: Tvector4_extended,
const y: Tvector4_extended)
: Tvector4_extended
```

Visibility: default

Description: This operator returns a vector that contains the element by element multiplication of the two multiplied vectors.

### 26.3.44 operator \*(Tvector4\_single, single): Tvector4\_single

Synopsis: Multiply a four-dimensional single precision vector by a scalar

Declaration: `operator operator *(Tvector4_single, single): Tvector4_single`

```
(const x: Tvector4_single,
y: single)
: Tvector4_single
```

Visibility: default

Description: This operator allows you to multiply a vector by a scalar value. Each vector element is multiplied by the scalar value; the result is returned as a new vector.

### 26.3.45 operator \*(Tvector4\_single, Tvector4\_single): Tvector4\_single

Synopsis: Multiply two vectors element wise

Declaration: `operator operator *(Tvector4_single, Tvector4_single): Tvector4_single`

```
(const x: Tvector4_single,
const y: Tvector4_single)
: Tvector4_single
```

Visibility: default

Description: This operator returns a vector that contains the element by element multiplication of the two multiplied vectors.

### 26.3.46 operator \*\*(Tvector2\_double, Tvector2\_double): double

Synopsis: Calculate the internal product of two vectors.

Declaration: `operator operator **(Tvector2_double, Tvector2_double): double`

```
(const x: Tvector2_double,
const y: Tvector2_double)
: double
```

Visibility: default

Description: This operator returns the internal product of the two vectors, that is, the elements of the two vectors are element-wise multiplied, and then added together.

### 26.3.47 operator \*\*(Tvector2\_extended, Tvector2\_extended): extended

Synopsis: Calculate the internal product of two vectors.

Declaration: `operator operator **(Tvector2_extended, Tvector2_extended): extended`

```
(const x: Tvector2_extended,
const y: Tvector2_extended)
: extended
```

Visibility: default

Description: This operator returns the internal product of the two vectors, that is, the elements of the two vectors are element-wise multiplied, and then added together.

### 26.3.48 operator \*\*(Tvector2\_single, Tvector2\_single): single

Synopsis: Calculate the internal product of two vectors.

Declaration: `operator operator **(Tvector2_single, Tvector2_single): single`

```
(const x: Tvector2_single,
const y: Tvector2_single)
: single
```

Visibility: default

Description: This operator returns the internal product of the two vectors, that is, the elements of the two vectors are element-wise multiplied, and then added together.

### 26.3.49 operator \*\*(Tvector3\_double, Tvector3\_double): double

Synopsis: Calculate the internal product of two vectors.

Declaration: `operator operator **(Tvector3_double, Tvector3_double): double`

```
(const x: Tvector3_double,
const y: Tvector3_double)
: double
```

Visibility: default

Description: This operator returns the internal product of the two vectors, that is, the elements of the two vectors are element-wise multiplied, and then added together.

### 26.3.50 operator \*\* (Tvector3\_extended, Tvector3\_extended): extended

Synopsis: Calculate the internal product of two vectors.

Declaration: `operator operator ** (Tvector3_extended, Tvector3_extended): extended`

```
(const x: Tvector3_extended,
const y: Tvector3_extended)
: extended
```

Visibility: default

Description: This operator returns the internal product of the two vectors, that is, the elements of the two vectors are element-wise multiplied, and then added together.

### 26.3.51 operator \*\* (Tvector3\_single, Tvector3\_single): single

Synopsis: Calculate the internal product of two vectors.

Declaration: `operator operator ** (Tvector3_single, Tvector3_single): single`

```
(const x: Tvector3_single,
const y: Tvector3_single)
: single
```

Visibility: default

Description: This operator returns the internal product of the two vectors, that is, the elements of the two vectors are element-wise multiplied, and then added together.

### 26.3.52 operator \*\* (Tvector4\_double, Tvector4\_double): double

Synopsis: Calculate the internal product of two vectors.

Declaration: `operator operator ** (Tvector4_double, Tvector4_double): double`

```
(const x: Tvector4_double,
const y: Tvector4_double)
: double
```

Visibility: default

Description: This operator returns the internal product of the two vectors, that is, the elements of the two vectors are element-wise multiplied, and then added together.

### 26.3.53 operator \*\* (Tvector4\_extended, Tvector4\_extended): extended

Synopsis: Calculate the internal product of two vectors.

Declaration: `operator operator ** (Tvector4_extended, Tvector4_extended): extended`

```
(const x: Tvector4_extended,
const y: Tvector4_extended)
: extended
```

Visibility: default

Description: This operator returns the internal product of the two vectors, that is, the elements of the two vectors are element-wise multiplied, and then added together.

### 26.3.54 operator **\*\*(Tvector4\_single, Tvector4\_single): single**

Synopsis: Calculate the internal product of two vectors.

Declaration: `operator operator **(Tvector4_single, Tvector4_single): single`

```
(const x: Tvector4_single,
const y: Tvector4_single)
: single
```

Visibility: default

Description: This operator returns the internal product of the two vectors, that is, the elements of the two vectors are element-wise multiplied, and then added together.

### 26.3.55 operator **+(Tmatrix2\_double, double): Tmatrix2\_double**

Synopsis: Add scalar to two-dimensional double precision matrix

Declaration: `operator operator +(Tmatrix2_double, double): Tmatrix2_double`

```
(const m: Tmatrix2_double,
const x: double)
: Tmatrix2_double
```

Visibility: default

Description: This operator allows you to add a scalar value to a matrix. The scalar is added to all elements of the matrix, the result is returned as a new vector.

### 26.3.56 operator **+(Tmatrix2\_double, Tmatrix2\_double): Tmatrix2\_double**

Synopsis: Add two two-dimensional double precision matrices together.

Declaration: `operator operator +(Tmatrix2_double, Tmatrix2_double): Tmatrix2_double`

```
(const m1: Tmatrix2_double,
const m2: Tmatrix2_double)
: Tmatrix2_double
```

Visibility: default

Description: This operator allows you to add two two-dimensional double precision matrices together. A new matrix is returned with all elements of the two matrices added together.

### 26.3.57 operator **+(Tmatrix2\_extended, extended): Tmatrix2\_extended**

Synopsis: Add scalar to two-dimensional extended precision matrix

Declaration: `operator operator +(Tmatrix2_extended, extended): Tmatrix2_extended`

```
(const m: Tmatrix2_extended,
const x: extended)
: Tmatrix2_extended
```



Visibility: default

Description: This operator allows you to add a scalar value to a matrix. The scalar is added to all elements of the matrix, the result is returned as a new vector.

### 26.3.58 operator +(Tmatrix2\_extended, Tmatrix2\_extended): Tmatrix2\_extended

Synopsis: Add two two-dimensional extended precision matrices together.

Declaration:

```
operator
(const m
const m2
: Tmatr
```

Visibility: default

Description: This operator allows you to add two two-dimensional extended precision matrices together. A new matrix is returned with all elements of the two matrices added together.

### 26.3.59 operator +(Tmatrix2\_single, single): Tmatrix2\_single

Synopsis: Add scalar to two-dimensional single precision matrix

Declaration: `operator operator +(Tmatrix2_single, single): Tmatrix2_single`

```
(const m: Tmatrix2_sing
const x: single)
: Tmatrix2_single
```

Visibility: default

Description: This operator allows you to add a scalar value to a matrix. The scalar is added to all elements of the matrix, the result is returned as a new vector.

### 26.3.60 operator +(Tmatrix2\_single, Tmatrix2\_single): Tmatrix2\_single

Synopsis: Add two two-dimensional single precision matrices together.

Declaration: `operator operator +(Tmatrix2_single, Tmatrix2_single): Tmatrix2_single`

```
(const m1: Tma
const m2: Tmat
: Tmatrix2_si
```

Visibility: default

Description: This operator allows you to add two two-dimensional single precision matrices together. A new matrix is returned with all elements of the two matrices added together.

### 26.3.61 operator +(Tmatrix3\_double, double): Tmatrix3\_double

Synopsis: Add scalar to three-dimensional double precision matrix

Declaration: `operator operator +(Tmatrix3_double, double): Tmatrix3_double`

```
(const m: Tmatrix3_doub
const x: double)
: Tmatrix3_double
```

Visibility: default

Description: This operator allows you to add a scalar value to a matrix. The scalar is added to all elements of the matrix, the result is returned as a new vector.

### 26.3.62 operator +(Tmatrix3\_double, Tmatrix3\_double): Tmatrix3\_double

Synopsis: Add two three-dimensional double precision matrices together.

Declaration: `operator operator +(Tmatrix3_double, Tmatrix3_double): Tmatrix3_double`

```
(const m1: Tmatrix3_double,
const m2: Tmatrix3_double)
: Tmatrix3_double
```

Visibility: default

Description: This operator allows you to add two three-dimensional double precision matrices together. A new matrix is returned with all elements of the two matrices added together.

### 26.3.63 operator +(Tmatrix3\_extended, extended): Tmatrix3\_extended

Synopsis: Add scalar to three-dimensional extended precision matrix

Declaration: `operator operator +(Tmatrix3_extended, extended): Tmatrix3_extended`

```
(const m: Tmatrix3_extended,
const x: extended)
: Tmatrix3_extended
```

Visibility: default

Description: This operator allows you to add a scalar value to a matrix. The scalar is added to all elements of the matrix, the result is returned as a new vector.

### 26.3.64 operator +(Tmatrix3\_extended, Tmatrix3\_extended): Tmatrix3\_extended

Synopsis: Add two three-dimensional extended precision matrices together.

Declaration:

```
operator operator +(Tmatrix3_extended, Tmatrix3_extended)
(const m1: Tmatrix3_extended,
const m2: Tmatrix3_extended)
: Tmatrix3_extended
```

Visibility: default

Description: This operator allows you to add two three-dimensional extended precision matrices together. A new matrix is returned with all elements of the two matrices added together.

### 26.3.65 operator +(Tmatrix3\_single, single): Tmatrix3\_single

Synopsis: Add scalar to three-dimensional single precision matrix

Declaration: `operator operator +(Tmatrix3_single, single): Tmatrix3_single`

```
(const m: Tmatrix3_single,
const x: single)
: Tmatrix3_single
```

Visibility: default

Description: This operator allows you to add a scalar value to a matrix. The scalar is added to all elements of the matrix, the result is returned as a new vector.

### 26.3.66 operator +(Tmatrix3\_single, Tmatrix3\_single): Tmatrix3\_single

Synopsis: Add two three-dimensional single precision matrices together.

Declaration: `operator operator +(Tmatrix3_single, Tmatrix3_single): Tmatrix3_single`

```
(const m1: Tmatrix3_single,
const m2: Tmatrix3_single)
: Tmatrix3_single
```

Visibility: default

Description: This operator allows you to add two three-dimensional single precision matrices together. A new matrix is returned with all elements of the two matrices added together.

### 26.3.67 operator +(Tmatrix4\_double, double): Tmatrix4\_double

Synopsis: Add scalar to four-dimensional double precision matrix

Declaration: `operator operator +(Tmatrix4_double, double): Tmatrix4_double`

```
(const m: Tmatrix4_double,
const x: double)
: Tmatrix4_double
```

Visibility: default

Description: This operator allows you to add a scalar value to a matrix. The scalar is added to all elements of the matrix, the result is returned as a new vector.

### 26.3.68 operator +(Tmatrix4\_double, Tmatrix4\_double): Tmatrix4\_double

Synopsis: Add two four-dimensional double precision matrices together.

Declaration: `operator operator +(Tmatrix4_double, Tmatrix4_double): Tmatrix4_double`

```
(const m1: Tmatrix4_double,
const m2: Tmatrix4_double)
: Tmatrix4_double
```

Visibility: default

Description: This operator allows you to add two four-dimensional double precision matrices together. A new matrix is returned with all elements of the two matrices added together.

### 26.3.69 operator +(Tmatrix4\_extended, extended): Tmatrix4\_extended

Synopsis: Add scalar to four-dimensional extended precision matrix

Declaration: `operator operator +(Tmatrix4_extended, extended): Tmatrix4_extended`

```
(const m: Tmatrix4_extended,
const x: extended)
: Tmatrix4_extended
```

Visibility: default

Description: This operator allows you to add a scalar value to a matrix. The scalar is added to all elements of the matrix, the result is returned as a new vector.

### 26.3.70 operator +(Tmatrix4\_extended, Tmatrix4\_extended): Tmatrix4\_extended

Synopsis: Add two four-dimensional extended precision matrices together.

Declaration:

```
operator
(const m
const m2
: Tmatr
```

Visibility: default

Description: This operator allows you to add two four-dimensional extended precision matrices together. A new matrix is returned with all elements of the two matrices added together.

### 26.3.71 operator +(Tmatrix4\_single, single): Tmatrix4\_single

Synopsis: Add scalar to four-dimensional single precision matrix

Declaration: `operator operator +(Tmatrix4_single, single): Tmatrix4_single`

```
(const m: Tmatrix4_sing
const x: single)
: Tmatrix4_single
```

Visibility: default

Description: This operator allows you to add a scalar value to a matrix. The scalar is added to all elements of the matrix, the result is returned as a new vector.

### 26.3.72 operator +(Tmatrix4\_single, Tmatrix4\_single): Tmatrix4\_single

Synopsis: Add two four-dimensional single precision matrices together.

Declaration: `operator operator +(Tmatrix4_single, Tmatrix4_single): Tmatrix4_single`

```
(const m1: Tma
const m2: Tmat
: Tmatrix4_si
```

Visibility: default

Description: This operator allows you to add two four-dimensional single precision matrices together. A new matrix is returned with all elements of the two matrices added together.

### 26.3.73 operator +(Tvector2\_double, double): Tvector2\_double

Synopsis: Add scalar to two-dimensional double precision vector

Declaration: `operator operator +(Tvector2_double, double): Tvector2_double`

```
(const x: Tvector2_doub
y: double)
: Tvector2_double
```

Visibility: default

Description: This operator allows you to add a scalar value to a vector. The scalar is added to all elements of the vector, the result is returned as a new vector.

### 26.3.74 operator +(Tvector2\_double, Tvector2\_double): Tvector2\_double

Synopsis: Add two-dimensional double precision vectors together

Declaration: `operator operator +(Tvector2_double, Tvector2_double): Tvector2_double`

```
(const x: Tvector2_double,
const y: Tvector2_double)
: Tvector2_double
```

Visibility: default

Description: This operator allows you to add two two-dimensional vectors with double precision together. The result is a new vector which consists of the sums of the individual elements of the two vectors.

### 26.3.75 operator +(Tvector2\_extended, extended): Tvector2\_extended

Synopsis: Add scalar to two-dimensional extended precision vector

Declaration: `operator operator +(Tvector2_extended, extended): Tvector2_extended`

```
(const x: Tvector2_extended,
y: extended)
: Tvector2_extended
```

Visibility: default

Description: This operator allows you to add a scalar value to a vector. The scalar is added to all elements of the vector, the result is returned as a new vector.

### 26.3.76 operator +(Tvector2\_extended, Tvector2\_extended): Tvector2\_extended

Synopsis: Add two-dimensional extended precision vectors together

Declaration:

```
operator operator +(Tvector2_extended, Tvector2_extended)
(const x: Tvector2_extended,
const y: Tvector2_extended)
: Tvector2_extended
```

Visibility: default

Description: This operator allows you to add two two-dimensional vectors with extended precision together. The result is a new vector which consists of the sums of the individual elements of the two vectors.

### 26.3.77 operator +(Tvector2\_single, single): Tvector2\_single

Synopsis: Add scalar to two-dimensional single precision vector

Declaration: `operator operator +(Tvector2_single, single): Tvector2_single`

```
(const x: Tvector2_single,
y: single)
: Tvector2_single
```

Visibility: default

Description: This operator allows you to add a scalar value to a vector. The scalar is added to all elements of the vector, the result is returned as a new vector.

### 26.3.78 operator +(Tvector2\_single, Tvector2\_single): Tvector2\_single

Synopsis: Add two-dimensional single precision vectors together

Declaration: `operator operator +(Tvector2_single, Tvector2_single): Tvector2_single`

```
(const x: Tvector2_single,
const y: Tvector2_single)
: Tvector2_single
```

Visibility: default

Description: This operator allows you to add two two-dimensional vectors with single precision together. The result is a new vector which consists of the sums of the individual elements of the two vectors.

### 26.3.79 operator +(Tvector3\_double, double): Tvector3\_double

Synopsis: Add scalar to three-dimensional double precision vector

Declaration: `operator operator +(Tvector3_double, double): Tvector3_double`

```
(const x: Tvector3_double,
y: double)
: Tvector3_double
```

Visibility: default

Description: This operator allows you to add a scalar value to a vector. The scalar is added to all elements of the vector, the result is returned as a new vector.

### 26.3.80 operator +(Tvector3\_double, Tvector3\_double): Tvector3\_double

Synopsis: Add three-dimensional double precision vectors together

Declaration: `operator operator +(Tvector3_double, Tvector3_double): Tvector3_double`

```
(const x: Tvector3_double,
const y: Tvector3_double)
: Tvector3_double
```

Visibility: default

Description: This operator allows you to add two three-dimensional vectors with double precision together. The result is a new vector which consists of the sums of the individual elements of the two vectors.

### 26.3.81 operator +(Tvector3\_extended, extended): Tvector3\_extended

Synopsis: Add scalar to three-dimensional extended precision vector

Declaration: `operator operator +(Tvector3_extended, extended): Tvector3_extended`

```
(const x: Tvector3_extended,
y: extended)
: Tvector3_extended
```

Visibility: default

Description: This operator allows you to add a scalar value to a vector. The scalar is added to all elements of the vector, the result is returned as a new vector.

### 26.3.82 operator +(Tvector3\_extended, Tvector3\_extended): Tvector3\_extended

Synopsis: Add three-dimensional extended precision vectors together

Declaration:

```
operator
(const x: Tvector3_extended,
const y: Tvector3_extended)
: Tvector3_extended
```

Visibility: default

Description: This operator allows you to add two three-dimensional vectors with extended precision together. The result is a new vector which consists of the sums of the individual elements of the two vectors.

### 26.3.83 operator +(Tvector3\_single, single): Tvector3\_single

Synopsis: Add scalar to three-dimensional single precision vector

Declaration: operator operator +(Tvector3\_single, single): Tvector3\_single

```
(const x: Tvector3_single,
y: single)
: Tvector3_single
```

Visibility: default

Description: This operator allows you to add a scalar value to a vector. The scalar is added to all elements of the vector, the result is returned as a new vector.

### 26.3.84 operator +(Tvector3\_single, Tvector3\_single): Tvector3\_single

Synopsis: Add three-dimensional extended precision vectors together

Declaration: operator operator +(Tvector3\_single, Tvector3\_single): Tvector3\_single

```
(const x: Tvector3_single,
const y: Tvector3_single)
: Tvector3_single
```

Visibility: default

Description: This operator allows you to add two three-dimensional vectors with single precision together. The result is a new vector which consists of the sums of the individual elements of the two vectors.

### 26.3.85 operator +(Tvector4\_double, double): Tvector4\_double

Synopsis: Add scalar to four-dimensional double precision vector

Declaration: operator operator +(Tvector4\_double, double): Tvector4\_double

```
(const x: Tvector4_double,
y: double)
: Tvector4_double
```

Visibility: default

Description: This operator allows you to add a scalar value to a vector. The scalar is added to all elements of the vector, the result is returned as a new vector.

### 26.3.86 operator +(Tvector4\_double, Tvector4\_double): Tvector4\_double

Synopsis: Add four-dimensional double precision vectors together

Declaration: `operator operator +(Tvector4_double, Tvector4_double): Tvector4_double`

```
(const x: Tvector4_double,
const y: Tvector4_double)
: Tvector4_double
```

Visibility: default

Description: This operator allows you to add two four-dimensional vectors with single precision together. The result is a new vector which consists of the sums of the individual elements of the two vectors.

### 26.3.87 operator +(Tvector4\_extended, extended): Tvector4\_extended

Synopsis: Add scalar to four-dimensional extended precision vector

Declaration: `operator operator +(Tvector4_extended, extended): Tvector4_extended`

```
(const x: Tvector4_extended,
y: extended)
: Tvector4_extended
```

Visibility: default

Description: This operator allows you to add a scalar value to a vector. The scalar is added to all elements of the vector, the result is returned as a new vector.

### 26.3.88 operator +(Tvector4\_extended, Tvector4\_extended): Tvector4\_extended

Synopsis: Add four-dimensional extended precision vectors together

Declaration:

```
operator operator +(Tvector4_extended, Tvector4_extended): Tvector4_extended
(const x: Tvector4_extended,
const y: Tvector4_extended)
: Tvector4_extended
```

Visibility: default

Description: This operator allows you to add two two-dimensional vectors with extended precision together. The result is a new vector which consists of the sums of the individual elements of the two vectors.

### 26.3.89 operator +(Tvector4\_single, single): Tvector4\_single

Synopsis: Add scalar to four-dimensional single precision vector

Declaration: `operator operator +(Tvector4_single, single): Tvector4_single`

```
(const x: Tvector4_single,
y: single)
: Tvector4_single
```



Visibility: default

Description: This operator allows you to add a scalar value to a vector. The scalar is added to all elements of the vector, the result is returned as a new vector.

### 26.3.90 operator +(Tvector4\_single, Tvector4\_single): Tvector4\_single

Synopsis: Add four-dimensional single precision vectors together

Declaration: `operator operator +(Tvector4_single, Tvector4_single): Tvector4_single`

```
(const x: Tvector4_single,
const y: Tvector4_single)
: Tvector4_single
```

Visibility: default

Description: This operator allows you to add two four-dimensional vectors with single precision together. The result is a new vector which consists of the sums of the individual elements of the two vectors.

### 26.3.91 operator -(Tmatrix2\_double): Tmatrix2\_double

Synopsis: Negate two-dimensional double precision matrix.

Declaration: `operator operator -(Tmatrix2_double): Tmatrix2_double`

```
(const m1: Tmatrix2_double)
: Tmatrix2_double
```

Visibility: default

Description: This operation returns a matrix with all elements negated.

### 26.3.92 operator -(Tmatrix2\_double, double): Tmatrix2\_double

Synopsis: Subtract scalar to two-dimensional double precision matrix

Declaration: `operator operator -(Tmatrix2_double, double): Tmatrix2_double`

```
(const m: Tmatrix2_double,
const x: double)
: Tmatrix2_double
```

Visibility: default

Description: This operator allows you to subtract a scalar value from a matrix. The scalar is subtracted from all elements of the matrix, the result is returned as a new matrix.

### 26.3.93 operator -(Tmatrix2\_double, Tmatrix2\_double): Tmatrix2\_double

Synopsis: Subtract a two-dimensional double precision matrix from another.

Declaration: `operator operator -(Tmatrix2_double, Tmatrix2_double): Tmatrix2_double`

```
(const m1: Tmatrix2_double,
const m2: Tmatrix2_double)
: Tmatrix2_double
```

Visibility: default

Description: This operator allows you to subtract a two-dimensional double precision matrix from another. A new matrix is returned with all elements of the two matrices subtracted from each other.

**26.3.94 operator -(Tmatrix2\_extended): Tmatrix2\_extended**

Synopsis: Negate two-dimensional extended precision matrix.

Declaration: `operator operator -(Tmatrix2_extended): Tmatrix2_extended`  
`(const m1: Tmatrix2_extended)`  
`: Tmatrix2_extended`

Visibility: default

Description: This operation returns a matrix with all elements negated.

**26.3.95 operator -(Tmatrix2\_extended, extended): Tmatrix2\_extended**

Synopsis: Add scalar to two-dimensional extended precision matrix

Declaration: `operator operator -(Tmatrix2_extended, extended): Tmatrix2_extended`  
`(const m: Tmatrix2_extended)`  
`const x: extended`  
`: Tmatrix2_extended`

Visibility: default

Description: This operator allows you to subtract a scalar value from a matrix. The scalar is subtracted from all elements of the matrix, the result is returned as a new matrix.

**26.3.96 operator -(Tmatrix2\_extended, Tmatrix2\_extended): Tmatrix2\_extended**

Synopsis: Subtract a two-dimensional extended precision matrix from another.

Declaration: `operator operator -(Tmatrix2_extended, Tmatrix2_extended): Tmatrix2_extended`  
`(const m1: Tmatrix2_extended)`  
`const m2: Tmatrix2_extended`  
`: Tmatrix2_extended`

Visibility: default

Description: This operator allows you to subtract a two-dimensional extended precision matrix from another. A new matrix is returned with all elements of the two matrices subtracted from each other.

**26.3.97 operator -(Tmatrix2\_single): Tmatrix2\_single**

Synopsis: Negate two-dimensional single precision matrix.

Declaration: `operator operator -(Tmatrix2_single): Tmatrix2_single`  
`(const m1: Tmatrix2_single)`  
`: Tmatrix2_single`

Visibility: default

Description: This operation returns a matrix with all elements negated.

**26.3.98 operator -(Tmatrix2\_single, single): Tmatrix2\_single**

Synopsis: Subtract scalar to two-dimensional single precision matrix

Declaration: `operator operator -(Tmatrix2_single, single): Tmatrix2_single`

```
(const m: Tmatrix2_single)
const x: single)
: Tmatrix2_single
```

Visibility: default

Description: This operator allows you to subtract a scalar value from a matrix. The scalar is subtracted from all elements of the matrix, the result is returned as a new matrix.

**26.3.99 operator -(Tmatrix2\_single, Tmatrix2\_single): Tmatrix2\_single**

Synopsis: Subtract a two-dimensional single precision matrix from another.

Declaration: `operator operator -(Tmatrix2_single, Tmatrix2_single): Tmatrix2_single`

```
(const m1: Tmatrix2_single)
const m2: Tmatrix2_single)
: Tmatrix2_single
```

Visibility: default

Description: This operator allows you to subtract a two-dimensional single precision matrix from another. A new matrix is returned with all elements of the two matrices subtracted from each other.

**26.3.100 operator -(Tmatrix3\_double): Tmatrix3\_double**

Synopsis: Negate three-dimensional double precision matrix.

Declaration: `operator operator -(Tmatrix3_double): Tmatrix3_double`

```
(const m1: Tmatrix3_double)
: Tmatrix3_double
```

Visibility: default

Description: This operation returns a matrix with all elements negated.

**26.3.101 operator -(Tmatrix3\_double, double): Tmatrix3\_double**

Synopsis: Add scalar to three-dimensional double precision matrix

Declaration: `operator operator -(Tmatrix3_double, double): Tmatrix3_double`

```
(const m: Tmatrix3_double)
const x: double)
: Tmatrix3_double
```

Visibility: default

Description: This operator allows you to subtract a scalar value from a matrix. The scalar is subtracted from all elements of the matrix, the result is returned as a new matrix.

**26.3.102 operator -(Tmatrix3\_double, Tmatrix3\_double): Tmatrix3\_double**

Synopsis: Subtract a three-dimensional double precision matrix from another.

Declaration: `operator operator -(Tmatrix3_double, Tmatrix3_double): Tmatrix3_double`

```
(const m1: Tmatrix3_double,
const m2: Tmatrix3_double)
: Tmatrix3_double
```

Visibility: default

Description: This operator allows you to subtract a three-dimensional double precision matrix from another. A new matrix is returned with all elements of the two matrices subtracted from each other.

**26.3.103 operator -(Tmatrix3\_extended): Tmatrix3\_extended**

Synopsis: Negate three-dimensional extended precision matrix.

Declaration: `operator operator -(Tmatrix3_extended): Tmatrix3_extended`

```
(const m1: Tmatrix3_extended)
: Tmatrix3_extended
```

Visibility: default

Description: This operation returns a matrix with all elements negated.

**26.3.104 operator -(Tmatrix3\_extended, extended): Tmatrix3\_extended**

Synopsis: Add scalar to three-dimensional extended precision matrix

Declaration: `operator operator -(Tmatrix3_extended, extended): Tmatrix3_extended`

```
(const m: Tmatrix3_extended,
const x: extended)
: Tmatrix3_extended
```

Visibility: default

Description: This operator allows you to subtract a scalar value from a matrix. The scalar is subtracted from all elements of the matrix, the result is returned as a new matrix.

**26.3.105 operator -(Tmatrix3\_extended, Tmatrix3\_extended): Tmatrix3\_extended**

Synopsis: Subtract a three-dimensional extended precision matrix from another.

Declaration:

```
operator operator -(
const m1: Tmatrix3_extended,
const m2: Tmatrix3_extended)
: Tmatrix3_extended
```

Visibility: default

Description: This operator allows you to subtract a three-dimensional extended precision matrix from another. A new matrix is returned with all elements of the two matrices subtracted from each other.

**26.3.106 operator -(Tmatrix3\_single): Tmatrix3\_single**

Synopsis: Negate three-dimensional single precision matrix.

Declaration: `operator operator -(Tmatrix3_single): Tmatrix3_single`  
`(const m1: Tmatrix3_single)`  
`: Tmatrix3_single`

Visibility: default

Description: This operation returns a matrix with all elements negated.

**26.3.107 operator -(Tmatrix3\_single, single): Tmatrix3\_single**

Synopsis: Add scalar to three-dimensional single precision matrix

Declaration: `operator operator -(Tmatrix3_single, single): Tmatrix3_single`  
`(const m: Tmatrix3_single,`  
`const x: single)`  
`: Tmatrix3_single`

Visibility: default

Description: This operator allows you to subtract a scalar value from a matrix. The scalar is subtracted from all elements of the matrix, the result is returned as a new matrix.

**26.3.108 operator -(Tmatrix3\_single, Tmatrix3\_single): Tmatrix3\_single**

Synopsis: Subtract a three-dimensional single precision matrix from another.

Declaration: `operator operator -(Tmatrix3_single, Tmatrix3_single): Tmatrix3_single`  
`(const m1: Tmatrix3_single,`  
`const m2: Tmatrix3_single)`  
`: Tmatrix3_single`

Visibility: default

Description: This operator allows you to subtract a three-dimensional single precision matrix from another. A new matrix is returned with all elements of the two matrices subtracted from each other.

**26.3.109 operator -(Tmatrix4\_double): Tmatrix4\_double**

Synopsis: Negate four-dimensional double precision matrix.

Declaration: `operator operator -(Tmatrix4_double): Tmatrix4_double`  
`(const m1: Tmatrix4_double)`  
`: Tmatrix4_double`

Visibility: default

Description: This operation returns a matrix with all elements negated.

**26.3.110 operator -(Tmatrix4\_double, double): Tmatrix4\_double**

Synopsis: Add scalar to four-dimensional double precision matrix

Declaration: `operator operator -(Tmatrix4_double, double): Tmatrix4_double`

```
(const m: Tmatrix4_double,
const x: double)
: Tmatrix4_double
```

Visibility: default

Description: This operator allows you to subtract a scalar value from a matrix. The scalar is subtracted from all elements of the matrix, the result is returned as a new matrix.

**26.3.111 operator -(Tmatrix4\_double, Tmatrix4\_double): Tmatrix4\_double**

Synopsis: Subtract a four-dimensional double precision matrix from another.

Declaration: `operator operator -(Tmatrix4_double, Tmatrix4_double): Tmatrix4_double`

```
(const m1: Tmatrix4_double,
const m2: Tmatrix4_double)
: Tmatrix4_double
```

Visibility: default

Description: This operator allows you to subtract a four-dimensional double precision matrix from another. A new matrix is returned with all elements of the two matrices subtracted from each other.

**26.3.112 operator -(Tmatrix4\_extended): Tmatrix4\_extended**

Synopsis: Negate four-dimensional extended precision matrix.

Declaration: `operator operator -(Tmatrix4_extended): Tmatrix4_extended`

```
(const m1: Tmatrix4_extended)
: Tmatrix4_extended
```

Visibility: default

Description: This operation returns a matrix with all elements negated.

**26.3.113 operator -(Tmatrix4\_extended, extended): Tmatrix4\_extended**

Synopsis: Add scalar to four-dimensional extended precision matrix

Declaration: `operator operator -(Tmatrix4_extended, extended): Tmatrix4_extended`

```
(const m: Tmatrix4_extended,
const x: extended)
: Tmatrix4_extended
```

Visibility: default

Description: This operator allows you to subtract a scalar value from a matrix. The scalar is subtracted from all elements of the matrix, the result is returned as a new matrix.

**26.3.114 operator -(Tmatrix4\_extended, Tmatrix4\_extended): Tmatrix4\_extended**

Synopsis: Subtract a four-dimensional extended precision matrix from another.

Declaration:

```
operator
(const m1: Tmatrix4_extended,
const m2: Tmatrix4_extended)
: Tmatrix4_extended
```

Visibility: default

Description: This operator allows you to subtract a four-dimensional extended precision matrix from another. A new matrix is returned with all elements of the two matrices subtracted from each other.

**26.3.115 operator -(Tmatrix4\_single): Tmatrix4\_single**

Synopsis: Negate four-dimensional single precision matrix.

Declaration: `operator operator -(Tmatrix4_single): Tmatrix4_single`  
`(const m1: Tmatrix4_single)`  
`: Tmatrix4_single`

Visibility: default

Description: This operation returns a matrix with all elements negated.

**26.3.116 operator -(Tmatrix4\_single, single): Tmatrix4\_single**

Synopsis: Add scalar to four-dimensional single precision matrix

Declaration: `operator operator -(Tmatrix4_single, single): Tmatrix4_single`  
`(const m: Tmatrix4_single,`  
`const x: single)`  
`: Tmatrix4_single`

Visibility: default

Description: This operator allows you to subtract a scalar value from a matrix. The scalar is subtracted from all elements of the matrix, the result is returned as a new matrix.

**26.3.117 operator -(Tmatrix4\_single, Tmatrix4\_single): Tmatrix4\_single**

Synopsis: Subtract a four-dimensional single precision matrix from another.

Declaration: `operator operator -(Tmatrix4_single, Tmatrix4_single): Tmatrix4_single`  
`(const m1: Tmatrix4_single,`  
`const m2: Tmatrix4_single)`  
`: Tmatrix4_single`

Visibility: default

Description: This operator allows you to subtract a four-dimensional single precision matrix from another. A new matrix is returned with all elements of the two matrices subtracted from each other.

**26.3.118 operator -(Tvector2\_double): Tvector2\_double**

Synopsis: Negate two-dimensional vector.

Declaration: `operator operator -(Tvector2_double) : Tvector2_double`  
`(const x: Tvector2_double)`  
`: Tvector2_double`

Visibility: default

Description: This operation returns a vector in the opposite direction of the vector that is passed. In order to do so, all values in the vector are negated.

**26.3.119 operator -(Tvector2\_double, double): Tvector2\_double**

Synopsis: Subtract scalar from two-dimensional double precision vector

Declaration: `operator operator -(Tvector2_double, double) : Tvector2_double`  
`(const x: Tvector2_double`  
`y: double)`  
`: Tvector2_double`

Visibility: default

Description: This operator allows you to subtract a scalar value from a vector. The scalar is subtracted from all elements of the vector, the result is returned as a new vector.

**26.3.120 operator -(Tvector2\_double, Tvector2\_double): Tvector2\_double**

Synopsis: Subtract two-dimensional double precision vectors from each other

Declaration: `operator operator -(Tvector2_double, Tvector2_double) : Tvector2_double`  
`(const x: Tvec`  
`const y: Tvect`  
`: Tvector2_do`

Visibility: default

Description: This operator allows you to subtract two two-dimensional vectors with double precision from each other. The result is a new vector which consists of the difference of the individual elements of the two vectors.

**26.3.121 operator -(Tvector2\_extended): Tvector2\_extended**

Synopsis: Negate two-dimensional vector.

Declaration: `operator operator -(Tvector2_extended) : Tvector2_extended`  
`(const x: Tvector2_extended`  
`: Tvector2_extended`

Visibility: default

Description: This operation returns a vector in the opposite direction of the vector that is passed. In order to do so, all values in the vector are negated.



**26.3.122 operator -(Tvector2\_extended, extended): Tvector2\_extended**

Synopsis: Subtract scalar from two-dimensional extended precision vector

Declaration: `operator operator -(Tvector2_extended, extended): Tvector2_extended`

```
(const x: Tvector2_extended,
y: extended)
: Tvector2_extended
```

Visibility: default

Description: This operator allows you to subtract a scalar value from a vector. The scalar is subtracted from all elements of the vector, the result is returned as a new vector.

**26.3.123 operator -(Tvector2\_extended, Tvector2\_extended): Tvector2\_extended**

Synopsis: Subtract two-dimensional extended precision vectors from each other

Declaration:

```
operator operator -(Tvector2_extended, Tvector2_extended): Tvector2_extended
(const x: Tvector2_extended,
const y: Tvector2_extended)
: Tvector2_extended
```

Visibility: default

Description: This operator allows you to subtract two two-dimensional vectors with extended precision from each other. The result is a new vector which consists of the difference of the individual elements of the two vectors.

**26.3.124 operator -(Tvector2\_single): Tvector2\_single**

Synopsis: Negate two-dimensional vector.

Declaration: `operator operator -(Tvector2_single): Tvector2_single`

```
(const x: Tvector2_single)
: Tvector2_single
```

Visibility: default

Description: This operation returns a vector in the opposite direction of the vector that is passed. In order to do so, all values in the vector are negated.

**26.3.125 operator -(Tvector2\_single, single): Tvector2\_single**

Synopsis: Subtract scalar from two-dimensional single precision vector

Declaration: `operator operator -(Tvector2_single, single): Tvector2_single`

```
(const x: Tvector2_single,
y: single)
: Tvector2_single
```

Visibility: default

Description: This operator allows you to subtract a scalar value from a vector. The scalar is subtracted from all elements of the vector, the result is returned as a new vector.

**26.3.126 operator -(Tvector2\_single, Tvector2\_single): Tvector2\_single**

Synopsis: Subtract two-dimensional single precision vectors from each other

Declaration: `operator operator -(Tvector2_single, Tvector2_single): Tvector2_single`

```
(const x: Tvector2_single,
const y: Tvector2_single)
: Tvector2_single
```

Visibility: default

Description: This operator allows you to subtract two two-dimensional vectors with single precision from each other. The result is a new vector which consists of the difference of the individual elements of the two vectors.

**26.3.127 operator -(Tvector3\_double): Tvector3\_double**

Synopsis: Negate three-dimensional vector.

Declaration: `operator operator -(Tvector3_double): Tvector3_double`

```
(const x: Tvector3_double)
: Tvector3_double
```

Visibility: default

Description: This operation returns a vector in the opposite direction of the vector that is passed. In order to do so, all values in the vector are negated.

**26.3.128 operator -(Tvector3\_double, double): Tvector3\_double**

Synopsis: Subtract scalar from three-dimensional double precision vector

Declaration: `operator operator -(Tvector3_double, double): Tvector3_double`

```
(const x: Tvector3_double,
y: double)
: Tvector3_double
```

Visibility: default

Description: This operator allows you to subtract a scalar value from a vector. The scalar is subtracted from all elements of the vector, the result is returned as a new vector.

**26.3.129 operator -(Tvector3\_double, Tvector3\_double): Tvector3\_double**

Synopsis: Subtract three-dimensional double precision vectors from each other

Declaration: `operator operator -(Tvector3_double, Tvector3_double): Tvector3_double`

```
(const x: Tvector3_double,
const y: Tvector3_double)
: Tvector3_double
```

Visibility: default

Description: This operator allows you to subtract two two-dimensional vectors with double precision from each other. The result is a new vector which consists of the difference of the individual elements of the two vectors.

**26.3.130 operator -(Tvector3\_extended): Tvector3\_extended**

Synopsis: Negate three-dimensional vector.

Declaration: `operator operator -(Tvector3_extended) : Tvector3_extended`  
`(const x: Tvector3_extended`  
`: Tvector3_extended`

Visibility: default

Description: This operation returns a vector in the opposite direction of the vector that is passed. In order to do so, all values in the vector are negated.

**26.3.131 operator -(Tvector3\_extended, extended): Tvector3\_extended**

Synopsis: Subtract scalar from three-dimensional extended precision vector

Declaration: `operator operator -(Tvector3_extended, extended) : Tvector3_extended`  
`(const x: Tvector`  
`y: extended)`  
`: Tvector3_exten`

Visibility: default

Description: This operator allows you to subtract a scalar value from a vector. The scalar is subtracted from all elements of the vector, the result is returned as a new vector.

**26.3.132 operator -(Tvector3\_extended, Tvector3\_extended): Tvector3\_extended**

Synopsis: Subtract three-dimensional extended precision vectors from each other

Declaration: `operator operator -(Tvector3_extended, Tvector3_extended) : Tvector3_extended`  
`operator`  
`(const x`  
`const y:`  
`: Tvect`

Visibility: default

Description: This operator allows you to subtract two three-dimensional vectors with extended precision from each other. The result is a new vector which consists of the difference of the individual elements of the two vectors.

**26.3.133 operator -(Tvector3\_single): Tvector3\_single**

Synopsis: Negate three-dimensional vector.

Declaration: `operator operator -(Tvector3_single) : Tvector3_single`  
`(const x: Tvector3_single)`  
`: Tvector3_single`

Visibility: default

Description: This operation returns a vector in the opposite direction of the vector that is passed. In order to do so, all values in the vector are negated.

**26.3.134 operator -(Tvector3\_single, single): Tvector3\_single**

Synopsis: Subtract scalar from three-dimensional single precision vector

Declaration: `operator operator -(Tvector3_single, single): Tvector3_single`  
`(const x: Tvector3_single, y: single): Tvector3_single`

Visibility: default

Description: This operator allows you to subtract a scalar value from a vector. The scalar is subtracted from all elements of the vector, the result is returned as a new vector.

**26.3.135 operator -(Tvector3\_single, Tvector3\_single): Tvector3\_single**

Synopsis: Subtract three-dimensional single precision vectors from each other

Declaration: `operator operator -(Tvector3_single, Tvector3_single): Tvector3_single`  
`(const x: Tvector3_single, const y: Tvector3_single): Tvector3_single`

Visibility: default

Description: This operator allows you to subtract two three-dimensional vectors with single precision from each other. The result is a new vector which consists of the difference of the individual elements of the two vectors.

**26.3.136 operator -(Tvector4\_double): Tvector4\_double**

Synopsis: Negate four-dimensional vector.

Declaration: `operator operator -(Tvector4_double): Tvector4_double`  
`(const x: Tvector4_double): Tvector4_double`

Visibility: default

Description: This operation returns a vector in the opposite direction of the vector that is passed. In order to do so, all values in the vector are negated.

**26.3.137 operator -(Tvector4\_double, double): Tvector4\_double**

Synopsis: Subtract scalar from four-dimensional double precision vector

Declaration: `operator operator -(Tvector4_double, double): Tvector4_double`  
`(const x: Tvector4_double, y: double): Tvector4_double`

Visibility: default

Description: This operator allows you to subtract a scalar value from a vector. The scalar is subtracted from all elements of the vector, the result is returned as a new vector.

**26.3.138 operator-(Tvector4\_double, Tvector4\_double): Tvector4\_double**

Synopsis: Subtract four-dimensional double precision vectors from each other

Declaration: `operator operator -(Tvector4_double, Tvector4_double): Tvector4_double`

```
(const x: Tvector4_double,
const y: Tvector4_double)
: Tvector4_double
```

Visibility: default

Description: This operator allows you to subtract two four-dimensional vectors with double precision from each other. The result is a new vector which consists of the difference of the individual elements of the two vectors.

**26.3.139 operator-(Tvector4\_extended): Tvector4\_extended**

Synopsis: Negate four-dimensional vector.

Declaration: `operator operator -(Tvector4_extended): Tvector4_extended`

```
(const x: Tvector4_extended)
: Tvector4_extended
```

Visibility: default

Description: This operation returns a vector in the opposite direction of the vector that is passed. In order to do so, all values in the vector are negated.

**26.3.140 operator-(Tvector4\_extended, extended): Tvector4\_extended**

Synopsis: Subtract scalar from four-dimensional extended precision vector

Declaration: `operator operator -(Tvector4_extended, extended): Tvector4_extended`

```
(const x: Tvector4_extended,
y: extended)
: Tvector4_extended
```

Visibility: default

Description: This operator allows you to subtract a scalar value from a vector. The scalar is subtracted from all elements of the vector, the result is returned as a new vector.

**26.3.141 operator-(Tvector4\_extended, Tvector4\_extended): Tvector4\_extended**

Synopsis: Subtract four-dimensional extended precision vectors from each other

Declaration:

```
operator operator -(
(const x: Tvector4_extended,
const y: Tvector4_extended)
: Tvector4_extended)
```

Visibility: default

Description: This operator allows you to subtract two four-dimensional vectors with extended precision from each other. The result is a new vector which consists of the difference of the individual elements of the two vectors.

**26.3.142 operator -(Tvector4\_single): Tvector4\_single**

Synopsis: Negate four-dimensional vector.

Declaration: `operator operator -(Tvector4_single): Tvector4_single`  
`(const x: Tvector4_single)`  
`: Tvector4_single`

Visibility: default

Description: This operation returns a vector in the opposite direction of the vector that is passed. In order to do so, all values in the vector are negated.

**26.3.143 operator -(Tvector4\_single, single): Tvector4\_single**

Synopsis: Subtract scalar from four-dimensional single precision vector

Declaration: `operator operator -(Tvector4_single, single): Tvector4_single`  
`(const x: Tvector4_single,`  
`y: single)`  
`: Tvector4_single`

Visibility: default

Description: This operator allows you to subtract a scalar value from a vector. The scalar is subtracted from all elements of the vector, the result is returned as a new vector.

**26.3.144 operator -(Tvector4\_single, Tvector4\_single): Tvector4\_single**

Synopsis: Subtract four-dimensional single precision vectors from each other

Declaration: `operator operator -(Tvector4_single, Tvector4_single): Tvector4_single`  
`(const x: Tvector4_single,`  
`const y: Tvector4_single)`  
`: Tvector4_single`

Visibility: default

Description: This operator allows you to subtract two four-dimensional vectors with single precision from each other. The result is a new vector which consists of the difference of the individual elements of the two vectors.

**26.3.145 operator /(Tmatrix2\_double, double): Tmatrix2\_double**

Synopsis: Divide a two-dimensional single precision matrix by a scalar

Declaration: `operator operator /(Tmatrix2_double, double): Tmatrix2_double`  
`(const m: Tmatrix2_double,`  
`const x: double)`  
`: Tmatrix2_double`

Visibility: default

Description: This operator allows you to divide a matrix by a scalar. All elements in the matrix are divided by the scalar, the result is returned as a new matrix.

**26.3.146 operator /(Tmatrix2\_extended, extended): Tmatrix2\_extended**

Synopsis: Divide a two-dimensional single precision matrix by a scalar

Declaration: `operator operator / (Tmatrix2_extended, extended): Tmatrix2_extended`

```
(const m: Tmatrix2_extended,
const x: extended)
: Tmatrix2_extended
```

Visibility: default

Description: This operator allows you to divide a matrix by a scalar. All elements in the matrix are divided by the scalar, the result is returned as a new matrix.

**26.3.147 operator /(Tmatrix2\_single, single): Tmatrix2\_single**

Synopsis: Divide a two-dimensional single precision matrix by a scalar

Declaration: `operator operator / (Tmatrix2_single, single): Tmatrix2_single`

```
(const m: Tmatrix2_single,
const x: single)
: Tmatrix2_single
```

Visibility: default

Description: This operator allows you to divide a matrix by a scalar. All elements in the matrix are divided by the scalar, the result is returned as a new matrix.

**26.3.148 operator /(Tmatrix3\_double, double): Tmatrix3\_double**

Synopsis: Divide a two-dimensional single precision matrix by a scalar

Declaration: `operator operator / (Tmatrix3_double, double): Tmatrix3_double`

```
(const m: Tmatrix3_double,
const x: double)
: Tmatrix3_double
```

Visibility: default

Description: This operator allows you to divide a matrix by a scalar. All elements in the matrix are divided by the scalar, the result is returned as a new matrix.

**26.3.149 operator /(Tmatrix3\_extended, extended): Tmatrix3\_extended**

Synopsis: Divide a two-dimensional single precision matrix by a scalar

Declaration: `operator operator / (Tmatrix3_extended, extended): Tmatrix3_extended`

```
(const m: Tmatrix3_extended,
const x: extended)
: Tmatrix3_extended
```

Visibility: default

Description: This operator allows you to divide a matrix by a scalar. All elements in the matrix are divided by the scalar, the result is returned as a new matrix.

**26.3.150 operator /(Tmatrix3\_single, single): Tmatrix3\_single**

Synopsis: Divide a two-dimensional single precision matrix by a scalar

Declaration: `operator operator / (Tmatrix3_single, single): Tmatrix3_single`

```
(const m: Tmatrix3_sing
const x: single)
: Tmatrix3_single
```

Visibility: default

Description: This operator allows you to divide a matrix by a scalar. All elements in the matrix are divided by the scalar, the result is returned as a new matrix.

**26.3.151 operator /(Tmatrix4\_double, double): Tmatrix4\_double**

Synopsis: Divide a two-dimensional single precision matrix by a scalar

Declaration: `operator operator / (Tmatrix4_double, double): Tmatrix4_double`

```
(const m: Tmatrix4_doub
const x: double)
: Tmatrix4_double
```

Visibility: default

Description: This operator allows you to divide a matrix by a scalar. All elements in the matrix are divided by the scalar, the result is returned as a new matrix.

**26.3.152 operator /(Tmatrix4\_extended, extended): Tmatrix4\_extended**

Synopsis: Divide a two-dimensional single precision matrix by a scalar

Declaration: `operator operator / (Tmatrix4_extended, extended): Tmatrix4_extended`

```
(const m: Tmatrix
const x: extended)
: Tmatrix4_exten
```

Visibility: default

Description: This operator allows you to divide a matrix by a scalar. All elements in the matrix are divided by the scalar, the result is returned as a new matrix.

**26.3.153 operator /(Tmatrix4\_single, single): Tmatrix4\_single**

Synopsis: Divide a two-dimensional single precision matrix by a scalar

Declaration: `operator operator / (Tmatrix4_single, single): Tmatrix4_single`

```
(const m: Tmatrix4_sing
const x: single)
: Tmatrix4_single
```

Visibility: default

Description: This operator allows you to divide a matrix by a scalar. All elements in the matrix are divided by the scalar, the result is returned as a new matrix.



**26.3.154 operator /(Tvector2\_double, double): Tvector2\_double**

Synopsis: Divide a two-dimensional double precision vector by a scalar

Declaration: `operator operator / (Tvector2_double, double): Tvector2_double`  
`(const x: Tvector2_double`  
`y: double)`  
`: Tvector2_double`

Visibility: default

Description: This operator allows you to divide a vector by a scalar value. Each vector element is divided by the scalar value; the result is returned as a new vector.

**26.3.155 operator /(Tvector2\_extended, extended): Tvector2\_extended**

Synopsis: Divide a two-dimensional extended precision vector by a scalar

Declaration: `operator operator / (Tvector2_extended, extended): Tvector2_extended`  
`(const x: Tvector`  
`y: extended)`  
`: Tvector2_exten`

Visibility: default

Description: This operator allows you to divide a vector by a scalar value. Each vector element is divided by the scalar value; the result is returned as a new vector.

**26.3.156 operator /(Tvector2\_single, single): Tvector2\_single**

Synopsis: Divide a two-dimensional single precision vector by a scalar

Declaration: `operator operator / (Tvector2_single, single): Tvector2_single`  
`(const x: Tvector2_sing`  
`y: single)`  
`: Tvector2_single`

Visibility: default

Description: This operator allows you to divide a vector by a scalar value. Each vector element is divided by the scalar value; the result is returned as a new vector.

**26.3.157 operator /(Tvector3\_double, double): Tvector3\_double**

Synopsis: Divide a three-dimensional double precision vector by a scalar

Declaration: `operator operator / (Tvector3_double, double): Tvector3_double`  
`(const x: Tvector3_doub`  
`y: double)`  
`: Tvector3_double`

Visibility: default

Description: This operator allows you to divide a vector by a scalar value. Each vector element is divided by the scalar value; the result is returned as a new vector.

**26.3.158 operator /(Tvector3\_extended, extended): Tvector3\_extended**

Synopsis: Divide a three-dimensional extended precision vector by a scalar

Declaration: `operator operator / (Tvector3_extended, extended) : Tvector3_extended`  
`(const x: Tvector3_extended, y: extended) : Tvector3_extended`

Visibility: default

Description: This operator allows you to divide a vector by a scalar value. Each vector element is divided by the scalar value; the result is returned as a new vector.

**26.3.159 operator /(Tvector3\_single, single): Tvector3\_single**

Synopsis: Divide a three-dimensional single precision vector by a scalar

Declaration: `operator operator / (Tvector3_single, single) : Tvector3_single`  
`(const x: Tvector3_single, y: single) : Tvector3_single`

Visibility: default

Description: This operator allows you to divide a vector by a scalar value. Each vector element is divided by the scalar value; the result is returned as a new vector.

**26.3.160 operator /(Tvector4\_double, double): Tvector4\_double**

Synopsis: Divide a four-dimensional double precision vector by a scalar

Declaration: `operator operator / (Tvector4_double, double) : Tvector4_double`  
`(const x: Tvector4_double, y: double) : Tvector4_double`

Visibility: default

Description: This operator allows you to divide a vector by a scalar value. Each vector element is divided by the scalar value; the result is returned as a new vector.

**26.3.161 operator /(Tvector4\_extended, extended): Tvector4\_extended**

Synopsis: Divide a four-dimensional extended precision vector by a scalar

Declaration: `operator operator / (Tvector4_extended, extended) : Tvector4_extended`  
`(const x: Tvector4_extended, y: extended) : Tvector4_extended`

Visibility: default

Description: This operator allows you to divide a vector by a scalar value. Each vector element is divided by the scalar value; the result is returned as a new vector.

**26.3.162 operator /(Tvector4\_single, single): Tvector4\_single**

Synopsis: Divide a four-dimensional single precision vector by a scalar

Declaration: `operator operator /(Tvector4_single, single): Tvector4_single`

```
(const x: Tvector4_single,
 y: single)
: Tvector4_single
```

Visibility: default

Description: This operator allows you to divide a vector by a scalar value. Each vector element is divided by the scalar value; the result is returned as a new vector.

**26.3.163 operator :=(Tmatrix2\_double): Tmatrix2\_extended**

Synopsis: Allow assignment of two-dimensional double precision matrix to two-dimensional extended precision matrix

Declaration: `operator operator :=(Tmatrix2_double): Tmatrix2_extended`

```
(const v: Tmatrix2_double)
: Tmatrix2_extended
```

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with double precision values wherever a two-dimensional matrix with extended precision is expected.

**26.3.164 operator :=(Tmatrix2\_double): Tmatrix2\_single**

Synopsis: Allow assignment of two-dimensional double precision matrix to two-dimensional single precision matrix

Declaration: `operator operator :=(Tmatrix2_double): Tmatrix2_single`

```
(const v: Tmatrix2_double)
: Tmatrix2_single
```

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with double precision values wherever a two-dimensional matrix with single precision is expected. Some accuracy is lost because of the conversion.

**26.3.165 operator :=(Tmatrix2\_double): Tmatrix3\_double**

Synopsis: Allow assignment of two-dimensional double precision matrix to three-dimensional double precision matrix

Declaration: `operator operator :=(Tmatrix2_double): Tmatrix3_double`

```
(const v: Tmatrix2_double)
: Tmatrix3_double
```

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with double precision values wherever a three-dimensional matrix with double precision is expected. The extra fields are set to 0.

### 26.3.166 operator :=(Tmatrix2\_double): Tmatrix3\_extended

Synopsis: Allow assignment of two-dimensional double precision matrix to three-dimensional extended precision matrix

Declaration: `operator operator :=(Tmatrix2_double): Tmatrix3_extended`  
`(const v: Tmatrix2_double)`  
`: Tmatrix3_extended`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with double precision values wherever a three-dimensional matrix with extended precision is expected. The extra fields are set to 0.

### 26.3.167 operator :=(Tmatrix2\_double): Tmatrix3\_single

Synopsis: Allow assignment of two-dimensional single precision matrix to three-dimensional single precision matrix

Declaration: `operator operator :=(Tmatrix2_double): Tmatrix3_single`  
`(const v: Tmatrix2_double)`  
`: Tmatrix3_single`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with single precision values wherever a three-dimensional matrix with single precision is expected. The extra fields are set to 0 and some accuracy is lost because of the conversion.

### 26.3.168 operator :=(Tmatrix2\_double): Tmatrix4\_double

Synopsis: Allow assignment of two-dimensional double precision matrix to four-dimensional double precision matrix

Declaration: `operator operator :=(Tmatrix2_double): Tmatrix4_double`  
`(const v: Tmatrix2_double)`  
`: Tmatrix4_double`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with double precision values wherever a four-dimensional matrix with double precision is expected. The extra fields are set to 0.

### 26.3.169 operator :=(Tmatrix2\_double): Tmatrix4\_extended

Synopsis: Allow assignment of two-dimensional double precision matrix to four-dimensional extended precision matrix

Declaration: `operator operator :=(Tmatrix2_double): Tmatrix4_extended`  
`(const v: Tmatrix2_double)`  
`: Tmatrix4_extended`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with double precision values wherever a four-dimensional matrix with extended precision is expected. The extra fields are set to 0.

**26.3.170 operator :=(Tmatrix2\_double): Tmatrix4\_single**

Synopsis: Allow assignment of two-dimensional double precision matrix to four-dimensional single precision matrix

Declaration: `operator operator :=(Tmatrix2_double): Tmatrix4_single`  
`(const v: Tmatrix2_double)`  
`: Tmatrix4_single`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with double precision values wherever a four-dimensional matrix with single precision is expected. The extra fields are set to 0 and some precision is lost because of the conversion.

**26.3.171 operator :=(Tmatrix2\_extended): Tmatrix2\_double**

Synopsis: Allow assignment of two-dimensional extended precision matrix to two-dimensional double precision matrix

Declaration: `operator operator :=(Tmatrix2_extended): Tmatrix2_double`  
`(const v: Tmatrix2_extended)`  
`: Tmatrix2_double`

Visibility: default

Description: This operator allows you to use a two-dimensional two with extended precision values wherever a two-dimensional matrix with double precision is expected. Some accuracy is lost because of the conversion.

**26.3.172 operator :=(Tmatrix2\_extended): Tmatrix2\_single**

Synopsis: Allow assignment of two-dimensional extended precision matrix to two-dimensional single precision matrix

Declaration: `operator operator :=(Tmatrix2_extended): Tmatrix2_single`  
`(const v: Tmatrix2_extended)`  
`: Tmatrix2_single`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with extended precision values wherever a two-dimensional matrix with single precision is expected. Some accuracy is lost because of the conversion.

**26.3.173 operator :=(Tmatrix2\_extended): Tmatrix3\_double**

Synopsis: Allow assignment of two-dimensional extended precision matrix to three-dimensional double precision matrix

Declaration: `operator operator :=(Tmatrix2_extended): Tmatrix3_double`  
`(const v: Tmatrix2_extended)`  
`: Tmatrix3_double`

Visibility: default

**Description:** This operator allows you to use a two-dimensional matrix with extended precision values wherever a three-dimensional matrix with double precision is expected. The extra fields are set to 0 and some accuracy is lost because of the conversion.

### 26.3.174 operator :=(Tmatrix2\_extended): Tmatrix3\_extended

**Synopsis:** Allow assignment of two-dimensional extended precision matrix to three-dimensional extended precision matrix

**Declaration:** `operator operator :=(Tmatrix2_extended): Tmatrix3_extended`  
`(const v: Tmatrix2_extended): Tmatrix3_extended`

**Visibility:** default

**Description:** This operator allows you to use a two-dimensional matrix with extended precision values wherever a three-dimensional matrix with extended precision is expected. The extra fields are set to 0.

### 26.3.175 operator :=(Tmatrix2\_extended): Tmatrix3\_single

**Synopsis:** Allow assignment of two-dimensional extended precision matrix to three-dimensional single precision matrix

**Declaration:** `operator operator :=(Tmatrix2_extended): Tmatrix3_single`  
`(const v: Tmatrix2_extended): Tmatrix3_single`

**Visibility:** default

**Description:** This operator allows you to use a two-dimensional matrix with extended precision values wherever a three-dimensional matrix with single precision is expected. The extra fields are set to 0 and some accuracy is lost because of the conversion.

### 26.3.176 operator :=(Tmatrix2\_extended): Tmatrix4\_double

**Synopsis:** Allow assignment of two-dimensional extended precision matrix to four-dimensional double precision matrix

**Declaration:** `operator operator :=(Tmatrix2_extended): Tmatrix4_double`  
`(const v: Tmatrix2_extended): Tmatrix4_double`

**Visibility:** default

**Description:** This operator allows you to use a two-dimensional matrix with extended precision values wherever a four-dimensional matrix with double precision is expected. The extra fields are set to 0 and some accuracy is lost because of the conversion.

### 26.3.177 operator :=(Tmatrix2\_extended): Tmatrix4\_extended

**Synopsis:** Allow assignment of two-dimensional extended precision matrix to four-dimensional extended precision matrix

**Declaration:** `operator operator :=(Tmatrix2_extended): Tmatrix4_extended`  
`(const v: Tmatrix2_extended): Tmatrix4_extended`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with single precision values wherever a four-dimensional matrix with single precision is expected. The extra fields are set to 0.

### 26.3.178 operator :=(Tmatrix2\_extended): Tmatrix4\_single

Synopsis: Allow assignment of two-dimensional extended precision matrix to four-dimensional single precision matrix

Declaration: `operator operator :=(Tmatrix2_extended): Tmatrix4_single`  
`(const v: Tmatrix2_extended)`  
`: Tmatrix4_single`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with extended precision values wherever a four-dimensional matrix with single precision is expected. The extra fields are set to 0 and some precision is lost because of the conversion.

### 26.3.179 operator :=(Tmatrix2\_single): Tmatrix2\_double

Synopsis: Allow assignment of two-dimensional single precision matrix to two-dimensional double precision matrix

Declaration: `operator operator :=(Tmatrix2_single): Tmatrix2_double`  
`(const v: Tmatrix2_single)`  
`: Tmatrix2_double`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with single precision values wherever a two-dimensional matrix with double precision is expected.

### 26.3.180 operator :=(Tmatrix2\_single): Tmatrix2\_extended

Synopsis: Allow assignment of two-dimensional single precision matrix to two-dimensional extended precision matrix

Declaration: `operator operator :=(Tmatrix2_single): Tmatrix2_extended`  
`(const v: Tmatrix2_single)`  
`: Tmatrix2_extended`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with single precision values wherever a two-dimensional matrix with extended precision is expected.

### 26.3.181 operator :=(Tmatrix2\_single): Tmatrix3\_double

Synopsis: Allow assignment of two-dimensional single precision matrix to three-dimensional double precision matrix

Declaration: `operator operator :=(Tmatrix2_single): Tmatrix3_double`  
`(const v: Tmatrix2_single)`  
`: Tmatrix3_double`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with single precision values wherever a three-dimensional matrix with double precision is expected. The extra fields are set to 0.

### 26.3.182 operator :=(Tmatrix2\_single): Tmatrix3\_extended

Synopsis: Allow assignment of two-dimensional single precision matrix to three-dimensional extended precision matrix

Declaration: `operator operator :=(Tmatrix2_single): Tmatrix3_extended`  
`(const v: Tmatrix2_single)`  
`: Tmatrix3_extended`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with single precision values wherever a three-dimensional matrix with extended precision is expected. The extra fields are set to 0.

### 26.3.183 operator :=(Tmatrix2\_single): Tmatrix3\_single

Synopsis: Allow assignment of two-dimensional single precision matrix to three-dimensional single precision matrix

Declaration: `operator operator :=(Tmatrix2_single): Tmatrix3_single`  
`(const v: Tmatrix2_single)`  
`: Tmatrix3_single`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with single precision values wherever a three-dimensional matrix with single precision is expected. The extra fields are set to 0.

### 26.3.184 operator :=(Tmatrix2\_single): Tmatrix4\_double

Synopsis: Allow assignment of two-dimensional single precision matrix to four-dimensional double precision matrix

Declaration: `operator operator :=(Tmatrix2_single): Tmatrix4_double`  
`(const v: Tmatrix2_single)`  
`: Tmatrix4_double`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with single precision values wherever a four-dimensional matrix with double precision is expected. The extra fields are set to 0.

### 26.3.185 operator :=(Tmatrix2\_single): Tmatrix4\_extended

Synopsis: Allow assignment of two-dimensional single precision matrix to four-dimensional extended precision matrix

Declaration: `operator operator :=(Tmatrix2_single): Tmatrix4_extended`  
`(const v: Tmatrix2_single)`  
`: Tmatrix4_extended`



Visibility: default

Description: This operator allows you to use a two-dimensional matrix with single precision values wherever a four-dimensional matrix with extended precision is expected. The extra fields are set to 0.

### 26.3.186 operator :=(Tmatrix2\_single): Tmatrix4\_single

Synopsis: Allow assignment of two-dimensional single precision matrix to four-dimensional single precision matrix

Declaration: `operator operator :=(Tmatrix2_single): Tmatrix4_single`  
`(const v: Tmatrix2_single)`  
`: Tmatrix4_single`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with single precision values wherever a four-dimensional matrix with single precision is expected. The extra fields are set to 0.

### 26.3.187 operator :=(Tmatrix3\_double): Tmatrix2\_double

Synopsis: Allow assignment of three-dimensional double precision matrix to two-dimensional double precision matrix

Declaration: `operator operator :=(Tmatrix3_double): Tmatrix2_double`  
`(const v: Tmatrix3_double)`  
`: Tmatrix2_double`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with double precision values wherever a two-dimensional matrix with double precision is expected. The surplus fields are thrown away.

### 26.3.188 operator :=(Tmatrix3\_double): Tmatrix2\_extended

Synopsis: Allow assignment of three-dimensional double precision matrix to two-dimensional extended precision matrix

Declaration: `operator operator :=(Tmatrix3_double): Tmatrix2_extended`  
`(const v: Tmatrix3_double)`  
`: Tmatrix2_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with double precision values wherever a two-dimensional matrix with extended precision is expected. The surplus fields are thrown away.

### 26.3.189 operator :=(Tmatrix3\_double): Tmatrix2\_single

Synopsis: Allow assignment of three-dimensional double precision matrix to two-dimensional single precision matrix

Declaration: `operator operator :=(Tmatrix3_double): Tmatrix2_single`  
`(const v: Tmatrix3_double)`  
`: Tmatrix2_single`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with double precision values wherever a two-dimensional matrix with single precision is expected. The surplus fields are thrown away and some accuracy is lost because of the conversion.

### 26.3.190 operator :=(Tmatrix3\_double): Tmatrix3\_extended

Synopsis: Allow assignment of three-dimensional double precision matrix to three-dimensional extended precision matrix

Declaration: `operator operator :=(Tmatrix3_double): Tmatrix3_extended`  
`(const v: Tmatrix3_double)`  
`: Tmatrix3_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with double precision values wherever a three-dimensional matrix with extended precision is expected.

### 26.3.191 operator :=(Tmatrix3\_double): Tmatrix3\_single

Synopsis: Allow assignment of three-dimensional double precision matrix to three-dimensional single precision matrix

Declaration: `operator operator :=(Tmatrix3_double): Tmatrix3_single`  
`(const v: Tmatrix3_double)`  
`: Tmatrix3_single`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with double precision values wherever a three-dimensional matrix with single precision is expected. Some precision is lost because of the conversion.

### 26.3.192 operator :=(Tmatrix3\_double): Tmatrix4\_double

Synopsis: Allow assignment of three-dimensional double precision matrix to four-dimensional double precision matrix

Declaration: `operator operator :=(Tmatrix3_double): Tmatrix4_double`  
`(const v: Tmatrix3_double)`  
`: Tmatrix4_double`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with double precision values wherever a four-dimensional matrix with double precision is expected.

### 26.3.193 operator :=(Tmatrix3\_double): Tmatrix4\_extended

Synopsis: Allow assignment of three-dimensional double precision matrix to four-dimensional extended precision matrix

**Declaration:** `operator operator := (Tmatrix3_double) : Tmatrix4_extended`  
`(const v: Tmatrix3_double)`  
`: Tmatrix4_extended`

**Visibility:** default

**Description:** This operator allows you to use a three-dimensional matrix with double precision values wherever a four-dimensional matrix with extended precision is expected.

### 26.3.194 operator :=(Tmatrix3\_double): Tmatrix4\_single

**Synopsis:** Allow assignment of three-dimensional double precision matrix to four-dimensional single precision matrix

**Declaration:** `operator operator := (Tmatrix3_double) : Tmatrix4_single`  
`(const v: Tmatrix3_double)`  
`: Tmatrix4_single`

**Visibility:** default

**Description:** This operator allows you to use a three-dimensional matrix with double precision values wherever a four-dimensional matrix with single precision is expected. Some precision is lost because of the conversion.

### 26.3.195 operator :=(Tmatrix3\_extended): Tmatrix2\_double

**Synopsis:** Allow assignment of three-dimensional extended precision matrix to two-dimensional double precision matrix

**Declaration:** `operator operator := (Tmatrix3_extended) : Tmatrix2_double`  
`(const v: Tmatrix3_extended)`  
`: Tmatrix2_double`

**Visibility:** default

**Description:** This operator allows you to use a three-dimensional matrix with extended precision values wherever a two-dimensional matrix with double precision is expected. The surplus fields are thrown away and some accuracy is lost because of the conversion.

### 26.3.196 operator :=(Tmatrix3\_extended): Tmatrix2\_extended

**Synopsis:** Allow assignment of three-dimensional extended precision matrix to two-dimensional extended precision matrix

**Declaration:** `operator operator := (Tmatrix3_extended) : Tmatrix2_extended`  
`(const v: Tmatrix3_extended)`  
`: Tmatrix2_extended`

**Visibility:** default

**Description:** This operator allows you to use a three-dimensional matrix with extended precision values wherever a two-dimensional matrix with extended precision is expected. The surplus fields are thrown away.

**26.3.197 operator :=(Tmatrix3\_extended): Tmatrix2\_single**

Synopsis: Allow assignment of three-dimensional extended precision matrix to two-dimensional single precision matrix

Declaration: `operator operator :=(Tmatrix3_extended) : Tmatrix2_single`  
`(const v: Tmatrix3_extended)`  
`: Tmatrix2_single`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with extended precision values wherever a two-dimensional matrix with single precision is expected. The surplus fields are thrown away and some precision is lost because of the conversion.

**26.3.198 operator :=(Tmatrix3\_extended): Tmatrix3\_double**

Synopsis: Allow assignment of three-dimensional extended precision matrix to three-dimensional double precision matrix

Declaration: `operator operator :=(Tmatrix3_extended) : Tmatrix3_double`  
`(const v: Tmatrix3_extended)`  
`: Tmatrix3_double`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with extended precision values wherever a three-dimensional matrix with double precision is expected. Some precision is lost because of the conversion.

**26.3.199 operator :=(Tmatrix3\_extended): Tmatrix3\_single**

Synopsis: Allow assignment of three-dimensional extended precision matrix to three-dimensional single precision matrix

Declaration: `operator operator :=(Tmatrix3_extended) : Tmatrix3_single`  
`(const v: Tmatrix3_extended)`  
`: Tmatrix3_single`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with extended precision values wherever a three-dimensional matrix with single precision is expected. Some precision is lost because of the conversion.

**26.3.200 operator :=(Tmatrix3\_extended): Tmatrix4\_double**

Synopsis: Allow assignment of three-dimensional extended precision matrix to four-dimensional double precision matrix

Declaration: `operator operator :=(Tmatrix3_extended) : Tmatrix4_double`  
`(const v: Tmatrix3_extended)`  
`: Tmatrix4_double`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with extended precision values wherever a four-dimensional matrix with double precision is expected. Some precision is lost because of the conversion.

**26.3.201 operator :=(Tmatrix3\_extended): Tmatrix4\_extended**

Synopsis: Allow assignment of three-dimensional extended precision matrix to four-dimensional extended precision matrix

Declaration: `operator operator :=(Tmatrix3_extended): Tmatrix4_extended`  
`(const v: Tmatrix3_extended): Tmatrix4_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with extended precision values wherever a four-dimensional matrix with extended precision is expected.

**26.3.202 operator :=(Tmatrix3\_extended): Tmatrix4\_single**

Synopsis: Allow assignment of three-dimensional extended precision matrix to four-dimensional single precision matrix

Declaration: `operator operator :=(Tmatrix3_extended): Tmatrix4_single`  
`(const v: Tmatrix3_extended): Tmatrix4_single`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with extended precision values wherever a four-dimensional matrix with single precision is expected. Some precision is lost because of the conversion.

**26.3.203 operator :=(Tmatrix3\_single): Tmatrix2\_double**

Synopsis: Allow assignment of three-dimensional single precision matrix to two-dimensional double precision matrix

Declaration: `operator operator :=(Tmatrix3_single): Tmatrix2_double`  
`(const v: Tmatrix3_single): Tmatrix2_double`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with single precision values wherever a two-dimensional matrix with double precision is expected. The surplus fields are thrown away.

**26.3.204 operator :=(Tmatrix3\_single): Tmatrix2\_extended**

Synopsis: Allow assignment of three-dimensional single precision matrix to two-dimensional extended precision matrix

Declaration: `operator operator :=(Tmatrix3_single): Tmatrix2_extended`  
`(const v: Tmatrix3_single): Tmatrix2_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with single precision values wherever a two-dimensional matrix with extended precision is expected. The surplus fields are thrown away.

**26.3.205 operator :=(Tmatrix3\_single): Tmatrix2\_single**

Synopsis: Allow assignment of three-dimensional single precision matrix to two-dimensional single precision matrix

Declaration: `operator operator :=(Tmatrix3_single): Tmatrix2_single`  
`(const v: Tmatrix3_single)`  
`: Tmatrix2_single`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with single precision values wherever a two-dimensional matrix with single precision is expected. The surplus fields are thrown away.

**26.3.206 operator :=(Tmatrix3\_single): Tmatrix3\_double**

Synopsis: Allow assignment of three-dimensional single precision matrix to three-dimensional double precision matrix

Declaration: `operator operator :=(Tmatrix3_single): Tmatrix3_double`  
`(const v: Tmatrix3_single)`  
`: Tmatrix3_double`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with single precision values wherever a three-dimensional matrix with double precision is expected.

**26.3.207 operator :=(Tmatrix3\_single): Tmatrix3\_extended**

Synopsis: Allow assignment of three-dimensional single precision matrix to three-dimensional extended precision matrix

Declaration: `operator operator :=(Tmatrix3_single): Tmatrix3_extended`  
`(const v: Tmatrix3_single)`  
`: Tmatrix3_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with single precision values wherever a three-dimensional matrix with extended precision is expected.

**26.3.208 operator :=(Tmatrix3\_single): Tmatrix4\_double**

Synopsis: Allow assignment of three-dimensional single precision matrix to four-dimensional double precision matrix

Declaration: `operator operator :=(Tmatrix3_single): Tmatrix4_double`  
`(const v: Tmatrix3_single)`  
`: Tmatrix4_double`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with single precision values wherever a four-dimensional matrix with double precision is expected.

**26.3.209 operator :=(Tmatrix3\_single): Tmatrix4\_extended**

Synopsis: Allow assignment of three-dimensional single precision matrix to four-dimensional extended precision matrix

Declaration: `operator operator :=(Tmatrix3_single): Tmatrix4_extended`  
`(const v: Tmatrix3_single)`  
`: Tmatrix4_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with single precision values wherever a four-dimensional matrix with extended precision is expected.

**26.3.210 operator :=(Tmatrix3\_single): Tmatrix4\_single**

Synopsis: Allow assignment of three-dimensional single precision matrix to four-dimensional single precision matrix

Declaration: `operator operator :=(Tmatrix3_single): Tmatrix4_single`  
`(const v: Tmatrix3_single)`  
`: Tmatrix4_single`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with single precision values wherever a four-dimensional matrix with single precision is expected.

**26.3.211 operator :=(Tmatrix4\_double): Tmatrix2\_double**

Synopsis: Allow assignment of four-dimensional double precision matrix to two-dimensional double precision matrix

Declaration: `operator operator :=(Tmatrix4_double): Tmatrix2_double`  
`(const v: Tmatrix4_double)`  
`: Tmatrix2_double`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with double precision values wherever a two-dimensional matrix with double precision is expected. The surplus fields are thrown away.

**26.3.212 operator :=(Tmatrix4\_double): Tmatrix2\_extended**

Synopsis: Allow assignment of four-dimensional double precision matrix to two-dimensional extended precision matrix

Declaration: `operator operator :=(Tmatrix4_double): Tmatrix2_extended`  
`(const v: Tmatrix4_double)`  
`: Tmatrix2_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with double precision values wherever a two-dimensional matrix with extended precision is expected. The surplus fields are thrown away.

**26.3.213 operator :=(Tmatrix4\_double): Tmatrix2\_single**

Synopsis: Allow assignment of four-dimensional double precision matrix to two-dimensional single precision matrix

Declaration: `operator operator :=(Tmatrix4_double): Tmatrix2_single`  
`(const v: Tmatrix4_double)`  
`: Tmatrix2_single`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with double precision values wherever a two-dimensional matrix with single precision is expected. The surplus fields are thrown away and some precision is lost in the conversion.

**26.3.214 operator :=(Tmatrix4\_double): Tmatrix3\_double**

Synopsis: Allow assignment of four-dimensional double precision matrix to three-dimensional double precision matrix

Declaration: `operator operator :=(Tmatrix4_double): Tmatrix3_double`  
`(const v: Tmatrix4_double)`  
`: Tmatrix3_double`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with double precision values wherever a three-dimensional matrix with double precision is expected. The surplus fields are thrown away.

**26.3.215 operator :=(Tmatrix4\_double): Tmatrix3\_extended**

Synopsis: Allow assignment of four-dimensional double precision matrix to three-dimensional extended precision matrix

Declaration: `operator operator :=(Tmatrix4_double): Tmatrix3_extended`  
`(const v: Tmatrix4_double)`  
`: Tmatrix3_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with double precision values wherever a three-dimensional matrix with extended precision is expected. The surplus fields are thrown away.

**26.3.216 operator :=(Tmatrix4\_double): Tmatrix3\_single**

Synopsis: Allow assignment of four-dimensional double precision matrix to three-dimensional single precision matrix

Declaration: `operator operator :=(Tmatrix4_double): Tmatrix3_single`  
`(const v: Tmatrix4_double)`  
`: Tmatrix3_single`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with double precision values wherever a three-dimensional matrix with single precision is expected. The surplus fields are thrown away and some precision is lost because of the conversion.



**26.3.217 operator :=(Tmatrix4\_double): Tmatrix4\_extended**

Synopsis: Allow assignment of four-dimensional double precision matrix to four-dimensional extended precision matrix

Declaration: `operator operator :=(Tmatrix4_double): Tmatrix4_extended`  
`(const v: Tmatrix4_double)`  
`: Tmatrix4_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with double precision values wherever a four-dimensional matrix with extended precision is expected.

**26.3.218 operator :=(Tmatrix4\_double): Tmatrix4\_single**

Synopsis: Allow assignment of four-dimensional single precision matrix to four-dimensional single precision matrix

Declaration: `operator operator :=(Tmatrix4_double): Tmatrix4_single`  
`(const v: Tmatrix4_double)`  
`: Tmatrix4_single`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with double precision values wherever a four-dimensional matrix with single precision is expected. Some precision is lost because of the conversion.

**26.3.219 operator :=(Tmatrix4\_extended): Tmatrix2\_double**

Synopsis: Allow assignment of four-dimensional extended precision matrix to two-dimensional double precision matrix

Declaration: `operator operator :=(Tmatrix4_extended): Tmatrix2_double`  
`(const v: Tmatrix4_extended)`  
`: Tmatrix2_double`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with extended precision values wherever a two-dimensional matrix with double precision is expected. The surplus fields are thrown away and some precision is lost in the conversion.

**26.3.220 operator :=(Tmatrix4\_extended): Tmatrix2\_extended**

Synopsis: Allow assignment of four-dimensional extended precision matrix to two-dimensional extended precision matrix

Declaration: `operator operator :=(Tmatrix4_extended): Tmatrix2_extended`  
`(const v: Tmatrix4_extended)`  
`: Tmatrix2_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with single precision values wherever a two-dimensional matrix with single precision is expected. The surplus fields are thrown away.

**26.3.221 operator :=(Tmatrix4\_extended): Tmatrix2\_single**

Synopsis: Allow assignment of four-dimensional extended precision matrix to two-dimensional single precision matrix

Declaration: `operator operator :=(Tmatrix4_extended): Tmatrix2_single`  
`(const v: Tmatrix4_extended)`  
`: Tmatrix2_single`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with extended precision values wherever a two-dimensional matrix with single precision is expected. The surplus fields are thrown away and some precision is lost in the conversion.

**26.3.222 operator :=(Tmatrix4\_extended): Tmatrix3\_double**

Synopsis: Allow assignment of four-dimensional extended precision matrix to three-dimensional double precision matrix

Declaration: `operator operator :=(Tmatrix4_extended): Tmatrix3_double`  
`(const v: Tmatrix4_extended)`  
`: Tmatrix3_double`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with extended precision values wherever a three-dimensional matrix with double precision is expected. The surplus fields are thrown away.

**26.3.223 operator :=(Tmatrix4\_extended): Tmatrix3\_extended**

Synopsis: Allow assignment of four-dimensional extended precision matrix to three-dimensional extended precision matrix

Declaration: `operator operator :=(Tmatrix4_extended): Tmatrix3_extended`  
`(const v: Tmatrix4_extended)`  
`: Tmatrix3_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with extended precision values wherever a three-dimensional matrix with double precision is expected. The surplus fields are thrown away.

**26.3.224 operator :=(Tmatrix4\_extended): Tmatrix3\_single**

Synopsis: Allow assignment of four-dimensional extended precision matrix to three-dimensional single precision matrix

Declaration: `operator operator :=(Tmatrix4_extended): Tmatrix3_single`  
`(const v: Tmatrix4_extended)`  
`: Tmatrix3_single`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with extended precision values wherever a three-dimensional matrix with single precision is expected. The surplus fields are thrown away and some precision is lost because of the conversion.

**26.3.225 operator :=(Tmatrix4\_extended): Tmatrix4\_double**

Synopsis: Allow assignment of four-dimensional extended precision matrix to four-dimensional double precision matrix

Declaration: `operator operator :=(Tmatrix4_extended): Tmatrix4_double`  
`(const v: Tmatrix4_extended)`  
`: Tmatrix4_double`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with extended precision values wherever a four-dimensional matrix with double precision is expected.

**26.3.226 operator :=(Tmatrix4\_extended): Tmatrix4\_single**

Synopsis: Allow assignment of four-dimensional extended precision matrix to four-dimensional single precision matrix

Declaration: `operator operator :=(Tmatrix4_extended): Tmatrix4_single`  
`(const v: Tmatrix4_extended)`  
`: Tmatrix4_single`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with extended precision values wherever a four-dimensional matrix with single precision is expected. Some precision is lost because of the conversion.

**26.3.227 operator :=(Tmatrix4\_single): Tmatrix2\_double**

Synopsis: Allow assignment of four-dimensional single precision matrix to two-dimensional double precision matrix

Declaration: `operator operator :=(Tmatrix4_single): Tmatrix2_double`  
`(const v: Tmatrix4_single)`  
`: Tmatrix2_double`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with single precision values wherever a two-dimensional matrix with double precision is expected. The surplus fields are thrown away.

**26.3.228 operator :=(Tmatrix4\_single): Tmatrix2\_extended**

Synopsis: Allow assignment of four-dimensional single precision matrix to two-dimensional extended precision matrix

Declaration: `operator operator :=(Tmatrix4_single): Tmatrix2_extended`  
`(const v: Tmatrix4_single)`  
`: Tmatrix2_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with single precision values wherever a two-dimensional matrix with extended precision is expected. The surplus fields are thrown away.

**26.3.229 operator :=(Tmatrix4\_single): Tmatrix2\_single**

Synopsis: Allow assignment of four-dimensional single precision matrix to two-dimensional single precision matrix

Declaration: `operator operator :=(Tmatrix4_single): Tmatrix2_single`  
`(const v: Tmatrix4_single)`  
`: Tmatrix2_single`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with single precision values wherever a two-dimensional matrix with single precision is expected. The surplus fields are thrown away.

**26.3.230 operator :=(Tmatrix4\_single): Tmatrix3\_double**

Synopsis: Allow assignment of four-dimensional single precision matrix to three-dimensional double precision matrix

Declaration: `operator operator :=(Tmatrix4_single): Tmatrix3_double`  
`(const v: Tmatrix4_single)`  
`: Tmatrix3_double`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with single precision values wherever a three-dimensional matrix with double precision is expected. The surplus fields are thrown away.

**26.3.231 operator :=(Tmatrix4\_single): Tmatrix3\_extended**

Synopsis: Allow assignment of four-dimensional single precision matrix to three-dimensional extended precision matrix

Declaration: `operator operator :=(Tmatrix4_single): Tmatrix3_extended`  
`(const v: Tmatrix4_single)`  
`: Tmatrix3_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with single precision values wherever a three-dimensional matrix with extended precision is expected. The surplus fields are thrown away.

**26.3.232 operator :=(Tmatrix4\_single): Tmatrix3\_single**

Synopsis: Allow assignment of four-dimensional single precision matrix to three-dimensional single precision matrix

Declaration: `operator operator :=(Tmatrix4_single): Tmatrix3_single`  
`(const v: Tmatrix4_single)`  
`: Tmatrix3_single`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with single precision values wherever a three-dimensional matrix with single precision is expected. The surplus fields are thrown away.

**26.3.233 operator :=(Tmatrix4\_single): Tmatrix4\_double**

Synopsis: Allow assignment of four-dimensional single precision matrix to four-dimensional double precision matrix

Declaration: `operator operator :=(Tmatrix4_single): Tmatrix4_double`  
`(const v: Tmatrix4_single)`  
`: Tmatrix4_double`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with single precision values wherever a four-dimensional matrix with double precision is expected.

**26.3.234 operator :=(Tmatrix4\_single): Tmatrix4\_extended**

Synopsis: Allow assignment of four-dimensional single precision matrix to four-dimensional extended precision matrix

Declaration: `operator operator :=(Tmatrix4_single): Tmatrix4_extended`  
`(const v: Tmatrix4_single)`  
`: Tmatrix4_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with single precision values wherever a four-dimensional matrix with extended precision is expected.

**26.3.235 operator :=(Tvector2\_double): Tvector2\_extended**

Synopsis: Allow assignment of double precision vector to extended precision vector

Declaration: `operator operator :=(Tvector2_double): Tvector2_extended`  
`(const v: Tvector2_double)`  
`: Tvector2_extended`

Visibility: default

Description: This operator allows you to use a vector with double precision values wherever an extended precision vector is expected.

**26.3.236 operator :=(Tvector2\_double): Tvector2\_single**

Synopsis: Allow assignment of double precision vector to single precision vector

Declaration: `operator operator :=(Tvector2_double): Tvector2_single`  
`(const v: Tvector2_double)`  
`: Tvector2_single`

Visibility: default

Description: This operator allows you to use a vector with double precision values wherever a single precision vector is expected, at the cost of losing some precision.

**26.3.237 operator :=(Tvector2\_double): Tvector3\_double**

Synopsis: Allow assignment of two-dimensional double precision vector to three-dimensional double precision vector

Declaration: `operator operator :=(Tvector2_double) : Tvector3_double`  
`(const v: Tvector2_double)`  
`: Tvector3_double`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with double precision values wherever a three-dimensional vector with double precision is expected. The third dimension is set to 0.0.

**26.3.238 operator :=(Tvector2\_double): Tvector3\_extended**

Synopsis: Allow assignment of two-dimensional double precision vector to three-dimensional extended precision vector

Declaration: `operator operator :=(Tvector2_double) : Tvector3_extended`  
`(const v: Tvector2_double)`  
`: Tvector3_extended`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with double precision values wherever a three-dimensional vector with extended precision is expected. The third dimension is set to 0.0.

**26.3.239 operator :=(Tvector2\_double): Tvector3\_single**

Synopsis: Allow assignment of two-dimensional double precision vector to three-dimensional single precision vector

Declaration: `operator operator :=(Tvector2_double) : Tvector3_single`  
`(const v: Tvector2_double)`  
`: Tvector3_single`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with double precision values wherever a three-dimensional vector with single precision is expected. Some accuracy is lost because of the conversion and the third dimension is set to 0.0.

**26.3.240 operator :=(Tvector2\_double): Tvector4\_double**

Synopsis: Allow assignment of two-dimensional double precision vector to four-dimensional double precision vector

Declaration: `operator operator :=(Tvector2_double) : Tvector4_double`  
`(const v: Tvector2_double)`  
`: Tvector4_double`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with double precision values wherever a four-dimensional vector with double precision is expected. The third and fourth dimensions are set to 0.0.

**26.3.241 operator :=(Tvector2\_double): Tvector4\_extended**

Synopsis: Allow assignment of two-dimensional double precision vector to four-dimensional extended precision vector

Declaration: `operator operator :=(Tvector2_double): Tvector4_extended`  
`(const v: Tvector2_double)`  
`: Tvector4_extended`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with single precision values wherever a four-dimensional vector with extended precision is expected. The third and fourth dimensions are set to 0.0.

**26.3.242 operator :=(Tvector2\_double): Tvector4\_single**

Synopsis: Allow assignment of two-dimensional double precision vector to four-dimensional single precision vector

Declaration: `operator operator :=(Tvector2_double): Tvector4_single`  
`(const v: Tvector2_double)`  
`: Tvector4_single`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with double precision values wherever a four-dimensional vector with single precision is expected. Some accuracy is lost because of the conversion and the third and fourth dimensions are set to 0.0.

**26.3.243 operator :=(Tvector2\_extended): Tvector2\_double**

Synopsis: Allow assignment of extended precision vector to double precision vector

Declaration: `operator operator :=(Tvector2_extended): Tvector2_double`  
`(const v: Tvector2_extended)`  
`: Tvector2_double`

Visibility: default

Description: This operator allows you to use a vector with extended precision values wherever a double precision vector is expected, at the cost of losing some precision.

**26.3.244 operator :=(Tvector2\_extended): Tvector2\_single**

Synopsis: Allow assignment of extended precision vector to single precision vector

Declaration: `operator operator :=(Tvector2_extended): Tvector2_single`  
`(const v: Tvector2_extended)`  
`: Tvector2_single`

Visibility: default

Description: This operator allows you to use a vector with extended precision values wherever a single precision vector is expected, at the cost of losing some precision.

**26.3.245 operator :=(Tvector2\_extended): Tvector3\_double**

Synopsis: Allow assignment of two-dimensional extended precision vector to three-dimensional double precision vector

Declaration: `operator operator :=(Tvector2_extended) : Tvector3_double`  
`(const v: Tvector2_extended)`  
`: Tvector3_double`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with extended precision values wherever a three-dimensional vector with double precision is expected. Some accuracy is lost because of the conversion and the third dimension is set to 0.0.

**26.3.246 operator :=(Tvector2\_extended): Tvector3\_extended**

Synopsis: Allow assignment of two-dimensional extended precision vector to three-dimensional extended precision vector

Declaration: `operator operator :=(Tvector2_extended) : Tvector3_extended`  
`(const v: Tvector2_extended)`  
`: Tvector3_extended`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with extended precision values wherever a three-dimensional vector with extended precision is expected. The third dimension is set to 0.0.

**26.3.247 operator :=(Tvector2\_extended): Tvector3\_single**

Synopsis: Allow assignment of two-dimensional extended precision vector to three-dimensional single precision vector

Declaration: `operator operator :=(Tvector2_extended) : Tvector3_single`  
`(const v: Tvector2_extended)`  
`: Tvector3_single`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with extended precision values wherever a three-dimensional vector with single precision is expected. Some accuracy is lost because of the conversion and the third dimension is set to 0.0.

**26.3.248 operator :=(Tvector2\_extended): Tvector4\_double**

Synopsis: Allow assignment of two-dimensional extended precision vector to four-dimensional double precision vector

Declaration: `operator operator :=(Tvector2_extended) : Tvector4_double`  
`(const v: Tvector2_extended)`  
`: Tvector4_double`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with extended precision values wherever a four-dimensional vector with double precision is expected. Some accuracy is lost because of the conversion and the third and fourth dimensions are set to 0.0.



**26.3.249 operator :=(Tvector2\_extended): Tvector4\_extended**

Synopsis: Allow assignment of two-dimensional extended precision vector to four-dimensional extended precision vector

Declaration: `operator operator :=(Tvector2_extended) : Tvector4_extended`  
`(const v: Tvector2_extended)`  
`: Tvector4_extended`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with extended precision values wherever a four-dimensional vector with extended precision is expected. The third and fourth dimensions are set to 0.0.

**26.3.250 operator :=(Tvector2\_extended): Tvector4\_single**

Synopsis: Allow assignment of two-dimensional extended precision vector to four-dimensional single precision vector

Declaration: `operator operator :=(Tvector2_extended) : Tvector4_single`  
`(const v: Tvector2_extended)`  
`: Tvector4_single`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with extended precision values wherever a four-dimensional vector with single precision is expected. Some accuracy is lost because of the conversion and the third and fourth dimensions are set to 0.0.

**26.3.251 operator :=(Tvector2\_single): Tvector2\_double**

Synopsis: Allow assignment of single precision vector to double precision vector

Declaration: `operator operator :=(Tvector2_single) : Tvector2_double`  
`(const v: Tvector2_single)`  
`: Tvector2_double`

Visibility: default

Description: This operator allows you to use a vector with single precision values wherever a double precision vector is expected.

**26.3.252 operator :=(Tvector2\_single): Tvector2\_extended**

Synopsis: Allow assignment of single precision vector to extended precision vector

Declaration: `operator operator :=(Tvector2_single) : Tvector2_extended`  
`(const v: Tvector2_single)`  
`: Tvector2_extended`

Visibility: default

Description: This operator allows you to use a vector with single precision values wherever an extended precision vector is expected.

**26.3.253 operator :=(Tvector2\_single): Tvector3\_double**

Synopsis: Allow assignment of two-dimensional single precision vector to three-dimensional double precision vector

Declaration: `operator operator :=(Tvector2_single): Tvector3_double`  
`(const v: Tvector2_single)`  
`: Tvector3_double`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with single precision values wherever a three-dimensional vector with double precision is expected. The third dimension is set to 0.0.

**26.3.254 operator :=(Tvector2\_single): Tvector3\_extended**

Synopsis: Allow assignment of two-dimensional single precision vector to three-dimensional extended precision vector

Declaration: `operator operator :=(Tvector2_single): Tvector3_extended`  
`(const v: Tvector2_single)`  
`: Tvector3_extended`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with single precision values wherever a three-dimensional vector with extended precision is expected. The third dimension is set to 0.0.

**26.3.255 operator :=(Tvector2\_single): Tvector3\_single**

Synopsis: Allow assignment of two-dimensional single precision vector to three-dimensional single precision vector

Declaration: `operator operator :=(Tvector2_single): Tvector3_single`  
`(const v: Tvector2_single)`  
`: Tvector3_single`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with single precision values wherever a three-dimensional vector with single precision is expected. The third dimension is set to 0.0.

**26.3.256 operator :=(Tvector2\_single): Tvector4\_double**

Synopsis: Allow assignment of two-dimensional single precision vector to four-dimensional double precision vector

Declaration: `operator operator :=(Tvector2_single): Tvector4_double`  
`(const v: Tvector2_single)`  
`: Tvector4_double`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with single precision values wherever a four-dimensional vector with double precision is expected. The third and fourth dimensions are set to 0.0.

**26.3.257 operator :=(Tvector2\_single): Tvector4\_extended**

Synopsis: Allow assignment of two-dimensional single precision vector to four-dimensional extended precision vector

Declaration: `operator operator :=(Tvector2_single): Tvector4_extended`  
`(const v: Tvector2_single)`  
`: Tvector4_extended`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with single precision values wherever a four-dimensional vector with extended precision is expected. The third and fourth dimensions are set to 0.0.

**26.3.258 operator :=(Tvector2\_single): Tvector4\_single**

Synopsis: Allow assignment of two-dimensional single precision vector to four-dimensional single precision vector

Declaration: `operator operator :=(Tvector2_single): Tvector4_single`  
`(const v: Tvector2_single)`  
`: Tvector4_single`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with single precision values wherever a four-dimensional vector with single precision is expected. The third and fourth dimensions are set to 0.0.

**26.3.259 operator :=(Tvector3\_double): Tvector2\_double**

Synopsis: Allow assignment of three-dimensional double precision vector to two-dimensional double precision vector

Declaration: `operator operator :=(Tvector3_double): Tvector2_double`  
`(const v: Tvector3_double)`  
`: Tvector2_double`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with double precision values wherever a two-dimensional vector with double precision is expected. The third dimension is thrown away.

**26.3.260 operator :=(Tvector3\_double): Tvector2\_extended**

Synopsis: Allow assignment of three-dimensional double precision vector to two-dimensional extended precision vector

Declaration: `operator operator :=(Tvector3_double): Tvector2_extended`  
`(const v: Tvector3_double)`  
`: Tvector2_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with double precision values wherever a two-dimensional vector with extended precision is expected. The third dimension is thrown away.

**26.3.261 operator :=(Tvector3\_double): Tvector2\_single**

Synopsis: Allow assignment of three-dimensional double precision vector to two-dimensional single precision vector

Declaration: `operator operator :=(Tvector3_double): Tvector2_single`  
`(const v: Tvector3_double)`  
`: Tvector2_single`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with double precision values wherever a two-dimensional vector with single precision is expected. The third dimension is thrown away and some precision is lost because of the conversion.

**26.3.262 operator :=(Tvector3\_double): Tvector3\_extended**

Synopsis: Allow assignment of three-dimensional double precision vector to three-dimensional extended precision vector

Declaration: `operator operator :=(Tvector3_double): Tvector3_extended`  
`(const v: Tvector3_double)`  
`: Tvector3_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with double precision values wherever a three-dimensional vector with extended precision is expected.

**26.3.263 operator :=(Tvector3\_double): Tvector3\_single**

Synopsis: Allow assignment of three-dimensional double precision vector to three-dimensional single precision vector

Declaration: `operator operator :=(Tvector3_double): Tvector3_single`  
`(const v: Tvector3_double)`  
`: Tvector3_single`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with double precision values wherever a three-dimensional vector with single precision is expected. Some precision is lost because of the conversion.

**26.3.264 operator :=(Tvector3\_double): Tvector4\_double**

Synopsis: Allow assignment of three-dimensional double precision vector to four-dimensional double precision vector

Declaration: `operator operator :=(Tvector3_double): Tvector4_double`  
`(const v: Tvector3_double)`  
`: Tvector4_double`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with double precision values wherever a four-dimensional vector with double precision is expected. The fourth dimension is set to 0.

**26.3.265 operator :=(Tvector3\_double): Tvector4\_extended**

Synopsis: Allow assignment of three-dimensional double precision vector to four-dimensional extended precision vector

Declaration: `operator operator :=(Tvector3_double): Tvector4_extended`  
`(const v: Tvector3_double)`  
`: Tvector4_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with double precision values wherever a four-dimensional vector with extended precision is expected. The fourth dimension is set to 0.

**26.3.266 operator :=(Tvector3\_double): Tvector4\_single**

Synopsis: Allow assignment of three-dimensional double precision vector to four-dimensional single precision vector

Declaration: `operator operator :=(Tvector3_double): Tvector4_single`  
`(const v: Tvector3_double)`  
`: Tvector4_single`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with single precision values wherever a four-dimensional vector with double precision is expected. The fourth dimension is set to 0 and some precision is lost because of the conversion.

**26.3.267 operator :=(Tvector3\_extended): Tvector2\_double**

Synopsis: Allow assignment of three-dimensional extended precision vector to two-dimensional double precision vector

Declaration: `operator operator :=(Tvector3_extended): Tvector2_double`  
`(const v: Tvector3_extended)`  
`: Tvector2_double`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with extended precision values wherever a two-dimensional vector with double precision is expected. The third dimension is thrown away and some precision is lost because of the conversion.

**26.3.268 operator :=(Tvector3\_extended): Tvector2\_extended**

Synopsis: Allow assignment of three-dimensional extended precision vector to two-dimensional extended precision vector

Declaration: `operator operator :=(Tvector3_extended): Tvector2_extended`  
`(const v: Tvector3_extended)`  
`: Tvector2_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with extended precision values wherever a two-dimensional vector with extended precision is expected. The third dimension is thrown away.

**26.3.269 operator :=(Tvector3\_extended): Tvector2\_single**

Synopsis: Allow assignment of three-dimensional extended precision vector to two-dimensional single precision vector

Declaration: `operator operator :=(Tvector3_extended) : Tvector2_single`  
`(const v: Tvector3_extended)`  
`: Tvector2_single`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with extended precision values wherever a two-dimensional vector with single precision is expected. The third dimension is thrown away and some precision is lost because of the conversion.

**26.3.270 operator :=(Tvector3\_extended): Tvector3\_double**

Synopsis: Allow assignment of three-dimensional extended precision vector to three-dimensional double precision vector

Declaration: `operator operator :=(Tvector3_extended) : Tvector3_double`  
`(const v: Tvector3_extended)`  
`: Tvector3_double`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with extended precision values wherever a three-dimensional vector with double precision is expected. Some precision is lost because of the conversion.

**26.3.271 operator :=(Tvector3\_extended): Tvector3\_single**

Synopsis: Allow assignment of three-dimensional single precision vector to three-dimensional double precision vector

Declaration: `operator operator :=(Tvector3_extended) : Tvector3_single`  
`(const v: Tvector3_extended)`  
`: Tvector3_single`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with single precision values wherever a three-dimensional vector with double precision is expected. Some precision is lost because of the conversion.

**26.3.272 operator :=(Tvector3\_extended): Tvector4\_double**

Synopsis: Allow assignment of three-dimensional extended precision vector to four-dimensional double precision vector

Declaration: `operator operator :=(Tvector3_extended) : Tvector4_double`  
`(const v: Tvector3_extended)`  
`: Tvector4_double`

Visibility: default

**Description:** This operator allows you to use a three-dimensional vector with extended precision values wherever a four-dimensional vector with double precision is expected. The fourth dimension is set to 0 and some accuracy is lost because of the conversion.

### 26.3.273 operator :=(Tvector3\_extended): Tvector4\_extended

**Synopsis:** Allow assignment of three-dimensional extended precision vector to four-dimensional extended precision vector

**Declaration:** `operator operator :=(Tvector3_extended): Tvector4_extended`  
`(const v: Tvector3_extended)`  
`: Tvector4_extended`

**Visibility:** default

**Description:** This operator allows you to use a three-dimensional vector with extended precision values wherever a four-dimensional vector with extended precision is expected. The fourth dimension is set to 0.

### 26.3.274 operator :=(Tvector3\_extended): Tvector4\_single

**Synopsis:** Allow assignment of three-dimensional extended precision vector to four-dimensional single precision vector

**Declaration:** `operator operator :=(Tvector3_extended): Tvector4_single`  
`(const v: Tvector3_extended)`  
`: Tvector4_single`

**Visibility:** default

**Description:** This operator allows you to use a three-dimensional vector with extended precision values wherever a four-dimensional vector with single precision is expected. The fourth dimension is set to 0 and some accuracy is lost because of the conversion.

### 26.3.275 operator :=(Tvector3\_single): Tvector2\_double

**Synopsis:** Allow assignment of three-dimensional single precision vector to two-dimensional double precision vector

**Declaration:** `operator operator :=(Tvector3_single): Tvector2_double`  
`(const v: Tvector3_single)`  
`: Tvector2_double`

**Visibility:** default

**Description:** This operator allows you to use a three-dimensional vector with single precision values wherever a two-dimensional vector with double precision is expected. The third dimension is thrown away.

### 26.3.276 operator :=(Tvector3\_single): Tvector2\_extended

**Synopsis:** Allow assignment of three-dimensional single precision vector to two-dimensional extended precision vector

**Declaration:** `operator operator :=(Tvector3_single): Tvector2_extended`  
`(const v: Tvector3_single)`  
`: Tvector2_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with single precision values wherever a two-dimensional vector with extended precision is expected. The third dimension is thrown away.

### 26.3.277 operator :=(Tvector3\_single): Tvector2\_single

Synopsis: Allow assignment of three-dimensional single precision vector to two-dimensional single precision vector

Declaration: `operator operator :=(Tvector3_single): Tvector2_single`  
`(const v: Tvector3_single)`  
`: Tvector2_single`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with single precision values wherever a two-dimensional vector with single precision is expected. The third dimension is thrown away.

### 26.3.278 operator :=(Tvector3\_single): Tvector3\_double

Synopsis: Allow assignment of three-dimensional single precision vector to three-dimensional double precision vector

Declaration: `operator operator :=(Tvector3_single): Tvector3_double`  
`(const v: Tvector3_single)`  
`: Tvector3_double`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with single precision values wherever a three-dimensional vector with double precision is expected.

### 26.3.279 operator :=(Tvector3\_single): Tvector3\_extended

Synopsis: Allow assignment of three-dimensional single precision vector to three-dimensional extended precision vector

Declaration: `operator operator :=(Tvector3_single): Tvector3_extended`  
`(const v: Tvector3_single)`  
`: Tvector3_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with single precision values wherever a three-dimensional vector with extended precision is expected.

### 26.3.280 operator :=(Tvector3\_single): Tvector4\_double

Synopsis: Allow assignment of three-dimensional single precision vector to four-dimensional double precision vector

Declaration: `operator operator :=(Tvector3_single): Tvector4_double`  
`(const v: Tvector3_single)`  
`: Tvector4_double`



Visibility: default

Description: This operator allows you to use a three-dimensional vector with single precision values wherever a four-dimensional vector with double precision is expected. The fourth dimension is set to 0.

### 26.3.281 operator :=(Tvector3\_single): Tvector4\_extended

Synopsis: Allow assignment of three-dimensional single precision vector to four-dimensional extended precision vector

Declaration: `operator operator :=(Tvector3_single): Tvector4_extended`  
`(const v: Tvector3_single)`  
`: Tvector4_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with single precision values wherever a four-dimensional vector with extended precision is expected. The fourth dimension is set to 0.

### 26.3.282 operator :=(Tvector3\_single): Tvector4\_single

Synopsis: Allow assignment of three-dimensional single precision vector to four-dimensional single precision vector

Declaration: `operator operator :=(Tvector3_single): Tvector4_single`  
`(const v: Tvector3_single)`  
`: Tvector4_single`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with single precision values wherever a four-dimensional vector with single precision is expected. The fourth dimension is set to 0.

### 26.3.283 operator :=(Tvector4\_double): Tvector2\_double

Synopsis: Allow assignment of four-dimensional double precision vector to two-dimensional double precision vector

Declaration: `operator operator :=(Tvector4_double): Tvector2_double`  
`(const v: Tvector4_double)`  
`: Tvector2_double`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with double precision values wherever a two-dimensional vector with double precision is expected. The third and fourth dimensions are thrown away.

### 26.3.284 operator :=(Tvector4\_double): Tvector2\_extended

Synopsis: Allow assignment of four-dimensional double precision vector to two-dimensional extended precision vector

Declaration: `operator operator :=(Tvector4_double): Tvector2_extended`  
`(const v: Tvector4_double)`  
`: Tvector2_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with double precision values wherever a two-dimensional vector with extended precision is expected. The third and fourth dimensions are thrown away.

### 26.3.285 operator :=(Tvector4\_double): Tvector2\_single

Synopsis: Allow assignment of four-dimensional double precision vector to two-dimensional single precision vector

Declaration: `operator operator :=(Tvector4_double): Tvector2_single`  
`(const v: Tvector4_double)`  
`: Tvector2_single`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with double precision values wherever a two-dimensional vector with single precision is expected. The third and fourth dimensions are thrown away and some accuracy is lost because of the conversion.

### 26.3.286 operator :=(Tvector4\_double): Tvector3\_double

Synopsis: Allow assignment of four-dimensional double precision vector to three-dimensional double precision vector

Declaration: `operator operator :=(Tvector4_double): Tvector3_double`  
`(const v: Tvector4_double)`  
`: Tvector3_double`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with double precision values wherever a three-dimensional vector with double precision is expected. The fourth dimension is thrown away.

### 26.3.287 operator :=(Tvector4\_double): Tvector3\_extended

Synopsis: Allow assignment of four-dimensional double precision vector to three-dimensional extended precision vector

Declaration: `operator operator :=(Tvector4_double): Tvector3_extended`  
`(const v: Tvector4_double)`  
`: Tvector3_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with double precision values wherever a three-dimensional vector with extended precision is expected. The fourth dimension is thrown away.

### 26.3.288 operator :=(Tvector4\_double): Tvector3\_single

Synopsis: Allow assignment of four-dimensional double precision vector to three-dimensional single precision vector

**Declaration:** `operator operator :=(Tvector4_double): Tvector3_single`  
`(const v: Tvector4_double)`  
`: Tvector3_single`

Visibility: default

**Description:** This operator allows you to use a four-dimensional vector with double precision values wherever a three-dimensional vector with single precision is expected. The fourth dimension is thrown away and some accuracy is lost because of the conversion.

### 26.3.289 operator :=(Tvector4\_double): Tvector4\_extended

**Synopsis:** Allow assignment of four-dimensional single precision vector to four-dimensional extended precision vector

**Declaration:** `operator operator :=(Tvector4_double): Tvector4_extended`  
`(const v: Tvector4_double)`  
`: Tvector4_extended`

Visibility: default

**Description:** This operator allows you to use a four-dimensional vector with double precision values wherever a four-dimensional vector with extended precision is expected.

### 26.3.290 operator :=(Tvector4\_double): Tvector4\_single

**Synopsis:** Allow assignment of four-dimensional double precision vector to four-dimensional single precision vector

**Declaration:** `operator operator :=(Tvector4_double): Tvector4_single`  
`(const v: Tvector4_double)`  
`: Tvector4_single`

Visibility: default

**Description:** This operator allows you to use a four-dimensional vector with double precision values wherever a four-dimensional vector with single precision is expected. Some accuracy is lost because of the conversion.

### 26.3.291 operator :=(Tvector4\_extended): Tvector2\_double

**Synopsis:** Allow assignment of four-dimensional extended precision vector to two-dimensional double precision vector

**Declaration:** `operator operator :=(Tvector4_extended): Tvector2_double`  
`(const v: Tvector4_extended)`  
`: Tvector2_double`

Visibility: default

**Description:** This operator allows you to use a four-dimensional vector with extended precision values wherever a two-dimensional vector with double precision is expected. The third and fourth dimensions are thrown away and some accuracy is lost because of the conversion.

**26.3.292 operator :=(Tvector4\_extended): Tvector2\_extended**

Synopsis: Allow assignment of four-dimensional extended precision vector to two-dimensional extended precision vector

Declaration: `operator operator :=(Tvector4_extended) : Tvector2_extended`  
`(const v: Tvector4_extended)`  
`: Tvector2_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with extended precision values wherever a two-dimensional vector with extended precision is expected. The third and fourth dimensions are thrown away.

**26.3.293 operator :=(Tvector4\_extended): Tvector2\_single**

Synopsis: Allow assignment of four-dimensional extended precision vector to two-dimensional single precision vector

Declaration: `operator operator :=(Tvector4_extended) : Tvector2_single`  
`(const v: Tvector4_extended)`  
`: Tvector2_single`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with extended precision values wherever a two-dimensional vector with single precision is expected. The third and fourth dimensions are thrown away and some accuracy is lost because of the conversion.

**26.3.294 operator :=(Tvector4\_extended): Tvector3\_double**

Synopsis: Allow assignment of four-dimensional extended precision vector to three-dimensional double precision vector

Declaration: `operator operator :=(Tvector4_extended) : Tvector3_double`  
`(const v: Tvector4_extended)`  
`: Tvector3_double`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with extended precision values wherever a three-dimensional vector with double precision is expected. The fourth dimension is thrown away and some accuracy is lost because of the conversion.

**26.3.295 operator :=(Tvector4\_extended): Tvector3\_extended**

Synopsis: Allow assignment of four-dimensional extended precision vector to three-dimensional extended precision vector

Declaration: `operator operator :=(Tvector4_extended) : Tvector3_extended`  
`(const v: Tvector4_extended)`  
`: Tvector3_extended`

Visibility: default

**Description:** This operator allows you to use a four-dimensional vector with extended precision values wherever a three-dimensional vector with extended precision is expected. The fourth dimensions are thrown away.

### 26.3.296 operator :=(Tvector4\_extended): Tvector3\_single

**Synopsis:** Allow assignment of four-dimensional extended precision vector to three-dimensional single precision vector

**Declaration:** `operator operator :=(Tvector4_extended): Tvector3_single`  
`(const v: Tvector4_extended)`  
`: Tvector3_single`

**Visibility:** default

**Description:** This operator allows you to use a four-dimensional vector with extended precision values wherever a three-dimensional vector with single precision is expected. The fourth dimension is thrown away and some accuracy is lost because of the conversion.

### 26.3.297 operator :=(Tvector4\_extended): Tvector4\_double

**Synopsis:** Allow assignment of four-dimensional single precision vector to four-dimensional double precision vector

**Declaration:** `operator operator :=(Tvector4_extended): Tvector4_double`  
`(const v: Tvector4_extended)`  
`: Tvector4_double`

**Visibility:** default

**Description:** This operator allows you to use a four-dimensional vector with extended precision values wherever a four-dimensional vector with double precision is expected. Some accuracy is lost because of the conversion.

### 26.3.298 operator :=(Tvector4\_extended): Tvector4\_single

**Synopsis:** Allow assignment of four-dimensional extended precision vector to four-dimensional single precision vector

**Declaration:** `operator operator :=(Tvector4_extended): Tvector4_single`  
`(const v: Tvector4_extended)`  
`: Tvector4_single`

**Visibility:** default

**Description:** This operator allows you to use a four-dimensional vector with extended precision values wherever a four-dimensional vector with single precision is expected. Some accuracy is lost because of the conversion.

### 26.3.299 operator :=(Tvector4\_single): Tvector2\_double

**Synopsis:** Allow assignment of four-dimensional single precision vector to two-dimensional double precision vector

**Declaration:** `operator operator :=(Tvector4_single): Tvector2_double`  
`(const v: Tvector4_single)`  
`: Tvector2_double`

**Visibility:** default

**Description:** This operator allows you to use a four-dimensional vector with single precision values wherever a two-dimensional vector with double precision is expected. The third and fourth dimensions are thrown away.

### 26.3.300 operator :=(Tvector4\_single): Tvector2\_extended

**Synopsis:** Allow assignment of four-dimensional single precision vector to two-dimensional extended precision vector

**Declaration:** `operator operator :=(Tvector4_single): Tvector2_extended`  
`(const v: Tvector4_single)`  
`: Tvector2_extended`

**Visibility:** default

**Description:** This operator allows you to use a four-dimensional vector with single precision values wherever a two-dimensional vector with extended precision is expected. The third and fourth dimensions are thrown away.

### 26.3.301 operator :=(Tvector4\_single): Tvector2\_single

**Synopsis:** Allow assignment of four-dimensional single precision vector to two-dimensional single precision vector

**Declaration:** `operator operator :=(Tvector4_single): Tvector2_single`  
`(const v: Tvector4_single)`  
`: Tvector2_single`

**Visibility:** default

**Description:** This operator allows you to use a four-dimensional vector with single precision values wherever a two-dimensional vector with single precision is expected. The third and fourth dimensions are thrown away.

### 26.3.302 operator :=(Tvector4\_single): Tvector3\_double

**Synopsis:** Allow assignment of four-dimensional single precision vector to three-dimensional double precision vector

**Declaration:** `operator operator :=(Tvector4_single): Tvector3_double`  
`(const v: Tvector4_single)`  
`: Tvector3_double`

**Visibility:** default

**Description:** This operator allows you to use a four-dimensional vector with single precision values wherever a three-dimensional vector with double precision is expected. The fourth dimension is thrown away.

**26.3.303 operator :=(Tvector4\_single): Tvector3\_extended**

Synopsis: Allow assignment of four-dimensional single precision vector to three-dimensional extended precision vector

Declaration: `operator operator :=(Tvector4_single): Tvector3_extended`  
`(const v: Tvector4_single)`  
`: Tvector3_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with single precision values wherever a three-dimensional vector with extended precision is expected. The fourth dimension is thrown away.

**26.3.304 operator :=(Tvector4\_single): Tvector3\_single**

Synopsis: Allow assignment of four-dimensional single precision vector to three-dimensional single precision vector

Declaration: `operator operator :=(Tvector4_single): Tvector3_single`  
`(const v: Tvector4_single)`  
`: Tvector3_single`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with single precision values wherever a three-dimensional vector with single precision is expected. The fourth dimension is thrown away.

**26.3.305 operator :=(Tvector4\_single): Tvector4\_double**

Synopsis: Allow assignment of four-dimensional single precision vector to four-dimensional double precision vector

Declaration: `operator operator :=(Tvector4_single): Tvector4_double`  
`(const v: Tvector4_single)`  
`: Tvector4_double`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with single precision values wherever a four-dimensional vector with double precision is expected.

**26.3.306 operator :=(Tvector4\_single): Tvector4\_extended**

Synopsis: Allow assignment of four-dimensional single precision vector to four-dimensional extended precision vector

Declaration: `operator operator :=(Tvector4_single): Tvector4_extended`  
`(const v: Tvector4_single)`  
`: Tvector4_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with single precision values wherever a four-dimensional vector with extended precision is expected.

**26.3.307 operator ><(Tvector3\_double, Tvector3\_double): Tvector3\_double**

Synopsis: Calculate the external product of two three-dimensional vectors

Declaration: `operator operator ><(Tvector3_double, Tvector3_double): Tvector3_double`

```
(const x: Tvector3_double,
const y: Tvector3_double)
: Tvector3_double
```

Visibility: default

Description: This operator returns the external product of two three dimensional vector. It is a vector orthonormal to the two multiplied vectors. The length of that vector is equal to the surface area of a parallelogram with the two vectors as sides.

The external product is often used to get a vector orthonormal to two other vectors, but of a predefined length. In order to do so, the result vector from the external product, is divided by its length, and then multiplied by the desired size.

**26.3.308 operator ><(Tvector3\_extended, Tvector3\_extended): Tvector3\_extended**

Synopsis: Calculate the external product of two three-dimensional vectors

Declaration:

```
operator operator ><(Tvector3_extended,
Tvector3_extended): Tvector3_extended
```

Visibility: default

Description: This operator returns the external product of two three dimensional vector. It is a vector orthonormal to the two multiplied vectors. The length of that vector is equal to the surface area of a parallelogram with the two vectors as sides.

The external product is often used to get a vector orthonormal to two other vectors, but of a predefined length. In order to do so, the result vector from the external product, is divided by its length, and then multiplied by the desired size.

**26.3.309 operator ><(Tvector3\_single, Tvector3\_single): Tvector3\_single**

Synopsis: Calculate the external product of two three-dimensional vectors

Declaration: `operator operator ><(Tvector3_single, Tvector3_single): Tvector3_single`

```
(const x: Tvector3_single,
const y: Tvector3_single)
: Tvector3_single
```

Visibility: default

Description: This operator returns the external product of two three dimensional vector. It is a vector orthonormal to the two multiplied vectors. The length of that vector is equal to the surface area of a parallelogram with the two vectors as sides.

The external product is often used to get a vector orthonormal to two other vectors, but of a predefined length. In order to do so, the result vector from the external product, is divided by its length, and then multiplied by the desired size.



## 26.4 Tmatrix2\_double

### 26.4.1 Description

The `Tmatrix2_double` object provides a matrix of 2\*2 double precision scalars.

### 26.4.2 Method overview

Page	Property	Description
<a href="#">864</a>	<code>determinant</code>	Calculates the determinant of the matrix.
<a href="#">864</a>	<code>get\_column</code>	Returns the c-th column of the matrix as vector.
<a href="#">864</a>	<code>get\_row</code>	Returns the r-th row of the matrix as vector.
<a href="#">863</a>	<code>init</code>	Initializes the matrix, setting its elements to the values passed to the constructor.
<a href="#">863</a>	<code>init\_identity</code>	Initializes the matrix and sets its elements to the identity matrix.
<a href="#">863</a>	<code>init\_zero</code>	Initializes the matrix and sets its elements to zero
<a href="#">864</a>	<code>inverse</code>	Calculates the inverse of the matrix.
<a href="#">864</a>	<code>set\_column</code>	Sets c-th column of the matrix with a vector.
<a href="#">864</a>	<code>set\_row</code>	Sets r-th row of the matrix with a vector.
<a href="#">865</a>	<code>transpose</code>	Returns the transposition of the matrix.

### 26.4.3 Tmatrix2\_double.init\_zero

Synopsis: Initializes the matrix and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

### 26.4.4 Tmatrix2\_double.init\_identity

Synopsis: Initializes the matrix and sets its elements to the identity matrix.

Declaration: `constructor init_identity`

Visibility: default

Description: Initializes the matrix and sets its elements to the identity matrix, that is, elements to 1 on the left-upper to right-lower diagonal, the rest zero.

### 26.4.5 Tmatrix2\_double.init

Synopsis: Initializes the matrix, setting its elements to the values passed to the constructor.

Declaration: `constructor init(aa: double;ab: double;ba: double;bb: double)`

Visibility: default

Description: Initializes the matrix, setting its elements to the values passed to the constructor. The order of the values is left to right, then top to bottom.

### 26.4.6 Tmatrix2\_double.get\_column

Synopsis: Returns the *c*-th column of the matrix as vector.

Declaration: `function get_column(c: Byte) : Tvector2_double`

Visibility: default

Description: Returns the *c*-th column of the matrix as vector. The column numbering starts at 0.

### 26.4.7 Tmatrix2\_double.get\_row

Synopsis: Returns the *r*-th row of the matrix as vector.

Declaration: `function get_row(r: Byte) : Tvector2_double`

Visibility: default

Description: Returns the *r*-th row of the matrix as vector. The row numbering starts at 0.

### 26.4.8 Tmatrix2\_double.set\_column

Synopsis: Sets *c*-th column of the matrix with a vector.

Declaration: `procedure set_column(c: Byte; const v: Tvector2_double)`

Visibility: default

Description: Replaces the *c*-th column of the matrix with vector *v*. The column numbering starts at 0.

### 26.4.9 Tmatrix2\_double.set\_row

Synopsis: Sets *r*-th row of the matrix with a vector.

Declaration: `procedure set_row(r: Byte; const v: Tvector2_double)`

Visibility: default

Description: Replaces the *r*-th row of the matrix with vector *v*. The row numbering starts at 0.

### 26.4.10 Tmatrix2\_double.determinant

Synopsis: Calculates the determinant of the matrix.

Declaration: `function determinant : double`

Visibility: default

Description: Returns the determinant of the matrix.

### 26.4.11 Tmatrix2\_double.inverse

Synopsis: Calculates the inverse of the matrix.

Declaration: `function inverse(A_determinant: double) : Tmatrix2_double`

Visibility: default

Description: `Tmatrix2_double.inverse` returns a new matrix that is the inverse of the matrix. You must pass the determinant of the matrix as parameter.

### 26.4.12 Tmatrix2\_double.transpose

Synopsis: Returns the transposition of the matrix.

Declaration: `function transpose : Tmatrix2_double`

Visibility: default

Description: `Tmatrix2_double.transpose` returns a new matrix that is the transposition of the matrix, that is, the matrix with the x and y coordinates of the values swapped.

## 26.5 Tmatrix2\_extended

### 26.5.1 Description

The `Tmatrix2_extended` object provides a matrix of 2\*2 extended precision scalars.

### 26.5.2 Method overview

Page	Property	Description
<a href="#">866</a>	<code>determinant</code>	Calculates the determinant of the matrix.
<a href="#">866</a>	<code>get\_column</code>	Returns the c-th column of the matrix as vector.
<a href="#">866</a>	<code>get\_row</code>	Returns the r-th row of the matrix as vector.
<a href="#">866</a>	<code>init</code>	Initializes the matrix, setting its elements to the values passed to the constructor.
<a href="#">865</a>	<code>init\_identity</code>	Initializes the matrix and sets its elements to the identity matrix.
<a href="#">865</a>	<code>init\_zero</code>	Initializes the matrix and sets its elements to zero
<a href="#">867</a>	<code>inverse</code>	Calculates the inverse of the matrix.
<a href="#">866</a>	<code>set\_column</code>	Sets c-th column of the matrix with a vector.
<a href="#">866</a>	<code>set\_row</code>	Sets r-th row of the matrix with a vector.
<a href="#">867</a>	<code>transpose</code>	Returns the transposition of the matrix.

### 26.5.3 Tmatrix2\_extended.init\_zero

Synopsis: Initializes the matrix and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

### 26.5.4 Tmatrix2\_extended.init\_identity

Synopsis: Initializes the matrix and sets its elements to the identity matrix.

Declaration: `constructor init_identity`

Visibility: default

Description: Initializes the matrix and sets its elements to the identity matrix, that is, elements to 1 on the left-upper to right-lower diagonal, the rest zero.

### 26.5.5 Tmatrix2\_extended.init

Synopsis: Initializes the matrix, setting its elements to the values passed to the constructor.

Declaration: `constructor init(aa: extended; ab: extended; ba: extended; bb: extended)`

Visibility: default

Description: Initializes the matrix, setting its elements to the values passed to the constructor. The order of the values is left to right, then top to bottom.

### 26.5.6 Tmatrix2\_extended.get\_column

Synopsis: Returns the *c*-th column of the matrix as vector.

Declaration: `function get_column(c: Byte) : Tvector2_extended`

Visibility: default

Description: Returns the *c*-th column of the matrix as vector. The column numbering starts at 0.

### 26.5.7 Tmatrix2\_extended.get\_row

Synopsis: Returns the *r*-th row of the matrix as vector.

Declaration: `function get_row(r: Byte) : Tvector2_extended`

Visibility: default

Description: Returns the *r*-th row of the matrix as vector. The row numbering starts at 0.

### 26.5.8 Tmatrix2\_extended.set\_column

Synopsis: Sets *c*-th column of the matrix with a vector.

Declaration: `procedure set_column(c: Byte; const v: Tvector2_extended)`

Visibility: default

Description: Replaces the *c*-th column of the matrix with vector *v*. The column numbering starts at 0.

### 26.5.9 Tmatrix2\_extended.set\_row

Synopsis: Sets *r*-th row of the matrix with a vector.

Declaration: `procedure set_row(r: Byte; const v: Tvector2_extended)`

Visibility: default

Description: Replaces the *r*-th row of the matrix with vector *v*. The row numbering starts at 0.

### 26.5.10 Tmatrix2\_extended.determinant

Synopsis: Calculates the determinant of the matrix.

Declaration: `function determinant : extended`

Visibility: default

Description: Returns the determinant of the matrix.

### 26.5.11 Tmatrix2\_extended.inverse

Synopsis: Calculates the inverse of the matrix.

Declaration: `function inverse(Adeterminant: extended) : Tmatrix2_extended`

Visibility: default

Description: Tmatrix2\_extended.inverse returns a new matrix that is the inverse of the matrix. You must pass the determinant of the matrix as parameter.

### 26.5.12 Tmatrix2\_extended.transpose

Synopsis: Returns the transposition of the matrix.

Declaration: `function transpose : Tmatrix2_extended`

Visibility: default

Description: Tmatrix2\_extended.transpose returns a new matrix that is the transposition of the matrix, that is, the matrix with the x and y coordinates of the values swapped.

## 26.6 Tmatrix2\_single

### 26.6.1 Description

The Tmatrix2\_single object provides a matrix of 2\*2 single precision scalars.

### 26.6.2 Method overview

Page	Property	Description
<a href="#">869</a>	determinant	Calculates the determinant of the matrix.
<a href="#">868</a>	get\_column	Returns the c-th column of the matrix as vector.
<a href="#">868</a>	get\_row	Returns the r-th row of the matrix as vector.
<a href="#">868</a>	init	Initializes the matrix, setting its elements to the values passed to the constructor.
<a href="#">868</a>	init\_identity	Initializes the matrix and sets its elements to the identity matrix.
<a href="#">867</a>	init\_zero	Initializes the matrix and sets its elements to zero
<a href="#">869</a>	inverse	Calculates the inverse of the matrix.
<a href="#">868</a>	set\_column	Sets c-th column of the matrix with a vector.
<a href="#">869</a>	set\_row	Sets r-th row of the matrix with a vector.
<a href="#">869</a>	transpose	Returns the transposition of the matrix.

### 26.6.3 Tmatrix2\_single.init\_zero

Synopsis: Initializes the matrix and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

### 26.6.4 Tmatrix2\_single.init\_identity

Synopsis: Initializes the matrix and sets its elements to the identity matrix.

Declaration: `constructor init_identity`

Visibility: default

Description: Initializes the matrix and sets its elements to the identity matrix, that is, elements to 1 on the left-upper to right-lower diagonal, the rest zero.

### 26.6.5 Tmatrix2\_single.init

Synopsis: Initializes the matrix, setting its elements to the values passed to the constructor.

Declaration: `constructor init(aa: single;ab: single;ba: single;bb: single)`

Visibility: default

Description: Initializes the matrix, setting its elements to the values passed to the constructor. The order of the values is left to right, then top to bottom.

### 26.6.6 Tmatrix2\_single.get\_column

Synopsis: Returns the c-th column of the matrix as vector.

Declaration: `function get_column(c: Byte) : Tvector2_single`

Visibility: default

Description: Returns the c-th column of the matrix as vector. The column numbering starts at 0.

### 26.6.7 Tmatrix2\_single.get\_row

Synopsis: Returns the r-th row of the matrix as vector.

Declaration: `function get_row(r: Byte) : Tvector2_single`

Visibility: default

Description: Returns the r-th row of the matrix as vector. The row numbering starts at 0.

### 26.6.8 Tmatrix2\_single.set\_column

Synopsis: Sets c-th column of the matrix with a vector.

Declaration: `procedure set_column(c: Byte;const v: Tvector2_single)`

Visibility: default

Description: Replaces the c-th column of the matrix with vector v. The column numbering starts at 0.

### 26.6.9 Tmatrix2\_single.set\_row

Synopsis: Sets r-th row of the matrix with a vector.

Declaration: `procedure set_row(r: Byte; const v: Tvector2_single)`

Visibility: default

Description: Replaces the r-th row of the matrix with vector v. The row numbering starts at 0.

### 26.6.10 Tmatrix2\_single.determinant

Synopsis: Calculates the determinant of the matrix.

Declaration: `function determinant : single`

Visibility: default

Description: Returns the determinant of the matrix.

### 26.6.11 Tmatrix2\_single.inverse

Synopsis: Calculates the inverse of the matrix.

Declaration: `function inverse(A_determinant: single) : Tmatrix2_single`

Visibility: default

Description: `Tmatrix2_single.inverse` returns a new matrix that is the inverse of the matrix. You must pass the determinant of the matrix as parameter.

### 26.6.12 Tmatrix2\_single.transpose

Synopsis: Returns the transposition of the matrix.

Declaration: `function transpose : Tmatrix2_single`

Visibility: default

Description: `Tmatrix2_single.transpose` returns a new matrix that is the transposition of the matrix, that is, the matrix with the x and y coordinates of the values swapped.

## 26.7 Tmatrix3\_double

### 26.7.1 Description

The `Tmatrix3_double` object provides a matrix of 3\*3 double precision scalars.

### 26.7.2 Method overview

Page	Property	Description
<a href="#">871</a>	determinant	Calculates the determinant of the matrix.
<a href="#">870</a>	get\_column	Returns the c-th column of the matrix as vector.
<a href="#">871</a>	get\_row	Returns the r-th row of the matrix as vector.
<a href="#">870</a>	init	Initializes the matrix, setting its elements to the values passed to the constructor.
<a href="#">870</a>	init\_identity	Initializes the matrix and sets its elements to the identity matrix.
<a href="#">870</a>	init\_zero	Initializes the matrix and sets its elements to zero
<a href="#">871</a>	inverse	Calculates the inverse of the matrix.
<a href="#">871</a>	set\_column	Sets c-th column of the matrix with a vector.
<a href="#">871</a>	set\_row	Sets r-th row of the matrix with a vector.
<a href="#">871</a>	transpose	Returns the transposition of the matrix.

### 26.7.3 Tmatrix3\_double.init\_zero

Synopsis: Initializes the matrix and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

### 26.7.4 Tmatrix3\_double.init\_identity

Synopsis: Initializes the matrix and sets its elements to the identity matrix.

Declaration: `constructor init_identity`

Visibility: default

Description: Initializes the matrix and sets its elements to the identity matrix, that is, elements to 1 on the left-upper to right-lower diagonal, the rest zero.

### 26.7.5 Tmatrix3\_double.init

Synopsis: Initializes the matrix, setting its elements to the values passed to the constructor.

Declaration: `constructor init(aa: double;ab: double;ac: double;ba: double;bb: double;  
bc: double;ca: double;cb: double;cc: double)`

Visibility: default

Description: Initializes the matrix, setting its elements to the values passed to the constructor. The order of the values is left to right, then top to bottom.

### 26.7.6 Tmatrix3\_double.get\_column

Synopsis: Returns the c-th column of the matrix as vector.

Declaration: `function get_column(c: Byte) : Tvector3_double`

Visibility: default

Description: Returns the c-th column of the matrix as vector. The column numbering starts at 0.



### 26.7.7 Tmatrix3\_double.get\_row

Synopsis: Returns the *r*-th row of the matrix as vector.

Declaration: `function get_row(r: Byte) : Tvector3_double`

Visibility: default

Description: Returns the *r*-th row of the matrix as vector. The row numbering starts at 0.

### 26.7.8 Tmatrix3\_double.set\_column

Synopsis: Sets *c*-th column of the matrix with a vector.

Declaration: `procedure set_column(c: Byte; const v: Tvector3_double)`

Visibility: default

Description: Replaces the *c*-th column of the matrix with vector *v*. The column numbering starts at 0.

### 26.7.9 Tmatrix3\_double.set\_row

Synopsis: Sets *r*-th row of the matrix with a vector.

Declaration: `procedure set_row(r: Byte; const v: Tvector3_double)`

Visibility: default

Description: Replaces the *r*-th row of the matrix with vector *v*. The row numbering starts at 0.

### 26.7.10 Tmatrix3\_double.determinant

Synopsis: Calculates the determinant of the matrix.

Declaration: `function determinant : double`

Visibility: default

Description: Returns the determinant of the matrix.

### 26.7.11 Tmatrix3\_double.inverse

Synopsis: Calculates the inverse of the matrix.

Declaration: `function inverse(A_determinant: double) : Tmatrix3_double`

Visibility: default

Description: `Tmatrix3_double.inverse` returns a new matrix that is the inverse of the matrix. You must pass the determinant of the matrix as parameter.

### 26.7.12 Tmatrix3\_double.transpose

Synopsis: Returns the transposition of the matrix.

Declaration: `function transpose : Tmatrix3_double`

Visibility: default

Description: `Tmatrix2_double.transpose` returns a new matrix that is the transposition of the matrix, that is, the matrix with the *x* and *y* coordinates of the values swapped.

## 26.8 Tmatrix3\_extended

### 26.8.1 Description

The Tmatrix3\_extended object provides a matrix of 3\*3 extended precision scalars.

### 26.8.2 Method overview

Page	Property	Description
<a href="#">873</a>	determinant	Calculates the determinant of the matrix.
<a href="#">873</a>	get\_column	Returns the c-th column of the matrix as vector.
<a href="#">873</a>	get\_row	Returns the r-th row of the matrix as vector.
<a href="#">872</a>	init	Initializes the matrix, setting its elements to the values passed to the constructor.
<a href="#">872</a>	init\_identity	Initializes the matrix and sets its elements to the identity matrix.
<a href="#">872</a>	init\_zero	Initializes the matrix and sets its elements to zero
<a href="#">873</a>	inverse	Calculates the inverse of the matrix.
<a href="#">873</a>	set\_column	Sets r-th column of the matrix with a vector.
<a href="#">873</a>	set\_row	Sets r-th row of the matrix with a vector.
<a href="#">874</a>	transpose	Returns the transposition of the matrix.

### 26.8.3 Tmatrix3\_extended.init\_zero

Synopsis: Initializes the matrix and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

### 26.8.4 Tmatrix3\_extended.init\_identity

Synopsis: Initializes the matrix and sets its elements to the identity matrix.

Declaration: `constructor init_identity`

Visibility: default

Description: Initializes the matrix and sets its elements to the identity matrix, that is, elements to 1 on the left-upper to right-lower diagonal, the rest zero.

### 26.8.5 Tmatrix3\_extended.init

Synopsis: Initializes the matrix, setting its elements to the values passed to the constructor.

Declaration: `constructor init(aa: extended;ab: extended;ac: extended;ba: extended;  
bb: extended;bc: extended;ca: extended;cb: extended;  
cc: extended)`

Visibility: default

Description: Initializes the matrix, setting its elements to the values passed to the constructor. The order of the values is left to right, then top to bottom.

### 26.8.6 Tmatrix3\_extended.get\_column

Synopsis: Returns the *c*-th column of the matrix as vector.

Declaration: `function get_column(c: Byte) : Tvector3_extended`

Visibility: default

Description: Returns the *c*-th column of the matrix as vector. The column numbering starts at 0.

### 26.8.7 Tmatrix3\_extended.get\_row

Synopsis: Returns the *r*-th row of the matrix as vector.

Declaration: `function get_row(r: Byte) : Tvector3_extended`

Visibility: default

Description: Returns the *r*-th row of the matrix as vector. The row numbering starts at 0.

### 26.8.8 Tmatrix3\_extended.set\_column

Synopsis: Sets *r*-th column of the matrix with a vector.

Declaration: `procedure set_column(c: Byte; const v: Tvector3_extended)`

Visibility: default

Description: Replaces the *c*-th column of the matrix with vector *v*. The column numbering starts at 0.

### 26.8.9 Tmatrix3\_extended.set\_row

Synopsis: Sets *r*-th row of the matrix with a vector.

Declaration: `procedure set_row(r: Byte; const v: Tvector3_extended)`

Visibility: default

Description: Replaces the *r*-th row of the matrix with vector *v*. The row numbering starts at 0.

### 26.8.10 Tmatrix3\_extended.determinant

Synopsis: Calculates the determinant of the matrix.

Declaration: `function determinant : extended`

Visibility: default

Description: Returns the determinant of the matrix.

### 26.8.11 Tmatrix3\_extended.inverse

Synopsis: Calculates the inverse of the matrix.

Declaration: `function inverse(A: Tmatrix3_extended) : Tmatrix3_extended`

Visibility: default

Description: `Tmatrix3_extended.inverse` returns a new matrix that is the inverse of the matrix. You must pass the determinant of the matrix as parameter.

### 26.8.12 Tmatrix3\_extended.transpose

Synopsis: Returns the transposition of the matrix.

Declaration: `function transpose : Tmatrix3_extended`

Visibility: default

Description: `Tmatrix2_extended.transpose` returns a new matrix that is the transposition of the matrix, that is, the matrix with the x and y coordinates of the values swapped.

## 26.9 Tmatrix3\_single

### 26.9.1 Description

The `Tmatrix3_single` object provides a matrix of 3\*3 single precision scalars.

### 26.9.2 Method overview

Page	Property	Description
<a href="#">876</a>	<code>determinant</code>	Calculates the determinant of the matrix.
<a href="#">875</a>	<code>get\_column</code>	Returns the c-th column of the matrix as vector.
<a href="#">875</a>	<code>get\_row</code>	Returns the r-th row of the matrix as vector.
<a href="#">875</a>	<code>init</code>	Initializes the matrix, setting its elements to the values passed to the constructor.
<a href="#">874</a>	<code>init\_identity</code>	Initializes the matrix and sets its elements to the identity matrix.
<a href="#">874</a>	<code>init\_zero</code>	Initializes the matrix and sets its elements to zero
<a href="#">876</a>	<code>inverse</code>	Calculates the inverse of the matrix.
<a href="#">875</a>	<code>set\_column</code>	Sets c-th column of the matrix with a vector.
<a href="#">875</a>	<code>set\_row</code>	Sets r-th row of the matrix with a vector.
<a href="#">876</a>	<code>transpose</code>	Returns the transposition of the matrix.

### 26.9.3 Tmatrix3\_single.init\_zero

Synopsis: Initializes the matrix and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

### 26.9.4 Tmatrix3\_single.init\_identity

Synopsis: Initializes the matrix and sets its elements to the identity matrix.

Declaration: `constructor init_identity`

Visibility: default

Description: Initializes the matrix and sets its elements to the identity matrix, that is, elements to 1 on the left-upper to right-lower diagonal, the rest zero.

### 26.9.5 Tmatrix3\_single.init

Synopsis: Initializes the matrix, setting its elements to the values passed to the constructor.

Declaration: `constructor init(aa: single;ab: single;ac: single;ba: single;bb: single;  
bc: single;ca: single;cb: single;cc: single)`

Visibility: default

Description: Initializes the matrix, setting its elements to the values passed to the constructor. The order of the values is left to right, then top to bottom.

### 26.9.6 Tmatrix3\_single.get\_column

Synopsis: Returns the c-th column of the matrix as vector.

Declaration: `function get_column(c: Byte) : Tvector3_single`

Visibility: default

Description: Returns the c-th column of the matrix as vector. The column numbering starts at 0.

### 26.9.7 Tmatrix3\_single.get\_row

Synopsis: Returns the r-th row of the matrix as vector.

Declaration: `function get_row(r: Byte) : Tvector3_single`

Visibility: default

Description: Returns the r-th row of the matrix as vector. The row numbering starts at 0.

### 26.9.8 Tmatrix3\_single.set\_column

Synopsis: Sets c-th column of the matrix with a vector.

Declaration: `procedure set_column(c: Byte;const v: Tvector3_single)`

Visibility: default

Description: Replaces the c-th column of the matrix with vector v. The column numbering starts at 0.

### 26.9.9 Tmatrix3\_single.set\_row

Synopsis: Sets r-th row of the matrix with a vector.

Declaration: `procedure set_row(r: Byte;const v: Tvector3_single)`

Visibility: default

Description: Replaces the r-th row of the matrix with vector v. The row numbering starts at 0.

### 26.9.10 Tmatrix3\_single.determinant

Synopsis: Calculates the determinant of the matrix.

Declaration: `function determinant : single`

Visibility: default

Description: Returns the determinant of the matrix.

### 26.9.11 Tmatrix3\_single.inverse

Synopsis: Calculates the inverse of the matrix.

Declaration: `function inverse(Adeterminant: single) : Tmatrix3_single`

Visibility: default

Description: `Tmatrix3_single.inverse` returns a new matrix that is the inverse of the matrix. You must pass the determinant of the matrix as parameter.

### 26.9.12 Tmatrix3\_single.transpose

Synopsis: Returns the transposition of the matrix.

Declaration: `function transpose : Tmatrix3_single`

Visibility: default

Description: `Tmatrix2_single.transpose` returns a new matrix that is the transposition of the matrix, that is, the matrix with the x and y coordinates of the values swapped.

## 26.10 Tmatrix4\_double

### 26.10.1 Description

The `Tmatrix4_double` object provides a matrix of 4\*4 double precision scalars.

### 26.10.2 Method overview

Page	Property	Description
<a href="#">878</a>	<code>determinant</code>	Calculates the determinant of the matrix.
<a href="#">877</a>	<code>get\_column</code>	Returns the c-th column of the matrix as vector.
<a href="#">877</a>	<code>get\_row</code>	Returns the r-th row of the matrix as vector.
<a href="#">877</a>	<code>init</code>	Initializes the matrix, setting its elements to the values passed to the constructor.
<a href="#">877</a>	<code>init\_identity</code>	Initializes the matrix and sets its elements to the identity matrix.
<a href="#">877</a>	<code>init\_zero</code>	Initializes the matrix and sets its elements to zero
<a href="#">878</a>	<code>inverse</code>	Calculates the inverse of the matrix.
<a href="#">878</a>	<code>set\_column</code>	Sets c-th column of the matrix with a vector.
<a href="#">878</a>	<code>set\_row</code>	Sets r-th row of the matrix with a vector.
<a href="#">878</a>	<code>transpose</code>	Returns the transposition of the matrix.

**26.10.3 Tmatrix4\_double.init\_zero**

Synopsis: Initializes the matrix and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

**26.10.4 Tmatrix4\_double.init\_identity**

Synopsis: Initializes the matrix and sets its elements to the identity matrix.

Declaration: `constructor init_identity`

Visibility: default

Description: Initializes the matrix and sets its elements to the identity matrix, that is, elements to 1 on the left-upper to right-lower diagonal, the rest zero.

**26.10.5 Tmatrix4\_double.init**

Synopsis: Initializes the matrix, setting its elements to the values passed to the constructor.

Declaration: `constructor init(aa: double;ab: double;ac: double;ad: double;ba: double;  
bb: double;bc: double;bd: double;ca: double;cb: double;  
cc: double;cd: double;da: double;db: double;dc: double;  
dd: double)`

Visibility: default

Description: Initializes the matrix, setting its elements to the values passed to the constructor. The order of the values is left to right, then top to bottom.

**26.10.6 Tmatrix4\_double.get\_column**

Synopsis: Returns the c-th column of the matrix as vector.

Declaration: `function get_column(c: Byte) : Tvector4_double`

Visibility: default

Description: Returns the c-th column of the matrix as vector. The column numbering starts at 0.

**26.10.7 Tmatrix4\_double.get\_row**

Synopsis: Returns the r-th row of the matrix as vector.

Declaration: `function get_row(r: Byte) : Tvector4_double`

Visibility: default

Description: Returns the r-th row of the matrix as vector. The row numbering starts at 0.

### 26.10.8 Tmatrix4\_double.set\_column

Synopsis: Sets c-th column of the matrix with a vector.

Declaration: `procedure set_column(c: Byte; const v: Tvector4_double)`

Visibility: default

Description: Replaces the c-th column of the matrix with vector v. The column numbering starts at 0.

### 26.10.9 Tmatrix4\_double.set\_row

Synopsis: Sets r-th row of the matrix with a vector.

Declaration: `procedure set_row(r: Byte; const v: Tvector4_double)`

Visibility: default

Description: Replaces the r-th row of the matrix with vector v. The row numbering starts at 0.

### 26.10.10 Tmatrix4\_double.determinant

Synopsis: Calculates the determinant of the matrix.

Declaration: `function determinant : double`

Visibility: default

Description: Returns the determinant of the matrix. Note: Calculating the determinant of a 4\*4 matrix requires quite a few operations.

### 26.10.11 Tmatrix4\_double.inverse

Synopsis: Calculates the inverse of the matrix.

Declaration: `function inverse(A: Tmatrix4_double) : Tmatrix4_double`

Visibility: default

Description: `Tmatrix4_double.inverse` returns a new matrix that is the inverse of the matrix. You must pass the determinant of the matrix as parameter. Note: Calculating the inverse of a 4\*4 matrix requires quite a few operations.

### 26.10.12 Tmatrix4\_double.transpose

Synopsis: Returns the transposition of the matrix.

Declaration: `function transpose : Tmatrix4_double`

Visibility: default

Description: `Tmatrix2_double.transpose` returns a new matrix that is the transposition of the matrix, that is, the matrix with the x and y coordinates of the values swapped.



## 26.11 Tmatrix4\_extended

### 26.11.1 Description

The Tmatrix4\_extended object provides a matrix of 4\*4 extended precision scalars.

### 26.11.2 Method overview

Page	Property	Description
880	determinant	Calculates the determinant of the matrix.
880	get\_column	Returns the c-th column of the matrix as vector.
880	get\_row	Returns the r-th row of the matrix as vector.
879	init	Initializes the matrix, setting its elements to the values passed to the constructor.
879	init\_identity	Initializes the matrix and sets its elements to the identity matrix.
879	init\_zero	Initializes the matrix and sets its elements to zero
881	inverse	Calculates the inverse of the matrix.
880	set\_column	Sets c-th column of the matrix with a vector.
880	set\_row	Sets r-th row of the matrix with a vector.
881	transpose	Returns the transposition of the matrix.

### 26.11.3 Tmatrix4\_extended.init\_zero

Synopsis: Initializes the matrix and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

### 26.11.4 Tmatrix4\_extended.init\_identity

Synopsis: Initializes the matrix and sets its elements to the identity matrix.

Declaration: `constructor init_identity`

Visibility: default

Description: Initializes the matrix and sets its elements to the identity matrix, that is, elements to 1 on the left-upper to right-lower diagonal, the rest zero.

### 26.11.5 Tmatrix4\_extended.init

Synopsis: Initializes the matrix, setting its elements to the values passed to the constructor.

Declaration: `constructor init(aa: extended;ab: extended;ac: extended;ad: extended;  
ba: extended;bb: extended;bc: extended;bd: extended;  
ca: extended;cb: extended;cc: extended;cd: extended;  
da: extended;db: extended;dc: extended;dd: extended)`

Visibility: default

Description: Initializes the matrix, setting its elements to the values passed to the constructor. The order of the values is left to right, then top to bottom.

### 26.11.6 Tmatrix4\_extended.get\_column

Synopsis: Returns the *c*-th column of the matrix as vector.

Declaration: `function get_column(c: Byte) : Tvector4_extended`

Visibility: default

Description: Returns the *c*-th column of the matrix as vector. The column numbering starts at 0.

### 26.11.7 Tmatrix4\_extended.get\_row

Synopsis: Returns the *r*-th row of the matrix as vector.

Declaration: `function get_row(r: Byte) : Tvector4_extended`

Visibility: default

Description: Returns the *r*-th row of the matrix as vector. The row numbering starts at 0.

### 26.11.8 Tmatrix4\_extended.set\_column

Synopsis: Sets *c*-th column of the matrix with a vector.

Declaration: `procedure set_column(c: Byte; const v: Tvector4_extended)`

Visibility: default

Description: Replaces the *c*-th column of the matrix with vector *v*. The column numbering starts at 0.

### 26.11.9 Tmatrix4\_extended.set\_row

Synopsis: Sets *r*-th row of the matrix with a vector.

Declaration: `procedure set_row(r: Byte; const v: Tvector4_extended)`

Visibility: default

Description: Replaces the *r*-th row of the matrix with vector *v*. The row numbering starts at 0.

### 26.11.10 Tmatrix4\_extended.determinant

Synopsis: Calculates the determinant of the matrix.

Declaration: `function determinant : extended`

Visibility: default

Description: Returns the determinant of the matrix. Note: Calculating the determinant of a 4\*4 matrix requires quite a few operations.

### 26.11.11 Tmatrix4\_extended.inverse

Synopsis: Calculates the inverse of the matrix.

Declaration: `function inverse (Adeterminant: extended) : Tmatrix4_extended`

Visibility: default

Description: `Tmatrix4_extended.inverse` returns a new matrix that is the inverse of the matrix. You must pass the determinant of the matrix as parameter. Note: Calculating the inverse of a 4\*4 matrix requires quite a few operations.

### 26.11.12 Tmatrix4\_extended.transpose

Synopsis: Returns the transposition of the matrix.

Declaration: `function transpose : Tmatrix4_extended`

Visibility: default

Description: `Tmatrix2_extended.transpose` returns a new matrix that is the transposition of the matrix, that is, the matrix with the x and y coordinates of the values swapped.

## 26.12 Tmatrix4\_single

### 26.12.1 Description

The `Tmatrix4_single` object provides a matrix of 4\*4 single precision scalars.

### 26.12.2 Method overview

Page	Property	Description
<a href="#">883</a>	<code>determinant</code>	Calculates the determinant of the matrix.
<a href="#">882</a>	<code>get\_column</code>	Returns the c-th column of the matrix as vector.
<a href="#">882</a>	<code>get\_row</code>	Returns the r-th row of the matrix as vector.
<a href="#">882</a>	<code>init</code>	Initializes the matrix, setting its elements to the values passed to the constructor.
<a href="#">882</a>	<code>init\_identity</code>	Initializes the matrix and sets its elements to the identity matrix.
<a href="#">881</a>	<code>init\_zero</code>	Initializes the matrix and sets its elements to zero
<a href="#">883</a>	<code>inverse</code>	Calculates the inverse of the matrix.
<a href="#">882</a>	<code>set\_column</code>	Sets c-th column of the matrix with a vector.
<a href="#">883</a>	<code>set\_row</code>	Sets r-th row of the matrix with a vector.
<a href="#">883</a>	<code>transpose</code>	Returns the transposition of the matrix.

### 26.12.3 Tmatrix4\_single.init\_zero

Synopsis: Initializes the matrix and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

### 26.12.4 Tmatrix4\_single.init\_identity

Synopsis: Initializes the matrix and sets its elements to the identity matrix.

Declaration: `constructor init_identity`

Visibility: default

Description: Initializes the matrix and sets its elements to the identity matrix, that is, elements to 1 on the left-upper to right-lower diagonal, the rest zero.

### 26.12.5 Tmatrix4\_single.init

Synopsis: Initializes the matrix, setting its elements to the values passed to the constructor.

Declaration: `constructor init(aa: single;ab: single;ac: single;ad: single;ba: single;  
bb: single;bc: single;bd: single;ca: single;cb: single;  
cc: single;cd: single;da: single;db: single;dc: single;  
dd: single)`

Visibility: default

Description: Initializes the matrix, setting its elements to the values passed to the constructor. The order of the values is left to right, then top to bottom.

### 26.12.6 Tmatrix4\_single.get\_column

Synopsis: Returns the c-th column of the matrix as vector.

Declaration: `function get_column(c: Byte) : Tvector4_single`

Visibility: default

Description: Returns the c-th column of the matrix as vector. The column numbering starts at 0.

### 26.12.7 Tmatrix4\_single.get\_row

Synopsis: Returns the r-th row of the matrix as vector.

Declaration: `function get_row(r: Byte) : Tvector4_single`

Visibility: default

Description: Returns the r-th row of the matrix as vector. The row numbering starts at 0.

### 26.12.8 Tmatrix4\_single.set\_column

Synopsis: Sets c-th column of the matrix with a vector.

Declaration: `procedure set_column(c: Byte;const v: Tvector4_single)`

Visibility: default

Description: Replaces the c-th column of the matrix with vector v. The column numbering starts at 0.

### 26.12.9 Tmatrix4\_single.set\_row

Synopsis: Sets r-th row of the matrix with a vector.

Declaration: `procedure set_row(r: Byte; const v: Tvector4_single)`

Visibility: default

Description: Replaces the r-th row of the matrix with vector v. The row numbering starts at 0.

### 26.12.10 Tmatrix4\_single.determinant

Synopsis: Calculates the determinant of the matrix.

Declaration: `function determinant : single`

Visibility: default

Description: Returns the determinant of the matrix. Note: Calculating the determinant of a 4\*4 matrix requires quite a few operations.

### 26.12.11 Tmatrix4\_single.inverse

Synopsis: Calculates the inverse of the matrix.

Declaration: `function inverse(Adeterminant: single) : Tmatrix4_single`

Visibility: default

Description: `Tmatrix4_single.inverse` returns a new matrix that is the inverse of the matrix. You must pass the determinant of the matrix as parameter. Note: Calculating the inverse of a 4\*4 matrix requires quite a few operations.

### 26.12.12 Tmatrix4\_single.transpose

Synopsis: Returns the transposition of the matrix.

Declaration: `function transpose : Tmatrix4_single`

Visibility: default

Description: `Tmatrix2_single.transpose` returns a new matrix that is the transposition of the matrix, that is, the matrix with the x and y coordinates of the values swapped.

## 26.13 Tvector2\_double

### 26.13.1 Description

The `Tvector2_double` object provides a vector of two double precision scalars.

**26.13.2 Method overview**

Page	Property	Description
<a href="#">884</a>	<code>init</code>	Initializes the vector, setting its elements to the values passed to the constructor.
<a href="#">884</a>	<code>init\_one</code>	Initializes the vector and sets its elements to one
<a href="#">884</a>	<code>init\_zero</code>	Initializes the vector and sets its elements to zero
<a href="#">884</a>	<code>length</code>	Calculates the length of the vector.
<a href="#">884</a>	<code>squared\_length</code>	Calculates the squared length of the vector.

**26.13.3 Tvector2\_double.init\_zero**

Synopsis: Initializes the vector and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

**26.13.4 Tvector2\_double.init\_one**

Synopsis: Initializes the vector and sets its elements to one

Declaration: `constructor init_one`

Visibility: default

**26.13.5 Tvector2\_double.init**

Synopsis: Initializes the vector, setting its elements to the values passed to the constructor.

Declaration: `constructor init(a: double;b: double)`

Visibility: default

**26.13.6 Tvector2\_double.length**

Synopsis: Calculates the length of the vector.

Declaration: `function length : double`

Visibility: default

Description: Calculate the length of the vector: `length=sqrt(data[0]**2+data[1]**2)`. Try to use `squared_length` ([884](#)) if you are able to, as it is faster.

**26.13.7 Tvector2\_double.squared\_length**

Synopsis: Calculates the squared length of the vector.

Declaration: `function squared_length : double`

Visibility: default

Description: Calculate the squared length of the vector: `squared_length=data[0]**2+data[1]**2`.

## 26.14 Tvector2\_extended

### 26.14.1 Description

The `Tvector2_extended` object provides a vector of two extended precision scalars.

### 26.14.2 Method overview

Page	Property	Description
<a href="#">885</a>	<code>init</code>	Initializes the vector, setting its elements to the values passed to the constructor.
<a href="#">885</a>	<code>init\_one</code>	Initializes the vector and sets its elements to one
<a href="#">885</a>	<code>init\_zero</code>	Initializes the vector and sets its elements to zero
<a href="#">885</a>	<code>length</code>	Calculates the length of the vector.
<a href="#">886</a>	<code>squared\_length</code>	Calculates the squared length of the vector.

### 26.14.3 Tvector2\_extended.init\_zero

Synopsis: Initializes the vector and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

### 26.14.4 Tvector2\_extended.init\_one

Synopsis: Initializes the vector and sets its elements to one

Declaration: `constructor init_one`

Visibility: default

### 26.14.5 Tvector2\_extended.init

Synopsis: Initializes the vector, setting its elements to the values passed to the constructor.

Declaration: `constructor init(a: extended;b: extended)`

Visibility: default

### 26.14.6 Tvector2\_extended.length

Synopsis: Calculates the length of the vector.

Declaration: `function length : extended`

Visibility: default

Description: Calculate the length of the vector: `length=sqrt(data[0]**2+data[1]**2)`. Try to use `squared_length` ([886](#)) if you are able to, as it is faster.

### 26.14.7 Tvector2\_extended.squared\_length

Synopsis: Calculates the squared length of the vector.

Declaration: `function squared_length : extended`

Visibility: default

Description: Calculate the squared length of the vector: `squared_length=data[0]**2+data[1]**2`.

## 26.15 Tvector2\_single

### 26.15.1 Description

The `Tvector2_single` object provides a vector of two single precision scalars.

### 26.15.2 Method overview

Page	Property	Description
<a href="#">886</a>	<code>init</code>	Initializes the vector, setting its elements to the values passed to the constructor.
<a href="#">886</a>	<code>init\_one</code>	Initializes the vector and sets its elements to one
<a href="#">886</a>	<code>init\_zero</code>	Initializes the vector and sets its elements to zero
<a href="#">887</a>	<code>length</code>	Calculates the length of the vector.
<a href="#">887</a>	<code>squared\_length</code>	Calculates the squared length of the vector.

### 26.15.3 Tvector2\_single.init\_zero

Synopsis: Initializes the vector and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

### 26.15.4 Tvector2\_single.init\_one

Synopsis: Initializes the vector and sets its elements to one

Declaration: `constructor init_one`

Visibility: default

### 26.15.5 Tvector2\_single.init

Synopsis: Initializes the vector, setting its elements to the values passed to the constructor.

Declaration: `constructor init(a: single;b: single)`

Visibility: default



### 26.15.6 Tvector2\_single.length

Synopsis: Calculates the length of the vector.

Declaration: `function length : single`

Visibility: default

Description: Calculate the length of the vector: `length=sqrt(data[0]**2+data[1]**2)`. Try to use `squared_length` (887) if you are able to, as it is faster.

### 26.15.7 Tvector2\_single.squared\_length

Synopsis: Calculates the squared length of the vector.

Declaration: `function squared_length : single`

Visibility: default

Description: Calculate the squared length of the vector: `squared_length=data[0]**2+data[1]**2`.

## 26.16 Tvector3\_double

### 26.16.1 Description

The `Tvector3_double` object provides a vector of three double precision scalars.

### 26.16.2 Method overview

Page	Property	Description
888	<code>init</code>	Initializes the vector, setting its elements to the values passed to the constructor.
887	<code>init\_one</code>	Initializes the vector and sets its elements to one
887	<code>init\_zero</code>	Initializes the vector and sets its elements to zero
888	<code>length</code>	Calculates the length of the vector.
888	<code>squared\_length</code>	Calculates the squared length of the vector.

### 26.16.3 Tvector3\_double.init\_zero

Synopsis: Initializes the vector and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

### 26.16.4 Tvector3\_double.init\_one

Synopsis: Initializes the vector and sets its elements to one

Declaration: `constructor init_one`

Visibility: default

### 26.16.5 Tvector3\_double.init

Synopsis: Initializes the vector, setting its elements to the values passed to the constructor.

Declaration: `constructor init(a: double;b: double;c: double)`

Visibility: default

### 26.16.6 Tvector3\_double.length

Synopsis: Calculates the length of the vector.

Declaration: `function length : double`

Visibility: default

Description: Calculate the length of the vector: `length=sqrt(data[0]**2+data[1]**2+data[2]**2)`. Try to use `squared_length` (888) if you are able to, as it is faster.

### 26.16.7 Tvector3\_double.squared\_length

Synopsis: Calculates the squared length of the vector.

Declaration: `function squared_length : double`

Visibility: default

Description: Calculate the squared length of the vector: `squared_length=data[0]**2+data[1]**2+data[2]**2`.

## 26.17 Tvector3\_extended

### 26.17.1 Description

The `Tvector3_extended` object provides a vector of three extended precision scalars.

### 26.17.2 Method overview

Page	Property	Description
<a href="#">889</a>	<code>init</code>	Initializes the vector, setting its elements to the values passed to the constructor.
<a href="#">889</a>	<code>init\_one</code>	Initializes the vector and sets its elements to one
<a href="#">888</a>	<code>init\_zero</code>	Initializes the vector and sets its elements to zero
<a href="#">889</a>	<code>length</code>	Calculates the length of the vector.
<a href="#">889</a>	<code>squared\_length</code>	Calculates the squared length of the vector.

### 26.17.3 Tvector3\_extended.init\_zero

Synopsis: Initializes the vector and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

### 26.17.4 Tvector3\_extended.init\_one

Synopsis: Initializes the vector and sets its elements to one

Declaration: `constructor init_one`

Visibility: default

### 26.17.5 Tvector3\_extended.init

Synopsis: Initializes the vector, setting its elements to the values passed to the constructor.

Declaration: `constructor init(a: extended;b: extended;c: extended)`

Visibility: default

### 26.17.6 Tvector3\_extended.length

Synopsis: Calculates the length of the vector.

Declaration: `function length : extended`

Visibility: default

Description: Calculate the length of the vector: `length=sqrt(data[0]**2+data[1]**2+data[2]**2)`. Try to use `squared_length` (889) if you are able to, as it is faster.

### 26.17.7 Tvector3\_extended.squared\_length

Synopsis: Calculates the squared length of the vector.

Declaration: `function squared_length : extended`

Visibility: default

Description: Calculate the squared length of the vector: `squared_length=data[0]**2+data[1]**2+data[2]**2`.

## 26.18 Tvector3\_single

### 26.18.1 Description

The `Tvector3_single` object provides a vector of three single precision scalars.

### 26.18.2 Method overview

Page	Property	Description
<a href="#">890</a>	<code>init</code>	Initializes the vector, setting its elements to the values passed to the constructor.
<a href="#">890</a>	<code>init\_one</code>	Initializes the vector and sets its elements to one
<a href="#">890</a>	<code>init\_zero</code>	Initializes the vector and sets its elements to zero
<a href="#">890</a>	<code>length</code>	Calculates the length of the vector.
<a href="#">890</a>	<code>squared\_length</code>	Calculates the squared length of the vector.

### 26.18.3 Tvector3\_single.init\_zero

Synopsis: Initializes the vector and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

### 26.18.4 Tvector3\_single.init\_one

Synopsis: Initializes the vector and sets its elements to one

Declaration: `constructor init_one`

Visibility: default

### 26.18.5 Tvector3\_single.init

Synopsis: Initializes the vector, setting its elements to the values passed to the constructor.

Declaration: `constructor init(a: single;b: single;c: single)`

Visibility: default

### 26.18.6 Tvector3\_single.length

Synopsis: Calculates the length of the vector.

Declaration: `function length : single`

Visibility: default

Description: Calculate the length of the vector: `length=sqrt(data[0]**2+data[1]**2+data[2]**2)`. Try to use `squared_length` ([890](#)) if you are able to, as it is faster.

### 26.18.7 Tvector3\_single.squared\_length

Synopsis: Calculates the squared length of the vector.

Declaration: `function squared_length : single`

Visibility: default

Description: Calculate the squared length of the vector: `squared_length=data[0]**2+data[1]**2+data[2]**2`.

## 26.19 Tvector4\_double

### 26.19.1 Description

The `Tvector4_double` object provides a vector of four double precision scalars.

**26.19.2 Method overview**

Page	Property	Description
<a href="#">891</a>	<code>init</code>	Initializes the vector, setting its elements to the values passed to the constructor.
<a href="#">891</a>	<code>init\_one</code>	Initializes the vector and sets its elements to one
<a href="#">891</a>	<code>init\_zero</code>	Initializes the vector and sets its elements to zero
<a href="#">891</a>	<code>length</code>	Calculates the length of the vector.
<a href="#">891</a>	<code>squared\_length</code>	Calculates the squared length of the vector.

**26.19.3 Tvector4\_double.init\_zero**

Synopsis: Initializes the vector and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

**26.19.4 Tvector4\_double.init\_one**

Synopsis: Initializes the vector and sets its elements to one

Declaration: `constructor init_one`

Visibility: default

**26.19.5 Tvector4\_double.init**

Synopsis: Initializes the vector, setting its elements to the values passed to the constructor.

Declaration: `constructor init(a: double;b: double;c: double;d: double)`

Visibility: default

**26.19.6 Tvector4\_double.length**

Synopsis: Calculates the length of the vector.

Declaration: `function length : double`

Visibility: default

Description: Calculate the length of the vector: `length=sqrt(data[0]**2+data[1]**2+data[2]**2+data[3]**2)`. Try to use `squared_length` ([891](#)) if you are able to, as it is faster.

**26.19.7 Tvector4\_double.squared\_length**

Synopsis: Calculates the squared length of the vector.

Declaration: `function squared_length : double`

Visibility: default

Description: Calculate the squared length of the vector: `squared_length=data[0]**2+data[1]**2+data[2]**2+data[3]**2`.

## 26.20 Tvector4\_extended

### 26.20.1 Description

The `Tvector4_extended` object provides a vector of four extended precision scalars.

### 26.20.2 Method overview

Page	Property	Description
<a href="#">892</a>	<code>init</code>	Initializes the vector, setting its elements to the values passed to the constructor.
<a href="#">892</a>	<code>init\_one</code>	Initializes the vector and sets its elements to one
<a href="#">892</a>	<code>init\_zero</code>	Initializes the vector and sets its elements to zero
<a href="#">892</a>	<code>length</code>	Calculates the length of the vector.
<a href="#">893</a>	<code>squared\_length</code>	Calculates the squared length of the vector.

### 26.20.3 Tvector4\_extended.init\_zero

Synopsis: Initializes the vector and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

### 26.20.4 Tvector4\_extended.init\_one

Synopsis: Initializes the vector and sets its elements to one

Declaration: `constructor init_one`

Visibility: default

### 26.20.5 Tvector4\_extended.init

Synopsis: Initializes the vector, setting its elements to the values passed to the constructor.

Declaration: `constructor init(a: extended;b: extended;c: extended;d: extended)`

Visibility: default

### 26.20.6 Tvector4\_extended.length

Synopsis: Calculates the length of the vector.

Declaration: `function length : extended`

Visibility: default

Description: Calculate the length of the vector: `length=sqrt(data[0]**2+data[1]**2+data[2]**2+data[3]**2)`. Try to use `squared_length` ([893](#)) if you are able to, as it is faster.

### 26.20.7 Tvector4\_extended.squared\_length

Synopsis: Calculates the squared length of the vector.

Declaration: `function squared_length : extended`

Visibility: default

Description: Calculate the squared length of the vector: `squared_length=data[0]**2+data[1]**2+data[2]**2+data[3]**2`.

## 26.21 Tvector4\_single

### 26.21.1 Description

The `Tvector4_single` object provides a vector of four single precision scalars.

#### 26.21.2 Method overview

Page	Property	Description
<a href="#">893</a>	<code>init</code>	Initializes the vector, setting its elements to the values passed to the constructor.
<a href="#">893</a>	<code>init\_one</code>	Initializes the vector and sets its elements to one
<a href="#">893</a>	<code>init\_zero</code>	Initializes the vector and sets its elements to zero
<a href="#">894</a>	<code>length</code>	Calculates the length of the vector.
<a href="#">894</a>	<code>squared\_length</code>	Calculates the squared length of the vector.

### 26.21.3 Tvector4\_single.init\_zero

Synopsis: Initializes the vector and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

### 26.21.4 Tvector4\_single.init\_one

Synopsis: Initializes the vector and sets its elements to one

Declaration: `constructor init_one`

Visibility: default

### 26.21.5 Tvector4\_single.init

Synopsis: Initializes the vector, setting its elements to the values passed to the constructor.

Declaration: `constructor init(a: single;b: single;c: single;d: single)`

Visibility: default

### 26.21.6 Tvector4\_single.length

Synopsis: Calculates the length of the vector.

Declaration: `function length : single`

Visibility: default

Description: Calculate the length of the vector: `length=sqrt(data[0]**2+data[1]**2+data[2]**2+data[3]**2)`. Try to use `squared_length` ([894](#)) if you are able to, as it is faster.

### 26.21.7 Tvector4\_single.squared\_length

Synopsis: Calculates the squared length of the vector.

Declaration: `function squared_length : single`

Visibility: default

Description: Calculate the squared length of the vector: `squared_length=data[0]**2+data[1]**2+data[2]**2+data[3]**2`.



## Chapter 27

# Reference for unit 'mmx'

### 27.1 Overview

This document describes the MMX unit. This unit allows you to use the MMX capabilities of the Free Pascal compiler. It was written by Florian Klaempfl for the I386 processor. It should work on all platforms that use the Intel processor.

### 27.2 Constants, types and variables

#### 27.2.1 Constants

```
is_amd_3d_cpu : Boolean = false
```

The `is_amd_3d_cpu` initialized constant allows you to determine if the computer has the AMD 3D extensions. It is set correctly in the unit's initialization code.

```
is_amd_3d_dsp_cpu : Boolean = false
```

The `is_amd_3d_dsp_cpu` initialized constant allows you to determine if the computer has the AMD 3D DSP extensions. It is set correctly in the unit's initialization code.

```
is_amd_3d_mmx_cpu : Boolean = false
```

The `is_amd_3d_mmx_cpu` initialized constant allows you to determine if the computer has the AMD 3D MMX extensions. It is set correctly in the unit's initialization code.

```
is_mmx_cpu : Boolean = false
```

The `is_mmx_cpu` initialized constant allows you to determine if the computer has MMX extensions. It is set correctly in the unit's initialization code.

```
is_sse2_cpu : Boolean = false
```

The `is_sse2_cpu` initialized constant allows you to determine if the computer has the SSE2 extensions. It is set correctly in the unit's initialization code.

```
is_sse_cpu : Boolean = false
```

The `is_sse_cpu` initialized constant allows you to determine if the computer has the SSE extensions. It is set correctly in the unit's initialization code.

### 27.2.2 Types

`pmmxbyte = ^tmmxbyte`

Pointer to `tmmxbyte` (896) array type

`pmmxcardinal = ^tmmxcardinal`

Pointer to `tmmxcardinal` (896) array type

`pmmxinteger = ^tmmxinteger`

Pointer to `tmmxinteger` (896) array type

`pmmxlongint = ^tmmxlongint`

Pointer to `tmmxlongint` (896) array type

`pmmxshortint = ^tmmxshortint`

Pointer to `tmmxshortint` (896) array type

`pmmxsingle = ^tmmxsingle`

Pointer to `tmmxsingle` (896) array type

`pmmxword = ^tmmxword`

Pointer to `tmmxword` (896) array type

`tmmxbyte = Array[0..7] of Byte`

Array of bytes, 64 bits in size

`tmmxcardinal = Array[0..1] of cardinal`

Array of cardinals, 64 bits in size

`tmmxinteger = Array[0..3] of Integer`

Array of integers, 64 bits in size

`tmmxlongint = Array[0..1] of LongInt`

Array of longint, 64 bits in size

`tmmxshortint = Array[0..7] of ShortInt`

Array of shortints, 64 bits in size

`tmmxsingle = Array[0..1] of single`

Array of singles, 64 bits in size

`tmmxword = Array[0..3] of Word`

Array of words, 64 bits in size

## 27.3 Procedures and functions

### 27.3.1 emms

Synopsis: Reset floating point registers

Declaration: `procedure emms`

Visibility: `default`

Description: `Emms` sets all floating point registers to empty. This procedure must be called after you have used any MMX instructions, if you want to use floating point arithmetic. If you just want to move floating point data around, it isn't necessary to call this function, the compiler doesn't use the FPU registers when moving data. Only when doing calculations, you should use this function. The following code demonstrates this:

```
Program MMXDemo;
uses mmx;
var
  dl : double;
  a : array[0..10000] of double;
  i : longint;
begin
  dl:=1.0;
  {$mmx+}
  { floating point data is used, but we do _no_ arithmetic }
  for i:=0 to 10000 do
    a[i]:=d2; { this is done with 64 bit moves }
  {$mmx-}
  emms; { clear fpu }
  { now we can do floating point arithmetic again }
end.
```

See also: `femms` ([897](#))

### 27.3.2 femms

Synopsis: Reset floating point registers - AMD version

Declaration: `procedure femms`

Visibility: `default`

Description: `femms` executes the `femms` assembler instruction for AMD processors. it is not supported by all assemblers, hence it is coded as byte codes.

See also: `emms` ([897](#))

## Chapter 28

# Reference for unit 'Mouse'

### 28.1 Overview

The `Mouse` unit implements a platform independent mouse handling interface. It is implemented identically on all platforms supported by Free Pascal and can be enhanced with custom drivers, should this be needed. It is intended to be used only in text-based screens, for instance in conjunction with the keyboard and video unit. No support for graphical screens is implemented, and there are (currently) no plans to implement this.

### 28.2 Writing a custom mouse driver

The `mouse` unit has support for adding a custom mouse driver. This can be used to add support for mice not supported by the standard Free Pascal driver, but also to enhance an existing driver for instance to log mouse events or to implement a record and playback function.

The following unit shows how a mouse driver can be enhanced by adding some logging capabilities to the driver.

### 28.3 Constants, types and variables

#### 28.3.1 Constants

```
errMouseBase = 1030
```

Base for mouse error codes.

```
errMouseInitError = errMouseBase+0
```

Mouse initialization error

```
errMouseNotImplemented = errMouseBase+1
```

Mouse driver not implemented.

```
MouseActionDown = $0001
```

Mouse button down event signal.

```
MouseActionMove = $0004
```

Mouse cursor move event signal.

```
MouseActionUp = $0002
```

Mouse button up event signal.

```
MouseEventBufSize = 16
```

The mouse unit has a mechanism to buffer mouse events. This constant defines the size of the event buffer.

```
MouseLeftButton = $01
```

Left mouse button event.

```
MouseMiddleButton = $04
```

Middle mouse button event.

```
MouseRightButton = $02
```

Right mouse button event.

### 28.3.2 Types

```
PMouseEvent = ^TMouseEvent
```

Pointer to TMouseEvent (900) record.

```
TMouseDriver = record
  UseDefaultQueue : Boolean;
  InitDriver : procedure;
  DoneDriver : procedure;
  DetectMouse : function : Byte;
  ShowMouse : procedure;
  HideMouse : procedure;
  GetMouseX : function : Word;
  GetMouseY : function : Word;
  GetMouseButtons : function : Word;
  SetMouseXY : procedure(x: Word;y: Word);
  GetMouseEvent : procedure(var MouseEvent: TMouseEvent);
  PollMouseEvent : function(var MouseEvent: TMouseEvent) : Boolean;
  PutMouseEvent : procedure(const MouseEvent: TMouseEvent);
end
```

The TMouseDriver record is used to implement a mouse driver in the SetMouseDriver (905) function. Its fields must be filled in before calling the SetMouseDriver (905) function.

```

TMouseEvent = packed record
  buttons : Word;
  x : Word;
  y : Word;
  Action : Word;
end

```

The `TMouseEvent` is the central type of the mouse unit, it is used to describe all mouse events.

The `Buttons` field describes which buttons were down when the event occurred. The `x`, `y` fields describe where the event occurred on the screen. The `Action` describes what action was going on when the event occurred. The `Buttons` and `Action` field can be examined using the constants defined in the unit interface.

### 28.3.3 Variables

```
MouseButtons : Byte
```

This variable keeps track of the last known mouse button state. Do not use.

```
MouseIntFlag : Byte
```

This variable keeps track of the last known internal mouse state. Do not use.

```
MouseWhereX : Word
```

This variable keeps track of the last known cursor position. Do not use.

```
MouseWhereY : Word
```

This variable keeps track of the last known cursor position. Do not use.

## 28.4 Procedures and functions

### 28.4.1 DetectMouse

Synopsis: Detect the presence of a mouse.

Declaration: `function DetectMouse : Byte`

Visibility: default

Description: `DetectMouse` detects whether a mouse is attached to the system or not. If there is no mouse, then zero is returned. If a mouse is attached, then the number of mouse buttons is returned.

This function should be called after the mouse driver was initialized.

Errors: None.

See also: `InitMouse` ([904](#)), `DoneMouse` ([901](#))

**Listing:** `./mouseex/ex1.pp`

---

```

Program Example1;

{ Program to demonstrate the DetectMouse function. }

Uses mouse;

Var
    Buttons : Byte;

begin
    InitMouse;
    Buttons:=DetectMouse;
    If Buttons=0 then
        WriteLn( 'No mouse present.' )
    else
        WriteLn( 'Found mouse with ',Buttons,' buttons.' );
    DoneMouse;
end.

```

---

### 28.4.2 DoneMouse

Synopsis: Deinitialize mouse driver.

Declaration: `procedure DoneMouse`

Visibility: default

Description: `DoneMouse` De-initializes the mouse driver. It cleans up any memory allocated when the mouse was initialized, or removes possible mouse hooks from memory. The mouse functions will not work after `DoneMouse` was called. If `DoneMouse` is called a second time, it will exit at once. `InitMouse` should be called before `DoneMouse` can be called again.

For an example, see most other mouse functions.

Errors: None.

See also: `DetectMouse` ([900](#)), `InitMouse` ([904](#))

### 28.4.3 GetMouseButtons

Synopsis: Get the state of the mouse buttons

Declaration: `function GetMouseButtons : Word`

Visibility: default

Description: `GetMouseButtons` returns the current button state of the mouse, i.e. it returns a or-ed combination of the following constants:

**MouseLeftButton** When the left mouse button is held down.

**MouseRightButton** When the right mouse button is held down.

**MouseMiddleButton** When the middle mouse button is held down.

Errors: None.

See also: `GetMouseEvent` ([902](#)), `GetMouseX` ([902](#)), `GetMouseY` ([903](#))

**Listing:** ./mouseex/ex2.pp

**Program** Example2;

*{ Program to demonstrate the GetMouseButtons function. }*

**Uses** mouse;

**begin**

InitMouse;

**WriteLn**('Press right mouse button to exit program');

**While** (GetMouseButtons<>MouseRightButton) **do** ;

DoneMouse;

**end.**

#### 28.4.4 GetMouseDriver

**Synopsis:** Get a copy of the currently active mouse driver.

**Declaration:** `procedure GetMouseDriver (var Driver: TMouseDriver)`

**Visibility:** default

**Description:** `GetMouseDriver` returns the currently set mouse driver. It can be used to retrieve the current mouse driver, and override certain callbacks.

A more detailed explanation about getting and setting mouse drivers can be found in `mousedrv` (898).

For an example, see the section on writing a custom mouse driver, `mousedrv` (898)

**Errors:** None.

**See also:** `SetMouseDriver` (905)

#### 28.4.5 GetMouseEvent

**Synopsis:** Get next mouse event from the queue.

**Declaration:** `procedure GetMouseEvent (var MouseEvent: TMouseEvent)`

**Visibility:** default

**Description:** `GetMouseEvent` returns the next mouse event (a movement, button press or button release), and waits for one if none is available in the queue.

Some mouse drivers can implement a mouse event queue which can hold multiple events till they are fetched. Others don't, and in that case, a one-event queue is implemented for use with `PollMouseEvent` (905).

**Errors:** None.

**See also:** `GetMouseButtons` (901), `GetMouseX` (902), `GetMouseY` (903)

#### 28.4.6 GetMouseX

**Synopsis:** Query the current horizontal position of the mouse cursor.

**Declaration:** `function GetMouseX : Word`



Visibility: default

Description: `GetMouseX` returns the current X position of the mouse. X is measured in characters, starting at 0 for the left side of the screen.

Errors: None.

See also: `GetMouseButtons` (901), `GetMouseEvent` (902), `GetMouseY` (903)

**Listing:** `./mouseex/ex4.pp`

---

**Program** `Example4`;

*{ Program to demonstrate the GetMouseX,GetMouseY functions. }*

**Uses** `mouse`;

**Var**

`X,Y : Word`;

**begin**

`InitMouse`;

**WriteLn** ( 'Move mouse cursor to square 10,10 to end' );

**Repeat**

`X:=GetMouseX`;

`Y:=GetMouseY`;

**WriteLn** ( 'X,Y= ( ',X, ', ',Y, ' ) ' );

**Until** (X=9) **and** (Y=9);

`DoneMouse`;

**end.**

---

### 28.4.7 GetMouseY

Synopsis: Query the current vertical position of the mouse cursor.

Declaration: `function GetMouseY : Word`

Visibility: default

Description: `GetMouseY` returns the current Y position of the mouse. Y is measured in characters, starting at 0 for the top of the screen.

For an example, see `GetMouseX` (902)

Errors: None.

See also: `GetMouseButtons` (901), `GetMouseEvent` (902), `GetMouseX` (902)

### 28.4.8 HideMouse

Synopsis: Hide the mouse cursor.

Declaration: `procedure HideMouse`

Visibility: default

Description: `HideMouse` hides the mouse cursor. This may or may not be implemented on all systems, and depends on the driver.

Errors: None.

See also: ShowMouse ([906](#))

**Listing:** ./mouseex/ex5.pp

---

**Program** Example5;

*{ Program to demonstrate the HideMouse function. }*

**Uses** mouse;

**Var**

Event : TMouseEvent;

Visible : Boolean;

**begin**

InitMouse;

ShowMouse;

Visible:=True;

**WriteIn**('Press left mouse button to hide/show, right button quits');

**Repeat**

GetMouseEvent(Event);

**With** Event **do**

**If** (Buttons=MouseLeftbutton) **and**  
(Action=MouseActionDown) **then**

**begin**

**If** Visible **then**

HideMouse

**else**

ShowMouse;

Visible:=**Not** Visible;

**end**;

**Until** (Event.Buttons=MouseRightButton) **and**  
(Event.Action=MouseActionDown);

DoneMouse;

**end.**

---

### 28.4.9 InitMouse

Synopsis: Initialize the FPC mouse driver.

Declaration: procedure InitMouse

Visibility: default

Description: InitMouse Initializes the mouse driver. This will allocate any data structures needed for the mouse to function. All mouse functions can be used after a call to InitMouse.

A call to InitMouse must always be followed by a call to DoneMouse ([901](#)) at program exit. Failing to do so may leave the mouse in an unusable state, or may result in memory leaks.

For an example, see most other functions.

Errors: None.

See also: DoneMouse ([901](#)), DetectMouse ([900](#))

### 28.4.10 PollMouseEvent

Synopsis: Query next mouse event. Do not wait if none available.

Declaration: `function PollMouseEvent (var MouseEvent: TMouseEvent) : Boolean`

Visibility: default

Description: `PollMouseEvent` checks whether a mouse event is available, and returns it in `MouseEvent` if one is found. The function result is `True` in that case. If no mouse event is pending, the function result is `False`, and the contents of `MouseEvent` is undefined.

Note that after a call to `PollMouseEvent`, the event should still be removed from the mouse event queue with a call to `GetMouseEvent`.

Errors: None.

See also: `GetMouseEvent` (902), `PutMouseEvent` (905)

### 28.4.11 PutMouseEvent

Synopsis: Put a mouse event in the venet queue.

Declaration: `procedure PutMouseEvent (const MouseEvent: TMouseEvent)`

Visibility: default

Description: `PutMouseEvent` adds `MouseEvent` to the input queue. The next call to `GetMouseEvent` (902) or `PollMouseEvent` will then return `MouseEvent`.

Please note that depending on the implementation the mouse event queue can hold only one value.

Errors: None.

See also: `GetMouseEvent` (902), `PollMouseEvent` (905)

### 28.4.12 SetMouseDriver

Synopsis: Set a new mouse driver.

Declaration: `procedure SetMouseDriver (const Driver: TMouseDriver)`

Visibility: default

Description: `SetMouseDriver` sets the mouse driver to `Driver`. This function should be called before `InitMouse` (904) is called, or after `DoneMouse` is called. If it is called after the mouse has been initialized, it does nothing.

For more information on setting the mouse driver, `mousedrv` (898).

For an example, see `mousedrv` (898)

Errors:

See also: `InitMouse` (904), `DoneMouse` (901), `GetMouseDriver` (902)

### 28.4.13 SetMouseXY

Synopsis: Set the mouse cursor position.

Declaration: `procedure SetMouseXY(x: Word; y: Word)`

Visibility: default

Description: `SetMouseXY` places the mouse cursor on X, Y. X and Y are zero based character coordinates: 0, 0 is the top-left corner of the screen, and the position is in character cells (i.e. not in pixels).

Errors: None.

See also: `GetMouseX` (902), `GetMouseY` (903)

**Listing:** `./mouseex/ex7.pp`

---

**Program** `Example7;`

*{ Program to demonstrate the SetMouseXY function. }*

**Uses** `mouse;`

**begin**

`InitMouse;`

`WriteLn('Click right mouse button to quit.');`

`SetMouseXY(40,12);`

**Repeat**

`WriteLn(GetMouseX, ' ', GetMouseY);`

**If** `(GetMouseX>70) then`

`SetMouseXY(10,GetMouseY);`

**If** `(GetMouseY>20) then`

`SetMouseXY(GetMouseX, 5);`

**Until** `(GetMouseButtons=MouseRightButton);`

`DoneMouse;`

**end.**

---

### 28.4.14 ShowMouse

Synopsis: Show the mouse cursor.

Declaration: `procedure ShowMouse`

Visibility: default

Description: `ShowMouse` shows the mouse cursor if it was previously hidden. The capability to hide or show the mouse cursor depends on the driver.

For an example, see `HideMouse` (903)

Errors: None.

See also: `HideMouse` (903)

## Chapter 29

# Reference for unit 'Objects'

### 29.1 Overview

This document documents the `objects` unit. The unit was implemented by many people, and was mainly taken from the FreeVision sources. It has been ported to all supported platforms.

The methods and fields that are in a `Private` part of an object declaration have been left out of this documentation.

### 29.2 Constants, types and variables

#### 29.2.1 Constants

`coIndexError = -1`

Collection list error: Index out of range

`coOverflow = -2`

Collection list error: Overflow

`DefaultTPCompatible : Boolean = false`

`DefaultTPCompatible` is used to initialize `tstream.tpcompatible` (??).

`MaxBytes = 128*1024*128`

Maximum data size (in bytes)

`MaxCollectionSize = MaxBytes div SizeOf(Pointer)`

Maximum collection size (in items)

`MaxPtrs = MaxBytes div SizeOf(Pointer)`

Maximum data size (in pointers)

`MaxReadBytes = $7fffffff`

Maximum data that can be read from a stream (not used)

`MaxTPCompatibleCollectionSize = 65520div4`

Maximum collection size (in items, same value as in TP)

`MaxWords = MaxBytes div SizeOf(Word)`

Maximum data size (in words)

`RCollection : TStreamRec = (ObjType:50;VmtLink:Ofs(KindOf(TCollection)^);Load:@TCollection)`

Default stream record for the TCollection (924) object.

`RStrCollection : TStreamRec = (ObjType:69;VmtLink:Ofs(KindOf(TStrCollection)^);Load:@TStrCollection)`

Default stream record for the TStrCollection (963) object.

`RStringCollection : TStreamRec = (ObjType:51;VmtLink:Ofs(KindOf(TStringCollection)^);Load:@TStringCollection)`

Default stream record for the TStringCollection (973) object.

`RStringList : TStreamRec = (ObjType:52;VmtLink:Ofs(KindOf(TStringList)^);Load:@TStringList)`

Default stream record for the TStringList (975) object.

`RStrListMaker : TStreamRec = (ObjType:52;VmtLink:Ofs(KindOf(TStrListMaker)^);Load:@TStrListMaker)`

Default stream record for the TStrListMaker (977) object.

`stCreate = $3C00`

Stream initialization mode: Create new file

`stError = -1`

Stream error codes: Access error

`stGetError = -5`

Stream error codes: Get object error

`stInitError = -2`

Stream error codes: Initialize error

`stOk = 0`

Stream error codes: No error

`stOpen = $3D02`

Stream initialization mode: Read/write access

`stOpenError = -8`

Stream error codes: Error opening stream

`stOpenRead = $3D00`

Stream initialization mode: Read access only

`stOpenWrite = $3D01`

Stream initialization mode: Write access only

`stPutError = -6`

Stream error codes: Put object error

`stReadError = -3`

Stream error codes: Stream read error

`StreamError : Pointer = nil`

Pointer to default stream error handler.

`stSeekError = -7`

Stream error codes: Seek error in stream

`stWriteError = -4`

Stream error codes: Stream write error

`vmtHeaderSize = 8`

Size of the VMT header in an object (not used).

### 29.2.2 Types

`AsciiZ = Array[0..255] of Char`

Filename - null terminated array of characters.

`FNameStr = String`

Filename - shortstring version.

```
LongRec = packed record
  Hi : Word;
  Lo : Word;
end
```

Record describing a longint (in Words)

```
PBufStream = ^TBufStream
```

Pointer to TBufStream (920) object.

```
PByteArray = ^TByteArray
```

Pointer to TByteArray (912)

```
PCharSet = ^TCharSet
```

Pointer to TCharSet (912).

```
PCollection = ^TCollection
```

Pointer to TCollection (924) object.

```
PDosStream = ^TDosStream
```

Pointer to TDosStream (938) object.

```
PItemList = ^TItemList
```

Pointer to TItemList (912) object.

```
PMemoryStream = ^TMemoryStream
```

Pointer to TMemoryStream (943) object.

```
PObject = ^TObject
```

Pointer to TObject (945) object.

```
PPoint = ^TPoint
```

Pointer to TPoint (947) record.

```
PPointerArray = ^TPointerArray
```

Pointer to TPointerArray (912)

```
PRect = ^TRect
```

Pointer to TRect (947) object.



`PResourceCollection = ^TResourceCollection`

Pointer to `TResourceCollection` (953) object.

`PResourceFile = ^TResourceFile`

Pointer to `TResourceFile` (954) object.

`PSortedCollection = ^TSortedCollection`

Pointer to `TSortedCollection` (957) object.

`PStrCollection = ^TStrCollection`

Pointer to `TStrCollection` (963) object.

`PStream = ^TStream`

Pointer type to `TStream` (965)

`PStreamRec = ^TStreamRec`

Pointer to `TStreamRec` (912)

`PStrIndex = ^TStrIndex`

Pointer to `TStrIndex` (912) array.

`PString = PShortString`

Pointer to a shortstring.

`PStringCollection = ^TStringCollection`

Pointer to `TStringCollection` (973) object.

`PStringList = ^TStringList`

Pointer to `TStringList` (975) object.

`PStrListMaker = ^TStrListMaker`

Pointer to `TStrListMaker` (977) object.

```
PtrRec = packed record
  Ofs : Word;
  Seg : Word;
end
```

Record describing a pointer to a memory location.

`PUnSortedStrCollection = ^TUnSortedStrCollection`

Pointer to `TUnsortedStrCollection` (978) object.

`PWordArray = ^TWordArray`

Pointer to `TWordArray` (913)

`Sw_Integer = LongInt`

Alias for `longint`

`Sw_Word = Cardinal`

Alias for `Cardinal`

`TByteArray = Array[0..MaxBytes-1] of Byte`

Array with maximum allowed number of bytes.

`TCharSet = Set of Char`

Generic set of characters type.

`TItemList = Array[0..MaxCollectionSize-1] of Pointer`

Pointer array type used in a `TCollection` (924)

`TPointerArray = Array[0..MaxPtrs-1] of Pointer`

Array with maximum allowed number of pointers

```
TStreamRec = packed record
  ObjType : Sw_Word;
  VmtLink : pointer;
  Load : Pointer;
  Store : Pointer;
  Next : PStreamRec;
end
```

`TStreamRec` is used by the `Objects` unit streaming mechanism: when an object is registered, a `TStreamRec` record is added to a list of records. This list is used when objects need to be streamed from/streamed to a stream. It contains all the information needed to stream the object.

`TStrIndex = Array[0..9999] of TStrIndexRec`

Pointer array type used in a `TStringList` (975)

```
TStrIndexRec = packed record
  Key : Sw_Word;
  Count : Word;
  Offset : Word;
end
```

Record type used in a TStringList (975) to store the strings

```
TWordArray = Array[0..MaxWords-1] of Word
```

Array with maximum allowed number of words.

```
WordRec = packed record
  Hi : Byte;
  Lo : Byte;
end
```

Record describing a Word (in bytes)

### 29.2.3 Variables

```
invalidhandle : THandle
```

Value for invalid handle. Initial value for file stream handles or when the stream is closed.

## 29.3 Procedures and functions

### 29.3.1 Abstract

Synopsis: Abstract error handler.

Declaration: `procedure Abstract`

Visibility: default

Description: When implementing abstract methods, do not declare them as `abstract`. Instead, define them simply as `virtual`. In the implementation of such abstract methods, call the `Abstract` procedure. This allows explicit control of what happens when an abstract method is called.

The current implementation of `Abstract` terminates the program with a run-time error 211.

Errors: None.

### 29.3.2 CallPointerConstructor

Synopsis: Call a constructor with a pointer argument.

Declaration: `function CallPointerConstructor(Ctor: pointer; Obj: pointer; VMT: pointer; Param1: pointer) : pointer`

Visibility: default

Note that this can only be used on constructors that require a pointer as the sole argument. It can also be used to call a constructor with a single argument by reference.

Errors: If the local function expects other parameters than a pointer, the stack may become corrupted.

See also: [CallPointerMethod \(914\)](#), [CallVoidMethod \(915\)](#), [CallPointerLocal \(914\)](#), [CallVoidLocal \(915\)](#), [CallVoidMethodLocal \(916\)](#), [CallVoidConstructor \(915\)](#), [CallPointerConstructor \(913\)](#)

### 29.3.6 CallVoidConstructor

Synopsis: Call a constructor with no arguments

Declaration: `function CallVoidConstructor (Ctor: pointer; Obj: pointer; VMT: pointer)  
: pointer`

Visibility: default

Description: `CallVoidConstructor` calls the constructor of an object. `Ctor` is the address of the constructor, `Obj` is a pointer to the instance. If it is `Nil`, then a new instance is allocated. `VMT` is a pointer to the object's VMT. The return value is a pointer to the instance.

Note that this can only be used on constructors that require no arguments.

Errors: If the constructor expects arguments, the stack may be corrupted.

See also: [CallPointerConstructor \(913\)](#), [CallPointerMethod \(914\)](#), [CallVoidLocal \(915\)](#), [CallPointerLocal \(914\)](#), [CallVoidMethodLocal \(916\)](#), [CallPointerMethodLocal \(914\)](#)

### 29.3.7 CallVoidLocal

Synopsis: Call a local nested procedure.

Declaration: `function CallVoidLocal (Func: pointer; Frame: Pointer) : pointer`

Visibility: default

Description: `CallVoidLocal` calls the local procedure with address `Func`, where `Frame` is the frame of the wrapping function.

Errors: If the local function expects parameters, the stack may become corrupted.

See also: [CallPointerMethod \(914\)](#), [CallVoidMethod \(915\)](#), [CallPointerLocal \(914\)](#), [CallVoidMethodLocal \(916\)](#), [CallPointerMethodLocal \(914\)](#), [CallVoidConstructor \(915\)](#), [CallPointerConstructor \(913\)](#)

### 29.3.8 CallVoidMethod

Synopsis: Call an object method

Declaration: `function CallVoidMethod (Method: pointer; Obj: pointer) : pointer`

Visibility: default

Description: `CallVoidMethod` calls the method with address `Method` for instance `Obj`. It returns a pointer to the instance.

Errors: If the method expects parameters, the stack may become corrupted.

See also: [CallPointerMethod \(914\)](#), [CallVoidLocal \(915\)](#), [CallPointerLocal \(914\)](#), [CallVoidMethodLocal \(916\)](#), [CallPointerMethodLocal \(914\)](#), [CallVoidConstructor \(915\)](#), [CallPointerConstructor \(913\)](#)

### 29.3.9 CallVoidMethodLocal

Synopsis: Call a local procedure of a method

Declaration: `function CallVoidMethodLocal (Func: pointer; Frame: Pointer; Obj: pointer)  
: pointer`

Visibility: default

Description: `CallVoidMethodLocal` calls the local procedure with address `Func`, where `Frame` is the frame of the wrapping method.

Errors: If the local function expects parameters, the stack may become corrupted.

See also: `CallPointerMethod` (914), `CallVoidMethod` (915), `CallPointerLocal` (914), `CallVoidLocal` (915), `CallPointerMethodLocal` (914), `CallVoidConstructor` (915), `CallPointerConstructor` (913)

### 29.3.10 DisposeStr

Synopsis: Dispose of a shortstring which was allocated on the heap.

Declaration: `procedure DisposeStr (P: PString)`

Visibility: default

Description: `DisposeStr` removes a dynamically allocated string from the heap.

For an example, see `NewStr` (917).

Errors: None.

See also: `NewStr` (917), `SetStr` (919)

### 29.3.11 LongDiv

Synopsis: Overflow safe divide

Declaration: `function LongDiv (X: LongInt; Y: Integer) : Integer`

Visibility: default

Description: `LongDiv` divides `X` by `Y`. The result is of type `Integer` instead of type `Longint`, as you would get normally.

Errors: If `Y` is zero, a run-time error will be generated.

See also: `LongMul` (916)

### 29.3.12 LongMul

Synopsis: Overflow safe multiply.

Declaration: `function LongMul (X: Integer; Y: Integer) : LongInt`

Visibility: default

Description: `LongMul` multiplies `X` with `Y`. The result is of type `Longint`. This avoids possible overflow errors you would normally get when multiplying `X` and `Y` that are too big.

Errors: None.

See also: `LongDiv` (916)

### 29.3.13 NewStr

Synopsis: Allocate a copy of a shortstring on the heap.

Declaration: `function NewStr(const S: String) : PString`

Visibility: default

Description: `NewStr` makes a copy of the string `S` on the heap, and returns a pointer to this copy. If the string is empty then `Nil` is returned.

The allocated memory is not based on the declared size of the string passed to `NewStr`, but is based on the actual length of the string.

Errors: If not enough memory is available, an 'out of memory' error will occur.

See also: `DisposeStr` (916), `SetStr` (919)

**Listing:** `./objectex/ex40.pp`

---

```

Program ex40;

{ Program to demonstrate the NewStr function }

Uses Objects;

Var S : String;
    P : PString;

begin
    S:= 'Some really cute string';
    P:=NewStr(S);
    If P^<>S then
        WriteLn ( 'Oh-oh... Something is wrong !!' );
    DisposeStr(P);
end.

```

---

### 29.3.14 RegisterObjects

Synopsis: Register standard objects.

Declaration: `procedure RegisterObjects`

Visibility: default

Description: `RegisterObjects` registers the following objects for streaming:

1. `TCollection`, see `TCollection` (924).
2. `TStringCollection`, see `TStringCollection` (973).
3. `TStrCollection`, see `TStrCollection` (963).

Errors: None.

See also: `RegisterType` (918)

### 29.3.15 RegisterType

Synopsis: Register new object for streaming.

Declaration: `procedure RegisterType (var S: TStreamRec)`

Visibility: default

Description: `RegisterType` registers a new type for streaming. An object cannot be streamed unless it has been registered first. The stream record `S` needs to have the following fields set:

**ObjType: Sw\_Word** This should be a unique identifier. Each possible type should have it's own identifier.

**VmtLink: pointer** This should contain a pointer to the VMT (Virtual Method Table) of the object you try to register.

**Load : Pointer** is a pointer to a method that initializes an instance of that object, and reads the initial values from a stream. This method should accept as it's sole argument a `PStream` type variable.

**Store: Pointer** is a pointer to a method that stores an instance of the object to a stream. This method should accept as it's sole argument a `PStream` type variable.

The VMT of the object can be retrieved with the following expression:

```
VmtLink: Ofs (TypeOf (MyType) ^);
```

Errors: In case of error (if a object with the same `ObjType`) is already registered), run-time error 212 occurs.

Listing: `./objectex/myobject.pp`

---

```
Unit MyObject;
```

#### Interface

```
Uses Objects;
```

#### Type

```
PMyObject = ^TMyObject;
TMyObject = Object (TObject)
  Field : Longint;
  Constructor Init;
  Constructor Load (Var Stream : TStream);
  Destructor Done;
  Procedure Store (Var Stream : TStream);
  Function GetField : Longint;
  Procedure SetField (Value : Longint);
end;
```

#### Implementation

```
Constructor TMyobject.Init;

begin
  Inherited Init;
  Field := -1;
end;
```



---

```

Constructor TMyobject.Load ( Var Stream : TStream );

begin
    Stream.Read( Field , Sizeof( Field ) );
end;

Destructor TMyObject.Done;

begin
end;

Function TMyObject.GetField : Longint;

begin
    GetField := Field;
end;

Procedure TMyObject.SetField ( Value : Longint );

begin
    Field := Value;
end;

Procedure TMyObject.Store ( Var Stream : TStream );

begin
    Stream.Write( Field , SizeOf( Field ) );
end;

Const MyObjectRec : TStreamRec = (
    Objtype : 666;
    vmtlink : Ofs( TypeOf( TMyObject ) ^ );
    Load : @TMyObject.Load;
    Store : @TMyObject.Store;
    );

begin
    RegisterObjects;
    RegisterType ( MyObjectRec );
end.

```

---

### 29.3.16 SetStr

**Synopsis:** Allocate a copy of a shortstring on the heap.

**Declaration:** `procedure SetStr( var p: PString; const s: String )`

**Visibility:** default

**Description:** `SetStr` makes a copy of the string `S` on the heap and returns the pointer to this copy in `P`. If `P` pointed to another string (i.e. was not `Nil`, the memory is released first. Contrary to `NewStr` (917), if the string is empty then a pointer to an empty string is returned.

The allocated memory is not based on the declared size of the string passed to `NewStr`, but is based on the actual length of the string.

**Errors:** If not enough memory is available, an 'out of memory' error will occur.

See also: [DisposeStr \(916\)](#), [NewStr \(917\)](#)

## 29.4 TBufStream

### 29.4.1 Description

`TBufStream` implements a buffered file stream. That is, all data written to the stream is written to memory first. Only when the buffer is full, or on explicit request, the data is written to disk.

Also, when reading from the stream, first the buffer is checked if there is any unread data in it. If so, this is read first. If not the buffer is filled again, and then the data is read from the buffer.

The size of the buffer is fixed and is set when constructing the file.

This is useful if you need heavy throughput for your stream, because it speeds up operations.

### 29.4.2 Method overview

Page	Property	Description
<a href="#">921</a>	<code>Close</code>	Flush data and Close the file.
<a href="#">921</a>	<code>Done</code>	Close the file and cleans up the instance.
<a href="#">921</a>	<code>Flush</code>	FLush data from buffer, and write it to stream.
<a href="#">920</a>	<code>Init</code>	Initialize an instance of <code>TBufStream</code> and open the file.
<a href="#">923</a>	<code>Open</code>	Open the file if it is closed.
<a href="#">923</a>	<code>Read</code>	Read data from the file to a buffer in memory.
<a href="#">922</a>	<code>Seek</code>	Set current position in file.
<a href="#">922</a>	<code>Truncate</code>	Flush buffer, and truncate the file at current position.
<a href="#">923</a>	<code>Write</code>	Write data to the file from a buffer in memory.

### 29.4.3 TBufStream.Init

**Synopsis:** Initialize an instance of `TBufStream` and open the file.

**Declaration:** `constructor Init (FileName: FNameStr; Mode: Word; Size: Word)`

**Visibility:** default

**Description:** `Init` instantiates an instance of `TBufStream`. The name of the file that contains (or will contain) the data of the stream is given in `FileName`. The `Mode` parameter determines whether a new file should be created and what access rights you have on the file. It can be one of the following constants:

**`stCreate`** Creates a new file.

**`stOpenRead`** Read access only.

**`stOpenWrite`** Write access only.

**`stOpenRead`** and write access.

The `Size` parameter determines the size of the buffer that will be created. It should be different from zero.

For an example see `TBufStream.Flush` ([921](#)).

**Errors:** On error, `Status` is set to `stInitError`, and `ErrorInfo` is set to the dos error code.

See also: `TDosStream.Init` ([939](#)), `TBufStream.Done` ([921](#))

### 29.4.4 TBufStream.Done

Synopsis: Close the file and cleans up the instance.

Declaration: `destructor Done; Virtual`

Visibility: `default`

Description: `Done` flushes and closes the file if it was open and cleans up the instance of `TBufStream`.

For an example see `TBufStream.Flush` (921).

Errors: None.

See also: `TDosStream.Done` (939), `TBufStream.Init` (920), `TBufStream.Close` (921)

### 29.4.5 TBufStream.Close

Synopsis: Flush data and Close the file.

Declaration: `procedure Close; Virtual`

Visibility: `default`

Description: `Close` flushes and closes the file if it was open, and sets `Handle` to -1. Contrary to `Done` (921) it does not clean up the instance of `TBufStream`

For an example see `TBufStream.Flush` (921).

Errors: None.

See also: `TStream.Close` (969), `TBufStream.Init` (920), `TBufStream.Done` (921)

### 29.4.6 TBufStream.Flush

Synopsis: FLush data from buffer, and write it to stream.

Declaration: `procedure Flush; Virtual`

Visibility: `default`

Description: When the stream is in write mode, the contents of the buffer are written to disk, and the buffer position is set to zero. When the stream is in read mode, the buffer position is set to zero.

Errors: Write errors may occur if the file was in write mode. see `Write` (923) for more info on the errors.

See also: `TStream.Close` (969), `TBufStream.Init` (920), `TBufStream.Done` (921)

**Listing:** `./objectex/ex15.pp`

---

**Program** `ex15;`

*{ Program to demonstrate the TStream.Flush method }*

**Uses** `Objects;`

**Var** `L : String;`

`P : PString;`

`S : PBufStream; { Only one with Flush implemented. }`

**begin**

---

```

L:= 'Some constant string';
{ Buffer size of 100 }
S:=New(PBufStream, Init('test.dat', stcreate, 100));
WriteLn ('Writing "', L, '" to stream with handle ', S^.Handle);
S^.WriteStr(@L);
{ At this moment, there is no data on disk yet. }
S^.Flush;
{ Now there is. }
S^.WriteStr(@L);
{ Close calls flush first }
S^.Close;
WriteLn ('Closed stream. File handle is ', S^.Handle);
S^.Open (stOpenRead);
P:=S^.ReadStr;
L:=P^;
DisposeStr(P);
WriteLn ('Read "', L, '" from stream with handle ', S^.Handle);
S^.Close;
Dispose (S, Done);
end.

```

---

### 29.4.7 TBufStream.Truncate

Synopsis: Flush buffer, and truncate the file at current position.

Declaration: `procedure Truncate; Virtual`

Visibility: default

Description: If the status of the stream is `stOK`, then `Truncate` tries to flush the buffer, and then truncates the stream size to the current file position.

For an example, see `TDosStream.Truncate` (940).

Errors: Errors can be those of `Flush` (921) or `TDosStream.Truncate` (940).

See also: `TStream.Truncate` (970), `TDosStream.Truncate` (940), `TStream.GetSize` (967)

### 29.4.8 TBufStream.Seek

Synopsis: Set current position in file.

Declaration: `procedure Seek(Pos: LongInt); Virtual`

Visibility: default

Description: If the stream's status is `stOK`, then `Seek` sets the file position to `Pos`. `Pos` is a zero-based offset, counted from the beginning of the file.

For an example, see `TStream.Seek` (971);

Errors: In case an error occurs, the stream's status is set to `stSeekError`, and the OS error code is stored in `ErrorInfo`.

See also: `TStream.Seek` (971), `TStream.GetPos` (967)

### 29.4.9 TBufStream.Open

Synopsis: Open the file if it is closed.

Declaration: `procedure Open(OpenMode: Word); Virtual`

Visibility: default

Description: If the stream's status is `stOK`, and the stream is closed then `Open` re-opens the file stream with mode `OpenMode`. This call can be used after a `Close` (921) call.

For an example, see `TDosStream.Open` (942).

Errors: If an error occurs when re-opening the file, then `Status` is set to `stOpenError`, and the OS error code is stored in `ErrorInfo`

See also: `TStream.Open` (969), `TBufStream.Close` (921)

### 29.4.10 TBufStream.Read

Synopsis: Read data from the file to a buffer in memory.

Declaration: `procedure Read(var Buf; Count: LongInt); Virtual`

Visibility: default

Description: If the Stream is open and the stream status is `stOK` then `Read` will read `Count` bytes from the stream and place them in `Buf`.

`Read` will first try to read the data from the stream's internal buffer. If insufficient data is available, the buffer will be filled before continuing to read. This process is repeated until all needed data has been read.

For an example, see `TStream.Read` (972).

Errors: In case of an error, `Status` is set to `StReadError`, and `ErrorInfo` gets the OS specific error, or 0 when an attempt was made to read beyond the end of the stream.

See also: `TStream.Read` (972), `TBufStream.Write` (923)

### 29.4.11 TBufStream.Write

Synopsis: Write data to the file from a buffer in memory.

Declaration: `procedure Write(var Buf; Count: LongInt); Virtual`

Visibility: default

Description: If the Stream is open and the stream status is `stOK` then `Write` will write `Count` bytes from `Buf` and place them in the stream.

`Write` will first try to write the data to the stream's internal buffer. When the internal buffer is full, then the contents will be written to disk. This process is repeated until all data has been written.

For an example, see `TStream.Read` (972).

Errors: In case of an error, `Status` is set to `StWriteError`, and `ErrorInfo` gets the OS specific error.

See also: `TStream.Write` (972), `TBufStream.Read` (923)

## 29.5 TCollection

### 29.5.1 Description

The `TCollection` object manages a collection of pointers or objects. It also provides a series of methods to manipulate these pointers or objects.

Whether or not objects are used depends on the kind of calls you use. All kinds come in 2 flavors, one for objects, one for pointers.

### 29.5.2 Method overview

Page	Property	Description
<a href="#">926</a>	<code>At</code>	Return the item at a certain index.
<a href="#">934</a>	<code>AtDelete</code>	Delete item at certain position.
<a href="#">933</a>	<code>AtFree</code>	Free an item at the indicates position, calling it's destructor.
<a href="#">937</a>	<code>AtInsert</code>	Insert an element at a certain position in the collection.
<a href="#">937</a>	<code>AtPut</code>	Set collection item, overwriting an existing value.
<a href="#">933</a>	<code>Delete</code>	Delete an item from the collection, but does not destroy it.
<a href="#">931</a>	<code>DeleteAll</code>	Delete all elements from the collection. Objects are not destroyed.
<a href="#">925</a>	<code>Done</code>	Clean up collection, release all memory.
<a href="#">936</a>	<code>Error</code>	Set error code.
<a href="#">928</a>	<code>FirstThat</code>	Return first item which matches a test.
<a href="#">935</a>	<code>ForEach</code>	Execute procedure for each item in the list.
<a href="#">932</a>	<code>Free</code>	Free item from collection, calling it's destructor.
<a href="#">930</a>	<code>FreeAll</code>	Release all objects from the collection.
<a href="#">934</a>	<code>FreeItem</code>	Destroy a non-nil item.
<a href="#">927</a>	<code>GetItem</code>	Read one item off the stream.
<a href="#">926</a>	<code>IndexOf</code>	Find the position of a certain item.
<a href="#">924</a>	<code>Init</code>	Instantiate a new collection.
<a href="#">932</a>	<code>Insert</code>	Insert a new item in the collection at the end.
<a href="#">928</a>	<code>LastThat</code>	Return last item which matches a test.
<a href="#">925</a>	<code>Load</code>	Initialize a new collection and load collection from a stream.
<a href="#">929</a>	<code>Pack</code>	Remove all <code>&gt;Nil</code> pointers from the collection.
<a href="#">938</a>	<code>PutItem</code>	Put one item on the stream
<a href="#">936</a>	<code>SetLimit</code>	Set maximum number of elements in the collection.
<a href="#">938</a>	<code>Store</code>	Write collection to a stream.

### 29.5.3 TCollection.Init

Synopsis: Instantiate a new collection.

Declaration: `constructor Init (ALimit: Sw_Integer; ADelta: Sw_Integer)`

Visibility: default

Description: `Init` initializes a new instance of a collection. It sets the (initial) maximum number of items in the collection to `ALimit`. `ADelta` is the increase size : The number of memory places that will be allocated in case `ALimit` is reached, and another element is added to the collection.

For an example, see `TCollection.ForEach` ([935](#)).

Errors: None.

See also: `TCollection.Load` ([925](#)), `TCollection.Done` ([925](#))

### 29.5.4 TCollection.Load

Synopsis: Initialize a new collection and load collection from a stream.

Declaration: constructor Load(var S: TStream)

Visibility: default

Description: Load initializes a new instance of a collection. It reads from stream S the item count, the item limit count, and the increase size. After that, it reads the specified number of items from the stream.

Errors: Errors returned can be those of GetItem (927).

See also: TCollection.Init (924), TCollection.GetItem (927), TCollection.Done (925)

**Listing:** ./objectex/ex22.pp

---

**Program** ex22;

*{ Program to demonstrate the TCollection.Load method }*

**Uses** Objects, MyObject; *{ For TMyObject definition and registration }*

**Var** C : PCollection;  
       M : PMyObject;  
       I : Longint;  
       S : PMemoryStream;

**begin**

  C:=**New**(PCollection, Init(100,10));

**For** I:=1 **to** 100 **do**

**begin**

      M:=**New**(PMyObject, Init);

      M^.SetField(100-I);

      C^.Insert(M);

**end**;

**WriteLn** ('Inserted ', C^.Count, ' objects');

  S:=**New**(PMemoryStream, Init(1000,10));

  C^.Store(S^);

  C^.FreeAll;

**Dispose**(C, Done);

  S^.Seek(0);

  C^.Load(S^);

**WriteLn** ('Read ', C^.Count, ' objects from stream.');

**Dispose**(S, Done);

**Dispose**(C, Done);

**end.**

---

### 29.5.5 TCollection.Done

Synopsis: Clean up collection, release all memory.

Declaration: destructor Done; Virtual

Visibility: default

Description: Done frees all objects in the collection, and then releases all memory occupied by the instance.

For an example, see TCollection.ForEach (935).

Errors: None.

See also: `TCollection.Init` (924), `TCollection.FreeAll` (930)

### 29.5.6 `TCollection.At`

Synopsis: Return the item at a certain index.

Declaration: `function At(Index: Sw_Integer) : Pointer`

Visibility: default

Description: `At` returns the item at position `Index`.

Errors: If `Index` is less than zero or larger than the number of items in the collection, `seep1{Error}{TCollection.Error}` is called with `coIndexError` and `Index` as arguments, resulting in a run-time error.

See also: `TCollection.Insert` (932)

**Listing:** `./objectex/ex23.pp`

---

**Program** `ex23`;

*{ Program to demonstrate the TCollection.At method }*

**Uses** `Objects, MyObject`; *{ For TMyObject definition and registration }*

**Var** `C` : `PCollection`;  
       `M` : `PMMyObject`;  
       `I` : `Longint`;

**begin**  
   `C:=New(PCollection, Init(100,10));`  
   **For** `I:=1 to 100 do`  
     **begin**  
       `M:=New(PMyObject, Init);`  
       `M^.SetField(100-I);`  
       `C^.Insert(M);`  
     **end**;  
   **For** `I:=0 to C^.Count-1 do`  
     **begin**  
       `M:=C^.At(I);`  
       `Writeln('Object ',i,' has field : ',M^.GetField);`  
     **end**;  
   `C^.FreeAll;`  
   `Dispose(C, Done);`  
**end.**

---

### 29.5.7 `TCollection.IndexOf`

Synopsis: Find the position of a certain item.

Declaration: `function IndexOf(Item: Pointer) : Sw_Integer; Virtual`

Visibility: default

Description: `IndexOf` returns the index of `Item` in the collection. If `Item` isn't present in the collection, -1 is returned.



Errors: If the item is not present, -1 is returned.

See also: `TCollection.At` (926), `TCollection.GetItem` (927), `TCollection.Insert` (932)

**Listing:** ./objectex/ex24.pp

---

```

Program ex24;

{ Program to demonstrate the TCollection.IndexOf method }

Uses Objects, MyObject; { For TMyObject definition and registration }

Var C : PCollection;
    M, Keep : PMyObject;
    I : Longint;

begin
  Randomize;
  C:=New(PCollection, Init(100,10));
  Keep:=Nil;
  For I:=1 to 100 do
    begin
      M:=New(PMyObject, Init);
      M^.SetField(I-1);
      If Random<0.1 then
        Keep:=M;
      C^.Insert(M);
    end;
  If Keep=Nil then
    begin
      Writeln ( 'Please run again. No object selected' );
      Halt (1);
    end;
  Writeln ( 'Selected object has field : ', Keep^.GetField );
  Write ( 'Selected object has index : ', C^.IndexOf(Keep) );
  Writeln ( ' should match it's field.' );
  C^.FreeAll;
  Dispose(C, Done);
end.
```

---

### 29.5.8 TCollection.GetItem

Synopsis: Read one item off the stream.

Declaration: `function GetItem(var S: TStream) : Pointer; Virtual`

Visibility: default

Description: `GetItem` reads a single item off the stream `S`, and returns a pointer to this item. This method is used internally by the `Load` method, and should not be used directly.

Errors: Possible errors are the ones from `TStream.Get` (965).

See also: `TStream.Get` (965), `TCollection.Store` (938)

### 29.5.9 TCollection.LastThat

Synopsis: Return last item which matches a test.

Declaration: `function LastThat (Test: Pointer) : Pointer`

Visibility: default

Description: This function returns the last item in the collection for which `Test` returns a non-nil result. `Test` is a function that accepts 1 argument: a pointer to an object, and that returns a pointer as a result.

Errors: None.

See also: `TCollection.FirstThat` ([928](#))

**Listing:** `./objectex/ex25.pp`

---

**Program** `ex21`;

*{ Program to demonstrate the TCollection.Foreach method }*

**Uses** `Objects, MyObject`; *{ For TMyObject definition and registration }*

**Var** `C : PCollection`;  
       `M : PMyObject`;  
       `I : Longint`;

**Function** `CheckField (Dummy: Pointer; P : PMyObject) : Longint`;

**begin**  
     **If** `P^.GetField < 56` **then**  
         `Checkfield := 1`  
     **else**  
         `CheckField := 0`;  
**end**;

**begin**  
     `C := New (PCollection, Init (100, 10));`  
     **For** `I := 1` **to** `100` **do**  
         **begin**  
             `M := New (PMyObject, Init);`  
             `M^.SetField (I);`  
             `C^.Insert (M);`  
         **end**;  
     **WriteLn** ( 'Inserted ', `C^.Count`, ' objects ' );  
     **WriteLn** ( 'Last one for which Field < 56 has index (should be 54) : ',  
                 `C^.IndexOf (C^.LastThat (@CheckField))` );  
     `C^.FreeAll`;  
     **Dispose** (`C`, `Done`);  
**end**.

---

### 29.5.10 TCollection.FirstThat

Synopsis: Return first item which matches a test.

Declaration: `function FirstThat (Test: Pointer) : Pointer`

Visibility: default

**Description:** This function returns the first item in the collection for which `Test` returns a non-nil result. `Test` is a function that accepts 1 argument: a pointer to an object, and that returns a pointer as a result.

**Errors:** None.

**See also:** `TCollection.LastThat` ([928](#))

**Listing:** `./objectex/ex26.pp`

---

**Program** `ex21`;

*{ Program to demonstrate the TCollection.FirstThat method }*

**Uses** `Objects, MyObject`; *{ For TMyObject definition and registration }*

**Var** `C` : `PCollection`;  
       `M` : `PMMyObject`;  
       `I` : `Longint`;

**Function** `CheckField` (`Dummy`: `Pointer`; `P` : `PMMyObject`) : `Longint`;

**begin**  
     **If** `P^.GetField > 56` **then**  
         `Checkfield := 1`  
     **else**  
         `CheckField := 0`;  
**end**;

**begin**  
     `C := New(PCollection, Init(100, 10));`  
     **For** `I := 1` **to** `100` **do**  
         **begin**  
             `M := New(PMyObject, Init);`  
             `M^.SetField(I);`  
             `C^.Insert(M);`  
         **end**;  
     **Writeln** ('Inserted ', `C^.Count`, ' objects');  
     **Writeln** ('first one for which Field > 56 has index (should be 56) : ',  
               `C^.IndexOf(C^.FirstThat(@CheckField))`);  
     `C^.FreeAll`;  
     **Dispose**(`C`, `Done`);  
**end**.

---

### 29.5.11 TCollection.Pack

**Synopsis:** Remove all `>Nil` pointers from the collection.

**Declaration:** `procedure Pack`

**Visibility:** `default`

**Description:** `Pack` removes all `Nil` pointers from the collection, and adjusts `Count` to reflect this change. No memory is freed as a result of this call. In order to free any memory, you can call `SetLimit` with an argument of `Count` after a call to `Pack`.

**Errors:** None.

**See also:** `TCollection.SetLimit` ([936](#))

**Listing:** ./objectex/ex26.pp

---

**Program** ex21;

*{ Program to demonstrate the TCollection.FirstThat method }*

**Uses** Objects, MyObject; *{ For TMyObject definition and registration }*

**Var** C : PCollection;  
       M : PMyObject;  
       I : Longint;

**Function** CheckField (Dummy: Pointer; P : PMyObject) : Longint;

**begin**

**If** P^.GetField > 56 **then**  
     Checkfield := 1

**else**  
     CheckField := 0;

**end**;

**begin**

  C := **New**(PCollection, Init(100, 10));

**For** I := 1 **to** 100 **do**

**begin**

      M := **New**(PMyObject, Init);

      M^.SetField(I);

      C^.Insert(M);

**end**;

**WriteLn** ('Inserted ', C^.Count, ' objects');

**WriteLn** ('first one for which Field > 56 has index (should be 56) : ',  
           C^.IndexOf(C^.FirstThat(@CheckField)));

  C^.FreeAll;

**Dispose**(C, Done);

**end**.

---

### 29.5.12 TCollection.FreeAll

**Synopsis:** Release all objects from the collection.

**Declaration:** procedure FreeAll

**Visibility:** default

**Description:** FreeAll calls the destructor of each object in the collection. It doesn't release any memory occupied by the collection itself, but it does set Count to zero.

**Errors:**

**See also:** TCollection.DeleteAll ([931](#)), TCollection.FreeItem ([934](#))

**Listing:** ./objectex/ex28.pp

---

**Program** ex28;

*{ Program to demonstrate the TCollection.FreeAll method }*

**Uses** Objects, MyObject; *{ For TMyObject definition and registration }*

```

Var C : PCollection;
      M : PMyObject;
      I : Longint;

begin
  Randomize;
  C:=New(PCollection, Init(120,10));
  For I:=1 to 100 do
    begin
      M:=New(PMyObject, Init);
      M^.SetField(I-1);
      C^.Insert(M);
    end;
  WriteLn ('Added 100 Items. ');
  C^.FreeAll;
  WriteLn ('Freed all objects. ');
  Dispose(C, Done);
end.

```

---

### 29.5.13 TCollection.DeleteAll

Synopsis: Delete all elements from the collection. Objects are not destroyed.

Declaration: `procedure DeleteAll`

Visibility: default

Description: `DeleteAll` deletes all elements from the collection. It just sets the `Count` variable to zero. Contrary to `FreeAll` (930), `DeleteAll` doesn't call the destructor of the objects.

Errors: None.

See also: `TCollection.FreeAll` (930), `TCollection.Delete` (933)

**Listing:** `./objectex/ex29.pp`

---

**Program** `ex29`;

```

{
  Program to demonstrate the TCollection.DeleteAll method
  Compare with example 28, where FreeAll is used.
}

```

**Uses** `Objects, MyObject; { For TMyObject definition and registration }`

```

Var C : PCollection;
      M : PMyObject;
      I : Longint;

begin
  Randomize;
  C:=New(PCollection, Init(120,10));
  For I:=1 to 100 do
    begin
      M:=New(PMyObject, Init);
      M^.SetField(I-1);
      C^.Insert(M);
    end;
  WriteLn ('Added 100 Items. ');
  C^.FreeAll;
  WriteLn ('Freed all objects. ');
  Dispose(C, Done);
end.

```

---

```

    end;
    Writeln ( 'Added 100 Items. ');
    C^.DeleteAll;
    Writeln ( 'Deleted all objects. ');
    Dispose(C,Done);
end.

```

---

### 29.5.14 TCollection.Free

Synopsis: Free item from collection, calling it's destructor.

Declaration: `procedure Free(Item: Pointer)`

Visibility: default

Description: `Free` Deletes `Item` from the collection, and calls the destructor `Done` of the object.

Errors: If the `Item` is not in the collection, `Error` will be called with `coIndexError`.

See also: `TCollection.FreeItem` ([934](#))

**Listing:** `./objectex/ex30.pp`

---

```

Program ex30;

{ Program to demonstrate the TCollection.Free method }

Uses Objects,MyObject; { For TMyObject definition and registration }

Var C : PCollection;
    M : PMyObject;
    I : Longint;

begin
    Randomize;
    C:=New(PCollection, Init(120,10));
    For I:=1 to 100 do
        begin
            M:=New(PMyObject, Init);
            M^.SetField(I-1);
            C^.Insert(M);
        end;
    Writeln ( 'Added 100 Items. ');
    With C^ do
        While Count>0 do Free(At(Count-1));
    Writeln ( 'Freed all objects. ');
    Dispose(C,Done);
end.

```

---

### 29.5.15 TCollection.Insert

Synopsis: Insert a new item in the collection at the end.

Declaration: `procedure Insert(Item: Pointer); Virtual`

Visibility: default

**Description:** `Insert` inserts `Item` in the collection. `TCollection` inserts this item at the end, but descendent objects may insert it at another place.

**Errors:** None.

**See also:** `TCollection.AtInsert` (937), `TCollection.AtPut` (937)

### 29.5.16 TCollection.Delete

**Synopsis:** Delete an item from the collection, but does not destroy it.

**Declaration:** `procedure Delete(Item: Pointer)`

**Visibility:** default

**Description:** `Delete` deletes `Item` from the collection. It doesn't call the item's destructor, though. For this the `Free` (932) call is provided.

**Errors:** If the `Item` is not in the collection, `Error` will be called with `coIndexError`.

**See also:** `TCollection.AtDelete` (934), `TCollection.Free` (932)

**Listing:** `./objectex/ex31.pp`

---

```

Program ex31;

{ Program to demonstrate the TCollection.Delete method }

Uses Objects, MyObject; { For TMyObject definition and registration }

Var C : PCollection;
    M : PMyObject;
    I : Longint;

begin
    Randomize;
    C:=New(PCollection, Init(120,10));
    For I:=1 to 100 do
        begin
            M:=New(PMyObject, Init);
            M^.SetField(I-1);
            C^.Insert(M);
        end;
    Writeln('Added 100 Items. ');
    With C^ do
        While Count>0 do Delete(At(Count-1));
    Writeln('Freed all objects ');
    Dispose(C, Done);
end.
```

---

### 29.5.17 TCollection.AtFree

**Synopsis:** Free an item at the indicates position, calling it's destructor.

**Declaration:** `procedure AtFree(Index: Sw_Integer)`

**Visibility:** default

**Description:** `AtFree` deletes the item at position `Index` in the collection, and calls the item's destructor if it is not `Nil`.

**Errors:** If `Index` isn't valid then `Error` (936) is called with `CoIndexError`.

**See also:** `TCollection.Free` (932), `TCollection.AtDelete` (934)

**Listing:** `./objectex/ex32.pp`

---

**Program** `ex32`;

*{ Program to demonstrate the TCollection.AtFree method }*

**Uses** `Objects, MyObject`; *{ For TMyObject definition and registration }*

**Var** `C` : `PCollection`;  
       `M` : `PMyObject`;  
       `I` : `Longint`;

**begin**  
     **Randomize**;  
     `C:=New`(`PCollection`, `Init`(120,10));  
     **For** `I:=1` **to** 100 **do**  
         **begin**  
             `M:=New`(`PMyObject`, `Init`);  
             `M^.SetField`(`I-1`);  
             `C^.Insert`(`M`);  
         **end**;  
     **WriteLn** ( 'Added 100 Items' );  
     **With** `C^` **do**  
         **While** `Count>0` **do** `AtFree`(`Count-1`);  
     **WriteLn** ( 'Freed all objects.' );  
     **Dispose**(`C`, `Done`);  
**end**.

---

### 29.5.18 TCollection.FreeItem

**Synopsis:** Destroy a non-nil item.

**Declaration:** `procedure FreeItem(Item: Pointer); Virtual`

**Visibility:** `default`

**Description:** `FreeItem` calls the destructor of `Item` if it is not nil.

**Remark:** This function is used internally by the `TCollection` object, and should not be called directly.

**Errors:** None.

**See also:** `TCollection.Free` (932), `TCollection.AtFree` (933)

### 29.5.19 TCollection.AtDelete

**Synopsis:** Delete item at certain position.

**Declaration:** `procedure AtDelete(Index: Sw_Integer)`

**Visibility:** `default`



**Description:** `AtDelete` deletes the pointer at position `Index` in the collection. It doesn't call the object's destructor.

**Errors:** If `Index` isn't valid then `Error` (936) is called with `CoIndexError`.

See also: `TCollection.Delete` (933)

**Listing:** `./objectex/ex33.pp`

---

**Program** `ex33`;

*{ Program to demonstrate the TCollection.AtDelete method }*

**Uses** `Objects, MyObject`; *{ For TMyObject definition and registration }*

**Var** `C` : `PCollection`;  
       `M` : `PMyObject`;  
       `I` : `Longint`;

**begin**  
     `Randomize`;  
     `C:=New( PCollection , Init(120,10));`  
     **For** `I:=1 to 100 do`  
       **begin**  
         `M:=New( PMyObject, Init );`  
         `M^.SetField( I-1 );`  
         `C^.Insert( M );`  
       **end**;  
     `WriteLn ( 'Added 100 Items. ' );`  
     **With** `C^ do`  
       **While** `Count>0 do AtDelete( Count-1 );`  
     `WriteLn ( 'Freed all objects. ' );`  
     `Dispose( C, Done );`  
**end.**

---

### 29.5.20 TCollection.ForEach

**Synopsis:** Execute procedure for each item in the list.

**Declaration:** `procedure ForEach( Action: Pointer )`

**Visibility:** `default`

**Description:** `ForEach` calls `Action` for each element in the collection, and passes the element as an argument to `Action`.

`Action` is a procedural type variable that accepts a pointer as an argument.

**Errors:** None.

See also: `TCollection.FirstThat` (928), `TCollection.LastThat` (928)

**Listing:** `./objectex/ex21.pp`

---

**Program** `ex21`;

*{ Program to demonstrate the TCollection.Foreach method }*

**Uses** `Objects, MyObject`; *{ For TMyObject definition and registration }*

---

```

Var C : PCollection;
      M : PMyObject;
      I : Longint;

Procedure PrintField (Dummy: Pointer;P : PMyObject);

begin
  WriteLn ( 'Field : ',P^.GetField);
end;

begin
  C:=New( PCollection , Init(100,10));
  For I:=1 to 100 do
    begin
      M:=New(PMyObject, Init);
      M^.SetField(100-I);
      C^.Insert(M);
    end;
  WriteLn ( 'Inserted ',C^.Count,' objects ');
  C^.ForEach( @PrintField );
  C^.FreeAll;
  Dispose(C,Done);
end.

```

---

### 29.5.21 TCollection.SetLimit

Synopsis: Set maximum number of elements in the collection.

Declaration: `procedure SetLimit(ALimit: Sw_Integer); Virtual`

Visibility: default

Description: `SetLimit` sets the maximum number of elements in the collection. `ALimit` must not be less than `Count`, and should not be larger than `MaxCollectionSize`

For an example, see [Pack \(929\)](#).

Errors: None.

See also: `TCollection.Init` ([924](#))

### 29.5.22 TCollection.Error

Synopsis: Set error code.

Declaration: `procedure Error(Code: Integer;Info: Integer); Virtual`

Visibility: default

Description: `Error` is called by the various `TCollection` methods in case of an error condition. The default behaviour is to make a call to `RunError` with an error of `212-Code`.

This method can be overridden by descendent objects to implement a different error-handling.

Errors:

See also: `Abstract` ([913](#))

### 29.5.23 TCollection.AtPut

Synopsis: Set collection item, overwriting an existing value.

Declaration: `procedure AtPut (Index: Sw_Integer; Item: Pointer)`

Visibility: default

Description: `AtPut` sets the element at position `Index` in the collection to `Item`. Any previous value is overwritten.

For an example, see `Pack` (929).

Errors: If `Index` isn't valid then `Error` (936) is called with `CoIndexError`.

### 29.5.24 TCollection.AtInsert

Synopsis: Insert an element at a certain position in the collection.

Declaration: `procedure AtInsert (Index: Sw_Integer; Item: Pointer)`

Visibility: default

Description: `AtInsert` inserts `Item` in the collection at position `Index`, shifting all elements by one position. In case the current limit is reached, the collection will try to expand with a call to `SetLimit`

Errors: If `Index` isn't valid then `Error` (936) is called with `CoIndexError`. If the collection fails to expand, then `coOverflow` is passed to `Error`.

See also: `TCollection.Insert` (932)

**Listing:** `./objectex/ex34.pp`

---

**Program** `ex34`;

*{ Program to demonstrate the TCollection.AtInsert method }*

**Uses** `Objects, MyObject`; *{ For TMyObject definition and registration }*

**Var** `C` : `PCollection`;  
       `M` : `PMMyObject`;  
       `I` : `Longint`;

**Procedure** `PrintField` (`Dummy`: `Pointer`; `P` : `PMMyObject`);

**begin**  
     `WriteLn` ( 'Field : ', `P`^.`GetField` );  
**end**;

**begin**  
     `Randomize`;  
     `C`:=`New`(`PCollection`, `Init`(120,10));  
     `WriteLn` ( 'Inserting 100 records at random places.' );  
     **For** `I`:=1 **to** 100 **do**  
         **begin**  
             `M`:=`New`(`PMMyObject`, `Init` );  
             `M`^.`SetField`(`I`-1);  
             **If** `I`=1 **then**  
                 `C`^.`Insert`(`M`)

```

    else
      With C^ do
        AtInsert(Random(Count),M);
      end;
      WriteLn ('Values : ');
      C^.Foreach(@PrintField);
      Dispose(C,Done);
    end.

```

---

### 29.5.25 TCollection.Store

Synopsis: Write collection to a stream.

Declaration: `procedure Store(var S: TStream)`

Visibility: default

Description: `Store` writes the collection to the stream `S`. It does this by writeing the current `Count`, `Limit` and `Delta` to the stream, and then writing each item to the stream.

The contents of the stream are then suitable for instantiating another collection with `Load` ([925](#)).

For an example, see `TCollection.Load` ([925](#)).

Errors: Errors returned are those by `TStream.Put` ([970](#)).

See also: `TCollection.Load` ([925](#)), `TCollection.PutItem` ([938](#))

### 29.5.26 TCollection.PutItem

Synopsis: Put one item on the stream

Declaration: `procedure PutItem(var S: TStream; Item: Pointer); Virtual`

Visibility: default

Description: `PutItem` writes `Item` to stream `S`. This method is used internaly by the `TCollection` object, and should not be called directly.

Errors: Errors are those returned by `TStream.Put` ([970](#)).

See also: `TCollection.Store` ([938](#)), `TCollection.GetItem` ([927](#))

## 29.6 TDosStream

### 29.6.1 Description

`TDosStream` is a stream that stores it's contents in a file. it overrides a couple of methods of `TStream` ([965](#)) for this.

In addition to the fields inherited from `TStream` (see `TStream` ([965](#))), there are some extra fields, that describe the file. (mainly the name and the OS file handle)

No buffering in memory is done when using `TDosStream`. All data are written directly to the file. For a stream that buffers in memory, see `TBufStream` ([920](#)).

### 29.6.2 Method overview

Page	Property	Description
<a href="#">940</a>	Close	Close the file.
<a href="#">939</a>	Done	Closes the file and cleans up the instance.
<a href="#">939</a>	Init	Instantiate a new instance of TDosStream.
<a href="#">942</a>	Open	Open the file stream
<a href="#">942</a>	Read	Read data from the stream to a buffer.
<a href="#">941</a>	Seek	Set file position.
<a href="#">940</a>	Truncate	Truncate the file on the current position.
<a href="#">943</a>	Write	Write data from a buffer to the stream.

### 29.6.3 TDosStream.Init

Synopsis: Instantiate a new instance of TDosStream.

Declaration: `constructor Init (FileName: FNameStr; Mode: Word)`

Visibility: default

Description: `Init` instantiates an instance of `TDosStream`. The name of the file that contains (or will contain) the data of the stream is given in `FileName`. The `Mode` parameter determines whether a new file should be created and what access rights you have on the file. It can be one of the following constants:

**stCreate** Creates a new file.

**stOpenRead** Read access only.

**stOpenWrite** Write access only.

**stOpenRead** and write access.

For an example, see `TDosStream.Truncate` ([940](#)).

Errors: On error, `Status` (??) is set to `stInitError`, and `ErrorInfo` is set to the dos error code.

See also: `TDosStream.Done` ([939](#))

### 29.6.4 TDosStream.Done

Synopsis: Closes the file and cleans up the instance.

Declaration: `destructor Done; Virtual`

Visibility: default

Description: `Done` closes the file if it was open and cleans up the instance of `TDosStream`.  
for an example, see e.g. `TDosStream.Truncate` ([940](#)).

Errors: None.

See also: `TDosStream.Init` ([939](#)), `TDosStream.Close` ([940](#))

### 29.6.5 TDosStream.Close

Synopsis: Close the file.

Declaration: `procedure Close; Virtual`

Visibility: `default`

Description: `Close` closes the file if it was open, and sets `Handle` to -1. Contrary to `Done` (939) it does not clean up the instance of `TDosStream`

For an example, see `TDosStream.Open` (942).

Errors: None.

See also: `TStream.Close` (969), `TDosStream.Init` (939), `TDosStream.Done` (939)

### 29.6.6 TDosStream.Truncate

Synopsis: Truncate the file on the current position.

Declaration: `procedure Truncate; Virtual`

Visibility: `default`

Description: If the status of the stream is `stOK`, then `Truncate` tries to truncate the stream size to the current file position.

Errors: If an error occurs, the stream's status is set to `stError` and `ErrorInfo` is set to the OS error code.

See also: `TStream.Truncate` (970), `TStream.GetSize` (967)

**Listing:** `./objectex/ex16.pp`

---

**Program** `ex16;`

*{ Program to demonstrate the TStream.Truncate method }*

**Uses** `Objects;`

**Var** `L : String;`  
       `P : PString;`  
       `S : PDosStream; { Only one with Truncate implemented. }`

**begin**

```

  L:= 'Some constant string';
  { Buffer size of 100 }
  S:=New(PDosStream, Init('test.dat', stcreate));
  Writeln ('Writing "', L, '" to stream with handle ', S^.Handle);
  S^.WriteStr(@L);
  S^.WriteStr(@L);
  { Close calls flush first }
  S^.Close;
  S^.Open (stOpen);
  Writeln ('Size of stream is : ', S^.GetSize);
  P:=S^.ReadStr;
  L:=P^;
  DisposeStr(P);
  Writeln ('Read "', L, '" from stream with handle ', S^.Handle);

```

---

```

S^.Truncate;
Writeln ( 'Truncated stream. Size is : ',S^.GetSize);
S^.Close;
Dispose (S,Done);
end.

```

---

### 29.6.7 TDosStream.Seek

Synopsis: Set file position.

Declaration: `procedure Seek(Pos: LongInt); Virtual`

Visibility: default

Description: If the stream's status is `stOK`, then `Seek` sets the file position to `Pos`. `Pos` is a zero-based offset, counted from the beginning of the file.

Errors: In case an error occurs, the stream's status is set to `stSeekError`, and the OS error code is stored in `ErrorInfo`.

See also: `TStream.Seek` ([971](#)), `TStream.GetPos` ([967](#))

**Listing:** `./objectex/ex17.pp`

---

**Program** `ex17;`

*{ Program to demonstrate the TStream.Seek method }*

**Uses** `Objects;`

**Var** `L : String;`  
       `Marker : Word;`  
       `P : PString;`  
       `S : PDosStream;`

**begin**

```

L:= 'Some constant string';
{ Buffer size of 100 }
S:=New(PDosStream, Init( 'test.dat', stcreate));
Writeln ( 'Writing "',L, '" to stream. ');
S^.WriteStr(@L);
Marker:=S^.GetPos;
Writeln ( 'Set marker at ',Marker);
L:= 'Some other constant String';
Writeln ( 'Writing "',L, '" to stream. ');
S^.WriteStr(@L);
S^.Close;
S^.Open (stOpenRead);
Writeln ( 'Size of stream is : ',S^.GetSize);
Writeln ( 'Seeking to marker');
S^.Seek(Marker);
P:=S^.ReadStr;
L:=P^;
DisposeStr(P);
Writeln ( 'Read "',L, '" from stream. ');
S^.Close;
Dispose (S,Done);
end.

```

---

### 29.6.8 TDosStream.Open

Synopsis: Open the file stream

Declaration: `procedure Open (OpenMode: Word); Virtual`

Visibility: default

Description: If the stream's status is `stOK`, and the stream is closed then `Open` re-opens the file stream with mode `OpenMode`. This call can be used after a `Close` (940) call.

Errors: If an error occurs when re-opening the file, then `Status` is set to `stOpenError`, and the OS error code is stored in `ErrorInfo`

See also: `TStream.Open` (969), `TDosStream.Close` (940)

**Listing:** `./objectex/ex14.pp`

---

**Program** `ex14;`

*{ Program to demonstrate the TStream.Close method }*

**Uses** `Objects;`

**Var** `L : String;`  
       `P : PString;`  
       `S : PDosStream; { Only one with Close implemented. }`

**begin**

```

L:= 'Some constant string';
S:=New(PDosStream, Init('test.dat', stcreate));
WriteLn ('Writing "', L, '" to stream with handle ', S^.Handle);
S^.WriteStr(@L);
S^.Close;
WriteLn ('Closed stream. File handle is ', S^.Handle);
S^.Open (stOpenRead);
P:=S^.ReadStr;
L:=P^;
DisposeStr(P);
WriteLn ('Read "', L, '" from stream with handle ', S^.Handle);
S^.Close;
Dispose (S, Done);

```

**end.**

---

### 29.6.9 TDosStream.Read

Synopsis: Read data from the stream to a buffer.

Declaration: `procedure Read (var Buf; Count: LongInt); Virtual`

Visibility: default

Description: If the Stream is open and the stream status is `stOK` then `Read` will read `Count` bytes from the stream and place them in `Buf`.

For an example, see `TStream.Read` (972).

Errors: In case of an error, `Status` is set to `StReadError`, and `ErrorInfo` gets the OS specific error, or 0 when an attempt was made to read beyond the end of the stream.

See also: `TStream.Read` (972), `TDosStream.Write` (943)



### 29.6.10 TDosStream.Write

Synopsis: Write data from a buffer to the stream.

Declaration: `procedure Write(var Buf; Count: LongInt); Virtual`

Visibility: default

Description: If the Stream is open and the stream status is `stOK` then `Write` will write `Count` bytes from `Buf` and place them in the stream.

For an example, see `TStream.Read` (972).

Errors: In case of an error, `Status` is set to `StWriteError`, and `ErrorInfo` gets the OS specific error.

See also: `TStream.Write` (972), `TDosStream.Read` (942)

## 29.7 TMemoryStream

### 29.7.1 Description

The `TMemoryStream` object implements a stream that stores its data in memory. The data is stored on the heap, with the possibility to specify the maximum amount of data, and the size of the memory blocks being used.

### 29.7.2 Method overview

Page	Property	Description
<a href="#">944</a>	<code>Done</code>	Clean up memory and destroy the object instance.
<a href="#">943</a>	<code>Init</code>	Initialize memory stream, reserves memory for stream data.
<a href="#">945</a>	<code>Read</code>	Read data from the stream to a location in memory.
<a href="#">944</a>	<code>Truncate</code>	Set the stream size to the current position.
<a href="#">945</a>	<code>Write</code>	Write data to the stream.

### 29.7.3 TMemoryStream.Init

Synopsis: Initialize memory stream, reserves memory for stream data.

Declaration: `constructor Init(ALimit: LongInt; ABlockSize: Word)`

Visibility: default

Description: `Init` instantiates a new `TMemoryStream` object. The `memorystreamobject` will initially allocate at least `ALimit` bytes memory, divided into memory blocks of size `ABlockSize`. The number of blocks needed to get to `ALimit` bytes is rounded up.

By default, the number of blocks is 1, and the size of a block is 8192. This is selected if you specify 0 as the blocksize.

For an example, see e.g. `TStream.CopyFrom` (973).

Errors: If the stream cannot allocate the initial memory needed for the memory blocks, then the stream's status is set to `stInitError`.

See also: `TMemoryStream.Done` (944)

### 29.7.4 TMemoryStream.Done

Synopsis: Clean up memory and destroy the object instance.

Declaration: `destructor Done; Virtual`

Visibility: `default`

Description: `Done` releases the memory blocks used by the stream, and then cleans up the memory used by the stream object itself.

For an example, see e.g `TStream.CopyFrom` ([973](#)).

Errors: `None`.

See also: `TMemoryStream.Init` ([943](#))

### 29.7.5 TMemoryStream.Truncate

Synopsis: Set the stream size to the current position.

Declaration: `procedure Truncate; Virtual`

Visibility: `default`

Description: `Truncate` sets the size of the memory stream equal to the current position. It de-allocates any memory-blocks that are no longer needed, so that the new size of the stream is the current position in the stream, rounded up to the first multiple of the stream blocksize.

Errors: If an error occurs during memory de-allocation, the stream's status is set to `stError`

See also: `TStream.Truncate` ([970](#))

**Listing:** `./objectex/ex20.pp`

---

**Program** `ex20;`

*{ Program to demonstrate the TMemoryStream.Truncate method }*

**Uses** `Objects;`

**Var** `L : String;`  
`P : PString;`  
`S : PMemoryStream;`  
`I : Longint;`

**begin**

```

L:= 'Some constant string';
{ Buffer size of 100 }
S:=New(PMemoryStream, Init(1000,100));
Writeln ( 'Writing 100 times "',L,'" to stream.' );
For I:=1 to 100 do
  S^. WriteStr(@L);
Writeln ( 'Finished.' );
S^.Seek(100);
S^.Truncate;
Writeln ( 'Truncated at byte 100.' );
Dispose (S,Done);
Writeln ( 'Finished.' );

```

**end.**

---

### 29.7.6 TMemoryStream.Read

Synopsis: Read data from the stream to a location in memory.

Declaration: `procedure Read(var Buf; Count: LongInt); Virtual`

Visibility: default

Description: Read reads Count bytes from the stream to Buf. It updates the position of the stream.

For an example, see TStream.Read (972).

Errors: If there is not enough data available, no data is read, and the stream's status is set to `stReadError`.

See also: TStream.Read (972), TMemoryStream.Write (945)

### 29.7.7 TMemoryStream.Write

Synopsis: Write data to the stream.

Declaration: `procedure Write(var Buf; Count: LongInt); Virtual`

Visibility: default

Description: Write copies Count bytes from Buf to the stream. It updates the position of the stream.

If not enough memory is available to hold the extra Count bytes, then the stream will try to expand, by allocating as much blocks with size `BlkSize` (as specified in the constructor call `Init` (943)) as needed.

For an example, see TStream.Read (972).

Errors: If the stream cannot allocate more memory, then the status is set to `stWriteError`

See also: TStream.Write (972), TMemoryStream.Read (945)

## 29.8 TObject

### 29.8.1 Description

This type serves as the basic object for all other objects in the Objects unit.

### 29.8.2 Method overview

Page	Property	Description
<a href="#">947</a>	Done	Destroy an object.
<a href="#">946</a>	Free	Destroy an object and release all memory.
<a href="#">945</a>	Init	Construct (initialize) a new object
<a href="#">946</a>	Is\_Object	Check whether a pointer points to an object.

### 29.8.3 TObject.Init

Synopsis: Construct (initialize) a new object

Declaration: `constructor Init`

Visibility: default

Description: Instantiates a new object of type `TObject`. It fills the instance up with Zero bytes.

For an example, see [Free \(946\)](#)

Errors: None.

See also: [TObject.Free \(946\)](#), [TObject.Done \(947\)](#)

### 29.8.4 TObject.Free

Synopsis: Destroy an object and release all memory.

Declaration: `procedure Free`

Visibility: default

Description: `Free` calls the destructor of the object, and releases the memory occupied by the instance of the object.

Errors: No checking is performed to see whether `self` is `nil` and whether the object is indeed allocated on the heap.

See also: [TObject.Init \(945\)](#), [TObject.Done \(947\)](#)

**Listing:** `./objectex/ex7.pp`

---

```

program ex7;

  { Program to demonstrate the TObject.Free call }

Uses Objects;

Var O : TObject;

begin
  // Allocate memory for object.
  O:=New(TObject, Init);
  // Free memory of object.
  O^.free;
end.
```

---

### 29.8.5 TObject.Is\_Object

Synopsis: Check whether a pointer points to an object.

Declaration: `function Is_Object(P: Pointer) : Boolean`

Visibility: default

Description: `Is_Object` returns `True` if the pointer `P` points to an instance of a `TObject` descendent, it returns `false` otherwise.

### 29.8.6 TObject.Done

Synopsis: Destroy an object.

Declaration: `destructor Done; Virtual`

Visibility: `default`

Description: `Done`, the destructor of `TObject` does nothing. It is mainly intended to be used in the `TObject.Free` (946) method.

The destructore `Done` does not free the memory occupied by the object.

Errors: None.

See also: `TObject.Free` (946), `TObject.Init` (945)

**Listing:** `./objectex/ex8.pp`

---

```

program ex8;

  { Program to demonstrate the TObject.Done call }

Uses Objects;

Var O : PObject;

begin
  // Allocate memory for object.
  O:=New(PObject, Init);
  O^.Done;
end.

```

---

## 29.9 TPoint

### 29.9.1 Description

Record describing a point in a 2 dimensional plane.

## 29.10 TRect

### 29.10.1 Description

Describes a rectangular region in a plane.

### 29.10.2 Method overview

Page	Property	Description
952	Assign	Set rectangle corners.
949	Contains	Determine if a point is inside the rectangle
949	Copy	Copy cornerpoints from another rectangle.
948	Empty	Is the surface of the rectangle zero
949	Equals	Do the corners of the rectangles match
952	Grow	Expand rectangle with certain size.
950	Intersect	Reduce rectangle to intersection with another rectangle
951	Move	Move rectangle along a vector.
950	Union	Enlarges rectangle to encompass another rectangle.

---

### 29.10.3 TRect.Empty

Synopsis: Is the surface of the rectangle zero

Declaration: `function Empty : Boolean`

Visibility: default

Description: `Empty` returns `True` if the rectangle defined by the corner points A, B has zero or negative surface.

Errors: None.

See also: `TRect.Equals` ([949](#)), `TRect.Contains` ([949](#))

**Listing:** `./objectex/ex1.pp`

---

**Program** `ex1`;

*{ Program to demonstrate TRect.Empty }*

**Uses** `objects`;

**Var** `ARect,BRect : TRect`;  
       `P : TPoint`;

**begin**

**With** `ARect.A` **do**

**begin**

`X:=10`;

`Y:=10`;

**end**;

**With** `ARect.B` **do**

**begin**

`X:=20`;

`Y:=20`;

**end**;

*{ Offset B by (5,5) }*

**With** `BRect.A` **do**

**begin**

`X:=15`;

`Y:=15`;

**end**;

**With** `BRect.B` **do**

**begin**

`X:=25`;

`Y:=25`;

**end**;

*{ Point }*

**With** `P` **do**

**begin**

`X:=15`;

`Y:=15`;

**end**;

**Writeln** ( 'A empty : ',`ARect.Empty`);

**Writeln** ( 'B empty : ',`BRect.Empty`);

**Writeln** ( 'A Equals B : ',`ARect.Equals(BRect)`);

**Writeln** ( 'A Contains (15,15) : ',`ARect.Contains(P)`);

**end.**

---

### 29.10.4 TRect.Equals

Synopsis: Do the corners of the rectangles match

Declaration: `function Equals(R: TRect) : Boolean`

Visibility: default

Description: `Equals` returns `True` if the rectangle has the same corner points A, B as the rectangle R, and `False` otherwise.

For an example, see `TRect.Empty` (948)

Errors: None.

See also: `TRect.Empty` (948), `TRect.Contains` (949)

### 29.10.5 TRect.Contains

Synopsis: Determine if a point is inside the rectangle

Declaration: `function Contains(P: TPoint) : Boolean`

Visibility: default

Description: `Contains` returns `True` if the point P is contained in the rectangle (including borders), `False` otherwise.

Errors: None.

See also: `TRect.Intersect` (950), `TRect.Equals` (949)

### 29.10.6 TRect.Copy

Synopsis: Copy cornerpoints from another rectangle.

Declaration: `procedure Copy(R: TRect)`

Visibility: default

Description: Assigns the rectangle R to the object. After the call to `Copy`, the rectangle R has been copied to the object that invoked `Copy`.

Errors: None.

See also: `TRect.Assign` (952)

**Listing:** `./objectex/ex2.pp`

---

**Program** `ex2`;

*{ Program to demonstrate TRect.Copy }*

**Uses** `objects`;

**Var** `ARect, BRect, CRect : TRect`;

**begin**

`ARect.Assign(10,10,20,20);`

`BRect.Assign(15,15,25,25);`

---

```

CRect.Copy(ARect);
If ARect.Equals(CRect) Then
  Writeln ( 'ARect equals CRect')
Else
  Writeln ( 'ARect does not equal CRect !');
end.

```

---

### 29.10.7 TRect.Union

Synopsis: Enlarges rectangle to encompass another rectangle.

Declaration: `procedure Union(R: TRect)`

Visibility: default

Description: `Union` enlarges the current rectangle so that it becomes the union of the current rectangle with the rectangle `R`.

Errors: None.

See also: `TRect.Intersect` ([950](#))

**Listing:** `./objectex/ex3.pp`

---

**Program** `ex3`;

*{ Program to demonstrate TRect.Union }*

**Uses** `objects`;

**Var** `ARect, BRect, CRect : TRect`;

**begin**

```

  ARect.Assign(10,10,20,20);
  BRect.Assign(15,15,25,25);
  { CRect is union of ARect and BRect }

```

```

  CRect.Assign(10,10,25,25);
  { Calculate it explicitly }

```

```

  ARect.Union(BRect);

```

```

  If ARect.Equals(CRect) Then
    Writeln ( 'ARect equals CRect')

```

```

  Else
    Writeln ( 'ARect does not equal CRect !');

```

```

end.

```

---

### 29.10.8 TRect.Intersect

Synopsis: Reduce rectangle to intersection with another rectangle

Declaration: `procedure Intersect(R: TRect)`

Visibility: default

Description: `Intersect` makes the intersection of the current rectangle with `R`. If the intersection is empty, then the rectangle is set to the empty rectangle at coordinate (0,0).



Errors: None.

See also: [TRect.Union \(950\)](#)

**Listing:** ./objectex/ex4.pp

---

```

Program ex4;

{ Program to demonstrate TRect.Intersect }

Uses objects;

Var ARect, BRect, CRect : TRect;

begin
  ARect.Assign(10,10,20,20);
  BRect.Assign(15,15,25,25);
  { CRect is intersection of ARect and BRect }
  CRect.Assign(15,15,20,20);
  { Calculate it explicitly }
  ARect.Intersect(BRect);
  If ARect.Equals(CRect) Then
    Writeln ( 'ARect equals CRect' )
  Else
    Writeln ( 'ARect does not equal CRect !' );
  BRect.Assign(25,25,30,30);
  ARect.Intersect(BRect);
  If ARect.Empty Then
    Writeln ( 'ARect is empty' );
end.

```

---

### 29.10.9 TRect.Move

Synopsis: Move rectangle along a vector.

Declaration: `procedure Move(ADX: Sw_Integer; ADY: Sw_Integer)`

Visibility: default

Description: `Move` moves the current rectangle along a vector with components (ADX, ADY). It adds ADX to the X-coordinate of both corner points, and ADY to both end points.

Errors: None.

See also: [TRect.Grow \(952\)](#)

**Listing:** ./objectex/ex5.pp

---

```

Program ex5;

{ Program to demonstrate TRect.Move }

Uses objects;

Var ARect, BRect : TRect;

```

---

```

begin
  ARect.Assign(10,10,20,20);
  ARect.Move(5,5);
  // Brect should be where new ARect is.
  BRect.Assign(15,15,25,25);
  If ARect.Equals(BRect) Then
    Writeln ( 'ARect equals BRect' )
  Else
    Writeln ( 'ARect does not equal BRect !' );
end.

```

---

### 29.10.10 TRect.Grow

Synopsis: Expand rectangle with certain size.

Declaration: `procedure Grow(ADX: Sw_Integer;ADY: Sw_Integer)`

Visibility: default

Description: `Grow` expands the rectangle with an amount `ADX` in the `X` direction (both on the left and right side of the rectangle, thus adding a length `2*ADX` to the width of the rectangle), and an amount `ADY` in the `Y` direction (both on the top and the bottom side of the rectangle, adding a length `2*ADY` to the height of the rectangle).

`ADX` and `ADY` can be negative. If the resulting rectangle is empty, it is set to the empty rectangle at `(0,0)`.

Errors: None.

See also: `TRect.Move` ([951](#))

**Listing:** `./objectex/ex6.pp`

---

```

Program ex6;

{ Program to demonstrate TRect.Grow }

Uses objects;

Var ARect,BRect : TRect;

begin
  ARect.Assign(10,10,20,20);
  ARect.Grow(5,5);
  // Brect should be where new ARect is.
  BRect.Assign(5,5,25,25);
  If ARect.Equals(BRect) Then
    Writeln ( 'ARect equals BRect' )
  Else
    Writeln ( 'ARect does not equal BRect !' );
end.

```

---

### 29.10.11 TRect.Assign

Synopsis: Set rectangle corners.

**Declaration:** `procedure Assign(XA: Sw_Integer;YA: Sw_Integer;XB: Sw_Integer;  
YB: Sw_Integer)`

**Visibility:** default

**Description:** `Assign` sets the corner points of the rectangle to `(XA, YA)` and `(Xb, Yb)`.

For an example, see `TRect.Copy` (949).

**Errors:** None.

See also: `TRect.Copy` (949)

## 29.11 TResourceCollection

### 29.11.1 Description

A `TResourceCollection` manages a collection of resource names. It stores the position and the size of a resource, as well as the name of the resource. It stores these items in records that look like this:

```
TYPE
  TResourceItem = packed RECORD
    Posn: LongInt;
    Size: LongInt;
    Key : String;
  End;
  PResourceItem = ^TResourceItem;
```

It overrides some methods of `TStringCollection` in order to accomplish this.

**Remark:** Remark that the `TResourceCollection` manages the names of the resources and their associated positions and sizes, it doesn't manage the resources themselves.

### 29.11.2 Method overview

Page	Property	Description
<a href="#">954</a>	<code>FreeItem</code>	Release memory occupied by item.
<a href="#">954</a>	<code>GetItem</code>	Read an item from the stream.
<a href="#">953</a>	<code>KeyOf</code>	Return the key of an item in the collection.
<a href="#">954</a>	<code>PutItem</code>	Write an item to the stream.

### 29.11.3 TResourceCollection.KeyOf

**Synopsis:** Return the key of an item in the collection.

**Declaration:** `function KeyOf(Item: Pointer) : Pointer; Virtual`

**Visibility:** default

**Description:** `KeyOf` returns the key of an item in the collection. For resources, the key is a pointer to the string with the resource name.

**Errors:** None.

See also: `TStringCollection.Compare` (974)

### 29.11.4 TResourceCollection.GetItem

Synopsis: Read an item from the stream.

Declaration: `function GetItem(var S: TStream) : Pointer; Virtual`

Visibility: default

Description: `GetItem` reads a resource item from the stream `S`. It reads the position, size and name from the stream, in that order. It DOES NOT read the resource itself from the stream.

The resulting item is not inserted in the collection. This call is mainly for internal use by the `TCollection.Load` (925) method.

Errors: Errors returned are those by `TStream.Read` (972)

See also: `TCollection.Load` (925), `TStream.Read` (972)

### 29.11.5 TResourceCollection.FreeItem

Synopsis: Release memory occupied by item.

Declaration: `procedure FreeItem(Item: Pointer); Virtual`

Visibility: default

Description: `FreeItem` releases the memory occupied by `Item`. It de-allocates the name, and then the resource item record.

It does NOT remove the item from the collection.

Errors: None.

See also: `TCollection.FreeItem` (934)

### 29.11.6 TResourceCollection.PutItem

Synopsis: Write an item to the stream.

Declaration: `procedure PutItem(var S: TStream; Item: Pointer); Virtual`

Visibility: default

Description: `PutItem` writes `Item` to the stream `S`. It does this by writing the position and size and name of the resource item to the stream.

This method is used primarily by the `Store` (938) method.

Errors: Errors returned are those by `TStream.Write` (972).

See also: `TCollection.Store` (938)

## 29.12 TResourceFile

### 29.12.1 Description

`TResourceFile` (954) represents the resources in a binary file image.

**29.12.2 Method overview**

Page	Property	Description
<a href="#">955</a>	Count	Number of resources in the file
<a href="#">957</a>	Delete	Delete a resource from the file
<a href="#">955</a>	Done	Destroy the instance and remove it from memory.
<a href="#">956</a>	Flush	Writes the resources to the stream.
<a href="#">956</a>	Get	Return a resource by key name.
<a href="#">955</a>	Init	Instantiate a new instance.
<a href="#">956</a>	KeyAt	Return the key of the item at a certain position.
<a href="#">957</a>	Put	Set a resource by key name.
<a href="#">956</a>	SwitchTo	Write resources to a new stream.

**29.12.3 TResourceFile.Init**

Synopsis: Instantiate a new instance.

Declaration: `constructor Init (AStream: PStream)`

Visibility: default

Description: `Init` instantiates a new instance of a `TResourceFile` object. If `AStream` is not nil then it is considered as a stream describing an executable image on disk.

`Init` will try to position the stream on the start of the resources section, and read all resources from the stream.

Errors: None.

See also: `TResourceFile.Done` ([955](#))

**29.12.4 TResourceFile.Done**

Synopsis: Destroy the instance and remove it from memory.

Declaration: `destructor Done; Virtual`

Visibility: default

Description: `Done` cleans up the instance of the `TResourceFile` Object. If `Stream` was specified at initialization, then `Stream` is disposed of too.

Errors: None.

See also: `TResourceFile.Init` ([955](#))

**29.12.5 TResourceFile.Count**

Synopsis: Number of resources in the file

Declaration: `function Count : Sw_Integer`

Visibility: default

Description: `Count` returns the number of resources. If no resources were read, zero is returned.

Errors: None.

See also: `TResourceFile.Init` ([955](#))

### 29.12.6 TResourceFile.KeyAt

Synopsis: Return the key of the item at a certain position.

Declaration: `function KeyAt (I: Sw_Integer) : String`

Visibility: default

Description: `KeyAt` returns the key (the name) of the `I`-th resource.

Errors: In case `I` is invalid, `TCollection.Error` will be executed.

See also: `TResourceFile.Get` (956)

### 29.12.7 TResourceFile.Get

Synopsis: Return a resource by key name.

Declaration: `function Get (Key: String) : PObject`

Visibility: default

Description: `Get` returns a pointer to a instance of a resource identified by `Key`. If `Key` cannot be found in the list of resources, then `Nil` is returned.

Errors: Errors returned may be those by `TStream.Get`

### 29.12.8 TResourceFile.SwitchTo

Synopsis: Write resources to a new stream.

Declaration: `function SwitchTo (AStream: PStream; Pack: Boolean) : PStream`

Visibility: default

Description: `SwitchTo` switches to a new stream to hold the resources in. `AStream` will be the new stream after the call to `SwitchTo`.

If `Pack` is true, then all the known resources will be copied from the current stream to the new stream (`AStream`). If `Pack` is False, then only the current resource is copied.

The return value is the value of the original stream: `Stream`.

The `Modified` flag is set as a consequence of this call.

Errors: Errors returned can be those of `TStream.Read` (972) and `TStream.Write` (972).

See also: `TResourceFile.Flush` (956)

### 29.12.9 TResourceFile.Flush

Synopsis: Writes the resources to the stream.

Declaration: `procedure Flush`

Visibility: default

Description: If the `Modified` flag is set to `True`, then `Flush` writes the resources to the stream `Stream`. It sets the `Modified` flag to true after that.

Errors: Errors can be those by `TStream.Seek` (971) and `TStream.Write` (972).

See also: `TResourceFile.SwitchTo` (956)

### 29.12.10 TResourceFile.Delete

Synopsis: Delete a resource from the file

Declaration: `procedure Delete(Key: String)`

Visibility: default

Description: `Delete` deletes the resource identified by `Key` from the collection. It sets the `Modified` flag to `true`.

Errors: None.

See also: `TResourceFile.Flush` ([956](#))

### 29.12.11 TResourceFile.Put

Synopsis: Set a resource by key name.

Declaration: `procedure Put(Item: PObject; Key: String)`

Visibility: default

Description: `Put` sets the resource identified by `Key` to `Item`. If no such resource exists, a new one is created. The item is written to the stream.

Errors: Errors returned may be those by `TStream.Put` ([970](#)) and `TStream.Seek`

See also: `TResourceFile.Get` ([956](#))

## 29.13 TSortedCollection

### 29.13.1 Description

`TSortedCollection` is an abstract class, implementing a sorted collection. You should never use an instance of `TSortedCollection` directly, instead you should declare a descendent type, and override the `Compare` ([959](#)) method.

Because the collection is ordered, `TSortedCollection` overrides some `TCollection` methods, to provide faster routines for lookup.

The `Compare` ([959](#)) method decides how elements in the collection should be ordered. Since `TCollection` has no way of knowing how to order pointers, you must override the compare method.

Additionally, `TCollection` provides a means to filter out duplicates. if you set `Duplicates` to `False` (the default) then duplicates will not be allowed.

The example below defines a descendent of `TSortedCollection` which is used in the examples.

### 29.13.2 Method overview

Page	Property	Description
<a href="#">959</a>	Compare	Compare two items in the collection.
<a href="#">959</a>	IndexOf	Return index of an item in the collection.
<a href="#">958</a>	Init	Instantiates a new instance of a <code>TSortedCollection</code>
<a href="#">961</a>	Insert	Insert new item in collection.
<a href="#">958</a>	KeyOf	Return the key of an item
<a href="#">958</a>	Load	Instantiates a new instance of a <code>TSortedCollection</code> and loads it from stream.
<a href="#">960</a>	Search	Search for item with given key.
<a href="#">962</a>	Store	Write the collection to the stream.

### 29.13.3 `TSortedCollection.Init`

Synopsis: Instantiates a new instance of a `TSortedCollection`

Declaration: `constructor Init (ALimit: Sw_Integer; ADelta: Sw_Integer)`

Visibility: default

Description: `Init` calls the inherited constructor (see `TCollection.Init` ([924](#))) and sets the `Duplicates` flag to `false`.

You should not call this method directly, since `TSortedCollection` is a abstract class. Instead, the descendent classes should call it via the `inherited` keyword.

Errors: None.

See also: `TSortedCollection.Load` ([958](#)), `TCollection.Done` ([925](#))

### 29.13.4 `TSortedCollection.Load`

Synopsis: Instantiates a new instance of a `TSortedCollection` and loads it from stream.

Declaration: `constructor Load (var S: TStream)`

Visibility: default

Description: `Load` calls the inherited constructor (see `TCollection.Load` ([925](#))) and reads the `Duplicates` flag from the stream..

You should not call this method directly, since `TSortedCollection` is a abstract class. Instead, the descendent classes should call it via the `inherited` keyword.

For an example, see `TCollection.Load` ([925](#)).

Errors: None.

See also: `TSortedCollection.Init` ([958](#)), `TCollection.Done` ([925](#))

### 29.13.5 `TSortedCollection.KeyOf`

Synopsis: Return the key of an item

Declaration: `function KeyOf (Item: Pointer) : Pointer; Virtual`

Visibility: default



**Description:** `KeyOf` returns the key associated with `Item`. `TSortedCollection` returns the item itself as the key, descendent objects can override this method to calculate a (unique) key based on the item passed (such as hash values).

`Keys` are used to sort the objects, they are used to search and sort the items in the collection. If descendent types override this method then it allows possibly for faster search/sort methods based on keys rather than on the objects themselves.

**Errors:** None.

**See also:** `TSortedCollection.IndexOf` (959), `TSortedCollection.Compare` (959)

### 29.13.6 `TSortedCollection.IndexOf`

**Synopsis:** Return index of an item in the collection.

**Declaration:** `function IndexOf(Item: Pointer) : Sw_Integer; Virtual`

**Visibility:** default

**Description:** `IndexOf` returns the index of `Item` in the collection. It searches for the object based on it's key. If duplicates are allowed, then it returns the index of last object that matches `Item`.

In case `Item` is not found in the collection, -1 is returned.

For an example, see `TCollection.IndexOf` (926)

**Errors:** None.

**See also:** `TSortedCollection.Search` (960), `TSortedCollection.Compare` (959)

### 29.13.7 `TSortedCollection.Compare`

**Synopsis:** Compare two items in the collection.

**Declaration:** `function Compare(Key1: Pointer;Key2: Pointer) : Sw_Integer; Virtual`

**Visibility:** default

**Description:** `Compare` is an abstract method that should be overridden by descendent objects in order to compare two items in the collection. This method is used in the `Search` (960) method and in the `Insert` (961) method to determine the ordering of the objects.

The function should compare the two keys of items and return the following function results:

**Result < 0** If `Key1` is logically before `Key2` (`Key1<Key2`)

**Result = 0** If `Key1` and `Key2` are equal. (`Key1=Key2`)

**Result > 0** If `Key1` is logically after `Key2` (`Key1>Key2`)

**Errors:** An 'abstract run-time error' will be generated if you call `TSortedCollection.Compare` directly.

**See also:** `TSortedCollection.IndexOf` (959), `TSortedCollection.Search` (960)

**Listing:** `./objectex/mysortc.pp`

---

**Unit** MySortC;

**Interface**

**Uses** Objects;

**Type**

```

PMySortedCollection = ^TMySortedCollection;
TMySortedCollection = Object(TSortedCollection)
    Function Compare (Key1,Key2 : Pointer) : Sw_integer; virtual;
    end;

```

**Implementation**

**Uses** MyObject;

**Function** TMySortedCollection.Compare (Key1,Key2 : Pointer) : sw\_integer;

**begin**

```

    Compare:=PMyobject(Key1)^.GetField - PMyObject(Key2)^.GetField;

```

**end**;

**end**.

---

### 29.13.8 TSortedCollection.Search

Synopsis: Search for item with given key.

Declaration: `function Search(Key: Pointer;var Index: Sw_Integer) : Boolean; Virtual`

Visibility: default

Description: Search looks for the item with key Key and returns the position of the item (if present) in the collection in Index.

Instead of a linear search as TCollection does, TSortedCollection uses a binary search based on the keys of the objects. It uses the Compare (959) function to implement this search.

If the item is found, Search returns True, otherwise False is returned.

Errors: None.

See also: TCollection.IndexOf (926)

**Listing:** ./objectex/ex36.pp

---

**Program** ex36;

*{ Program to demonstrate the TSortedCollection.Insert method }*

**Uses** Objects, MyObject, MySortC;

*{ For TMyObject, TMySortedCollection definition and registration }*

**Var** C : PSortedCollection;

    M : PMyObject;

    I : Longint;

**Procedure** PrintField (Dummy: Pointer;P : PMyObject);

```

begin
  Writeln ( 'Field : ', P^.GetField );
end;

begin
  Randomize;
  C:=New( PMySortedCollection, Init(120,10));
  C^.Duplicates:=True;
  Writeln ( 'Inserting 100 records at random places.' );
  For I:=1 to 100 do
    begin
      M:=New(PMyObject, Init);
      M^.SetField(Random(100));
      C^.Insert(M)
    end;
  M:=New(PMyObject, Init);
  Repeat;
    Write ( 'Value to search for (-1 stops) : ' );
    read ( I );
    If I<>-1 then
      begin
        M^.SetField(i);
        If Not C^.Search (M,I) then
          Writeln ( 'No such value found' )
        else
          begin
            Write ( 'Value ', PMyObject(C^.At(I))^ .GetField );
            Writeln ( ' present at position ', I );
          end;
      end;
    Until I=-1;
    Dispose (M, Done );
    Dispose (C, Done );
  end.

```

---

### 29.13.9 TSortedCollection.Insert

Synopsis: Insert new item in collection.

Declaration: `procedure Insert(Item: Pointer); Virtual`

Visibility: default

Description: `Insert` inserts an item in the collection at the correct position, such that the collection is ordered at all times. You should never use `Atinsert` (937), since then the collection ordering is not guaranteed.

If `Item` is already present in the collection, and `Duplicates` is `False`, the item will not be inserted.

Errors: None.

See also: `TCollection.AtInsert` (937)

**Listing:** `./objectex/ex35.pp`

---

```

Program ex35;

{ Program to demonstrate the TSortedCollection.Insert method }

Uses Objects, MyObject, MySortC;
{ For TMyObject, TMySortedCollection definition and registration }

Var C : PSortedCollection;
    M : PMyObject;
    I : Longint;

Procedure PrintField (Dummy: Pointer; P : PMyObject);

begin
    WriteLn ( 'Field : ', P^.GetField );
end;

begin
    Randomize;
    C:=New( PMySortedCollection, Init(120,10));
    WriteLn ( 'Inserting 100 records at random places.' );
    For I:=1 to 100 do
        begin
            M:=New( PMyObject, Init );
            M^.SetField(Random(100));
            C^.Insert(M)
        end;
    WriteLn ( 'Values : ' );
    C^.Foreach( @PrintField );
    Dispose(C, Done);
end.

```

---

### 29.13.10 TSortedCollection.Store

Synopsis: Write the collection to the stream.

Declaration: `procedure Store(var S: TStream)`

Visibility: default

Description: `Store` writes the collection to the stream `S`. It does this by calling the inherited `TCollection.Store` (938), and then writing the `Duplicates` flag to the stream.

After a `Store`, the collection can be loaded from the stream with the constructor `Load` (958)

For an example, see `TCollection.Load` (925).

Errors: Errors can be those of `TStream.Put` (970).

See also: `TSortedCollection.Load` (958)

## 29.14 TStrCollection

### 29.14.1 Description

The `TStrCollection` object manages a sorted collection of null-terminated strings (pchar strings). To this end, it overrides the `Compare` (959) method of `TSortedCollection`, and it introduces methods to read/write strings from a stream.

### 29.14.2 Method overview

Page	Property	Description
<a href="#">963</a>	<code>Compare</code>	Compare two strings in the collection.
<a href="#">964</a>	<code>FreeItem</code>	Free null-terminated string from the collection.
<a href="#">964</a>	<code>GetItem</code>	Read a null-terminated string from the stream.
<a href="#">964</a>	<code>PutItem</code>	Write a null-terminated string to the stream.

### 29.14.3 TStrCollection.Compare

Synopsis: Compare two strings in the collection.

Declaration: `function Compare(Key1: Pointer;Key2: Pointer) : Sw_Integer; Virtual`

Visibility: default

Description: `TStrCollection` overrides the `Compare` function so it compares the two keys as if they were pointers to strings. The compare is done case sensitive. It returns

-1 if the first string is alphabetically earlier than the second string.

0 if the two strings are equal.

1 if the first string is alphabetically later than the second string.

Errors: None.

See also: `TSortedCollection.Compare` (959)

**Listing:** `./objectex/ex38.pp`

---

**Program** `ex38;`

*{ Program to demonstrate the TStrCollection.Compare method }*

**Uses** `Objects , Strings ;`

**Var** `C : PStrCollection ;`

`S : String ;`

`I : longint ;`

`P : Pchar ;`

**begin**

`Randomize ;`

`C:=New( PStrCollection , Init(120,10));`

`C^.Duplicates:=True; { Duplicates allowed }`

`WriteLn ( 'Inserting 100 records at random places.' );`

`For I:=1 to 100 do`

`begin`

`Str(Random(100),S);`

---

```

S:= 'String with value '+S;
P:= StrAlloc (Length(S)+1);
C^.Insert(StrPCopy(P,S));
end;
For I:=0 to 98 do
  With C^ do
    If Compare (At(I),At(I+1))=0 then
      WriteLn ('Duplicate string found at position ',I);
    Dispose(C,Done);
  end.

```

---

#### 29.14.4 TStrCollection.GetItem

Synopsis: Read a null-terminated string from the stream.

Declaration: `function GetItem(var S: TStream) : Pointer; Virtual`

Visibility: default

Description: `GetItem` reads a null-terminated string from the stream `S` and returns a pointer to it. It doesn't insert the string in the collection.

This method is primarily introduced to be able to load and store the collection from and to a stream.

Errors: The errors returned are those of `TStream.StrRead` (966).

See also: `TStrCollection.PutItem` (964)

#### 29.14.5 TStrCollection.FreeItem

Synopsis: Free null-terminated string from the collection.

Declaration: `procedure FreeItem(Item: Pointer); Virtual`

Visibility: default

Description: `TStrCollection` overrides `FreeItem` so that the string pointed to by `Item` is disposed from memory.

Errors: None.

See also: `TCollection.FreeItem` (934)

#### 29.14.6 TStrCollection.PutItem

Synopsis: Write a null-terminated string to the stream.

Declaration: `procedure PutItem(var S: TStream; Item: Pointer); Virtual`

Visibility: default

Description: `PutItem` writes the string pointed to by `Item` to the stream `S`.

This method is primarily used in the `Load` and `Store` methods, and should not be used directly.

Errors: Errors are those of `TStream.StrWrite` (971).

See also: `TStrCollection.GetItem` (964)

## 29.15 TStream

### 29.15.1 Description

The `TStream` object is the ancestor for all streaming objects, i.e. objects that have the capability to store and retrieve data.

It defines a number of methods that are common to all objects that implement streaming, many of them are virtual, and are only implemented in the descendent types.

Programs should not instantiate objects of type `TStream` directly, but instead instantiate a descendant type, such as `TDosStream`, `TMemoryStream`.

### 29.15.2 Method overview

Page	Property	Description
969	<code>Close</code>	Close the stream
973	<code>CopyFrom</code>	Copy data from another stream.
971	<code>Error</code>	Set stream status
970	<code>Flush</code>	Flush the stream data from the buffer, if any.
965	<code>Get</code>	Read an object definition from the stream.
967	<code>GetPos</code>	Return current position in the stream
967	<code>GetSize</code>	Return the size of the stream.
965	<code>Init</code>	Constructor for <code>TStream</code> instance
969	<code>Open</code>	Open the stream
970	<code>Put</code>	Write an object to the stream.
972	<code>Read</code>	Read data from stream to buffer.
968	<code>ReadStr</code>	Read a shortstring from the stream.
969	<code>Reset</code>	Reset the stream
971	<code>Seek</code>	Set stream position.
966	<code>StrRead</code>	Read a null-terminated string from the stream.
971	<code>StrWrite</code>	Write a null-terminated string to the stream.
970	<code>Truncate</code>	Truncate the stream size on current position.
972	<code>Write</code>	Write a number of bytes to the stream.
971	<code>WriteStr</code>	Write a pascal string to the stream.

### 29.15.3 TStream.Init

Synopsis: Constructor for `TStream` instance

Declaration: `constructor Init`

Visibility: default

Description: `Init` initializes a `TStream` instance. Descendent streams should always call the inherited `Init`.

### 29.15.4 TStream.Get

Synopsis: Read an object definition from the stream.

Declaration: `function Get : PObject`

Visibility: default

Description: `Get` reads an object definition from a stream, and returns a pointer to an instance of this object.

Errors: On error, TStream.Status (??) is set, and NIL is returned.

See also: TStream.Put ([970](#))

**Listing:** ./objectex/ex9.pp

---

**Program** ex9;

*{ Program to demonstrate TStream.Get and TStream.Put }*

**Uses** Objects, MyObject; *{ Definition and registration of TMyObject }*

**Var** Obj : PMyObject;  
S : PStream;

**begin**

```
Obj:=New(PMyObject, Init);
Obj^.SetField($1111);
Writeln('Field value : ', Obj^.GetField);
{ Since Stream is an abstract type, we instantiate a TMemoryStream }
S:=New(PMemoryStream, Init(100,10));
S^.Put(Obj);
Writeln('Disposing object');
S^.Seek(0);
Dispose(Obj, Done);
Writeln('Reading object');
Obj:=PMyObject(S^.Get);
Writeln('Field Value : ', Obj^.GetField);
Dispose(Obj, Done);
```

**end.**

---

### 29.15.5 TStream.StrRead

Synopsis: Read a null-terminated string from the stream.

Declaration: `function StrRead : PChar`

Visibility: default

Description: StrRead reads a string from the stream, allocates memory for it, and returns a pointer to a null-terminated copy of the string on the heap.

Errors: On error, Nil is returned.

See also: TStream.StrWrite ([971](#)), TStream.ReadStr ([968](#))

**Listing:** ./objectex/ex10.pp

---

**Program** ex10;

*{  
Program to demonstrate the TStream.StrRead TStream.StrWrite functions  
}*

**Uses** objects;

**Var** P : PChar;  
S : PStream;



---

```

begin
  P:= 'Constant Pchar string';
  Writeln ('Writing to stream : ',P,'');
  S:=New(PMemoryStream, Init(100,10));
  S^.StrWrite(P);
  S^.Seek(0);
  P:= Nil;
  P:=S^.StrRead;
  Dispose (S,Done);
  Writeln ('Read from stream : ',P,'');
  Freemem(P, Strlen(P)+1);
end.

```

---

### 29.15.6 TStream.GetPos

Synopsis: Return current position in the stream

Declaration: `function GetPos : LongInt; Virtual`

Visibility: default

Description: If the stream's status is `stOk`, `GetPos` returns the current position in the stream. Otherwise it returns `-1`

Errors: `-1` is returned if the status is an error condition.

See also: `TStream.Seek` ([971](#)), `TStream.GetSize` ([967](#))

**Listing:** `./objectex/ex11.pp`

---

```

Program ex11;

{ Program to demonstrate the TStream.GetPos function }

Uses objects;

Var L : String;
    S : PStream;

begin
  L:= 'Some kind of string';
  S:=New(PMemoryStream, Init(100,10));
  Writeln ('Stream position before write : ',S^.GetPos);
  S^.WriteStr(@L);
  Writeln ('Stream position after write : ',S^.GetPos);
  Dispose(S,Done);
end.

```

---

### 29.15.7 TStream.GetSize

Synopsis: Return the size of the stream.

Declaration: `function GetSize : LongInt; Virtual`

Visibility: default

Description: If the stream's status is `stOk` then `GetSize` returns the size of the stream, otherwise it returns `-1`.

Errors: `-1` is returned if the status is an error condition.

See also: `TStream.Seek` (971), `TStream.GetPos` (967)

**Listing:** `./objectex/ex12.pp`

---

```

Program ex12;

{ Program to demonstrate the TStream.GetSize function }

Uses objects;

Var L : String;
    S : PStream;

begin
  L:= 'Some kind of string';
  S:=New(PMemoryStream, Init(100,10));
  Writeln ( 'Stream size before write : ',S^.GetSize);
  S^.WriteStr(@L);
  Writeln ( 'Stream size after write : ',S^.GetSize);
  Dispose(S,Done);
end.
```

---

### 29.15.8 TStream.ReadStr

Synopsis: Read a shortstring from the stream.

Declaration: `function ReadStr : PString`

Visibility: default

Description: `ReadStr` reads a string from the stream, copies it to the heap and returns a pointer to this copy. The string is saved as a pascal string, and hence is NOT null terminated.

Errors: On error (e.g. not enough memory), `Nil` is returned.

See also: `TStream.StrRead` (966)

**Listing:** `./objectex/ex13.pp`

---

```

Program ex13;

{
  Program to demonstrate the TStream.ReadStr TStream.WriteStr functions
}

Uses objects;

Var P : PString;
    L : String;
    S : PStream;

begin
  L:= 'Constant string line';
  Writeln ( 'Writing to stream : " ',L,'" ');
```

---

---

```

S:=New(PMemoryStream, Init(100,10));
S^.WriteStr(@L);
S^.Seek(0);
P:=S^.ReadStr;
L:=P^;
DisposeStr(P);
Dispose(S, Done);
WriteLn('Read from stream : "', L, '"');
end.

```

---

### 29.15.9 TStream.Open

Synopsis: Open the stream

Declaration: `procedure Open(OpenMode: Word); Virtual`

Visibility: default

Description: `Open` is an abstract method, that should be overridden by descendent objects. Since opening a stream depends on the stream's type this is not surprising.

For an example, see `TDosStream.Open` ([942](#)).

Errors: None.

See also: `TStream.Close` ([969](#)), `TStream.Reset` ([969](#))

### 29.15.10 TStream.Close

Synopsis: Close the stream

Declaration: `procedure Close; Virtual`

Visibility: default

Description: `Close` is an abstract method, that should be overridden by descendent objects. Since Closing a stream depends on the stream's type this is not surprising.

for an example, see `TDosStream.Open` ([942](#)).

Errors: None.

See also: `TStream.Open` ([969](#)), `TStream.Reset` ([969](#))

### 29.15.11 TStream.Reset

Synopsis: Reset the stream

Declaration: `procedure Reset`

Visibility: default

Description: `Reset` sets the stream's status to 0, as well as the `ErrorInfo`

Errors: None.

See also: `TStream.Open` ([969](#)), `TStream.Close` ([969](#))

### 29.15.12 TStream.Flush

Synopsis: Flush the stream data from the buffer, if any.

Declaration: `procedure Flush; Virtual`

Visibility: default

Description: `Flush` is an abstract method that should be overridden by descendent objects. It serves to enable the programmer to tell streams that implement a buffer to clear the buffer.

for an example, see `TBufStream.Flush` ([921](#)).

Errors: None.

See also: `TStream.Truncate` ([970](#))

### 29.15.13 TStream.Truncate

Synopsis: Truncate the stream size on current position.

Declaration: `procedure Truncate; Virtual`

Visibility: default

Description: `Truncate` is an abstract procedure that should be overridden by descendent objects. It serves to enable the programmer to truncate the size of the stream to the current file position.

For an example, see `TDosStream.Truncate` ([940](#)).

Errors: None.

See also: `TStream.Seek` ([971](#))

### 29.15.14 TStream.Put

Synopsis: Write an object to the stream.

Declaration: `procedure Put (P: PObject)`

Visibility: default

Description: `Put` writes the object pointed to by `P`. `P` should be non-nil. The object type must have been registered with `RegisterType` ([918](#)).

After the object has been written, it can be read again with `Get` ([965](#)).

For an example, see `TStream.Get` ([965](#));

Errors: No check is done whether `P` is `Nil` or not. Passing `Nil` will cause a run-time error 216 to be generated. If the object has not been registered, the status of the stream will be set to `stPutError`.

See also: `TStream.Get` ([965](#))

### 29.15.15 TStream.StrWrite

Synopsis: Write a null-terminated string to the stream.

Declaration: `procedure StrWrite(P: PChar)`

Visibility: default

Description: `StrWrite` writes the null-terminated string `P` to the stream. `P` can only be 65355 bytes long.

For an example, see `TStream.StrRead` (966).

Errors: None.

See also: `TStream.WriteString` (971), `TStream.StrRead` (966), `TStream.ReadStr` (968)

### 29.15.16 TStream.WriteString

Synopsis: Write a pascal string to the stream.

Declaration: `procedure WriteStr(P: PString)`

Visibility: default

Description: `StrWrite` writes the pascal string pointed to by `P` to the stream.

For an example, see `TStream.ReadStr` (968).

Errors: None.

See also: `TStream.StrWrite` (971), `TStream.StrRead` (966), `TStream.ReadStr` (968)

### 29.15.17 TStream.Seek

Synopsis: Set stream position.

Declaration: `procedure Seek(Pos: LongInt); Virtual`

Visibility: default

Description: `Seek` sets the position to `Pos`. This position is counted from the beginning, and is zero based. (i.e. `seek(0)` sets the position pointer on the first byte of the stream)

For an example, see `TDosStream.Seek` (941).

Errors: If `Pos` is larger than the stream size, `Status` is set to `StSeekError`.

See also: `TStream.GetPos` (967), `TStream.GetSize` (967)

### 29.15.18 TStream.Error

Synopsis: Set stream status

Declaration: `procedure Error(Code: Integer; Info: Integer); Virtual`

Visibility: default

Description: `Error` sets the stream's status to `Code` and `ErrorInfo` to `Info`. If the `StreamError` procedural variable is set, `Error` executes it, passing `Self` as an argument.

This method should not be called directly from a program. It is intended to be used in descendent objects.

Errors: None.

**29.15.19 TStream.Read**

Synopsis: Read data from stream to buffer.

Declaration: `procedure Read(var Buf;Count: LongInt); Virtual`

Visibility: default

Description: Read is an abstract method that should be overridden by descendent objects.

Read reads Count bytes from the stream into Buf. It updates the position pointer, increasing it's value with Count. Buf must be large enough to contain Count bytes.

Errors: No checking is done to see if Buf is large enough to contain Count bytes.

See also: TStream.Write (972), TStream.ReadStr (968), TStream.StrRead (966)

**Listing:** ./objectex/ex18.pp

---

```

program ex18;

{ Program to demonstrate the TStream.Read method }

Uses Objects;

Var Buf1, Buf2 : Array[1..1000] of Byte;
    I : longint;
    S : PMemoryStream;

begin
    For I:=1 to 1000 do
        Buf1[I]:=Random(1000);
    Buf2:=Buf1;
    S:=New(PMemoryStream, Init(100,10));
    S^.Write(Buf1, SizeOf(Buf1));
    S^.Seek(0);
    For I:=1 to 1000 do
        Buf1[I]:=0;
    S^.Read(Buf1, SizeOf(Buf1));
    For I:=1 to 1000 do
        If Buf1[I]<>Buf2[I] then
            WriteLn('Buffer differs at position ',I);
    Dispose(S, Done);
end.

```

---

**29.15.20 TStream.Write**

Synopsis: Write a number of bytes to the stream.

Declaration: `procedure Write(var Buf;Count: LongInt); Virtual`

Visibility: default

Description: Write is an abstract method that should be overridden by descendent objects.

Write writes Count bytes to the stream from Buf. It updates the position pointer, increasing it's value with Count.

For an example, see TStream.Read (972).

Errors: No checking is done to see if Buf actually contains Count bytes.

See also: TStream.Read (972), TStream.WriteStr (971), TStream.StrWrite (971)

### 29.15.21 TStream.CopyFrom

Synopsis: Copy data from another stream.

Declaration: `procedure CopyFrom(var S: TStream; Count: LongInt)`

Visibility: default

Description: `CopyFrom` reads `Count` bytes from stream `S` and stores them in the current stream. It uses the `Read` (972) method to read the data, and the `Write` (972) method to write in the current stream.

Errors: None.

See also: `TStream.Read` (972), `TStream.Write` (972)

**Listing:** `./objectex/ex19.pp`

---

**Program** `ex19`;

*{ Program to demonstrate the TStream.CopyFrom function }*

**Uses** `objects`;

**Var** `P` : `PString`;  
    `L` : **String**;  
    `S1,S2` : `PStream`;

**begin**  
    `L:= 'Constant string line'`;  
    **Writeln** ( 'Writing to stream 1 : " ',`L`, ' " ');  
    `S1:=New(PMemoryStream, Init(100,10))`;  
    `S2:=New(PMemoryStream, Init(100,10))`;  
    `S1^.WriteStr(@L)`;  
    `S1^.Seek(0)`;  
    **Writeln** ( 'Copying contents of stream 1 to stream 2 ' );  
    `S2^.Copyfrom(S1^,S1^.GetSize)`;  
    `S2^.Seek(0)`;  
    `P:=S2^.ReadStr`;  
    `L:=P^`;  
    **DisposeStr**(`P`);  
    **Dispose** ( `S1`, `Done` );  
    **Dispose** ( `S2`, `Done` );  
    **Writeln** ( 'Read from stream 2 : " ',`L`, ' " ');  
**end.**

---

## 29.16 TStringCollection

### 29.16.1 Description

The `TStringCollection` object manages a sorted collection of pascal strings. To this end, it overrides the `Compare` (959) method of `TSortedCollection`, and it introduces methods to read/write strings from a stream.

### 29.16.2 Method overview

Page	Property	Description
<a href="#">974</a>	Compare	Compare two strings in the collection.
<a href="#">975</a>	FreeItem	Dispose a string in the collection from memory.
<a href="#">974</a>	GetItem	Get string from the stream.
<a href="#">975</a>	PutItem	Write a string to the stream.

### 29.16.3 TStringCollection.GetItem

Synopsis: Get string from the stream.

Declaration: `function GetItem(var S: TStream) : Pointer; Virtual`

Visibility: default

Description: `GetItem` reads a string from the stream `S` and returns a pointer to it. It doesn't insert the string in the collection.

This method is primarily introduced to be able to load and store the collection from and to a stream.

Errors: The errors returned are those of `TStream.ReadStr` ([968](#)).

See also: `TStringCollection.PutItem` ([975](#))

### 29.16.4 TStringCollection.Compare

Synopsis: Compare two strings in the collection.

Declaration: `function Compare(Key1: Pointer;Key2: Pointer) : Sw_Integer; Virtual`

Visibility: default

Description: `TStringCollection` overrides the `Compare` function so it compares the two keys as if they were pointers to strings. The compare is done case sensitive. It returns the following results:

-1if the first string is alphabetically earlier than the second string.

0if the two strings are equal.

1if the first string is alphabetically later than the second string.

Errors: None.

See also: `TSortedCollection.Compare` ([959](#))

**Listing:** `./objectex/ex37.pp`

---

**Program** `ex37`;

*{ Program to demonstrate the TStringCollection.Compare method }*

**Uses** `Objects`;

**Var** `C : PStringCollection`;  
       `S : String`;  
       `I : longint`;

**begin**  
       `Randomize`;



---

```

C:=New(PStringCollection, Init(120,10));
C^.Duplicates:=True; { Duplicates allowed }
WriteLn ('Inserting 100 records at random places. ');
For I:=1 to 100 do
  begin
    Str(Random(100),S);
    S:='String with value '+S;
    C^.Insert(NewStr(S));
  end;
For I:=0 to 98 do
  With C^ do
    If Compare (At(i),At(I+1))=0 then
      WriteLn ('Duplicate string found at position ',i);
Dispose(C,Done);
end.

```

---

### 29.16.5 TStringCollection.FreeItem

Synopsis: Dispose a string in the collection from memory.

Declaration: `procedure FreeItem(Item: Pointer); Virtual`

Visibility: default

Description: `TStringCollection` overrides `FreeItem` so that the string pointed to by `Item` is disposed from memory.

Errors: None.

See also: `TCollection.FreeItem` ([934](#))

### 29.16.6 TStringCollection.PutItem

Synopsis: Write a string to the stream.

Declaration: `procedure PutItem(var S: TStream; Item: Pointer); Virtual`

Visibility: default

Description: `PutItem` writes the string pointed to by `Item` to the stream `S`.

This method is primarily used in the `Load` and `Store` methods, and should not be used directly.

Errors: Errors are those of `TStream.WriteString` ([971](#)).

See also: `TStringCollection.GetItem` ([974](#))

## 29.17 TStringList

### 29.17.1 Description

A `TStringList` object can be used to read a collection of strings stored in a stream. If you register this object with the `RegisterType` ([918](#)) function, you cannot register the `TStrListMaker` object.

**29.17.2 Method overview**

Page	Property	Description
<a href="#">976</a>	Done	Clean up the instance
<a href="#">976</a>	Get	Return a string by key name
<a href="#">976</a>	Load	Load stringlist from stream.

**29.17.3 TStringList.Load**

Synopsis: Load stringlist from stream.

Declaration: `constructor Load(var S: TStream)`

Visibility: default

Description: The `Load` constructor reads the `TStringList` object from the stream `S`. It also reads the descriptions of the strings from the stream. The string descriptions are stored as an array of `TStrIndexrec` records, where each record describes a string on the stream. These records are kept in memory.

Errors: If an error occurs, a stream error is triggered.

See also: `TStringList.Done` ([976](#))

**29.17.4 TStringList.Done**

Synopsis: Clean up the instance

Declaration: `destructor Done; Virtual`

Visibility: default

Description: The `Done` destructor frees the memory occupied by the string descriptions, and destroys the object.

Errors: None.

See also: `TStringList.Load` ([976](#)), `TObject.Done` ([947](#))

**29.17.5 TStringList.Get**

Synopsis: Return a string by key name

Declaration: `function Get(Key: Sw_Word) : String`

Visibility: default

Description: `Get` reads the string with key `Key` from the list of strings on the stream, and returns this string. If there is no string with such a key, an empty string is returned.

Errors: If no string with key `Key` is found, an empty string is returned. A stream error may result if the stream doesn't contain the needed strings.

See also: `TStrListMaker.Put` ([977](#))

## 29.18 TStrListMaker

### 29.18.1 Description

The `TStrListMaker` object can be used to generate a stream with strings, which can be read with the `TStringList` object. If you register this object with the `RegisterType` (918) function, you cannot register the `TStringList` object.

### 29.18.2 Method overview

Page	Property	Description
<a href="#">977</a>	<code>Done</code>	Clean up the instance and free all related memory.
<a href="#">977</a>	<code>Init</code>	Instantiate a new instance of <code>TStrListMaker</code>
<a href="#">977</a>	<code>Put</code>	Add a new string to the list with associated key.
<a href="#">978</a>	<code>Store</code>	Write the strings to the stream.

### 29.18.3 TStrListMaker.Init

Synopsis: Instantiate a new instance of `TStrListMaker`

Declaration: `constructor Init (AStrSize: Sw_Word; AIndexSize: Sw_Word)`

Visibility: default

Description: The `Init` constructor creates a new instance of the `TstrListMaker` object. It allocates `AStrSize` bytes on the heap to hold all the strings you wish to store. It also allocates enough room for `AIndexSize` key description entries (of the type `TStrIndexrec`).

`AStrSize` must be large enough to contain all the strings you wish to store. If not enough memory is allocated, other memory will be overwritten. The same is true for `AIndexSize` : maximally `AIndexSize` strings can be written to the stream.

Errors: None.

See also: `TObject.Init` (945), `TStrListMaker.Done` (977)

### 29.18.4 TStrListMaker.Done

Synopsis: Clean up the instance and free all related memory.

Declaration: `destructor Done; Virtual`

Visibility: default

Description: The `Done` destructor de-allocates the memory for the index description records and the string data, and then destroys the object.

Errors: None.

See also: `TObject.Done` (947), `TStrListMaker.Init` (977)

### 29.18.5 TStrListMaker.Put

Synopsis: Add a new string to the list with associated key.

Declaration: `procedure Put (Key: Sw_Word; S: String)`

Visibility: default

Description: `Put` adds the string `S` with key `Key` to the collection of strings. This action doesn't write the string to a stream. To write the strings to the stream, see the `Store` (978) method.

Errors: None.

See also: `TStrListMaker.Store` (978)

### 29.18.6 TStrListMaker.Store

Synopsis: Write the strings to the stream.

Declaration: `procedure Store(var S: TStream)`

Visibility: default

Description: `Store` writes the collection of strings to the stream `S`. The collection can then be read with the `TStringList` object.

Errors: A stream error may occur when writing the strings to the stream.

See also: `TStringList.Load` (976), `TStrListMaker.Put` (977)

## 29.19 TUnSortedStrCollection

### 29.19.1 Description

The `TUnSortedStrCollection` object manages an unsorted list of strings. To this end, it overrides the `TStringCollection.Insert` (973) method to add strings at the end of the collection, rather than in the alphabetically correct position.

Take care, the `Search` (960) and `IndexOf` (926) methods will not work on an unsorted string collection.

### 29.19.2 Method overview

Page	Property	Description
978	<code>Insert</code>	Insert a new string in the collection.

### 29.19.3 TUnSortedStrCollection.Insert

Synopsis: Insert a new string in the collection.

Declaration: `procedure Insert(Item: Pointer); Virtual`

Visibility: default

Description: `Insert` inserts a string at the end of the collection, instead of on its alphabetical place, resulting in an unsorted collection of strings.

Errors: None.

See also: `TCollection.Insert` (932)

Listing: `./objectex/ex39.pp`

---

**Program** ex39;

*{ Program to demonstrate the TUnsortedStrCollection.Insert method }*

**Uses** Objects, Strings;

**Var** C : PUnsortedStrCollection;  
      S : **String**;  
      I : longint;  
      P : Pchar;

**begin**

**Randomize**;

  C:=**New**(PUnsortedStrCollection, Init(120,10));

**Writeln** ( 'Inserting 100 records at random places.' );

**For** I:=1 **to** 100 **do**

**begin**

**Str**(Random(100),S);

      S:= 'String with value ' + S;

      C^.**Insert**(**NewStr**(S));

**end**;

**For** I:=0 **to** 99 **do**

**Writeln** ( I:2, ': ', PString(C^.**At**(i))^ );

**Dispose**(C,Done);

**end**.

---

## Chapter 30

# Reference for unit 'objpas'

### 30.1 Overview

The `objpas` unit is meant for compatibility with Object Pascal as implemented by Delphi. The unit is loaded automatically by the Free Pascal compiler whenever the `Delphi` or `objfpc` more is entered, either through the command line switches `-Sd` or `-Sh` or with the `{ $MODE DELPHI }` or `{ $MODE OBJFPC }` directives.

It redefines some basic pascal types, introduces some functions for compatibility with Delphi's system unit, and introduces some methods for the management of the resource string tables.

### 30.2 Constants, types and variables

#### 30.2.1 Constants

`MaxInt = MaxLongint`

Maximum value for Integer (980) type.

#### 30.2.2 Types

`Integer = LongInt`

In OBJPAS mode and in DELPHI mode, an `Integer` has a size of 32 bit. In TP or regular FPC mode, an integer is 16 bit.

`IntegerArray = Array[0..$efffffff] of Integer`

Generic array of integer (980)

`PInteger = ^Integer`

Pointer to Integer (980) type.

`PIntegerArray = ^IntegerArray`

Pointer to TIntegerArray (981) type.

```
PointerArray = Array[0..512*1024*1024-2] of Pointer
```

Generic Array of pointers.

```
PPointerArray = ^PointerArray
```

Pointer to PointerArray ([981](#))

```
PResStringRec = ^AnsiString
```

Pointer to ansistring (Delphi compatibility).

```
PString = PAnsiString
```

Pointer to ansistring type.

```
TBoundArray = Array of Integer
```

Array of integer, used in interfaces.

```
TIntegerArray = IntegerArray
```

Alias for IntegerArray ([980](#))

```
TPointerArray = PointerArray
```

Alias for PointerArray ([981](#))

```
TResourceIterator = function(Name: AnsiString;Value: AnsiString;
                             Hash: LongInt;arg: pointer) : AnsiString
```

The resource string tables can be managed with a callback function which the user must provide:

```
TResourceIterator.
```

```
TResStringRec = AnsiString
```

Ansistring record in resource table (Delphi compatibility).

### 30.2.3 Variables

```
ExceptionClass : TClass
```

ExceptionClass is the base class for all exceptions. Normally, this is Exception ([1577](#)), defined in the Sysutils ([1426](#)) unit.

```
ExceptObjProc : Pointer
```

ExceptObjProc is unused in Free Pascal, and is provided for Delphi compatibility only.

## 30.3 Procedures and functions

### 30.3.1 FinalizeResourceTables

Synopsis: Finalize resource string tables

Declaration: `procedure FinalizeResourceTables`

Visibility: default

Description: `FinalizeResourceTables` should be called by any routine that sets the resource string tables to translated versions of the strings. Typically, it should be called in the `Finalization` code of the unit that does the initialization of the tables. This is needed to correctly deallocate the strings from memory

### 30.3.2 GetStringCurrentValue

Synopsis: Return current value of resourcestring

Declaration: `function GetStringCurrentValue (TableIndex: LongInt;  
StringIndex: LongInt) : AnsiString`

Visibility: default

Description: `GetStringCurrentValue` returns the current value of the resourcestring in table `TableIndex` with index `StringIndex`.

The current value depends on the system of internationalization that was used, and which language is selected when the program is executed.

Errors: If either `TableIndex` or `StringIndex` are out of range, then a empty string is returned.

See also: `SetResourceStrings` (986), `GetStringDefaultValue` (983), `GetStringHash` (983), `GetStringName` (984), `ResourceStringTableCount` (986), `ResourceStringCount` (986)

**Listing:** `./refex/ex90.pp`

---

**Program** `Example90`;

```
{ Program to demonstrate the GetStringCurrentValue function. }
{ $Mode Delphi }
```

```
ResourceString
```

```
    First = 'First string';
    Second = 'Second String';
```

```
Var I, J : Longint;
```

```
begin
```

```
    { Print current values of all resourcestrings }
```

```
    For I:=0 to ResourceStringTableCount-1 do
```

```
        For J:=0 to ResourceStringCount(i)-1 do
```

```
            WriteLn (I, ', ', J, ' : ', GetStringCurrentValue (I, J));
```

```
end.
```

---



### 30.3.3 GetResourceStringDefaultValue

Synopsis: Return default (original) value of resourcestring

Declaration: `function GetResourceStringDefaultValue (TableIndex: LongInt;  
StringIndex: LongInt) : AnsiString`

Visibility: default

Description: `GetResourceStringDefaultValue` returns the default value of the resourcestring in table `TableIndex` with index `StringIndex`.

The default value is the value of the string that appears in the source code of the programmer, and is compiled into the program.

Errors: If either `TableIndex` or `StringIndex` are out of range, then a empty string is returned.

See also: `SetResourceStrings` (986), `GetResourceStringCurrentValue` (982), `GetResourceStringHash` (983), `GetResourceStringName` (984), `ResourceStringTableCount` (986), `ResourceStringCount` (986)

Listing: `./refex/ex91.pp`

---

Program Example91;

*{ Program to demonstrate the GetResourceStringDefaultValue function. }*  
*{ \$Mode Delphi }*

ResourceString

First = 'First string';  
Second = 'Second String';

Var I,J : Longint;

begin  
  *{ Print default values of all resourcestrings }*  
  For I:=0 to ResourceStringTableCount-1 do  
    For J:=0 to ResourceStringCount(i)-1 do  
      WriteLn (I, ', ', J, ' : ', GetResourceStringDefaultValue (I,J));  
end.

---

### 30.3.4 GetResourceStringHash

Synopsis: Return hash value of resource string

Declaration: `function GetResourceStringHash (TableIndex: LongInt; StringIndex: LongInt)  
: LongInt`

Visibility: default

Description: `GetResourceStringHash` returns the hash value associated with the resource string in table `TableIndex`, with index `StringIndex`.

The hash value is calculated from the default value of the resource string in a manner that gives the same result as the GNU `gettext` mechanism. It is stored in the resourcestring tables, so retrieval is faster than actually calculating the hash for each string.

For an example, see `Hash` (984).

Errors: If either `TableIndex` or `StringIndex` is zero, 0 is returned.

See also: Hash (984), SetResourceStrings (986), GetResourceStringDefaultValue (983), GetResourceStringHash (983), GetResourceStringName (984), ResourceStringTableCount (986), ResourceStringCount (986)

### 30.3.5 GetResourceStringName

Synopsis: Return name of resource string.

Declaration: `function GetResourceStringName (TableIndex: LongInt; StringIndex: LongInt) : Ansistring`

Visibility: default

Description: `GetResourceStringName` returns the name of the resourcestring in table `TableIndex` with index `StringIndex`. The name of the string is always the unit name in which the string was declared, followed by a period and the name of the constant, all in lowercase.

If a unit `MyUnit` declares a resourcestring `MyTitle` then the name returned will be `myunit.mytitle`. A resourcestring in the program file will have the name of the program prepended.

The name returned by this function is also the name that is stored in the resourcestring file generated by the compiler.

Strictly speaking, this information isn't necessary for the functioning of the program, it is provided only as a means to easier translation of strings.

Errors: If either `TableIndex` or `StringIndex` is zero, an empty string is returned.

See also: SetResourceStrings (986), GetResourceStringDefaultValue (983), GetResourceStringHash (983), GetResourceStringName (984), ResourceStringTableCount (986), ResourceStringCount (986)

**Listing:** `./refex/ex92.pp`

**Program** Example92;

```
{ Program to demonstrate the GetResourceStringName function. }
{$Mode Delphi}
```

ResourceString

```
First  = 'First string';
Second = 'Second String';
```

**Var** I,J : Longint;

**begin**

```
{ Print names of all resourcestrings }
For I:=0 to ResourceStringTableCount-1 do
  For J:=0 to ResourceStringCount(I)-1 do
    Writeln (I, ', ', J, ' : ', GetResourceStringName(I,J));
```

**end.**

### 30.3.6 Hash

Synopsis: Create GNU Gettext hash value for a string

Declaration: `function Hash(S: AnsiString) : LongWord`

Visibility: default

Description: `Hash` calculates the hash value of the string `S` in a manner that is compatible with the GNU `gettext` hash value for the string. It is the same value that is stored in the Resource string tables, and which can be retrieved with the `GetResourceStringHash` (983) function call.

Errors: None. In case the calculated hash value should be 0, the returned result will be -1.

See also: `GetResourceStringHash` (983)

**Listing:** `./refex/ex93.pp`

---

**Program** `Example93`;

```
{ Program to demonstrate the Hash function. }
{$Mode Delphi}

ResourceString

    First  = 'First string';
    Second = 'Second String';

Var I,J : Longint;

begin
    For I:=0 to ResourceStringTableCount-1 do
        For J:=0 to ResourceStringCount(i)-1 do
            If Hash( GetResourceStringDefaultValue(I,J))
                <>GetResourceStringHash(I,J) then
                Writeln ( 'Hash mismatch at ',I,', ',J)
            else
                Writeln ( 'Hash ( ',I,', ',J, ' ) matches. ');
end.
```

---

### 30.3.7 LoadResString

Synopsis: Load resource string

Declaration: `function LoadResString(p: PResStringRec) : AnsiString`

Visibility: default

Description: `LoadResString` loads a resource string based on the description in the `p` parameter, and returns the current value of the string. It is provided for Delphi compatibility but is otherwise unused in the Free Pascal RTL.

### 30.3.8 ResetResourceTables

Synopsis: Restore all resource strings to their declared values

Declaration: `procedure ResetResourceTables`

Visibility: default

Description: `ResetResourceTables` resets all resource strings to their default (i.e. as in the source code) values.

Normally, this should never be called from a user's program. It is called in the initialization code of the `objpas` unit. However, if the resourcetables get messed up for some reason, this procedure will fix them again.

Errors: None.

See also: [SetResourceStrings \(986\)](#), [GetResourceStringDefaultValue \(983\)](#), [GetResourceStringHash \(983\)](#), [GetResourceStringName \(984\)](#), [ResourceStringTableCount \(986\)](#), [ResourceStringCount \(986\)](#)

### 30.3.9 ResourceStringCount

Synopsis: Return number of resource strings in table

Declaration: `function ResourceStringCount (TableIndex: LongInt) : LongInt`

Visibility: default

Description: `ResourceStringCount` returns the number of resource strings in the table with index `TableIndex`. The strings in a particular table are numbered from 0 to `ResourceStringCount-1`, i.e. they're zero based.

For an example, see [GetResourceStringDefaultValue \(983\)](#)

Errors: If an invalid `TableIndex` is given, -1 is returned.

See also: [SetResourceStrings \(986\)](#), [GetResourceStringCurrentValue \(982\)](#), [GetResourceStringDefaultValue \(983\)](#), [GetResourceStringHash \(983\)](#), [GetResourceStringName \(984\)](#), [ResourceStringTableCount \(986\)](#)

### 30.3.10 ResourceStringTableCount

Synopsis: Return number of resource string tables

Declaration: `function ResourceStringTableCount : LongInt`

Visibility: default

Description: `ResourceStringTableCount` returns the number of resource string tables; this may be zero if no resource strings are used in a program.

The tables are numbered from 0 to `ResourceStringTableCount-1`, i.e. they're zero based.

For an example, see [GetResourceStringDefaultValue \(983\)](#)

Errors:

See also: [SetResourceStrings \(986\)](#), [GetResourceStringDefaultValue \(983\)](#), [GetResourceStringHash \(983\)](#), [GetResourceStringName \(984\)](#), [ResourceStringCount \(986\)](#)

### 30.3.11 SetResourceStrings

Synopsis: Set values of all resource strings.

Declaration: `procedure SetResourceStrings (SetFunction: TResourceIterator;  
arg: pointer)`

Visibility: default

**Description:** `SetResourceStrings` calls `SetFunction` for all resourcestrings in the resourcestring tables and sets the resourcestring's current value to the value returned by `SetFunction`.

The `Name`, `Value` and `Hash` parameters passed to the iterator function are the values stored in the tables.

**Errors:** None.

**See also:** `GetResourceStringCurrentValue` (982), `GetResourceStringDefaultValue` (983), `GetResourceStringHash` (983), `GetResourceStringName` (984), `ResourceStringTableCount` (986), `ResourceStringCount` (986)

**Listing:** `./refex/ex95.pp`

---

**Program** `Example95`;

```
{ Program to demonstrate the SetResourceStrings function. }
{$Mode objfpc}
```

`ResourceString`

```
    First = 'First string';
    Second = 'Second String';
```

```
Var I,J : Longint;
    S : AnsiString;
```

```
Function Translate (Name, Value : AnsiString; Hash : longint): AnsiString;
```

```
begin
```

```
    WriteLn ( 'Translate ( ', Name, ') => ', Value );
```

```
    Write   ( ' -> ' );
```

```
    ReadLn  ( Result );
```

```
end;
```

```
begin
```

```
    SetResourceStrings (@Translate);
```

```
    WriteLn ( 'Translated strings : ' );
```

```
    For I:=0 to ResourceStringTableCount-1 do
```

```
        For J:=0 to ResourceStringCount(i)-1 do
```

```
            begin
```

```
                WriteLn ( GetResourceStringDefaultValue(I,J));
```

```
                WriteLn ( 'Translates to : ' );
```

```
                WriteLn ( GetResourceStringCurrentValue(I,J));
```

```
            end;
```

```
end.
```

---

### 30.3.12 SetResourceStringValue

**Synopsis:** Set value of a resource string

**Declaration:** `function SetResourceStringValue` (`TableIndex`: `LongInt`;  
`StringIndex`: `LongInt`; `Value`: `AnsiString`)  
: `Boolean`

**Visibility:** default

**Description:** `SetResourceStringValue` assigns `Value` to the resource string in table `TableIndex` with index `StringIndex`.

Errors:

See also: [SetResourceStrings \(986\)](#), [GetResourceStringCurrentValue \(982\)](#), [GetResourceStringDefaultValue \(983\)](#), [GetResourceStringHash \(983\)](#), [GetResourceStringName \(984\)](#), [ResourceStringTableCount \(986\)](#), [ResourceStringCount \(986\)](#)

**Listing:** ./refex/ex94.pp

---

**Program** Example94;

```
{ Program to demonstrate the SetResourceStringValue function. }
{$Mode Delphi}
```

ResourceString

```
First = 'First string';
Second = 'Second String';
```

```
Var I,J : Longint;
    S : AnsiString;
```

```
begin
  { Print current values of all resourcestrings }
  For I:=0 to ResourceStringTableCount-1 do
    For J:=0 to ResourceStringCount(i)-1 do
      begin
        WriteLn ( 'Translate => ',GetResourceStringDefaultValue(I,J));
        Write   ( '->' );
        ReadLn(S);
        SetResourceStringValue(I,J,S);
      end;
  WriteLn ( 'Translated strings : ');
  For I:=0 to ResourceStringTableCount-1 do
    For J:=0 to ResourceStringCount(i)-1 do
      begin
        WriteLn ( GetResourceStringDefaultValue(I,J));
        WriteLn ( 'Translates to : ');
        WriteLn ( GetResourceStringCurrentValue(I,J));
      end;
end.
```

---

### 30.3.13 SetUnitResourceStrings

Synopsis: Set unit resource strings for a given unit

Declaration: `procedure SetUnitResourceStrings(const UnitName: String;  
SetFunction: TResourceIterator;  
arg: pointer)`

Visibility: default

Description: `SetUnitResourceStrings` will call `SetFunction` for all resource strings of the unit indicated by `UnitName`. The additional `Arg` pointer will be passed to the `SetFunction` iterator.

Errors: None.

See also: [SetResourceStrings \(986\)](#), [ResetResourceTables \(985\)](#), [FinalizeResourceTables \(982\)](#)

## Chapter 31

# Reference for unit 'oldlinux'

### 31.1 Overview

This document describes the LINUX unit for Free Pascal. The unit was written by Michael van Canneyt. It works only on the Linux/X86 operating system.

### 31.2 Utility routines

Auxiliary functions that are useful in connection with the other functions.

Table 31.1:

Name	Description
CreateShellArgV ( <a href="#">1051</a> )	Create an array of pchars from string
EpochToLocal ( <a href="#">1053</a> )	Convert epoch time to local time
FD_Clr ( <a href="#">1064</a> )	Clear item of select filedescriptors
FD_IsSet ( <a href="#">1064</a> )	Check item of select filedescriptors
FD_Set ( <a href="#">1065</a> )	Set item of select filedescriptors
FD_ZERO ( <a href="#">1065</a> )	Clear all items in select filedescriptors
LocalToEpoch ( <a href="#">1084</a> )	Convert local time to epoch time
MMap ( <a href="#">1086</a> )	Map a file into memory
MUnMap ( <a href="#">1088</a> )	Unmap previously mapped memory file
Octal ( <a href="#">1090</a> )	Convert octal to digital
S_ISBLK ( <a href="#">1106</a> )	Check file mode for block device
S_ISCHR ( <a href="#">1107</a> )	Check file mode for character device
S_ISDIR ( <a href="#">1107</a> )	Check file mode for directory
S_ISFIFO ( <a href="#">1107</a> )	Check file mode for FIFO
S_ISLNK ( <a href="#">1107</a> )	Check file mode for symboloc link
S_ISREG ( <a href="#">1108</a> )	Check file mode for regular file
S_ISSOCK ( <a href="#">1108</a> )	Check file mode for socket
StringToPPchar ( <a href="#">1103</a> )	Create an array of pchars from string

### 31.3 Terminal functions

Functions for controlling the terminal to which the process is connected.

Table 31.2:

Name	Description
CFMakeRaw (1045)	Set terminal to raw mode
CFSetISpeed (1046)	Set terminal reading speed
CFSetOSpeed (1046)	Set terminal writing speed
IOCtl (1081)	General IO control call
IsATTY (1082)	See if filedescriptor is a terminal
TCDrain (1109)	Wait till all output was written
TCFlow (1109)	Suspend transmission or receipt of data
TCFlush (1109)	Discard data written to terminal
TCGetAttr (1110)	Get terminal attributes
TCGetPGrp (1110)	Return PID of foreground process
TCSendBreak (1111)	Send data for specific time
TCSetAttr (1111)	Set terminal attributes
TCSetPGrp (1112)	Set foreground process
TTYName (1112)	Name of tty file

### 31.4 System information

Functions for retrieving system information such as date and time.

Table 31.3:

Name	Description
GetDate (1071)	Return system date
GetDateTime (1072)	Return system date and time
GetDomainName (1072)	Return system domain name
GetEpochTime (1074)	Return epoch time
GetHostName (1076)	Return system host name
GetLocalTimezone (1076)	Return system timezone
GetTime (1078)	Return system time
GetTimeOfDay (1079)	Return system time
GetTimezoneFile (1079)	Return name of timezone file
ReadTimezoneFile (1095)	Read timezone file contents
SysInfo (1105)	Return general system information
Uname (1113)	Return system information

### 31.5 Signals

Functions for managing and responding to signals.



Table 31.4:

Name	Description
Alarm (1042)	Send alarm signal to self
Kill (1082)	Send arbitrary signal to process
pause (1091)	Wait for signal to arrive
SigAction (1099)	Set signal action
Signal (1100)	Set signal action
SigPending (1101)	See if signals are waiting
SigProcMask (1101)	Set signal processing mask
SigRaise (1102)	Send signal to self
SigSuspend (1103)	Sets signal mask and waits for signal
NanoSleep (1088)	Waits for a specific amount of time

## 31.6 Process handling

Functions for managing processes and programs.

Table 31.5:

Name	Description
Clone (1048)	Create a thread
Execl (1054)	Execute process with command-line list
Execle (1055)	Execute process with command-line list and environment
Execlp (1056)	Search in path and execute process with command list
Execv (1056)	Execute process
Execve (1057)	Execute process with environment
Execvp (1058)	Search in path and execute process
Fork (1067)	Spawn child process
GetEGid (1073)	Get effective group id
GetEnv (1073)	Get environment variable
GetEUid (1074)	Get effective user id
GetGid (1075)	Get group id
GetPid (1077)	Get process id
GetPPid (1077)	Get parent process id
GetPriority (1078)	Get process priority
GetUid (1079)	Get user id
Nice (1089)	Change priority of process
SetPriority (1098)	Change priority of process
Shell (1098)	Execute shell command
WaitPid (1115)	Wait for child process to terminate

## 31.7 Directory handling routines

Functions for reading and searching directories.

Table 31.6:

Name	Description
CloseDir (1050)	Close directory handle
Glob (1080)	Return files matching a search expression
GlobFree (1081)	Free result of Glob
OpenDir (1090)	Open directory for reading
ReadDir (1093)	Read directory entry
SeekDir (1095)	Seek directory
TellDir (1112)	Seek directory

## 31.8 Pipes, FIFOs and streams

Functions for creating and managing pipes.

Table 31.7:

Name	Description
AssignPipe (1042)	Create a pipe
AssignStream (1043)	Create pipes to program's input and output
MkFifo (1086)	Make a fifo
PClose (1092)	Close a pipe
POpen (1092)	Open a pipe for to program's input or output

## 31.9 General File handling routines

Functions for handling files on disk.

## 31.10 File Input/Output routines

Functions for handling file input/output.

## 31.11 Constants, types and variables

### 31.11.1 Constants

B0 = \$00000000

B110 = \$00000003

B115200 = \$0001002

B1200 = \$00000009

Table 31.8:

Name	Description
Access (1041)	Check access rights on file
BaseName (1045)	Return name part of file
Chown (1047)	Change owner of file
Chmod (1046)	Change access rights on file
DirName (1051)	Return directory part of file
FSplit (1068)	Split filename in parts
FExpand (1065)	Return full-grown filename
FLock (1066)	Set lock on a file
FNMatch (1066)	Match filename to searchpattern
FSearch (1068)	Search for a file in a path
FSSStat (1069)	Return filesystem information
FStat (1070)	Return file information
FRename (1067)	Rename file
LStat (1085)	Return information on a link
Link (1083)	Create a link
ReadLink (1093)	Read contents of a symbolic link
SymLink (1104)	Create a symbolic link
Umask (1113)	Set the file creation mask
UnLink (1113)	Remove a file
Utime (1114)	Change file timestamps

B134 = \$00000004

B150 = \$00000005

B1800 = \$0000000A

B19200 = \$0000000E

B200 = \$00000006

B230400 = \$0001003

B2400 = \$0000000B

B300 = \$00000007

B38400 = \$0000000F

B460800 = \$0001004

Table 31.9:

Name	Description
Dup ( <a href="#">1052</a> )	Duplicate a file handle
Dup2 ( <a href="#">1053</a> )	Copy one file handle to another
Fcntl ( <a href="#">1060</a> )	General file control
fdClose ( <a href="#">1060</a> )	Close file descriptor
fdFlush ( <a href="#">1060</a> )	Flush file descriptor
fdOpen ( <a href="#">1061</a> )	Open new file descriptor
fdRead ( <a href="#">1062</a> )	Read from file descriptor
fdSeek ( <a href="#">1063</a> )	Position in file
fdTruncate ( <a href="#">1063</a> )	Truncate file
fdWrite ( <a href="#">1064</a> )	Write to file descriptor
GetFS ( <a href="#">1075</a> )	Get file descriptor of pascal file
Select ( <a href="#">1095</a> )	Wait for input from file descriptor
SelectText ( <a href="#">1097</a> )	Wait for input from pascal file

B4800 = \$000000C

B50 = \$0000001

B57600 = \$0001001

B600 = \$0000008

B75 = \$0000002

B9600 = \$000000D

BRKINT = \$0000002

BS0 = \$0000000

BS1 = \$0002000

BSDLY = \$0002000

CBAUD = \$000100F

CBAUDEX = \$0001000

CIBAUD = \$100F0000

CLOCAL = \$0000800

CLONE\_FILES = \$00000400

Clone (1048) option: open files shared between processes

CLONE\_FS = \$00000200

Clone (1048) option: fs info shared between processes

CLONE\_PID = \$00001000

Clone (1048) option: PID shared between processes

CLONE\_SIGHAND = \$00000800

Clone (1048) option: signal handlers shared between processes

CLONE\_VM = \$00000100

Clone (1048) option: VM shared between processes

CMSPAR = \$40000000

CR0 = \$00000000

CR1 = \$0000200

CR2 = \$0000400

CR3 = \$0000600

CRDLY = \$0000600

CREAD = \$0000080

CRTSCTS = \$80000000

CS5 = \$00000000

CS6 = \$00000010

CS7 = \$0000020

CS8 = \$0000030

CSIGNAL = \$000000ff

Clone (1048) option: Signal mask to be sent at exit

CSIZE = \$0000030

CSTOPB = \$0000040

ECHO = \$0000008

ECHOCTL = \$0000200

ECHOE = \$0000010

ECHOK = \$0000020

ECHOKE = \$0000800

ECHONL = \$0000040

ECHOPRT = \$0000400

EXTA = B19200

EXTB = B38400

FF0 = \$0000000

FF1 = \$0008000

FFDLY = \$0008000

FIOASYNC = \$5452

FIOCLEX = \$5451

FIONBIO = \$5421

FIONCLEX = \$5450

FIONREAD = \$541B

FLUSHO = \$0001000

fs\_ext = \$137d

File system type (FSStat (1069)): (ext) Extended

fs\_ext2 = \$ef53

File system type (FSStat (1069)): (ext2) Second extended

fs\_iso = \$9660

File system type (FSStat (1069)): ISO 9660

fs\_minix = \$137f

File system type (FSStat (1069)): Minix

fs\_minix\_30 = \$138f

File system type (FSStat (1069)): Minix 3.0

fs\_minux\_V2 = \$2468

File system type (FSStat (1069)): Minix V2

fs\_msdos = \$4d44

File system type (FSStat (1069)): MSDOS (FAT)

fs\_nfs = \$6969

File system type (FSStat (1069)): NFS

fs\_old\_ext2 = \$ef51

File system type (FSStat (1069)): (ext2) Old second extended

fs\_proc = \$9fa0

File system type (FSStat (1069)): PROC fs

fs\_xia = \$012FD16D

File system type (FSStat (1069)): XIA

F\_GetFd = 1

FCntl (1060) command: Get close-on-exec flag

F\_GetFl = 3

FCntl (1060) command: Get filedescriptor flags

F\_GetLk = 5

FCntl (1060) command: Get lock

F\_GetOwn = 9

FCntl (1060) command: get owner of filedescriptor events

F\_OK = 0

Access (1041) call test: file exists.

F\_SetFd = 2

FCntl (1060) command: Set close-on-exec flag

F\_SetFl = 4

FCntl (1060) command: Set filedescriptor flags

F\_SetLk = 6

FCntl (1060) command: Set lock

F\_SetLkW = 7

FCntl (1060) command: Test lock

F\_SetOwn = 8

FCntl (1060) command: Set owner of filedescriptor events

HUPCL = \$0000400

ICANON = \$0000002



ICRNL = \$0000100

IEXTEN = \$0008000

IGNBRK = \$0000001

IGNCR = \$0000080

IGNPAR = \$0000004

IMAXBEL = \$0002000

INLCR = \$0000040

INPCK = \$0000010

IOctl\_TCGETS = \$5401

**IOCTL call number: get Terminal Control settings**

ISIG = \$0000001

ISTRIP = \$0000020

IUCLC = \$0000200

IXANY = \$0000800

IXOFF = \$0001000

IXON = \$0000400

LOCK\_EX = 2

**Flock (1066) Exclusive lock**

LOCK\_NB = 4

**Flock (1066) Non-blocking operation**

LOCK\_SH = 1

FLock (1066) Shared lock

LOCK\_UN = 8

FLock (1066) unlock

MAP\_ANONYMOUS = \$20

MMap (1086) map type: Don't use a file

MAP\_DENYWRITE = \$800

MMap (1086) option: Ignored.

MAP\_EXECUTABLE = \$1000

MMap (1086) option: Ignored.

MAP\_FIXED = \$10

MMap (1086) map type: Interpret addr exactly

MAP\_GROWSDOWN = \$100

MMap (1086) option: Memory grows downward (like a stack)

MAP\_LOCKED = \$2000

MMap (1086) option: lock the pages in memory.

MAP\_NORESERVE = \$4000

MMap (1086) option: Do not reserve swap pages for this memory.

MAP\_PRIVATE = 2

MMap (1086) map type: Changes are private

MAP\_SHARED = \$1

MMap (1086) map type: Share changes

MAP\_TYPE = \$f

MMap (1086) map type: Bitmask for type of mapping

MINSIGSTKSZ = 2048

NCC = 8

Number of control characters in termio (1037) record.

NCCS = 32

Number of control characters in termios (1037) record.

NL0 = \$00000000

NL1 = \$00000100

NLDLY = \$00000100

NOFLSH = \$00000080

OCRNL = \$00000008

OFDEL = \$00000080

OFILL = \$00000040

OLCUC = \$00000002

ONLCR = \$00000004

ONLRET = \$00000020

ONOCR = \$00000010

Open\_Accmode = 3

Bitmask to determine access mode in open flags.

Open\_Append = 2shl9

File open mode: Append to file

Open\_Creat = 1shl6

File open mode: Create if file does not yet exist.

Open\_Direct = 4shl12

File open mode: Minimize caching effects

`Open_Directory = 2shl15`

File open mode: File must be directory.

`Open_Excl = 2shl6`

File open mode: Open exclusively

`Open_LargeFile = 1shl15`

File open mode: Open for 64-bit I/O

`Open_NDelay = Open_NonBlock`

File open mode: Alias for `Open_NonBlock` ([1002](#))

`Open_NoCtty = 4shl6`

File open mode: No TTY control.

`Open_NoFollow = 4shl15`

File open mode: Fail if file is symbolic link.

`Open_NonBlock = 4shl9`

File open mode: Open in non-blocking mode

`Open_RdOnly = 0`

File open mode: Read only

`Open_RdWr = 2`

File open mode: Read/Write

`Open_Sync = 1shl12`

File open mode: Write to disc at once

`Open_Trunc = 1shl9`

File open mode: Truncate file to length 0

`Open_WrOnly = 1`

File open mode: Write only

`OPOST = $0000001`

PARENB = \$0000100

PARMRK = \$0000008

PARODD = \$0000200

PENDIN = \$0004000

Prio\_PGrp = 1

Get/set process group priority

Prio\_Process = 0

Get/Set process priority

Prio\_User = 2

Get/set user priority

PROT\_EXEC = \$4

MMap (1086) memory access: page can be executed

PROT\_NONE = \$0

MMap (1086) memory access: page can not be accessed

PROT\_READ = \$1

MMap (1086) memory access: page can be read

PROT\_WRITE = \$2

MMap (1086) memory access: page can be written

P\_IN = 1

Input file descriptor of pipe pair.

P\_OUT = 2

Output file descriptor of pipe pair.

R\_OK = 4

Access (1041) call test: read allowed

SA\_INTERRUPT = \$20000000

Sigaction options: ?

SA\_NOCLDSTOP = 1

Sigaction options: Do not receive notification when child processes stop

SA\_NOMASK = \$40000000

Sigaction options: Do not prevent the signal from being received when it is handled.

SA\_ONESHOT = \$80000000

Sigaction options: Restore the signal action to the default state.

SA\_ONSTACK = SA\_STACK

Socket option

SA\_RESTART = \$10000000

Sigaction options: Provide behaviour compatible with BSD signal semantics

SA\_SHIRQ = \$04000000

Sigaction options: ?

SA\_STACK = \$08000000

Sigaction options: Call the signal handler on an alternate signal stack.

Seek\_Cur = 1

Seek option: Set position relative to current position.

Seek\_End = 2

Seek option: Set position relative to end of file.

Seek\_set = 0

Seek option: Set absolute position.

SIGABRT = 6

Signal: ABRT (Abort)

SIGALRM = 14

Signal: ALRM (Alarm clock)

SIGBUS = 7

Signal: BUS (bus error)

SIGCHLD = 17

Signal: CHLD (child status changed)

SIGCONT = 18

Signal: CONT (Continue)

SIGFPE = 8

Signal: FPE (Floating point error)

SIGHUP = 1

Signal: HUP (Hangup)

SIGILL = 4

Signal: ILL (Illegal instruction)

SIGINT = 2

Signal: INT (Interrupt)

SIGIO = 29

Signal: IO (I/O operation possible)

SIGIOT = 6

Signal: IOT (IOT trap)

SIGKILL = 9

Signal: KILL (unblockable)

SIGPIPE = 13

Signal: PIPE (Broken pipe)

SIGPOLL = SIGIO

Signal: POLL (Pollable event)

SIGPROF = 27

Signal: PROF (Profiling alarm)

SIGPWR = 30

Signal: PWR (power failure restart)

SIGQUIT = 3

Signal: QUIT

SIGSEGV = 11

Signal: SEGV (Segmentation violation)

SIGSTKFLT = 16

Signal: STKFLT (Stack Fault)

SIGSTKSZ = 8192

Signal Stack size error

SIGSTOP = 19

Signal: STOP (Stop, unblockable)

SIGTerm = 15

Signal: TERM (Terminate)

SIGTRAP = 5

Signal: TRAP (Trace trap)

SIGTSTP = 20

Signal: TSTP (keyboard stop)

SIGTTIN = 21

Signal: TTIN (Terminal input, background)

SIGTTOU = 22

Signal: TTOU (Terminal output, background)

SIGUNUSED = 31

Signal: Unused

SIGURG = 23

Signal: URG (Socket urgent condition)



`SIGUSR1 = 10`

Signal: USR1 (User-defined signal 1)

`SIGUSR2 = 12`

Signal: USR2 (User-defined signal 2)

`SIGVTALRM = 26`

Signal: VTALRM (Virtual alarm clock)

`SIGWINCH = 28`

Signal: WINCH (Window/Terminal size change)

`SIGXCPU = 24`

Signal: XCPU (CPU limit exceeded)

`SIGXFSZ = 25`

Signal: XFSZ (File size limit exceeded)

`SIG_BLOCK = 0`

Sigprocmask flags: Add signals to the set of blocked signals.

`SIG_DFL = 0`

Signal handler: Default signal handler

`SIG_ERR = -1`

Signal handler: error

`SIG_IGN = 1`

Signal handler: Ignore signal

`SIG_SETMASK = 2`

Sigprocmask flags: Set of blocked signals is given.

`SIG_UNBLOCK = 1`

Sigprocmask flags: Remove signals from the set set of blocked signals.

`SI_PAD_SIZE = ((128/sizeof(longint))-3)`

Signal information record pad bytes size. Do not use.

SS\_DISABLE = 2

Socket options

SS\_ONSTACK = 1

Socket options

STAT\_IFBLK = \$6000

File (stat (1035) record) mode: Block device

STAT\_IFCHR = \$2000

File (stat (1035) record) mode: Character device

STAT\_IFDIR = \$4000

File (stat (1035) record) mode: Directory

STAT\_IFIFO = \$1000

File (stat (1035) record) mode: FIFO

STAT\_IFLNK = \$a000

File (stat (1035) record) mode: Link

STAT\_IFMT = \$f000

File (stat (1035) record) mode: File type bit mask

STAT\_IFREG = \$8000

File (stat (1035) record) mode: Regular file

STAT\_IFSOCK = \$c000

File (stat (1035) record) mode: Socket

STAT\_IRGRP = STAT\_IROTH shl3

File (stat (1035) record) mode: Group read permission

STAT\_IROTH = \$4

File (stat (1035) record) mode: Other read permission

STAT\_IRUSR = STAT\_IROTH shl6

File (stat (1035) record) mode: Owner read permission

`STAT_IRWXG = STAT_IRWXO shl3`

File (stat (1035) record) mode: Group permission bits mask

`STAT_IRWXO = $7`

File (stat (1035) record) mode: Other permission bits mask

`STAT_IRWXU = STAT_IRWXO shl6`

File (stat (1035) record) mode: Owner permission bits mask

`STAT_ISGID = $0400`

File (stat (1035) record) mode: GID bit set

`STAT_ISUID = $0800`

File (stat (1035) record) mode: UID bit set

`STAT_ISVTX = $0200`

File (stat (1035) record) mode: Sticky bit set

`STAT_IWGRP = STAT_IWOTH shl3`

File (stat (1035) record) mode: Group write permission

`STAT_IWOTH = $2`

File (stat (1035) record) mode: Other write permission

`STAT_IWUSR = STAT_IWOTH shl6`

File (stat (1035) record) mode: Owner write permission

`STAT_IXGRP = STAT_IXOTH shl3`

File (stat (1035) record) mode: Others execute permission

`STAT_IXOTH = $1`

File (stat (1035) record) mode: Others execute permission

`STAT_IXUSR = STAT_IXOTH shl6`

File (stat (1035) record) mode: Others execute permission

`syscall_nr_access = 33`

```
syscall_nr_acct = 51

syscall_nr_adjtimex = 124

syscall_nr_afs_syscall = 137

syscall_nr_alarm = 27

syscall_nr_bdflush = 134

syscall_nr_break = 17

syscall_nr_brk = 45

syscall_nr_chdir = 12

syscall_nr_chmod = 15

syscall_nr_chown = 16

syscall_nr_chroot = 61

syscall_nr_clone = 120

syscall_nr_close = 6

syscall_nr_creat = 8

syscall_nr_create_module = 127

syscall_nr_delete_module = 129

syscall_nr_dup = 41

syscall_nr_dup2 = 63

syscall_nr_execve = 11
```

```
syscall_nr_exit = 1

syscall_nr_fchdir = 133

syscall_nr_fchmod = 94

syscall_nr_fchown = 95

syscall_nr_fcntl = 55

syscall_nr_fdatasync = 148

syscall_nr_flock = 143

syscall_nr_fork = 2

syscall_nr_fstat = 108

syscall_nr_fstatfs = 100

syscall_nr_fsync = 118

syscall_nr_ftime = 35

syscall_nr_ftruncate = 93

syscall_nr_getdents = 141

syscall_nr_getegid = 50

syscall_nr_geteuid = 49

syscall_nr_getgid = 47

syscall_nr_getgroups = 80

syscall_nr_getitimer = 105
```

syscall\_nr\_getpgid = 132

syscall\_nr\_getpgrp = 65

syscall\_nr\_getpid = 20

syscall\_nr\_getppid = 64

syscall\_nr\_getpriority = 96

syscall\_nr\_getresuid = 165

syscall\_nr\_getrlimit = 76

syscall\_nr\_getrusage = 77

syscall\_nr\_getsid = 147

syscall\_nr\_gettimeofday = 78

syscall\_nr\_getuid = 24

syscall\_nr\_get\_kernel\_syms = 130

syscall\_nr\_gtty = 32

syscall\_nr\_idle = 112

syscall\_nr\_init\_module = 128

syscall\_nr\_ioctl = 54

syscall\_nr\_ioperm = 101

syscall\_nr\_iopl = 110

syscall\_nr\_ipc = 117

`syscall_nr_kill` = 37

`syscall_nr_link` = 9

`syscall_nr_lock` = 53

`syscall_nr_lseek` = 19

`syscall_nr_lstat` = 107

`syscall_nr_mkdir` = 39

`syscall_nr_mknod` = 14

`syscall_nr_mlock` = 150

`syscall_nr_mlockall` = 152

`syscall_nr_mmap` = 90

`syscall_nr_modify_ldt` = 123

`syscall_nr_mount` = 21

`syscall_nr_mprotect` = 125

`syscall_nr_mpx` = 56

`syscall_nr_mremap` = 163

`syscall_nr_msync` = 144

`syscall_nr_munlock` = 151

`syscall_nr_munlockall` = 153

`syscall_nr_munmap` = 91

syscall\_nr\_nanosleep = 162

syscall\_nr\_nice = 34

syscall\_nr\_oldfstat = 28

syscall\_nr\_oldlstat = 84

syscall\_nr\_oldolduname = 59

syscall\_nr\_oldstat = 18

syscall\_nr\_olduname = 109

syscall\_nr\_open = 5

syscall\_nr\_pause = 29

syscall\_nr\_personality = 136

syscall\_nr\_phys = 52

syscall\_nr\_pipe = 42

syscall\_nr\_poll = 168

syscall\_nr\_prof = 44

syscall\_nr\_profil = 98

syscall\_nr\_ptrace = 26

syscall\_nr\_query\_module = 167

syscall\_nr\_quotactl = 131

syscall\_nr\_read = 3



syscall\_nr\_readdir = 89

syscall\_nr\_readlink = 85

syscall\_nr\_readv = 145

syscall\_nr\_reboot = 88

syscall\_nr\_rename = 38

syscall\_nr\_rmdir = 40

syscall\_nr\_sched\_getparam = 155

syscall\_nr\_sched\_getscheduler = 157

syscall\_nr\_sched\_get\_priority\_max = 159

syscall\_nr\_sched\_get\_priority\_min = 160

syscall\_nr\_sched\_rr\_get\_interval = 161

syscall\_nr\_sched\_setparam = 154

syscall\_nr\_sched\_setscheduler = 156

syscall\_nr\_sched\_yield = 158

syscall\_nr\_select = 82

syscall\_nr\_setdomainname = 121

syscall\_nr\_setfsgid = 139

syscall\_nr\_setfsuid = 138

syscall\_nr\_setgid = 46

syscall\_nr\_setgroups = 81

syscall\_nr\_sethostname = 74

syscall\_nr\_setitimer = 104

syscall\_nr\_setpgid = 57

syscall\_nr\_setpriority = 97

syscall\_nr\_setregid = 71

syscall\_nr\_setresuid = 164

syscall\_nr\_setreuid = 70

syscall\_nr\_setrlimit = 75

syscall\_nr\_setsid = 66

syscall\_nr\_settimeofday = 79

syscall\_nr\_setuid = 23

syscall\_nr\_setup = 0

syscall\_nr\_sgetmask = 68

syscall\_nr\_sigaction = 67

syscall\_nr\_sigaltstack = 186

syscall\_nr\_signal = 48

syscall\_nr\_sigpending = 73

syscall\_nr\_sigprocmask = 126

`syscall_nr_sigreturn = 119`

`syscall_nr_sigsuspend = 72`

`syscall_nr_socketcall = 102`

`syscall_nr_ssetmask = 69`

`syscall_nr_stat = 106`

`syscall_nr_statfs = 99`

`syscall_nr_stime = 25`

`syscall_nr_stty = 31`

`syscall_nr_swapoff = 115`

`syscall_nr_swapon = 87`

`syscall_nr_symlink = 83`

`syscall_nr_sync = 36`

`syscall_nr_sysfs = 135`

`syscall_nr_sysinfo = 116`

`syscall_nr_syslog = 103`

`syscall_nr_time = 13`

`syscall_nr_times = 43`

`syscall_nr_truncate = 92`

`syscall_nr_ulimit = 58`

syscall\_nr\_umask = 60

syscall\_nr\_umount = 22

syscall\_nr\_uname = 122

syscall\_nr\_unlink = 10

syscall\_nr\_uselib = 86

syscall\_nr\_ustat = 62

syscall\_nr\_utime = 30

syscall\_nr\_vhangup = 111

syscall\_nr\_vm86 = 166

syscall\_nr\_vm86old = 113

syscall\_nr\_wait4 = 114

syscall\_nr\_waitpid = 7

syscall\_nr\_write = 4

syscall\_nr\_writev = 146

syscall\_nr\_\_llseek = 140

syscall\_nr\_\_newselect = 142

syscall\_nr\_\_sysctl = 149

Sys\_E2BIG = 7

Sys\_EACCES = 13

Sys\_EADDRINUSE = 98

Sys\_EADDRNOTAVAIL = 99

Sys\_EADV = 68

Sys\_EAFNOSUPPORT = 97

Sys\_EAGAIN = 11

Sys\_EALREADY = 114

Sys\_EBADE = 52

Sys\_EBADF = 9

Sys\_EBADFD = 77

Sys\_EBADMSG = 74

Sys\_EBADR = 53

Sys\_EBADRQC = 56

Sys\_EBADSLT = 57

Sys\_EBFONT = 59

Sys\_EBUSY = 16

Sys\_ECHILD = 10

Sys\_ECHRNG = 44

Sys\_ECOMM = 70

Sys\_ECONNABORTED = 103

Sys\_ECONNREFUSED = 111

Sys\_ECONNRESET = 104

Sys\_EDEADLK = 35

Sys\_EDEADLOCK = 58

Sys\_EDESTADDRREQ = 89

Sys\_EDOM = 33

Sys\_EDOTDOT = 73

Sys\_EDQUOT = 122

Sys\_EEXIST = 17

Sys\_EFAULT = 14

Sys\_EFBIG = 27

Sys\_EHOSTDOWN = 112

Sys\_EHOSTUNREACH = 113

Sys\_EIDRM = 43

Sys\_EILSEQ = 84

Sys\_EINPROGRESS = 115

Sys\_EINTR = 4

Sys\_EINVAL = 22

Sys\_EIO = 5

Sys\_EISCONN = 106

Sys\_EISDIR = 21

Sys\_EISNAM = 120

Sys\_EL2HLT = 51

Sys\_EL2NSYNC = 45

Sys\_EL3HLT = 46

Sys\_EL3RST = 47

Sys\_ELIBACC = 79

Sys\_ELIBBAD = 80

Sys\_ELIBEXEC = 83

Sys\_ELIBMAX = 82

Sys\_ELIBSCN = 81

Sys\_ELN RNG = 48

Sys\_ELOOP = 40

Sys\_EMFILE = 24

Sys\_EMLINK = 31

Sys\_MSGSIZE = 90

Sys\_EMULTIHOP = 72

Sys\_ENAMETOOLONG = 36

Sys\_ENAVAIL = 119

Sys\_ENETDOWN = 100

Sys\_ENETRESET = 102

Sys\_ENETUNREACH = 101

Sys\_ENFILE = 23

Sys\_ENOANO = 55

Sys\_ENOBUFS = 105

Sys\_ENOCSI = 50

Sys\_ENODATA = 61

Sys\_ENODEV = 19

Sys\_ENOENT = 2

Sys\_ENOEXEC = 8

Sys\_ENOLCK = 37

Sys\_ENOLINK = 67

Sys\_ENOMEM = 12

Sys\_ENOMSG = 42

Sys\_ENONET = 64

Sys\_ENOPKG = 65

Sys\_ENOPROTOOPT = 92



Sys\_ENOSPC = 28

Sys\_ENOSR = 63

Sys\_ENOSTR = 60

Sys\_ENOSYS = 38

Sys\_ENOTBLK = 15

Sys\_ENOTCONN = 107

Sys\_ENOTDIR = 20

Sys\_ENOTEMPTY = 39

Sys\_ENOTNAM = 118

Sys\_ENOTSOCK = 88

Sys\_ENOTTY = 25

Sys\_ENOTUNIQ = 76

Sys\_ENXIO = 6

Sys\_EOPNOTSUPP = 95

Sys\_EOVERFLOW = 75

Sys\_EPERM = 1

Sys\_EPFNOSUPPORT = 96

Sys\_EPIPE = 32

Sys\_EPROTO = 71

Sys\_EPROTONOSUPPORT = 93

Sys\_EPROTOTYPE = 91

Sys\_ERANGE = 34

Sys\_EREMCHG = 78

Sys\_EREMOTE = 66

Sys\_EREMOTEIO = 121

Sys\_ERESTART = 85

Sys\_EROFS = 30

Sys\_ERROR\_MAX = \$fff

Sys\_ESHUTDOWN = 108

Sys\_ESOCKTNOSUPPORT = 94

Sys\_ESPIPE = 29

Sys\_ESRCH = 3

Sys\_ESRMNT = 69

Sys\_ESTALE = 116

Sys ESTRPIPE = 86

Sys\_ETIME = 62

Sys\_ETIMEDOUT = 110

Sys\_ETOOMANYREFS = 109

Sys\_ETXTBSY = 26

Sys\_EUCLEAN = 117

Sys\_EUNATCH = 49

Sys\_EUSERS = 87

Sys\_EWOULDBLOCK = Sys\_EAGAIN

Sys\_EXDEV = 18

Sys\_EXFULL = 54

TAB0 = \$00000000

TAB1 = \$00008000

TAB2 = \$00010000

TAB3 = \$00018000

TABDLY = \$00018000

TCFLSH = \$540B

TCGETA = \$5405

TCGETS = \$5401

TCIFLUSH = 0

TCIOFF = 2

TCIOFLUSH = 2

TCION = 3

TCOFLUSH = 1

TCOOFF = 0

TCOON = 1

TCSADRAIN = 1

TCSAFLUSH = 2

TCSANOW = 0

TCSBRK = \$5409

TCSBRKP = \$5425

TCSETA = \$5406

TCSETAF = \$5408

TCSETAW = \$5407

TCSETS = \$5402

TCSETSF = \$5404

TCSETSW = \$5403

TCXONC = \$540A

TIOCCONS = \$541D

TIOCEXCL = \$540C

TIOCGETD = \$5424

TIOCGICOUNT = \$545D

TIOCGLOCKTRMIO = \$5456

TIOCGPGRP = \$540F

TIOCGSERIAL = \$541E

TIOCGSOFTCAR = \$5419

TIOCGWINSZ = \$5413

TIOCINQ = FIONREAD

TIOCLINUX = \$541C

TIOCMBIC = \$5417

TIOCMBIS = \$5416

TIOCMGET = \$5415

TIOCMWAIT = \$545C

TIOCMSET = \$5418

TIOCM\_CAR = \$040

TIOCM\_CD = TIOCM\_CAR

TIOCM\_CTS = \$020

TIOCM\_DSR = \$100

TIOCM\_DTR = \$002

TIOCM\_LE = \$001

TIOCM\_OUT1 = \$2000

TIOCM\_OUT2 = \$4000

TIOCM\_RI = TIOCM\_RNG

TIOCM\_RNG = \$080

TIOCM\_RTS = \$004

TIOCM\_SR = \$010

TIOCM\_ST = \$008

TIOCNOTTY = \$5422

TIOCNXCL = \$540D

TIOCOUTQ = \$5411

TIOCPKT = \$5420

TIOCPKT\_DATA = 0

TIOCPKT\_DOSTOP = 32

TIOCPKT\_FLUSHREAD = 1

TIOCPKT\_FLUSHWRITE = 2

TIOCPKT\_NOSTOP = 16

TIOCPKT\_START = 8

TIOCPKT\_STOP = 4

TIOCSCTTY = \$540E

TIOCSERCONFIG = \$5453

TIOCSERGETLSR = \$5459

TIOCSERGETMULTI = \$545A

TIOCSERGSTRUCT = \$5458

TIOCSERGWILD = \$5454

TIOCSERSETMULTI = \$545B

TIOCSERSWILD = \$5455

TIOCSETD = \$5423

TIOCSLCKTRMIOS = \$5457

TIOCSPPGRP = \$5410

TIOCSSERIAL = \$541F

TIOCSSOFTCAR = \$541A

TIOCSTI = \$5412

TIOCSWINSZ = \$5414

TIOCTTYGSTRUCT = \$5426

TOSTOP = \$0000100

VDISCARD = 13

VEOF = 4

VEOL = 11

VEOL2 = 16

VERASE = 2

VINTR = 0

VKILL = 3

VLNEXT = 15

VMIN = 6

VQUIT = 1

VREPRINT = 12

VSTART = 8

VSTOP = 9

VSUSP = 10

VSWTC = 7

VT0 = \$00000000

VT1 = \$0004000

VDLY = \$0004000

VTIME = 5

VWERASE = 14

Wait\_Any = -1

**WaitPID (115):** Wait on any process

Wait\_Clone = \$80000000

**WaitPID (115):** Wait on clone processes only.



Wait\_MyPGRP = 0

WaitPID (1115): Wait processes from current process group

Wait\_NoHang = 1

WaitPID (1115): Do not wait

Wait\_UnTraced = 2

WaitPID (1115): Also report stopped but untraced processes

WNOHANG = \$1

Waitpid (1115) option: Do not wait for processes to terminate.

WUNTRACED = \$2

Waitpid (1115) option: Also report children which were stopped but not yet reported

W\_OK = 2

Access (1041) call test: write allowed

XCASE = \$00000004

XTABS = \$0001800

X\_OK = 1

Access (1041) call test: execute allowed

\_\_WCLONE = \$80000000

Waitpid option: Wait for clone children only

### 31.11.2 Types

ComStr =

Command-line string type.

dev\_t = Word

Device descriptor type

```
dirent = packed record
  ino : LongInt;
  off : LongInt;
  reclen : Word;
  name : Array[0..255] of Char;
end
```

Record used in the ReadDir (1093) function to return files in a directory.

DirStr =

Filename directory part string type.

ExtStr =

Filename extension part string type.

fdSet = Array[0..7] of LongInt

Array containing file descriptor bitmask for the Select (1095) call.

NameStr =

Filename name part string type.

PathStr =

Filename path part string type.

PDir = ^TDir

Pointer to TDir (1036) record

pdirent = ^dirent

Pointer to Dirent (1032) record.

pfdsset = ^fdSet

Pointer to FDSet (1065) array.

pfpstate = ^tfpstate

Pointer to tfpstate (1037) record.

pglob = ^tglob

Pointer to TGlob (1037) record.

PSigActionRec = ^SigActionRec

Pointer to SigActionRec (1034) record.

PSigAltStack = ^SigAltStack

Pointer to SigAltStack (1034) record

PSigContextRec = ^SigContextRec

Pointer to SigContextRec (1034) record

PSignalHandler = ^SignalHandler

Pointer to SignalHandler (1035) type.

PSignalRestorer = ^SignalRestorer

Pointer to SignalRestorer (1035) type

PSigSet = ^SigSet

Pointer to signal set.

pstack\_t = ^stack\_t

Pointer to stack\_t (1035) record

PStat = ^Stat

Pointer to Stat (1035) record.

PStatFS = ^Statfs

Pointer to StatFS (1036) record.

PSysCallRegs = ^SysCallRegs

Pointer to SysCallRegs (1036) record.

PSysInfo = ^TSysinfo

Pointer to TSysInfo (1039) record.

ptimeval = ^timeval

Pointer to TTimeVal (1039) record

ptimezone = ^timezone

Pointer to TimeZone (1038) record.

PUTimeBuf = ^UTimeBuf

Pointer to UTimeBuf (1040) record

PUTSName = ^utsname

Pointer to UTSName (1040) record.

```

SigActionRec = packed record
  Handler : record
  end;
  Sa_Mask : SigSet;
  Sa_Flags : LongInt;
  Sa_restorer : SignalRestorer;
end

```

Record used in `SigAction` ([1099](#)) call.

```

SigAltStack = record
  ss_sp : pointer;
  ss_flags : LongInt;
  ss_size : Size_T;
end

```

Alternate stack registers record

```

SigContextRec = record
  gs : Word;
  __gsh : Word;
  fs : Word;
  __fsh : Word;
  es : Word;
  __esh : Word;
  ds : Word;
  __dsh : Word;
  edi : cardinal;
  esi : cardinal;
  ebp : cardinal;
  esp : cardinal;
  ebx : cardinal;
  edx : cardinal;
  ecx : cardinal;
  eax : cardinal;
  trapno : cardinal;
  err : cardinal;
  eip : cardinal;
  cs : Word;
  __csh : Word;
  eflags : cardinal;
  esp_at_signal : cardinal;
  ss : Word;
  __ssh : Word;
  fpstate : pfpstate;
  oldmask : cardinal;
  cr2 : cardinal;
end

```

The above records contain information about the processor state and process state at the moment a signal is sent to your program.

SignalHandler = procedure(Sig: LongInt) of object

Function prototype for the Signal ([1100](#)) call.

SignalRestorer = procedure of object

**Signal restorer function prototype**

SigSet = LongInt

**Signal set type**

Size\_T = cardinal

**Size type**

stack\_t = SigAltStack

**Alias for SigAltStack ([1034](#)) type**

```
Stat = packed record
  dev : dev_t;
  pad1 : Word;
  ino : LongInt;
  mode : Word;
  nlink : Word;
  uid : Word;
  gid : Word;
  rdev : dev_t;
  pad2 : Word;
  size : LongInt;
  blksize : LongInt;
  blocks : LongInt;
  atime : LongInt;
  unused1 : LongInt;
  mtime : LongInt;
  unused2 : LongInt;
  ctime : LongInt;
  unused3 : LongInt;
  unused4 : LongInt;
  unused5 : LongInt;
end
```

**Record describing an inode (file) in the fstat ([1070](#)) call.**

```
Statfs = packed record
  fstype : LongInt;
  bsize : LongInt;
  blocks : LongInt;
  bfree : LongInt;
  bavail : LongInt;
```

```

files : LongInt;
ffree : LongInt;
fsid : LongInt;
namelen : LongInt;
spare : Array[0..6] of LongInt;
end

```

Record describing a file system in the fsstat (1069) call.

```

SysCallRegs = record
  reg1 : LongInt;
  reg2 : LongInt;
  reg3 : LongInt;
  reg4 : LongInt;
  reg5 : LongInt;
  reg6 : LongInt;
end

```

Register describing system calls.

```

TCloneFunc = function(args: pointer) : LongInt of object

```

Clone function prototype.

```

TDir = packed record
  fd : Integer;
  loc : LongInt;
  size : Integer;
  buf : pdirent;
  nextoff : LongInt;
  dd_max : Integer;
  lock : pointer;
end

```

Record used in OpenDir (1090) and ReadDir (1093) calls

```

TDirEnt = dirent

```

Alias for DirEnt (1032) record

```

Termio = packed record
  c_iflag : Word;
  c_oflag : Word;
  c_cflag : Word;
  c_lflag : Word;
  c_line : Word;
  c_cc : Array[0..NCC-1] of Char;
end

```

Terminal I/O description record (small)

```
Termios = record
  c_iflag : Cardinal;
  c_oflag : Cardinal;
  c_cflag : Cardinal;
  c_lflag : Cardinal;
  c_line : Char;
  c_cc : Array[0..NCCS-1] of Byte;
  c_ispeed : LongInt;
  c_ospeed : LongInt;
end
```

Terminal I/O description record

```
TFDSet = fdSet
```

Alias for FDSets (1065) type.

```
tfpreg = record
  significand : Array[0..3] of Word;
  exponent : Word;
end
```

Record describing floating point register in signal handler.

```
tfpstate = record
  cw : cardinal;
  sw : cardinal;
  tag : cardinal;
  ipoff : cardinal;
  cssel : cardinal;
  dataoff : cardinal;
  datasel : cardinal;
  st : Array[0..7] of tfpreg;
  status : cardinal;
end
```

Record describing floating point unit in signal handler.

```
tglob = record
  name : pchar;
  next : pglob;
end
```

Record containing one entry in the result of Glob (1080)

```
timespec = packed record
```

```

    tv_sec : LongInt;
    tv_nsec : LongInt;
end

```

Time interval for the NanoSleep ([1088](#)) function.

```

timeval = packed record
    sec : LongInt;
    usec : LongInt;
end

```

Record specifying a time interval.

```

timezone = packed record
    minuteswest : LongInt;
    dsttime : LongInt;
end

```

Record describing a timezone

```

tmapargs = record
    address : LongInt;
    size : LongInt;
    prot : LongInt;
    flags : LongInt;
    fd : LongInt;
    offset : LongInt;
end

```

Record containing mmap args.

```

Tpipe = Array[1..2] of LongInt

```

Array describing a pipe pair of filedescriptors.

```

TSigAction = procedure(Sig: LongInt; SigContext: SigContextRec) of object

```

Function prototype for SigAction ([1099](#)) call.

```

TStat = Stat

```

Alias for Stat ([1035](#)) record.

```

TStatFS = Statfs

```

Alias for StatFS ([1036](#)) type.

```

TSysCallRegs = SysCallRegs

```



Alias for SysCallRegs (1036) record

```
TSysinfo = packed record
  uptime : LongInt;
  loads : Array[1..3] of LongInt;
  totalram : LongInt;
  freeram : LongInt;
  sharedram : LongInt;
  bufferram : LongInt;
  totalswap : LongInt;
  freeswap : LongInt;
  procs : Integer;
  s : String;
end
```

Record with system information, used by the SysInfo (1105) call.

```
TTermio = Termio
```

Alias for TermIO (1037) record

```
TTermios = Termios
```

Alias for Termios (1037) record.

```
TTimeVal = timeval
```

Alias for TimeVal (1038) record.

```
TTimeZone = timezone
```

Alias for TimeZone (1038) record.

```
TUTimeBuf = UTimeBuf
```

Alias for UTimBuf (1040) record.

```
TUTSName = utsname
```

Alias for UTSName (1040) record.

```
TWinSize = winsize
```

Alias for WinSize (1040) record.

```
UTimBuf = packed record
  actime : LongInt;
  modtime : LongInt;
end
```

Record used in Utime (1114) to set file access and modification times.

```
UtimeBuf = UtimeBuf
```

Alias for UtimeBuf (1040) record.

```
utsname = packed record
  sysname : Array[0..64] of Char;
  nodename : Array[0..64] of Char;
  release : Array[0..64] of Char;
  version : Array[0..64] of Char;
  machine : Array[0..64] of Char;
  domainname : Array[0..64] of Char;
end
```

The elements of this record are null-terminated C style strings, you cannot access them directly.

```
winsize = packed record
  ws_row : Word;
  ws_col : Word;
  ws_xpixel : Word;
  ws_ypixel : Word;
end
```

Record describing terminal window size.

### 31.11.3 Variables

```
ErrNo : LongInt
```

Error number of last operation.

```
LinuxError : LongInt
```

Linuxerror is the variable in which the procedures in the linux unit report errors.

```
tzdaylight : Boolean
```

Indicates whether daylight savings time is active.

```
tzname : Array[boolean] of pchar
```

Timezone name.

```
tzseconds : LongInt
```

Seconds west of GMT

## 31.12 Procedures and functions

### 31.12.1 Access

Synopsis: Check file access

Declaration: `function Access (Path: PathStr; mode: Integer) : Boolean`

Visibility: default

Description: `Access` tests user's access rights on the specified file. `Mode` is a mask existing of one or more of the following:

**R\_OK**User has read rights.

**W\_OK**User has write rights.

**X\_OK**User has execute rights.

**F\_OK**File exists.

The test is done with the real user ID, instead of the effective user ID. If access is denied, or an error occurred, `False` is returned.

Errors: `LinuxError` is used to report errors:

**sys\_eaccess**The requested access is denied, either to the file or one of the directories in its path.

**sys\_einval**Mode was incorrect.

**sys\_enoent**A directory component in `Path` doesn't exist or is a dangling symbolic link.

**sys\_enotdir**A directory component in `Path` is not a directory.

**sys\_enomem**Insufficient kernel memory.

**sys\_eloop**`Path` has a circular symbolic link.

See also: `Chown` ([1047](#)), `Chmod` ([1046](#))

**Listing:** `./olinuxex/ex26.pp`

---

**Program** `Example26`;

*{ Program to demonstrate the Access function. }*

**Uses** `oldlinux`;

**begin**

**if** `Access ( '/etc/passwd', W_OK )` **then**

**begin**

**Writeln** ( 'Better check your system.' );

**Writeln** ( 'I can write to the /etc/passwd file !' );

**end**;

**end.**

---

### 31.12.2 Alarm

**Synopsis:** Schedule an alarm signal to be delivered

**Declaration:** `function Alarm(Sec: LongInt) : LongInt`

**Visibility:** default

**Description:** `Alarm` schedules an alarm signal to be delivered to your process in `Sec` seconds. When `Sec` seconds have elapsed, Linux will send a `SIGALRM` signal to the current process. If `Sec` is zero, then no new alarm will be set. Whatever the value of `Sec`, any previous alarm is cancelled.

The function returns the number of seconds till the previously scheduled alarm was due to be delivered, or zero if there was none.

See also: `SigAction` ([1099](#))

**Listing:** `./olinuxex/ex59.pp`

**Program** `Example59`;

*{ Program to demonstrate the Alarm function. }*

**Uses** `oldlinux`;

**Procedure** `AlarmHandler(Sig : longint); cdecl`;

**begin**

**Writeln** ( 'Got to alarm handler' );  
**end**;

**begin**

**Writeln** ( 'Setting alarm handler' );  
    **Signal** (SIGALRM, @AlarmHandler);  
    **Writeln** ( 'Scheduling Alarm in 10 seconds' );  
    **Alarm** (10);  
    **Writeln** ( 'Pausing' );  
    **Pause**;  
    **Writeln** ( 'Pause returned' );  
**end**.

### 31.12.3 AssignPipe

**Synopsis:** Create a set of pipe file handlers

**Declaration:** `function AssignPipe(var pipe_in: LongInt; var pipe_out: LongInt) : Boolean`

`function AssignPipe(var pipe_in: text; var pipe_out: text) : Boolean`  
`function AssignPipe(var pipe_in: File; var pipe_out: File) : Boolean`

**Visibility:** default

**Description:** `AssignPipe` creates a pipe, i.e. two file objects, one for input, one for output. What is written to `Pipe_out`, can be read from `Pipe_in`.

This call is overloaded. The in and out pipe can take three forms: an typed or untyped file, a text file or a file descriptor.

If a text file is passed then reading and writing from/to the pipe can be done through the usual `Readln(Pipe_in, ...)` and `Writeln(Pipe_out, ...)` procedures.

The function returns `True` if everything went successfully, `False` otherwise.

Errors: In case the function fails and returns `False`, `LinuxError` is used to report errors:

`sys_enfile` Too many file descriptors for this process.

`sys_enfile` The system file table is full.

See also: `POpen` ([1092](#)), `MkFifo` ([1086](#))

**Listing:** `./olinuxex/ex36.pp`

---

**Program** `Example36`;

*{ Program to demonstrate the AssignPipe function. }*

**Uses** `oldlinux`;

**Var** `pipi, pipo` : `Text`;  
       `s` : **String**;

**begin**

```

  Writeln ( 'Assigning Pipes.' );
  If Not assignpipe(pipi, pipo) then
    Writeln('Error assigning pipes !', LinuxError);
  Writeln ( 'Writing to pipe, and flushing.' );
  Writeln ( pipo, 'This is a textstring' ); close(pipo);
  Writeln ( 'Reading from pipe.' );
  While not eof(pipo) do
    begin
      Readln ( pipi, s );
      Writeln ( 'Read from pipe : ', s );
    end;
  close ( pipi );
  writeln ( 'Closed pipes.' );
  writeln

```

**end.**

---

### 31.12.4 AssignStream

**Synopsis:** Assign stream for in and output to a program

**Declaration:**

```

function AssignStream(var StreamIn: text; var Streamout: text;
                     const Prog: String) : LongInt
function AssignStream(var StreamIn: Text; var StreamOut: Text;
                     var StreamErr: Text; const prog: String) : LongInt

```

**Visibility:** `default`

**Description:** `AssignStream` creates a 2 or 3 pipes, i.e. two (or three) file objects, one for input, one for output, (and one for standard error) the other ends of these pipes are connected to standard input and output (and standard error) of `Prog`. `Prog` is the name of a program (including path) with options, which will be executed.

What is written to `StreamOut`, will go to the standard input of `Prog`. Whatever is written by `Prog` to it's standard output can be read from `StreamIn`. Whatever is written by `Prog` to it's standard error read from `StreamErr`, if present.

Reading and writing happens through the usual `Readln(StreamIn, ...)` and `Writeln (StreamOut, ...)` procedures.

**Remark:** You should *not* use `Reset` or `Rewrite` on a file opened with `POpen`. This will close the file before re-opening it again, thereby closing the connection with the program.

The function returns the process ID of the spawned process, or -1 in case of error.

Errors: In case of error (return value -1) `LinuxError` is used to report errors:

**sys\_emfile** Too many file descriptors for this process.

**sys\_enfile** The system file table is full.

Other errors include the ones by the `fork` and `exec` programs

See also: `AssignPipe` ([1042](#)), `POpen` ([1092](#))

**Listing:** `./olinuxex/ex38.pp`

---

**Program** `Example38`;

*{ Program to demonstrate the AssignStream function. }*

**Uses** `oldlinux`;

**Var** `Si,So : Text;`  
       `S : String;`  
       `i : longint;`

**begin**

**if not** (`paramstr(1) = '-son'`) **then**

**begin**

`Writeln ('Calling son');`

`Assignstream (Si,So, './ex38 -son');`

**if** `linuxerror <> 0` **then**

**begin**

`writeln ('AssignStream failed !');`

`halt(1);`

**end;**

`Writeln ('Speaking to son');`

**For** `i:=1 to 10` **do**

**begin**

`writeln (so, 'Hello son !');`

**if** `ioresult <> 0` **then** `writeln ('Can't speak to son...');`

**end;**

**For** `i:=1 to 3` **do** `writeln (so, 'Hello chap !');`

`close (so);`

**while not eof**(`si`) **do**

**begin**

`readln (si,s);`

`writeln ('Father: Son said : ',S);`

**end;**

`Writeln ('Stopped conversation');`

`Close (Si);`

`Writeln ('Put down phone');`

**end**

**Else**

**begin**

`Writeln ('This is the son');`

**While not eof** (`input`) **do**

**begin**

`readln (s);`

```

    if pos ( 'Hello son ! ',S)<>0 then
      Writeln ( 'Hello Dad ! ')
    else
      writeln ( 'Who are you ? ');
    end;
  close (output);
end
end.

```

---

### 31.12.5 Basename

Synopsis: Return basename of a file

Declaration: `function Basename(const path: PathStr;const suf: PathStr) : PathStr`

Visibility: default

Description: Returns the filename part of Path, stripping off Suf if it exists. The filename part is the whole name if Path contains no slash, or the part of Path after the last slash. The last character of the result is not a slash, unless the directory is the root directory.

Errors: None.

See also: [DirName \(1051\)](#), [FExpand \(1065\)](#)

**Listing:** ./olinuxex/ex48.pp

---

**Program** Example48;

*{ Program to demonstrate the BaseName function. }*

**Uses** oldlinux;

**Var** S : **String**;

**begin**

  S:=FExpand(**Paramstr**(0));

**Writeln** ( 'This program is called : ',Basename(S,' '));

**end.**

---

### 31.12.6 CFMakeRaw

Synopsis: Sets flags in Termios ([1037](#)) record.

Declaration: `procedure CFMakeRaw(var tios: Termios)`

Visibility: default

Description: CFMakeRaw sets the flags in the Termios structure Tios to a state so that the terminal will function in Raw Mode.

For an example, see [TCGetAttr \(1110\)](#).

Errors: None.

See also: [CFSetOSpeed \(1046\)](#), [CFSetISpeed \(1046\)](#)

### 31.12.7 CFSetISpeed

Synopsis: Set input baud rate in Termios ([1037](#)) record

Declaration: `procedure CFSetISpeed(var tios: Termios; speed: Cardinal)`

Visibility: default

Description: `CFSetISpeed` Sets the input baudrate in the `TermIOS` structure `Tios` to `Speed`.

Errors: None.

See also: `CFSetOSpeed` ([1046](#)), `CFMakeRaw` ([1045](#))

### 31.12.8 CFSetOSpeed

Synopsis: Set output baud rate in Termios ([1037](#)) record

Declaration: `procedure CFSetOSpeed(var tios: Termios; speed: Cardinal)`

Visibility: default

Description: `CFSetOSpeed` Sets the output baudrate in the `Termios` structure `Tios` to `Speed`.

Errors: None.

See also: `CFSetISpeed` ([1046](#)), `CFMakeRaw` ([1045](#))

### 31.12.9 Chmod

Synopsis: Change file permission bits

Declaration: `function Chmod(path: PathStr; Newmode: LongInt) : Boolean`

Visibility: default

Description: `Chmod` Sets the Mode bits of the file in `Path` to `NewMode`. `Newmode` can be specified by 'or'-ing the following:

**S\_ISUID**Set user ID on execution.

**S\_ISGID**Set Group ID on execution.

**S\_ISVTX**Set sticky bit.

**S\_IRUSR**Read by owner.

**S\_IWUSR**Write by owner.

**S\_IXUSR**Execute by owner.

**S\_IRGRP**Read by group.

**S\_IWGRP**Write by group.

**S\_IXGRP**Execute by group.

**S\_IROTH**Read by others.

**S\_IWOTH**Write by others.

**S\_IXOTH**Execute by others.

**S\_IRWXO**Read, write, execute by others.

**S\_IRWXG**Read, write, execute by groups.

**S\_IRWXU**Read, write, execute by user.



Errors: Errors are returned in `LinuxError`.

**sys\_eperm**The effective UID doesn't match the ownership of the file, and is not zero. Owner or group were not specified correctly.

**sys\_eaccess**One of the directories in `Path` has no search (=execute) permission.

**sys\_enoent**A directory entry in `Path` does not exist or is a symbolic link pointing to a non-existent directory.

**sys\_enomem**Insufficient kernel memory.

**sys\_erofs**The file is on a read-only filesystem.

**sys\_eloop**`Path` has a reference to a circular symbolic link, i.e. a symbolic link, whose expansion points to itself.

See also: `Chown` ([1047](#)), `Access` ([1041](#)), `Octal` ([1090](#))

**Listing:** `./olinuxex/ex23.pp`

---

**Program** `Example23`;

*{ Program to demonstrate the Chmod function. }*

**Uses** `oldlinux`;

**Var** `F` : `Text`;

**begin**

```
{ Create a file }
Assign (f, 'testex21');
Rewrite (F);
WriteLn (f, '#!/bin/sh');
WriteLn (f, 'echo Some text for this file');
Close (F);
{ Octal() makes the correct number from a
   number that LOOKS octal }
Chmod ('testex21', octal (777));
{ File is now executable }
exec1 ('./testex21');
```

**end.**

---

### 31.12.10 Chown

**Synopsis:** Change owner of file

**Declaration:** `function Chown(path: PathStr; NewUid: LongInt; NewGid: LongInt) : Boolean`

**Visibility:** `default`

**Description:** `Chown` sets the User ID and Group ID of the file in `Path` to `NewUid`, `NewGid` The function returns `True` if the call was succesfull, `False` if the call failed.

Errors: Errors are returned in `LinuxError`.

**sys\_eperm**The effective UID doesn't match the ownership of the file, and is not zero. Owner or group were not specified correctly.

**sys\_eaccess**One of the directories in `Path` has no search (=execute) permission.

**sys\_enoent**A directory entry in `Path` does not exist or is a symbolic link pointing to a non-existent directory.

**sys\_enomem**Insufficient kernel memory.

**sys\_erofs**The file is on a read-only filesystem.

**sys\_eloop**`Path` has a reference to a circular symbolic link, i.e. a symbolic link, whose expansion points to itself.

See also: `Chmod` ([1046](#)), `Access` ([1041](#))

**Listing:** `./olinuxex/ex24.pp`

**Program** `Example24`;

*{ Program to demonstrate the Chown function. }*

**Uses** `oldlinux`;

**Var** `UID,GID : Longint`;  
       `F : Text`;

**begin**

```

  Writeln ('This will only work if you are root. ');
  Write ('Enter a UID : '); readln(UID);
  Write ('Enter a GID : '); readln(GID);
  Assign (f, 'test.txt');
  Rewrite (f);
  Writeln (f, 'The owner of this file should become : ');
  Writeln (f, 'UID : ',UID);
  Writeln (f, 'GID : ',GID);
  Close (F);
  if not Chown ('test.txt',UID,GID) then
    if LinuxError=Sys_EPERM then
      Writeln ('You are not root !')
    else
      Writeln ('Chmod failed with exit code : ',LinuxError)
    else
      Writeln ('Changed owner successfully !');
end.
```

### 31.12.11 Clone

**Synopsis:** Clone current process (create new thread)

**Declaration:** `function Clone(func: TCloneFunc; sp: pointer; flags: LongInt;`  
                   `args: pointer) : LongInt`

**Visibility:** default

**Description:** `Clone` creates a child process which is a copy of the parent process, just like `Fork` ([1067](#)) does. In difference with `Fork`, however, the child process shares some parts of it's execution context with its parent, so it is suitable for the implementation of threads: many instances of a program that share the same memory.

When the child process is created, it starts executing the function `Func`, and passes it `Args`. The return value of `Func` is either the explicit return value of the function, or the exit code of the child process.

The `sp` pointer points to the memory reserved as stack space for the child process. This address should be the top of the memory block to be used as stack.

The `Flags` determine the behaviour of the `Clone` call. The low byte of the `Flags` contains the number of the signal that will be sent to the parent when the child dies. This may be bitwise OR'ed with the following constants:

**CLONE\_VM**Parent and child share the same memory space, including memory (un)mapped with subsequent `mmap` calls.

**CLONE\_FS**Parent and child have the same view of the filesystem; the `chroot`, `chdir` and `umask` calls affect both processes.

**CLONE\_FILES**the file descriptor table of parent and child is shared.

**CLONE\_SIGHAND**the parent and child share the same table of signal handlers. The signal masks are different, though.

**CLONE\_PID**Parent and child have the same process ID.

`Clone` returns the process ID in the parent process, and -1 if an error occurred.

Errors: On error, -1 is returned to the parent, and no child is created.

**sys\_eagain**Too many processes are running.

**sys\_enomem**Not enough memory to create child process.

See also: Fork ([1067](#))

**Listing:** ./olinuxex/ex71.pp

---

```

program TestC{clone};

uses
  oldlinux , Errors , crt;

const
  Ready : Boolean = false;
  aChar : Char    = 'a';

function CloneProc( Arg: Pointer ): LongInt; Cdecl;
begin
  WriteLn('Hello from the clone ',PChar(Arg));
  repeat
    Write(aChar);
    Select(0,Nil,Nil,Nil,Nil);
  until Ready;
  WriteLn('Clone finished. ');
  CloneProc := 1;
end;

var
  PID : LongInt;

procedure MainProc;
begin
  WriteLn('cloned process PID: ', PID);
  WriteLn('Press <ESC> to kill ... ');
  repeat
    Write(' ');
    Select(0,Nil,Nil,Nil,Nil);

```

---

```

    if KeyPressed then
    case ReadKey of
        #27: Ready := true;
        'a': aChar := 'A';
        'A': aChar := 'a';
        'b': aChar := 'b';
        'B': aChar := 'B';
    end;
    until Ready;
    WriteLn('Ready. ');
end;

const
    StackSize = 16384;
    theFlags = CLONE_VM+CLONE_FS+CLONE_FILES+CLONE_SIGHAND;
    aMsg      : PChar = 'Oops !';

var
    theStack : Pointer;
    ExitStat : LongInt;

begin
    GetMem(theStack, StackSize);
    PID := Clone(@CloneProc,
                 Pointer(LongInt(theStack)+StackSize),
                 theFlags,
                 aMsg);
    if PID < 0 then
        WriteLn('Error : ', LinuxError, ' when cloning.')
    else
        begin
            MainProc;
            case WaitPID(0, @ExitStat, Wait_Untraced or wait_clone) of
                -1: WriteLn('error: ', LinuxError, '; ', StrError(LinuxError));
                0: WriteLn('error: ', LinuxError, '; ', StrError(LinuxError));
            else
                WriteLn('Clone exited with: ', ExitStat shr 8);
            end;
        end;
        FreeMem(theStack, StackSize);
    end.

```

---

### 31.12.12 CloseDir

Synopsis: Close directory file descriptor

Declaration: function CloseDir(p: PDir) : Integer

Visibility: default

Description: CloseDir closes the directory pointed to by p. It returns zero if the directory was closed successfully, -1 otherwise.

For an example, see OpenDir ([1090](#)).

Errors: Errors are returned in LinuxError.

See also: OpenDir ([1090](#)), ReadDir ([1093](#)), SeekDir ([1095](#)), TellDir ([1112](#))

### 31.12.13 CreateShellArgV

Synopsis: Create an array of null-terminated strings

Declaration: `function CreateShellArgV(const prog: String) : ppchar`  
`function CreateShellArgV(const prog: Ansistring) : ppchar`

Visibility: default

Description: `CreateShellArgV` creates an array of 3 `PChar` pointers that can be used as arguments to `ExecVE` the first elements in the array will contain `/bin/sh`, the second will contain `-c`, and the third will contain `prog`.

The function returns a pointer to this array, of type `PPChar`.

Errors: None.

See also: `Shell` ([1098](#))

**Listing:** `./olinuxex/ex61.pp`

---

**Program** `ex61`;

*{ Example program to demonstrate the CreateShellArgV function }*

**uses** `oldlinux`;

**Var**

`S: String;`  
`PP : PPchar;`  
`I : longint;`

**begin**

`S:= 'script -a -b -c -d -e fghijk ';`

`PP:=CreateShellArgV(S);`

`I:=0;`

**If** `PP<>Nil` **then**

**While** `PP[I]<>Nil` **do**

**begin**

`WriteLn ( 'Got : " ',PP[I], ' "');`

`Inc(I);`

**end;**

**end.**

---

### 31.12.14 Dirname

Synopsis: Extract directory part from filename

Declaration: `function Dirname(const path: PathStr) : PathStr`

Visibility: default

Description: Returns the directory part of `Path`. The directory is the part of `Path` before the last slash, or empty if there is no slash. The last character of the result is not a slash, unless the directory is the root directory.

Errors: None.

See also: `BaseName` ([1045](#)), `FExpand` ([1065](#))

**Listing:** ./olinuxex/ex47.pp

---

**Program** Example47;

*{ Program to demonstrate the DirName function. }*

**Uses** oldlinux;

**Var** S : **String**;

**begin**

  S:=FExpand(**Paramstr**(0));

**Writeln** ( 'This program is in directory : ',Dirname(S));

**end.**

---

### 31.12.15 Dup

Synopsis: Duplicate a file handle

**Declaration:** function Dup(oldfile: LongInt;var newfile: LongInt) : Boolean  
 function Dup(var oldfile: text;var newfile: text) : Boolean  
 function Dup(var oldfile: File;var newfile: File) : Boolean

Visibility: default

**Description:** Makes NewFile an exact copy of OldFile, after having flushed the buffer of OldFile in case it is a Text file or untyped file. Due to the buffering mechanism of Pascal, this has not the same functionality as the dup call in C. The internal Pascal buffers are not the same after this call, but when the buffers are flushed (e.g. after output), the output is sent to the same file. Doing an lseek will, however, work as in C, i.e. doing a lseek will change the fileposition in both files.

The function returns False in case of an error, True if successful.

**Errors:** In case of errors, Linuxerror is used to report errors.

**sys\_ebadf**OldFile hasn't been assigned.

**sys\_emfile**Maximum number of open files for the process is reached.

See also: Dup2 ([1053](#))

**Listing:** ./olinuxex/ex31.pp

---

**program** Example31;

*{ Program to demonstrate the Dup function. }*

**uses** oldlinux;

**var** f : text;

**begin**

**if not** dup (output,f) **then**

**Writeln** ( 'Dup Failed !');

**writeln** ( 'This is written to stdout.');

**writeln** (f, 'This is written to the dup file , and flushed');**flush**(f);

**writeln**

**end.**

---

### 31.12.16 Dup2

Synopsis: Duplicate one filehandle to another

Declaration: `function Dup2(oldfile: LongInt;newfile: LongInt) : Boolean`  
`function Dup2(var oldfile: text;var newfile: text) : Boolean`  
`function Dup2(var oldfile: File;var newfile: File) : Boolean`

Visibility: default

Description: Makes `NewFile` an exact copy of `OldFile`, after having flushed the buffer of `OldFile` in the case of text or untyped files.

`NewFile` can be an assigned file. If `newfile` was open, it is closed first. Due to the buffering mechanism of Pascal, this has not the same functionality as the `dup2` call in C. The internal Pascal buffers are not the same after this call, but when the buffers are flushed (e.g. after output), the output is sent to the same file. Doing an `lseek` will, however, work as in C, i.e. doing a `lseek` will change the fileposition in both files.

The function returns `True` if succesful, false otherwise.

Errors: In case of error, `Linuxerror` is used to report errors.

`sys_ebadfOldFile` hasn't been assigned.

`sys_emfile`Maximum number of open files for the process is reached.

See also: Dup ([1052](#))

**Listing:** `./olinuxex/ex32.pp`

---

```

program Example31;

  { Program to demonstrate the Dup function. }

uses oldlinux;

var f : text;
    i : longint;

begin
  Assign (f, 'text.txt');
  Rewrite (F);
  For i:=1 to 10 do writeln (F,'Line : ',i);
  if not dup2 (output,f) then
    Writeln ('Dup2 Failed !');
  writeln ('This is written to stdout. ');
  writeln (f,'This is written to the dup file , and flushed');
  flush(f);
  writeln;
  { Remove file . Comment this if you want to check flushing.}
  Unlink ('text.txt');
end.

```

---

### 31.12.17 EpochToLocal

Synopsis: Convert epoch time to local time

**Declaration:** `procedure EpochToLocal (epoch: LongInt; var year: Word; var month: Word;  
var day: Word; var hour: Word; var minute: Word;  
var second: Word)`

**Visibility:** default

**Description:** Converts the epoch time (=Number of seconds since 00:00:00 , January 1, 1970, corrected for your time zone ) to local date and time.

This function takes into account the timzone settings of your system.

**Errors:** None

See also: `GetEpochTime` ([1074](#)), `LocalToEpoch` ([1084](#)), `GetTime` ([1078](#)), `GetDate` ([1071](#))

**Listing:** ./olinuxex/ex3.pp

---

**Program** Example3;

*{ Program to demonstrate the EpochToLocal function. }*

**Uses** oldlinux;

**Var** Year, month, day, hour, minute, seconds : Word;

**begin**

EpochToLocal ( GetEpochTime, Year, month, day, hour, minute, seconds );

**Writeln** ( 'Current date : ', Day:2, '/', Month:2, '/', Year:4 );

**Writeln** ( 'Current time : ', Hour:2, ':', minute:2, ':', seconds:2 );

**end.**

---

### 31.12.18 Execl

**Synopsis:** Execute process (using argument list)

**Declaration:** `procedure Execl (const Todo: String)  
procedure Execl (const Todo: Ansistring)`

**Visibility:** default

**Description:** Replaces the currently running program with the program, specified in path. Path is split into a command and it's options. The executable in path is NOT searched in the path. The current environment is passed to the program. On success, execl does not return.

**Errors:** Errors are reported in `LinuxError`:

**sys\_eaccess**File is not a regular file, or has no execute permission. A component of the path has no search permission.

**sys\_eperm**The file system is mounted *noexec*.

**sys\_e2big**Argument list too big.

**sys\_enoexec**The magic number in the file is incorrect.

**sys\_enoent**The file does not exist.

**sys\_enomem**Not enough memory for kernel, or to split command line.

**sys\_enotdir**A component of the path is not a directory.

**sys\_eloop**The path contains a circular reference (via symlinks).



See also: [Execve \(1057\)](#), [Execv \(1056\)](#), [Execvp \(1058\)](#), [Execl \(1055\)](#), [Execlp \(1056\)](#), [Fork \(1067\)](#)

**Listing:** ./olinuxex/ex10.pp

**Program** Example10;

*{ Program to demonstrate the Execl function. }*

**Uses** oldlinux , strings ;

**begin**

*{ Execute 'ls -l', with current environment. }*  
*{ 'ls' is NOT looked for in PATH environment variable. }*  
 Execl ( '/bin/ls -l' );

**end.**

### 31.12.19 Execl

**Synopsis:** Execute process (using argument list, environment)

**Declaration:** `procedure Execl (Todo: String; Ep: ppchar)`  
`procedure Execl (Todo: AnsiString; Ep: ppchar)`

**Visibility:** default

**Description:** Replaces the currently running program with the program, specified in `path`. `Path` is split into a command and it's options. The executable in `path` is searched in the path, if it isn't an absolute filename. The environment in `ep` is passed to the program. On success, `execl` does not return.

**Errors:** Errors are reported in `LinuxError`:

**sys\_eaccess**File is not a regular file, or has no execute permission. A component of the path has no search permission.

**sys\_eperm**The file system is mounted *noexec*.

**sys\_e2big**Argument list too big.

**sys\_enoexec**The magic number in the file is incorrect.

**sys\_enoent**The file does not exist.

**sys\_enomem**Not enough memory for kernel, or to split command line.

**sys\_enotdir**A component of the path is not a directory.

**sys\_eloop**The path contains a circular reference (via symlinks).

See also: [Execve \(1057\)](#), [Execv \(1056\)](#), [Execvp \(1058\)](#), [Execl \(1054\)](#), [Execlp \(1056\)](#), [Fork \(1067\)](#)

**Listing:** ./olinuxex/ex11.pp

**Program** Example11;

*{ Program to demonstrate the Execl function. }*

**Uses** oldlinux , strings ;

**begin**

*{ Execute 'ls -l', with current environment. }*  
*{ 'ls' is NOT looked for in PATH environment variable. }*  
*{ envp is defined in the system unit. }*  
 Execl ( '/bin/ls -l', envp );

**end.**

**31.12.20 Execlp**

Synopsis: Execute process (using argument list, environment; search path)

Declaration: `procedure Execlp(Todo: String;Ep: ppchar)`  
`procedure Execlp(Todo: Ansistring;Ep: ppchar)`

Visibility: default

Description: Replaces the currently running program with the program, specified in `path`. `Path` is split into a command and it's options. The executable in `path` is searched in the path, if it isn't an absolute filename. The current environment is passed to the program. On success, `execlp` does not return.

Errors: Errors are reported in `LinuxError`:

**sys\_eaccess**File is not a regular file, or has no execute permission. A component of the path has no search permission.

**sys\_eperm**The file system is mounted *noexec*.

**sys\_e2big**Argument list too big.

**sys\_enoexec**The magic number in the file is incorrect.

**sys\_enoent**The file does not exist.

**sys\_enomem**Not enough memory for kernel, or to split command line.

**sys\_enotdir**A component of the path is not a directory.

**sys\_eloop**The path contains a circular reference (via symlinks).

See also: `Execve` ([1057](#)), `Execv` ([1056](#)), `Execvp` ([1058](#)), `Execle` ([1055](#)), `Execl` ([1054](#)), `Fork` ([1067](#))

**Listing:** `./olinuxex/ex12.pp`

**Program** `Example12;`

*{ Program to demonstrate the Execlp function. }*

**Uses** `oldlinux , strings;`

**begin**

*{ Execute 'ls -l', with current environment. }*  
*{ 'ls' is looked for in PATH environment variable. }*  
*{ envp is defined in the system unit. }*

`Execlp ('ls -l',envp);`

**end.**

**31.12.21 Execv**

Synopsis: Execute process

Declaration: `procedure Execv(const path: PathStr;args: ppchar)`  
`procedure Execv(const path: AnsiString;args: ppchar)`

Visibility: default

Description: Replaces the currently running program with the program, specified in `path`. It gives the program the options in `args`. This is a pointer to an array of pointers to null-terminated strings. The last pointer in this array should be nil. The current environment is passed to the program. On success, `execv` does not return.

Errors: Errors are reported in `LinuxError`:

**sys\_eaccess**File is not a regular file, or has no execute permission. A component of the path has no search permission.  
**sys\_eperm**The file system is mounted *noexec*.  
**sys\_e2big**Argument list too big.  
**sys\_enoexec**The magic number in the file is incorrect.  
**sys\_enoent**The file does not exist.  
**sys\_enomem**Not enough memory for kernel.  
**sys\_enotdir**A component of the path is not a directory.  
**sys\_eloop**The path contains a circular reference (via symlinks).

See also: `Execve` (1057), `Execvp` (1058), `Execle` (1055), `Execl` (1054), `Execvp` (1056), `Fork` (1067)

**Listing:** `./olinuxex/ex8.pp`

**Program** `Example8`;

*{ Program to demonstrate the Execv function. }*

**Uses** `oldlinux` , `strings`;

**Const** `Arg0` : `PChar` = `'/bin/l s '`;  
           `Arg1` : `Pchar` = `'-l '`;

**Var** `PP` : `PPchar`;

**begin**

`GetMem` (`PP`, `3 * SizeOf`(`Pchar`));  
  `PP`[0] := `Arg0`;  
  `PP`[1] := `Arg1`;  
  `PP`[3] := `Nil`;  
  *{ Execute '/bin/l s -l ', with current environment }*  
  `Execv` (`'/bin/l s '`, `pp`);

**end.**

### 31.12.22 Execve

Synopsis: Execute process using environment

**Declaration:** `procedure Execve(Path: PathStr; args: ppchar; ep: ppchar)`  
                   `procedure Execve(Path: AnsiString; args: ppchar; ep: ppchar)`  
                   `procedure Execve(path: pchar; args: ppchar; ep: ppchar)`

Visibility: default

**Description:** Replaces the currently running program with the program, specified in `path`. It gives the program the options in `args`, and the environment in `ep`. They are pointers to an array of pointers to null-terminated strings. The last pointer in this array should be `nil`. On success, `execve` does not return.

Errors: Errors are reported in `LinuxError`:

**sys\_eaccess**File is not a regular file, or has no execute permission. A component of the path has no search permission.

**sys\_eperm**The file system is mounted *noexec*.

**sys\_e2big**Argument list too big.

**sys\_enoexec**The magic number in the file is incorrect.

**sys\_enoent**The file does not exist.

**sys\_enomem**Not enough memory for kernel.

**sys\_enotdir**A component of the path is not a directory.

**sys\_eloop**The path contains a circular reference (via symlinks).

See also: `Execve` (1057), `Execv` (1056), `Execvp` (1058), `Execle` (1055), `Execl` (1054), `Execlp` (1056), `Fork` (1067)

**Listing:** ./olinuxex/ex7.pp

**Program** Example7;

*{ Program to demonstrate the Execve function. }*

**Uses** oldlinux , strings ;

**Const** Arg0 : PChar = '/bin/lS';  
Arg1 : Pchar = '-l';

**Var** PP : PPchar;

**begin**

GetMem (PP,3\*SizeOf(Pchar));

PP[0]:=Arg0;

PP[1]:=Arg1;

PP[3]:=Nil;

*{ Execute '/bin/lS -l', with current environment }*

*{ Env is defined in system.inc }*

ExecVe ('/bin/lS',pp,envp);

**end.**

### 31.12.23 Execvp

**Synopsis:** Execute process, search path

**Declaration:** `procedure Execvp(Path: PathStr;Args: ppchar;Ep: ppchar)`  
`procedure Execvp(Path: AnsiString;Args: ppchar;Ep: ppchar)`

**Visibility:** default

**Description:** Replaces the currently running program with the program, specified in `path`. The executable in `path` is searched in the path, if it isn't an absolute filename. It gives the program the options in `args`. This is a pointer to an array of pointers to null-terminated strings. The last pointer in this array should be nil. The current environment is passed to the program. On success, `execvp` does not return.

**Errors:** Errors are reported in `LinuxError`:

**sys\_eaccess**File is not a regular file, or has no execute permission. A component of the path has no search permission.

**sys\_eperm**The file system is mounted *noexec*.  
**sys\_e2big**Argument list too big.  
**sys\_enoexec**The magic number in the file is incorrect.  
**sys\_enoent**The file does not exist.  
**sys\_enomem**Not enough memory for kernel.  
**sys\_enotdir**A component of the path is not a directory.  
**sys\_eLOOP**The path contains a circular reference (via symlinks).

See also: `Execve` ([1057](#)), `Execv` ([1056](#)), `Execle` ([1055](#)), `Execl` ([1054](#)), `Execvp` ([1056](#)), `Fork` ([1067](#))

**Listing:** `./olinuxex/ex9.pp`

**Program** Example9;

*{ Program to demonstrate the Execvp function. }*

**Uses** `oldlinux` , `strings`;

**Const** `Arg0` : `PChar` = `'ls'`;  
           `Arg1` : `Pchar` = `'-l'`;

**Var** `PP` : `PPchar`;

**begin**

`GetMem` (`PP`, `3*SizeOf(Pchar)`);  
  `PP[0]` := `Arg0`;  
  `PP[1]` := `Arg1`;  
  `PP[3]` := `Nil`;  
  *{ Execute 'ls -l', with current environment. }*  
  *{ 'ls' is looked for in PATH environment variable. }*  
  *{ Env is defined in the system unit. }*  
  `Execvp` (`'ls'`, `pp`, `envp`);

**end.**

### 31.12.24 ExitProcess

**Synopsis:** Exit the current process

**Declaration:** `procedure ExitProcess(val: LongInt)`

**Visibility:** `default`

**Description:** `ExitProcess` exits the currently running process, and report `Val` as the exit status.

**Remark:** If this call is executed, the normal unit finalization code will not be executed. This may lead to unexpected errors and stray files on your system. It is therefore recommended to use the `Halt` call instead.

**Errors:** None.

See also: `Fork` ([1067](#)), `ExecVE` ([1057](#))

### 31.12.25 Fcntl

Synopsis: File control operations.

Declaration: `function Fcntl(Fd: LongInt;Cmd: LongInt) : LongInt`  
`procedure Fcntl(Fd: LongInt;Cmd: LongInt;Arg: LongInt)`  
`function Fcntl(var Fd: Text;Cmd: LongInt) : LongInt`  
`procedure Fcntl(var Fd: Text;Cmd: LongInt;Arg: LongInt)`

Visibility: default

Description: Read a file's attributes. `Fd` is an assigned file, or a valid file descriptor. `Cmd` specifies what to do, and is one of the following:

**F\_GetFd**Read the `close_on_exec` flag. If the low-order bit is 0, then the file will remain open across `execve` calls.

**F\_GetFl**Read the descriptor's flags.

**F\_GetOwn**Get the Process ID of the owner of a socket.

**F\_SetFd**Set the `close_on_exec` flag of `Fd`. (only the least significant bit is used).

**F\_GetLk**Return the `flock` record that prevents this process from obtaining the lock, or set the `l_type` field of the lock if there is no obstruction. `Arg` is a pointer to a `flock` record.

**F\_SetLk**Set the lock or clear it (depending on `l_type` in the `flock` structure). if the lock is held by another process, an error occurs.

**F\_GetLkw**Same as for **F\_Setlk**, but wait until the lock is released.

**F\_SetOwn**Set the Process or process group that owns a socket.

Errors: `LinuxError` is used to report errors.

**sys\_ebadf**`Fd` has a bad file descriptor.

**sys\_eagain or sys\_eaccess**For **F\_SetLk**, if the lock is held by another process.

### 31.12.26 fdClose

Synopsis: Close file descriptor

Declaration: `function fdClose(fd: LongInt) : Boolean`

Visibility: default

Description: `fdClose` closes a file with file descriptor `Fd`. The function returns `True` if the file was closed successfully, `False` otherwise.

For an example, see `fdOpen` (1061).

Errors: Errors are returned in `LinuxError`.

See also: `fdOpen` (1061), `fdRead` (1062), `fdWrite` (1064), `fdTruncate` (1063), `fdFlush` (1060), `fdSeek` (1063)

### 31.12.27 fdFlush

Synopsis: Flush kernel file buffer

Declaration: `function fdFlush(fd: LongInt) : Boolean`

Visibility: default

**Description:** `fdflush` flushes the Linux kernel file buffer, so the file is actually written to disk. This is NOT the same as the internal buffer, maintained by Free Pascal. The function returns `True` if the call was successful, `false` if an error occurred.

For an example, see `fdRead` (1062).

**Errors:** Errors are returned in `LinuxError`.

See also: `fdOpen` (1061), `fdClose` (1060), `fdRead` (1062), `fdWrite` (1064), `fdTruncate` (1063), `fdSeek` (1063)

### 31.12.28 fdOpen

**Synopsis:** Open file and return file descriptor

**Declaration:**

```
function fdOpen(pathname: String; flags: LongInt) : LongInt
function fdOpen(pathname: String; flags: LongInt; mode: LongInt) : LongInt
function fdOpen(pathname: pchar; flags: LongInt) : LongInt
function fdOpen(pathname: pchar; flags: LongInt; mode: LongInt) : LongInt
```

**Visibility:** default

**Description:** `fdOpen` opens a file in `PathName` with flags `flags` One of the following:

**Open\_RdOnlyFile** is opened Read-only

**Open\_WrOnlyFile** is opened Write-only

**Open\_RdWrFile** is opened Read-Write

The flags may be OR-ed with one of the following constants:

**Open\_CreatFile** is created if it doesn't exist.

**Open\_ExclIf** the file is opened with `Open_Creat` and it already exists, the call will fail.

**Open\_NoCttyIf** the file is a terminal device, it will NOT become the process' controlling terminal.

**Open\_TruncIf** the file exists, it will be truncated.

**Open\_Append** the file is opened in append mode. *Before each write*, the file pointer is positioned at the end of the file.

**Open\_NonBlock** The file is opened in non-blocking mode. No operation on the file descriptor will cause the calling process to wait till.

**Open\_NDelay** Idem as `Open_NonBlock`

**Open\_Sync** The file is opened for synchronous IO. Any write operation on the file will not return until the data is physically written to disk.

**Open\_NoFollow** if the file is a symbolic link, the open fails. (linux 2.1.126 and higher only)

**Open\_Directory** if the file is not a directory, the open fails. (linux 2.1.126 and higher only)

`PathName` can be of type `PChar` or `String`. The optional `mode` argument specifies the permissions to set when opening the file. This is modified by the `umask` setting. The real permissions are `Mode` and not `umask`. The return value of the function is the file descriptor, or a negative value if there was an error.

**Errors:** Errors are returned in `LinuxError`.

See also: `fdClose` (1060), `fdRead` (1062), `fdWrite` (1064), `fdTruncate` (1063), `fdFlush` (1060), `fdSeek` (1063)

**Listing:** `./olinuxex/ex19.pp`

---

```

Program Example19;

{ Program to demonstrate the fdOpen, fdwrite and fdClose functions. }

Uses oldlinux;

Const Line : String[80] = 'This is easy writing !';

Var FD : Longint;

begin
  FD:=fdOpen ( 'Test.dat',Open_WrOnly or Open_Creat);
  if FD>0 then
    begin
      if length(Line)<>fdwrite (FD,Line[1],Length(Line)) then
        WriteLn ( 'Error when writing to file !');
      fdClose(FD);
    end;
end.

```

---

### 31.12.29 fdRead

Synopsis: Read data from file descriptor

Declaration: function fdRead(fd: LongInt;var buf;size: LongInt) : LongInt

Visibility: default

Description: fdRead reads at most size bytes from the file descriptor fd, and stores them in buf. The function returns the number of bytes actually read, or -1 if an error occurred. No checking on the length of buf is done.

Errors: Errors are returned in LinuxError.

See also: fdOpen (1061), fdClose (1060), fdWrite (1064), fdTruncate (1063), fdFlush (1060), fdSeek (1063)

**Listing:** ./olinuxex/ex20.pp

---

```

Program Example20;

{ Program to demonstrate the fdRead and fdTruncate functions. }

Uses oldlinux;

Const Data : string[10] = '12345687890';

Var FD : Longint;
    I : longint;

begin
  FD:=fdOpen('test.dat',open_wronly or open_creat,octal(666));
  if fd>0 then
    begin
      { Fill file with data }
      for I:=1 to 10 do
        if fdWrite (FD,Data[I],10)<>10 then
          begin

```



---

```

        writeln ( 'Error when writing !');
        halt(1);
    end;
fdClose(FD);
FD:=fdOpen('test.dat',open_rdonly);
{ Read data again }
If FD>0 then
begin
    For I:=1 to 5 do
        if fdRead (FD,Data[1],10)<>10 then
            begin
                Writeln ( 'Error when Reading !');
                Halt(2);
            end;
        fdClose(FD);
        { Truncating file at 60 bytes }
        { For truncating , file must be open or write }
        FD:=fdOpen('test.dat',open_wronly,octal(666));
        if FD>0 then
            begin
                if not fdTruncate(FD,60) then
                    Writeln('Error when truncating !');
                fdClose (FD);
            end;
        end;
    end;
end.

```

---

### 31.12.30 fdSeek

Synopsis: Set file pointer position.

Declaration: `function fdSeek(fd: LongInt;pos: LongInt;seektype: LongInt) : LongInt`

Visibility: default

Description: `fdSeek` sets the current fileposition of file `fd` to `Pos`, starting from `SeekType`, which can be one of the following:

**Seek\_SetPos** is the absolute position in the file.

**Seek\_CurPos** is relative to the current position.

**Seek\_endPos** is relative to the end of the file.

The function returns the new fileposition, or -1 of an error occurred.

For an example, see `fdOpen` ([1061](#)).

Errors: Errors are returned in `LinuxError`.

See also: `fdOpen` ([1061](#)), `fdWrite` ([1064](#)), `fdClose` ([1060](#)), `fdRead` ([1062](#)), `fdTruncate` ([1063](#)), `fdFlush` ([1060](#))

### 31.12.31 fdTruncate

Synopsis: Truncate file on certain size.

Declaration: `function fdTruncate(fd: LongInt;size: LongInt) : Boolean`

Visibility: default

Description: `fdTruncate` sets the length of a file in `fd` on `size` bytes, where `size` must be less than or equal to the current length of the file in `fd`. The function returns `True` if the call was successful, `false` if an error occurred.

Errors: Errors are returned in `LinuxError`.

See also: `fdOpen` ([1061](#)), `fdClose` ([1060](#)), `fdRead` ([1062](#)), `fdWrite` ([1064](#)), `fdFlush` ([1060](#)), `fdSeek` ([1063](#))

### 31.12.32 `fdWrite`

Synopsis: Write data to file descriptor

Declaration: `function fdWrite(fd: LongInt; const buf; size: LongInt) : LongInt`

Visibility: default

Description: `fdWrite` writes at most `size` bytes from `buf` to file descriptor `fd`. The function returns the number of bytes actually written, or -1 if an error occurred.

Errors: Errors are returned in `LinuxError`.

See also: `fdOpen` ([1061](#)), `fdClose` ([1060](#)), `fdRead` ([1062](#)), `fdTruncate` ([1063](#)), `fdSeek` ([1063](#)), `fdFlush` ([1060](#))

### 31.12.33 `FD_Clr`

Synopsis: Clears a filedescriptor in a set

Declaration: `procedure FD_Clr(fd: LongInt; var fds: fdSet)`

Visibility: default

Description: `FD_Clr` clears file descriptor `fd` in filedescriptor set `fds`.

For an example, see `Select` ([1095](#)).

Errors: None.

See also: `Select` ([1095](#)), `SelectText` ([1097](#)), `GetFS` ([1075](#)), `FD_ZERO` ([1065](#)), `FD_Set` ([1065](#)), `FD_IsSet` ([1064](#))

### 31.12.34 `FD_IsSet`

Synopsis: Check whether a filedescriptor is set

Declaration: `function FD_IsSet(fd: LongInt; var fds: fdSet) : Boolean`

Visibility: default

Description: `FD_Set` Checks whether file descriptor `fd` in filedescriptor set `fds` is set.

For an example, see `Select` ([1095](#)).

Errors: None.

See also: `Select` ([1095](#)), `SelectText` ([1097](#)), `GetFS` ([1075](#)), `FD_ZERO` ([1065](#)), `FD_Clr` ([1064](#)), `FD_Set` ([1065](#))

### 31.12.35 FD\_Set

Synopsis: Set a filedescriptor in a set

Declaration: `procedure FD_Set (fd: LongInt; var fds: fdSet)`

Visibility: default

Description: `FD_Set` sets file descriptor `fd` in filedescriptor set `fds`.

For an example, see [Select \(1095\)](#).

Errors: None.

See also: [Select \(1095\)](#), [SelectText \(1097\)](#), [GetFS \(1075\)](#), [FD\\_ZERO \(1065\)](#), [FD\\_Clr \(1064\)](#), [FD\\_IsSet \(1064\)](#)

### 31.12.36 FD\_Zero

Synopsis: Clear all file descriptors in set

Declaration: `procedure FD_Zero (var fds: fdSet)`

Visibility: default

Description: `FD_ZERO` clears all the filedescriptors in the file descriptor set `fds`.

For an example, see [Select \(1095\)](#).

Errors: None.

See also: [Select \(1095\)](#), [SelectText \(1097\)](#), [GetFS \(1075\)](#), [FD\\_Clr \(1064\)](#), [FD\\_Set \(1065\)](#), [FD\\_IsSet \(1064\)](#)

### 31.12.37 FExpand

Synopsis: Expand filename to fully qualified path

Declaration: `function FExpand (const Path: PathStr) : PathStr`

Visibility: default

Description: `FExpand` expands `Path` to a full path, starting from root, eliminating directory references such as `.` and `..` from the result.

Errors: None

See also: [BaseName \(1045\)](#), [DirName \(1051\)](#)

**Listing:** `./olinuxex/ex45.pp`

---

**Program** `Example45;`

*{ Program to demonstrate the FExpand function. }*

**Uses** `oldlinux;`

**begin**

**WriteLn** ( 'This program is in : ', `FExpand (Paramstr (0))` );

**end.**

---

### 31.12.38 Flock

Synopsis: Lock a file (advisory lock)

Declaration: `function Flock(fd: LongInt;mode: LongInt) : Boolean`  
`function Flock(var T: text;mode: LongInt) : Boolean`  
`function Flock(var F: File;mode: LongInt) : Boolean`

Visibility: default

Description: `Flock` implements file locking. it sets or removes a lock on the file `F`. `F` can be of type `Text` or `File`, or it can be a linux filedescriptor (a longint) `Mode` can be one of the following constants :

**LOCK\_SH**sets a shared lock.

**LOCK\_EX**sets an exclusive lock.

**LOCK\_UN**unlocks the file.

**LOCK\_NB**This can be OR-ed together with the other. If this is done the application doesn't block when locking.

The function returns `True` if successful, `False` otherwise.

Errors: If an error occurs, it is reported in `LinuxError`.

See also: `Fcntl` ([1060](#))

### 31.12.39 FNMatch

Synopsis: Check whether filename matches wildcard specification

Declaration: `function FNMatch(const Pattern: String;const Name: String) : Boolean`

Visibility: default

Description: `FNMatch` returns `True` if the filename in `Name` matches the wildcard pattern in `Pattern`, `False` otherwise.

`Pattern` can contain the wildcards `*` (match zero or more arbitrary characters) or `?` (match a single character).

Errors: None.

See also: `FSearch` ([1068](#)), `FExpand` ([1065](#))

**Listing:** `./olinuxex/ex69.pp`

**Program** `Example69;`

*{ Program to demonstrate the FNMatch function. }*

**Uses** `oldlinux;`

**Procedure** `TestMatch(Pattern,Name : String);`

**begin**

`Write ('"',Name,'"');`

`If FNMatch ( Pattern,Name) then`

`Write ('matches')`

`else`

`Write ('does not match');`

```

    Writeln( ' ', Pattern, ' ". ');
end;

begin
    TestMatch( '*', 'FileName' );
    TestMatch( '.*', 'FileName' );
    TestMatch( '*a*', 'FileName' );
    TestMatch( '?ile*', 'FileName' );
    TestMatch( '?', 'FileName' );
    TestMatch( '.?', 'FileName' );
    TestMatch( '?a*', 'FileName' );
    TestMatch( '??*me?', 'FileName' );
end.

```

---

### 31.12.40 Fork

Synopsis: Create child process

Declaration: `function Fork : LongInt`

Visibility: default

Description: `Fork` creates a child process which is a copy of the parent process. `Fork` returns the process ID in the parent process, and zero in the child's process. (you can get the parent's PID with `GetPPid` ([1077](#))).

Errors: On error, -1 is returned to the parent, and no child is created.

**sys\_eagain** Not enough memory to create child process.

See also: `Execve` ([1057](#)), `Clone` ([1048](#))

### 31.12.41 FReName

Synopsis: Rename file

Declaration: `function FReName(OldName: Pchar; NewName: Pchar) : Boolean`  
`function FReName(OldName: String; NewName: String) : Boolean`

Visibility: default

Description: `FReName` renames the file `OldName` to `NewName`. `NewName` can be in a different directory than `OldName`, but it cannot be on another partition (device). Any existing file on the new location will be replaced.

If the operation fails, then the `OldName` file will be preserved.

The function returns `True` on succes, `False` on failure.

Errors: On error, errors are reported in `LinuxError`. Possible errors include:

**sys\_eisdir** `NewName` exists and is a directory, but `OldName` is not a directory.

**sys\_exdev** `NewName` and `OldName` are on different devices.

**sys\_enotempty or sys\_eexist** `NewName` is an existing, non-empty directory.

**sys\_ebusy** `OldName` or `NewName` is a directory and is in use by another process.

**sys\_einval** `NewName` is part of `OldName`.

**sys\_emlink**OldPath or NewPath already have the maximum amount of links pointing to them.

**sys\_enotdir**part of OldName or NewName is not directory.

**sys\_efault**For the pchar case: One of the pointers points to an invalid address.

**sys\_eaccess**access is denied when attempting to move the file.

**sys\_enametoolong**Either OldName or NewName is too long.

**sys\_enoent**a directory component in OldName or NewName didn't exist.

**sys\_enomem**not enough kernel memory.

**sys\_erofs**NewName or OldName is on a read-only file system.

**sys\_eloop**too many symbolic links were encountered trying to expand OldName or NewName

**sys\_enospc**the filesystem has no room for the new directory entry.

See also: UnLink ([1113](#))

### 31.12.42 FSearch

Synopsis: Search for file in search path.

Declaration: `function FSearch(const path: PathStr;dirlist: String) : PathStr`

Visibility: default

Description: `FSearch` searches in `DirList`, a colon separated list of directories, for a file named `Path`. It then returns a path to the found file.

Errors: An empty string if no such file was found.

See also: `BaseName` ([1045](#)), `DirName` ([1051](#)), `FExpand` ([1065](#)), `FNMatch` ([1066](#))

**Listing:** ./olinuxex/ex46.pp

---

**Program** Example46;

*{ Program to demonstrate the FSearch function. }*

**Uses** oldlinux, strings;

**begin**

**WriteLn** ('ls is in : ',FSearch ('ls',strpas(Getenv('PATH'))));

**end.**

---

### 31.12.43 FSplit

Synopsis: Split filename into path, name and extension

Declaration: `procedure FSplit(const Path: PathStr;var Dir: DirStr;var Name: NameStr;var Ext: ExtStr)`

Visibility: default

Description: `FSplit` splits a full file name into 3 parts : A `Path`, a `Name` and an extension (in `ext`). The extension is taken to be all letters after the last dot (.).

Errors: None.

See also: [FSearch \(1068\)](#)

**Listing:** ./olinuxex/ex67.pp

---

```

Program Example67;

uses oldlinux;

{ Program to demonstrate the FSplit function. }

var
  Path, Name, Ext : string;

begin
  FSplit(ParamStr(1), Path, Name, Ext);
  WriteLn('Split ', ParamStr(1), ' in:');
  WriteLn('Path      : ', Path);
  WriteLn('Name      : ', Name);
  WriteLn('Extension: ', Ext);
end.

```

---

### 31.12.44 FSStat

**Synopsis:** Retrieve filesystem information.

**Declaration:** `function FSStat(Path: PathStr; var Info: Statfs) : Boolean`  
`function FSStat(Fd: LongInt; var Info: Statfs) : Boolean`

**Visibility:** default

**Description:** FSStat returns in Info information about the filesystem on which the file Path resides, or on which the file with file descriptor fd resides. Info is of type statfs. The function returns True if the call was successful, False if the call failed.

**Errors:** LinuxError is used to report errors.

**sys\_enotdir** A component of Path is not a directory.  
**sys\_einval** Invalid character in Path.  
**sys\_enoent** Path does not exist.  
**sys\_eaccess** Search permission is denied for component in Path.  
**sys\_eloop** A circular symbolic link was encountered in Path.  
**sys\_eio** An error occurred while reading from the filesystem.

See also: [FStat \(1070\)](#), [LStat \(1085\)](#)

**Listing:** ./olinuxex/ex30.pp

---

```

program Example30;

{ Program to demonstrate the FSStat function. }

uses oldlinux;

var s : string;
    info : statfs;

```

---

```

begin
  writeln ('Info about current partition : ');
  s:= '.';
  while s<>'q' do
    begin
      if not fsstat (s,info) then
        begin
          writeln('Fstat failed. Errno : ',linuxerror);
          halt (1);
        end;
      writeln;
      writeln ('Result of fsstat on file ''',s,'''');
      writeln ('fstype   : ',info.fstype);
      writeln ('bsize    : ',info.bsize);
      writeln ('bfree    : ',info.bfree);
      writeln ('bavail   : ',info.bavail);
      writeln ('files    : ',info.files);
      writeln ('ffree    : ',info.ffree);
      writeln ('fsid     : ',info.fsid);
      writeln ('Namelen  : ',info.namelen);
      write ('Type name of file to do fsstat. (q quits) : ');
      readln (s)
    end;
  end.

```

---

### 31.12.45 FStat

Synopsis: Retrieve information about a file

Declaration: `function FStat (Path: PathStr;var Info: Stat) : Boolean`  
`function FStat (Fd: LongInt;var Info: Stat) : Boolean`  
`function FStat (var F: Text;var Info: Stat) : Boolean`  
`function FStat (var F: File;var Info: Stat) : Boolean`

Visibility: default

Description: `FStat` gets information about the file specified in one of the following:

**Path**a file on the filesystem.

**Fd**a valid file descriptor.

**F**an opened text file or untyped file.

and stores it in `Info`, which is of type `stat`. The function returns `True` if the call was succesfull, `False` if the call failed.

Errors: `LinuxError` is used to report errors.

`sys_enoent`Path does not exist.

See also: `FSSStat` ([1069](#)), `LStat` ([1085](#))

**Listing:** `./olinuxex/ex28.pp`



---

```

program example28;

{ Program to demonstrate the FStat function. }

uses oldlinux;

var f : text;
    i : byte;
    info : stat;

begin
  { Make a file }
  assign (f, 'test.fil');
  rewrite (f);
  for i:=1 to 10 do writeln (f, 'Testline # ', i);
  close (f);
  { Do the call on made file. }
  if not fstat ('test.fil', info) then
    begin
      writeln ('Fstat failed. Errno : ', linuxerror);
      halt (1);
    end;
  writeln;
  writeln ('Result of fstat on file ''test.fil''.');
  writeln ('Inode   : ', info.ino);
  writeln ('Mode    : ', info.mode);
  writeln ('nlink   : ', info.nlink);
  writeln ('uid     : ', info.uid);
  writeln ('gid     : ', info.gid);
  writeln ('rdev    : ', info.rdev);
  writeln ('Size    : ', info.size);
  writeln ('Blksize : ', info.blksize);
  writeln ('Blocks  : ', info.blocks);
  writeln ('atime   : ', info.atime);
  writeln ('mtime   : ', info.mtime);
  writeln ('ctime   : ', info.ctime);
  { Remove file }
  erase (f);
end.

```

---

### 31.12.46 GetDate

Synopsis: Return the system date

Declaration: `procedure GetDate(var Year: Word; var Month: Word; var Day: Word)`

Visibility: default

Description: Returns the current date.

Errors: None

See also: [GetEpochTime \(1074\)](#), [GetTime \(1078\)](#), [GetDateTime \(1072\)](#), [EpochToLocal \(1053\)](#)

**Listing:** ./olinuxex/ex6.pp

---

```

Program Example6;

{ Program to demonstrate the GetDate function. }

Uses oldlinux;

Var Year, Month, Day : Word;

begin
  GetDate (Year, Month, Day);
  WriteLn ( 'Date : ', Day:2, '/' , Month:2, '/' , Year:4);
end.

```

---

### 31.12.47 GetDateTime

Synopsis: Return system date and time

Declaration: `procedure GetDateTime(var Year: Word; var Month: Word; var Day: Word; var hour: Word; var minute: Word; var second: Word)`

Visibility: default

Description: Returns the current date and time. The time is corrected for the local time zone. This procedure is equivalent to the `GetDate` ([1071](#)) and `GetTime` calls.

Errors: None

See also: `GetEpochTime` ([1074](#)), `GetTime` ([1078](#)), `EpochToLocal` ([1053](#)), `GetDate` ([1071](#))

**Listing:** ./olinuxex/ex60.pp

---

```

Program Example6;

{ Program to demonstrate the GetDateTime function. }

Uses oldlinux;

Var Year, Month, Day, Hour, min, sec : Word;

begin
  GetDateTime (Year, Month, Day, Hour, min, sec);
  WriteLn ( 'Date : ', Day:2, '/' , Month:2, '/' , Year:4);
  WriteLn ( 'Time : ', Hour:2, ':' , Min:2, ':' , Sec:2);
end.

```

---

### 31.12.48 GetDomainName

Synopsis: Return current domain name

Declaration: `function GetDomainName : String`

Visibility: default

Description: Get the domain name of the machine on which the process is running. An empty string is returned if the domain is not set.

Errors: None.

See also: `GetHostName` ([1076](#))

**Listing:** ./olinuxex/ex39.pp

---

**Program** Example39;

*{ Program to demonstrate the GetDomainName function. }*

**Uses** oldlinux;

**begin**

**WriteLn** ( 'Domain name of this machine is : ', GetDomainName );  
**end.**

---

### 31.12.49 GetEGid

Synopsis: Return effective group ID

Declaration: `function GetEGid : LongInt`

Visibility: default

Description: Get the effective group ID of the currently running process.

Errors: None.

See also: `GetGid` ([1075](#))

**Listing:** ./olinuxex/ex18.pp

---

**Program** Example18;

*{ Program to demonstrate the GetGid and GetEGid functions. }*

**Uses** oldlinux;

**begin**

**writeln** ( 'Group Id = ', getgid, ' Effective group Id = ', getegid );  
**end.**

---

### 31.12.50 GetEnv

Synopsis: Return value of environment variable.

Declaration: `function GetEnv(P: String) : PChar`

Visibility: default

Description: `GetEnv` returns the value of the environment variable in `P`. If the variable is not defined, `nil` is returned. The value of the environment variable may be the empty string. A `PChar` is returned to accomodate for strings longer than 255 bytes, `TERMCAP` and `LS_COLORS`, for instance.

Errors: None.

**Listing:** ./olinuxex/ex41.pp

---

```

Program Example41;

{ Program to demonstrate the GetEnv function. }

Uses oldlinux;

begin
  WriteLn ( 'Path is : ',Getenv( 'PATH' ));
end.

```

---

### 31.12.51 GetEpochTime

Synopsis: Return the current unix time

Declaration: `function GetEpochTime : LongInt`

Visibility: default

Description: returns the number of seconds since 00:00:00 gmt, january 1, 1970. it is adjusted to the local time zone, but not to DST.

Errors: no errors

See also: EpochToLocal ([1053](#)), GetTime ([1078](#))

**Listing:** ./olinuxex/ex1.pp

---

```

Program Example1;

{ Program to demonstrate the GetEpochTime function. }

Uses oldlinux;

begin
  Write ( 'Secs past the start of the Epoch (00:00 1/1/1980) : ');
  WriteLn ( GetEpochTime );
end.

```

---

### 31.12.52 GetEUid

Synopsis: Return effective user ID

Declaration: `function GetEUid : LongInt`

Visibility: default

Description: Get the effective user ID of the currently running process.

Errors: None.

See also: GetUid ([1079](#))

**Listing:** ./olinuxex/ex17.pp

---

**Program** Example17;

*{ Program to demonstrate the GetUid and GetEUid functions. }*

**Uses** oldlinux;

**begin**

**writeln** ( 'User Id = ',getuid,' Effective user Id = ',geteuid);  
**end.**

---

### 31.12.53 GetFS

Synopsis: Return file selector

**Declaration:** function GetFS(var T: Text) : LongInt  
                  function GetFS(var F: File) : LongInt

Visibility: default

**Description:** GetFS returns the file selector that the kernel provided for your file. In principle you don't need this file selector. Only for some calls it is needed, such as the Select ([1095](#)) call or so.

**Errors:** In case the file was not opened, then -1 is returned.

See also: Select ([1095](#))

**Listing:** ./olinuxex/ex34.pp

---

**Program** Example33;

*{ Program to demonstrate the SelectText function. }*

**Uses** oldlinux;

**Var** tv : TimeVal;

**begin**

**Writeln** ( 'Press the <ENTER> to continue the program. ');  
    *{ Wait until File descriptor 0 (=Input) changes }*  
    SelectText (Input, nil);  
    *{ Get rid of <ENTER> in buffer }*  
    **readln**;  
    **Writeln** ( 'Press <ENTER> key in less than 2 seconds... ');  
    tv.sec:=2;  
    tv.usec:=0;  
    **if** SelectText (Input,@tv)>0 **then**  
        **Writeln** ( 'Thank you ! ' )  
    **else**  
        **Writeln** ( 'Too late ! ' );  
**end.**

---

### 31.12.54 GetGid

Synopsis: Return real group ID

**Declaration:** function GetGid : LongInt

Visibility: default

Description: Get the real group ID of the currently running process.

Errors: None.

See also: GetEGid ([1073](#))

**Listing:** ./olinuxex/ex18.pp

---

**Program** Example18;

*{ Program to demonstrate the GetGid and GetEGid functions. }*

**Uses** oldlinux;

```
begin
  writeln ( 'Group Id = ',getgid,' Effective group Id = ',getegid);
end.
```

---

### 31.12.55 GetHostName

Synopsis: Return host name

Declaration: function GetHostName : String

Visibility: default

Description: Get the hostname of the machine on which the process is running. An empty string is returned if hostname is not set.

Errors: None.

See also: GetDomainName ([1072](#))

**Listing:** ./olinuxex/ex40.pp

---

**Program** Example40;

*{ Program to demonstrate the GetHostName function. }*

**Uses** oldlinux;

```
begin
  WriteLn ( 'Name of this machine is : ',GetHostName);
end.
```

---

### 31.12.56 GetLocalTimezone

Synopsis: Return local timzeone information

Declaration: procedure GetLocalTimezone(timer: LongInt;var leap\_correct: LongInt;  
var leap\_hit: LongInt)  
procedure GetLocalTimezone(timer: LongInt)

Visibility: default

**Description:** `GetLocalTimeZone` returns the local timezone information. It also initializes the `TZSeconds` variable, which is used to correct the epoch time to local time.

There should never be any need to call this function directly. It is called by the initialization routines of the Linux unit.

See also: `GetTimezoneFile` ([1079](#)), `ReadTimezoneFile` ([1095](#))

### 31.12.57 GetPid

**Synopsis:** Return current process ID

**Declaration:** `function GetPid : LongInt`

**Visibility:** default

**Description:** Get the Process ID of the currently running process.

**Errors:** None.

See also: `GetPPid` ([1077](#))

---

**Listing:** `./olinuxex/ex16.pp`

**Program** `Example16;`

*{ Program to demonstrate the GetPid , GetPPid function . }*

**Uses** `oldlinux;`

**begin**

**WriteLn** ( 'Process Id = ',getpid , ' Parent process Id = ',getppid);

**end.**

---

### 31.12.58 GetPPid

**Synopsis:** Return parent process ID

**Declaration:** `function GetPPid : LongInt`

**Visibility:** default

**Description:** Get the Process ID of the parent process.

**Errors:** None.

See also: `GetPid` ([1077](#))

---

**Listing:** `./olinuxex/ex16.pp`

**Program** `Example16;`

*{ Program to demonstrate the GetPid , GetPPid function . }*

**Uses** `oldlinux;`

**begin**

**WriteLn** ( 'Process Id = ',getpid , ' Parent process Id = ',getppid);

**end.**

---

### 31.12.59 GetPriority

Synopsis: Return process priority

Declaration: `function GetPriority(Which: Integer;Who: Integer) : Integer`

Visibility: default

Description: GetPriority returns the priority with which a process is running. Which process(es) is determined by the Which and Who variables. Which can be one of the pre-defined Prio\_Process, Prio\_PGrp, Prio\_User, in which case Who is the process ID, Process group ID or User ID, respectively.

For an example, see Nice ([1089](#)).

Errors: Error checking must be done on LinuxError, since a priority can be negative.

**sys\_esrch**No process found using which and who.

**sys\_einval**Which was not one of Prio\_Process, Prio\_Grp or Prio\_User.

See also: SetPriority ([1098](#)), Nice ([1089](#))

### 31.12.60 GetTime

Synopsis: Return current system time

Declaration: `procedure GetTime(var hour: Word;var min: Word;var sec: Word;  
var msec: Word;var usec: Word)  
procedure GetTime(var hour: Word;var min: Word;var sec: Word;  
var sec100: Word)  
procedure GetTime(var hour: Word;var min: Word;var sec: Word)`

Visibility: default

Description: Returns the current time of the day, adjusted to local time. Upon return, the parameters are filled with

**hour**Hours since 00:00 today.

**min**minutes in current hour.

**sec**seconds in current minute.

**sec100**hundreds of seconds in current second.

**msec**milliseconds in current second.

**usec**microseconds in current second.

Errors: None

See also: GetEpochTime ([1074](#)), GetDate ([1071](#)), GetDateTime ([1072](#)), EpochToLocal ([1053](#))

**Listing:** ./olinuxex/ex5.pp

---

**Program** Example5;

*{ Program to demonstrate the GetTime function. }*

**Uses** oldlinux;

**Var** Hour, Minute, Second : Word;



---

```

begin
  GetTime (Hour, Minute, Second);
  WriteLn ('Time : ', Hour:2, ': ', Minute:2, ': ', Second:2);
end.

```

---

### 31.12.61 GetTimeOfDay

Synopsis: Return kernel time of day in GMT

Declaration: `procedure GetTimeOfDay (var tv: timeval)`  
`function GetTimeOfDay : LongInt`

Visibility: default

Description: `GetTimeOfDay` returns the number of seconds since 00:00, January 1 1970, GMT in a `timeval` record. This time NOT corrected any way, not taking into account timezones, daylight savings time and so on.

It is simply a wrapper to the kernel system call. To get the local time, `GetTime` ([1078](#)).

Errors: None.

See also: `GetTime` ([1078](#)), `GetTimeOfDay` ([1079](#))

### 31.12.62 GetTimezoneFile

Synopsis: Return name of timezone information file

Declaration: `function GetTimezoneFile : String`

Visibility: default

Description: `GetTimezoneFile` returns the location of the current timezone file. The location of file is determined as follows:

- 1.If `/etc/timezone` exists, it is read, and the contents of this file is returned. This should work on Debian systems.
- 2.If `/usr/lib/zoneinfo/localtime` exists, then it is returned. (this file is a symlink to the timezone file on SuSE systems)
- 3.If `/etc/localtime` exists, then it is returned. (this file is a symlink to the timezone file on RedHat systems)

Errors: If no file was found, an empty string is returned.

See also: `ReadTimezoneFile` ([1095](#))

### 31.12.63 GetUid

Synopsis: Return current user ID

Declaration: `function GetUid : LongInt`

Visibility: default

Description: Get the real user ID of the currently running process.

Errors: None.

See also: [GetEUid \(1074\)](#)

**Listing:** ./olinuxex/ex17.pp

---

**Program** Example17;

*{ Program to demonstrate the GetUid and GetEUid functions. }*

**Uses** oldlinux;

**begin**

**writeln** ( 'User Id = ',getuid,' Effective user Id = ',geteuid);

**end.**

---

### 31.12.64 Glob

Synopsis: Find filenames matching a wildcard pattern

Declaration: `function Glob(const path: PathStr) : pglob`

Visibility: default

Description: Glob returns a pointer to a glob structure which contains all filenames which exist and match the pattern in Path. The pattern can contain wildcard characters, which have their usual meaning.

Errors: Returns nil on error, and `LinuxError` is set.

**sys\_enomem**No memory on heap for glob structure.

**others**As returned by the opendir call, and sys\_readdir.

See also: [GlobFree \(1081\)](#)

**Listing:** ./olinuxex/ex49.pp

---

**Program** Example49;

*{ Program to demonstrate the Glob and GlobFree functions. }*

**Uses** oldlinux;

**Var** G1,G2 : PGlob;

**begin**

    G1:=Glob ( '\*' );

**if** LinuxError=0 **then**

**begin**

            G2:=G1;

**writeln** ( 'Files in this directory : ' );

**While** g2<>Nil **do**

**begin**

**writeln** ( g2^.name );

                    g2:=g2^.next;

**end;**

            GlobFree (g1);

**end;**

**end.**

---

### 31.12.65 Globfree

Synopsis: Free result of Glob (1080) call

Declaration: `procedure Globfree(var p: pglob)`

Visibility: default

Description: Releases the memory, occupied by a pglob structure. P is set to nil.

For an example, see Glob (1080).

Errors: None

See also: Glob (1080)

### 31.12.66 IOCtl

Synopsis: General kernel IOCTL call.

Declaration: `function IOCtl(Handle: LongInt; Ndx: LongInt; Data: Pointer) : Boolean`

Visibility: default

Description: This is a general interface to the Unix/ linux ioctl call. It performs various operations on the filedescriptor Handle. Ndx describes the operation to perform. Data points to data needed for the Ndx function. The structure of this data is function-dependent, so we don't elaborate on this here. For more information on this, see various manual pages under linux.

Errors: Errors are reported in LinuxError. They are very dependent on the used function, that's why we don't list them here

**Listing:** ./olinuxex/ex54.pp

---

**Program** Example54;

**uses** oldlinux;

*{ Program to demonstrate the IOCtl function. }*

**var**

tios : Termios;

**begin**

IOCtl(1, TCGETS, @tios);

**WriteLn**('Input Flags : \$', hexstr(tios.c\_iflag, 8));

**WriteLn**('Output Flags : \$', hexstr(tios.c\_oflag, 8));

**WriteLn**('Line Flags : \$', hexstr(tios.c\_lflag, 8));

**WriteLn**('Control Flags : \$', hexstr(tios.c\_cflag, 8));

**end.**

---

### 31.12.67 IOperm

Synopsis: Set permission on IO ports

Declaration: `function IOperm(From: Cardinal; Num: Cardinal; Value: LongInt) : Boolean`

Visibility: default

**Description:** `IOperm` sets permissions on `Num` ports starting with port `From` to `Value`. The function returns `True` if the call was successful, `False` otherwise.

**Note:**

- This works ONLY as root.
- Only the first `0x03ff` ports can be set.
- When doing a `Fork` (1067), the permissions are reset. When doing a `Execve` (1057) they are kept.

**Errors:** Errors are returned in `LinuxError`

### 31.12.68 IoPL

**Synopsis:** Set I/O privilege level

**Declaration:** `function IoPL(Level: LongInt) : Boolean`

**Visibility:** default

**Description:** `IoPL` sets the I/O privilege level. It is intended for completeness only, one should normally not use it.

### 31.12.69 IsATTY

**Synopsis:** Check if filehandle is a TTY (terminal)

**Declaration:** `function IsATTY(Handle: LongInt) : Boolean`  
`function IsATTY(var f: text) : Boolean`

**Visibility:** default

**Description:** Check if the filehandle described by `f` is a terminal. `f` can be of type

1. `longint` for file handles;
2. `Text` for text variables such as `input` etc.

Returns `True` if `f` is a terminal, `False` otherwise.

**Errors:** No errors are reported

See also: `IOCtl` (1081), `TTYName` (1112)

### 31.12.70 Kill

**Synopsis:** Send a signal to a process

**Declaration:** `function Kill(Pid: LongInt; Sig: LongInt) : Integer`

**Visibility:** default

**Description:** Send a signal `Sig` to a process or process group. If `Pid`>0 then the signal is sent to `Pid`, if it equals -1, then the signal is sent to all processes except process 1. If `Pid`<-1 then the signal is sent to process group -`Pid`. The return value is zero, except in case three, where the return value is the number of processes to which the signal was sent.

**Errors:** `LinuxError` is used to report errors:

**sys\_einval**An invalid signal is sent.

**sys\_esrch**The `Pid` or process group don't exist.

**sys\_eperm**The effective userid of the current process doesn't math the one of process `Pid`.

See also: `SigAction` ([1099](#)), `Signal` ([1100](#))

### 31.12.71 Link

Synopsis: Create a hard link to a file

Declaration: `function Link(OldPath: PathStr;NewPath: PathStr) : Boolean`

Visibility: default

Description: `Link` makes `NewPath` point to the same file als `OldPath`. The two files then have the same inode number. This is known as a 'hard' link. The function returns `True` if the call was succesfull, `False` if the call failed.

Errors: Errors are returned in `LinuxError`.

**sys\_exdev**`OldPath` and `NewPath` are not on the same filesystem.

**sys\_eperm**The filesystem containing `oldpath` and `newpath` doesn't support linking files.

**sys\_eaccess**Write access for the directory containing `Newpath` is disallowed, or one of the directories in `OldPath` or `{NewPath}` has no search (=execute) permission.

**sys\_enoent**A directory entry in `OldPath` or `NewPath` does not exist or is a symbolic link pointing to a non-existent directory.

**sys\_enotdir**A directory entry in `OldPath` or `NewPath` is nor a directory.

**sys\_enomem**Insufficient kernel memory.

**sys\_erofs**The files are on a read-only filesystem.

**sys\_eexist**`NewPath` already exists.

**sys\_mlink**`OldPath` has reached maximal link count.

**sys\_eloop**`OldPath` or `NewPath` has a reference to a circular symbolic link, i.e. a symbolic link, whose expansion points to itself.

**sys\_enospc**The device containing `NewPath` has no room for another entry.

**sys\_eperm**`OldPath` points to `.` or `..` of a directory.

See also: `SymLink` ([1104](#)), `UnLink` ([1113](#))

**Listing:** `./olinuxex/ex21.pp`

---

**Program** `Example21`;

*{ Program to demonstrate the Link and UnLink functions. }*

**Uses** `oldlinux`;

**Var** `F` : `Text`;

`S` : **String**;

**begin**

`Assign (F, 'test.txt');`

`Rewrite (F);`

`WriteLn (F, 'This is written to test.txt');`

```

Close(f);
{ new.txt and test.txt are now the same file }
if not Link ('test.txt', 'new.txt') then
  writeln ('Error when linking !');
{ Removing test.txt still leaves new.txt }
if not Unlink ('test.txt') then
  writeln ('Error when unlinking !');
Assign (f, 'new.txt');
Reset (F);
While not EOF(f) do
  begin
    Readln(F,S);
    Writeln ('> ',s);
  end;
Close (f);
{ Remove new.txt also }
if not Unlink ('new.txt') then
  writeln ('Error when unlinking !');
end.

```

---

### 31.12.72 LocalToEpoch

Synopsis: Convert local time to epoch (unix) time

Declaration: `function LocalToEpoch(year: Word; month: Word; day: Word; hour: Word; minute: Word; second: Word) : LongInt`

Visibility: default

Description: Converts the Local time to epoch time (=Number of seconds since 00:00:00 , January 1, 1970 ).

Errors: None

See also: [GetEpochTime \(1074\)](#), [EpochToLocal \(1053\)](#), [GetTime \(1078\)](#), [GetDate \(1071\)](#)

**Listing:** ./olinuxex/ex4.pp

---

**Program** Example4;

*{ Program to demonstrate the LocalToEpoch function. }*

**Uses** oldlinux;

**Var** year, month, day, hour, minute, second : Word;

```

begin
  Write ('Year      : '); readln(Year);
  Write ('Month     : '); readln(Month);
  Write ('Day        : '); readln(Day);
  Write ('Hour       : '); readln(Hour);
  Write ('Minute    : '); readln(Minute);
  Write ('Seonds   : '); readln(Second);
  Write ('This is  : ');
  Write (LocalToEpoch(year, month, day, hour, minute, second));
  Writeln (' seconds past 00:00 1/1/1980 ');
end.

```

---

**31.12.73 Lstat**

Synopsis: Return information about symbolic link. Do not follow the link

Declaration: `function Lstat (Filename: PathStr; var Info: Stat) : Boolean`

Visibility: default

Description: `LStat` gets information about the link specified in `Path`, and stores it in `Info`, which is of type `stat`. Contrary to `FStat`, it stores information about the link, not about the file the link points to. The function returns `True` if the call was succesfull, `False` if the call failed.

Errors: `LinuxError` is used to report errors.

`sys_enoent` `Path` does not exist.

See also: `FStat` ([1070](#)), `FStat` ([1069](#))

**Listing:** `./olinuxex/ex29.pp`

---

```

program example29;

  { Program to demonstrate the LStat function. }

uses oldlinux;

var f : text;
    i : byte;
    info : stat;

begin
  { Make a file }
  assign (f, 'test.fil');
  rewrite (f);
  for i:=1 to 10 do writeln (f, 'Testline # ', i);
  close (f);
  { Do the call on made file. }
  if not fstat ('test.fil', info) then
    begin
      writeln ('Fstat failed. Errno : ', linuxerror);
      halt (1);
    end;
  writeln;
  writeln ('Result of fstat on file ''test.fil''.');
  writeln ('Inode   : ', info.ino);
  writeln ('Mode    : ', info.mode);
  writeln ('nlink   : ', info.nlink);
  writeln ('uid     : ', info.uid);
  writeln ('gid     : ', info.gid);
  writeln ('rdev    : ', info.rdev);
  writeln ('Size    : ', info.size);
  writeln ('Blksize  : ', info.blksize);
  writeln ('Blocks  : ', info.blocks);
  writeln ('atime   : ', info.atime);
  writeln ('mtime   : ', info.mtime);
  writeln ('ctime   : ', info.ctime);

  if not SymLink ('test.fil', 'test.lnk') then
    writeln ('Link failed ! Errno : ', linuxerror);

```

---

```

if not lstat ('test.lnk',info) then
begin
  writeln('LStat failed. Errno : ',linuxerror);
  halt (1);
end;
writeln;
writeln ('Result of fstat on file ''test.lnk''.');
writeln ('Inode   : ',info.ino);
writeln ('Mode    : ',info.mode);
writeln ('nlink   : ',info.nlink);
writeln ('uid     : ',info.uid);
writeln ('gid     : ',info.gid);
writeln ('rdev    : ',info.rdev);
writeln ('Size    : ',info.size);
writeln ('Blksize  : ',info.blksize);
writeln ('Blocks  : ',info.blocks);
writeln ('atime   : ',info.atime);
writeln ('mtime   : ',info.mtime);
writeln ('ctime   : ',info.ctime);
{ Remove file and link }
erase (f);
unlink ('test.lnk');
end.

```

---

### 31.12.74 mkFifo

Synopsis: Create FIFO (named pipe) in file system

Declaration: `function mkFifo(pathname: String;mode: LongInt) : Boolean`

Visibility: default

Description: `MkFifo` creates named a named pipe in the filesystem, with name `PathName` and mode `Mode`.

Errors: `LinuxError` is used to report errors:

**sys\_enfile**Too many file descriptors for this process.

**sys\_enfile**The system file table is full.

See also: `POpen` ([1092](#)), `MkFifo` ([1086](#))

### 31.12.75 MMap

Synopsis: Create memory map of a file

Declaration: `function MMap(const m: tmmmapargs) : LongInt`

Visibility: default

Description: `MMap` maps or unmaps files or devices into memory. The different fields of the argument `m` determine what and how the `mmap` maps this:

**address**Address where to `mmap` the device. This address is a hint, and may not be followed.

**size**Size (in bytes) of area to be mapped.

**prot**Protection of mapped memory. This is a OR-ed combination of the following constants:



**PROT\_EXEC**The memory can be executed.

**PROT\_READ**The memory can be read.

**PROT\_WRITE**The memory can be written.

**PROT\_NONE**The memory can not be accessed.

**flags**Contains some options for the mmap call. It is an OR-ed combination of the following constants:

**MAP\_FIXED**Do not map at another address than the given address. If the address cannot be used, MMap will fail.

**MAP\_SHARED**Share this map with other processes that map this object.

**MAP\_PRIVATE**Create a private map with copy-on-write semantics.

**MAP\_ANONYMOUS**fd does not have to be a file descriptor.

One of the options MAP\_SHARED and MAP\_PRIVATE must be present, but not both at the same time.

**fd**File descriptor from which to map.

**offset**Offset to be used in file descriptor fd.

The function returns a pointer to the mapped memory, or a -1 in case of an error.

Errors: On error, -1 is returned and LinuxError is set to the error code:

**Sys\_EBADF**fd is not a valid file descriptor and MAP\_ANONYMOUS was not specified.

**Sys\_EACCESS**MAP\_PRIVATE was specified, but fd is not open for reading. Or MAP\_SHARED was asked and PROT\_WRITE is set, fd is not open for writing

**Sys\_EINVAL**One of the record fields Start, length or offset is invalid.

**Sys\_ETXTBUSY**MAP\_DENYWRITE was set but the object specified by fd is open for writing.

**Sys\_EAGAIN**fd is locked, or too much memory is locked.

**Sys\_ENOMEM**Not enough memory for this operation.

See also: MUnMap ([1088](#))

**Listing:** ./olinuxex/ex66.pp

---

**Program** Example66;

*{ Program to demonstrate the MMap function. }*

**Uses** oldlinux;

**Var** S : String;

fd, Len : Longint;

args : tmapargs;

P : PChar;

**begin**

S:= 'This is a string'#0;

Len:=Length(S);

fd:=fdOpen('testfile.txt',Open\_wrOnly or open\_creat);

**If** fd=-1 **then**

**Halt**(1);

**If** fdWrite(fd,S[1],Len)=-1 **then**

**Halt**(2);

fdClose(fd);

fdOpen('testfile.txt',Open\_rdOnly);

---

```

if fd=-1 then
  Halt(3);
  args.address:=0;
  args.offset:=0;
  args.size:=Len+1;
  args.fd:=Fd;
  args.flags:=MAP_PRIVATE;
  args.prot:=PROT_READ or PROT_WRITE;
  P:=Pchar(mmap(args));
  If longint(P)=-1 then
    Halt(4);
  WriteIn('Read in memory :',P);
  fdclose(fd);
  if Not MUnMap(P,Len) Then
    Halt(LinuxError);
end.

```

---

### 31.12.76 MUnMap

Synopsis: Unmap previously mapped memory block

Declaration: `function MUnMap(P: Pointer; Size: LongInt) : Boolean`

Visibility: default

Description: `MUnMap` unmaps the memory block of size `Size`, pointed to by `P`, which was previously allocated with `MMap` (1086).

The function returns `True` if successful, `False` otherwise.

For an example, see `MMap` (1086).

Errors: In case of error the function returns `False` and `LinuxError` is set to an error value. See `MMap` (1086) for possible error values.

See also: `MMap` (1086)

### 31.12.77 NanoSleep

Synopsis: Suspend process for a short time

Declaration: `function NanoSleep(const req: timespec; var rem: timespec) : LongInt`

Visibility: default

Description: `NanoSleep` suspends the process till a time period as specified in `req` has passed. Then the function returns. If the call was interrupted (e.g. by some signal) then the function may return earlier, and `rem` will contain the remaining time till the end of the intended period. In this case the return value will be -1, and `LinuxError` will be set to `EINTR`.

If the function returns without error, the return value is zero.

Errors: If the call was interrupted, -1 is returned, and `LinuxError` is set to `EINTR`. If invalid time values were specified, then -1 is returned and `LinuxError` is set to `EINVAL`.

See also: `Pause` (1091), `Alarm` (1042)

**Listing:** `./olinuxex/ex72.pp`

---

```

program example72;

{ Program to demonstrate the NanoSleep function. }

uses oldlinux;

Var
  Req,Rem : TimeSpec;
  Res : Longint;

begin
  With Req do
    begin
      tv_sec:=10;
      tv_nsec:=100;
    end;
  Write( 'NanoSleep returned : ');
  Flush(Output);
  Res:=( NanoSleep(Req,rem));
  Writeln(res);
  If (res<>0) then
    With rem do
      begin
        Writeln( 'Remaining seconds      : ',tv_sec);
        Writeln( 'Remaining nanoseconds : ',tv_nsec);
      end;
end.

```

---

### 31.12.78 Nice

Synopsis: Set process priority

Declaration: `procedure Nice(N: Integer)`

Visibility: default

Description: `Nice` adds `-N` to the priority of the running process. The lower the priority numerically, the less the process is favored. Only the superuser can specify a negative `N`, i.e. increase the rate at which the process is run.

Errors: Errors are returned in `LinuxError`

**sys\_eperm**A non-superuser tried to specify a negative `N`, i.e. do a priority increase.

See also: `GetPriority` ([1078](#)), `SetPriority` ([1098](#))

**Listing:** `./olinuxex/ex15.pp`

---

```

Program Example15;

{ Program to demonstrate the Nice and Get/SetPriority functions. }

Uses oldlinux;

begin
  writeln ( 'Setting priority to 5 ');
  setpriority ( prio_process , getpid , 5);

```

```
writeln ( 'New priority = ', getpriority (prio_process, getpid));
writeln ( 'Doing nice 10 ');
nice (10);
writeln ( 'New Priority = ', getpriority (prio_process, getpid));
end.
```

---

### 31.12.79 Octal

Synopsis: Convert octal to decimal value

Declaration: `function Octal(l: LongInt) : LongInt`

Visibility: default

Description: `Octal` will convert a number specified as an octal number to it's decimal value.

This is useful for the `Chmod` ([1046](#)) call, where permissions are specified as octal numbers.

Errors: No checking is performed whether the given number is a correct Octal number. e.g. specifying 998 is possible; the result will be wrong in that case.

See also: `Chmod` ([1046](#))

**Listing:** `./olinuxex/ex68.pp`

---

**Program** `Example68;`

*{ Program to demonstrate the Octal function. }*

**Uses** `oldlinux;`

```
begin
  Writeln ( 'Mode 777 : ', Octal(777));
  Writeln ( 'Mode 644 : ', Octal(644));
  Writeln ( 'Mode 755 : ', Octal(755));
end.
```

---

### 31.12.80 OpenDir

Synopsis: Open directory for reading

Declaration: `function OpenDir(f: pchar) : PDir`  
`function OpenDir(f: String) : PDir`

Visibility: default

Description: `OpenDir` opens the directory `f`, and returns a `pdir` pointer to a `Dir` record, which can be used to read the directory structure. If the directory cannot be opened, `nil` is returned.

Errors: Errors are returned in `LinuxError`.

See also: `CloseDir` ([1050](#)), `ReadDir` ([1093](#)), `SeekDir` ([1095](#)), `TellDir` ([1112](#))

**Listing:** `./olinuxex/ex35.pp`

---

**Program** Example35;

*{ Program to demonstrate the  
OpenDir, ReadDir, SeekDir and TellDir functions. }*

**Uses** oldlinux;

**Var** TheDir : PDir;  
ADirent : PDirent;  
Entry : Longint;

**begin**  
TheDir:=OpenDir( ' ./.' );  
**Repeat**  
Entry:=TellDir(TheDir);  
ADirent:=ReadDir ( TheDir);  
**If** ADirent<>Nil **then**  
    **With** ADirent^ **do**  
        **begin**  
            **Writeln** ( 'Entry No : ',Entry);  
            **Writeln** ( 'Inode : ',ino);  
            **Writeln** ( 'Offset : ',off);  
            **Writeln** ( 'Reclen : ',reclen);  
            **Writeln** ( 'Name : ',pchar(@name[0]));  
        **end**;  
**Until** ADirent=Nil;  
**Repeat**  
    **Write** ( 'Entry No. you would like to see again (-1 to stop): ');  
    **ReadLn** ( Entry );  
    **If** Entry<>-1 **then**  
        **begin**  
            SeekDir ( TheDir,Entry );  
            ADirent:=ReadDir ( TheDir);  
            **If** ADirent<>Nil **then**  
                **With** ADirent^ **do**  
                    **begin**  
                        **Writeln** ( 'Entry No : ',Entry);  
                        **Writeln** ( 'Inode : ',ino);  
                        **Writeln** ( 'Offset : ',off);  
                        **Writeln** ( 'Reclen : ',reclen);  
                        **Writeln** ( 'Name : ',pchar(@name[0]));  
                    **end**;  
            **end**;  
    **Until** Entry=-1;  
    CloseDir ( TheDir);  
**end**.

---

### 31.12.81 Pause

**Synopsis:** Wait for a signal

**Declaration:** procedure Pause

**Visibility:** default

**Description:** Pause puts the process to sleep and waits until the application receives a signal. If a signal handler is installed for the received sigal, the handler will be called and after that pause will return control to

the process.

For an example, see Alarm (1042).

### 31.12.82 PClose

Synopsis: Close file opened with POpen (1092)

Declaration: `function PClose(var F: text) : LongInt`  
`function PClose(var F: File) : LongInt`

Visibility: default

Description: PClose closes a file opened with POpen (1092). It waits for the command to complete, and then returns the exit status of the command.

For an example, see POpen (1092)

Errors: `LinuxError` is used to report errors. If it is different from zero, the exit status is not valid.

See also: POpen (1092)

### 31.12.83 POpen

Synopsis: Pipe file to standard input/output of program

Declaration: `procedure POpen(var F: text; const Prog: String; rw: Char)`  
`procedure POpen(var F: File; const Prog: String; rw: Char)`

Visibility: default

Description: POpen runs the command specified in `Cmd`, and redirects the standard in or output of the command to the other end of the pipe `F`. The parameter `rw` indicates the direction of the pipe. If it is set to 'W', then `F` can be used to write data, which will then be read by the command from `stdin`. If it is set to 'R', then the standard output of the command can be read from `F`. `F` should be reset or rewritten prior to using it. `F` can be of type `Text` or `File`. A file opened with POpen can be closed with `Close`, but also with `PClose` (1092). The result is the same, but `PClose` returns the exit status of the command `Cmd`.

Errors: Errors are reported in `LinuxError` and are essentially those of the `Execve`, `Dup` and `AssignPipe` commands.

See also: `AssignPipe` (1042), `PClose` (1092)

**Listing:** `./olinuxex/ex37.pp`

---

**Program** `Example37`;

*{ Program to demonstrate the Popen function. }*

**uses** `oldlinux`;

**var** `f : text;`  
`i : longint;`

**begin**

`writeln ('Creating a shell script to which echoes its arguments');`  
`writeln ('and input back to stdout');`  
`assign (f, 'test21a');`

---

```

rewrite (f);
writeln (f, '#!/bin/sh');
writeln (f, 'echo this is the child speaking.... ');
writeln (f, 'echo got arguments \'$*\'' );
writeln (f, 'cat');
writeln (f, 'exit 2');
writeln (f);
close (f);
chmod ('test21a', octal (755));
popen (f, './test21a arg1 arg2', 'W');
if linuxerror <> 0 then
    writeln ('error from POpen : Linuxerror : ', Linuxerror);
for i:=1 to 10 do
    writeln (f, 'This is written to the pipe, and should appear on stdout. ');
Flush(f);
Writeln ('The script exited with status : ', PClose (f));
writeln;
writeln ('Press <return> to remove shell script. ');
readln;
assign (f, 'test21a ');
erase (f)
end.

```

---

### 31.12.84 ReadDir

Synopsis: Read entry from directory

Declaration: `function ReadDir(p: PDir) : pdirent`

Visibility: default

Description: `ReadDir` reads the next entry in the directory pointed to by `p`. It returns a `pdirent` pointer to a structure describing the entry. If the next entry can't be read, `Nil` is returned.

For an example, see `OpenDir` ([1090](#)).

Errors: Errors are returned in `LinuxError`.

See also: `CloseDir` ([1050](#)), `OpenDir` ([1090](#)), `SeekDir` ([1095](#)), `TellDir` ([1112](#))

### 31.12.85 ReadLink

Synopsis: Read destination of symbolic link

Declaration: `function ReadLink(name: pchar; linkname: pchar; maxlen: LongInt) : LongInt`  
`function ReadLink(name: PathStr) : PathStr`

Visibility: default

Description: `ReadLink` returns the file the symbolic link `name` is pointing to. The first form of this function accepts a buffer `linkname` of length `maxlen` where the filename will be stored. It returns the actual number of characters stored in the buffer.

The second form of the function returns simply the name of the file.

Errors: On error, the first form of the function returns -1; the second one returns an empty string. `LinuxError` is set to report errors:

**SYS\_ENOTDIR** part of the path in `Name` is not a directory.

**SYS\_EINVAL**maxlen is not positive, or the file is not a symbolic link.

**SYS\_ENAMETOOLONG**A pathname, or a component of a pathname, was too long.

**SYS\_ENOENT**the link name does not exist.

**SYS\_EACCES**No permission to search a directory in the path

**SYS\_ELOOP**Too many symbolic links were encountered in translating the pathname.

**SYS\_EIO**An I/O error occurred while reading from the file system.

**SYS\_EFAULT**The buffer is not part of the the process's memory space.

**SYS\_ENOMEM**Not enough kernel memory was available.

See also: SymLink ([1104](#))

**Listing:** ./olinuxex/ex62.pp

---

**Program** Example62;

*{ Program to demonstrate the ReadLink function. }*

**Uses** oldlinux;

**Var** F : Text;  
      S : **String**;

**begin**  
  Assign (F, 'test.txt');  
  **Rewrite** (F);  
  **Writeln** (F, 'This is written to test.txt');  
  Close(f);  
  *{ new.txt and test.txt are now the same file }*  
  **if not** SymLink ('test.txt', 'new.txt') **then**  
    **writeln** ('Error when symlinking !');  
  S:=ReadLink('new.txt');  
  **if** S='' **then**  
    **Writeln** ('Error reading link !')  
  **Else**  
    **Writeln** ('Link points to : ',S);  
  *{ Now remove links }*  
  **if not** Unlink ('new.txt') **then**  
    **Writeln** ('Error when unlinking !');  
  **if not** Unlink ('test.txt') **then**  
    **Writeln** ('Error when unlinking !');  
**end.**

---

### 31.12.86 ReadPort

**Declaration:** procedure ReadPort (Port: LongInt; var Value: Byte)  
                  procedure ReadPort (Port: LongInt; var Value: Word)  
                  procedure ReadPort (Port: LongInt; var Value: LongInt)

Visibility: default

### 31.12.87 ReadPortB

**Declaration:** function ReadPortB (Port: LongInt) : Byte  
                  procedure ReadPortB (Port: LongInt; var Buf; Count: LongInt)



Visibility: default

### 31.12.88 ReadPortL

Declaration: `function ReadPortL(Port: LongInt) : LongInt`  
`procedure ReadPortL(Port: LongInt; var Buf; Count: LongInt)`

Visibility: default

### 31.12.89 ReadPortW

Declaration: `function ReadPortW(Port: LongInt) : Word`  
`procedure ReadPortW(Port: LongInt; var Buf; Count: LongInt)`

Visibility: default

### 31.12.90 ReadTimezoneFile

Synopsis: Read the timezone file and initialize time routines

Declaration: `procedure ReadTimezoneFile(fn: String)`

Visibility: default

Description: `ReadTimezoneFile` reads the timezone file `fn` and initializes the local time routines based on the information found there.

There should be no need to call this function. The initialization routines of the linux unit call this routine at unit startup.

Errors: None.

See also: `GetTimezoneFile` ([1079](#)), `GetLocalTimezone` ([1076](#))

### 31.12.91 SeekDir

Synopsis: Seek to position in directory

Declaration: `procedure SeekDir(p: PDir; off: LongInt)`

Visibility: default

Description: `SeekDir` sets the directory pointer to the `off`-th entry in the directory structure pointed to by `p`.

For an example, see `OpenDir` ([1090](#)).

Errors: Errors are returned in `LinuxError`.

See also: `CloseDir` ([1050](#)), `ReadDir` ([1093](#)), `OpenDir` ([1090](#)), `TellDir` ([1112](#))

### 31.12.92 Select

Synopsis: Wait for events on file descriptors

Declaration: `function Select(N: LongInt; readfds: pfdset; writefds: pfdset;`  
`exceptfds: pfdset; Timeout: ptimeval) : LongInt`  
`function Select(N: LongInt; readfds: pfdset; writefds: pfdset;`  
`exceptfds: pfdset; Timeout: LongInt) : LongInt`

Visibility: default

**Description:** `Select` checks one of the file descriptors in the `FDSet`s to see if its status changed.

`readfds`, `writfds` and `exceptfds` are pointers to arrays of 256 bits. If you want a file descriptor to be checked, you set the corresponding element in the array to 1. The other elements in the array must be set to zero. Three arrays are passed : The entries in `readfds` are checked to see if characters become available for reading. The entries in `writfds` are checked to see if it is OK to write to them, while entries in `exceptfds` are checked to see if an exception occurred on them.

You can use the functions `FD_ZERO` (1065), `FD_Clr` (1064), `FD_Set` (1065) or `FD_IsSet` (1064) to manipulate the individual elements of a set.

The pointers can be `Nil`.

`N` is the largest index of a nonzero entry plus 1. (= the largest file-descriptor + 1).

`Timeout` can be used to set a time limit. If `Timeout` can be two types :

1. `Timeout` is of type `PTime` and contains a zero time, the call returns immediately. If `Timeout` is `Nil`, the kernel will wait forever, or until a status changed.
2. `Timeout` is of type `Longint`. If it is -1, this has the same effect as a `Timeout` of type `PTime` which is `Nil`. Otherwise, `Timeout` contains a time in milliseconds.

When the `Timeout` is reached, or one of the file descriptors has changed, the `Select` call returns. On return, it will have modified the entries in the array which have actually changed, and it returns the number of entries that have been changed. If the timeout was reached, and no descriptor changed, zero is returned; The arrays of indexes are undefined after that. On error, -1 is returned.

**Errors:** On error, the function returns -1, and Errors are reported in `LinuxError` :

**SYS\_EBADF** An invalid descriptor was specified in one of the sets.

**SYS\_EINTR** A non blocked signal was caught.

**SYS\_EINVAL** `N` is negative or too big.

**SYS\_ENOMEM** `Select` was unable to allocate memory for its internal tables.

See also: `SelectText` (1097), `GetFS` (1075), `FD_ZERO` (1065), `FD_Clr` (1064), `FD_Set` (1065), `FD_IsSet` (1064)

**Listing:** `./olinuxex/ex33.pp`

**Program** `Example33`;

*{ Program to demonstrate the Select function. }*

**Uses** `oldlinux`;

**Var** `FDS` : `FDSet`;

**begin**

```

  FD_Zero (FDS);
  FD_Set (0,FDS);
  Writeln ('Press the <ENTER> to continue the program. ');
  { Wait until File descriptor 0 (=Input) changes }
  Select (1,@FDS,nil,nil,nil);
  { Get rid of <ENTER> in buffer }
  readln;
  Writeln ('Press <ENTER> key in less than 2 seconds... ');
  FD_Zero (FDS);

```

---

```

FD_Set (0,FDS);
if Select (1,@FDS,nil,nil,2000)>0 then
  Writeln ('Thank you !')
  { FD_ISSET(0,FDS) would be true here. }
else
  Writeln ('Too late !');
end.

```

---

### 31.12.93 SelectText

Synopsis: Wait for event on typed ontyped file.

Declaration: `function SelectText (var T: Text; Timeout: ptimeval) : LongInt`  
`function SelectText (var T: Text; Timeout: LongInt) : LongInt`

Visibility: default

Description: `SelectText` executes the `Select` ([1095](#)) call on a file of type `Text`. You can specify a timeout in `Timeout`. The `SelectText` call determines itself whether it should check for read or write, depending on how the file was opened : With `Reset` it is checked for reading, with `Rewrite` and `Append` it is checked for writing.

Errors: See `Select` ([1095](#)). `SYS_EBADF` can also mean that the file wasn't opened.

See also: `Select` ([1095](#)), `GetFS` ([1075](#))

### 31.12.94 SetDate

Synopsis: Set the current system date.

Declaration: `function SetDate (Year: Word; Month: Word; Day: Word) : Boolean`

Visibility: default

Description: `SetDate` sets the system date to year, month, day. This is the kernel date, so it is in GMT. The time is not touched. The function returns `True` if the call was executed corretly, `False` otherwise.

**Remark:** You must be root to execute this call.

Errors: Errors are returned in `LinuxError` ([1040](#))

See also: `GetDate` ([1071](#)), `SetTime` ([1098](#)), `SetDateTime` ([1097](#))

### 31.12.95 SetDateTime

Synopsis: Set the current system date and time

Declaration: `function SetDateTime (Year: Word; Month: Word; Day: Word; hour: Word;`  
`minute: Word; second: Word) : Boolean`

Visibility: default

Description: `SetDate` sets the system date and time to year, month, day, hour, min, Sec. This is the kernel date/time, so it is in GMT. The time is not touched. The function returns `True` if the call was executed corretly, `False` otherwise.

**Remark:** You must be root to execute this call.

Errors: Errors are returned in `LinuxError` ([1040](#))

See also: `SetDate` ([1097](#)), `SetTime` ([1098](#)), `GetDateTime` ([1072](#))

### 31.12.96 SetPriority

Synopsis: Set process priority

Declaration: `procedure SetPriority(Which: Integer;Who: Integer;What: Integer)`

Visibility: default

Description: SetPriority sets the priority with which a process is running. Which process(es) is determined by the Which and Who variables. Which can be one of the pre-defined constants:

**Prio\_Process**Who is interpreted as process ID

**Prio\_PGrp**Who is interpreted as process group ID

**Prio\_User**Who is interpreted as user ID

Prio is a value in the range -20 to 20.

For an example, see Nice (1089).

Errors: Error checking must be done on `LinuxError`, since a priority can be negative.

**sys\_esrch**No process found using which and who.

**sys\_einval**Which was not one of Prio\_Process, Prio\_Grp or Prio\_User.

**sys\_eperm**A process was found, but neither its effective or real user ID match the effective user ID of the caller.

**sys\_eaccess**A non-superuser tried to a priority increase.

See also: GetPriority (1078), Nice (1089)

### 31.12.97 SetTime

Synopsis: Set the current system time.

Declaration: `function SetTime(Hour: Word;Min: Word;Sec: Word) : Boolean`

Visibility: default

Description: SetTime sets the system time to hour, min, Sec. This is the kernel time, so it is in GMT. The date is not touched. The function returns `True` if the call was executed correctly, `False` otherwise.

**Remark:** You must be root to execute this call.

Errors: Errors are returned in `LinuxError` (1040)

See also: GetTime (1078), SetDate (1097), SetDateTime (1097)

### 31.12.98 Shell

Synopsis: Execute and feed command to system shell

Declaration: `function Shell(const Command: String) : LongInt`  
`function Shell(const Command: AnsiString) : LongInt`

Visibility: default

Description: Shell invokes the bash shell (`/bin/sh`), and feeds it the command `Command` (using the `-c` option). The function then waits for the command to complete, and then returns the exit status of the command, or 127 if it could not complete the `Fork` (1067) or `Execve` (1057) calls.

Errors: Errors are reported in `LinuxError`.

See also: `POpen` ([1092](#)), `Fork` ([1067](#)), `Execve` ([1057](#))

**Listing:** `./olinuxex/ex56.pp`

---

```

program example56;

uses oldlinux;

{ Program to demonstrate the Shell function }

Var S : Longint;

begin
  WriteLn ( 'Output of ls -l *.pp' );
  S:=Shell ( 'ls -l *.pp' );
  WriteLn ( 'Command exited with status : ',S);
end.

```

---

### 31.12.99 SigAction

Synopsis: Install signal handler

Declaration: `procedure SigAction(Signum: LongInt; Act: PSigActionRec;  
OldAct: PSigActionRec)`

Visibility: default

Description: Changes the action to take upon receipt of a signal. `Act` and `Oldact` are pointers to a `SigActionRec` record. `SigNum` specifies the signal, and can be any signal except **SIGKILL** or **SIGSTOP**.

If `Act` is non-nil, then the new action for signal `SigNum` is taken from it. If `OldAct` is non-nil, the old action is stored there. `Sa_Handler` may be `SIG_DFL` for the default action or `SIG_IGN` to ignore the signal. `Sa_Mask` Specifies which signals should be ignored during the execution of the signal handler. `Sa_Flags` Specifies a series of flags which modify the behaviour of the signal handler. You can 'or' none or more of the following :

**SA\_NOCLDSTOP** If `signum` is **SIGCHLD** do not receive notification when child processes stop.

**SA\_ONESHOT** or **SA\_RESETHAND** Restore the signal action to the default state once the signal handler has been called.

**SA\_RESTART** For compatibility with BSD signals.

**SA\_NOMASK** or **SA\_NODEFER** Do not prevent the signal from being received from within its own signal handler.

Errors: `LinuxError` is used to report errors.

**sys\_einval** an invalid signal was specified, or it was **SIGKILL** or **SIGSTOP**.

**sys\_efault** `Act`, `OldAct` point outside this process address space

**sys\_eintr** System call was interrupted.

See also: `SigProcMask` ([1101](#)), `SigPending` ([1101](#)), `SigSuspend` ([1103](#)), `Kill` ([1082](#))

**Listing:** `./olinuxex/ex57.pp`

---

```

Program example57;

{ Program to demonstrate the SigAction function.}

{
do a kill -USR1 pid from another terminal to see what happens.
replace pid with the real pid of this program.
You can get this pid by running 'ps'.
}

uses oldlinux;

Var
    oa, na : PSigActionRec;

Procedure DoSig(sig : Longint); cdecl;

begin
    writeln( 'Receiving signal: ', sig );
end;

begin
    new(na);
    new(oa);
    na^.Handler.sh:=@DoSig;
    na^.Sa_Mask:=0;
    na^.Sa_Flags:=0;
    na^.Sa_Restorer:=Nil;
    SigAction(SigUsr1, na, oa);
    if LinuxError <> 0 then
        begin
            writeln( 'Error: ', linuxerror, '.' );
            halt(1);
        end;
    Writeln( 'Send USR1 signal or press <ENTER> to exit' );
    readln;
end.

```

---

### 31.12.100 Signal

Synopsis: Install signal handler (deprecated)

Declaration: `function Signal(Signum: LongInt; Handler: SignalHandler) : SignalHandler`

Visibility: default

Description: `Signal` installs a new signal handler for signal `SigNum`. This call has the same functionality as the **SigAction** call. The return value for `Signal` is the old signal handler, or nil on error.

Errors: `LinuxError` is used to report errors :

**SIG\_ERR** An error occurred.

See also: `SigAction` ([1099](#)), `Kill` ([1082](#))

**Listing:** ./olinuxex/ex58.pp

---

**Program** example58;

```
{ Program to demonstrate the Signal function.}

{
do a kill -USR1 pid from another terminal to see what happens.
replace pid with the real pid of this program.
You can get this pid by running 'ps'.
}

uses oldlinux;

Procedure DoSig(sig : Longint);cdecl;

begin
  writeln('Receiving signal: ',sig);
end;

begin
  SigNal(SigUsr1,@DoSig);
  if LinuxError<>0 then
    begin
      writeln('Error: ',linuxerror, '.');
      halt(1);
    end;
  Writeln ('Send USR1 signal or press <ENTER> to exit');
  readln;
end.
```

---

### 31.12.101 SigPending

**Synopsis:** Return set of currently pending signals

**Declaration:** `function SigPending : SigSet`

**Visibility:** default

**Description:** Sigpending allows the examination of pending signals (which have been raised while blocked.) The signal mask of pending signals is returned.

**Errors:** None

**See also:** SigAction ([1099](#)), SigProcMask ([1101](#)), SigSuspend ([1103](#)), Signal ([1100](#)), Kill ([1082](#))

### 31.12.102 SigProcMask

**Synopsis:** Set list of blocked signals

**Declaration:** `procedure SigProcMask(How: LongInt; SSet: PSigSet; OldSSet: PSigSet)`

**Visibility:** default

**Description:** Changes the list of currently blocked signals. The behaviour of the call depends on How :

**SIG\_BLOCK**The set of blocked signals is the union of the current set and the SSet argument.

**SIG\_UNBLOCK**The signals in SSet are removed from the set of currently blocked signals.

**SIG\_SETMASK**The list of blocked signals is set so SSet.

If OldSSet is non-nil, then the old set is stored in it.

Errors: `LinuxError` is used to report errors.

**sys\_efault**SSet or OldSSet point to an adress outside the range of the process.

**sys\_eintr**System call was interrupted.

See also: `SigAction` (1099), `SigPending` (1101), `SigSuspend` (1103), `Kill` (1082)

### 31.12.103 SigRaise

Synopsis: Raise a signal (send to current process)

Declaration: `procedure SigRaise(Sig: Integer)`

Visibility: default

Description: `SigRaise` sends a `Sig` signal to the current process.

Errors: None.

See also: `Kill` (1082), `GetPid` (1077)

**Listing:** `./olinuxex/ex65.pp`

---

**Program** `example64`;

*{ Program to demonstrate the SigRaise function. }*

**uses** `oldlinux`;

**Var**

`oa, na : PSigActionRec;`

**Procedure** `DoSig(sig : Longint); cdecl;`

**begin**

`writeln('Receiving signal: ', sig);`

**end;**

**begin**

`new(na);`

`new(oa);`

`na^.handler.sh:=@DoSig;`

`na^.Sa_Mask:=0;`

`na^.Sa_Flags:=0;`

`na^.Sa_Restorer:= Nil;`

`SigAction(SigUsr1, na, oa);`

**if** `LinuxError <> 0` **then**

**begin**

`writeln('Error: ', linuxerror, '.');`

`halt(1);`

**end;**

`Writeln('Sending USR1 (', sigusr1, ') signal to self.');`

`SigRaise(sigusr1);`

**end.**

---



### 31.12.104 SigSuspend

Synopsis: Set signal mask and suspend process till signal is received

Declaration: `procedure SigSuspend(Mask: SigSet)`

Visibility: default

Description: SigSuspend temporarily replaces the signal mask for the process with the one given in Mask, and then suspends the process until a signal is received.

Errors: None

See also: SigAction ([1099](#)), SigProcMask ([1101](#)), SigPending ([1101](#)), Signal ([1100](#)), Kill ([1082](#))

### 31.12.105 StringToPPChar

Synopsis: Split string in list of null-terminated strings

Declaration: `function StringToPPChar(var S: String) : ppchar`  
`function StringToPPChar(var S: AnsiString) : ppchar`  
`function StringToPPChar(S: Pchar) : ppchar`

Visibility: default

Description: StringToPPChar splits the string S in words, replacing any whitespace with zero characters. It returns a pointer to an array of pchars that point to the first letters of the words in S. This array is terminated by a Nil pointer.

The function does *not* add a zero character to the end of the string unless it ends on whitespace.

The function reserves memory on the heap to store the array of PChar; The caller is responsible for freeing this memory.

This function can be called to create arguments for the various Exec calls.

Errors: None.

See also: CreateShellArgV ([1051](#)), Execve ([1057](#)), Execv ([1056](#))

**Listing:** ./olinuxex/ex70.pp

---

**Program** Example70;

*{ Program to demonstrate the StringToPPchar function. }*

**Uses** oldlinux;

**Var** S : **String**;  
P : PPChar;  
I : longint;

**begin**  
*// remark whitespace at end.*  
S:= 'This is a string with words. ';  
P:= StringToPPChar(S);  
I:=0;  
**While** P[I]<>Nil **do**  
  **begin**  
    **Writeln**( 'Word ',I, ' : ',P[I]);  
    **Inc**(I);  
  **end**

```

    end;
    FreeMem(P, i*SizeOf(Pchar));
end.

```

---

### 31.12.106 SymLink

Synopsis: Create a symbolic link

Declaration: `function SymLink(OldPath: PathStr; NewPath: PathStr) : Boolean`

Visibility: default

Description: `SymLink` makes `Newpath` point to the file in `OldPath`, which doesn't necessarily exist. The two files DO NOT have the same inode number. This is known as a 'soft' link.

The permissions of the link are irrelevant, as they are not used when following the link. Ownership of the file is only checked in case of removal or renaming of the link.

The function returns `True` if the call was succesfull, `False` if the call failed.

Errors: Errors are returned in `LinuxError`.

**sys\_eperm** The filesystem containing `oldpath` and `newpath` does not support linking files.

**sys\_eaccess** Write access for the directory containing `Newpath` is disallowed, or one of the directories in `OldPath` or `NewPath` has no search (=execute) permission.

**sys\_enoent** A directory entry in `OldPath` or `NewPath` does not exist or is a symbolic link pointing to a non-existent directory.

**sys\_enotdir** A directory entry in `OldPath` or `NewPath` is nor a directory.

**sys\_enomem** Insufficient kernel memory.

**sys\_erofs** The files are on a read-only filesystem.

**sys\_eexist** `NewPath` already exists.

**sys\_eloop** `OldPath` or `NewPath` has a reference to a circular symbolic link, i.e. a symbolic link, whose expansion points to itself.

**sys\_enospc** The device containing `NewPath` has no room for another entry.

See also: [Link \(1083\)](#), [UnLink \(1113\)](#), [ReadLink \(1093\)](#)

**Listing:** `./olinuxex/ex22.pp`

**Program** `Example22;`

*{ Program to demonstrate the SymLink and UnLink functions. }*

**Uses** `oldlinux;`

**Var** `F : Text;`  
`S : String;`

**begin**  
`Assign (F, 'test.txt');`  
`Rewrite (F);`  
`Writeln (F, 'This is written to test.txt');`  
`Close(f);`  
*{ new.txt and test.txt are now the same file }*  
**if not** `SymLink ('test.txt', 'new.txt')` **then**

---

```

    writeln ( 'Error when symlinking !');
  { Removing test.txt still leaves new.txt
    Pointing now to a non-existent file ! }
  if not Unlink ( 'test.txt') then
    writeln ( 'Error when unlinking !');
  Assign (f, 'new.txt');
  { This should fail, since the symbolic link
    points to a non-existent file ! }
  {$i-}
  Reset (F);
  {$i+}
  if IOResult=0 then
    writeln ( 'This shouldn''t happen');
  { Now remove new.txt also }
  if not Unlink ( 'new.txt') then
    writeln ( 'Error when unlinking !');
end.

```

---

### 31.12.107 SysCall

Synopsis: Execute system call.

Declaration: `function SysCall(callnr: LongInt; var regs: SysCallRegs) : LongInt`

Visibility: default

Description: `SysCall` can be used to execute a direct system call. The call parameters must be encoded in `regs` and the call number must be specified by `callnr`. The call result is returned, and any modified registers are in `regs`

Errors: None.

See also: `SysCallRegs` ([1036](#))

### 31.12.108 Sysinfo

Synopsis: Return kernel system information

Declaration: `function Sysinfo(var Info: TSysinfo) : Boolean`

Visibility: default

Description: `SysInfo` returns system information in `Info`. Returned information in `Info` includes:

**uptime** Number of seconds since boot.

**loads** 1, 5 and 15 minute load averages.

**totalram** total amount of main memory.

**freeram** amount of free memory.

**sharedram** amount of shared memory.

**bufferram** amount of memory used by buffers.

**totalswap** total amount of swapspace.

**freeswap** amount of free swapspace.

**procs** number of current processes.

Errors: None.

See also: Uname ([1113](#))

**Listing:** ./olinuxex/ex64.pp

---

```

program Example64;

{ Example to demonstrate the SysInfo function }

Uses oldlinux;

Function Mb(L : Longint) : longint;

begin
  Mb:=L div (1024*1024);
end;

Var Info : TSysInfo;
      D,M,Secs,H : longint;

begin
  If Not SysInfo(Info) then
    Halt(1);
  With Info do
    begin
      D:=Uptime div (3600*24);
      UpTime:=UpTime mod (3600*24);
      h:=uptime div 3600;
      uptime:=uptime mod 3600;
      m:=uptime div 60;
      secs:=uptime mod 60;
      Writeln( 'Uptime : ',d,'days', 'h,' hours', 'm,' min', 'secs,' s.' );
      Writeln( 'Loads   : ',Loads[1], '/' ,Loads[2], '/' ,Loads[3]);
      Writeln( 'Total Ram   : ',Mb(totalram), 'Mb.' );
      Writeln( 'Free Ram    : ',Mb(freeram), 'Mb.' );
      Writeln( 'Shared Ram  : ',Mb(sharedram), 'Mb.' );
      Writeln( 'Buffer Ram  : ',Mb(bufferram), 'Mb.' );
      Writeln( 'Total Swap  : ',Mb(totalswap), 'Mb.' );
      Writeln( 'Free Swap   : ',Mb(freeswap), 'Mb.' );
    end;
  end.

```

---

### 31.12.109 S\_ISBLK

Synopsis: Is file a block device

Declaration: function S\_ISBLK(m: Word) : Boolean

Visibility: default

Description: S\_ISBLK checks the file mode m to see whether the file is a block device file. If so it returns True.

See also: FStat ([1070](#)), S\_ISLNK ([1107](#)), S\_ISREG ([1108](#)), S\_ISDIR ([1107](#)), S\_ISCHR ([1107](#)), S\_ISFIFO ([1107](#)), S\_ISSOCK ([1108](#))

### 31.12.110 S\_ISCHR

Synopsis: Is file a character device

Declaration: `function S_ISCHR(m: Word) : Boolean`

Visibility: default

Description: `S_ISCHR` checks the file mode `m` to see whether the file is a character device file. If so it returns `True`.

See also: `FStat` (1070), `S_ISLNK` (1107), `S_ISREG` (1108), `S_ISDIR` (1107), `S_ISBLK` (1106), `S_ISFIFO` (1107), `S_ISSOCK` (1108)

### 31.12.111 S\_ISDIR

Synopsis: Is file a directory

Declaration: `function S_ISDIR(m: Word) : Boolean`

Visibility: default

Description: `S_ISDIR` checks the file mode `m` to see whether the file is a directory. If so it returns `True`

See also: `FStat` (1070), `S_ISLNK` (1107), `S_ISREG` (1108), `S_ISCHR` (1107), `S_ISBLK` (1106), `S_ISFIFO` (1107), `S_ISSOCK` (1108)

### 31.12.112 S\_ISFIFO

Synopsis: Is file a FIFO

Declaration: `function S_ISFIFO(m: Word) : Boolean`

Visibility: default

Description: `S_ISFIFO` checks the file mode `m` to see whether the file is a fifo (a named pipe). If so it returns `True`.

See also: `FStat` (1070), `S_ISLNK` (1107), `S_ISREG` (1108), `S_ISCHR` (1107), `S_ISBLK` (1106), `S_ISDIR` (1107), `S_ISSOCK` (1108)

### 31.12.113 S\_ISLNK

Synopsis: Is file a symbolic link

Declaration: `function S_ISLNK(m: Word) : Boolean`

Visibility: default

Description: `S_ISLNK` checks the file mode `m` to see whether the file is a symbolic link. If so it returns `True`

See also: `FStat` (1070), `S_ISFIFO` (1107), `S_ISREG` (1108), `S_ISCHR` (1107), `S_ISBLK` (1106), `S_ISDIR` (1107), `S_ISSOCK` (1108)

**Listing:** `./olinuxex/ex53.pp`

---

```

Program Example53;

{ Program to demonstrate the S_ISLNK function. }

Uses oldlinux;

Var Info : Stat;

begin
  if LStat ( paramstr(1),info ) then
    begin
      if S_ISLNK(info.mode) then
        Writeln ( 'File is a link' );
      if S_ISREG(info.mode) then
        Writeln ( 'File is a regular file' );
      if S_ISDIR(info.mode) then
        Writeln ( 'File is a directory' );
      if S_ISCHR(info.mode) then
        Writeln ( 'File is a character device file' );
      if S_ISBLK(info.mode) then
        Writeln ( 'File is a block device file' );
      if S_ISFIFO(info.mode) then
        Writeln ( 'File is a named pipe (FIFO)' );
      if S_ISSOCK(info.mode) then
        Writeln ( 'File is a socket' );
      end;
    end.

```

---

### 31.12.114 S\_ISREG

Synopsis: Is file a regular file

Declaration: `function S_ISREG(m: Word) : Boolean`

Visibility: default

Description: S\_ISREG checks the file mode `m` to see whether the file is a regular file. If so it returns `True`

See also: FStat ([1070](#)), S\_ISFIFO ([1107](#)), S\_ISLNK ([1107](#)), S\_ISCHR ([1107](#)), S\_ISBLK ([1106](#)), S\_ISDIR ([1107](#)), S\_ISSOCK ([1108](#))

### 31.12.115 S\_ISSOCK

Synopsis: Is file a unix socket

Declaration: `function S_ISSOCK(m: Word) : Boolean`

Visibility: default

Description: S\_ISSOCK checks the file mode `m` to see whether the file is a socket. If so it returns `True`.

See also: FStat ([1070](#)), S\_ISFIFO ([1107](#)), S\_ISLNK ([1107](#)), S\_ISCHR ([1107](#)), S\_ISBLK ([1106](#)), S\_ISDIR ([1107](#)), S\_ISREG ([1108](#))

**31.12.116 TCDrain**

Synopsis: Terminal control: Wait till all data was transmitted

Declaration: `function TCDrain(fd: LongInt) : Boolean`

Visibility: default

Description: `TCDrain` waits until all data to file descriptor `Fd` is transmitted.

The function returns `True` if the call was succesfull, `False` otherwise.

Errors: Errors are reported in `LinuxError`

See also: `TCFlow` (1109), `TCFlush` (1109), `TCGetAttr` (1110), `TCGetPGrp` (1110), `TCSendBreak` (1111), `TCSetAttr` (1111), `TCSetPGrp` (1112), `TTYName` (1112), `IsATTY` (1082)

**31.12.117 TCFlow**

Synopsis: Terminal control: Suspend transmission of data

Declaration: `function TCFlow(fd: LongInt;act: LongInt) : Boolean`

Visibility: default

Description: `TCFlow` suspends/resumes transmission or reception of data to or from the file descriptor `Fd`, depending on the action `Act`.

This can be one of the following pre-defined values:

**TCOOFF**suspend reception/transmission

**TCOON**resume reception/transmission

**TCIOFF**transmit a stop character to stop input from the terminal

**TCION**transmit start to resume input from the terminal.

The function returns `True` if the call was succesfull, `False` otherwise.

Errors: Errors are reported in `LinuxError`.

See also: `TCDrain` (1109), `TCFlow` (1109), `TCGetAttr` (1110), `TCGetPGrp` (1110), `TCSendBreak` (1111), `TCSetAttr` (1111), `TCSetPGrp` (1112), `TTYName` (1112), `IsATTY` (1082)

**31.12.118 TCFlush**

Synopsis: Terminal control: Discard data buffer

Declaration: `function TCFlush(fd: LongInt;qsel: LongInt) : Boolean`

Visibility: default

Description: `TCFlush` discards all data sent or received to/from file descriptor `fd`. `QSel` indicates which queue should be discard. It can be one of the following pre-defined values :

**TCIFLUSH**input buffer

**TCOFLUSH**output buffer

**TCIOFLUSH**both input and output buffers

The function returns `True` if the call was succesfull, `False` otherwise.

Errors: Errors are reported in `LinuxError`.

See also: `TCDrain` (1109), `TCFlow` (1109), `TCGetAttr` (1110), `TCGetPGrp` (1110), `TCSendBreak` (1111), `TCSetAttr` (1111), `TCSetPGrp` (1112), `TTYName` (1112), `IsATTY` (1082)

**31.12.119 TCGetAttr**

Synopsis: Terminal Control: Get terminal attributes

Declaration: `function TCGetAttr(fd: LongInt; var tios: Termios) : Boolean`

Visibility: default

Description: `TCGetAttr` gets the terminal parameters from the terminal referred to by the file descriptor `fd` and returns them in a `TermIOS` structure `tios`. The function returns `True` if the call was successful, `False` otherwise.

Errors: Errors are reported in `LinuxError`

See also: `TCDrain` (1109), `TCFlow` (1109), `TCFlush` (1109), `TCGetPGrp` (1110), `TCSendBreak` (1111), `TCSetAttr` (1111), `TCSetPGrp` (1112), `TTYName` (1112), `IsATTY` (1082)

**Listing:** `./olinuxex/ex55.pp`

---

**Program** Example55;

**uses** oldlinux;

*{ Program to demonstrate the TCGetAttr/TCSetAttr/CFMakeRaw functions. }*

**procedure** ShowTermios(**var** tios:Termios);

**begin**

**WriteLn**('Input Flags : \$',hexstr(tios.c\_iflag,8)+#13);

**WriteLn**('Output Flags : \$',hexstr(tios.c\_oflag,8));

**WriteLn**('Line Flags : \$',hexstr(tios.c\_lflag,8));

**WriteLn**('Control Flags: \$',hexstr(tios.c\_cflag,8));

**end**;

**var**

    oldios ,

    tios : Termios;

**begin**

**WriteLn**('Old attributes:');

    TCGetAttr(1,tios);

    ShowTermios(tios);

    oldios:=tios;

**WriteLn**('Setting raw terminal mode');

    CFMakeRaw(tios);

    TCSetAttr(1,TCSANOW,tios);

**WriteLn**('Current attributes:');

    TCGetAttr(1,tios);

    ShowTermios(tios);

    TCSetAttr(1,TCSANOW,oldios);

**end**.

---

**31.12.120 TCGetPGrp**

Synopsis: Terminal control: Get process group

Declaration: `function TCGetPGrp(fd: LongInt; var id: LongInt) : Boolean`

Visibility: default



**Description:** `TCGetPGrp` returns the process group ID of a foreground process group in `Id`. The function returns `True` if the call was successful, `False` otherwise.

**Errors:** Errors are reported in `LinuxError`.

**See also:** `TCDrain` (1109), `TCFlow` (1109), `TCFlush` (1109), `TCGetAttr` (1110), `TCSendBreak` (1111), `TCSetAttr` (1111), `TCSetPGrp` (1112), `TTYName` (1112), `IsATTY` (1082)

### 31.12.121 TCSendBreak

**Synopsis:** Terminal control: Send break

**Declaration:** `function TCSendBreak(fd: LongInt; duration: LongInt) : Boolean`

**Visibility:** default

**Description:** `TCSendBreak` Sends zero-valued bits on an asynchronouse serial connection described by file-descriptor `Fd`, for duration `Duration`. The function returns `True` if the action was performed successfully, `False` otherwise.

**Errors:** Errors are reported in `LinuxError`.

**See also:** `TCDrain` (1109), `TCFlow` (1109), `TCFlush` (1109), `TCGetAttr` (1110), `TCGetPGrp` (1110), `TCSetAttr` (1111), `TCSetPGrp` (1112), `TTYName` (1112), `IsATTY` (1082)

### 31.12.122 TCSetAttr

**Synopsis:** Terminal control: Set attributes

**Declaration:** `function TCSetAttr(fd: LongInt; OptAct: LongInt; const tios: Termios) : Boolean`

**Visibility:** default

**Description:** `TCSetAttr` sets the terminal parameters you specify in a `TermIOS` structure `Tios` for the terminal referred to by the file descriptor `Fd`.

`OptAct` specifies an optional action when the set need to be done, this could be one of the following pre-defined values:

**TCSANOW** set immediately.

**TCSADRAIN** wait for output.

**TCSAFLUSH** wait for output and discard all input not yet read.

The function Returns `True` if the call was successful, `False` otherwise.

For an example, see `TCGetAttr` (1110).

**Errors:** Errors are reported in `LinuxError`.

**See also:** `TCDrain` (1109), `TCFlow` (1109), `TCFlush` (1109), `TCGetAttr` (1110), `TCGetPGrp` (1110), `TCSendBreak` (1111), `TCSetPGrp` (1112), `TTYName` (1112), `IsATTY` (1082)

### 31.12.123 TCSetPGrp

Synopsis: Terminal control: Set process group

Declaration: `function TCSetPGrp(fd: LongInt;id: LongInt) : Boolean`

Visibility: default

Description: `TCSetPGrp` Sets the Process Group Id to `Id`. The function returns `True` if the call was successful, `False` otherwise.

For an example, see `TCGetPGrp` (1110).

Errors: Errors are returned in `LinuxError`.

See also: `TCDrain` (1109), `TCFlow` (1109), `TCFlush` (1109), `TCGetAttr` (1110), `TCGetPGrp` (1110), `TCSend-Break` (1111), `TCSetAttr` (1111), `TTYName` (1112), `IsATTY` (1082)

### 31.12.124 TellDir

Synopsis: Return current location in a directory

Declaration: `function TellDir(p: PDir) : LongInt`

Visibility: default

Description: `TellDir` returns the current location in the directory structure pointed to by `p`. It returns -1 on failure.

For an example, see `OpenDir` (1090).

Errors: Errors are returned in `LinuxError`.

See also: `CloseDir` (1050), `ReadDir` (1093), `SeekDir` (1095), `OpenDir` (1090)

### 31.12.125 TTYname

Synopsis: Terminal control: Get terminal name

Declaration: `function TTYname(Handle: LongInt) : String`  
`function TTYname(var F: Text) : String`

Visibility: default

Description: `TTYName` Returns the name of the terminal pointed to by `f`. `f` must be a terminal. `f` can be of type:

1. `longint` for file handles;
2. `Text` for text variables such as `input` etc.

Errors: Returns an empty string in case of an error. `Linuxerror` may be set to indicate what error occurred, but this is uncertain.

See also: `TCDrain` (1109), `TCFlow` (1109), `TCFlush` (1109), `TCGetAttr` (1110), `TCGetPGrp` (1110), `TCSend-Break` (1111), `TCSetAttr` (1111), `TCSetPGrp` (1112), `IsATTY` (1082), `IOCtl` (1081)

**31.12.126 Umask**

Synopsis: Set file creation mask.

Declaration: `function Umask(Mask: Integer) : Integer`

Visibility: default

Description: Change the file creation mask for the current user to `Mask`. The current mask is returned.

See also: `Chmod` ([1046](#))

**Listing:** `./olinuxex/ex27.pp`

---

**Program** `Example27;`

*{ Program to demonstrate the Umask function. }*

**Uses** `oldlinux;`

**begin**

**WriteLn** ( 'Old Umask was : ', Umask(Octal(111)));

**WRiteLn** ( 'New Umask is : ', Octal(111));

**end.**

---

**31.12.127 Uname**

Synopsis: Return system name.

Declaration: `function Uname(var unamerec: utsname) : Boolean`

Visibility: default

Description: `Uname` gets the name and configuration of the current linux kernel, and returns it in `unamerec`.

Errors: `LinuxError` is used to report errors.

See also: `GetHostName` ([1076](#)), `GetDomainName` ([1072](#))

**31.12.128 UnLink**

Synopsis: `Unlink` (i.e. remove) a file.

Declaration: `function UnLink(Path: PathStr) : Boolean`  
               `function UnLink(Path: pchar) : Boolean`

Visibility: default

Description: `UnLink` decreases the link count on file `Path`. `Path` can be of type `PathStr` or `PChar`. If the link count is zero, the file is removed from the disk. The function returns `True` if the call was succesfull, `False` if the call failed.

For an example, see `Link` ([1083](#)).

Errors: Errors are returned in `LinuxError`.

**sys\_eaccess** You have no write access right in the directory containing `Path`, or you have no search permission in one of the directory components of `Path`.

**sys\_eperm**The directory containing pathname has the sticky-bit set and the process's effective uid is neither the uid of the file to be deleted nor that of the directory containing it.

**sys\_enoent**A component of the path doesn't exist.

**sys\_enotdir**A directory component of the path is not a directory.

**sys\_eisdir**Path refers to a directory.

**sys\_enomem**Insufficient kernel memory.

**sys\_erofs**Path is on a read-only filesystem.

See also: [Link \(1083\)](#), [SymLink \(1104\)](#)

### 31.12.129 Utime

**Synopsis:** Set access and modification times of a file (touch).

**Declaration:** `function Utime(const path: PathStr; utim: UTimeBuf) : Boolean`

**Visibility:** default

**Description:** `Utime` sets the access and modification times of a file. the `utimbuf` record contains 2 fields, `actime`, and `modtime`, both of type `Longint`. They should be filled with an epoch-like time, specifying, respectively, the last access time, and the last modification time. For some filesystem (most notably, FAT), these times are the same.

**Errors:** Errors are returned in `LinuxError`.

**sys\_eaccess**One of the directories in `Path` has no search (=execute) permission.

**sys\_enoent**A directory entry in `Path` does not exist or is a symbolic link pointing to a non-existent directory.

Other errors may occur, but aren't documented.

See also: [GetEpochTime \(1074\)](#), [Chown \(1047\)](#), [Access \(1041\)](#)

**Listing:** `./olinuxex/ex25.pp`

---

**Program** `Example25;`

*{ Program to demonstrate the UTime function. }*

**Uses** `oldlinux;`

**Var** `utim : utimbuf;`  
`year, month, day, hour, minute, second : Word;`

**begin**  
*{ Set access and modification time of executable source }*  
`GetTime ( hour, minute, second );`  
`GetDate ( year, month, day );`  
`utim.actime := LocalToEpoch ( year, month, day, hour, minute, second );`  
`utim.modtime := utim.actime;`  
**if not** `Utime ( 'ex25.pp', utim ) then`  
    `writeln ( 'Call to UTime failed !' )`  
**else**  
    **begin**  
        `Write ( 'Set access and modification times to : ' );`  
        `Write ( Hour:2, ': ', minute:2, ': ', second, ' ', ' );`  
    **end**

```

    Writeln (Day:2, ' / ', month:2, ' / ', year:4);
end;
end.

```

---

### 31.12.130 WaitPid

Synopsis: Wait for a process to terminate

Declaration: `function WaitPid(Pid: LongInt; Status: pointer; Options: LongInt) : LongInt`

Visibility: default

Description: `WaitPid` waits for a child process with process ID `Pid` to exit. The value of `Pid` can be one of the following:

**Pid < -1** Causes `WaitPid` to wait for any child process whose process group ID equals the absolute value of `pid`.

**Pid = -1** Causes `WaitPid` to wait for any child process.

**Pid = 0** Causes `WaitPid` to wait for any child process whose process group ID equals the one of the calling process.

**Pid > 0** Causes `WaitPid` to wait for the child whose process ID equals the value of `Pid`.

The `Options` parameter can be used to specify further how `WaitPid` behaves:

**WNOHANG** Causes `Waitpid` to return immediately if no child has exited.

**WUNTRACED** Causes `WaitPid` to return also for children which are stopped, but whose status has not yet been reported.

**\_\_WCLONE** Causes `WaitPid` also to wait for threads created by the `Clone` (1048) call.

Upon return, it returns the exit status of the process, or -1 in case of failure.

For an example, see `Fork` (1067).

Errors: Errors are returned in `LinuxError`.

See also: `Fork` (1067), `Execve` (1057)

### 31.12.131 WaitProcess

Synopsis: Wait for process to terminate.

Declaration: `function WaitProcess(Pid: LongInt) : LongInt`

Visibility: default

Description: `WaitProcess` waits for process `PID` to exit. `WaitProcess` is equivalent to the `WaitPID` (1115) call:

```
WaitPid(PID, @result, 0)
```

Handles of Signal interrupts (`errno=EINTR`), and returns the Exitcode of Process `PID` (`>=0`) or - Status if it was terminated

Errors: None.

See also: `WaitPID` (1115), `WTERMSIG` (1117), `WSTOPSIG` (1117), `WIFEXITED` (1116), `WIFSTOPPED` (1116), `WIFSIGNALED` (1116), `W_EXITCODE` (1118), `W_STOPCODE` (1118), `WEXITSTATUS` (1116)

### 31.12.132 WEXITSTATUS

Synopsis: Extract the exit status from the WaitPID (1115) result.

Declaration: `function WEXITSTATUS (Status: Integer) : Integer`

Visibility: default

Description: WEXITSTATUS can be used to extract the exit status from Status, the result of the WaitPID (1115) call.

See also: WaitPID (1115), WaitProcess (1115), WTERMSIG (1117), WSTOPSIG (1117), WIFEXITED (1116), WIFSTOPPED (1116), WIFSIGNALED (1116), W\_EXITCODE (1118), W\_STOPCODE (1118)

### 31.12.133 WIFEXITED

Synopsis: Check whether the process exited normally

Declaration: `function WIFEXITED (Status: Integer) : Boolean`

Visibility: default

Description: WIFEXITED checks Status and returns True if the status indicates that the process terminated normally, i.e. was not stopped by a signal.

See also: WaitPID (1115), WaitProcess (1115), WTERMSIG (1117), WSTOPSIG (1117), WIFSTOPPED (1116), WIFSIGNALED (1116), W\_EXITCODE (1118), W\_STOPCODE (1118), WEXITSTATUS (1116)

### 31.12.134 WIFSIGNALED

Synopsis: Check whether the process was exited by a signal.

Declaration: `function WIFSIGNALED (Status: Integer) : Boolean`

Visibility: default

Description: WIFSIGNALED returns True if Status indicates that the process exited because it received a signal.

See also: WaitPID (1115), WaitProcess (1115), WTERMSIG (1117), WSTOPSIG (1117), WIFEXITED (1116), WIFSTOPPED (1116), W\_EXITCODE (1118), W\_STOPCODE (1118), WEXITSTATUS (1116)

### 31.12.135 WIFSTOPPED

Synopsis: Check whether the process is currently stopped.

Declaration: `function WIFSTOPPED (Status: Integer) : Boolean`

Visibility: default

Description: WIFSTOPPED checks Status and returns true if the process is currently stopped. This is only possible if WUNTRACED was specified in the options of WaitPID (1115).

See also: WaitPID (1115), WaitProcess (1115), WTERMSIG (1117), WSTOPSIG (1117), WIFEXITED (1116), WIFSIGNALED (1116), W\_EXITCODE (1118), W\_STOPCODE (1118), WEXITSTATUS (1116)

### 31.12.136 WritePort

Declaration: `procedure WritePort (Port: LongInt; Value: Byte)`  
`procedure WritePort (Port: LongInt; Value: Word)`  
`procedure WritePort (Port: LongInt; Value: LongInt)`

Visibility: default

### 31.12.137 WritePortB

Declaration: `procedure WritePortB (Port: LongInt; Value: Byte)`  
`procedure WritePortB (Port: LongInt; var Buf; Count: LongInt)`

Visibility: default

### 31.12.138 WritePortL

Declaration: `procedure WritePortL (Port: LongInt; Value: LongInt)`  
`procedure WritePortL (Port: LongInt; var Buf; Count: LongInt)`

Visibility: default

### 31.12.139 WritePortW

Declaration: `procedure WritePortW (Port: LongInt; Value: Word)`  
`procedure WritePortW (Port: LongInt; var Buf; Count: LongInt)`

Visibility: default

### 31.12.140 WSTOPSIG

Synopsis: Return the exit code from the process.

Declaration: `function WSTOPSIG (Status: Integer) : Integer`

Visibility: default

Description: WSTOPSIG is an alias for WEXITSTATUS ([1116](#)).

See also: WaitPID ([1115](#)), WaitProcess ([1115](#)), WTERMSIG ([1117](#)), WIFEXITED ([1116](#)), WIFSTOPPED ([1116](#)), WIFSIGNALED ([1116](#)), W\_EXITCODE ([1118](#)), W\_STOPCODE ([1118](#)), WEXITSTATUS ([1116](#))

### 31.12.141 WTERMSIG

Synopsis: Return the signal that caused a process to exit.

Declaration: `function WTERMSIG (Status: Integer) : Integer`

Visibility: default

Description: WTERMSIG extracts from Status the signal number which caused the process to exit.

See also: WaitPID ([1115](#)), WaitProcess ([1115](#)), WSTOPSIG ([1117](#)), WIFEXITED ([1116](#)), WIFSTOPPED ([1116](#)), WIFSIGNALED ([1116](#)), W\_EXITCODE ([1118](#)), W\_STOPCODE ([1118](#)), WEXITSTATUS ([1116](#))

### 31.12.142 W\_EXITCODE

Synopsis: Construct an exit status based on an return code and signal.

Declaration: `function W_EXITCODE(ReturnCode: Integer; Signal: Integer) : Integer`

Visibility: default

Description: `W_EXITCODE` combines `ReturnCode` and `Signal` to a status code fit for `WaitPid`.

See also: `WaitPID` ([1115](#)), `WaitProcess` ([1115](#)), `WTERMSIG` ([1117](#)), `WSTOPSIG` ([1117](#)), `WIFEXITED` ([1116](#)), `WIFSTOPPED` ([1116](#)), `WIFSIGNALED` ([1116](#)), `W_STOPCODE` ([1118](#)), `WEXITSTATUS` ([1116](#))

### 31.12.143 W\_STOPCODE

Synopsis: Construct an exit status based on a signal.

Declaration: `function W_STOPCODE(Signal: Integer) : Integer`

Visibility: default

Description: `W_STOPCODE` constructs an exit status based on `Signal`, which will cause `WIFSIGNALED` ([1116](#)) to return `True`

See also: `WaitPID` ([1115](#)), `WaitProcess` ([1115](#)), `WTERMSIG` ([1117](#)), `WSTOPSIG` ([1117](#)), `WIFEXITED` ([1116](#)), `WIFSTOPPED` ([1116](#)), `WIFSIGNALED` ([1116](#)), `W_EXITCODE` ([1118](#)), `WEXITSTATUS` ([1116](#))



## Chapter 32

# Reference for unit 'ports'

### 32.1 Overview

The ports unit implements the `port` constructs found in Turbo Pascal. It uses classes and default array properties to do this.

The unit exists on linux, os/2 and dos. It is implemented only for compatibility with Turbo Pascal. It's usage is discouraged, because using ports is not portable programming, and the operating system may not even allow it (for instance Windows).

Under linux, your program must be run as root, or the `IOPerm` call must be set in order to set appropriate permissions on the port access.

### 32.2 Constants, types and variables

#### 32.2.1 Variables

`port : tport`

Default instance of type `TPort` ([1120](#)). Do not free. This variable is initialized in the unit initialization code, and freed at finalization.

Since there is a default property for a variable of this type, a sentence as

```
port[221]:=12;
```

Will result in the integer 12 being written to port 221, if port is defined as a variable of type `tport`

`portb : tport`

Default instance of type `TPort` ([1120](#)). Do not free. This variable is initialized in the unit initialization code, and freed at finalization.

Since there is a default property for a variable of this type, a sentence as

```
portb[221]:=12;
```

Will result in the byte 12 being written to port 221, if port is defined as a variable of type `tport`

```
portl : tportl
```

Default instance of type TPortL ([1120](#)). Do not free. This variable is initialized in the unit initialization code, and freed at finalization.

Since there is a default property for a variable of this type, a sentence as

```
portl[221]:=12;
```

Will result in the longint 12 being written to port 221, if port is defined as a variable of type tport

```
portw : tportw
```

Default instance of type TPortW ([1121](#)). Do not free. This variable is initialized in the unit initialization code, and freed at finalization.

Since there is a default property for a variable of this type, a sentence as

```
portw[221]:=12;
```

Will result in the word 12 being written to port 221, if port is defined as a variable of type tport

## 32.3 tport

### 32.3.1 Description

The TPort type is implemented specially for access to the ports in a TP compatible manner. There is no need to create an instance of this type: the standard TP variables are instantiated at unit initialization.

### 32.3.2 Property overview

Page	Property	Access	Description
<a href="#">1120</a>	pp	rw	Access integer-sized port by port number

### 32.3.3 tport.pp

Synopsis: Access integer-sized port by port number

Declaration: Property pp[w: LongInt]: Byte; default

Visibility: public

Access: Read,Write

Description: Access integer-sized port by port number

## 32.4 tportl

### 32.4.1 Description

The TPortL type is implemented specially for access to the ports in a TP compatible manner. There is no need to create an instance of this type: the standard TP variables are instantiated at unit initialization.

### 32.4.2 Property overview

Page	Property	Access	Description
<a href="#">1121</a>	pp	rw	Access Longint-sized port by port number

### 32.4.3 tportl.pp

Synopsis: Access Longint-sized port by port number

Declaration: `Property pp[w: LongInt]: LongInt; default`

Visibility: `public`

Access: `Read,Write`

Description: Access Longint-sized port by port number

## 32.5 tportw

### 32.5.1 Description

The `TPortW` type is implemented specially for access to the ports in a TP compatible manner. There is no need to create an instance of this type: the standard TP variables are instantiated at unit initialization.

### 32.5.2 Property overview

Page	Property	Access	Description
<a href="#">1121</a>	pp	rw	Access word-sized port by port number

### 32.5.3 tportw.pp

Synopsis: Access word-sized port by port number

Declaration: `Property pp[w: LongInt]: Word; default`

Visibility: `public`

Access: `Read,Write`

Description: Access word-sized port by port number

## Chapter 33

# Reference for unit 'printer'

### 33.1 Overview

This chapter describes the PRINTER unit for Free Pascal. It was written for dos by Florian Klaempfl, and it was written for linux by Michael Van Canneyt, and has been ported to Windows and os/2 as well. Its basic functionality is the same for all supported systems, although there are minor differences on linux/unix.

### 33.2 Constants, types and variables

#### 33.2.1 Variables

`Lst : text`

`Lst` is the standard printing device.

On linux, `Lst` is set up using `AssignLst ('/tmp/PID.lst')`.

### 33.3 Procedures and functions

#### 33.3.1 AssignLst

Synopsis: Assign text file to printing device

Declaration: `procedure AssignLst (var F: text; ToFile: String)`

Visibility: default

Description: `AssignLst` Assigns to `F` a printing device - *Unix only*. `ToFile` is a string with the following form:

- `'|filename options'` : This sets up a pipe with the program filename, with the given options, such as in the `popen()` call.
- `'filename'` : Prints to file filename. Filename can contain the string 'PID' (No Quotes), which will be replaced by the PID of your program. When closing `lst`, the file will be sent to `lpr` and deleted. (`lpr` should be in `PATH`)
- `{'filename|'}` Idem as previous, only the file is NOT sent to `lpr`, nor is it deleted. (useful for opening `/dev/printer` or for later printing)

See also: `lst` ([1122](#))

**Listing:** `./printex/printex.pp`

---

```

program testprn;

uses printer;

var i : integer;
    f : text;

begin
  writeln ( 'Test of printer unit' );
  writeln ( 'Writing to lst...' );
  for i:=1 to 80 do writeln (lst, 'This is line ', i, '.' #13);
  close (lst);
  writeln ( 'Done.' );
  { $ifdef Unix }
  writeln ( 'Writing to pipe...' );
  assignlst ( f, '|/usr/bin/lpr -m' );
  rewrite ( f );
  for i:=1 to 80 do writeln ( f, 'This is line ', i, '.' #13 );
  close ( f );
  writeln ( 'Done.' )
  { $endif }
end.

```

---

### 33.3.2 InitPrinter

Synopsis: Initialize the printer

Declaration: `procedure InitPrinter(const PrinterName: String)`

Visibility: default

Description: Initialize the printer

### 33.3.3 IsLstAvailable

Synopsis: Determine whether printer is available.

Declaration: `function IsLstAvailable : Boolean`

Visibility: default

Description: Determine whether printer is available.

## Chapter 34

# Reference for unit 'Sockets'

### 34.1 Used units

Table 34.1: Used units by unit 'Sockets'

Name	Page
baseunix	<a href="#">1124</a>
UnixType	<a href="#">1124</a>

### 34.2 Overview

This document describes the SOCKETS unit for Free Pascal. it was written for linux by Michael Van Canneyt, and ported to Windows by Florian Klaempfl.

### 34.3 Constants, types and variables

#### 34.3.1 Constants

`AF_APPLETALK = 5`

Address family Appletalk DDP

`AF_ASH = 18`

Address family: Ash

`AF_ATMPVC = 8`

Address family: ATM PVCs

`AF_ATMSVC = 20`

Address family: ATM SVCs

AF\_AX25 = 3

Address family Amateur Radio AX.25

AF\_BLUETOOTH = 31

Address family: Bluetooth sockets

AF\_BRIDGE = 7

Address family Multiprotocol bridge

AF\_DECnet = 12

Address family: Reserved for DECnet project.

AF\_ECONET = 19

Address family: Acorn Econet

AF\_INET = 2

Address family Internet IP Protocol

AF\_INET6 = 10

Address family IP version 6

AF\_IPX = 4

Address family Novell IPX

AF\_IRDA = 23

Address family: IRDA sockets

AF\_KEY = 15

Address family: PF\_KEY key management API

AF\_LLC = 26

Address family: Linux LLC

AF\_LOCAL = 1

Address family: Unix socket

AF\_MAX = 32

Address family Maximum value

AF\_NETBEUI = 13

Address family: Reserved for 802.2LLC project

AF\_NETLINK = 16

Address family: ?

AF\_NETROM = 6

Address family Amateur radio NetROM

AF\_PACKET = 17

Address family: Packet family

AF\_PPPOX = 24

Address family: PPPoX sockets

AF\_ROSE = 11

Address family: Amateur Radio X.25 PLP

AF\_ROUTE = AF\_NETLINK

Address family: Alias to emulate 4.4BSD.

AF\_SECURITY = 14

Address family: Security callback pseudo AF

AF\_SNA = 22

Address family: Linux SNA project

AF\_TIPC = 30

Address family: TIPC sockets

AF\_UNIX = 1

Address family Unix domain sockets

AF\_UNSPEC = 0

Address family Not specified

AF\_WANPIPE = 25

Address family: Wanpipe API Sockets



`AF_X25 = 9`

Address family Reserved for X.25 project

`EsockEACCESS = ESysEAcces`

Access forbidden error

`EsockEBADF = EsysEBADF`

Alias: bad file descriptor

`EsockEFAULT = EsysEFAULT`

Alias: an error occurred

`EsockEINTR = EsysEINTR`

Alias : operation interrupted

`EsockEINVAL = EsysEINVAL`

Alias: Invalid value specified

`EsockEMFILE = ESysEmfile`

Error code ?

`EsockEMSGSIZE = ESysEMsgSize`

Wrong message size error

`EsockENOBUFS = ESysENoBufs`

No buffer space available error

`EsockENOTCONN = ESysENotConn`

Not connected error

`EsockENOTSOCK = ESysENotSock`

File descriptor is not a socket error

`EsockEPROTONOSUPPORT = ESysEProtoNoSupport`

Protocol not supported error

`EsockEWOULDBLOCK = ESysEWouldBlock`

Operation would block error

INADDR\_ANY = CARDINAL (0)

A bitmask matching any IP address on the local machine.

INADDR\_NONE = CARDINAL (\$FFFFFFFF)

A bitmask matching no valid IP address

IPPROTO\_AH = 51

authentication header.

IPPROTO\_COMP = 108

Compression Header Protocol.

IPPROTO\_DSTOPTS = 60

IPv6 destination options.

IPPROTO\_EGP = 8

Exterior Gateway Protocol.

IPPROTO\_ENCAP = 98

Encapsulation Header.

IPPROTO\_ESP = 50

encapsulating security payload.

IPPROTO\_FRAGMENT = 44

IPv6 fragmentation header.

IPPROTO\_GRE = 47

General Routing Encapsulation.

IPPROTO\_HOPOPTS = 0

IPv6 Hop-by-Hop options.

IPPROTO\_ICMP = 1

Internet Control Message Protocol.

IPPROTO\_ICMPV6 = 58

ICMPv6.

IPPROTO\_IDP = 22

XNS IDP protocol.

IPPROTO\_IGMP = 2

Internet Group Management Protocol.

IPPROTO\_IP = 0

Dummy protocol for TCP.

IPPROTO\_IPIP = 4

IPIP tunnels (older KA9Q tunnels use 94).

IPPROTO\_IPV6 = 41

IPv6 header.

IPPROTO\_MAX = 255

Maximum value for IPPROTO options

IPPROTO\_MTP = 92

Multicast Transport Protocol.

IPPROTO\_NONE = 59

IPv6 no next header.

IPPROTO\_PIM = 103

Protocol Independent Multicast.

IPPROTO\_PUP = 12

PUP protocol.

IPPROTO\_RAW = 255

Raw IP packets.

IPPROTO\_ROUTING = 43

IPv6 routing header.

IPPROTO\_RSVP = 46

Reservation Protocol.

IPPROTO\_SCTP = 132

Stream Control Transmission Protocol.

IPPROTO\_TCP = 6

Transmission Control Protocol.

IPPROTO\_TP = 29

SO Transport Protocol Class 4.

IPPROTO\_UDP = 17

User Datagram Protocol.

IPV6\_ADDRFORM = 1

Change the IPV6 address into a different address family. Deprecated

IPV6\_ADD\_MEMBERSHIP = IPV6\_JOIN\_GROUP

Undocumented Getsockopt option ?

IPV6\_AUTHHDR = 10

GetSockOpt/SetSockopt: Deliver authentication header messages

IPV6\_CHECKSUM = 7

Undocumented Getsockopt option ?

IPV6\_DROP\_MEMBERSHIP = IPV6\_LEAVE\_GROUP

Undocumented Getsockopt option ?

IPV6\_DSTOPTS = 4

Deliver destination option control messages

IPV6\_HOPLIMIT = 8

Deliver an integer containing the HOP count

IPV6\_HOPOPTS = 3

Deliver hop option control messages

IPV6\_IPSEC\_POLICY = 34

Undocumented Getsockopt option ?

IPV6\_JOIN\_ANYCAST = 27

Undocumented Getsockopt option ?

IPV6\_JOIN\_GROUP = 20

GetSockOpt/SetSockopt: Control membership (join group) in multicast groups

IPV6\_LEAVE\_ANYCAST = 28

Undocumented Getsockopt option ?

IPV6\_LEAVE\_GROUP = 21

GetSockOpt/SetSockopt: Control membership (leave group) in multicast groups

IPV6\_MTU = 24

GetSockOpt/SetSockopt: Get/Set the MTU for the socket

IPV6\_MTU\_DISCOVER = 23

GetSockOpt/SetSockopt: Get/Set Control path MTU Discovery on the socket

IPV6\_MULTICAST\_HOPS = 18

GetSockOpt/SetSockopt: Get/Set the multicast hop limit.

IPV6\_MULTICAST\_IF = 17

GetSockOpt/SetSockopt: Get/Set device for multicast packages on the socket.

IPV6\_MULTICAST\_LOOP = 19

GetSockOpt/SetSockopt: Control whether socket sees multicast packages that it has sent itself

IPV6\_NEXTHOP = 9

sendmsg: set next hop for IPV6 datagram

IPV6\_PKTINFO = 2

Change delivery options for incoming IPV6 datagrams

IPV6\_PKTOPTIONS = 6

Undocumented Getsockopt option ?

IPV6\_PMTUDISC\_DO = 2

Always DF.

IPV6\_PMTUDISC\_DONT = 0

Never send DF frames.

IPV6\_PMTUDISC\_WANT = 1

Use per route hints.

IPV6\_RECVERR = 25

GetSockOpt/SetSockopt: Control receiving of asynchronous error options

IPV6\_ROUTER\_ALERT = 22

GetSockOpt/SetSockopt: Get/Set Pass all forwarded packets containing router alert option

IPV6\_RTHDR = 5

Deliver routing header control messages

IPV6\_RTHDR\_LOOSE = 0

Hop doesn't need to be neighbour.

IPV6\_RTHDR\_STRICT = 1

Hop must be a neighbour.

IPV6\_RTHDR\_TYPE\_0 = 0

IPv6 Routing header type 0.

IPV6\_RXDSTOPTS = IPV6\_DSTOPTS

Undocumented Getsockopt option ?

IPV6\_RXHOPOPTS = IPV6\_HOPOPTS

Undocumented Getsockopt option ?

IPV6\_RXSRCRT = IPV6\_RTHDR

Undocumented Getsockopt option ?

IPV6\_UNICAST\_HOPS = 16

GetSockOpt/SetSockopt: Get/Set unicast hop limit

IPV6\_V6ONLY = 26

GetSockOpt/SetSockopt: Handle IPV6 connections only

IPV6\_XFRM\_POLICY = 35

Undocumented Getssockopt option ?

IP\_ADD\_MEMBERSHIP = 35

add an IP group membership

IP\_ADD\_SOURCE\_MEMBERSHIP = 39

join source group

IP\_BLOCK\_SOURCE = 38

block data from source

IP\_DEFAULT\_MULTICAST\_LOOP = 1

Undocumented ?

IP\_DEFAULT\_MULTICAST\_TTL = 1

Undocumented ?

IP\_DROP\_MEMBERSHIP = 36

drop an IP group membership

IP\_DROP\_SOURCE\_MEMBERSHIP = 40

leave source group

IP\_HDRINCL = 3

Header is included with data.

IP\_MAX\_MEMBERSHIPS = 20

Maximum group memberships for multicast messages

IP\_MSFILTER = 41

Undocumented ?

IP\_MTU\_DISCOVER = 10

Undocumented ?

IP\_MULTICAST\_IF = 32

set/get IP multicast i/f

IP\_MULTICAST\_LOOP = 34

set/get IP multicast loopback

IP\_MULTICAST\_TTL = 33

set/get IP multicast ttl

IP\_OPTIONS = 4

IP per-packet options.

IP\_PKTINFO = 8

Undocumented ?

IP\_PKTOPTIONS = 9

Undocumented ?

IP\_PMTUDISC = 10

Undocumented ?

IP\_PMTUDISC\_DO = 2

Always DF.

IP\_PMTUDISC\_DONT = 0

Never send DF frames.

IP\_PMTUDISC\_WANT = 1

Use per route hints.

IP\_RECVERR = 11

Undocumented ?

IP\_RECVOPTS = 6

Receive all IP options w/datagram.

IP\_RECVRETOPTS = IP\_RETOPTS

Receive IP options for response.

IP\_RECVTOS = 13

Undocumented ?



IP\_RECVTTL = 12

Undocumented ?

IP\_RETOPTS = 7

Set/get IP per-packet options.

IP\_ROUTER\_ALERT = 5

Undocumented ?

IP\_TOS = 1

IP type of service and precedence.

IP\_TTL = 2

IP time to live.

IP\_UNBLOCK\_SOURCE = 37

unblock data from source

MCAST\_BLOCK\_SOURCE = 43

block from given group

MCAST\_EXCLUDE = 0

Undocumented ?

MCAST\_INCLUDE = 1

Undocumented ?

MCAST\_JOIN\_GROUP = 42

join any-source group

MCAST\_JOIN\_SOURCE\_GROUP = 46

join source-spec group

MCAST\_LEAVE\_GROUP = 45

leave any-source group

MCAST\_LEAVE\_SOURCE\_GROUP = 47

leave source-spec group

MCAST\_MSFILTER = 48

Undocumented ?

MCAST\_UNBLOCK\_SOURCE = 44

unblock from given group

MSG\_CONFIRM = 0x0800

Send flags: Conform connection

MSG\_CTRUNC = 0x0008

Receive flags: Control Data was discarded (buffer too small)

MSG\_DONTROUTE = 0x0004

Send flags: don't use gateway

MSG\_DONTWAIT = 0x0040

Receive flags: Non-blocking operation request.

MSG\_EOF = MSG\_FIN

Alias for MSG\_FIN

MSG\_EOR = 0x0080

Receive flags: End of record

MSG\_ERRQUEUE = 0x2000

Receive flags: ?

MSG\_FIN = 0x0200

Receive flags: ?

MSG\_MORE = 0x8000

Receive flags: ?

MSG\_NOSIGNAL = 0x4000

Receive flags: Suppress SIG\_PIPE signal.

MSG\_OOB = 0x0001

Receive flags: receive out-of-band data.

MSG\_PEEK = \$0002

Receive flags: peek at data, don't remove from buffer.

MSG\_PROXY = \$0010

Receive flags: ?

MSG\_RST = \$1000

Receive flags: ?

MSG\_SYN = \$0400

Receive flags: ?

MSG\_TRUNC = \$0020

Receive flags: packet Data was discarded (buffer too small)

MSG\_TRYHARD = MSG\_DONTROUTE

Receive flags: ?

MSG\_WAITALL = \$0100

Receive flags: Wait till operation completed.

NoAddress : in\_addr = (s\_addr:0)

Constant indicating invalid (no) network address.

NoAddress6 : in6\_addr = (u6\_addr16:(0,0,0,0,0,0,0,0))

Constant indicating invalid (no) IPV6 network address.

NoNet : in\_addr = (s\_addr:0)

Constant indicating invalid (no) network address.

NoNet6 : in6\_addr = (u6\_addr16:(0,0,0,0,0,0,0,0))

Constant indicating invalid (no) IPV6 network address.

PF\_APPLETALK = AF\_APPLETALK

Protocol family: Appletalk DDP

PF\_ASH = AF\_ASH

Protocol family: Ash

PF\_ATMPVC = AF\_ATMPVC

Protocol family: ATM PVCs

PF\_ATMSVC = AF\_ATMSVC

Protocol family: ATM SVCs

PF\_AX25 = AF\_AX25

Protocol family: Amateur Radio AX.25

PF\_BLUETOOTH = AF\_BLUETOOTH

Protocol family: Bluetooth sockets

PF\_BRIDGE = AF\_BRIDGE

Protocol family: Multiprotocol bridge

PF\_DECnet = AF\_DECnet

Protocol Family: DECNET project

PF\_ECONET = AF\_ECONET

Protocol family: Acorn Econet

PF\_INET = AF\_INET

Protocol family: Internet IP Protocol

PF\_INET6 = AF\_INET6

Protocol family: IP version 6

PF\_IPX = AF\_IPX

Protocol family: Novell IPX

PF\_IRDA = AF\_IRDA

Protocol family: IRDA sockets

PF\_KEY = AF\_KEY

Protocol family: Key management API

PF\_LLC = AF\_LLC

Protocol family: Linux LLC

PF\_LOCAL = AF\_LOCAL

Protocol family: Unix socket

PF\_MAX = AF\_MAX

Protocol family: Maximum value

PF\_NETBEUI = AF\_NETBEUI

Protocol family: Reserved for 802.2LLC project

PF\_NETLINK = AF\_NETLINK

Protocol family: ?

PF\_NETROM = AF\_NETROM

Protocol family:Amateur radio NetROM

PF\_PACKET = AF\_PACKET

Protocol family: Packet family

PF\_PPPOX = AF\_PPPOX

Protocol family: PPPoX sockets

PF\_ROSE = AF\_ROSE

Protocol family: Amateur Radio X.25 PLP

PF\_ROUTE = AF\_ROUTE

Protocol Family: ?

PF\_SECURITY = AF\_SECURITY

Protocol family: Security callback pseudo PF

PF\_SNA = AF\_SNA

Protocol Family: Linux SNA project

PF\_TIPC = AF\_TIPC

Protocol family: TIPC sockets

PF\_UNIX = AF\_UNIX

Protocol family: Unix domain sockets

PF\_UNSPEC = AF\_UNSPEC

Protocol family: Unspecified

PF\_WANPIPE = AF\_WANPIPE

Protocol family: Wanpipe API Sockets

PF\_X25 = AF\_X25

Protocol family: Reserved for X.25 project

SCM\_SRCRT = IPV6\_RXSRCRT

Undocumented Getsockopt option ?

SCM\_TIMESTAMP = SO\_TIMESTAMP

Socket option: ?

SHUT\_RD = 0

Shutdown read part of full duplex socket

SHUT\_RDWR = 2

Shutdown read and write part of full duplex socket

SHUT\_WR = 1

Shutdown write part of full duplex socket

SOCK\_DGRAM = 2

Type of socket: datagram (conn.less) socket (UDP)

SOCK\_MAXADDRLLEN = 255

Maximum socket address length for Bind ([1150](#)) call.

SOCK\_RAW = 3

Type of socket: raw socket

SOCK\_RDM = 4

Type of socket: reliably-delivered message

SOCK\_SEQPACKET = 5

Type of socket: sequential packet socket

SOCK\_STREAM = 1

Type of socket: stream (connection) type socket (TCP)

SOL\_ICMPV6 = 58

Socket level values for IPv6: ICMPV6

SOL\_IP = 0

Undocumented ?

SOL\_IPV6 = 41

Socket level values for IPv6: IPV6

SOL\_SOCKET = 1

Socket option level: Socket level

SOMAXCONN = 128

Maximum queue length specifiable by listen.

SO\_ACCEPTCONN = 30

Socket option: ?

SO\_ATTACH\_FILTER = 26

Socket option: ?

SO\_BINDTODEVICE = 25

Socket option: ?

SO\_BROADCAST = 6

Socket option: Broadcast

SO\_BSDCOMPAT = 14

Socket option: ?

SO\_DEBUG = 1

Socket option level: debug

SO\_DETACH\_FILTER = 27

Socket option: ?

SO\_DONTROUTE = 5

Socket option: Don't route

SO\_ERROR = 4

Socket option: Error

SO\_KEEPALIVE = 9

Socket option: keep alive

SO\_LINGER = 13

Socket option: ?

SO\_NO\_CHECK = 11

Socket option: ?

SO\_OOBINLINE = 10

Socket option: ?

SO\_PASSCRED = 16

Socket option: ?

SO\_PEERCRECRED = 17

Socket option: ?

SO\_PEERNAME = 28

Socket option: ?

SO\_PRIORITY = 12

Socket option: ?

SO\_RCVBUF = 8

Socket option: receive buffer

SO\_RCVLOWAT = 18

Socket option: ?

SO\_RCVTIMEO = 20

Socket option: ?



SO\_REUSEADDR = 2

Socket option: Reuse address

SO\_SECURITY\_AUTHENTICATION = 22

Socket option: ?

SO\_SECURITY\_ENCRYPTION\_NETWORK = 24

Socket option: ?

SO\_SECURITY\_ENCRYPTION\_TRANSPORT = 23

Socket option: ?

SO\_SNDBUF = 7

Socket option: Send buffer

SO\_SNDLOWAT = 19

Socket option: ?

SO\_SNDTIMEO = 21

Socket option: ?

SO\_TIMESTAMP = 29

Socket option: ?

SO\_TYPE = 3

Socket option: Type

S\_IN = 0

Input socket in socket pair.

S\_OUT = 1

Output socket in socket pair

TCP\_CONGESTION = 13

Get/set the congestion-control algorithm for this socket

TCP\_CORK = 3

Get/Set CORK algorithm: Send only complete packets

TCP\_DEFER\_ACCEPT = 9

Get/Set deferred accept on server socket

TCP\_INFO = 11

Get TCP connection information (linux only)

TCP\_KEEPCNT = 6

Get/Set retry count for unacknowledged KEEPALIVE transmissions.

TCP\_KEEPIDL = 4

Get/Set inactivity interval between KEEPALIVE transmissions.

TCP\_KEEPINTVL = 5

Get/Set retry interval for unacknowledged KEEPALIVE transmissions.

TCP\_LINGER2 = 8

Get/Set Linger2 flag

TCP\_MAXSEG = 2

Get/Set Maximum segment size

TCP\_MD5SIG = 14

Get/Set TCP MD5 signature option

TCP\_NODELAY = 1

Get/Set No delay flag: disable Nagle algorithm

TCP\_QUICKACK = 12

Get/Set quick ACK packet option.

TCP\_SYNCNT = 7

Get/Set number of SYN packets to send before giving up on connection establishment

TCP\_WINDOW\_CLAMP = 10

Get/Set maximum packet size

UDP\_CORK = 1

Get/Set UDP CORK algorithm on datagram sockets

UDP\_ENCAP = 100

Get/Set UDP encapsulation flag for IPSec datagram sockets

UDP\_ENCAP\_ESPINUDP = 2

? Undocumented datagram option, IPSec related

UDP\_ENCAP\_ESPINUDP\_NON\_IKE = 1

? Undocumented datagram option, IPSec related

UDP\_ENCAP\_L2TPINUDP = 3

? Undocumented datagram option, IPSec related

### 34.3.2 Types

```
in6_addr = packed record
end
```

Record used to describe a general IPV6 address.

```
in_addr = packed record
end
```

General inet socket address.

```
linger = packed record
  l_onoff : cint;
  l_linger : cint;
end
```

This record is used in the `setsockopt` (1124) call to specify linger options.

PIn6Addr = pin6\_addr

Pointer to in6\_addr (1145) type.

pin6\_addr = ^in6\_addr

Pointer to Tin6\_addr (1147)

PInAddr = pin\_addr

Alias for pin\_addr (1146)

PInetSockAddr = psockaddr\_in

Pointer to `sockaddr_in` (1146)

```
PInetSockAddr6 = psockaddr_in6
```

Pointer to `sockaddr_in6` (1147) type

```
pin_addr = ^in_addr
```

Pointer to `in_addr` (1145) record.

```
plinger = ^linger
```

Pointer to `linger` (1145) type.

```
psockaddr = ^sockaddr
```

Pointer to `TSockAddr` (1147)

```
psockaddr_in = ^sockaddr_in
```

Pointer to `sockaddr_in` (1146)

```
psockaddr_in6 = ^sockaddr_in6
```

Pointer to `sockaddr_in6` (1147)

```
psockaddr_un = ^sockaddr_un
```

Pointer to `sockaddr_un` (1147) type.

```
sa_family_t = cushort
```

Address family type

```
sockaddr = packed record
end
```

`sockaddr` is used to store a general socket address for the `Bind` (1150), `Recv` (1124) and `Send` (1124) calls.

```
sockaddr_in = packed record
end
```

`sockaddr_in` is used to store a `INET` socket address for the `Bind` (1150), `Recv` (1124) and `Send` (1124) calls.

```

sockaddr_in6 = packed record
  sin6_family : sa_family_t;
  sin6_port   : cuint16;
  sin6_flowinfo : cuint32;
  sin6_addr   : in6_addr;
  sin6_scope_id : cuint32;
end

```

Alias for `sockaddr_in6` (1147)

```

sockaddr_un = packed record
  sun_family : sa_family_t;
  sun_path   : Array[0..107] of Char;
end

```

`sockaddr_un` is used to store a UNIX socket address for the `Bind` (1150), `Recv` (1124) and `Send` (1124) calls.

```
TIn6Addr = in6_addr
```

Alias for `in6_addr` (1145) type.

```
Tin6_addr = in6_addr
```

Alias for `sockaddr_in6` (1147)

```
TInAddr = in_addr
```

Alias for `in_addr` (1145) record type.

```
TInetSockAddr = sockaddr_in
```

Alias for `sockaddr_in` (1146)

```
TInetSockAddr6 = sockaddr_in6
```

Alias for `sockaddr_in6` (1147)

```
TIn_addr = in_addr
```

Alias for `in_addr` (1145) record type.

```
TLinger = linger
```

Alias for `linger` (1124)

```
TSockAddr = sockaddr
```

```
TSockArray = Array[1..2] of LongInt
```

Type returned by the `SocketPair` (1124) call.

```
Tsocket = LongInt
```

Alias for easy kylix porting

```
TSockLen = BaseUnix.TSocklen
```

The actual type of `TSockLen` depends on the platform.

```
TSockPairArray = Array[0..1] of LongInt
```

Array of sockets, used in `SocketPair` (1124) call.

```
TUnixSockAddr = packed record
    family : sa_family_t;
    path : Array[0..107] of Char;
end
```

Alias for `sockaddr_un` (1147)

## 34.4 Procedures and functions

### 34.4.1 Accept

Synopsis: Accept a connection from a socket (deprecated).

```
Declaration: function Accept(Sock: LongInt; var addr: TInetSockAddr; var SockIn: File;
    var SockOut: File) : Boolean
function Accept(Sock: LongInt; var addr: TInetSockAddr; var SockIn: text;
    var SockOut: text) : Boolean
function Accept(Sock: LongInt; var addr: String; var SockIn: text;
    var SockOut: text) : Boolean
function Accept(Sock: LongInt; var addr: String; var SockIn: File;
    var SockOut: File) : Boolean
```

Visibility: default

**Description:** `Accept` accepts a connection from a socket `Sock`, which was listening for a connection. If a connection is accepted, a file descriptor is returned. On error `-1` is returned. The returned socket may NOT be used to accept more connections. The original socket remains open.

The `Accept` call fills the address of the connecting entity in `Addr`, and sets its length in `AddrLen`. `Addr` should be pointing to enough space, and `AddrLen` should be set to the amount of space available, prior to the call.

The alternate forms of the `Accept` (1148) command, with the `Text` or `File` parameters are equivalent to subsequently calling the regular `Accept` (1148) function and the `Sock2Text` (1164) or `Sock2File` (1164) functions. These functions return `True` if successful, `False` otherwise.

**Errors:** On error, `-1` is returned, and errors are reported in `SocketError`, and include the following:

**SYS\_EBADF** The socket descriptor is invalid.

**SYS\_ENOTSOCK**The descriptor is not a socket.

**SYS\_EOPNOTSUPP**The socket type doesn't support the `Listen` operation.

**SYS\_EFAULT**`Addr` points outside your address space.

**SYS\_EWOULDBLOCK**The requested operation would block the process.

See also: `Listen` (1124), `Connect` (1150), `Bind` (1150)

**Listing:** `./sockex/socksvr.pp`

---

**Program** `server`;

```
{
  Program to test Sockets unit by Michael van Canneyt and Peter Vreman
  Server Version, First Run sock_svr to let it create a socket and then
  sock_cli to connect to that socket
}

uses Sockets;

Var
  FromName : string;
  Buffer    : string[255];
  S         : Longint;
  Sin, Sout : Text;
  SAddr     : TInetSockAddr;

procedure perror (const S:string);
begin
  writeln (S, SocketError);
  halt(100);
end;

begin
  S:=fpSocket (AF_INET, SOCK_STREAM, 0);
  if SocketError<>0 then
    Perror ('Server : Socket : ');
  SAddr.sin_family:=AF_INET;
  { port 50000 in network order }
  SAddr.sin_port:=htons(50000);
  SAddr.sin_addr.s_addr:=0;
  if fpBind(S, @SAddr, sizeof(saddr))=-1 then
    Perror ('Server : Bind : ');
  if fpListen (S, 1)=-1 then
    Perror ('Server : Listen : ');
  Writeln('Waiting for Connect from Client, run now sock_cli in an other tty');
  if not Accept (S, FromName, Sin, Sout) then
    Perror ('Server : Accept : '+fromname);
  Reset(Sin);
  Rewrite(Sout);
  Writeln(Sout, 'Message From Server');
  Flush(SOut);
  while not eof(sin) do
    begin
      Readln(Sin, Buffer);
      Writeln('Server : read : ', buffer);
    end;
end.
```

---

### 34.4.2 Bind

Synopsis: Bind a socket to an address (deprecated).

Declaration: `function Bind(Socket: LongInt; const addr: String) : Boolean`

Visibility: default

Description: `Bind` binds the socket `Socket` to address `Addr`. `Addr` has length `AddrLen`. The function returns `True` if the call was successful, `False` if not.

The form of the `Bind` command with the `TUnixSockAddr` (1148) is equivalent to subsequently calling `Str2UnixSockAddr` (1165) and the regular `Bind` function. The function returns `True` if successful, `False` otherwise.

Errors: Errors are returned in `SocketError` and include the following:

**SYS\_EBADF** The socket descriptor is invalid.

**SYS\_EINVAL** The socket is already bound to an address,

**SYS\_EACCESS** Address is protected and you don't have permission to open it.

More errors can be found in the Unix man pages.

See also: `Socket` (1124)

### 34.4.3 CloseSocket

Synopsis: Closes a socket handle.

Declaration: `function CloseSocket(Socket: LongInt) : LongInt`

Visibility: default

Description: `CloseSocket` closes a socket handle. It returns 0 if the socket was closed successfully, -1 if it failed.

Errors: On error, -1 is returned.

See also: `Socket` (1124)

### 34.4.4 Connect

Synopsis: Open a connection to a server socket (deprecated).

```
Declaration: function Connect(Socket: LongInt; const addr: TInetSockAddr;
                           var SocketIn: text; var SocketOut: text) : Boolean
function Connect(Socket: LongInt; const addr: TInetSockAddr;
                           var SocketIn: File; var SocketOut: File) : Boolean
function Connect(Socket: LongInt; const addr: String; var SocketIn: text;
                           var SocketOut: text) : Boolean
function Connect(Socket: LongInt; const addr: String; var SocketIn: File;
                           var SocketOut: File) : Boolean
```

Visibility: default



**Description:** `Connect` opens a connection to a peer, whose address is described by `Addr`. `AddrLen` contains the length of the address. The type of `Addr` depends on the kind of connection you're trying to make, but is generally one of `TSockAddr` or `TUnixSockAddr`.

The forms of the `Connect` (1150) command with the `Text` or `File` arguments are equivalent to subsequently calling the regular `Connect` function and the `Sock2Text` (1164) or `Sock2File` (1164) functions. These functions return `True` if successful, `False` otherwise.

The `Connect` function returns a file descriptor if the call was successful, `-1` in case of error.

**Errors:** On error, `-1` is returned and errors are reported in `SocketError`.

See also: `Listen` (1124), `Bind` (1150), `Accept` (1148)

**Listing:** `./sockex/sockcli.pp`

---

**Program** `Client`;

```
{
  Program to test Sockets unit by Michael van Canneyt and Peter Vreman
  Client Version, First Run sock_svr to let it create a socket and then
  sock_cli to connect to that socket
}
```

**uses** `Sockets`;

```
procedure PError(const S : string);
begin
  writeln(S, SocketError);
  halt(100);
end;
```

**Var**

```
SAddr   : TInetSockAddr;
Buffer  : string [255];
S       : Longint;
Sin, Sout : Text;
i       : integer;
```

**begin**

```
S:=fpSocket (AF_INET, SOCK_STREAM, 0);
if s=-1 then
  PError('Client : Socket : ');
SAddr.sin_family:=AF_INET;
{ port 50000 in network order }
SAddr.sin_port:=htons(50000);
{ localhost : 127.0.0.1 in network order }
SAddr.sin_addr.s_addr:=HostToNet((127 shl 24) or 1);
if not Connect (S, SAddr, Sin, Sout) then
  PError('Client : Connect : ');
Reset(Sin);
ReWrite(Sout);
Buffer:='This is a textstring sent by the Client.';
for i:=1 to 10 do
  WriteLn(Sout, Buffer);
Flush(Sout);
ReadLn(Sin, Buffer);
WriteLn(Buffer);
Close(sout);
```

---

**end.**

---

**Listing:** ./sockex/pfinger.pp

---

```

program pfinger;

uses sockets, errors;

Var
  Addr : TInetSockAddr;
  S : Longint;
  Sin, Sout : Text;
  Line : string;

begin
  Addr.sin_family:=AF_INET;
  { port 79 in network order }
  Addr.sin_port:=79 shl 8;
  { localhost : 127.0.0.1 in network order }
  Addr.sin_addr.s_addr:=((1 shl 24) or 127);
  S:=fpSocket(AF_INET, SOCK_STREAM, 0);
  If Not Connect (S, Addr, Sin, Sout) Then
    begin
      Writeln ('Couldn't connect to localhost');
      Writeln ('Socket error : ', strerror(SocketError));
      halt(1);
    end;
    rewrite (sout);
    reset(sin);
    writeln (sout, paramstr(1));
    flush(sout);
    while not eof(sin) do
      begin
        readln (Sin, line);
        writeln (line);
      end;
    fpShutdown(s, 2);
    close (sin);
    close (sout);
  end.

```

---

### 34.4.5 fpaccept

**Synopsis:** Accept a connection from a socket.

**Declaration:** function fpaccept(s: cint; addrx: psockaddr; addrlen: psocklen) : cint

**Visibility:** default

**Description:** Accept accepts a connection from a socket S, which was listening for a connection. If a connection is accepted, a file descriptor is returned (positive number). On error -1 is returned. The returned socket may NOT be used to accept more connections. The original socket remains open.

The Accept call fills the address of the connecting entity in Addr<sub>x</sub>, and sets its length in Addr<sub>len</sub>. Addr<sub>x</sub> should be pointing to enough space, and Addr<sub>len</sub> should be set to the amount of space available, prior to the call.

**Errors:** On error, -1 is returned, and errors are reported in SocketError, and include the following:

**SYS\_EBADF**The socket descriptor is invalid.

**SYS\_ENOTSOCK**The descriptor is not a socket.

**SYS\_EOPNOTSUPP**The socket type doesn't support the `Listen` operation.

**SYS\_EFAULT**`Addr` points outside your address space.

**SYS\_EWOULDBLOCK**The requested operation would block the process.

See also: `fpListen` (1157), `fpConnect` (1154), `fpBind` (1154)

**Listing:** `./sockex/socksvr.pp`

---

```

Program server;

{
  Program to test Sockets unit by Michael van Canneyt and Peter Vreman
  Server Version, First Run sock_svr to let it create a socket and then
  sock_cli to connect to that socket
}

uses Sockets;

Var
  FromName : string;
  Buffer    : string[255];
  S         : Longint;
  Sin, Sout : Text;
  SAddr     : TInetSockAddr;

procedure perror (const S:string);
begin
  writeln (S, SocketError);
  halt(100);
end;

begin
  S:=fpSocket (AF_INET, SOCK_STREAM, 0);
  if SocketError<>0 then
    PError ('Server : Socket : ');
  SAddr.sin_family:=AF_INET;
  { port 50000 in network order }
  SAddr.sin_port:=htons(50000);
  SAddr.sin_addr.s_addr:=0;
  if fpBind(S, @SAddr, sizeof(saddr))=-1 then
    PError ('Server : Bind : ');
  if fpListen (S,1)=-1 then
    PError ('Server : Listen : ');
  Writeln('Waiting for Connect from Client, run now sock_cli in an other tty');
  if not Accept (S, FromName, Sin, Sout) then
    PError ('Server : Accept : '+fromname);
  Reset(Sin);
  ReWrite(Sout);
  Writeln(Sout, 'Message From Server');
  Flush(SOut);
  while not eof(sin) do
    begin
      Readln(Sin, Buffer);
      Writeln('Server : read : ', buffer);
    end;

```

---

end.

---

### 34.4.6 fpbind

Synopsis: Bind a socket to an address.

Declaration: `function fpbind(s: cint; addrx: psockaddr; addrlen: TSocketLen) : cint`

Visibility: default

Description: `fpBind` binds the socket `s` to address `Addrx`. `Addrx` has length `Addrlen`. The function returns 0 if the call was succesful, -1 if not.

Errors: Errors are returned in `SocketError` and include the following:

**SYS\_EBADF**The socket descriptor is invalid.

**SYS\_EINVAL**The socket is already bound to an address,

**SYS\_EACCESS**Address is protected and you don't have permission to open it.

More errors can be found in the Unix man pages.

See also: `Socket` ([1124](#))

### 34.4.7 fpconnect

Synopsis: Open a connection to a server socket.

Declaration: `function fpconnect(s: cint; name: psockaddr; namelen: TSocketLen) : cint`

Visibility: default

Description: `fpConnect` uses the socket `s` to open a connection to a peer, whose address is described by `Name`. `NameLen` contains the length of the address. The type of `Name` depends on the kind of connection you are trying to make, but is generally one of `TSocketAddr` or `TUnixSocketAddr`.

The `fpConnect` function returns zero if the call was successfull, -1 in case of error.

Errors: On error, -1 is returned and errors are reported in `SocketError`.

See also: `fpListen` ([1157](#)), `fpBind` ([1154](#)), `fpAccept` ([1152](#))

**Listing:** `./sockex/sockcli.pp`

---

**Program** Client;

```
{
  Program to test Sockets unit by Michael van Canneyt and Peter Vreman
  Client Version, First Run sock_svr to let it create a socket and then
  sock_cli to connect to that socket
}
```

**uses** Sockets;

```
procedure PError(const S : string);
begin
  writeln(S, SocketError);
  halt(100);
```

**end;**

**Var**

**SAddr** : TInetSockAddr;  
**Buffer** : **string** [255];  
**S** : Longint;  
**Sin**, **Sout** : Text;  
**i** : integer;

**begin**

**S**:=fpSocket (AF\_INET,SOCK\_STREAM,0);  
**if** **s**=-1 **then**  
    Perror('Client : Socket : ');  
**SAddr.sin\_family**:=AF\_INET;  
    { port 50000 in network order }  
**SAddr.sin\_port**:=htons(50000);  
    { localhost : 127.0.0.1 in network order }  
**SAddr.sin\_addr.s\_addr**:=HostToNet((127 **shl** 24) **or** 1);  
**if not** Connect (S,**SAddr**,**Sin**,**Sout**) **then**  
    PError('Client : Connect : ');  
**Reset**(**Sin**);  
**ReWrite**(**Sout**);  
**Buffer**:= 'This is a textstring sent by the Client.';  
**for** **i**:=1 **to** 10 **do**  
    **WriteLn**(**Sout**, **Buffer**);  
**Flush**(**Sout**);  
**ReadLn**(**Sin**, **Buffer**);  
**WriteLn**(**Buffer**);  
    Close(**sout**);

**end.**

---

**Listing:** ./sockex/pfinger.pp

---

**program** pfinger;

**uses** sockets, errors;

**Var**

**Addr** : TInetSockAddr;  
**S** : Longint;  
**Sin**, **Sout** : Text;  
**Line** : **string**;

**begin**

**Addr.sin\_family**:=AF\_INET;  
    { port 79 in network order }  
**Addr.sin\_port**:=79 **shl** 8;  
    { localhost : 127.0.0.1 in network order }  
**Addr.sin\_addr.s\_addr**:=((1 **shl** 24) **or** 127);  
**S**:=fpSocket(AF\_INET,SOCK\_STREAM,0);  
**If Not** Connect (S,**ADDR**,**SIN**,**SOUT**) **Then**  
    **begin**  
        **WriteLn** ( 'Couldn't connect to localhost' );  
        **WriteLn** ( 'Socket error : ',strerror(SocketError));  
        **halt**(1);  
    **end**;  
**rewrite** ( **sout** );  
**reset**(**sin**);

---

```

writeln (sout,paramstr(1));
flush(sout);
while not eof(sin) do
  begin
    readln (Sin,line);
    writeln (line);
  end;
fpShutdown(s,2);
close (sin);
close (sout);
end.

```

---

### 34.4.8 fpgetpeername

**Synopsis:** Return the name (address) of the connected peer.

**Declaration:** `function fpgetpeername(s: cint;name: psockaddr;namelen: psocklen) : cint`

**Visibility:** default

**Description:** `fpGetPeerName` returns the name of the entity connected to the specified socket S. The Socket must be connected for this call to work.

Name should point to enough space to store the name, the amount of space pointed to should be set in `Namelen`. When the function returns successfully, Name will be filled with the name, and Name will be set to the length of Name.

**Errors:** Errors are reported in `SocketError`, and include the following:

**SYS\_EBADF**The socket descriptor is invalid.

**SYS\_ENOBUFS**The system doesn't have enough buffers to perform the operation.

**SYS\_ENOTSOCK**The descriptor is not a socket.

**SYS\_EFAULT**Addr points outside your address space.

**SYS\_ENOTCONN**The socket isn't connected.

See also: `fpConnect` ([1154](#)), `fpSocket` ([1160](#))

### 34.4.9 fpgetsockname

**Synopsis:** Return name of socket.

**Declaration:** `function fpgetsockname(s: cint;name: psockaddr;namelen: psocklen) : cint`

**Visibility:** default

**Description:** `fpGetSockName` returns the current name of the specified socket S. Name should point to enough space to store the name, the amount of space pointed to should be set in `Namelen`. When the function returns successfully, Name will be filled with the name, and `Namelen` will be set to the length of Name.

**Errors:** Errors are reported in `SocketError`, and include the following:

**SYS\_EBADF**The socket descriptor is invalid.

**SYS\_ENOBUFS**The system doesn't have enough buffers to perform the operation.

**SYS\_ENOTSOCK**The descriptor is not a socket.

**SYS\_EFAULT**Addr points outside your address space.

See also: `fpBind` ([1154](#))

### 34.4.10 `fpgetsockopt`

Synopsis: Get current socket options

Declaration: `function fpgetsockopt(s: cint; level: cint; optname: cint; optval: pointer; optlen: psocklen) : cint`

Visibility: default

Description: `fpGetSockOpt` gets the connection option `optname`, for socket `S`. The socket may be obtained from different levels, indicated by `Level`, which can be one of the following:

**SOL\_SOCKET** From the socket itself.

**XXX** set `Level` to `XXX`, the protocol number of the protocol which should interpret the option.

The options are stored in the memory location pointed to by `optval`. `optlen` should point to the initial length of `optval`, and on return will contain the actual length of the stored data.

On success, 0 is returned. On Error, -1 is returned.

Errors: Errors are reported in `SocketError`, and include the following:

**SYS\_EBADF** The socket descriptor is invalid.

**SYS\_ENOTSOCK** The descriptor is not a socket.

**SYS\_EFAULT** `OptVal` points outside your address space.

See also: `fpSetSockOpt` ([1159](#))

### 34.4.11 `fplisten`

Synopsis: Listen for connections on a socket.

Declaration: `function fplisten(s: cint; backlog: cint) : cint`

Visibility: default

Description: `fpListen` listens for up to `backlog` connections from socket `S`. The socket `S` must be of type `SOCK_STREAM` or `Sock_SEQPACKET`.

The function returns 0 if a connection was accepted, -1 if an error occurred.

Errors: Errors are reported in `SocketError`, and include the following:

**SYS\_EBADF** The socket descriptor is invalid.

**SYS\_ENOTSOCK** The descriptor is not a socket.

**SYS\_EOPNOTSUPP** The socket type doesn't support the `Listen` operation.

See also: `fpSocket` ([1160](#)), `fpBind` ([1154](#)), `fpConnect` ([1154](#))

### 34.4.12 `fprecv`

Synopsis: Receive data on socket

Declaration: `function fprecv(s: cint; buf: pointer; len: size_t; flags: cint) : ssize_t`

Visibility: default

**Description:** `fpRecv` reads at most `len` bytes from socket `S` into address `buf`. The socket must be in a connected state. `Flags` can be one of the following:

- 1**Process out-of band data.
- 4**Bypass routing, use a direct interface.
- ??**Wait for full request or report an error.

The functions returns the number of bytes actually read from the socket, or -1 if a detectable error occurred.

**Errors:** Errors are reported in `SocketError`, and include the following:

- SYS\_EBADF**The socket descriptor is invalid.
- SYS\_ENOTCONN**The socket isn't connected.
- SYS\_ENOTSOCK**The descriptor is not a socket.
- SYS\_EFAULT**The address is outside your address space.
- SYS EMSGSIZE**The message cannot be sent atomically.
- SYS\_EWOULDBLOCK**The requested operation would block the process.
- SYS\_ENOBUFS**The system doesn't have enough free buffers available.

See also: `Send` ([1124](#))

### 34.4.13 `fprecvfrom`

**Synopsis:** Receive data from an unconnected socket

**Declaration:** `function fprecvfrom(s: cint;buf: pointer;len: size_t;flags: cint;  
from: psockaddr;fromlen: psocklen) : ssize_t`

**Visibility:** default

**Description:** `fpRecvFrom` receives data in buffer `Buf` with maximum length `Len` from socket `S`. Receipt is controlled by options in `Flags`. The location pointed to by `from` will be filled with the address from the sender, and it's length will be stored in `fromlen`. The function returns the number of bytes received, or -1 on error. `AddrLen`.

**Errors:** On error, -1 is returned.

See also: `fpSocket` ([1160](#)), `frecv` ([1157](#))

### 34.4.14 `fpSend`

**Synopsis:** Send data through socket

**Declaration:** `function fpSend(s: cint;msg: pointer;len: size_t;flags: cint) : ssize_t`

**Visibility:** default

**Description:** `fpSend` sends `Len` bytes starting from address `Msg` to socket `S`. `S` must be in a connected state. Options can be passed in `Flags`.

The function returns the number of bytes sent, or -1 if a detectable error occurred.

`Flags` can be one of the following:

- 1**Process out-of band data.



4Bypass routing, use a direct interface.

Errors: Errors are reported in `SocketError`, and include the following:

**SYS\_EBADF**The socket descriptor is invalid.

**SYS\_ENOTSOCK**The descriptor is not a socket.

**SYS\_EFAULT**The address is outside your address space.

**SYS\_MSGSIZE**The message cannot be sent atomically.

**SYS\_EWOULDBLOCK**The requested operation would block the process.

**SYS\_ENOBUFS**The system doesn't have enough free buffers available.

See also: `fpRecv` (1157)

### 34.4.15 `fpsendto`

Synopsis: Send data through an unconnected socket to an address.

Declaration: `function fp sendto(s: cint;msg: pointer;len: size_t;flags: cint;  
                                  tox: psockaddr;tolen: TSocketLen) : ssize_t`

Visibility: default

Description: `fpSendTo` sends data from buffer `Msg` with length `len` through socket `S` with options `Flags`.  
The data is sent to address `tox`, which has length `toLen`

Errors: On error, -1 is returned.

See also: `fpSocket` (1160), `fpSend` (1158), `fpRecvFrom` (1158)

### 34.4.16 `fpsetsockopt`

Synopsis: Set socket options.

Declaration: `function fpsetsockopt(s: cint;level: cint;optname: cint;optval: pointer;  
                                  optlen: TSocketLen) : cint`

Visibility: default

Description: `fpSetSockOpt` sets the connection options for socket `S`. The socket may be manipulated at different levels, indicated by `Level`, which can be one of the following:

**SOL\_SOCKET**To manipulate the socket itself.

**XXX**set `Level` to `XXX`, the protocol number of the protocol which should interpret the option.

The actual option is stored in a buffer pointed to by `optval`, with length `optlen`.

For more information on this call, refer to the unix manual page `setsockopt`

Errors: Errors are reported in `SocketError`, and include the following:

**SYS\_EBADF**The socket descriptor is invalid.

**SYS\_ENOTSOCK**The descriptor is not a socket.

**SYS\_EFAULT**`OptVal` points outside your address space.

See also: `fpGetSockOpt` (1157)

### 34.4.17 `fpshutdown`

Synopsis: Close one end of full duplex connection.

Declaration: `function fpshutdown(s: cint;how: cint) : cint`

Visibility: default

Description: `fpShutDown` closes one end of a full duplex socket connection, described by `S`. The parameter `How` determines how the connection will be shut down, and can be one of the following:

**0**Further receives are disallowed.

**1**Further sends are disallowed.

**2**Sending nor receiving are allowed.

On succes, the function returns 0, on error -1 is returned.

Errors: `SocketError` is used to report errors, and includes the following:

**SYS\_EBADF**The socket descriptor is invalid.

**SYS\_ENOTCONN**The socket isn't connected.

**SYS\_ENOTSOCK**The descriptor is not a socket.

See also: `fpSocket` ([1160](#)), `fpConnect` ([1154](#))

### 34.4.18 `fpsocket`

Synopsis: Create new socket

Declaration: `function fpsocket(domain: cint;xtype: cint;protocol: cint) : cint`

Visibility: default

Description: `fpSocket` creates a new socket in domain `Domain`, from type `xType` using protocol `Protocol`. The Domain, Socket type and Protocol can be specified using predefined constants (see the section on constants for available constants) If succesfull, the function returns a socket descriptor, which can be passed to a subsequent `fpBind` ([1154](#)) call. If unsuccesfull, the function returns -1.

for an example, see `Accept` ([1148](#)).

Errors: Errors are returned in `SocketError`, and include the follwing:

**SYS\_EPROTONOSUPPORT**The protocol type or the specified protocol is not supported within this domain.

**SYS\_EMFILE**The per-process descriptor table is full.

**SYS\_ENFILE**The system file table is full.

**SYS\_EACCESS**Permission to create a socket of the specified type and/or protocol is denied.

**SYS\_ENOBUFS**Insufficient buffer space is available. The socket cannot be created until sufficient resources are freed.

See also: `SocketPair` ([1124](#))

### 34.4.19 `fpsocketpair`

Synopsis: Create socket pair.

Declaration: `function fpsocketpair(d: cint; xtype: cint; protocol: cint; sv: puint) : cint`

Visibility: default

Description: `fpSocketPair` creates 2 sockets in domain `D`, from type `xType` and using protocol `Protocol`. The pair is returned in `sv`, and they are indistinguishable. The function returns -1 upon error and 0 upon success.

Errors: Errors are reported in `SocketError`, and are the same as in `Socket` ([1124](#))

See also: `Str2UnixSockAddr` ([1165](#))

### 34.4.20 `HostAddrToStr`

Synopsis: Convert a host address to a string.

Declaration: `function HostAddrToStr(Entry: in_addr) : AnsiString`

Visibility: default

Description: `HostAddrToStr` converts the host address in `Entry` to a string representation in human-readable form (a dotted quad).

Basically, it is the same as `NetAddrToStr` ([1162](#)), but with the bytes in correct order.

See also: `NetAddrToStr` ([1162](#)), `StrToHostAddr` ([1165](#)), `StrToNetAddr` ([1165](#))

### 34.4.21 `HostAddrToStr6`

Synopsis: Convert a IPV6 host address to a string representation.

Declaration: `function HostAddrToStr6(Entry: Tin6_addr) : AnsiString`

Visibility: default

Description: `HostAddrToStr6` converts the IPV6 host address in `Entry` to a string representation in human-readable form.

Basically, it is the same as `NetAddrToStr6` ([1162](#)), but with the bytes in correct order.

See also: `NetAddrToStr` ([1162](#)), `StrToHostAddr` ([1165](#)), `StrToNetAddr` ([1165](#)), `StrToHostAddr6` ([1165](#))

### 34.4.22 `HostToNet`

Synopsis: Convert a host address to a network address

Declaration: `function HostToNet(Host: in_addr) : in_addr`  
`function HostToNet(Host: LongInt) : LongInt`

Visibility: default

Description: `HostToNet` converts a host address to a network address. It takes care of endianness of the host machine. The address can be specified as a dotted quad or as a longint.

Errors: None.

See also: `NetToHost` ([1163](#)), `NToHS` ([1163](#)), `HToNS` ([1162](#)), `ShortHostToNet` ([1163](#)), `ShortNetToHost` ([1164](#))

### 34.4.23 htonl

Synopsis: Convert long integer from host ordered to network ordered

Declaration: `function htonl(host: LongInt) : LongInt`

Visibility: default

Description: `htonl` makes sure that the bytes in `host` are ordered in the correct way for sending over the network and returns the correctly ordered result.

See also: `htons` ([1162](#)), `ntohl` ([1163](#)), `ntohs` ([1163](#))

### 34.4.24 htons

Synopsis: Convert short integer from host ordered to network ordered

Declaration: `function htons(host: Word) : Word`

Visibility: default

Description: `htons` makes sure that the bytes in `host` are ordered in the correct way for sending over the network and returns the correctly ordered result.

See also: `htonl` ([1162](#)), `ntohl` ([1163](#)), `ntohs` ([1163](#))

### 34.4.25 NetAddrToStr

Synopsis: Convert a network address to a string.

Declaration: `function NetAddrToStr(Entry: in_addr) : AnsiString`

Visibility: default

Description: `NetAddrToStr` converts the network address in `Entry` to a string representation in human-readable form (a dotted quad).

See also: `HostAddrToStr` ([1161](#)), `StrToNetAddr` ([1165](#)), `StrToHostAddr` ([1165](#))

### 34.4.26 NetAddrToStr6

Synopsis: Convert a IPV6 network address to a string.

Declaration: `function NetAddrToStr6(Entry: Tin6_addr) : AnsiString`

Visibility: default

Description: `NetAddrToStr6` converts the IPV6 network address in `Entry` to a string representation in human-readable form.

Basically, it is the same as `NetAddrToStr6` ([1162](#)), but with the bytes in correct order.

See also: `NetAddrToStr` ([1162](#)), `StrToHostAddr` ([1165](#)), `StrToNetAddr` ([1165](#)), `StrToHostAddr6` ([1165](#))

### 34.4.27 NetToHost

Synopsis: Convert a network address to a host address.

Declaration: `function NetToHost (Net: in_addr) : in_addr`  
`function NetToHost (Net: LongInt) : LongInt`

Visibility: default

Description: `NetToHost` converts a network address to a host address. It takes care of endianness of the host machine. The address can be specified as a dotted quad or as a longint.

Errors: None.

See also: `HostToNet` (1161), `NToHS` (1163), `HToNS` (1162), `ShortHostToNet` (1163), `ShortNetToHost` (1164)

### 34.4.28 NToHl

Synopsis: Convert long integer from network ordered to host ordered

Declaration: `function NToHl (Net: LongInt) : LongInt`

Visibility: default

Description: `ntohs` makes sure that the bytes in `Net`, received from the network, are ordered in the correct way for handling by the host machine, and returns the correctly ordered result.

See also: `htonl` (1162), `htons` (1162), `ntohs` (1163)

### 34.4.29 NToHs

Synopsis: Convert short integer from network ordered to host ordered

Declaration: `function NToHs (Net: Word) : Word`

Visibility: default

Description: `ntohs` makes sure that the bytes in `Net`, received from the network, are ordered in the correct way for handling by the host machine, and returns the correctly ordered result.

See also: `htonl` (1162), `htons` (1162), `ntohl` (1163)

### 34.4.30 ShortHostToNet

Synopsis: Convert a host port number to a network port number

Declaration: `function ShortHostToNet (Host: Word) : Word`

Visibility: default

Description: `ShortHostToNet` converts a host port number to a network port number. It takes care of endianness of the host machine.

Errors: None.

See also: `ShortNetToHost` (1164), `HostToNet` (1161), `NToHS` (1163), `HToNS` (1162)

### 34.4.31 ShortNetToHost

Synopsis: Convert a network port number to a host port number

Declaration: `function ShortNetToHost (Net: Word) : Word`

Visibility: default

Description: `ShortNetToHost` converts a network port number to a host port number. It takes care of endianness of the host machine.

Errors: None.

See also: `ShortNetToHost` ([1164](#)), `HostToNet` ([1161](#)), `NToHS` ([1163](#)), `HToNS` ([1162](#))

### 34.4.32 Sock2File

Synopsis: Convert socket to untyped file descriptors

Declaration: `procedure Sock2File (Sock: LongInt; var SockIn: File; var SockOut: File)`

Visibility: default

Description: `Sock2File` transforms a socket `Sock` into 2 Pascal file descriptors of type `File`, one for reading from the socket (`SockIn`), one for writing to the socket (`SockOut`).

Errors: None.

See also: `Socket` ([1124](#)), `Sock2Text` ([1164](#))

### 34.4.33 Sock2Text

Synopsis: Convert socket to text file descriptors

Declaration: `procedure Sock2Text (Sock: LongInt; var SockIn: Text; var SockOut: Text)`

Visibility: default

Description: `Sock2Text` transforms a socket `Sock` into 2 Pascal file descriptors of type `Text`, one for reading from the socket (`SockIn`), one for writing to the socket (`SockOut`).

Errors: None.

See also: `Socket` ([1124](#)), `Sock2File` ([1164](#))

### 34.4.34 socketerror

Synopsis: Contains the error code for the last socket operation.

Declaration: `function socketerror : cint`

Visibility: default

Description: `SocketError` contains the error code for the last socket operation. It can be examined to return the last socket error.

### 34.4.35 Str2UnixSockAddr

Synopsis: Convert path to TUnixSockAddr ([1148](#))

Declaration: `procedure Str2UnixSockAddr(const addr: String; var t: TUnixSockAddr;  
var len: LongInt)`

Visibility: default

Description: `Str2UnixSockAddr` transforms a Unix socket address in a string to a `TUnixSockAddr` structure which can be passed to the `Bind` ([1150](#)) call.

Errors: None.

See also: `Socket` ([1124](#)), `Bind` ([1150](#))

### 34.4.36 StrToHostAddr

Synopsis: Convert a string to a host address.

Declaration: `function StrToHostAddr(IP: AnsiString) : in_addr`

Visibility: default

Description: `StrToHostAddr` converts the string representation in `IP` to a host address and returns the host address.

Errors: On error, the host address is filled with zeroes.

See also: `NetAddrToStr` ([1162](#)), `HostAddrToStr` ([1161](#)), `StrToNetAddr` ([1165](#))

### 34.4.37 StrToHostAddr6

Synopsis: Convert a string to a IPV6 host address.

Declaration: `function StrToHostAddr6(IP: String) : Tin6_addr`

Visibility: default

Description: `StrToHostAddr6` converts the string representation in `IP` to a IPV6 host address and returns the host address.

Errors: On error, the address is filled with zeroes.

See also: `NetAddrToStr6` ([1162](#)), `HostAddrToStr6` ([1161](#)), `StrToHostAddr` ([1165](#))

### 34.4.38 StrToNetAddr

Synopsis: Convert a string to a network address.

Declaration: `function StrToNetAddr(IP: AnsiString) : in_addr`

Visibility: default

Description: `StrToNetAddr` converts the string representation in `IP` to a network address and returns the network address.

Errors: On error, the network address is filled with zeroes.

See also: `NetAddrToStr` ([1162](#)), `HostAddrToStr` ([1161](#)), `StrToHostAddr` ([1165](#))

### 34.4.39 StrToNetAddr6

Synopsis: Convert a string to a IPV6 network address

Declaration: `function StrToNetAddr6(IP: AnsiString) : Tin6_addr`

Visibility: default

Description: `StrToNetAddr6` converts the string representation in `IP` to a IPV6 network address and returns the network address.

Errors: On error, the address is filled with zeroes.

See also: `NetAddrToStr6` ([1162](#)), `HostAddrToStr6` ([1161](#)), `StrToHostAddr6` ([1165](#))



# Chapter 35

## Reference for unit 'strings'

### 35.1 Overview

This chapter describes the `STRINGS` unit for Free Pascal. This unit is system independent, and therefore works on all supported platforms.

### 35.2 Procedures and functions

#### 35.2.1 `stralloc`

Synopsis: Allocate memory for a new null-terminated string on the heap

Declaration: `function stralloc(L: SizeInt) : pchar`

Visibility: default

Description: `StrAlloc` reserves memory on the heap for a string with length `Len`, terminating `#0` included, and returns a pointer to it.

Errors: If there is not enough memory, a run-time error occurs.

See also: `StrNew` ([1176](#)), `StrPCopy` ([1177](#))

#### 35.2.2 `strcat`

Synopsis: Concatenate 2 null-terminated strings.

Declaration: `function strcat(dest: pchar; source: pchar) : pchar`

Visibility: default

Description: Attaches `Source` to `Dest` and returns `Dest`.

Errors: No length checking is performed.

See also: `StrLCat` ([1172](#))

**Listing:** `./stringex/ex11.pp`

---

```

Program Example11;

Uses strings;

{ Program to demonstrate the StrCat function. }

Const P1 : PChar = 'This is a PChar String.';

Var P2 : PChar;

begin
  P2:= StrAlloc ( StrLen(P1)*2+1);
  StrMove (P2,P1,StrLen(P1)+1); { P2=P1 }
  StrCat (P2,P1); { Append P2 once more }
  WriteLn ( 'P2 : ',P2);
  StrDispose(P2);
end.

```

---

### 35.2.3 strcmp

Synopsis: Compare 2 null-terminated strings, case sensitive.

Declaration: `function strcmp(str1: pchar;str2: pchar) : SizeInt`

Visibility: default

Description: Compares the null-terminated strings S1 and S2. The result is

- A negative `SizeInt` when  $S1 < S2$ .
- 0 when  $S1 = S2$ .
- A positive `SizeInt` when  $S1 > S2$ .

For an example, see `StrLComp` ([1173](#)).

Errors: None.

See also: `StrLComp` ([1173](#)), `StrIComp` ([1171](#)), `StrLComp` ([1174](#))

### 35.2.4 strcpy

Synopsis: Copy a null-terminated string

Declaration: `function strcpy(dest: pchar;source: pchar) : pchar`

Visibility: default

Description: Copy the null terminated string in `Source` to `Dest`, and returns a pointer to `Dest`. `Dest` needs enough room to contain `Source`, i.e. `StrLen(Source)+1` bytes.

Errors: No length checking is performed.

See also: `StrPCopy` ([1177](#)), `StrLCopy` ([1173](#)), `StrECopy` ([1169](#))

**Listing:** `./stringex/ex4.pp`

---

```

Program Example4;

Uses strings;

{ Program to demonstrate the StrCopy function. }

Const P : PChar = 'This is a PCHAR string.';

var PP : PChar;

begin
  PP:= StrAlloc (Strlen(P)+1);
  STrCopy (PP,P);
  If StrComp (PP,P)<>0 then
    Writeln ( 'Oh-oh problems...' )
  else
    Writeln ( 'All is well : PP=',PP);
  StrDispose(PP);
end.

```

---

### 35.2.5 strdispose

Synopsis: disposes of a null-terminated string on the heap

Declaration: `procedure strdispose(p: pchar)`

Visibility: default

Description: Removes the string in P from the heap and releases the memory.

Errors: None.

See also: StrNew ([1176](#))

**Listing:** ./stringex/ex17.pp

---

```

Program Example17;

Uses strings;

{ Program to demonstrate the StrDispose function. }

Const P1 : PChar = 'This is a PChar string';

var P2 : PChar;

begin
  P2:=StrNew (P1);
  Writeln ( 'P2 : ',P2);
  StrDispose(P2);
end.

```

---

### 35.2.6 strecopy

Synopsis: Copy a null-terminated string, return a pointer to the end.

**Declaration:** `function strecopy(dest: pchar;source: pchar) : pchar`

**Visibility:** default

**Description:** Copies the Null-terminated string in `Source` to `Dest`, and returns a pointer to the end (i.e. the terminating Null-character) of the copied string.

**Errors:** No length checking is performed.

**See also:** `StrLCopy` ([1173](#)), `StrCopy` ([1168](#))

**Listing:** `./stringex/ex6.pp`

---

**Program** Example6;

**Uses** strings;

*{ Program to demonstrate the StrECopy function. }*

**Const** P : PChar = 'This is a PCHAR string.';

**Var** PP : PChar;

**begin**

PP:= StrAlloc (StrLen(P)+1);

**If** Longint(StrECopy(PP,P)) – Longint(PP) <> StrLen(P) **then**

    Writeln('Something is wrong here !')

**else**

    Writeln('PP= ',PP);

    StrDispose(PP);

**end.**

---

### 35.2.7 strend

**Synopsis:** Return a pointer to the end of a null-terminated string

**Declaration:** `function strend(p: pchar) : pchar`

**Visibility:** default

**Description:** Returns a pointer to the end of P. (i.e. to the terminating null-character.

**Errors:** None.

**See also:** `StrLen` ([1174](#))

**Listing:** `./stringex/ex7.pp`

---

**Program** Example6;

**Uses** strings;

*{ Program to demonstrate the StrEnd function. }*

**Const** P : PChar = 'This is a PCHAR string.';

**begin**

**If** Longint(StrEnd(P)) – Longint(P) <> StrLen(P) **then**

    Writeln('Something is wrong here !')

---

```

    else
      Writeln ( 'All is well..' );
    end.

```

---

### 35.2.8 stricmp

Synopsis: Compare 2 null-terminated strings, case insensitive.

Declaration: `function stricmp(str1: pchar;str2: pchar) : SizeInt`

Visibility: default

Description: Compares the null-terminated strings S1 and S2, ignoring case. The result is

- A negative `SizeInt` when  $S1 < S2$ .
- 0 when  $S1 = S2$ .
- A positive `SizeInt` when  $S1 > S2$ .

Errors: None.

See also: `StrLComp` ([1173](#)), `StrComp` ([1168](#)), `StrLComp` ([1174](#))

**Listing:** ./stringex/ex8.pp

---

**Program** Example8;

**Uses** strings;

*{ Program to demonstrate the StrLComp function. }*

```

Const P1 : PChar = 'This is the first string.';
      P2 : PChar = 'This is the second string.';

```

```

Var L : Longint;

```

```

begin
  Write ( 'P1 and P2 are ');
  If StrComp (P1,P2)<>0 then write ( 'NOT ');
  write ( 'equal. The first ');
  L:=1;
  While StrLComp(P1,P2,L)=0 do inc (L);
  dec(L);
  Writeln (L,' characters are the same. ');
end.

```

---

### 35.2.9 stripos

Synopsis: Return the position of a substring in a string, case insensitive.

Declaration: `function stripos(str1: pchar;str2: pchar) : pchar`

Visibility: default

Description: `stripos` returns the position of `str2` in `str1`. It searches in a case-insensitive manner, and if it finds a match, it returns a pointer to the location of the match. If no match is found, `Nil` is returned.

**Errors:** No checks are done on the validity of the pointers, and the pointers are assumed to point to a properly null-terminated string. If either of these conditions are not met, a run-time error may follow.

See also: `striscan` ([1172](#)), `strpos` ([1178](#))

### 35.2.10 `striscan`

**Synopsis:** Scan a string for a character, case-insensitive

**Declaration:** `function striscan(p: pchar; c: Char) : pchar`

**Visibility:** default

**Description:** `striscan` does the same as `strscan` ([1179](#)) but compares the characters case-insensitively. It returns a pointer to the first occurrence of the character `c` in the null-terminated string `p`, or `Nil` if `c` is not present in the string.

See also: `strscan` ([1179](#)), `striscan` ([1178](#))

### 35.2.11 `strlcat`

**Synopsis:** Concatenate 2 null-terminated strings, with length boundary.

**Declaration:** `function strlcat(dest: pchar; source: pchar; l: SizeInt) : pchar`

**Visibility:** default

**Description:** Adds `L` characters from `Source` to `Dest`, and adds a terminating null-character. Returns `Dest`.

**Errors:** None.

See also: `StrCat` ([1167](#))

**Listing:** `./stringex/ex12.pp`

---

**Program** `Example12;`

**Uses** `strings;`

*{ Program to demonstrate the StrLCat function. }*

**Const** `P1 : PChar = '1234567890';`

**Var** `P2 : PChar;`

**begin**

`P2:=StrAlloc (StrLen(P1)*2+1);`

`P2^:=#0; { Zero length }`

`StrCat (P2,P1);`

`StrLCat (P2,P1,5);`

`Writeln ( 'P2 = ',P2);`

`StrDispose(P2)`

**end.**

---

### 35.2.12 strlcomp

Synopsis: Compare limited number of characters of 2 null-terminated strings

Declaration: `function strlcomp(str1: pchar;str2: pchar;l: SizeInt) : SizeInt`

Visibility: default

Description: Compares maximum L characters of the null-terminated strings S1 and S2. The result is

- A negative `SizeInt` when `S1<S2`.
- 0 when `S1=S2`.
- A positive `SizeInt` when `S1>S2`.

Errors: None.

See also: `StrComp` ([1168](#)), `StrIComp` ([1171](#)), `StrLComp` ([1174](#))

**Listing:** `./stringex/ex8.pp`

---

**Program** `Example8`;

**Uses** `strings`;

*{ Program to demonstrate the StrLComp function. }*

**Const** `P1 : PChar = 'This is the first string.'`;  
          `P2 : PChar = 'This is the second string.'`;

**Var** `L : Longint`;

**begin**

`Write ( 'P1 and P2 are ' );`  
  `If StrComp (P1,P2)<>0 then write ( 'NOT ' );`  
  `write ( 'equal. The first ' );`  
  `L:=1;`  
  `While StrLComp(P1,P2,L)=0 do inc ( L );`  
  `dec(L);`  
  `WriteLn (L,' characters are the same.');`

**end.**

---

### 35.2.13 strlcopy

Synopsis: Copy a null-terminated string, limited in length.

Declaration: `function strlcopy(dest: pchar;source: pchar;maxlen: SizeInt) : pchar`

Visibility: default

Description: Copies `MaxLen` characters from `Source` to `Dest`, and makes `Dest` a null terminated string.

Errors: No length checking is performed.

See also: `StrCopy` ([1168](#)), `StrECopy` ([1169](#))

**Listing:** `./stringex/ex5.pp`

---

```

Program Example5;

Uses strings;

{ Program to demonstrate the StrLCopy function. }

Const P : PChar = '123456789ABCDEF';

var PP : PChar;

begin
  PP:= StrAlloc(11);
  WriteLn ( 'First 10 characters of P : ',StrLCopy (PP,P,10));
  StrDispose(PP);
end.

```

---

### 35.2.14 strlen

Synopsis: Length of a null-terminated string.

Declaration: `function strlen(p: pchar) : sizeint`

Visibility: default

Description: Returns the length of the null-terminated string P.

Errors: None.

See also: StrNew ([1176](#))

**Listing:** ./stringex/ex1.pp

---

```

Program Example1;

Uses strings;

{ Program to demonstrate the StrLen function. }

Const P : PChar = 'This is a constant pchar string';

begin
  WriteLn ( 'P          : ',p);
  WriteLn ( 'length(P) : ',StrLen(P));
end.

```

---

### 35.2.15 strlicomp

Synopsis: Compare limited number of characters in 2 null-terminated strings, ignoring case.

Declaration: `function strlicomp(str1: pchar;str2: pchar;l: SizeInt) : SizeInt`

Visibility: default

Description: Compares maximum L characters of the null-terminated strings S1 and S2, ignoring case. The result is



- A negative `SizeInt` when  $S1 < S2$ .
- 0 when  $S1 = S2$ .
- A positive `SizeInt` when  $S1 > S2$ .

For an example, see `StrIComp` ([1171](#))

Errors: None.

See also: `StrLComp` ([1173](#)), `StrComp` ([1168](#)), `StrIComp` ([1171](#))

### 35.2.16 `strlower`

Synopsis: Convert null-terminated string to all-lowercase.

Declaration: `function strlower(p: pchar) : pchar`

Visibility: default

Description: Converts `P` to an all-lowercase string. Returns `P`.

Errors: None.

See also: `StrUpper` ([1179](#))

**Listing:** `./stringex/ex14.pp`

---

**Program** `Example14;`

**Uses** `strings;`

*{ Program to demonstrate the StrLower and StrUpper functions. }*

**Const**

`P1 : PChar = 'THIS IS AN UPPERCASE PCHAR STRING';`  
`P2 : PChar = 'this is a lowercase string';`

**begin**

`WriteLn ('Uppercase : ', StrUpper(P2));`  
`StrLower (P1);`  
`WriteLn ('Lowercase : ', P1);`

**end.**

---

### 35.2.17 `strmove`

Synopsis: Move a null-terminated string to new location.

Declaration: `function strmove(dest: pchar;source: pchar;l: SizeInt) : pchar`

Visibility: default

Description: Copies `MaxLen` characters from `Source` to `Dest`. No terminating null-character is copied. Returns `Dest`

Errors: None.

See also: `StrLCopy` ([1173](#)), `StrCopy` ([1168](#))

**Listing:** ./stringex/ex10.pp

---

**Program** Example10;

**Uses** strings;

*{ Program to demonstrate the StrMove function. }*

**Const** P1 : PCHAR = 'This is a pchar string.';

**Var** P2 : Pchar;

**begin**

  P2:=StrAlloc (StrLen(P1)+1);

**StrMove** (P2,P1,StrLen(P1)+1); { P2:=P1 }

**Writeln** ( 'P2 = ',P2);

**StrDispose**(P2);

**end.**

---

### 35.2.18 strnew

Synopsis: Allocate room for new null-terminated string.

Declaration: function strnew(p: pchar) : pchar

Visibility: default

Description: Copies P to the Heap, and returns a pointer to the copy.

Errors: Returns Nil if no memory was available for the copy.

See also: StrCopy ([1168](#)), StrDispose ([1169](#))

**Listing:** ./stringex/ex16.pp

---

**Program** Example16;

**Uses** strings;

*{ Program to demonstrate the StrNew function. }*

**Const** P1 : PChar = 'This is a PChar string';

**var** P2 : PChar;

**begin**

  P2:=StrNew (P1);

**If** P1=P2 **then**

**writeln** ( 'This can''t be happening... ')

**else**

**writeln** ( 'P2 : ',P2);

**StrDispose**(P2);

**end.**

---

**35.2.19 strpas**

Synopsis: Convert a null-terminated string to a shortstring.

Declaration: `function strpas(p: pchar) : shortstring`

Visibility: default

Description: Converts a null terminated string in P to a Pascal string, and returns this string. The string is truncated at 255 characters.

Errors: None.

See also: StrPCopy ([1177](#))

**Listing:** ./stringex/ex3.pp

---

**Program** Example3;

**Uses** strings;

*{ Program to demonstrate the StrPas function. }*

**Const** P : PChar = 'This is a PCHAR string';

**var** S : **string**;

**begin**

    S:=StrPas (P);

    WriteLn ('S : ',S);

**end.**

---

**35.2.20 strcpy**

Synopsis: Copy a pascal string to a null-terminated string

Declaration: `function strcpy(d: pchar;const s: String) : pchar`

Visibility: default

Description: Converts the Pascal string in Se to a Null-terminated string, and copies it to D. D needs enough room to contain the string Source, i.e. Length(S)+1 bytes.

Errors: No length checking is performed.

See also: StrPas ([1177](#))

**Listing:** ./stringex/ex2.pp

---

**Program** Example2;

**Uses** strings;

*{ Program to demonstrate the StrPCopy function. }*

**Const** S = 'This is a normal string.';

**Var** P : Pchar;

---

```

begin
  p:= StrAlloc (length(S)+1);
  if StrPCopy (P,S)<>P then
    Writeln ('This is impossible !!')
  else
    writeln (P);
    StrDispose(P);
end.

```

---

### 35.2.21 strpos

Synopsis: Search for a null-terminated substring in a null-terminated string

Declaration: `function strpos(str1: pchar;str2: pchar) : pchar`

Visibility: default

Description: Returns a pointer to the first occurrence of S2 in S1. If S2 does not occur in S1, returns Nil.

Errors: None.

See also: StrScan ([1179](#)), StrRScan ([1179](#))

**Listing:** ./stringex/ex15.pp

---

**Program** Example15;

**Uses** strings;

*{ Program to demonstrate the StrPos function. }*

**Const** P : PChar = 'This is a PChar string.';  
           S : PChar = 'is';

**begin**  
     Writeln ('Position of ''is'' in P : ',sizeint(StrPos(P,S))-sizeint(P));  
**end.**

---

### 35.2.22 strriscan

Synopsis: Scan a string reversely for a character, case-insensitive

Declaration: `function strriscan(p: pchar;c: Char) : pchar`

Visibility: default

Description: `strriscan` does the same as `strrscan` ([1179](#)) but compares the characters case-insensitively. It returns a pointer to the last occurrence of the character `c` in the null-terminated string `p`, or Nil if `c` is not present in the string.

See also: `strrscan` ([1179](#)), `striscan` ([1172](#))

**35.2.23 strscan**

Synopsis: Find last occurrence of a character in a null-terminated string.

Declaration: `function strscan(p: pchar; c: Char) : pchar`

Visibility: default

Description: Returns a pointer to the last occurrence of the character C in the null-terminated string P. If C does not occur, returns Nil.

For an example, see StrScan (1179).

Errors: None.

See also: StrScan (1179), StrPos (1178)

**35.2.24 strscan**

Synopsis: Find first occurrence of a character in a null-terminated string.

Declaration: `function strscan(p: pchar; c: Char) : pchar`

Visibility: default

Description: Returns a pointer to the first occurrence of the character C in the null-terminated string P. If C does not occur, returns Nil.

Errors: None.

See also: StrRScan (1179), StrPos (1178)

**Listing:** ./stringex/ex13.pp

---

**Program** Example13;

**Uses** strings;

*{ Program to demonstrate the StrScan and StrRScan functions. }*

**Const** P : PChar = 'This is a PCHAR string.';  
           S : Char = 's' ;

**begin**

**WriteLn** ('P, starting from first 's' : ', **StrScan**(P,s));

**WriteLn** ('P, starting from last 's' : ', **StrRScan**(P,s));

**end.**

---

**35.2.25 strupper**

Synopsis: Convert null-terminated string to all-uppercase

Declaration: `function strupper(p: pchar) : pchar`

Visibility: default

Description: Converts P to an all-uppercase string. Returns P.

For an example, see StrLower (1175)

Errors: None.

See also: StrLower (1175)

# Chapter 36

## Reference for unit 'strutils'

### 36.1 Used units

Table 36.1: Used units by unit 'strutils'

Name	Page
SysUtils	<a href="#">1180</a>

### 36.2 Constants, types and variables

#### 36.2.1 Resource strings

`SErrAmountStrings` = 'Amount of search and replace strings don''t match'

Error message used in stringsreplace function

#### 36.2.2 Constants

`AnsiResemblesProc` : `TCompareTextProc` = `@SoundexProc`

This procedural variable is standard set to `SoundexProc` ([1204](#)) but can be overridden with a user-defined algorithm. This algorithm should return `True` if `AText` resembles `AOtherText`, or `False` otherwise. The standard routine compares the soundexes of the two strings and returns `True` if they are equal.

`Brackets` = ['(', ')', '[', ']', '{', '}', '']

Set of characters that contain all possible bracket characters

`DigitChars` = ['0'..'9']

Set of digit characters

`StdSwitchChars` = ['-','/']

Standard characters for the `SwitchChars` argument of `GetCmdLineArg` (1193).

```
StdWordDelims = [#0..' ',',','.',':','/','\',' ','"',',','`']+Brackets
```

Standard word delimiter values.

```
WordDelimiters : Set of Char = [#0..#255]-['a'..'z','A'..'Z','1'..'9','0']
```

Standard word delimiters, used in the `SearchBuf` (1203) call.

### 36.2.3 Types

```
TCompareTextProc = function(const AText: String;const AOther: String)
                    : Boolean
```

Function prototype for comparing two string in `AnsiResemblesText` (1186)

```
TSoundexIntLength = 1..8
```

Range of allowed integer soundex lengths.

```
TSoundexLength = 1..MaxInt
```

Range of allowed soundex lengths.

```
TStringSeachOption = TStringSearchOption
```

There is an typo error in the original Borland `StrUtils` unit. This type just refers to the correct `TStringSearchOption` (1181) and is provided for compatibility only.

```
TStringSearchOption = (soDown,soMatchCase,soWholeWord)
```

Table 36.2: Enumeration values for type `TStringSearchOption`

Value	Explanation
<code>soDown</code>	Search in down direction.
<code>soMatchCase</code>	Match case
<code>soWholeWord</code>	Search whole words only.

Possible options for `SearchBuf` (1203) call.

```
TStringSearchOptions= Set of (soDown,soMatchCase,soWholeWord)
```

Set of options for `SearchBuf` (1203) call.

## 36.3 Procedures and functions

### 36.3.1 AddChar

Synopsis: Add characters to the left of a string till a certain length

Declaration: `function AddChar(C: Char; const S: String; N: Integer) : String`

Visibility: default

Description: `AddChar` adds characters (C) to the left of S till the length N is reached, and returns the resulting string. If the length of S is already equal to or larger than N, then no characters are added. The resulting string can be thought of as a right-aligned version of S, with length N.

Errors: None

See also: `AddCharR` ([1182](#)), `PadLeft` ([1198](#)), `PadRight` ([1199](#)), `PadCenter` ([1198](#))

### 36.3.2 AddCharR

Synopsis: Add chars at the end of a string till it reaches a certain length

Declaration: `function AddCharR(C: Char; const S: String; N: Integer) : String`

Visibility: default

Description: `AddCharR` adds characters (C) to the right of S till the length N is reached, and returns the resulting string. If the length of S is already equal to or larger than N, then no characters are added. The resulting string can be thought of as a left-aligned version of S, with length N.

Errors: None

See also: `AddChar` ([1182](#))

### 36.3.3 AnsiContainsStr

Synopsis: Checks whether a string contains a given substring

Declaration: `function AnsiContainsStr(const AText: String; const ASubText: String) : Boolean`

Visibility: default

Description: `AnsiContainsString` checks whether AText contains ASubText, and returns True if this is the case, or returns False otherwise. The search is performed case-sensitive.

Errors: None

See also: `AnsiContainsText` ([1182](#)), `AnsiEndsStr` ([1183](#)), `AnsiIndexStr` ([1183](#)), `AnsiStartsStr` ([1187](#))

### 36.3.4 AnsiContainsText

Synopsis: Check whether a string contains a certain substring, ignoring case.

Declaration: `function AnsiContainsText(const AText: String; const ASubText: String) : Boolean`

Visibility: default



**Description:** `AnsiContainsString` checks whether `AText` contains `ASubText`, and returns `True` if this is the case, or returns `False` otherwise. The search is performed case-insensitive.

**Errors:**

See also: `AnsiContainsStr` (1182), `AnsiEndsText` (1183), `AnsiIndexText` (1184), `AnsiStartsText` (1187)

### 36.3.5 `AnsiEndsStr`

**Synopsis:** Check whether a string ends with a certain substring

**Declaration:** `function AnsiEndsStr(const ASubText: String; const AText: String) : Boolean`

**Visibility:** default

**Description:** `AnsiEndsStr` checks `AText` to see whether it ends with `ASubText`, and returns `True` if it does, `False` if not. The check is performed case-sensitive. Basically, it checks whether the position of `ASubText` equals the length of `AText` minus the length of `ASubText` plus one.

**Errors:** None.

See also: `AnsiEndsText` (1183), `AnsiStartsStr` (1187), `AnsiIndexStr` (1183), `AnsiContainsStr` (1182)

### 36.3.6 `AnsiEndsText`

**Synopsis:** Check whether a string ends with a certain substring, ignoring case.

**Declaration:** `function AnsiEndsText(const ASubText: String; const AText: String) : Boolean`

**Visibility:** default

**Description:** `AnsiEndsText` checks `AText` to see whether it ends with `ASubText`, and returns `True` if it does, `False` if not. The check is performed case-insensitive. Basically, it checks whether the position of `ASubText` equals the length of `AText` minus the length of `ASubText` plus one.

**Errors:** None

See also: `AnsiStartsText` (1187), `AnsiEndsStr` (1183), `AnsiIndexText` (1184), `AnsiContainsText` (1182)

### 36.3.7 `AnsiIndexStr`

**Synopsis:** Searches, observing case, for a string in an array of strings.

**Declaration:** `function AnsiIndexStr(const AText: String; const AValues: Array of String) : Integer`

**Visibility:** default

**Description:** `AnsiIndexStr` matches `AText` against each string in `AValues`. If a match is found, the corresponding index (zero-based) in the `AValues` array is returned. If no match is found, -1 is returned. The strings are matched observing case.

**Errors:** None.

See also: `AnsiIndexText` (1184), `AnsiMatchStr` (1184), `AnsiMatchText` (1185)

### 36.3.8 AnsiIndexText

Synopsis: Searches, case insensitive, for a string in an array of strings.

Declaration: `function AnsiIndexText(const AText: String;  
const AValues: Array of String) : Integer`

Visibility: default

Description: `AnsiIndexStr` matches `AText` against each string in `AValues`. If a match is found, the corresponding index (zero-based) in the `AValues` array is returned. If no match is found, -1 is returned. The strings are matched ignoring case.

Errors: None

See also: `AnsiIndexStr` ([1183](#)), `AnsiMatchStr` ([1184](#)), `AnsiMatchText` ([1185](#))

### 36.3.9 AnsiLeftStr

Synopsis: Copies a number of characters starting at the left of a string

Declaration: `function AnsiLeftStr(const AText: AnsiString; const ACount: Integer)  
: AnsiString`

Visibility: default

Description: `AnsiLeftStr` returns the `ACount` leftmost characters from `AText`. If `ACount` is larger than the length of `AText`, only as much characters as available in `AText` will be copied. If `ACount` is zero or negative, no characters will be copied. The characters are counted as characters, not as Bytes. This function corresponds to the Visual Basic `LeftStr` function.

Errors: None.

See also: `AnsiMidStr` ([1185](#)), `AnsiRightStr` ([1187](#)), `LeftStr` ([1196](#)), `RightStr` ([1201](#)), `MidStr` ([1197](#)), `LeftBStr` ([1196](#)), `RightBStr` ([1201](#)), `MidBStr` ([1197](#))

### 36.3.10 AnsiMatchStr

Synopsis: Check whether a string occurs in an array of strings, observing case.

Declaration: `function AnsiMatchStr(const AText: String;  
const AValues: Array of String) : Boolean`

Visibility: default

Description: `AnsiIndexStr` matches `AText` against each string in `AValues`. If a match is found, it returns `True`, otherwise `False` is returned. The strings are matched observing case.

This function simply calls `AnsiIndexStr` ([1183](#)) and checks whether it returns -1 or not.

Errors:

### 36.3.11 AnsiMatchText

Synopsis: Check whether a string occurs in an array of strings, disregarding case.

Declaration: `function AnsiMatchText(const AText: String;  
const AValues: Array of String) : Boolean`

Visibility: default

Description: `AnsiIndexStr` matches `AText` against each string in `AValues`. If a match is found, it returns `True`, otherwise `False` is returned. The strings are matched ignoring case.

This function simply calls `AnsiIndexText` (1184) and checks whether it returns -1 or not.

Errors:

### 36.3.12 AnsiMidStr

Synopsis: Returns a number of characters copied from a given location in a string

Declaration: `function AnsiMidStr(const AText: AnsiString; const AStart: Integer;  
const ACount: Integer) : AnsiString`

Visibility: default

Description: `AnsiMidStr` returns `ACount` characters from `AText`, starting at position `AStart`. If `AStart+ACount` is larger than the length of `AText`, only as much characters as available in `AText` (starting from `AStart`) will be copied. If `ACount` is zero or negative, no characters will be copied. The characters are counted as characters, not as Bytes.

This function corresponds to the Visual Basic `MidStr` function.

Errors: None

See also: `AnsiLeftStr` (1184), `AnsiRightStr` (1187), `LeftStr` (1196), `RightStr` (1201), `MidStr` (1197), `LeftBStr` (1196), `RightBStr` (1201), `MidBStr` (1197)

### 36.3.13 AnsiProperCase

Synopsis: Pretty-Print a string: make lowercase and capitalize first letters of words

Declaration: `function AnsiProperCase(const S: String; const WordDelims: TSysCharSet)  
: String`

Visibility: default

Description: `AnsiProperCase` converts `S` to an all lowercase string, but capitalizes the first letter of every word in the string, and returns the resulting string. When searching for words, the characters in `WordDelimiters` are used to determine the boundaries of words. The constant `StdWordDelims` (1181) can be used for this.

Errors:

### 36.3.14 AnsiReplaceStr

Synopsis: Search and replace all occurrences of a string, case sensitive.

Declaration: `function AnsiReplaceStr(const AText: String;const AFromText: String;  
const AToText: String) : String`

Visibility: default

Description: `AnsiReplaceString` searches `AText` for all occurrences of the string `AFromText` and replaces them with `AToText`, and returns the resulting string. The search is performed observing case.

Errors: None.

See also: `AnsiReplaceText` ([1186](#)), `SearchBuf` ([1203](#))

### 36.3.15 AnsiReplaceText

Synopsis: Search and replace all occurrences of a string, case insensitive.

Declaration: `function AnsiReplaceText(const AText: String;const AFromText: String;  
const AToText: String) : String`

Visibility: default

Description: `AnsiReplaceString` searches `AText` for all occurrences of the string `AFromText` and replaces them with `AToText`, and returns the resulting string. The search is performed ignoring case.

Errors: None.

See also: `AnsiReplaceStr` ([1186](#)), `SearchBuf` ([1203](#))

### 36.3.16 AnsiResemblesText

Synopsis: Check whether 2 strings resemble each other.

Declaration: `function AnsiResemblesText(const AText: String;const AOther: String)  
: Boolean`

Visibility: default

Description: `AnsiResemblesText` will check whether `AnsiResemblesProc` ([1180](#)) is set. If it is not set, `False` is returned. If it is set, `AText` and `AOtherText` are passed to it and its result is returned.

Errors: None.

See also: `AnsiResemblesProc` ([1180](#)), `SoundexProc` ([1204](#))

### 36.3.17 AnsiReverseString

Synopsis: Reverse the letters in a string.

Declaration: `function AnsiReverseString(const AText: AnsiString) : AnsiString`

Visibility: default

Description: `AnsiReverseString` returns a string with all characters of `AText` in reverse order.  
if the result of this function equals `AText`, `AText` is called an anagram.

Errors: None.

### 36.3.18 AnsiRightStr

Synopsis: Copies a number of characters starting at the right of a string

Declaration: `function AnsiRightStr(const AText: AnsiString; const ACount: Integer)  
: AnsiString`

Visibility: default

Description: `AnsiRightStr` returns the `ACount` rightmost characters from `AText`. If `ACount` is larger than the length of `AText`, only as much characters as available in `AText` will be copied. If `ACount` is zero or negative, no characters will be copied. The characters are counted as characters, not as Bytes. This function corresponds to the Visual Basic `RightStr` function.

Errors: None.

See also: `AnsiLeftStr` (1184), `AnsiMidStr` (1185), `LeftStr` (1196), `RightStr` (1201), `MidStr` (1197), `LeftBStr` (1196), `RightBStr` (1201), `MidBStr` (1197)

### 36.3.19 AnsiStartsStr

Synopsis: Check whether a string starts with a given substring, observing case

Declaration: `function AnsiStartsStr(const ASubText: String; const AText: String)  
: Boolean`

Visibility: default

Description: `AnsiStartsStr` checks `AText` to see whether it starts with `ASubText`, and returns `True` if it does, `False` if not. The check is performed case-sensitive. Basically, it checks whether the position of `ASubText` equals 1.

Errors:

See also: `AnsiEndsStr` (1183), `AnsiStartsStr` (1187), `AnsiIndexStr` (1183), `AnsiContainsStr` (1182)

### 36.3.20 AnsiStartsText

Synopsis: Check whether a string starts with a given substring, ignoring case

Declaration: `function AnsiStartsText(const ASubText: String; const AText: String)  
: Boolean`

Visibility: default

Description: `AnsiStartsText` checks `AText` to see whether it starts with `ASubText`, and returns `True` if it does, `False` if not. The check is performed case-insensitive. Basically, it checks whether the position of `ASubText` equals 1.

Errors: None.

See also: `AnsiEndsText` (1183), `AnsiStartsStr` (1187), `AnsiIndexText` (1184), `AnsiContainsText` (1182)

### 36.3.21 BinToHex

Synopsis: Convert a binary buffer to a hexadecimal string

Declaration: `procedure BinToHex (BinValue: PChar; HexValue: PChar; BinBufSize: Integer)`

Visibility: default

Description: `BinToHex` converts the byte values in `BinValue` to a string consisting of 2-character hexadecimal strings in `HexValue`. `BufSize` specifies the length of `BinValue`, which means that `HexValue` must have size  $2 * \text{BufSize}$ .

For example a buffer containing the byte values 255 and 0 will be converted to FF00.

Errors: No length checking is done, so if an invalid size is specified, an exception may follow.

See also: `HexToBin` ([1194](#))

### 36.3.22 Copy2Space

Synopsis: Returns all characters in a string till the first space character (not included).

Declaration: `function Copy2Space (const S: String) : String`

Visibility: default

Description: `Copy2Space` determines the position of the first space in the string `S` and returns all characters up to this position. The space character itself is not included in the result string. The string `S` is left untouched. If there is no space in `S`, then the whole string `S` is returned.

This function simply calls `Copy2Symb` ([1189](#)) with the space (ASCII code 32) as the symbol argument.

Errors: None.

See also: `Copy2Symb` ([1189](#)), `Copy2SpaceDel` ([1188](#))

### 36.3.23 Copy2SpaceDel

Synopsis: Deletes and returns all characters in a string till the first space character (not included).

Declaration: `function Copy2SpaceDel (var S: String) : String`

Visibility: default

Description: `Copy2SpaceDel` determines the position of the first space in the string `S` and returns all characters up to this position. The space character itself is not included in the result string. All returned characters, including the space, are deleted from the string `S`, after which it is right-trimmed. If there is no space in `S`, then the whole string `S` is returned, and `S` itself is emptied.

This function simply calls `Copy2SymbDel` ([1189](#)) with the space (ASCII code 32) as the symbol argument.

Errors: None.

See also: `Copy2SymbDel` ([1189](#)), `Copy2Space` ([1188](#))

### 36.3.24 Copy2Symb

Synopsis: Returns all characters in a string till a given character (not included).

Declaration: `function Copy2Symb(const S: String;Symb: Char) : String`

Visibility: default

Description: `Copy2Symb` determines the position of the first occurrence of `Symb` in the string `S` and returns all characters up to this position. The `Symb` character itself is not included in the result string. The string `S` is left untouched. If `Symb` does not appear in `S`, then the whole of `S` is returned.

Errors: None.

See also: `Copy2Space` ([1188](#)), `Copy2SymbDel` ([1189](#))

### 36.3.25 Copy2SymbDel

Synopsis: Deletes and returns all characters in a string till a given character (not included).

Declaration: `function Copy2SymbDel(var S: String;Symb: Char) : String`

Visibility: default

Description: `Copy2SymbDel` determines the position of the first occurrence of `Symb` in the string `S` and returns all characters up to this position. The `Symb` character itself is not included in the result string. All returned characters and the `Symb` character, are deleted from the string `S`, after which it is right-trimmed. If `Symb` does not appear in `S`, then the whole of `S` is returned, and `S` itself is emptied.

Errors: None.

See also: `Copy2SpaceDel` ([1188](#)), `Copy2Symb` ([1189](#))

### 36.3.26 Dec2Numb

Synopsis: Convert a decimal number to a string representation, using given a base.

Declaration: `function Dec2Numb(N: LongInt;Len: Byte;Base: Byte) : String`

Visibility: default

Description: `Dec2Numb` converts `N` to its representation using base `Base`. The resulting string is left-padded with zeroes till it has length `Len`. `Base` must be in the range 2-36 to be meaningful, but no checking on this is performed.

Errors: If `Base` is out of range, the resulting string will contain unreadable (non-alphanumeric) characters.

See also: `Hex2Dec` ([1193](#)), `IntToBin` ([1194](#)), `intToRoman` ([1195](#)), `RomanToInt` ([1202](#))

### 36.3.27 DecodeSoundexInt

Synopsis: Decodes the integer representation of a soundex code and returns the original soundex code.

Declaration: `function DecodeSoundexInt(AValue: Integer) : String`

Visibility: default

Description: `DecodeSoundexInt` converts the integer value `AValue` to a soundex string. It performs the reverse operation of the `SoundexInt` ([1204](#)) function. The result is the soundex string corresponding to `AValue`.

Errors: None.

See also: [SoundexInt \(1204\)](#), [DecodeSoundexWord \(1190\)](#), [Soundex \(1203\)](#)

### 36.3.28 DecodeSoundexWord

Synopsis: Decodes the word-sized representation of a soundex code and returns the original soundex code.

Declaration: `function DecodeSoundexWord(AValue: Word) : String`

Visibility: default

Description: `DecodeSoundexWord` converts the integer value `AValue` to a soundex string. It performs the reverse operation of the [SoundexWord \(1205\)](#) function. The result is the soundex string corresponding to `AValue`.

Errors: None.

See also: [SoundexInt \(1204\)](#), [DecodeSoundexInt \(1189\)](#), [Soundex \(1203\)](#)

### 36.3.29 DelChars

Synopsis: Delete all occurrences of a given character from a string.

Declaration: `function DelChars(const S: String; Chr: Char) : String`

Visibility: default

Description: `DelChars` returns a copy of `S` with all `Chr` characters removed from it.

Errors: None.

See also: [DelSpace \(1190\)](#), [DelSpace1 \(1190\)](#)

### 36.3.30 DelSpace

Synopsis: Delete all occurrences of a space from a string.

Declaration: `function DelSpace(const S: String) : String`

Visibility: default

Description: `DelSpace` returns a copy of `S` with all spaces (ASCII code 32) removed from it.

Errors: None.

See also: [DelChars \(1190\)](#), [DelSpace1 \(1190\)](#)

### 36.3.31 DelSpace1

Synopsis: Reduces sequences of space characters to 1 space character.

Declaration: `function DelSpace1(const S: String) : String`

Visibility: default

Description: `DelSpace1` returns a copy of `S` with all sequences of spaces reduced to 1 space.

Errors: None.

See also: [DelChars \(1190\)](#), [DelSpace \(1190\)](#)



### 36.3.32 DupeString

**Synopsis:** Creates and concatenates N copies of a string

**Declaration:** `function DupeString(const AText: String; ACount: Integer) : String`

**Visibility:** default

**Description:** `DupeString` returns a string consisting of `ACount` concatenations of `AText`. Thus

```
DupeString('1234567890', 3);  
  
will produce a string  
  
'123456789012345678901234567890'
```

**Errors:** None.

### 36.3.33 ExtractDelimited

**Synopsis:** Extract the N-th delimited part from a string.

**Declaration:** `function ExtractDelimited(N: Integer; const S: String;  
const Delims: TSysCharSet) : String`

**Visibility:** default

**Description:** `ExtractDelimited` extracts the N-th part from the string `S`. The set of characters in `Delims` are used to mark part boundaries. When a delimiter is encountered, a new part is started and the old part is ended. Another way of stating this is that any (possibly empty) series of characters not in `Delims`, situated between 2 characters in `Delims`, it is considered as piece of a part. This means that if 2 delimiter characters appear next to each other, there is an empty part between it. If an N-th part cannot be found, an empty string is returned. However, unlike `ExtractWord` (1192), an empty string is a valid return value, i.e. a part can be empty.

The pre-defined constant `StdWordDelims` (1181) can be used for the `Delims` argument. The pre-defined constant `Brackets` (1180) would be better suited the `Delims` argument e.g. in case factors in a mathematical expression are searched.

**Errors:** None.

See also: `ExtractSubStr` (1191), `ExtractWord` (1192), `ExtractWordPos` (1192)

### 36.3.34 ExtractSubstr

**Synopsis:** Extract a word from a string, starting at a given position in the string.

**Declaration:** `function ExtractSubstr(const S: String; var Pos: Integer;  
const Delims: TSysCharSet) : String`

**Visibility:** default

**Description:** `ExtractSubStr` returns all characters from `S` starting at position `Pos` till the first character in `Delims`, or till the end of `S` is reached. The delimiter character is not included in the result. `Pos` is then updated to point to the next first non-delimiter character in `S`. If `Pos` is larger than the `Length` of `S`, an empty string is returned.

The pre-defined constant `StdWordDelims` (1181) can be used for the `Delims` argument.

**Errors:** None.

See also: `ExtractDelimited` (1191), `ExtractWord` (1192), `ExtractWordPos` (1192)

### 36.3.35 ExtractWord

Synopsis: Extract the N-th word out of a string.

Declaration: `function ExtractWord(N: Integer; const S: String;  
const WordDelims: TSysCharSet) : String`

Visibility: default

Description: `ExtractWord` extracts the N-th word from the string `S`. The set of characters in `WordDelims` are used to mark word boundaries. A word is defined as any non-empty sequence of characters which are not present in `WordDelims`: if a character is not in `WordDelims`, it is considered as part of a word. If an N-th word cannot be found, an empty string is returned.

Unlike `ExtractDelimited` (1191), an empty string is not a valid return value, i.e. is not a word. If an empty string is returned, the index `N` was out of range.

The pre-defined constant `StdWordDelims` (1181) can be used for the `WordDelims` argument.

Errors: None.

See also: `ExtractWordPos` (1192), `ExtractSubStr` (1191), `ExtractDelimited` (1191), `IsWordPresent` (1196), `WordCount` (1207), `WordPosition` (1207)

### 36.3.36 ExtractWordPos

Synopsis: Extract a word from a string, and return the position where it was located in the string.

Declaration: `function ExtractWordPos(N: Integer; const S: String;  
const WordDelims: TSysCharSet; var Pos: Integer)  
: String`

Visibility: default

Description: `ExtractWordPos` extracts the N-th word from the string `S` and returns the position of this word in `Pos`. The set of characters in `WordDelims` are used to mark word boundaries. A word is defined as any non-empty sequence of characters which are not present in `WordDelims`: if a character is not in `WordDelims`, it is considered as part of a word. If an N-th word cannot be found, an empty string is returned and `Pos` is zero.

Unlike `ExtractDelimited` (1191), an empty string is not a valid return value, i.e. is not a word. If an empty string is returned, the index `N` was out of range.

The pre-defined constant `StdWordDelims` (1181) can be used for the `WordDelims` argument.

Errors: None.

See also: `ExtractWord` (1192), `ExtractSubStr` (1191), `IsWordPresent` (1196), `WordCount` (1207), `WordPosition` (1207)

### 36.3.37 FindPart

Synopsis: Search for a substring in a string, using wildcards.

Declaration: `function FindPart(const HelpWilds: String; const InputStr: String)  
: Integer`

Visibility: default

**Description:** `FindPart` searches the string `InputStr` and returns the first string that matches the wildcards specification in `HelpWilds`. If no match is found, an empty string is returned. Currently, the only valid wildcards is the "?" character.

**Errors:** None.

**See also:** `SearchBuf` ([1203](#))

### 36.3.38 GetCmdLineArg

**Synopsis:** Returns the command-line argument following the given switch.

**Declaration:** `function GetCmdLineArg(const Switch: String; SwitchChars: TSysCharSet) : String`

**Visibility:** default

**Description:** `GetCmdLineArg` returns the value for the `Switch` option on the command-line, if any is given. Command-line arguments are considered switches if they start with one of the characters in the `SwitchChars` set. The value is the command-line argument following the switch command-line argument.

Gnu-style (long) Options of the form `switch=value` are not supported.

The `StdSwitchChars` ([1181](#)) constant can be used as value for the `SwitchChars` parameter.

**Errors:** The `GetCmdLineArg` does not check whether the value of the option does not start with a switch character. i.e.

```
myprogram -option1 -option2
```

will result in "-option2" as the result of the `GetCmdLineArg` call for `option1`.

**See also:** `StdSwitchChars` ([1181](#))

### 36.3.39 Hex2Dec

**Synopsis:** Converts a hexadecimal string to a decimal value

**Declaration:** `function Hex2Dec(const S: String) : LongInt`

**Visibility:** default

**Description:** `Hex2Dec` converts the hexadecimal value in the string `S` to its decimal value. Unlike the standard `Val` or `StrToInt` functions, there need not be a \$ sign in front of the hexadecimal value to indicate that it is indeed a hexadecimal value.

**Errors:** If `S` does not contain a valid hexadecimal value, an `EConvertError` exception will be raised.

**See also:** `Dec2Numb` ([1189](#)), `IntToBin` ([1194](#)), `intToRoman` ([1195](#)), `RomanToInt` ([1202](#))

### 36.3.40 HexToBin

Synopsis: Convert a hexadecimal string to a binary buffer

Declaration: `function HexToBin(HexValue: PChar; BinValue: PChar; BinBufSize: Integer)  
: Integer`

Visibility: default

Description: `HexToBin` scans the hexadecimal string representation in `HexValue` and transforms every 2 character hexadecimal number to a byte and stores it in `BinValue`. The buffer size is the size of the binary buffer. Scanning will stop if the size of the binary buffer is reached or when an invalid character is encountered. The return value is the number of stored bytes.

Errors: No length checking is done, so if an invalid size is specified, an exception may follow.

See also: `BinToHex` ([1188](#))

### 36.3.41 IfThen

Synopsis: Returns one of two strings, depending on a boolean expression

Declaration: `function IfThen(AValue: Boolean; const ATrue: String;  
const AFalse: String) : String; Overload`

Visibility: default

Description: `IfThen` returns `ATrue` if `AValue` is `True`, and returns `AFalse` if `AValue` is `false`.

Errors: None.

See also: `AnsiMatchStr` ([1184](#)), `AnsiMatchText` ([1185](#))

### 36.3.42 IntToBin

Synopsis: Converts an integer to a binary string representation, inserting spaces at fixed locations.

Declaration: `function IntToBin(Value: LongInt; Digits: Integer; Spaces: Integer)  
: String  
function IntToBin(Value: LongInt; Digits: Integer) : String  
function intToBin(Value: Int64; Digits: Integer) : String`

Visibility: default

Description: `IntToBin` converts `Value` to a string with its binary (base 2) representation. The resulting string contains at least `Digits` digits, with spaces inserted every `Spaces` digits. `Spaces` should be a nonzero value. If `Digits` is larger than 32, it is truncated to 32.

Errors: If `spaces` is zero, a division by zero error will occur.

See also: `Hex2Dec` ([1193](#)), `IntToRoman` ([1195](#))

### 36.3.43 IntToRoman

Synopsis: Represent an integer with roman numerals

Declaration: `function IntToRoman(Value: LongInt) : String`

Visibility: default

Description: `IntToRoman` converts `Value` to a string with the Roman representation of `Value`. Number up to 1 million can be represented this way.

Errors: None.

See also: `RomanToInt` ([1202](#)), `Hex2Dec` ([1193](#)), `IntToBin` ([1194](#))

### 36.3.44 IsEmptyStr

Synopsis: Check whether a string is empty, disregarding whitespace characters

Declaration: `function IsEmptyStr(const S: String; const EmptyChars: TSysCharSet) : Boolean`

Visibility: default

Description: `IsEmptyStr` returns `True` if the string `S` only contains characters whitespace characters, all characters in `EmptyChars` are considered whitespace characters. If a character not present in `EmptyChars` is found in `S`, `False` is returned.

Errors: None.

See also: `IsWild` ([1195](#)), `FindPart` ([1192](#)), `IsWordPresent` ([1196](#))

### 36.3.45 IsWild

Synopsis: Check whether a string matches a wildcard search expression.

Declaration: `function IsWild(InputStr: String; Wilds: String; IgnoreCase: Boolean) : Boolean`

Visibility: default

Description: `IsWild` checks `InputStr` for the presence of the `Wilds` string. `Wilds` may contain "?" and "\*" wildcard characters, which have their usual meaning: "\*" matches any series of characters, possibly empty. "?" matches any single character. The function returns `True` if a string is found that matches `Wilds`, `False` otherwise.

If `IgnoreCase` is `True`, the non-wildcard characters are matched case insensitively. If it is `False`, case is observed when searching.

Errors: None.

See also: `SearchBuf` ([1203](#)), `FindPart` ([1192](#))

### 36.3.46 IsWordPresent

Synopsis: Check for the presence of a word in a string.

Declaration: `function IsWordPresent(const W: String;const S: String;  
const WordDelims: TSysCharSet) : Boolean`

Visibility: default

Description: `IsWordPresent` checks for the presence of the word `W` in the string `S`. Words are delimited by the characters found in `WordDelims`. The function returns `True` if a match is found, `False` otherwise. The search is performed case sensitive.

This function is equivalent to the `SearchBuf` (1203) function with the `soWholeWords` option specified.

Errors: None.

See also: `SearchBuf` (1203)

### 36.3.47 LeftBStr

Synopsis: Copies Count characters starting at the left of a string.

Declaration: `function LeftBStr(const AText: AnsiString;const AByteCount: Integer)  
: AnsiString`

Visibility: default

Description: `LeftBStr` returns a string containing the leftmost `AByteCount` bytes from the string `AText`. If `AByteCount` is larger than the length (in bytes) of `AText`, only as many bytes as available are returned.

Errors: None.

See also: `LeftStr` (1196), `AnsiLeftStr` (1184), `RightBStr` (1201), `MidBStr` (1197)

### 36.3.48 LeftStr

Synopsis: Copies Count characters starting at the left of a string.

Declaration: `function LeftStr(const AText: AnsiString;const ACount: Integer)  
: AnsiString  
function LeftStr(const AText: WideString;const ACount: Integer)  
: WideString`

Visibility: default

Description: `LeftStr` returns a string containing the leftmost `ACount` characters from the string `AText`. If `ACount` is larger than the length (in characters) of `AText`, only as many characters as available are returned.

Errors: None.

See also: `LeftBStr` (1196), `AnsiLeftStr` (1184), `RightStr` (1201), `MidStr` (1197)

### 36.3.49 MidBStr

Synopsis: Copies a number of characters starting at a given position in a string.

Declaration: `function MidBStr(const AText: AnsiString; const AByteStart: Integer;  
const AByteCount: Integer) : AnsiString`

Visibility: default

Description: `MidBStr` returns a string containing the first `AByteCount` bytes from the string `AText` starting at position `AByteStart`. If `AByteStart+AByteCount` is larger than the length (in bytes) of `AText`, only as many bytes as available are returned. If `AByteStart` is less than 1 or larger than the length of `AText`, then no characters are returned.

Errors: None.

See also: `LeftBStr` (1196), `AnsiMidStr` (1185), `RightBStr` (1201), `MidStr` (1197)

### 36.3.50 MidStr

Synopsis: Copies a number of characters starting at a given position in a string.

Declaration: `function MidStr(const AText: AnsiString; const AStart: Integer;  
const ACount: Integer) : AnsiString`  
`function MidStr(const AText: WideString; const AStart: Integer;  
const ACount: Integer) : WideString`

Visibility: default

Description: `MidStr` returns a string containing the first `ACount` bytes from the string `AText` starting at position `AStart`. If `AStart+ACount` is larger than the length (in characters) of `AText`, only as many characters as available are returned. If `AStart` is less than 1 or larger than the length of `AText`, then no characters are returned.

This function is equivalent to the standard `Copy` function, and is provided for completeness only.

Errors: None.

See also: `LeftStr` (1196), `AnsiMidStr` (1185), `RightStr` (1201), `MidBStr` (1197)

### 36.3.51 NPos

Synopsis: Returns the position of the N-th occurrence of a substring in a string.

Declaration: `function NPos(const C: String; S: String; N: Integer) : Integer`

Visibility: default

Description: `NPos` checks `S` for the position of the `N`-th occurrence of `C`. If `C` occurs less than `N` times in `S`, or does not occur in `S` at all, 0 is returned. If `N` is less than 1, zero is returned.

Errors: None.

See also: `WordPosition` (1207), `FindPart` (1192)

### 36.3.52 Numb2Dec

Synopsis: Converts a string representation of a number to its numerical value, given a certain base.

Declaration: `function Numb2Dec(S: String;Base: Byte) : LongInt`

Visibility: default

Description: `Numb2Dec` converts the number in string `S` to a decimal value. It assumes the number is represented using `Base` as the base. No checking is performed to see whether `S` contains a valid number using base `Base`.

Errors: None.

See also: `Hex2Dec` ([1193](#)), `Numb2USA` ([1198](#))

### 36.3.53 Numb2USA

Synopsis: Insert thousand separators.

Declaration: `function Numb2USA(const S: String) : String`

Visibility: default

Description: `Numb2USA` inserts thousand separators in the string `S` at the places where they are supposed to be, i.e. every 3 digits. The string `S` should contain a valid integer number, i.e. no digital number. No checking on this is done.

Errors: None.

### 36.3.54 PadCenter

Synopsis: Pad the string to a certain length, so the string is centered.

Declaration: `function PadCenter(const S: String;Len: Integer) : String`

Visibility: default

Description: `PadCenter` add spaces to the left and right of the string `S` till the result reaches length `Len`. If the number of spaces to add is odd, then the extra space will be added at the end. If the string `S` has length equal to or largert than `Len`, no spaces are added, and the string `S` is returned as-is.

Errors: None.

See also: `PadLeft` ([1198](#)), `PadRight` ([1199](#)), `AddChar` ([1182](#)), `AddCharR` ([1182](#))

### 36.3.55 PadLeft

Synopsis: Add spaces to the left of a string till a certain length is reached.

Declaration: `function PadLeft(const S: String;N: Integer) : String`

Visibility: default

Description: `PadLeft` add spaces to the left of the string `S` till the result reaches length `Len`. If the string `S` has length equal to or largert than `Len`, no spaces are added, and the string `S` is returned as-is. The resulting string is `S`, right-justified on length `Len`.

Errors: None.

See also: `PadLeft` ([1198](#)), `PadCenter` ([1198](#)), `AddChar` ([1182](#)), `AddCharR` ([1182](#))



### 36.3.56 PadRight

Synopsis: Add spaces to the right of a string till a certain length is reached.

Declaration: `function PadRight(const S: String; N: Integer) : String`

Visibility: default

Description: `PadRight` add spaces to the left of the string `S` till the result reaches length `Len`. If the string `S` has length equal to or larger than `Len`, no spaces are added, and the string `S` is returned as-is. The resulting string is `S`, left-justified on length `Len`.

Errors: None.

See also: `PadLeft` ([1198](#)), `PadCenter` ([1198](#)), `AddChar` ([1182](#)), `AddCharR` ([1182](#))

### 36.3.57 PosEx

Synopsis: Search for the occurrence of a character in a string, starting at a certain position.

Declaration: `function PosEx(const SubStr: String; const S: String; Offset: Cardinal) : Integer`  
`function PosEx(const SubStr: String; const S: String) : Integer`  
`function PosEx(c: Char; const S: String; Offset: Cardinal) : Integer`

Visibility: default

Description: `PosEx` returns the position of the first occurrence of the character `C` or the substring `SubStr` in the string `S`, starting the search at position `Offset` (default 1). If `C` or `SubStr` does not occur in `S` after the given `Offset`, zero is returned. The position `Offset` is also searched.

Errors: None.

See also: `NPos` ([1197](#)), `AnsiContainsText` ([1182](#)), `AnsiContainsStr` ([1182](#))

### 36.3.58 PosSet

Synopsis: Return the position in a string of any character out of a set of characters

Declaration: `function PosSet(const c: TSysCharSet; const s: ansistring) : Integer`  
`function PosSet(const c: String; const s: ansistring) : Integer`

Visibility: default

Description: `PosSet` returns the position in `s` of the first found character which is in the set `c`. If none of the characters in `c` is found in `s`, then 0 is returned.

Errors: None.

See also: `PosEx` ([1199](#)), `PosSetEx` ([1199](#)), `#rtl.system.pos` ([1356](#)), `RPosEx` ([1202](#))

### 36.3.59 PosSetEx

Synopsis: Return the position in a string of any character out of a set of characters, starting at a certain position

Declaration: `function PosSetEx(const c: TSysCharSet; const s: ansistring; count: Integer) : Integer`  
`function PosSetEx(const c: String; const s: ansistring; count: Integer) : Integer`

Visibility: default

Description: `PosSetEx` returns the position in `s` of the first found character which is in the set `c`, and starts searching at character position `Count`. If none of the characters in `c` is found in `s`, then 0 is returned.

Errors: None.

See also: `PosEx` ([1199](#)), `PosSet` ([1199](#)), `#rtl.system.pos` ([1356](#)), `RPosEx` ([1202](#))

### 36.3.60 RandomFrom

Synopsis: Choose a random string from an array of strings.

Declaration: `function RandomFrom(const AValues: Array of String) : String; Overload`

Visibility: default

Description: `RandomFrom` picks at random a valid index in the array `AValues` and returns the string at that position in the array.

Errors: None.

See also: `AnsiMatchStr` ([1184](#)), `AnsiMatchText` ([1185](#))

### 36.3.61 Removeleadingchars

Synopsis: Remove any leading characters in a set from a string

Declaration: `procedure Removeleadingchars(var S: AnsiString; const CSet: TSysCharSet)`

Visibility: default

Description: `Removeleadingchars` removes any starting characters from `S` that appear in the set `CSet`. It stops removing characters as soon as a character not in `CSet` is encountered. This is similar in behaviour to `TrimLeft` ([1561](#)) which used whitespace as the set.

Errors: None.

See also: `rtl.sysutils.TrimLeft` ([1180](#)), `RemoveTrailingChars` ([1201](#)), `RemovePadChars` ([1200](#)), `TrimLeftSet` ([1206](#))

### 36.3.62 RemovePadChars

Synopsis: Remove any trailing or leading characters in a set from a string

Declaration: `procedure RemovePadChars(var S: AnsiString; const CSet: TSysCharSet)`

Visibility: default

Description: `RemovePadChars` removes any leading trailing characters from `S` that appear in the set `CSet`, i.e. it starts with the last character and works its way to the start of the string, and it stops removing characters as soon as a character not in `CSet` is encountered. Then the same procedure is repeated starting from the beginning of the string. This is similar in behaviour to `Trim` ([1560](#)) which used whitespace as the set.

Errors: None.

See also: `rtl.sysutils.Trim` ([1180](#)), `RemoveLeadingChars` ([1200](#)), `RemoveTrailingChars` ([1201](#)), `TrimSet` ([1207](#)), `TrimLeftSet` ([1206](#)), `TrimRightSet` ([1206](#))

### 36.3.63 RemoveTrailingChars

Synopsis: Remove any trailing characters in a set from a string

Declaration: `procedure RemoveTrailingChars(var S: AnsiString; const CSet: TSysCharset)`

Visibility: default

Description: `RemoveTrailingChars` removes any trailing characters from `S` that appear in the set `CSet`, i.e. it starts with the last character and works its way to the start of the string. It stops removing characters as soon as a character not in `CSet` is encountered. This is similar in behaviour to `TrimRight` (1562) which used whitespace as the set.

Errors:

See also: `rtl.sysutils.TrimLeft` (1180), `RemoveLeadingChars` (1200), `TrimRightSet` (1206)

### 36.3.64 ReverseString

Synopsis: Reverse characters in a string

Declaration: `function ReverseString(const AText: String) : String`

Visibility: default

Description: `ReverseString` returns a string, made up of the characters in string `AText`, in reverse order.

Errors: None.

See also: `RandomFrom` (1200)

### 36.3.65 RightBStr

Synopsis: Copy a given number of characters (bytes), counting from the right of a string.

Declaration: `function RightBStr(const AText: AnsiString; const AByteCount: Integer) : AnsiString`

Visibility: default

Description: `RightBStr` returns a string containing the rightmost `AByteCount` bytes from the string `AText`. If `AByteCount` is larger than the length (in bytes) of `AText`, only as many bytes as available are returned.

Errors: None.

See also: `LeftBStr` (1196), `AnsiRightStr` (1187), `RightStr` (1201), `MidBStr` (1197)

### 36.3.66 RightStr

Synopsis: Copy a given number of characters, counting from the right of a string.

Declaration: `function RightStr(const AText: AnsiString; const ACount: Integer) : AnsiString`  
`function RightStr(const AText: WideString; const ACount: Integer) : WideString`

Visibility: default

**Description:** `RightStr` returns a string containing the rightmost `ACount` characters from the string `AText` .  
If `ACount` is larger than the length (in characters) of `AText` , only as many characters as available are returned.

**Errors:** None.

**See also:** `LeftStr` ([1196](#)), `AnsiRightStr` ([1187](#)), `RightBStr` ([1201](#)), `MidStr` ([1197](#))

### 36.3.67 RomanToInt

**Synopsis:** Convert a string with a Roman number to it's decimal value.

**Declaration:** `function RomanToInt(const S: String) : LongInt`

**Visibility:** default

**Description:** `RomanToInt` returns the decimal equivalent of the Roman numerals in the string `S`. Invalid characters are dropped from `S`. A negative numeral is supported as well.

**Errors:** None.

**See also:** `IntToRoman` ([1195](#)), `Hex2Dec` ([1193](#)), `Numb2Dec` ([1198](#))

### 36.3.68 RPos

**Synopsis:** Find last occurrence of substring or character in a string

**Declaration:** `function RPos(c: Char;const S: AnsiString) : Integer; Overload`  
`function RPos(const Substr: AnsiString;const Source: AnsiString)`  
`: Integer; Overload`

**Visibility:** default

**Description:** `RPos` looks in `S` for the character `C` or the string `SubStr`. It starts looking at the end of the string, and searches towards the beginning of the string. If a match is found, it returns the position of the match.

**See also:** `RPosEx` ([1202](#))

### 36.3.69 RPosEx

**Synopsis:** Find last occurrence substring or character in a string, starting at a certain position

**Declaration:** `function RPosEX(C: Char;const S: AnsiString;offs: cardinal) : Integer`  
`; Overload`  
`function RPosEx(const Substr: AnsiString;const Source: AnsiString;`  
`offs: cardinal) : Integer; Overload`

**Visibility:** default

**Description:** `RPos` looks in `S` for the character `C` or the string `SubStr`. It starts looking at position `Offs` (counted from the start of the string), and searches towards the beginning of the string. If a match is found, it returns the position of the match.

**See also:** `RPos` ([1202](#))

### 36.3.70 SearchBuf

Synopsis: Search a buffer for a certain string.

Declaration: `function SearchBuf(Buf: PChar; BufLen: Integer; SelStart: Integer; SelLength: Integer; SearchString: String; Options: TStringSearchOptions) : PChar`  
`function SearchBuf(Buf: PChar; BufLen: Integer; SelStart: Integer; SelLength: Integer; SearchString: String) : PChar`

Visibility: default

Description: `SearchBuf` searches the buffer `Buf` for the occurrence of `SearchString`. At most `BufLen` characters are searched, and the search is started at `SelStart+SelLength`. If a match is found, a pointer to the position of the match is returned. The parameter `Options` (1181) specifies how the search is conducted. It is a set of the following options:

Table 36.3:

Option	Effect
<code>soDown</code>	Searches forward, starting at the end of the selection. Default is searching up
<code>soMatchCase</code>	Observe case when searching. Default is to ignore case.
<code>soWholeWord</code>	Match only whole words. Default also returns parts of words

The standard constant `WordDelimiters` (1181) is used to mark the boundaries of words.

The `SelStart` parameter is zero based.

Errors: `BufLen` must be the real length of the string, no checking on this is performed.

See also: `FindPart` (1192), `ExtractWord` (1192), `ExtractWordPos` (1192), `ExtractSubStr` (1191), `IsWordPresent` (1196)

### 36.3.71 Soundex

Synopsis: Compute the soundex of a string

Declaration: `function Soundex(const AText: String; ALength: TSoundexLength) : String`  
`function Soundex(const AText: String) : String`

Visibility: default

Description: `Soundex` computes a soundex code for `AText`. The resulting code will at most have `ALength` characters. The soundex code is computed according to the US system of soundex computing, which may result in inaccurate results in other languages.

Errors: None.

See also: `SoundexCompare` (1203), `SoundexInt` (1204), `SoundexProc` (1204), `SoundexWord` (1205), `SoundexSimilar` (1205)

### 36.3.72 SoundexCompare

Synopsis: Compare soundex values of 2 strings.

**Declaration:** `function SoundexCompare(const AText: String;const AOther: String;  
  ALength: TSoundexLength) : Integer  
function SoundexCompare(const AText: String;const AOther: String)  
  : Integer`

**Visibility:** default

**Description:** `SoundexCompare` computes the soundex codes of `AText` and `AOther` and feeds these to `CompareText`. It will return -1 if the soundex code of `AText` is less than the soundex code of `AOther`, 0 if they are equal, and 1 if the code of `AOther` is larger than the code of `AText`.

**Errors:** None.

**See also:** `Soundex` (1203), `SoundexInt` (1204), `SoundexProc` (1204), `SoundexWord` (1205), `SoundexSimilar` (1205)

### 36.3.73 SoundexInt

**Synopsis:** Soundex value as an integer.

**Declaration:** `function SoundexInt(const AText: String;ALength: TSoundexIntLength)  
  : Integer  
function SoundexInt(const AText: String) : Integer`

**Visibility:** default

**Description:** `SoundexInt` computes the `Soundex` (1203) code (with length `ALength`, default 4) of `AText`, and converts the code to an integer value.

**Errors:** None.

**See also:** `Soundex` (1203), `SoundexCompare` (1203), `SoundexProc` (1204), `SoundexWord` (1205), `SoundexSimilar` (1205)

### 36.3.74 SoundexProc

**Synopsis:** Default `AnsiResemblesText` implementation.

**Declaration:** `function SoundexProc(const AText: String;const AOther: String) : Boolean`

**Visibility:** default

**Description:** `SoundexProc` is the standard implementation for the `AnsiResemblesText` (1186) procedure: By default, `AnsiResemblesProc` is set to this function. It compares the soundex codes of `AOther` and `AText` and returns `True` if they are equal, or `False` if they are not.

**Errors:** None.

**See also:** `Soundex` (1203), `SoundexCompare` (1203), `SoundexInt` (1204), `SoundexWord` (1205), `SoundexSimilar` (1205)

### 36.3.75 SoundexSimilar

Synopsis: Check whether 2 strings have equal soundex values

Declaration: 

```
function SoundexSimilar(const AText: String;const AOther: String;
                        ALength: TSoundexLength) : Boolean
function SoundexSimilar(const AText: String;const AOther: String)
                        : Boolean
```

Visibility: default

Description: `SoundexSimilar` returns `True` if the soundex codes (with length `ALength`) of `AText` and `AOther` are equal, and `False` if they are not.

Errors: None.

See also: `Soundex` (1203), `SoundexCompare` (1203), `SoundexInt` (1204), `SoundexProc` (1204), `SoundexWord` (1205), `Soundex` (1203)

### 36.3.76 SoundexWord

Synopsis: Calculate a word-sized soundex value

Declaration: 

```
function SoundexWord(const AText: String) : Word
```

Visibility: default

Description: `SoundexInt` computes the `Soundex` (1203) code (with length 4) of `AText`, and converts the code to a word-sized value.

Errors: None.

See also: `Soundex` (1203), `SoundexCompare` (1203), `SoundexInt` (1204), `SoundexProc` (1204), `SoundexSimilar` (1205)

### 36.3.77 StringsReplace

Synopsis: Replace occurrences of a set of strings to another set of strings

Declaration: 

```
function StringsReplace(const S: String;OldPattern: Array of String;
                        NewPattern: Array of String;Flags: TReplaceFlags)
                        : String
```

Visibility: default

Description: `StringsReplace` scans `S` for the occurrence of one of the strings in `OldPattern` and replaces it with the corresponding string in `NewPattern`. It takes into account `Flags`, which has the same meaning as in `StringReplace` (1539).

Corresponding strings are matched by location: the `N`-th string in `OldPattern` is replaced by the `N`-th string in `NewPattern`. Note that this means that the number of strings in both arrays must be the same.

Errors: If the number of strings in both arrays is different, then an exception is raised.

See also: `#rtl.sysutils.StringReplace` (1539), `#rtl.sysutils.TReplaceFlags` (1440)

### 36.3.78 StuffString

Synopsis: Replace part of a string with another string.

Declaration: `function StuffString(const AText: String; AStart: Cardinal;  
                                  ALength: Cardinal; const ASubText: String) : String`

Visibility: default

Description: `StuffString` returns a copy of `AText` with the segment starting at `AStart` with length `ALength`, replaced with the string `ASubText`. Basically it deletes the segment of `Atext` and inserts the new text in it's place.

Errors: No checking on the validity of the `AStart` and `ALength` parameters is done. Providing invalid values may result in access violation errors.

See also: [FindPart \(1192\)](#), [DelChars \(1190\)](#), [DelSpace \(1190\)](#), [ExtractSubStr \(1191\)](#), [DupeString \(1191\)](#)

### 36.3.79 Tab2Space

Synopsis: Convert tab characters to a number of spaces

Declaration: `function Tab2Space(const S: String; Numb: Byte) : String`

Visibility: default

Description: `Tab2Space` returns a copy of `S` with all tab characters (ASCII character 9) converted to `Numb` spaces.

Errors: None.

See also: [StuffString \(1206\)](#), [FindPart \(1192\)](#), [ExtractWord \(1192\)](#), [DelChars \(1190\)](#), [DelSpace \(1190\)](#), [DelSpace1 \(1190\)](#), [DupeString \(1191\)](#)

### 36.3.80 TrimLeftSet

Synopsis: Remove any leading characters in a set from a string and returns the result

Declaration: `function TrimLeftSet(const S: String; const CSet: TSysCharSet) : String`

Visibility: default

Description: `TrimLeftSet` performs the same action as [RemoveLeadingChars \(1200\)](#), but returns the resulting string.

Errors: None.

See also: [rtl.sysutils.TrimLeft \(1180\)](#), [RemoveLeadingChars \(1200\)](#), [RemoveTrailingChars \(1201\)](#), [RemovePadChars \(1200\)](#), [TrimSet \(1207\)](#), [TrimRightSet \(1206\)](#)

### 36.3.81 TrimRightSet

Synopsis: Remove any trailing characters in a set from a string and returns the result

Declaration: `function TrimRightSet(const S: String; const CSet: TSysCharSet) : String`

Visibility: default



**Description:** `TrimLeftSet` performs the same action as `RemoveTrailingChars` (1201), but returns the resulting string.

**Errors:** None.

**See also:** `rtl.sysutils.TrimRight` (1180), `RemoveLeadingChars` (1200), `RemoveTrailingChars` (1201), `RemovePadChars` (1200), `TrimSet` (1207), `TrimLeftSet` (1206)

### 36.3.82 TrimSet

**Synopsis:** Remove any leading or trailing characters in a set from a string and returns the result

**Declaration:** `function TrimSet(const S: String; const CSet: TSysCharSet) : String`

**Visibility:** default

**Description:** `TrimSet` performs the same action as `RemovePadChars` (1200), but returns the resulting string.

**Errors:** None.

**See also:** `rtl.sysutils.Trim` (1180), `RemoveLeadingChars` (1200), `RemoveTrailingChars` (1201), `RemovePadChars` (1200), `TrimRightSet` (1206), `TrimLeftSet` (1206)

### 36.3.83 WordCount

**Synopsis:** Count the number of words in a string.

**Declaration:** `function WordCount(const S: String; const WordDelims: TSysCharSet) : Integer`

**Visibility:** default

**Description:** `WordCount` returns the number of words in the string `S`. A word is a non-empty string of characters bounded by one of the characters in `WordDelims`.

The pre-defined `StdWordDelims` (1181) constant can be used for the `WordDelims` argument.

**Errors:** None.

**See also:** `WordPosition` (1207), `StdWordDelims` (1181), `ExtractWord` (1192), `ExtractWordPos` (1192)

### 36.3.84 WordPosition

**Synopsis:** Search position of Nth word in a string.

**Declaration:** `function WordPosition(const N: Integer; const S: String; const WordDelims: TSysCharSet) : Integer`

**Visibility:** default

**Description:** `WordPosition` returns the position (in characters) of the N-th word in the string `S`. A word is a non-empty string of characters bounded by one of the characters in `WordDelims`. If `N` is out of range, zero is returned.

The pre-defined `StdWordDelims` (1181) constant can be used for the `WordDelims` argument.

**Errors:** None

**See also:** `WordCount` (1207), `StdWordDelims` (1181), `ExtractWord` (1192), `ExtractWordPos` (1192)

### 36.3.85 XorDecode

Synopsis: Decode a string encoded with XorEncode (1208)

Declaration: `function XorDecode(const Key: String;const Source: String) : String`

Visibility: default

Description: `XorDecode` decodes `Source` and returns the original string that was encrypted using `XorEncode` (1208) with key `Key`. If a different key is used than the key used to encode the string, the result will be unreadable.

Errors: If the string `Source` is not a valid `XorEncode` result (e.g. contains non-numerical characters), then a `EConversionError` exception will be raised.

See also: `XorEncode` (1208), `XorString` (1208)

### 36.3.86 XorEncode

Synopsis: Encode a string by XOR-ing its characters using characters of a given key, representing the result as hex values.

Declaration: `function XorEncode(const Key: String;const Source: String) : String`

Visibility: default

Description: `XorEncode` encodes the string `Source` by XOR-ing each character in `Source` with the corresponding character in `Key` (repeating `Key` as often as necessary) and representing the resulting ASCII code as a hexadecimal number (of length 2). The result is therefore twice as long as the original string, and every 2 bytes represent an ASCII code.

Feeding the resulting string with the same key `Key` to the `XorDecode` (1208) function will result in the original `Source` string.

This function can be used e.g. to trivially encode a password in a configuration file.

Errors: None.

See also: `XorDecode` (1208), `XorString` (1208), `Hex2Dec` (1193)

### 36.3.87 XorString

Synopsis: Encode a string by XOR-ing its characters using characters of a given key.

Declaration: `function XorString(const Key: ShortString;const Src: ShortString)  
: ShortString`

Visibility: default

Description: `XorString` encodes the string `Src` by XOR-ing each character in `Source` with the corresponding character in `Key`, repeating `Key` as often as necessary. The resulting string may contain unreadable characters and may even contain null characters. For this reason it may be a better idea to use the `XorEncode` (1208) function instead, which will representing each resulting ASCII code as a hexadecimal number (of length 2).

Feeding the result again to `XorString` with the same `Key`, will result in the original string `Src`.

Errors: None.

See also: `XorEncode` (1208), `XorDecode` (1208)

## Chapter 37

# Reference for unit 'System'

### 37.1 Overview

The system unit contains the standard supported functions of Free Pascal. It is the same for all platforms. Basically it is the same as the system unit provided with Borland or Turbo Pascal.

Functions are listed in alphabetical order. Arguments of functions or procedures that are optional are put between square brackets.

The pre-defined constants and variables are listed in the first section. The second section contains an overview of all functions, grouped by functionality, and the last section contains the supported functions and procedures.

### 37.2 Miscellaneous functions

Functions that do not belong in one of the other categories.

Table 37.1:

Name	Description
Assert ( <a href="#">1262</a> )	Conditionally abort program with error
Break ( <a href="#">1267</a> )	Abort current loop
Continue ( <a href="#">1276</a> )	Next cycle in current loop
Exclude ( <a href="#">1288</a> )	Exclude an element from a set
Exit ( <a href="#">1289</a> )	Exit current function or procedure
Include ( <a href="#">1307</a> )	Include an element into a set
LongJump ( <a href="#">1320</a> )	Jump to execution point
Ord ( <a href="#">1354</a> )	Return ordinal value of enumerated type
Pred ( <a href="#">1357</a> )	Return previous value of ordinal type
SetJump ( <a href="#">1374</a> )	Mark execution point for jump
SizeOf ( <a href="#">1380</a> )	Return size of variable or type
Succ ( <a href="#">1386</a> )	Return next value of ordinal type

### 37.3 Operating System functions

Functions that are connected to the operating system.

Table 37.2:

Name	Description
Chdir ( <a href="#">1268</a> )	Change working directory
Getdir ( <a href="#">1299</a> )	Return current working directory
Halt ( <a href="#">1303</a> )	Halt program execution
Paramcount ( <a href="#">1355</a> )	Number of parameters with which program was called
Paramstr ( <a href="#">1355</a> )	Retrieve parameters with which program was called
Mkdir ( <a href="#">1322</a> )	Make a directory
Rmdir ( <a href="#">1366</a> )	Remove a directory
Runerror ( <a href="#">1371</a> )	Abort program execution with error condition

### 37.4 String handling

All things connected to string handling.

Table 37.3:

Name	Description
BinStr ( <a href="#">1265</a> )	Construct binary representation of integer
Chr ( <a href="#">1269</a> )	Convert ASCII code to character
Concat ( <a href="#">1275</a> )	Concatenate two strings
Copy ( <a href="#">1277</a> )	Copy part of a string
Delete ( <a href="#">1280</a> )	Delete part of a string
HexStr ( <a href="#">1303</a> )	Construct hexadecimal representation of integer
Insert ( <a href="#">1312</a> )	Insert one string in another
Length ( <a href="#">1317</a> )	Return length of string
Lowercase ( <a href="#">1321</a> )	Convert string to all-lowercase
OctStr ( <a href="#">1324</a> )	Construct octal representation of integer
Pos ( <a href="#">1356</a> )	Calculate position of one string in another
SetLength ( <a href="#">1375</a> )	Set length of a string
SetString ( <a href="#">1376</a> )	Set contents and length of a string
Str ( <a href="#">1383</a> )	Convert number to string representation
StringOfChar ( <a href="#">1384</a> )	Create string consisting of a number of characters
Uppcase ( <a href="#">1397</a> )	Convert string to all-uppercase
Val ( <a href="#">1399</a> )	Convert string to number

### 37.5 Mathematical routines

Functions connected to calculating and converting numbers.

Table 37.4:

Name	Description
Abs (1258)	Calculate absolute value
Arctan (1261)	Calculate inverse tangent
Cos (1277)	Calculate cosine of angle
Dec (1278)	Decrease value of variable
Exp (1290)	Exponentiate
Frac (1297)	Return fractional part of floating point value
Hi (1304)	Return high byte/word of value
Inc (1306)	Increase value of variable
Int (1312)	Calculate integer part of floating point value
Ln (1318)	Calculate logarithm
Lo (1319)	Return low byte/word of value
Odd (1325)	Is a value odd or even ?
Pi (1356)	Return the value of pi
Power (1209)	Raise float to integer power
Random (1359)	Generate random number
Randomize (1359)	Initialize random number generator
Round (1369)	Round floating point value to nearest integer number
Sin (1380)	Calculate sine of angle
Sqr (1382)	Calculate the square of a value
Sqrt (1383)	Calculate the square root of a value
Swap (1387)	Swap high and low bytes/words of a variable
Trunc (1392)	Truncate a floating point value

## 37.6 Memory management functions

Functions concerning memory issues.

## 37.7 File handling functions

Functions concerning input and output from and to file.

## 37.8 Constants, types and variables

### 37.8.1 Constants

```
AbstractErrorProc : TAbstractErrorProc = nil
```

If set, the `AbstractErrorProc` constant is used when an abstract error occurs. If it is not set, then the standard error handling is done: A stack dump is performed, and the program exits with error code 211.

The `SysUtils` unit sets this procedure and raises an exception in its handler.

```
AllFilesMask = '*'
```

`AllFilesMask` is the wildcard that can be used to return all files in a directory. On windows and dos based systems, this will be `'*.*'`, while for unix systems, this will be `'*'`.

```
AllowDirectorySeparators : Set of Char = ['\\', '/']
```

`AllowDirectorySeparators` is the set of characters which are considered directory separators by the RTL units. By default, this is set to the most common directory separators: forward slash and backslash, so routines will work in a cross-platform manner, no matter which character was used:

```
AllowDirectorySeparators : set of char = ['\\', '/'];
```

If a more strict behaviour is desired, then `AllowDirectorySeparators` can be set to the only character allowed on the current operating system, and all RTL routines that handle filenames (splitting filenames, extracting parts of the filename and so on) will use that character only.

```
AllowDriveSeparators : Set of Char = []
```

`AllowDriveSeparators` are the characters which are considered to separate the drive part from the directory part in a filename. This will be an empty set on systems that do not support drive letters. Other systems (dos, windows and OS/2) will have the colon (:) character as the only member of this set.

```
AssertErrorProc : TAssertErrorProc = @SysAssert
```

If set, the `AbstractErrorProc` constant is used when an assert error occurs. If it is not set, then the standard error handling is done: The assertion error message is printed, together with the location of the assertion, and A stack dump is performed, and the program exits with error code 227.

The `SysUtils` unit sets this procedure and raises an exception in its handler.

```
BackTraceStrFunc : TBackTraceStrFunc = @SysBackTraceStr
```

This handler is called to get a standard format for the backtrace routine.

```
CtrlZMarksEOF : Boolean = false
```

`CtrlZMarksEOF` indicates whether on this system, an CTRL-Z character (ordinal 26) in a file marks the end of the file. This is `False` on most systems apart from DOS and Windows.

To get DOS/Windows-compatible behaviour, this constant can be set to `True`

```
DefaultStackSize = 4*1024*1024
```

Default size for a new thread's stack (4MiB by default).

```
DefaultTextLineBreakStyle : TTextLineBreakStyle = tlbsLF
```

`DefaultTextLineBreakStyle` contains the default OS setting for the `TTextLineBreakStyle` (1249) type. It is initialized by the system unit, and is used to determine the default line ending when writing to text files.

This constant is part of a set of constants that describe the OS characteristics. These constants should be used instead of hardcoding OS characteristics.

```
DirectorySeparator = '/'
```

`DirectorySeparator` is the character used by the current operating system to separate directory parts in a pathname. This constant is system dependent, and should not be set.

This constant is part of a set of constants that describe the OS characteristics. These constants should be used instead of hardcoding OS characteristics.

`DriveSeparator = '/'`

On systems that support driveletters, the `DriveSeparator` constant denotes the character that separates the drive indicator from the directory part in a filename path.

This constant is part of a set of constants that describe the OS characteristics. These constants should be used instead of hardcoding OS characteristics.

`Erroraddr : pointer = nil`

Address where the last error occurred.

`Errorcode : Word = 0`

Last error code.

`ErrorProc : TErrorProc = nil`

If set, the `ErrorProc` constant is used when a run-time error occurs. If it is not set, then the standard error handling is done: a stack dump is performed, and the program exits with the indicated error code.

The `SysUtils` unit sets this procedure and raises an exception in its handler.

`ExceptProc : TExceptProc = nil`

This constant points to the current exception handling procedure. This routine is called when an unhandled exception occurs, i.e. an exception that is not stopped by a `except` block.

If the handler is not set, the RTL will emit a run-time error 217 when an unhandler exception occurs.

It is set by the `sysutils` ([1426](#)) unit.

`ExitProc : pointer = nil`

Exit procedure pointer.

`ExtensionSeparator = '.'`

`ExtensionSeparator` is the character which separates the filename from the file extension. On all current platforms, this is the `.` (dot) character. All RTL filename handling routines use this constant.

`E_NOINTERFACE = HRESULT($80004002)`

Interface call result: Error: not an interface

`E_NOTIMPL = HRESULT($80004001)`

Interface call result: Interface not implemented

```
E_UNEXPECTED = HRESULT($8000FFFF)
```

Interface call result: Unexpected error

```
Filemode : Byte = 2
```

Default file mode for untyped files.

```
FileNameCaseSensitive : Boolean = true
```

FileNameCaseSensitive is True if case is important when using filenames on the current OS. In this case, the OS will treat files with different cased names as different files. Note that this may depend on the filesystem: Unix operating systems that access a DOS or Windows partition will have this constant set to true, but when writing to the DOS partition, the casing is ignored.

This constant is part of a set of constants that describe the OS characteristics. These constants should be used instead of hardcoding OS characteristics.

```
float_flag_denormal = 2
```

IEC/IEEE floating-point exception flag: ?

```
float_flag_divbyzero = 4
```

IEC/IEEE floating-point exception flag: Division by zero error

```
float_flag_inexact = 32
```

IEC/IEEE floating-point exception flag: ?

```
float_flag_invalid = 1
```

IEC/IEEE floating-point exception flag: Invalid operation error

```
float_flag_overflow = 8
```

IEC/IEEE floating-point exception flag: Overflow error

```
float_flag_underflow = 16
```

IEC/IEEE floating-point exception flag: Underflow error

```
float_round_down = 1
```

Round down

```
float_round_nearest_even = 0
```

Round to nearest even number



`float_round_to_zero = 3`

Round in the direction of zero (down for positive, up for negative)

`float_round_up = 2`

Round up

`fmAppend = $D7B4`

File mode: File is open for writing, appending to the end.

`fmClosed = $D7B0`

File mode: File is closed.

`fmInOut = $D7B3`

File mode: File is open for reading and writing.

`fmInput = $D7B1`

File mode: File is open for reading.

`fmOutput = $D7B2`

File mode: File is open for writing.

`fpc_in_abs_long = 64`

Internal ABS function

`fpc_in_abs_real = 127`

FPC compiler internal procedure index: abs (real)

`fpc_in_addr_x = 42`

FPC compiler internal procedure index: addr

`fpc_in_arctan_real = 130`

FPC compiler internal procedure index: arctan (real)

`fpc_in_assert_x_y = 41`

FPC compiler internal procedure index: assert

`fpc_in_assigned_x = 19`

FPC compiler internal procedure index: assigned

fpc\_in\_bitsizeof\_x = 61

FPC compiler internal procedure index: bitsizeof

fpc\_in\_break = 39

FPC compiler internal procedure index: break

fpc\_in\_chr\_byte = 7

FPC compiler internal procedure index: chr

fpc\_in\_concat\_x = 18

FPC compiler internal procedure index: concat

fpc\_in\_const\_abs = 101

FPC compiler internal procedure index: abs

fpc\_in\_const\_odd = 102

FPC compiler internal procedure index: sqr

fpc\_in\_const\_ptr = 103

FPC compiler internal procedure index: sqr

fpc\_in\_const\_sqr = 100

FPC compiler internal procedure index: sqr

fpc\_in\_const\_swap\_long = 105

FPC compiler internal procedure index: swap (long)

fpc\_in\_const\_swap\_qword = 108

FPC compiler internal procedure index: swap (qword)

fpc\_in\_const\_swap\_word = 104

FPC compiler internal procedure index: swap (word)

fpc\_in\_continue = 40

FPC compiler internal procedure index: continue

fpc\_in\_copy\_x = 49

FPC compiler internal procedure index: copy

fpc\_in\_cos\_real = 125

FPC compiler internal procedure index: cos (real)

fpc\_in\_cycle = 52

FPC compiler internal procedure index: cycle

fpc\_in\_dec\_x = 36

FPC compiler internal procedure index: dec

fpc\_in\_dispose\_x = 47

FPC compiler internal procedure index: dispose

fpc\_in\_exclude\_x\_y = 38

FPC compiler internal procedure index: exclude

fpc\_in\_exit = 48

FPC compiler internal procedure index: exit

fpc\_in\_exp\_real = 124

FPC internal compiler routine: in\_exp\_real

fpc\_in\_fillchar\_x = 55

FPC internal compiler routine: in\_fillchar\_x

fpc\_in\_finalize\_x = 45

FPC compiler internal procedure index: finalize

fpc\_in\_frac\_real = 122

FPC internal compiler routine: in\_frac\_real

fpc\_in\_get\_caller\_addr = 57

FPC internal compiler routine: in\_get\_caller\_addr

fpc\_in\_get\_caller\_frame = 58

FPC internal compiler routine: in\_get\_caller\_frame

fpc\_in\_get\_frame = 56

FPC internal compiler routine: in\_get\_frame

fpc\_in\_high\_x = 28

FPC compiler internal procedure index: high

fpc\_in\_hi\_long = 4

FPC compiler internal procedure index: hi (long)

fpc\_in\_hi\_qword = 107

FPC compiler internal procedure index: hi (qword)

fpc\_in\_hi\_word = 2

FPC compiler internal procedure index: hi (word)

fpc\_in\_include\_x\_y = 37

FPC compiler internal procedure index: include

fpc\_in\_inc\_x = 35

FPC compiler internal procedure index: inc

fpc\_in\_initialize\_x = 50

FPC compiler internal procedure index: initialize

fpc\_in\_int\_real = 123

FPC internal compiler routine: in\_int\_real

fpc\_in\_leave = 51

FPC compiler internal procedure index: leave

fpc\_in\_length\_string = 6

FPC compiler internal procedure index: length

fpc\_in\_ln\_real = 131

FPC compiler internal procedure index: ln (real)

fpc\_in\_low\_x = 27

FPC compiler internal procedure index: low

fpc\_in\_lo\_long = 3

FPC compiler internal procedure index: lo (long)

fpc\_in\_lo\_qword = 106

FPC compiler internal procedure index: lo (qword)

fpc\_in\_lo\_word = 1

FPC compiler internal procedure index: lo (word)

fpc\_in\_mmx\_pcmpeqb = 200

FPC compiler internal procedure index: MMX

fpc\_in\_mmx\_pcmpeqd = 202

FPC compiler internal procedure index: MMX

fpc\_in\_mmx\_pcmpeqw = 201

FPC compiler internal procedure index: MMX

fpc\_in\_mmx\_pcmpgtb = 203

FPC compiler internal procedure index: MMX

fpc\_in\_mmx\_pcmpgtd = 205

FPC compiler internal procedure index: MMX

fpc\_in\_mmx\_pcmpgtw = 204

FPC compiler internal procedure index: MMX

fpc\_in\_move\_x = 54

FPC internal compiler routine: in\_move\_x

fpc\_in\_new\_x = 46

FPC compiler internal procedure index: new

fpc\_in\_ofs\_x = 21

FPC compiler internal procedure index: ofs

fpc\_in\_ord\_x = 5

FPC compiler internal procedure index: ord

fpc\_in\_pack\_x\_y\_z = 59

FPC compiler internal procedure index: pack

fpc\_in\_pi\_real = 126

FPC internal compiler routine: in\_pi\_real

fpc\_in\_pred\_x = 30

FPC compiler internal procedure index: pred

fpc\_in\_prefetch\_var = 109

FPC compiler internal procedure index: prefetch

fpc\_in\_readln\_x = 17

FPC compiler internal procedure index: readln

fpc\_in\_readstr\_x = 63

Internal read string procedure

fpc\_in\_read\_x = 16

FPC compiler internal procedure index: read

fpc\_in\_reset\_typedfile = 32

FPC compiler internal procedure index: reset

fpc\_in\_reset\_x = 25

FPC compiler internal procedure index: reset

fpc\_in\_rewrite\_typedfile = 33

FPC compiler internal procedure index: rewrite

fpc\_in\_rewrite\_x = 26

FPC compiler internal procedure index: rewrite

fpc\_in\_rol\_x = 67

fpc\_in\_rol\_x\_x = 68

fpc\_in\_ror\_x = 65

fpc\_in\_ror\_x\_x = 66

fpc\_in\_round\_real = 121

FPC internal compiler routine: in\_round\_real

fpc\_in\_seg\_x = 29

FPC compiler internal procedure index: seg

fpc\_in\_setlength\_x = 44

FPC compiler internal procedure index: setlength

fpc\_in\_settextbuf\_file\_x = 34

FPC compiler internal procedure index: settextbuf

fpc\_in\_sin\_real = 132

FPC compiler internal procedure index: sin (real)

fpc\_in\_sizeof\_x = 22

FPC compiler internal procedure index: sizeof

fpc\_in\_slice = 53

FPC internal compiler routine: in\_slice

fpc\_in\_sqrt\_real = 129

FPC compiler internal procedure index: sqrt (real)

fpc\_in\_sqr\_real = 128

FPC compiler internal procedure index: sqr (real)

fpc\_in\_str\_x\_string = 20

FPC compiler internal procedure index: str

fpc\_in\_succ\_x = 31

FPC compiler internal procedure index: succ

fpc\_in\_trunc\_real = 120

FPC internal compiler routine: in\_trunc\_real

fpc\_in\_typeinfo\_x = 43

FPC compiler internal procedure index: typeinfo

```
fpc_in_typeof_x = 23
```

FPC compiler internal procedure index: typeof

```
fpc_in_unpack_x_y_z = 60
```

FPC compiler internal procedure index: unpack

```
fpc_in_val_x = 24
```

FPC compiler internal procedure index: val

```
fpc_in_writeln_x = 15
```

FPC compiler internal procedure index: writeln

```
fpc_in_writestr_x = 62
```

Internal write string procedure

```
fpc_in_write_x = 14
```

FPC compiler internal procedure index: write

```
growheapsize1 : PtrUInt = 256*1024
```

Grow rate for block less than 256 Kb.

```
growheapsize2 : PtrUInt = 1024*1024
```

Grow rate for block larger than 256 Kb.

```
growheapsizesmall : PtrUInt = 32*1024
```

Fixed size small blocks grow rate

```
has_mmx_support : Boolean = false
```

```
has_sse_support : Boolean = false
```

```
InitProc : Pointer = nil
```

InitProc is a routine that can be called after all units were initialized. It can be set by units to execute code that can be initialized after all units were initialized.

**Remark:** When setting the value of InitProc, the previous value should always be saved, and called when the installed initialization routine has finished executing.

```
IsMultiThread : longbool = false
```



Indicates whether more than one thread is running in the application.

```
LFNSupport = true
```

`LFNSupport` determines whether the current OS supports long file names, i.e. filenames that are not of the form 8.3 as on ancient DOS systems. If the value of this constant is `True` then long filenames are supported. If it is false, then not.

This constant is part of a set of constants that describe the OS characteristics. These constants should be used instead of hardcoding OS characteristics.

```
LineEnding = #10
```

`LineEnding` is a constant which contains the current line-ending character. This character is system dependent, and is initialized by the system. It should not be set.

This constant is part of a set of constants that describe the OS characteristics. These constants should be used instead of hardcoding OS characteristics.

```
maxExitCode = 255
```

`maxExitCode` is the maximum value for the `Halt` (1303) call.

```
maxint = maxsmallint
```

Maximum integer value.

```
MaxKeptOSChunks : DWord = 4
```

`MaxKeptOSChunks` tells the heap manager how many free chunks of OS-allocated memory it should keep in memory. When freeing memory, it can happen that a memory block obtained from the OS is completely free. If more than `MaxKeptOSChunks` such blocks are free, then the heap manager will return them to the OS, to reduce memory requirements.

```
maxLongint = $7fffffff
```

Maximum longint value.

```
MaxPathLen = 4096
```

This constant is system dependent.

```
MaxSIntValue = High(ValSInt)
```

Maximum String-size value.

```
maxSmallint = 32767
```

Maximum smallint value.

```
MaxUIntValue = High(ValUInt)
```

Maximum unsigned integer value.

`Max_Frame_Dump : Word = 8`

Maximum number of frames to show in error frame dump.

`ModuleIsCpp : Boolean = false`

`ModuleIsCpp` is always false for FPC programs, it is provided for Delphi compatibility only.

`ModuleIsLib : Boolean = false`

`ModuleIsLib` is set by the compiler when linking a library, program or package, and determines whether the current module is a library (or package) (`True`) or program (`False`).

`ModuleIsPackage : Boolean = false`

`ModuleIsLib` is set by the compiler when linking a library, program or package, and determines whether the current module is a package (`True`) or a library or program (`False`).

`PathSeparator = ':'`

`PathSeparator` is the character used commonly on the current operating system to separate paths in a list of paths, such as the `PATH` environment variable.

This constant is part of a set of constants that describe the OS characteristics. These constants should be used instead of hardcoding OS characteristics.

`RaiseMaxFrameCount : LongInt = 16`

Maximum number of frames to include in `TExceptObject` ([1244](#))

`RaiseProc : TExceptProc = nil`

Procedure to raise an exception.

`RT_ACCELERATOR = MAKEINTRESOURCE (9)`

Constant identifying an accelerator resource

`RT_ANICURSOR = MAKEINTRESOURCE (21)`

This constant can be used to specify a resource of type "animated cursor".

`RT_ANIICON = MAKEINTRESOURCE (22)`

This constant can be used to specify a resource of type "animated icon".

`RT_BITMAP = MAKEINTRESOURCE (2)`

Constant identifying a bitmap resource

`RT_CURSOR = MAKEINTRESOURCE (1)`

Constant identifying a cursor resource

RT\_DIALOG = MAKEINTRESOURCE (5)

Constant identifying a dialog resource

RT\_FONT = MAKEINTRESOURCE (8)

Constant identifying a font resource

RT\_FONTDIR = MAKEINTRESOURCE (7)

Constant identifying a font directory resource

RT\_GROUP\_CURSOR = MAKEINTRESOURCE (12)

Constant identifying a group cursor resource

RT\_GROUP\_ICON = MAKEINTRESOURCE (14)

Constant identifying a group icon resource

RT\_HTML = MAKEINTRESOURCE (23)

This constant can be used to specify a resource of type "HTML data".

RT\_ICON = MAKEINTRESOURCE (3)

Constant identifying an icon resource

RT\_MANIFEST = MAKEINTRESOURCE (24)

This constant can be used to specify a resource of type "Manifest".

RT\_MENU = MAKEINTRESOURCE (4)

Constant identifying a menu resource

RT\_MESSAGE\_TABLE = MAKEINTRESOURCE (11)

Constant identifying a message data resource

RT\_RC\_DATA = MAKEINTRESOURCE (10)

Constant identifying a binary data resource

RT\_STRING = MAKEINTRESOURCE (6)

Constant identifying a string table resource

RT\_VERSION = MAKEINTRESOURCE (16)

Constant identifying a version info resource

```
RuntimeErrorExitCodes : Array[TRuntimeError] of Byte = (0,203,204,200,201,215,207,2
```

This array is used by the `Error` (1288) routine to convert a `TRuntimeError` (1248) enumeration type to a process exit code.

```
SafeCallErrorProc : TSafeCallErrorProc = nil
```

`SafeCallErrorProc` is a Handler called in case of a safecall calling convention error. `Error` is the error number (passed by the Windows operating system) and `Addr` is the address where the error occurred.

```
sLineBreak = LineEnding
```

`sLineBreak` is an alias for `LineEnding` (1223) and is supplied for Delphi compatibility.

This constant is part of a set of constants that describe the OS characteristics. These constants should be used instead of hardcoding OS characteristics.

```
StackError : Boolean = false
```

Indicate whether there was a stack error.

```
StdErrorHandle = 2
```

Value of the OS handle for the standard error-output file.

```
StdInputHandle = 0
```

Value of the OS handle for the standard input file.

```
StdOutputHandle = 1
```

Value of the OS handle for the standard output file.

```
S_FALSE = 1
```

Interface call result: Not OK

```
S_OK = 0
```

Interface call result: OK

```
Test8086 : Byte = 2
```

```
Test8087 : Byte = 3
```

```
ThreadingAlreadyUsed : Boolean = false
```

Internal constant for the threading system. Don't use.

`UnixGetModuleByAddrHook` : procedure(addr: pointer;var baseaddr: pointer;var filename

`UnixGetModuleByAddrHook` is used on unix systems to retrieve a module name based on an address. It is used in the `exeinfo` (559) unit to map addresses to module (programs or library) names.

`UnusedHandle` = -1

Value indicating an unused file handle (as reported by the OS).

`VarAddRefProc` : procedure(var v: tvardata) = nil

Callback to increase reference count of a variant.

`varany` = \$101

Variant type: Any

`vararray` = \$2000

Variant type: variant Array

`varboolean` = 11

Variant type: Boolean type

`varbyref` = \$4000

Variant type: By reference

`varbyte` = 17

Variant type: Byte (8 bit)

`VarClearProc` : procedure(var v: tvardata) = nil

Callback to clear a variant.

`VarCopyProc` : procedure(var d: tvardata;const s: tvardata) = nil

Callback to copy a variant

`varcurrency` = 6

Variant type: Currency

`vardate` = 7

Variant type: Date

`vardecimal = 14`

Variant type: Decimal (BCD)

`vardispatch = 9`

Variant type: dispatch interface

`vardouble = 5`

Variant type: Double float

`vareempty = 0`

Variant type: Empty variant

`varerror = 10`

Variant type: Error type

`varint64 = 20`

Variant type: Integer (64-Bit)

`varinteger = 3`

Variant type: Integer (32-bit)

`varlongword = 19`

Variant type: Word (32 bit)

`varnull = 1`

Variant type: Null ([1324](#)) variant

`varolestr = 8`

Variant type: OLE string (widestring)

`varqword = 21`

Variant type: Word (64-bit)

`varrecord = 36`

Record variant type

`varshortint = 16`

Variant type: Shortint (16 bit)

`varsingle = 4`

Variant type: Single float

`varsmallint = 2`

Variant type: smallint (8 bit)

`varstrarg = $48`

Variant type: String

`varstring = $100`

Variant type: String

`VarToLStrProc : procedure(var d: AnsiString;const s: tvardata) = nil`

Callback to convert a variant to a ansistring.

`VarToWStrProc : procedure(var d: WideString;const s: tvardata) = nil`

Callback to convert a variant to a widestring.

`vartypemask = $fff`

Variant type: Mask to extract type

`varunknown = 13`

Variant type: Unknown

`varvariant = 12`

Variant type: Variant (arrays only)

`varword = 18`

Variant type: Word (16 bit)

`varword64 = varqword`

Variant type: Word (64-bit)

`vmtAfterConstruction = vmtMethodStart+sizeof(pointer)*5`

VMT Layout: ?

`vmtAutoTable = vmtParent+sizeof(pointer)*7`

VMT layout: ?

`vmtBeforeDestruction = vmtMethodStart+sizeof(pointer)*6`

**VM T Layout:** ?

`vmtClassName = vmtParent+sizeof(pointer)`

**VM T Layout:** location of class name.

`vmtDefaultHandler = vmtMethodStart+sizeof(pointer)*4`

**VM T Layout:** ?

`vmtDefaultHandlerStr = vmtMethodStart+sizeof(pointer)*7`

**VM T Layout:** ?

`vmtDestroy = vmtMethodStart`

**VM T Layout:** Location of destructor pointer.

`vmtDispatch = vmtMethodStart+sizeof(pointer)*8`

`vmtDispatch` is the offset from the VM T start, in bytes to the dispatch table for a class. The dispatch table is used when dispatching messages in `TObject.Dispatch` ([1418](#))

`vmtDispatchStr = vmtMethodStart+sizeof(pointer)*9`

`vmtDispatchStr` is the offset from the VM T start, in bytes to the dispatch table for a class. The dispatch table is used when dispatching messages in `TObject.DispatchStr` ([1418](#))

`vmtDynamicTable = vmtParent+sizeof(pointer)*2`

**VM T Layout:** location of dynamic methods table.

`vmtEquals = vmtMethodStart+sizeof(pointer)*10`

`vmtEquals` contains the offset from the VM T start, of the location of the `TObject.Equals` ([1420](#)) method pointer.

`vmtFieldTable = vmtParent+sizeof(pointer)*4`

**VM T Layout:** Location of fields table.

`vmtFreeInstance = vmtMethodStart+sizeof(pointer)*2`

**VM T Layout:** location of `FreeInstance` method.

`vmtGetHashCode = vmtMethodStart+sizeof(pointer)*11`

`vmtGetHashCode` contains the offset from the VM T start, of the location of the `TObject.GetHashCode` ([1421](#)) method pointer.



`vmtInitTable = vmtParent+sizeof(pointer)*6`

**VMТ Layout: ?**

`vmtInstanceSize = 0`

**VMТ Layout: Location of class instance size in VMТ**

`vmtIntfTable = vmtParent+sizeof(pointer)*8`

**VMТ layout: Interface table**

`vmtMethodStart = vmtParent+sizeof(pointer)*10`

**VMТ layout: start of method table.**

`vmtMethodTable = vmtParent+sizeof(pointer)*3`

**VMТ Layout: Method table start.**

`vmtMsgStrPtr = vmtParent+sizeof(pointer)*9`

**VMТ layout: message strings table.**

`vmtNewInstance = vmtMethodStart+sizeof(pointer)`

**VMТ Layout: location of NewInstance method.**

`vmtParent = sizeof(ptruint)*2`

**VMТ Layout: location of pointer to parent VMТ.**

`vmtSafeCallException = vmtMethodStart+sizeof(pointer)*3`

**VMТ Layout: ?**

`vmtToString = vmtMethodStart+sizeof(pointer)*12`

`vmtToString` contains the offset from the VMТ start, of the location of the `TObject.ToString` (1421) method pointer.

`vmtTypeInfo = vmtParent+sizeof(pointer)*5`

**VMТ Layout: Location of class type information.**

`vtAnsiString = 11`

**TVarRec type: Ansistring**

`vtBoolean = 1`

TVarRec type: Boolean

vtChar = 2

TVarRec type: Char

vtClass = 8

TVarRec type: Class type

vtCurrency = 12

TVarRec type: Currency

vtExtended = 3

TVarRec type: Extended

vtInt64 = 16

TVarRec type: Int64 (signed 64-bit integer)

vtInteger = 0

TVarRec type: Integer

vtInterface = 14

TVarRec type: Interface

vtObject = 7

TVarRec type: Object instance

vtPChar = 6

TVarRec type: PChar

vtPointer = 5

TVarRec type: pointer

vtPWideChar = 10

TVarRec type: PWideChar

vtQWord = 17

TVarRec type: QWord (unsigned 64-bit integer)

vtString = 4

TVarRec type: String

vtVariant = 13

TVarRec type: Variant

vtWideChar = 9

TVarRec type: Widechar

vtWideString = 15

TVarRec type: WideString

### 37.8.2 Types

AnsiChar = Char

Alias for 1-byte sized char.

Cardinal = LongWord

An unsigned 32-bits integer.

DWord = LongWord

An unsigned 32-bits integer

```
EnumResLangProc = function(ModuleHandle: TFPResourceHMODULE;
                           ResourceType: PChar;ResourceName: PChar;
                           IDLanguage: Word;lParam: PtrInt) : LongBool
                           of object
```

EnumResNameProcs used in the EnumResourceLanguages (1285) call. It is called for all languages for a resource of the specified type and name, and is passed the ModuleHandle, ResourceName, ResourceName and IDLanguage values for each language encountered for the specified resource. Additionally, the lParam parameter from the EnumResourceLanguages is passed unaltered.

```
EnumResNameProc = function(ModuleHandle: TFPResourceHMODULE;
                           ResourceType: PChar;ResourceName: PChar;
                           lParam: PtrInt) : LongBool of object
```

EnumResNameProcs used in the EnumResourceNames (1285) call. It is called for all resources of the specified type, and is passed the ModuleHandle, ResourceType, ResourceName values for each resource encountered. Additionally, the lParam parameter from the EnumResourceNames is passed unaltered.

```
EnumResTypeProc = function(ModuleHandle: TFPResourceHMODULE;
                           ResourceType: PChar;lParam: PtrInt)
                           : LongBool of object
```

`EnumResTypeProc` is used in the `EnumResourceTypes` (1285) call. It is called for all resources, and is passed the `ModuleHandle`, `ResourceType` values for each resource encountered. Additionally, the `lParam` parameter from the `EnumResourceTypes` is passed unaltered.

```
HGLOBAL = PtrUInt
```

This is an opaque type.

```
HMODULE = PtrUInt
```

This is an opaque type.

```
HRESULT = LongInt
```

32-Bit signed integer.

```
IInterface = IUnknown
```

`IInterface` is the basic interface from which all COM style interfaces descend.

```
Integer = SmallInt
```

The system unit defines `Integer` as a signed 16-bit integer. But when DELPHI or OBJFPC mode are active, then the `objpas` unit redefines `Integer` as a 32-bit integer.

```
IntegerArray = Array[0..$ffffff] of Integer
```

Generic array of integer.

```
jmp_buf = packed record
  ebx : LongInt;
  esi : LongInt;
  edi : LongInt;
  bp  : Pointer;
  sp  : Pointer;
  pc  : Pointer;
end
```

Record type to store processor information.

```
MAKEINTRESOURCE = PChar
```

Alias for the `PChar` (1235) type.

```
PAnsiChar = PChar
```

Alias for `PChar` (1235) type.

```
PAnsiString = ^AnsiString
```

Pointer to an ansistring type.

```
PBoolean = ^Boolean
```

Pointer to a Boolean type.

```
PByte = ^Byte
```

Pointer to byte (1209) type

```
pcallldesc = ^tcallldesc
```

Pointer to TCallDesc (1243) record.

```
PCardinal = ^Cardinal
```

Pointer to Cardinal (1233) type

```
PChar = ^Char
```

Or the same as a pointer to an array of char. See the reference manual for more information about this type.

```
PClass = ^TClass
```

Pointer to TClass (1243)

```
PComp = ^Comp
```

```
PCurrency = ^Currency
```

Pointer to currency type.

```
PDate = ^TDateTime
```

Pointer to a TDateTime (1243) type.

```
PDateTime = ^TDateTime
```

Pointer to Tdatetime

```
PDispatch = ^IDispatch
```

Pointer to IDispatch (1404) interface type

```
pdispdesc = ^tdispdesc
```

Pointer to tdispdesc (1243) record

```
PDouble = ^Double
```

Pointer to double-sized float value.

```
PDWord = ^DWord
```

Pointer to DWord (1233) type

```
pdynarrayindex = ^tdynarrayindex
```

Pointer to tdynarrayindex (1243) type.

```
pdynarraytypeinfo = ^tdynarraytypeinfo
```

Pointer to TDynArrayTypeInfo (1244) type.

```
PError = ^TError
```

Pointer to an Error (1288) type.

```
PEventState = pointer
```

Pointer to EventState, which is an opaque type.

```
PExceptObject = ^TExceptObject
```

Pointer to Exception handler procedural type TExceptProc (1244)

```
PExtended = ^Extended
```

Pointer to extended-sized float value.

```
PGuid = ^TGuid
```

Pointer to TGUID (1245) type.

```
PInt64 = ^Int64
```

Pointer to Int64 type

```
PInteger = ^Integer
```

Pointer to integer (1234) type

```
PIntegerArray = ^IntegerArray
```

Pointer to IntegerArray (1234) type

```
PInterface = PUnknown
```

Pointer to IInterface (1234) interface

```
pinterfaceentry = ^tinterfaceentry
```

Pointer to `tinterfaceentry` (1246) record.

```
pinterfacetable = ^tinterfacetable
```

Pointer to `tinterfacetable` (1246) record.

```
PJump_buf = ^jump_buf
```

Pointer to `jump_buf` (1234) record

```
PLongBool = ^LongBool
```

Pointer to a `LongBool` type.

```
PLongint = ^LongInt
```

Pointer to `Longint` (1209) type

```
PLongWord = ^LongWord
```

Pointer to `LongWord` type

```
PMemoryManager = ^TMemoryManager
```

Pointer to `TMemoryManager` (1246) record

```
PMsgStrTable = ^TMsgStrTable
```

Pointer to array of `TMsgStrTable` (1247) records.

```
PointerArray = Array[0..512*1024*1024-2] of Pointer
```

Generic pointer array.

```
POleVariant = ^OleVariant
```

Pointer to `OleVariant` type.

```
PPAnsiChar = PPChar
```

Alias for `PPChar` (1237) type.

```
PPByte = ^PByte
```

`PPByte` is a pointer to a `PByte` (1235) type.

```
PPChar = ^PChar
```

Pointer to an array of pointers to null-terminated strings.

```
PPCharArray = ^TPCharArray
```

Pointer to TPCharArray (1247) type.

```
PPDispatch = ^PDispatch
```

Pointer to PDispatch (1235) pointer type

```
PPDouble = ^PDouble
```

PPDouble is a pointer to a PDouble (1236) type.

```
PPLongint = ^PLongint
```

PPLongint is a pointer to a PLongint (1237) type.

```
PPPointer = ^Pointer
```

Pointer to a pointer type.

```
PPPointerArray = ^PointerArray
```

Pointer to PointerArray (1237) type

```
PPPChar = ^PPChar
```

PPPChar is a pointer to a PPChar (1237)

```
PPPPointer = ^PPPointer
```

Pointer to a PPointer (1238) type.

```
PPPWideChar = ^PPWideChar
```

PPPWideChar is a pointer to a PPWideChar (1238) type.

```
PPPtrInt = ^PtrInt
```

Pointer to PtrInt (1239) type.

```
PPPtrUInt = ^PtrUInt
```

Pointer to unsigned integer of pointer size

```
PPUnknown = ^PUnknown
```

Pointer to untyped pointer

```
PPWideChar = ^PWideChar
```

Pointer to link id="PWideChar"> type.

```
PQWord = ^QWord
```



Pointer to QWord type

```
PRTLCriticalSection = ^TRTLCriticalSection
```

Pointer to #rtl.system.TRTLCriticalSection (1248) type.

```
PRTLEvent = pointer
```

Pointer to RTLEvent, which is an opaque type.

```
PShortInt = ^ShortInt
```

Pointer to shortint (1209) type

```
PShortString = ^ShortString
```

Pointer to a shortstring type.

```
PSingle = ^Single
```

Pointer to single-sized float value.

```
PSizeInt = ^SizeInt
```

Pointer to a SizeInt (1241) type

```
PSmallInt = ^SmallInt
```

Pointer to smallint (1209) type

```
pstringmessagetable = ^TStringMessageTable
```

Pointer to TStringMessageTable (1249) record.

```
PText = ^Text
```

Pointer to text file.

```
PtrInt = LongInt
```

P`trint` is a signed integer type which has always the same size as a pointer. P`trint` is considered harmful and should almost never be used in actual code, because pointers are normally unsigned. For example, consider the following code:

```
getmem(p, 2048);           {Assume the address of p becomes $7ffffff0.}
q:=pointer(ptrint(p)+1024); {Overflow error.}
writeln(q>p);              {Incorrect answer.}
```

P`trint` might have a valid use when two pointers are subtracted from each other if it is unknown which pointer has the largest address. However, even in this case p`trint` causes trouble in case the distance is larger than high(p`trint`) and must be used with great care.

The introduction of the p`trint` type was a mistake. Please use p`truint` (1240) instead.

```
PtrUInt = DWord
```

`PtrUInt` is an unsigned integer type which has always the same size as a pointer. When using integers which will be cast to pointers and vice versa, use this type, never the regular `Cardinal` type.

```
PUCS2Char = PWideChar
```

Pointer to UCS2Char (1254) character.

```
PUCS4Char = ^UCS4Char
```

Pointer to UCS4Char (1255)

```
PUCS4CharArray = ^TUCS4CharArray
```

Pointer to array of UCS4Char (1255) characters.

```
PUnicodeChar = ^UnicodeChar
```

`PUnicodeChar` is a pointer to a unicode character, just like `PChar` is a pointer to a `Char` an-  
sistring character.

```
PUnicodeString = ^UnicodeString
```

`PUnicodeString` is a pointer to a `UnicodeString` string.

```
PUnknown = ^IUnknown
```

Untyped pointer

```
PUTF8String = ^UTF8String
```

Pointer to UTF8String (1255)

```
pvararray = ^tvararray
```

Pointer to TVarArray (1252) type.

```
pvararraybound = ^tvararraybound
```

Pointer to tvararraybound (1252) type.

```
pvararrayboundarray = ^tvararrayboundarray
```

Pointer to tvararrayboundarray (1252) type.

```
pvararraycoorarray = ^tvararraycoorarray
```

Pointer to tvararraycoorarray (1252) type.

```
pvardata = ^tvardata
```

Pointer to TVarData (1252) record.

PVariant = ^Variant

Pointer to Variant type.

pvariantmanager = ^tvariantmanager

Pointer to TVariantManager (1253) record.

PVarRec = ^TVarRec

Pointer to TVarRec (1254) type.

PVmt = ^TVmt

Pointer to TVMT (1254) record

PWideChar = ^WideChar

Pointer to WChar (1255).

PWideString = ^WideString

Pointer to widestring type

PWord = ^Word

Pointer to word (1209) type

PWordBool = ^WordBool

Pointer to a WordBool type.

Real = Double

Alias for real type

real48 = Array[0..5] of Byte

TP compatible real type (6 bytes) definition

SizeInt = LongInt

Signed integer type which fits for sizes

SizeUInt = DWord

Unsigned Integer type which fits for sizes

TAbstractErrorProc = procedure

Abstract error handler procedural type.

TAllocateThreadVarsHandler = procedure

Threadvar allocation callback type for TThreadManager (1250).

TAnsiChar = Char

Alias for 1-byte sized char.

```
TAssertErrorProc = procedure(const msg: ShortString;
                             const fname: ShortString; lineno: LongInt;
                             erroraddr: pointer)
```

Assert error handler procedural type.

TBackTraceStrFunc = function(Addr: Pointer) : ShortString

Type for formatting of backtrace dump.

```
TBasicEventCreateHandler = function(EventAttributes: Pointer;
                                     AManualReset: Boolean;
                                     InitialState: Boolean;
                                     const Name: ansistring)
                             : PEventState
```

callback type for creating eventstate in TThreadManager (1250).

TBasicEventHandler = procedure(state: PEventState)

Generic callback type for handling eventstate in TThreadManager (1250).

```
TBasicEventWaitForHandler = function(timeout: Cardinal;
                                     state: PEventState) : LongInt
```

Wait for basic event callback type for TThreadManager (1250).

```
TBeginThreadHandler = function(sa: Pointer; stacksize: PtrUInt;
                               ThreadFunction: TThreadFunc; p: pointer;
                               creationFlags: DWord;
                               var ThreadId: TThreadID) : TThreadID
```

Callback for thread start in TThreadManager (1250).

TBoundArray = Array of SizeInt

Dynamic array of integer.

```
tcalldesc = packed record
  calltype : Byte;
  argcount : Byte;
  namedargcount : Byte;
  argtypes : Array[0..255] of Byte;
end
```

`tcalldesc` is used to encode the arguments to a dispatch call to an OLE dual interface. It is used on windows only. It describes the arguments to a call.

`TClass = Class of TObject`

Class of `TObject` ([1411](#)).

`TCriticalSectionHandler = procedure(var cs)`

Generic callback type for critical section handling in `TThreadManager` ([1250](#)).

`TCriticalSectionHandlerTryEnter = function(var cs) : LongInt`

`TCriticalSectionHandlerTryEnter` is the function prototype for the `TryEnterCriticalSection` ([1393](#)) function, in the `ThreadManager` ([1209](#)) record's `TryEnterCriticalSection` field.

`TCtrlBreakHandler = function(CtrlBreak: Boolean) : Boolean`

`TCtrlBreakHandler` is the prototype for the CTRL-C handler. If `CtrlBreak` is `True` then Ctrl-Break was hit, otherwise CTRL-C was hit. The handlers should return `True` to signal that the key-combination was handled. If `False` is returned, then default handling will be used, which by default means an exception will be raised if the `sysutils` unit is used.

`TDate = TDateTime`

`TDate` is defined for Delphi compatibility. This type is deprecated, use `TDateTime` ([1243](#)) instead.

`TDateTime = Double`

Encoded Date-Time type.

```
tdispdesc = packed record
  dispid : LongInt;
  restype : Byte;
  calldesc : tcalldesc;
end
```

`tcalldesc` is used to encode a dispatch call to an OLE dispatch interface. It is used on windows only. It describes the dispatch call.

`tdynarrayindex = SizeInt`

A variable of type `tdynarrayindex` will always have the correct size, suitable for serving as an index in a dynamic array.

```
tdynarraytypeinfo = packed record
  kind : Byte;
  namelen : Byte;
  elesize : SizeInt;
  eletype : pdynarraytypeinfo;
  vartype : LongInt;
end
```

`tdynarraytypeinfo` describes the structure of a multi-dimensional dynamical array. It is used in the `DynArraySetLength` (1283) call.

`TEndThreadHandler` = procedure(`ExitCode`: `DWord`)

Callback for thread end in `TThreadManager` (1250).

```
TEntryInformation = record
  InitFinalTable : Pointer;
  ThreadvarTablesTable : Pointer;
  asm_exit : procedure of object;
  PascalMain : procedure of object;
  valgrind_used : Boolean;
end
```

`TEntryInformation` is used to initialize a Free Pascal program or library. Under normal circumstances, there should be no need to use this structure directly: it is used by the system unit and special linking units.

`TError` = `LongInt`

Error type, used in variants.

`TErrorProc` = procedure(`ErrNo`: `LongInt`; `Address`: `Pointer`; `Frame`: `Pointer`)

Standard error handler procedural type.

```
TExceptObject = record
  FObject : TObject;
  Addr : pointer;
  Next : PExceptObject;
  refcount : LongInt;
  Framecount : LongInt;
  Frames : PPointer;
end
```

`TExceptObject` is the exception description record which is found on the exception stack.

```
TExceptProc = procedure(Obj: TObject; Addr: Pointer; FrameCount: LongInt;
  Frame: PPointer)
```

Exception handler procedural type

`TextFile` = `Text`

Alias for `Text` file type.

```
TFPCHeapStatus = record
  MaxHeapSize : PtrUInt;
  MaxHeapUsed : PtrUInt;
```

```

    CurrHeapSize : PtrUInt;
    CurrHeapUsed : PtrUInt;
    CurrHeapFree : PtrUInt;
end

```

TFCHeapStatus describes the state of the FPC heap manager. This is not equivalent to the THeapStatus (1246) record defined by Delphi, which contains information not meaningful for the FPC heap manager. The heap status can be retrieved by the GetFPCHeapStatus (1299) call.

```
TFCResourceHandle = PtrUInt
```

TFCResourceHandle represents a handle to a binary resource and is used in the various resource calls. Its actual type and size may differ across platforms.

```
TFCResourceHGLOBAL = PtrUInt
```

TFCResourceHGLOBAL represents a handle to the global module containing a resource. It is used in the various resource calls. It is an opaque type: its actual type and size may differ across platforms.

```
TFCResourceHMODULE = PtrUInt
```

TFCResourceHMODULE represents a module (library, executable, other) in which a resource is located. It is used in the various resource calls. It is an opaque type: its actual type and size may differ across platforms.

```
TGetCurrentThreadIdHandler = function : TThreadId
```

Callback type for retrieving thread ID in TThreadManager (1250).

```

TGuid = packed record
end

```

Standard GUID representation type.

```
THandle = LongInt
```

This type should be considered opaque. It is used to describe file and other handles.

```

THeapStatus = record
    TotalAddrSpace : Cardinal;
    TotalUncommitted : Cardinal;
    TotalCommitted : Cardinal;
    TotalAllocated : Cardinal;
    TotalFree : Cardinal;
    FreeSmall : Cardinal;
    FreeBig : Cardinal;
    Unused : Cardinal;
    Overhead : Cardinal;
    HeapErrorCode : Cardinal;
end

```

THeapStatus is the record describing the current heap status. It is returned by the GetHeapStatus (1299) call.

TInitThreadVarHandler = procedure (var offset: DWord; size: DWord)

Threadvar initialization callback type for TThreadManager (1250).

TInterfacedClass = Class of TInterfacedObject

TInterfacedClass is a descendent of

```
tinterfaceentry = record
  IID : PGuid;
  VTable : Pointer;
  IOffset : PtrUInt;
  IIDStr : PShortString;
end
```

tinterfaceentry is used to store the list of Interfaces of a class. This list is stored as an array of tinterfaceentry records.

```
tinterfaceentrytype = (etStandard, etVirtualMethodResult,
                      etStaticMethodResult, etFieldValue)
```

This is an internal type for the compiler to encode calls to dispatch interfaces.

```
tinterfacetable = record
  EntryCount : PtrUInt;
  Entries : Array[0..0] of tinterfaceentry;
end
```

Record to store list of interfaces of a class.

```
TMemoryManager = record
  NeedLock : Boolean;
  Getmem : function(Size: PtrUInt) : Pointer;
  Freemem : function(p: pointer) : PtrUInt;
  FreememSize : function(p: pointer; Size: PtrUInt) : PtrUInt;
  AllocMem : function(Size: PtrUInt) : Pointer;
  ReAllocMem : function(var p: pointer; Size: PtrUInt) : Pointer;
  MemSize : function(p: pointer) : PtrUInt;
  InitThread : procedure;
  DoneThread : procedure;
  RelocateHeap : procedure;
  GetHeapStatus : function : THeapStatus;
  GetFPCHeapStatus : function : TFPCHHeapStatus;
end
```

TMemoryManager describes the memory manager. For more information about the memory manager, see the programmer's reference.



```
TMethod = record
  Code : Pointer;
  Data : Pointer;
end
```

TMethod describes a general method pointer, and is used in Run-Time Type Information handling.

```
TMsgStrTable = record
  name : PShortString;
  method : pointer;
end
```

Record used in string message handler table.

```
TPCharArray = packed Array[0..(MaxLongintdivSizeOf(PChar))-1] of PChar
```

Array of PChar

```
TProcedure = procedure
```

Simple procedural type.

```
TReleaseThreadVarsHandler = procedure
```

Threadvar release callback type for TThreadManager ([1250](#)).

```
TRelocateThreadVarHandler = function(offset: DWord) : pointer
```

Threadvar relocation callback type for TThreadManager ([1250](#)).

```
TResourceHandle = PtrUInt
```

This is an opaque type.

```
TResourceManager = record
  HINSTANCEFunc : function : TFPResourceHMODULE;
  EnumResourceTypesFunc : function(ModuleHandle: TFPResourceHMODULE; EnumFunc: EnumResNameProc; lParam: PtrInt) : LongBool;
  EnumResourceNamesFunc : function(ModuleHandle: TFPResourceHMODULE; ResourceType: PChar; EnumFunc: EnumResNameProc; lParam: PtrInt) : LongBool;
  EnumResourceLanguagesFunc : function(ModuleHandle: TFPResourceHMODULE; ResourceType: PChar; ResourceName: PChar; EnumFunc: EnumResLangProc; lParam: PtrInt) : LongBool;
  FindResourceFunc : function(ModuleHandle: TFPResourceHMODULE; ResourceName: PChar; ResourceType: PChar) : TFPResourceHandle;
  FindResourceExFunc : function(ModuleHandle: TFPResourceHMODULE; ResourceType: PChar; ResourceName: PChar; Language: Word) : TFPResourceHandle;
  LoadResourceFunc : function(ModuleHandle: TFPResourceHMODULE; ResHandle: TFPResourceHandle) : TFPResourceHGLOBAL;
  SizeofResourceFunc : function(ModuleHandle: TFPResourceHMODULE; ResHandle: TFPResourceHandle) : LongInt;
```

```

        : LongWord;
    LockResourceFunc : function(ResData: TFPResourceHGLOBAL) : Pointer;
    UnlockResourceFunc : function(ResData: TFPResourceHGLOBAL) : LongBool;
    FreeResourceFunc : function(ResData: TFPResourceHGLOBAL) : LongBool;
end

```

TResourceManager is the record describing the resource manager. Depending on the kind of resources (internal, external), another resource managing handler is installed by the system. The resource manager record is used by all resource handling functions to do the actual work: for each function in the API, a handler function is available. People wishing to implement their own resource manager, must implement all handler functions in their implementation.

As soon as resources are used, the compiler will install a resource manager, depending on the platform, this may be an internal or an external resource manager.

```
TRTLCreateEventHandler = function : PRTLEvent
```

Callback type for creating a TRTLEvent type in TThreadManager ([1250](#)).

```
TRTLCriticalSection = Opaque type
```

TRTLCriticalSection represents a critical section (a mutex). This is an opaque type, it can differ from operating system to operating system. No assumptions should be made about its structure or contents.

```
TRTLEventHandler = procedure(AEvent: PRTLEvent)
```

Generic TRTLEvent handling type for TThreadManager ([1250](#)).

```
TRTLEventHandlerTimeout = procedure(AEvent: PRTLEvent; timeout: LongInt)
```

TRTLEvent timeout handling type for TThreadManager ([1250](#)).

```
TRTLEventSyncHandler = procedure(m: trtlmethod; p: TProcedure)
```

Callback type for event synchronization in TThreadManager ([1250](#)).

```
trtlmethod = procedure of object
```

Callback type for synchronization event.

```

TRuntimeError = (reNone, reOutOfMemory, reInvalidPtr, reDivByZero,
                  reRangeError, reIntOverflow, reInvalidOp, reZeroDivide,
                  reOverflow, reUnderflow, reInvalidCast, reAccessViolation,
                  rePrivInstruction, reControlBreak, reStackOverflow,
                  reVarTypeCast, reVarInvalidOp, reVarDispatch,
                  reVarArrayCreate, reVarNotArray, reVarArrayBounds,
                  reAssertionFailed, reExternalException, reIntfCastError,
                  reSafeCallError, reQuit, reCodesetConversion)

```

TRuntimeError is used in the Error ([1288](#)) procedure to indicate what kind of error should be reported.

`TSafeCallErrorProc = procedure(error: HRESULT;addr: pointer)`

Prototype of a safecall error handler routine. Error is the error number (passed by the Windows operating system) and Addr is the address where the error occurred.

`TSemaphoreDestroyHandler = procedure(const sem: Pointer)`

`TSemaphoreDestroyHandler` is the function prototype to destroy an existing semaphore, as returned by `(ThreadManager.SemaphoreInit)`. It is used by the thread manager `(ThreadManager.SemaphoreDest`

`TSemaphorePostHandler = procedure(const sem: Pointer)`

`TSemaphorePostHandler` is the function prototype to post an event to the semaphore. It should handle a pointer as returned by the `ThreadManager.SemaphoreInit` procedure. it's used by the thread manager `ThreadManager.SemaphorePost`.

`TSemaphoreWaitHandler = procedure(const sem: Pointer)`

`TSemaphoreWaitHandler` is the function prototype to wait on an event on the semaphore (which should be posted to the semaphore with `ThreadManager.SemaphorePost`). It should handle a pointer as returned by the `ThreadManager.SemaphoreInit` procedure. it's used by the thread manager `ThreadManager.SemaphoreWait`.

`TSemaphoreInitHandler = function : Pointer`

`TSemaphoreInitHandler` is the function prototype for initializing a semaphore. It is used by the thread manager `(ThreadManager.SemaphoreInit)` to create semaphores. The function should return a pointer, usable by the other semaphore functions of the thread manager.

```
TStringMessageTable = record
    count : PtrUInt;
    msgstrtable : Array[0..0] of TMsgStrTable;
end
```

Record used to describe the string messages handled by a class. It consists of a count, followed by an array of `TMsgStrTable` (1247) records.

`TTextLineBreakStyle = (tlbsLF,tlbsCRLF,tlbsCR)`

Text line break style. (end of line character)

`TThreadFunc = function(parameter: pointer) : PtrInt`

Thread function prototype

`TThreadGetPriorityHandler = function(threadHandle: TThreadID) : LongInt`

Callback type for thread priority getting in `TThreadManager` (1250).

`TThreadHandler = function(threadHandle: TThreadID) : DWord`

Generic thread handler callback for TThreadManager ([1250](#)).

```
TThreadID = PtrUInt
```

This is an opaque type, it can differ from operating system to operating system.

```
TThreadManager = record
  InitManager : function : Boolean;
  DoneManager : function : Boolean;
  BeginThread : TBeginThreadHandler;
  EndThread : TEndThreadHandler;
  SuspendThread : TThreadHandler;
  ResumeThread : TThreadHandler;
  KillThread : TThreadHandler;
  CloseThread : TThreadHandler;
  ThreadSwitch : TThreadSwitchHandler;
  WaitForThreadTerminate : TWaitForThreadTerminateHandler;
  ThreadSetPriority : TThreadSetPriorityHandler;
  ThreadGetPriority : TThreadGetPriorityHandler;
  GetCurrentThreadId : TGetCurrentThreadIdHandler;
  InitCriticalSection : TCriticalSectionHandler;
  DoneCriticalSection : TCriticalSectionHandler;
  EnterCriticalSection : TCriticalSectionHandler;
  TryEnterCriticalSection : TCriticalSectionHandlerTryEnter;
  LeaveCriticalSection : TCriticalSectionHandler;
  InitThreadVar : TInitThreadVarHandler;
  RelocateThreadVar : TRelocateThreadVarHandler;
  AllocateThreadVars : TAllocateThreadVarsHandler;
  ReleaseThreadVars : TReleaseThreadVarsHandler;
  BasicEventCreate : TBasicEventCreateHandler;
  BasicEventDestroy : TBasicEventHandler;
  BasicEventResetEvent : TBasicEventHandler;
  BasicEventSetEvent : TBasicEventHandler;
  BasicEventWaitFor : TBasicEventWaitForHandler;
  RTLEventCreate : TRTLCreateEventHandler;
  RTLEventDestroy : TRTLEventHandler;
  RTLEventSetEvent : TRTLEventHandler;
  RTLEventResetEvent : TRTLEventHandler;
  RTLEventWaitFor : TRTLEventHandler;
  RTLEventSync : TRTLEventSyncHandler;
  RTLEventWaitForTimeout : TRTLEventHandlerTimeout;
  SemaphoreInit : TSemaphoreInitHandler;
  SemaphoreDestroy : TSemaphoreDestroyHandler;
  SemaphorePost : TSemaphorePostHandler;
  SemaphoreWait : TSemaphoreWaitHandler;
end
```

TThreadManager is a record that contains all callbacks needed for the thread handling routines of the Free Pascal Run-Time Library. The thread manager can be set by the SetThreadManager ([1378](#)) procedure, and the current thread manager can be retrieved with the GetThreadManager ([1301](#)) procedure.

The Windows RTL will set the thread manager automatically to a system thread manager, based on the Windows threading routines. Unix operating systems provide a unit `cthreads` which implements

threads based on the C library POSIX thread routines. It is not included by default, because it would make the system unit dependent on the C library.

For more information about thread programming, see the programmer's guide.

```
TThreadSetPriorityHandler = function(threadHandle: TThreadID;
                                   Prio: LongInt) : Boolean
```

Callback type for thread priority setting in TThreadManager ([1250](#)).

```
TThreadSwitchHandler = procedure
```

Callback type for thread switch in TThreadManager ([1250](#)).

```
TTime = TDateTime
```

TTime is defined for Delphi compatibility. This type is deprecated, use TDateTime ([1243](#)) instead.

```
TUCS4CharArray = Array[0..$efffffff] of UCS4Char
```

Array of UCS4Char ([1255](#)) characters.

```
TUnicodeStringManager = record
  Wide2AnsiMoveProc : procedure(source: PWideChar;var dest: ansistring;len: SizeInt)
  Ansi2WideMoveProc : procedure(source: PChar;var dest: widestring;len: SizeInt);
  UpperWideStringProc : function(const S: WideString) : WideString;
  LowerWideStringProc : function(const S: WideString) : WideString;
  CompareWideStringProc : function(const s1: WideString;const s2: WideString) : PtrInt;
  CompareTextWideStringProc : function(const s1: WideString;const s2: WideString) : PtrInt;
  CharLengthPCharProc : function(const Str: PChar) : PtrInt;
  UpperAnsiStringProc : function(const s: ansistring) : ansistring;
  LowerAnsiStringProc : function(const s: ansistring) : ansistring;
  CompareStrAnsiStringProc : function(const S1: ansistring;const S2: ansistring) : PtrInt;
  CompareTextAnsiStringProc : function(const S1: ansistring;const S2: ansistring) : PtrInt;
  StrCompAnsiStringProc : function(S1: PChar;S2: PChar) : PtrInt;
  StrICompAnsiStringProc : function(S1: PChar;S2: PChar) : PtrInt;
  StrLCompAnsiStringProc : function(S1: PChar;S2: PChar;MaxLen: PtrUInt) : PtrInt;
  StrLICompAnsiStringProc : function(S1: PChar;S2: PChar;MaxLen: PtrUInt) : PtrInt;
  StrLowerAnsiStringProc : function(Str: PChar) : PChar;
  StrUpperAnsiStringProc : function(Str: PChar) : PChar;
  ThreadInitProc : procedure;
  ThreadFiniProc : procedure;
  Unicode2AnsiMoveProc : procedure(source: PUnicodeChar;var dest: ansistring;len: SizeInt);
  Ansi2UnicodeMoveProc : procedure(source: PChar;var dest: unicodestring;len: SizeInt);
  UpperUnicodeStringProc : function(const S: UnicodeString) : UnicodeString;
  LowerUnicodeStringProc : function(const S: UnicodeString) : UnicodeString;
  CompareUnicodeStringProc : function(const s1: UnicodeString;const s2: UnicodeString) : PtrInt;
  CompareTextUnicodeStringProc : function(const s1: UnicodeString;const s2: UnicodeString) : PtrInt;
end
```

TUnicodeStringManager is currently the same as the TUnicodeStringManager ([1251](#)) manager record. It performs the same functions: converting unicode strings to ansistrings and vice-versa, performing uppercase to lowercase transformations and comparing strings.

```

tvararray = record
  dimcount : Word;
  flags : Word;
  elementsize : LongInt;
  lockcount : LongInt;
  data : pointer;
  bounds : tvararrayboundarray;
end

```

tvararray is a record describing a variant array. It contains some general data, followed by a number of TVarArrayBound (1252) records equal to the number of dimensions in the array (dimcount).

```

tvararraybound = record
  elementcount : LongInt;
  lowbound : LongInt;
end

```

tvararraybound is used to describe one dimension in a variant array.

```

tvararrayboundarray = Array[0..0] of tvararraybound

```

array of tvararraybound (1252) records.

```

tvararraycoorarray = Array[0..0] of LongInt

```

Array of variant array coordinates

```

tvardata = packed record
  vtype : tvartype;
end

```

TVarData is a record representation of a variant. It contains the internal structure of a variant and is handled by the various variant handling routines.

```

tvariantmanager = record
  vartoint : function(const v: variant) : LongInt;
  vartoint64 : function(const v: variant) : Int64;
  vartoword64 : function(const v: variant) : qword;
  vartobool : function(const v: variant) : Boolean;
  vartoreal : function(const v: variant) : extended;
  vartotdatetime : function(const v: variant) : TDateTime;
  vartocurr : function(const v: variant) : currency;
  vartopstr : procedure(var s; const v: variant);
  vartolstr : procedure(var s: ansistring; const v: variant);
  vartowstr : procedure(var s: widestring; const v: variant);
  vartointf : procedure(var intf: IInterface; const v: variant);
  vartodisp : procedure(var disp: IDispatch; const v: variant);
  vartodynarray : procedure(var dynarr: pointer; const v: variant; typeinfo: pointer);
  varfrombool : procedure(var dest: variant; const source: Boolean);

```

```

varfromint : procedure(var dest: variant;const source: LongInt;const Range: LongInt);
varfromint64 : procedure(var dest: variant;const source: Int64);
varfromword64 : procedure(var dest: variant;const source: qword);
varfromreal : procedure(var dest: variant;const source: extended);
varfromdatetime : procedure(var dest: Variant;const source: TDateTime);
varfromcurr : procedure(var dest: Variant;const source: Currency);
varfrompstr : procedure(var dest: variant;const source: ShortString);
varfromlstr : procedure(var dest: variant;const source: ansistring);
varfromwstr : procedure(var dest: variant;const source: WideString);
varfromintf : procedure(var dest: variant;const source: IInterface);
varfromdisp : procedure(var dest: variant;const source: IDispatch);
varfromdynarray : procedure(var dest: variant;const source: pointer;typeinfo: pointer);
olevarfrompstr : procedure(var dest: olevariant;const source: shortstring);
olevarfromlstr : procedure(var dest: olevariant;const source: ansistring);
olevarfromvar : procedure(var dest: olevariant;const source: variant);
olevarfromint : procedure(var dest: olevariant;const source: LongInt;
    const range: ShortInt);
varop : procedure(var left: variant;const right: variant;opcode: tvarop);
cmpop : function(const left: variant;const right: variant;const opcode: tvarop)
    : Boolean;
varneg : procedure(var v: variant);
varnot : procedure(var v: variant);
varinit : procedure(var v: variant);
varclear : procedure(var v: variant);
varaddrref : procedure(var v: variant);
varcopy : procedure(var dest: variant;const source: variant);
varcast : procedure(var dest: variant;const source: variant;vartype: LongInt);
varcastole : procedure(var dest: variant;const source: variant;vartype: LongInt);
dispinvoke : procedure(dest: pvardata;const source: tvardata;calldesc: pcalldesc;
    params: pointer) of object;
vararrayredim : procedure(var a: variant;highbound: SizeInt);
vararrayget : function(const a: variant;indexcount: SizeInt;indices: PLongint)
    : variant of object;
vararrayput : procedure(var a: variant;const value: variant;indexcount: SizeInt;
    indices: PLongint) of object;
writevariant : function(var t: text;const v: variant;width: LongInt) : Pointer;
write0Variant : function(var t: text;const v: Variant) : Pointer;
end

```

TVariantManager describes the variant manager as expected by the SetVariantManager (1379) call.

```

tvarop = (opadd, opsubtract, opmultiply, opdivide, opintdivide, opmodulus,
    opshiftleft, opshiftright, opand, opor, opxor, opcompare, opnegate,
    opnot, opcmpeq, opcmpne, opcmplt, opcmple, opcmpgt, opcmpge, oppower)

```

tvarop describes a variant operation. It is mainly used for the variant manager to implement the various conversions and mathematical operations on a variant.

```

TVarRec = record
end

```

TVarRec is a record generated by the compiler for each element in a array of const call. The procedure that receives the constant array receives an array of TVarRec elements, with lower bound zero and high bound equal to the number of elements in the array minus one (as returned by High (Args))

```
tvartype = Word
```

Type with size of variant type.

```
TVmt = record
  vInstanceSize : SizeInt;
  vInstanceSize2 : SizeInt;
  vParent : PVmt;
  vClassName : PShortString;
  vDynamicTable : Pointer;
  vMethodTable : Pointer;
  vFieldTable : Pointer;
  vTypeInfo : Pointer;
  vInitTable : Pointer;
  vAutoTable : Pointer;
  vIntfTable : pinterfacetable;
  vMsgStrPtr : pstringmessagetable;
  vDestroy : Pointer;
  vNewInstance : Pointer;
  vFreeInstance : Pointer;
  vSafeCallException : Pointer;
  vDefaultHandler : Pointer;
  vAfterConstruction : Pointer;
  vBeforeDestruction : Pointer;
  vDefaultHandlerStr : Pointer;
  vDispatch : Pointer;
  vDispatchStr : Pointer;
  vEquals : Pointer;
  vGetHashCode : Pointer;
  vToString : Pointer;
end
```

TVMT is a record describing the VMT of a class. It's various fields represent the available information in the VMT, as far as it is common to all classes.

```
TWaitForThreadTerminateHandler = function(threadHandle: TThreadID;
                                          TimeoutMs: LongInt) : DWord
```

Callback type for thread termination in TThreadManager ([1250](#)).

```
TWideStringManager = TUnicodeStringManager
```

TWideStringManager contains the definition of the widestring manager.

```
UCS2Char = WideChar
```

UCS2 unicode character.



UCS4Char =

UCS unicode character (unsigned 32 bit word)

UCS4String = Array of UCS4Char

String of UCS4Char (1255) characters.

UInt64 = QWord

Unsigned 64-bit integer

UnicodeChar = WideChar

UnicodeChar is a single character from a UnicodeString. It equals WideChar in all respects.

UTF8String = ansistring

UTF-8 unicode (ansi) string.

ValReal = Extended

ValSInt = LongInt

Integer with the same size as the return code of the Val (1399) function.

ValUInt = Cardinal

Integer with the same size as the return code of the Val (1399) function.

WChar = Widechar

Wide char (16-bit sized char)

### 37.8.3 Variables

argc : LongInt; external name operatingsystem\_parameter\_argc

argc contains the number of command-line arguments passed to the program by the OS. It is not available on all systems.

argv : PPChar; external name operatingsystem\_parameter\_argv

argv contains a pointer to a nil-terminated array of null-terminated strings, containing the command-line arguments passed to the program by the OS. It is not available on all systems.

DispCallByIDProc : pointer

VarDispProc is called by the compiler if it needs to perform an interface call from a variant which contains a dispatch interface. For instance, the following call:

```
Var
  V : OleVariant;
begin
  (V as IWord).OpenDocument('c:\temp\mydoc.doc');
end;
```

where IWord is a dispatch interface is encoded by the compiler and passed to DispCallByIDProc. This pointer must be set by a routine that calls the OS COM handling routines.

```
envp : PPChar; external name operatingsystem_parameter_envp
```

envp contains a pointer to a nil-terminated array of null-terminated strings, containing the environment variables passed to the program by the OS. It is not available on all systems.

```
ErrOutput : Text
```

ErrOutput is provided for Delphi compatibility.

```
ExitCode : LongInt; public name operatingsystem_result
```

Exit code for the program, will be communicated to the OS on exit.

```
fpc_threadvar_relocate_proc : pointer; public name FPC_THREADVAR_RELOCATE
```

```
InOutRes : Word
```

Result of last I/O operation. Read-Only.

```
Input : Text
```

Standard input text file.

```
IsConsole : Boolean
```

True for console applications, False for GUI applications.

```
IsLibrary : Boolean = false
```

True if the current module is a library. Otherwise module is an executable

```
Output : Text
```

Standard output text file.

```
RandSeed : Cardinal
```

Seed for Random ([1359](#)) function.

```
ReturnNilIfGrowHeapFails : Boolean
```

`ReturnNilIfGrowHeapFails` describes what happens if there is no more memory available from the operating system. if set to `True` the memory manager will return `Nil`. If set to `False` then a run-time error will occur.

`softfloat_exception_flags` : `Byte`

Current soft float exception flags

`softfloat_exception_mask` : `Byte`

Current soft float exception mask

`softfloat_rounding_mode` : `Byte`

`softfloat_rounding_mode` determines how the software floating-point emulation routines do the rounding. The value can be one of the following:

**`float_round_nearest_even`** Round to nearest even number

**`float_round_down`** Round down

**`float_round_up`** Round up

**`float_round_to_zero`** Round in the direction of zero (down for positive, up for negative)

`StackBottom` : `Pointer`

Current stack bottom.

`StackLength` : `SizeUInt`

Maximum stack length.

`StackTop` : `Pointer`

`StackTop` contains the top of the stack for the current process. It is used to check the heap on some operating systems, and is set by the system unit initialization code. Do not use or modify this value.

`StdErr` : `Text`

Standard diagnostic output text file.

`StdOut` : `Text`

Alias for Output ([1256](#)).

`ThreadID` : `TThreadID`

Current Thread ID.

`widestringmanager` : `TUnicodeStringManager`

Contains the current widestring manager. Do not use directly.

## 37.9 Procedures and functions

### 37.9.1 abs

Synopsis: Calculate absolute value

Declaration: `function abs(l: LongInt) : LongInt`  
`function abs(l: Int64) : Int64`  
`function abs(d: ValReal) : ValReal`

Visibility: default

Description: `Abs` returns the absolute value of a variable. The result of the function has the same type as its argument, which can be any numerical type.

Errors: None.

See also: `Round` ([1369](#))

**Listing:** `./refex/ex1.pp`

---

```
Program Example1;

{ Program to demonstrate the Abs function. }

Var
  r : real;
  i : integer;

begin
  r:=abs(-1.0);   { r:=1.0 }
  i:=abs(-21);   { i:=21 }
end.
```

---

### 37.9.2 AbstractError

Synopsis: Generate an abstract error.

Declaration: `procedure AbstractError`

Visibility: default

Description: `AbstractError` generates an abstract error (run-time error 211). If the `AbstractErrorProc` ([1211](#)) constant is set, it will be called instead.

Errors: This routine causes a run-time error 211.

See also: `AbstractErrorProc` ([1211](#))

### 37.9.3 AcquireExceptionObject

Synopsis: Obtain a reference to the current exception object

Declaration: `function AcquireExceptionObject : Pointer`

Visibility: default

**Description:** `AcquireExceptionObject` returns the current exception object. It raises the reference count of the exception object, so it will not be freed. Calling this method is only valid within an except block.

The effect of this function is countered by re-raising an exception via `raise`;

To make sure that the exception object is released when it is no longer needed, `ReleaseExceptionObject` (1363) must be called when the reference is no longer needed.

**Errors:** If there is no current exception, a run-time error 231 will occur.

**See also:** `ReleaseExceptionObject` (1363)

### 37.9.4 AddExitProc

**Synopsis:** Add an exit procedure to the exit procedure chain.

**Declaration:** `procedure AddExitProc(Proc: TProcedure)`

**Visibility:** default

**Description:** `AddExitProc` adds `Proc` to the exit procedure chain. At program exit, all procedures added in this way will be called in reverse order.

**Errors:** None.

**See also:** `ExitProc` (1213)

### 37.9.5 Addr

**Synopsis:** Return address of a variable

**Declaration:** `function Addr(X: TAnytype) : Pointer`

**Visibility:** default

**Description:** `Addr` returns a pointer to its argument, which can be any type, or a function or procedure name. The returned pointer isn't typed. The same result can be obtained by the `@` operator, which can return a typed pointer (see the programmer's guide).

**Errors:** None

**See also:** `SizeOf` (1380)

**Listing:** `./refex/ex2.pp`

---

**Program** Example2;

*{ Program to demonstrate the Addr function. }*

**Const** Zero : integer = 0;

**Var** p : pointer;  
i : Integer;

**begin**  
  p:=**Addr**(p);       *{ P points to itself }*  
  p:=**Addr**(1);       *{ P points to 1 }*  
  p:=**Addr**(Zero);   *{ P points to 'Zero' }*  
**end.**

---

### 37.9.6 Align

Synopsis: Return aligned version of an address

Declaration: `function Align (Addr: PtrUInt; Alignment: PtrUInt) : PtrUInt`  
`function Align (Addr: Pointer; Alignment: PtrUInt) : Pointer`

Visibility: default

Description: `Align` returns `Address`, aligned to `Alignment` bytes.

Errors: None.

### 37.9.7 AllocMem

Synopsis: Allocate and clear memory.

Declaration: `function AllocMem (Size: PtrUInt) : pointer`

Visibility: default

Description: `AllocMem` calls `getmem GetMem` ([1299](#)), and clears the allocated memory, i.e. the allocated memory is filled with `Size` zero bytes.

See also: `GetMem` ([1299](#))

### 37.9.8 AnsiToUtf8

Synopsis: Convert ansi string to UTF-8 string

Declaration: `function AnsiToUtf8 (const s: ansistring) : UTF8String`

Visibility: default

Description: `AnsiToUtf8` converts the `ansistring` `S` to a UTF-8 format, that is, it converts the string from whatever codepage is currently in use, to UTF-8.

The current codepage is fetched from the system, if internationalization support is enabled. It can be UTF-8, in which case the function simply returns `S`.

Errors: None.

See also: `Utf8toAnsi` ([1398](#))

### 37.9.9 Append

Synopsis: Open a file in append mode

Declaration: `procedure Append (var t: Text)`

Visibility: default

Description: `Append` opens an existing file in append mode. Any data written to `F` will be appended to the file. Only text files can be opened in append mode. After a call to `Append`, the file `F` becomes write-only. File sharing is not taken into account when calling `Append`.

Errors: If the file doesn't exist when appending, a run-time error will be generated. This behaviour has changed on Windows and Linux platforms, where in versions prior to 1.0.6, the file would be created in append mode.

See also: Rewrite ([1365](#)), Close ([1269](#)), Reset ([1364](#))

**Listing:** ./refex/ex3.pp

---

**Program** Example3;

*{ Program to demonstrate the Append function. }*

**Var** f : text;

**begin**

Assign (f, 'test.txt');

**Rewrite** (f); *{ file is opened for write , and emptied }*

**Writeln** (F, 'This is the first line of text.txt');

close (f);

**Append**(f); *{ file is opened for write , but NOT emptied.  
any text written to it is appended. }*

**Writeln** (f, 'This is the second line of text.txt');

close (f);

**end.**

---

### 37.9.10 arctan

Synopsis: Calculate inverse tangent

Declaration: function arctan(d: ValReal) : ValReal

Visibility: default

Description: ArcTan returns the Arctangent of X, which can be any Real type. The resulting angle is in radial units.

Errors: None

See also: Sin ([1380](#)), Cos ([1277](#))

**Listing:** ./refex/ex4.pp

---

**Program** Example4;

*{ Program to demonstrate the ArcTan function. }*

**Var** R : Real;

**begin**

R:=ArcTan(0); *{ R:=0 }*

R:=ArcTan(1)/pi; *{ R:=0.25 }*

**end.**

---

### 37.9.11 ArrayStringToPPchar

Synopsis: Concert an array of string to an array of null-terminated strings

Declaration: function ArrayStringToPPchar(const S: Array of AnsiString;  
reserveentries: LongInt) : PPChar

Visibility: default

**Description:** `ArrayStringToPPchar` creates an array of null-terminated strings that point to strings which are the same as the strings in the array `S`. The function returns a pointer to this array. The array and the strings it contains must be disposed of after being used, because it they are allocated on the heap.

The `ReserveEntries` parameter tells `ArrayStringToPPchar` to allocate room at the end of the array for another `ReserveEntries` entries.

**Errors:** If not enough memory is available, an error may occur.

See also: `StringToPPChar` ([1385](#))

### 37.9.12 Assert

**Synopsis:** Check validity of a given condition.

**Declaration:** `procedure Assert (Expr: Boolean)`  
`procedure Assert (Expr: Boolean; const Msg: String)`

**Visibility:** default

**Description:** With assertions on, `Assert` tests if `expr` is false, and if so, aborts the application with a Runtime error 227 and an optional error message in `msg`. If `expr` is true, program execution continues normally. If assertions are not enabled at compile time, this routine does nothing, and no code is generated for the `Assert` call. Enabling and disabling assertions at compile time is done via the `\$C` or `\$ASSERTIONS` compiler switches. These are global switches. The default behavior of the assert call can be changed by setting a new handler in the `AssertErrorProc` variable. `Sysutils` overrides the default handler to raise a `EAssertionFailed` exception.

**Errors:** None.

See also: `Halt` ([1303](#)), `Runerror` ([1371](#))

### 37.9.13 Assign

**Synopsis:** Assign a name to a file

**Declaration:** `procedure Assign (out f: File; const Name: String)`  
`procedure Assign (out f: File; p: PChar)`  
`procedure Assign (out f: File; c: Char)`  
`procedure Assign (out f: TypedFile; const Name: String)`  
`procedure Assign (out f: TypedFile; p: PChar)`  
`procedure Assign (out f: TypedFile; c: Char)`  
`procedure Assign (out t: Text; const s: String)`  
`procedure Assign (out t: Text; p: PChar)`  
`procedure Assign (out t: Text; c: Char)`

**Visibility:** default

**Description:** `Assign` assigns a name to `F`, which can be any file type. This call doesn't open the file, it just assigns a name to a file variable, and marks the file as closed.

**Errors:** None.

See also: `Reset` ([1364](#)), `Rewrite` ([1365](#)), `Append` ([1260](#))

**Listing:** `./refex/ex5.pp`



---

**Program** Example5;

```
{ Program to demonstrate the Assign function. }

    Var F : text;

begin
    Assign (F, '');
    Rewrite (f);
    { The following can be put in any file by redirecting it
      from the command line.}
    Writeln (f, 'This goes to standard output !');
    Close (f);
    Assign (F, 'Test.txt');
    rewrite (f);
    writeln (f, 'This doesn''t go to standard output !');
    close (f);
end.
```

---

### 37.9.14 Assigned

Synopsis: Check if a pointer is valid

Declaration: `function Assigned(P: Pointer) : Boolean`

Visibility: default

Description: `Assigned` returns `True` if `P` is non-nil and returns `False` if `P` is nil. The main use of `Assigned` is that Procedural variables, method variables and class-type variables also can be passed to `Assigned`.

Errors: None

See also: `New` ([1323](#))

**Listing:** ./refex/ex96.pp

---

**Program** Example96;

```
{ Program to demonstrate the Assigned function. }

Var P : Pointer;

begin
    If Not Assigned(P) then
        Writeln ('Pointer is initially NIL');
    P:=@P;
    If Not Assigned(P) then
        Writeln ('Internal inconsistency')
    else
        Writeln ('All is well in FPC')
end.
```

---

### 37.9.15 BasicEventCreate

Synopsis: Obsolete. Don't use

Declaration: `function BasicEventCreate(EventAttributes: Pointer;  
  AManualReset: Boolean;InitialState: Boolean;  
  const Name: ansistring) : PEventState`

Visibility: default

Description: `BasicEventCreate` is obsolete, use `RTLEventCreate` ([1370](#)) instead.

See also: `RTLEventCreate` ([1370](#))

### 37.9.16 basiceventdestroy

Synopsis: Obsolete. Don't use

Declaration: `procedure basiceventdestroy(state: PEventState)`

Visibility: default

Description: `basiceventdestroy` is obsolete. Use `RTLEventDestroy` ([1370](#)) instead.

See also: `RTLEventDestroy` ([1370](#))

### 37.9.17 basiceventResetEvent

Synopsis: Obsolete. Don't use

Declaration: `procedure basiceventResetEvent(state: PEventState)`

Visibility: default

Description: `basiceventResetEvent` is obsolete. Use `RTLEventResetEvent` ([1370](#)) instead.

See also: `RTLEventResetEvent` ([1370](#))

### 37.9.18 basiceventSetEvent

Synopsis: Obsolete. Don't use

Declaration: `procedure basiceventSetEvent(state: PEventState)`

Visibility: default

Description: `basiceventSetEvent` is obsolete. Use `RTLEventSetEvent` ([1371](#)) instead.

See also: `RTLEventSetEvent` ([1371](#))

### 37.9.19 basiceventWaitFor

Synopsis: Obsolete. Don't use

Declaration: `function basiceventWaitFor(Timeout: Cardinal;state: PEventState)  
  : LongInt`

Visibility: default

Description: `basiceventwaitfor` is obsolete. Use `RTLEventWaitFor` ([1371](#)) instead.

See also: `RTLEventWaitFor` ([1371](#))

### 37.9.20 BeginThread

Synopsis: Start a new thread.

Declaration: 

```
function BeginThread(sa: Pointer;stacksize: SizeUInt;
                    ThreadFunction: TThreadFunc;p: pointer;
                    creationFlags: DWord;var ThreadId: TThreadID)
                    : TThreadID
function BeginThread(ThreadFunction: TThreadFunc) : TThreadID
function BeginThread(ThreadFunction: TThreadFunc;p: pointer) : TThreadID
function BeginThread(ThreadFunction: TThreadFunc;p: pointer;
                    var ThreadId: TThreadID) : TThreadID
function BeginThread(ThreadFunction: TThreadFunc;p: pointer;
                    var ThreadId: TThreadID;const stacksize: SizeUInt)
                    : TThreadID
```

Visibility: default

Description: `BeginThread` starts a new thread and executes `ThreadFunction` in the new thread. If `P` is specified, then it is passed to `ThreadFunction`. If `ThreadId` is specified, it is filled with the thread ID of the newly started thread. If `StackSize` is specified, it is set as the stack size for the new thread. If none is specified, a default stack size of 4MiB is used.

The function returns the thread handle (or ID, on Linux) on success, or 0 if an error occurred. Note that the thread ID and handle are the same on unix processes, and that the thread ID and thread handle are different on windows systems.

Errors: On error, the value "0" is returned.

See also: `EndThread` ([1284](#))

### 37.9.21 BEtoN

Synopsis: Convert Big Endian-ordered integer to Native-ordered integer

Declaration: 

```
function BEtoN(const AValue: SmallInt) : SmallInt
function BEtoN(const AValue: Word) : Word
function BEtoN(const AValue: LongInt) : LongInt
function BEtoN(const AValue: DWord) : DWord
function BEtoN(const AValue: Int64) : Int64
function BEtoN(const AValue: QWord) : QWord
```

Visibility: default

Description: `BEtoN` will rearrange the bytes in a Big-Endian number to the native order for the current processor. That is, for a big-endian processor, it will do nothing, and for a little-endian processor, it will invert the order of the bytes.

See also: `LEtoN` ([1318](#)), `NtoBE` ([1323](#)), `NtoLE` ([1324](#))

### 37.9.22 binStr

Synopsis: Convert integer to string with binary representation.

Declaration: 

```
function binStr(Val: LongInt;cnt: Byte) : shortstring
function binStr(Val: Int64;cnt: Byte) : shortstring
function binStr(Val: qword;cnt: Byte) : shortstring
```

Visibility: default

**Description:** `BinStr` returns a string with the binary representation of `Value`. The string has at most `cnt` characters. (i.e. only the `cnt` rightmost bits are taken into account) To have a complete representation of any longint-type value, 32 bits are needed, i.e. `cnt=32`

Errors: None.

See also: `Str` ([1383](#)), `Val` ([1399](#)), `HexStr` ([1303](#)), `OctStr` ([1324](#))

**Listing:** `./refex/ex82.pp`

---

```

Program example82;

{ Program to demonstrate the BinStr function }

Const Value = 45678;

Var I : longint;

begin
  For I:=8 to 20 do
    WriteLn ( BinStr(Value,I):20);
end.

```

---

### 37.9.23 BlockRead

Synopsis: Read data from an untyped file into memory

**Declaration:**

```

procedure BlockRead(var f: File;var Buf;count: Int64;var Result: Int64)
procedure BlockRead(var f: File;var Buf;count: LongInt;
                    var Result: LongInt)
procedure BlockRead(var f: File;var Buf;count: Cardinal;
                    var Result: Cardinal)
procedure BlockRead(var f: File;var Buf;count: Word;var Result: Word)
procedure BlockRead(var f: File;var Buf;count: Word;var Result: Integer)
procedure BlockRead(var f: File;var Buf;count: Int64)

```

Visibility: default

**Description:** `Blockread` reads `count` or less records from file `F`. A record is a block of bytes with size specified by the `Rewrite` ([1365](#)) or `Reset` ([1364](#)) statement. The result is placed in `Buffer`, which must contain enough room for `Count` records. The function cannot read partial records. If `Result` is specified, it contains the number of records actually read. If `Result` isn't specified, and less than `Count` records were read, a run-time error is generated. This behavior can be controlled by the `{SI}` switch.

**Errors:** Depending on the state of the `{SI}` switch, a runtime error can be generated if there is an error. In the `{SI-}` state, use `IOResult` to check for errors.

See also: `Blockwrite` ([1267](#)), `Close` ([1269](#)), `Reset` ([1364](#)), `Assign` ([1262](#))

**Listing:** `./refex/ex6.pp`

---

```

Program Example6;

{ Program to demonstrate the BlockRead and BlockWrite functions. }

```

---

---

```

Var Fin, fout : File;
    NumRead, NumWritten : Word;
    Buf : Array[1..2048] of byte;
    Total : Longint;

begin
    Assign (Fin, Paramstr(1));
    Assign (Fout, Paramstr(2));
    Reset (Fin, 1);
    Rewrite (Fout, 1);
    Total:=0;
    Repeat
        BlockRead (Fin, buf, Sizeof(buf), NumRead);
        BlockWrite (Fout, Buf, NumRead, NumWritten);
        inc (Total, NumWritten);
    Until (NumRead=0) or (NumWritten<>NumRead);
    Write ('Copied ', Total, ' bytes from file ', paramstr(1));
    Writeln (' to file ', paramstr(2));
    close(fin);
    close(fout);
end.

```

---

### 37.9.24 BlockWrite

Synopsis: Write data from memory to an untyped file

Declaration: `procedure BlockWrite(var f: File; const Buf; Count: Int64; var Result: Int64)`  
`procedure BlockWrite(var f: File; const Buf; Count: LongInt; var Result: LongInt)`  
`procedure BlockWrite(var f: File; const Buf; Count: Cardinal; var Result: Cardinal)`  
`procedure BlockWrite(var f: File; const Buf; Count: Word; var Result: Word)`  
`procedure BlockWrite(var f: File; const Buf; Count: Word; var Result: Integer)`  
`procedure BlockWrite(var f: File; const Buf; Count: LongInt)`

Visibility: default

Description: `BlockWrite` writes `count` records from `buffer` to the file `F`. A record is a block of bytes with size specified by the `Rewrite` (1365) or `Reset` (1364) statement. If the records couldn't be written to disk, a run-time error is generated. This behavior can be controlled by the `{SI}` switch.

Errors: Depending on the state of the `{SI}` switch, a runtime error can be generated if there is an error. In the `{SI-}` state, use `IOResult` to check for errors.

See also: `Blockread` (1266), `Close` (1269), `Rewrite` (1365), `Assign` (1262)

### 37.9.25 Break

Synopsis: Exit current loop construct.

Declaration: `procedure Break`

Visibility: default

**Description:** `Break` jumps to the statement following the end of the current repetitive statement. The code between the `Break` call and the end of the repetitive statement is skipped. The condition of the repetitive statement is NOT evaluated.

This can be used with `For`, `var{repeat}` and `While` statements.

Note that while this is a procedure, `Break` is a reserved word and hence cannot be redefined.

**Errors:** None.

See also: `Continue` ([1276](#)), `Exit` ([1289](#))

**Listing:** `./refex/ex87.pp`

---

**Program** `Example87`;

*{ Program to demonstrate the Break function. }*

```

Var I : longint;

begin
  I:=0;
  While I<10 Do
    begin
      Inc(I);
      If I>5 Then
        Break;
      Writeln (i);
    end;
  I:=0;
  Repeat
    Inc(I);
    If I>5 Then
      Break;
    Writeln (i);
  Until I>=10;
  For I:=1 to 10 do
    begin
      If I>5 Then
        Break;
      Writeln (i);
    end;
end.
```

---

### 37.9.26 `chdir`

**Synopsis:** Change current working directory.

**Declaration:** `procedure chdir(const s: String);` Overload

**Visibility:** default

**Description:** `Chdir` changes the working directory of the process to `S`.

**Errors:** Depending on the state of the `{SI}` switch, a runtime error can be generated if there is an error. In the `{SI-}` state, use `IOResult` to check for errors.

See also: `Mkdir` ([1322](#)), `Rmdir` ([1366](#))

**Listing:** ./refex/ex7.pp

**Program** Example7;

---

```

        { Program to demonstrate the ChDir function. }

begin
  {$I-}
  ChDir (ParamStr(1));
  if IOResult <> 0 then
    Writeln ('Cannot change to directory : ', paramstr (1));
end.

```

---

### 37.9.27 chr

Synopsis: Convert byte value to character value

Declaration: `function chr(b: Byte) : Char`

Visibility: default

Description: Chr returns the character which has ASCII value X.

Historical note:

Originally, Pascal did not have typecasts and chr was a necessary function in order to do certain operations on ASCII values of characters. With the arrival of typecasting a generic approach became possible, making chr mostly obsolete. However, chr is not considered deprecated and remains in wide use today.

Errors: None.

See also: Ord ([1354](#)), Str ([1383](#))

**Listing:** ./refex/ex8.pp

**Program** Example8;

---

```

        { Program to demonstrate the Chr function. }

begin
  Write (chr(10),chr(13)); { The same effect as Writeln; }
end.

```

---

### 37.9.28 Close

Synopsis: Close a file

Declaration: `procedure Close(var f: File)`  
`procedure Close(var t: Text)`

Visibility: default

Description: Close flushes the buffer of the file F and closes F. After a call to Close, data can no longer be read from or written to F. To reopen a file closed with Close, it isn't necessary to assign the file again. A call to Reset ([1364](#)) or Rewrite ([1365](#)) is sufficient.

**Errors:** Depending on the state of the `{ $I }` switch, a runtime error can be generated if there is an error. In the `{ $I- }` state, use `IOResult` to check for errors.

See also: [Assign \(1262\)](#), [Reset \(1364\)](#), [Rewrite \(1365\)](#), [Flush \(1296\)](#)

**Listing:** `./refex/ex9.pp`

---

**Program** `Example9;`

```
{ Program to demonstrate the Close function. }

Var F : text;

begin
  Assign (f, 'Test.txt');
  ReWrite (F);
  WriteLn (F, 'Some text written to Test.txt');
  close (f); { Flushes contents of buffer to disk,
              closes the file. Omitting this may
              cause data NOT to be written to disk.}
end.
```

---

### 37.9.29 CloseThread

**Synopsis:** Close a thread and free up resources used by the thread

**Declaration:** `function CloseThread(threadHandle: TThreadID) : DWord`

**Visibility:** `default`

**Description:** `CloseThread` must be called on any thread started with `BeginThread (1265)`. It must be called after the thread has ended (either by exiting the thread function or after calling `EndThread (1284)`).

**Errors:** If no threadmanager is installed, an exception may be raised or runtime error 232 may occur if no exceptions are used.

See also: [BeginThread \(1265\)](#), [EndThread \(1284\)](#)

### 37.9.30 CompareByte

**Synopsis:** Compare 2 memory buffers byte per byte

**Declaration:** `function CompareByte(const buf1;const buf2;len: SizeInt) : SizeInt`

**Visibility:** `default`

**Description:** `CompareByte` compares two memory regions `buf1`, `buf2` on a byte-per-byte basis for a total of `len` bytes.

The function returns one of the following values:

**less than 0** if `buf1` and `buf2` contain different bytes in the first `len` bytes, and the first such byte is smaller in `buf1` than the byte at the same position in `buf2`.

**0** if the first `len` bytes in `buf1` and `buf2` are equal.

**greater than 0** if `buf1` and `buf2` contain different bytes in the first `len` bytes, and the first such byte is larger in `buf1` than the byte at the same position in `buf2`.



Errors: None.

See also: CompareChar ([1271](#)), CompareChar0 ([1273](#)), CompareWord ([1274](#)), CompareDWord ([1273](#))

**Listing:** ./refex/ex99.pp

---

**Program** Example99;

*{ Program to demonstrate the CompareByte function. }*

**Const**

    ArraySize      = 100;  
    HalfArraySize = ArraySize **Div** 2;

**Var**

    Buf1, Buf2 : **Array**[1..ArraySize] **of** byte;  
    I : longint;

**Procedure** CheckPos(Len : Longint);

**Begin**

**Write**( 'First ', Len, ' positions are ' );  
    **if** CompareByte( Buf1, Buf2, Len ) <> 0 **then**  
        **Write**( 'NOT ' );  
    **Writeln**( 'equal' );  
**end**;

**begin**

**For** I:=1 **to** ArraySize **do**  
        **begin**  
            Buf1[ I ]:= I;  
            **If** I<=HalfArraySize **Then**  
                Buf2[ I ]:= I  
            **else**  
                Buf2[ I ]:= HalfArraySize-I;  
            **end**;  
        CheckPos( HalfArraySize **div** 2 );  
        CheckPos( HalfArraySize );  
        CheckPos( HalfArraySize+1 );  
        CheckPos( HalfArraySize + HalfArraySize **Div** 2 );  
    **end**.

---

### 37.9.31 CompareChar

Synopsis: ompare 2 memory buffers character per character

Declaration: function CompareChar(const buf1;const buf2;len: SizeInt) : SizeInt

Visibility: default

Description: CompareChar compares two memory regions buf1,buf2 on a character-per-character basis for a total of len characters.

The CompareChar0 variant compares len bytes, or until a zero character is found.

The function returns one of the following values:

**-If** buf1 and buf2 contain different characters in the first len positions, and the first such character is smaller in buf1 than the character at the same position in buf2.

**0If** the first len characters in buf1 and buf2 are equal.

**1If** buf1 and buf2 contain different characters in the first len positions, and the first such character is larger in buf1 than the character at the same position in buf2.

Errors: None.

See also: CompareByte (1270), CompareChar0 (1273), CompareWord (1274), CompareDWord (1273)

**Listing:** ./refex/ex100.pp

---

**Program** Example100;

*{ Program to demonstrate the CompareChar function. }*

**Const**

    ArraySize      = 100;  
    HalfArraySize = ArraySize Div 2;

**Var**

    Buf1, Buf2 : **Array**[1..ArraySize] **of** char;  
    I : longint;

**Procedure** CheckPos(Len : Longint);

**Begin**

**Write**('First ', Len, ' characters are ');  
    **if** CompareChar(Buf1, Buf2, Len) <> 0 **then**  
        **Write**('NOT ');  
        **Writeln**('equal');  
**end**;

**Procedure** CheckNullPos(Len : Longint);

**Begin**

**Write**('First ', Len, ' non-null characters are ');  
    **if** CompareChar0(Buf1, Buf2, Len) <> 0 **then**  
        **Write**('NOT ');  
        **Writeln**('equal');  
**end**;

**begin**

**For** I:=1 **to** ArraySize **do**  
        **begin**  
            Buf1[I]:=chr(I);  
            **If** I<=HalfArraySize **Then**  
                Buf2[I]:=chr(I)  
            **else**  
                Buf2[I]:=chr(HalfArraySize-I);  
            **end**;  
        CheckPos(HalfArraySize div 2);  
        CheckPos(HalfArraySize);  
        CheckPos(HalfArraySize+1);  
        CheckPos(HalfArraySize + HalfArraySize Div 2);  
    **For** I:=1 **to** 4 **do**  
        **begin**  
            buf1[Random(ArraySize)+1]:=Chr(0);

---

```

    buf2[Random(ArraySize)+1]:=Chr(0);
end;

    Randomize;
    CheckNullPos(HalfArraySize div 2);
    CheckNullPos(HalfArraySize);
    CheckNullPos(HalfArraySize+1);
    CheckNullPos(HalfArraySize + HalfArraySize Div 2);
end.

```

---

### 37.9.32 CompareChar0

Synopsis: Compare two buffers character by character till a null-character is reached.

Declaration: `function CompareChar0(const buf1;const buf2;len: SizeInt) : SizeInt`

Visibility: default

Description: `CompareChar0` compares 2 buffers `buf1` and `buf2` for a maximum length of `len` or till a null character is reached in either buffer. The result depends on the contents of the buffers:

< 0 If `buf1` contains a character less than the corresponding character in `buf2`.  
 0 If both buffers are equal  
 > 0 If `buf1` contains a character greater than the corresponding character in `buf2`.

Errors: None.

See also: `CompareByte` ([1270](#)), `CompareChar` ([1271](#)), `CompareDWord` ([1273](#)), `CompareWord` ([1274](#))

### 37.9.33 CompareDWord

Synopsis: Compare 2 memory buffers DWord per DWord

Declaration: `function CompareDWord(const buf1;const buf2;len: SizeInt) : SizeInt`

Visibility: default

Description: `CompareDWord` compares two memory regions `buf1`, `buf2` on a DWord-per-DWord basis for a total of `len` DWords. (A DWord is 4 bytes).

The function returns one of the following values:

-1 if `buf1` and `buf2` contain different DWords in the first `len` DWords, and the first such DWord is smaller in `buf1` than the DWord at the same position in `buf2`.  
 0 if the first `len` DWords in `buf1` and `buf2` are equal.  
 1 if `buf1` and `buf2` contain different DWords in the first `len` DWords, and the first such DWord is larger in `buf1` than the DWord at the same position in `buf2`.

Errors: None.

See also: `CompareChar` ([1271](#)), `CompareByte` ([1270](#)), `CompareWord` ([1274](#))

Listing: `./refex/ex101.pp`

---

**Program** Example101;

*{ Program to demonstrate the CompareDWord function. }*

**Const**

ArraySize = 100;  
HalfArraySize = ArraySize Div 2;

**Var**

Buf1, Buf2 : **Array**[1..ArraySize] **of** Dword;  
I : longint;

**Procedure** CheckPos(Len : Longint);

**Begin**

Write('First ', Len, ' DWords are ');  
if CompareDWord(Buf1, Buf2, Len) <> 0 then  
Write('NOT ');  
Writeln('equal');  
end;

**begin**

For I:=1 to ArraySize do  
begin  
Buf1[I]:=I;  
If I<=HalfArraySize Then  
Buf2[I]:=I  
else  
Buf2[I]:=HalfArraySize-I;  
end;  
CheckPos(HalfArraySize div 2);  
CheckPos(HalfArraySize);  
CheckPos(HalfArraySize+1);  
CheckPos(HalfArraySize + HalfArraySize Div 2);  
end.

---

### 37.9.34 CompareWord

**Synopsis:** Compare 2 memory buffers word per word

**Declaration:** function CompareWord(const buf1;const buf2;len: SizeInt) : SizeInt

**Visibility:** default

**Description:** CompareWord compares two memory regions buf1,buf2 on a Word-per-Word basis for a total of len Words. (A Word is 2 bytes).

The function returns one of the following values:

-1if buf1 and buf2 contain different Words in the first len Words, and the first such Word is smaller in buf1 than the Word at the same position in buf2.

0if the first len Words in buf1 and buf2 are equal.

1if buf1 and buf2 contain different Words in the first len Words, and the first such Word is larger in buf1 than the Word at the same position in buf2.

Errors: None.

See also: [CompareChar \(1271\)](#), [CompareByte \(1270\)](#), [CompareDWord \(1273\)](#)

**Listing:** ./refex/ex102.pp

---

**Program** Example102;

*{ Program to demonstrate the CompareWord function. }*

**Const**

    ArraySize      = 100;  
    HalfArraySize = ArraySize **Div** 2;

**Var**

    Buf1, Buf2 : **Array**[1..ArraySize] **of** Word;  
    I : longint;

**Procedure** CheckPos(Len : Longint);

**Begin**

**Write**( 'First ', Len, ' words are ' );  
    **if** CompareWord( Buf1, Buf2, Len ) <> 0 **then**  
        **Write**( 'NOT ' );  
        **Writeln**( 'equal' );  
    **end**;

**begin**

**For** I:=1 **to** ArraySize **do**  
        **begin**  
            Buf1[ I ]:= I;  
            **If** I<=HalfArraySize **Then**  
                Buf2[ I ]:= I  
            **else**  
                Buf2[ I ]:= HalfArraySize-I;  
            **end**;  
        CheckPos( HalfArraySize **div** 2 );  
        CheckPos( HalfArraySize );  
        CheckPos( HalfArraySize+1 );  
        CheckPos( HalfArraySize + HalfArraySize **Div** 2 );  
    **end**.

---

### 37.9.35 Concat

Synopsis: Append one string to another.

Declaration: `function Concat(const S1: String; const S2: String; const S3: String;  
                                  const Sn: String) : String`

Visibility: default

Description: `Concat` concatenates the strings S1, S2 etc. to one long string. The resulting string is truncated at a length of 255 bytes. The same operation can be performed with the + operation.

Errors: None.

See also: [Copy \(1277\)](#), [Delete \(1280\)](#), [Insert \(1312\)](#), [Pos \(1356\)](#), [Length \(1317\)](#)

**Listing:** ./refex/ex10.pp

**Program** Example10;

---

```
{ Program to demonstrate the Concat function. }
Var
  S : String;

begin
  S:=Concat('This can be done',' Easier ','with the + operator !');
end.
```

---

### 37.9.36 Continue

Synopsis: Continue with next loop cycle.

Declaration: procedure Continue

Visibility: default

Description: Continue jumps to the end of the current repetitive statement. The code between the Continue call and the end of the repetitive statement is skipped. The condition of the repetitive statement is then checked again.

This can be used with For, repeat and While statements.

Note that while this is a procedure, Continue is a reserved word and hence cannot be redefined.

Errors: None.

See also: Break ([1267](#)), Exit ([1289](#))

**Listing:** ./refex/ex86.pp

**Program** Example86;

---

```
{ Program to demonstrate the Continue function. }

Var I : longint;

begin
  I:=0;
  While I<10 Do
    begin
      Inc(I);
      If I<5 Then
        Continue;
      Writeln (i);
    end;
  I:=0;
  Repeat
    Inc(I);
    If I<5 Then
      Continue;
    Writeln (i);
  Until I>=10;
  For I:=1 to 10 do
    begin
      If I<5 Then
```

---

```

    Continue ;
    Writeln (i);
end;
end.
```

---

### 37.9.37 Copy

Synopsis: Copy part of a string.

Declaration: `function Copy(S: AStringType; Index: Integer; Count: Integer) : String`  
`function Copy(A: DynArrayType; Index: Integer; Count: Integer) : DynArray`

Visibility: default

Description: `Copy` returns a string which is a copy of the `Count` characters in `S`, starting at position `Index`. If `Count` is larger than the length of the string `S`, the result is truncated. If `Index` is larger than the length of the string `S`, then an empty string is returned. `Index` is 1-based.

For dynamical arrays, `Copy` returns a new dynamical array of the same type as the original one, and copies `Count` elements from the old array, starting at position `Index`.

Errors: None.

See also: `Delete` ([1280](#)), `Insert` ([1312](#)), `Pos` ([1356](#))

**Listing:** `./refex/ex11.pp`

---

**Program** `Example11`;

*{ Program to demonstrate the Copy function. }*

**Var** `S, T : String`;

**begin**

`T := '1234567' ;`

`S := Copy (T, 1, 2); { S := '12' }`

`S := Copy (T, 4, 2); { S := '45' }`

`S := Copy (T, 4, 8); { S := '4567' }`

**end.**

---

### 37.9.38 cos

Synopsis: Calculate cosine of angle

Declaration: `function cos(d: ValReal) : ValReal`

Visibility: default

Description: `Cos` returns the cosine of `X`, where `X` is an angle, in radians. If the absolute value of the argument is larger than  $2\hat{6}3$ , then the result is undefined.

Errors: None.

See also: `Arctan` ([1261](#)), `Sin` ([1380](#))

**Listing:** `./refex/ex12.pp`

---

```

Program Example12;

{ Program to demonstrate the Cos function. }

    Var R : Real;

begin
    R:=Cos(Pi);    { R:=-1 }
    R:=Cos(Pi/2); { R:=0 }
    R:=Cos(0);     { R:=1 }
end.

```

---

### 37.9.39 Cseg

Synopsis: Return code segment

Declaration: `function Cseg : Word`

Visibility: default

Description: `Cseg` returns the Code segment register. In Free Pascal, it returns always a zero, since Free Pascal is a 32 bit compiler.

Errors: None.

See also: `Dseg` ([1282](#)), `Seg` ([1374](#)), `Ofs` ([1325](#)), `Ptr` ([1358](#))

**Listing:** `./refex/ex13.pp`

---

```

Program Example13;

{ Program to demonstrate the CSeg function. }

var W : word;

begin
    W:=CSeg; {W:=0, provided for compatibility,
              FPC is 32 bit.}
end.

```

---

### 37.9.40 Dec

Synopsis: Decrease value of variable

Declaration: `procedure Dec(var X: TOrdinal)`  
`procedure Dec(var X: TOrdinal;Decrement: TOrdinal)`

Visibility: default

Description: `Dec` decreases the value of `X` with `Decrement`. If `Decrement` isn't specified, then 1 is taken as a default.

Errors: A range check can occur, or an underflow error, if an attempt it made to decrease `X` below its minimum value.

See also: `Inc` ([1306](#))



**Listing:** ./refex/ex14.pp

**Program** Example14;

*{ Program to demonstrate the Dec function. }*

**Var**

I : Integer;  
L : Longint;  
W : Word;  
B : Byte;  
Si : ShortInt;

**begin**

I:=1;  
L:=2;  
W:=3;  
B:=4;  
Si:=5;  
**Dec** (i); { i:=0 }  
**Dec** (L,2); { L:=0 }  
**Dec** (W,2); { W:=1 }  
**Dec** (B,-2); { B:=6 }  
**Dec** (Si,0); { Si:=5 }

**end.**

### 37.9.41 DefaultAnsi2UnicodeMove

Synopsis: Standard widestring manager callback

**Declaration:** procedure DefaultAnsi2UnicodeMove(source: PChar; var dest: unicodestring;  
len: SizeInt)

Visibility: default

**Description:** DefaultAnsi2UnicodeMove is the standard callback used for the widestring manager when an ansistring must be converted to a unicodestring. It simply copies over all characters from the ansistring to the unicodestring, no conversion whatsoever is performed.

Errors:

### 37.9.42 DefaultAnsi2WideMove

Synopsis: Standard implementation of Ansi to Widestring conversion routine

**Declaration:** procedure DefaultAnsi2WideMove(source: PChar; var dest: widestring;  
len: SizeInt)

Visibility: default

**Description:** DefaultAnsi2WideMove simply copies each character of the null-terminated ansi-string Source to the corresponding WideChar in Dest. At most Len characters will be copied.

Errors: None.

See also: DefaultWide2AnsiMove ([1280](#))

### 37.9.43 DefaultUnicode2AnsiMove

Synopsis: Standard widestring manager callback

Declaration: `procedure DefaultUnicode2AnsiMove(source: PUnicodeChar;  
var dest: ansistring; len: SizeInt)`

Visibility: default

Description: `DefaultUnicode2AnsiMove` is the standard callback used for the widestring manager when a unicode string must be converted to an ansistring. It replaces all words with value < 256 with their value as ASCII code.

Errors: None.

See also: `WidestringManager` ([1257](#))

### 37.9.44 DefaultWide2AnsiMove

Synopsis: Standard implementation of Widestring to Ansi conversion routine

Declaration: `procedure DefaultWide2AnsiMove(source: PWideChar; var dest: ansistring;  
len: SizeInt)`

Visibility: default

Description: `DefaultWide2AnsiMove` simply copies each character from `Source` having an ordinal value of less than 255 to the corresponding character in `Dest`. Characters having an ordinal value larger than 255 will be replaced by question marks. At most `Len` characters will be copied.

Errors: None.

See also: `DefaultAnsi2WideMove` ([1279](#))

### 37.9.45 Delete

Synopsis: Delete part of a string.

Declaration: `procedure Delete(var s: shortstring; index: SizeInt; count: SizeInt)  
procedure Delete(var S: AnsiString; Index: SizeInt; Size: SizeInt)  
procedure Delete(var S: UnicodeString; Index: SizeInt; Size: SizeInt)  
procedure Delete(var S: WideString; Index: SizeInt; Size: SizeInt)`

Visibility: default

Description: `Delete` removes `Count` characters from string `S`, starting at position `Index`. All characters after the deleted characters are shifted `Count` positions to the left, and the length of the string is adjusted.

Errors: None.

See also: `Copy` ([1277](#)), `Pos` ([1356](#)), `Insert` ([1312](#))

Listing: `./refex/ex15.pp`

Program `Example15`;

*{ Program to demonstrate the Delete function. }*

**Var**

---

```

S : String;

begin
  S:= 'This is not easy !';
      Delete (S,9,4); { S:= 'This is easy !' }
end.

```

---

### 37.9.46 Dispose

Synopsis: Free dynamically allocated memory

Declaration: `procedure Dispose(P: Pointer)`  
`procedure Dispose(P: TypedPointer;Des: TProcedure)`

Visibility: default

Description: The first form `Dispose` releases the memory allocated with a call to `New` ([1323](#)). The pointer `P` must be typed. The released memory is returned to the heap.

The second form of `Dispose` accepts as a first parameter a pointer to an object type, and as a second parameter the name of a destructor of this object. The destructor will be called, and the memory allocated for the object will be freed.

Errors: An runtime error will occur if the pointer doesn't point to a location in the heap.

See also: `New` ([1323](#)), `Getmem` ([1299](#)), `Freemem` ([1297](#))

**Listing:** `./refex/ex16.pp`

---

**Program** `Example16;`

*{ Program to demonstrate the Dispose and New functions. }*

**Type** `SS = String[20];`

```

AnObj = Object
  I : integer;
  Constructor Init;
  Destructor Done;
end;

```

**Var**

```

P : ^SS;
T : ^AnObj;

```

**Constructor** `Anobj.Init;`

**begin**

```

  WriteLn ('Initializing an instance of AnObj !');
end;

```

**Destructor** `AnObj.Done;`

**begin**

```

  WriteLn ('Destroying an instance of AnObj !');
end;

```

**begin**

---

```

New (P);
P^:= 'Hello , World !';
      Dispose (P);
{ P is undefined from here on !}
New(T, Init);
T^.i:=0;
Dispose (T, Done);
end.

```

---

### 37.9.47 DoneCriticalSection

Synopsis: Clean up a critical section.

Declaration: `procedure DoneCriticalSection(var cs: TRTLCriticalSection)`

Visibility: default

Description: `DoneCriticalSection` cleans up the critical section CS. After a call to `DoneCriticalSection`, the critical section can no longer be used with `EnterCriticalSection` ([1284](#)) or `LeaveCriticalSection` ([1317](#)), unless it is again initialized with `InitCriticalSection` ([1311](#))

See also: `InitCriticalSection` ([1311](#)), `EnterCriticalSection` ([1284](#)), `LeaveCriticalSection` ([1317](#))

### 37.9.48 DoneThread

Synopsis: End the current thread

Declaration: `procedure DoneThread`

Visibility: default

Description: `DoneThread` should be used to end the current thread. It performs the necessary housekeeping before actually ending the thread. Using the operating system calls to end the thread may result in data corruption or memory leaks.

See also: `BeginThread` ([1265](#))

### 37.9.49 Dseg

Synopsis: Return data segment

Declaration: `function Dseg : Word`

Visibility: default

Description: `Dseg` returns the data segment register. In Free Pascal, it returns always a zero, since Free Pascal is a 32 bit compiler.

Errors: None.

See also: `Cseg` ([1278](#)), `Seg` ([1374](#)), `Ofs` ([1325](#)), `Ptr` ([1358](#))

**Listing:** `./refex/ex17.pp`

---

```

Program Example17;

{ Program to demonstrate the DSeg function. }

Var
  W : Word;

      begin
    W:=DSeg; {W:=0, This function is provided for compatibility,
              FPC is a 32 bit comiler.}
end.

```

---

### 37.9.50 DumpExceptionBackTrace

Synopsis: Create backtrace

Declaration: `procedure DumpExceptionBackTrace(var f: text)`

Visibility: default

Description: `DumpExceptionBackTrace` writes a backtrace of the current exception to the file `f`. If no exception is currently being raised, nothing is written. As much frames as available are written. If debug info is available, then file names and line numbers will be written as well.

Errors: No check is done to see whether `f` is opened for writing.

See also: `dump_stack` ([1283](#))

### 37.9.51 Dump\_Stack

Synopsis: Dump stack to the given text file.

Declaration: `procedure Dump_Stack(var f: text; bp: pointer)`

Visibility: default

Description: `Dump_Stack` prints a stack dump to the file `f`, with base frame pointer `bp`

Errors: The file `f` must be opened for writing or an error will occur.

See also: `get_caller_addr` ([1302](#)), `get_caller_frame` ([1302](#)), `get_frame` ([1303](#))

### 37.9.52 DynArraySetLength

Synopsis: Set the length of a dynamic array

Declaration: `procedure DynArraySetLength(var a: Pointer; typeInfo: Pointer;  
dimCnt: SizeInt; lengthVec: PSizeInt)`

Visibility: default

Description: `DynArraySetLength` sets the length of the dynamical array `a` to the first `dimCnt` lengths specified in the array `lengthVec`. The dynamical array type is described in `typeInfo` which points to a record of type `TDynArrayTypeInfo` ([1244](#))

It should never be necessary to call this function directly, the standard `SetLength` ([1375](#)) function should be used instead.

Errors: If an invalid pointer is specified, an error may occur.

See also: [SetLength \(1375\)](#), [tdynarraytypeinfo \(1244\)](#)

### 37.9.53 EndThread

Synopsis: End the current thread.

Declaration: `procedure EndThread(ExitCode: DWord)`  
`procedure EndThread`

Visibility: default

Description: `EndThread` ends the current thread. If `ExitCode` is supplied, it is returned as the exit code for the thread to a function waiting for the thread to terminate ([WaitForThreadTerminate \(1401\)](#)). If it is omitted, zero is used.

This function does not return.

See also: [WaitForThreadTerminate \(1401\)](#), [BeginThread \(1265\)](#)

### 37.9.54 EnterCriticalSection

Synopsis: Enter a critical section

Declaration: `procedure EnterCriticalSection(var cs: TRTLCriticalSection)`

Visibility: default

Description: `EnterCriticalSection` will suspend the current thread if another thread has currently entered the critical section. When the other thread has left the critical section (through `LeaveCriticalSection (1317)`), the current thread resumes execution. The result is that only 1 thread is executing code which is protected by a `EnterCriticalSection` and `LeaveCriticalSection` pair.

The critical section must have been initialized with `InitCriticalSection (1311)` prior to a call to `EnterCriticalSection`.

A call to `EnterCriticalSection` must always be matched by a call to `LeaveCriticalSection (1317)`. To avoid problems, it is best to include the code to be execute in a `try...finally` block, as follows:

```
EnterCriticalSection(Section);
Try
    // Code to be protected goes here.
Finally
    LeaveCriticalSection(Section);
end;
```

For performance reasons it is best to limit the code between the entering and leaving of a critical section as short as possible.

See also: [InitCriticalSection \(1311\)](#), [DoneCriticalSection \(1282\)](#), [LeaveCriticalSection \(1317\)](#)

### 37.9.55 EnumResourceLanguages

Synopsis: Enumerate available languages for a resource of given type and name

Declaration: `function EnumResourceLanguages (ModuleHandle: TFPResourceHMODULE;  
ResourceType: PChar; ResourceName: PChar;  
EnumFunc: EnumResLangProc; lParam: PtrInt)  
: LongBool`

Visibility: default

Description: `EnumResourceLanguages` enumerates the available languages for a resource of given `ResourceName` and type `ResourceType` in the module `ModuleHandle`. For each language available, it calls `EnumFunc` and passes it `ModuleHandle`, the type of the resource `ResourceType`, the name of the resource `ResourceName`, the language ID, and `lParam`. It returns `False` if no resources are available for the specified resource type and module, or `True` if there are resources available.

Errors: None.

See also: `EnumResourceTypes` ([1285](#)), `EnumResourceNames` ([1285](#)), `EnumResourceLanguages` ([1285](#))

### 37.9.56 EnumResourceNames

Synopsis: Enumerate available resource names for a specified resource type

Declaration: `function EnumResourceNames (ModuleHandle: TFPResourceHMODULE;  
ResourceType: PChar; EnumFunc: EnumResNameProc;  
lParam: PtrInt) : LongBool`

Visibility: default

Description: `EnumResourceNames` enumerates the names of all resources of type `ResourceType` in the module `ModuleHandle`. For each resource available it calls `EnumFunc` and passes it `ModuleHandle`, the type of the resource `ResourceType`, the name of the resource, and `lParam`. It returns `False` if no resources are available for the specified resource type and module, or `True` if there are resources available.

Errors: None.

See also: `EnumResourceTypes` ([1285](#)), `EnumResourceLanguages` ([1285](#))

### 37.9.57 EnumResourceTypes

Synopsis: Enumerate available resource types

Declaration: `function EnumResourceTypes (ModuleHandle: TFPResourceHMODULE;  
EnumFunc: EnumResTypeProc; lParam: PtrInt)  
: LongBool`

Visibility: default

Description: `EnumResourceTypes` enumerates the types of all resources in the module `ModuleHandle`. For each resource available it calls `EnumFunc` and passes it `ModuleHandle`, the type of the resource, and `lParam`. It returns `False` if no resources are available for the specified module, or `True` if there are resources available.

Errors: None.

See also: `EnumResourceNames` ([1285](#)), `EnumResourceLanguages` ([1285](#))

### 37.9.58 EOF

Synopsis: Check for end of file

Declaration: `function EOF(var f: File) : Boolean`  
`function EOF(var t: Text) : Boolean`  
`function EOF : Boolean`

Visibility: default

Description: `Eof` returns `True` if the file-pointer has reached the end of the file, or if the file is empty. In all other cases `Eof` returns `False`. If no file `F` is specified, standard input is assumed.

Note that calling this function may cause your program to wait: to determine whether you are at EOF, it is necessary to read data. If the file descriptor is not a real file (for instance for standard input or sockets), then this call may seem to hang the program while it is waiting for data to appear or for the file descriptor to be closed.

Errors: Depending on the state of the `{SI}` switch, a runtime error can be generated if there is an error. In the `{SI-}` state, use `IOResult` to check for errors.

See also: `Eoln` ([1286](#)), `Assign` ([1262](#)), `Reset` ([1364](#)), `Rewrite` ([1365](#))

**Listing:** `./refex/ex18.pp`

**Program** `Example18;`

*{ Program to demonstrate the Eof function. }*

**Var** `T1,T2 : text;`  
`C : Char;`

**begin**  
*{ Set file to read from. Empty means from standard input. }*  
`assign (t1,paramstr(1));`  
`reset (t1);`  
*{ Set file to write to. Empty means to standard output. }*  
`assign (t2,paramstr(2));`  
`rewrite (t2);`  
**While not eof**(t1) **do**  
  **begin**  
    `read (t1,C);`  
    `write (t2,C);`  
  **end;**  
  `Close (t1);`  
  `Close (t2);`  
**end.**

### 37.9.59 EOLn

Synopsis: Check for end of line

Declaration: `function EOLn(var t: Text) : Boolean`  
`function EOLn : Boolean`

Visibility: default

Description: `Eof` returns `True` if the file pointer has reached the end of a line, which is demarcated by a line-feed character (ASCII value 10), or if the end of the file is reached. In all other cases `Eof` returns `False`. If no file `F` is specified, standard input is assumed. It can only be used on files of type `Text`.



Errors: None.

See also: Eof ([1286](#)), Assign ([1262](#)), Reset ([1364](#)), Rewrite ([1365](#))

**Listing:** ./refex/ex19.pp

---

**Program** Example19;

```
{ Program to demonstrate the Eoln function. }

begin
  { This program waits for keyboard input. }
  { It will print True when an empty line is put in,
    and false when you type a non-empty line.
    It will only stop when you press enter.}
  While not Eoln do
    Writeln (eoln);
end.
```

---

### 37.9.60 Erase

Synopsis: Delete a file from disk

Declaration: `procedure Erase(var f: File)`  
`procedure Erase(var t: Text)`

Visibility: default

Description: Erase removes an unopened file from disk. The file should be assigned with Assign, but not opened with Reset or Rewrite

Errors: Depending on the state of the `{SI}` switch, a runtime error can be generated if there is an error. In the `{SI-}` state, use `IOResult` to check for errors.

See also: Assign ([1262](#))

**Listing:** ./refex/ex20.pp

---

**Program** Example20;

```
{ Program to demonstrate the Erase function. }

Var F : Text;

begin
  { Create a file with a line of text in it }
  Assign (F, 'test.txt');
  Rewrite (F);
  Writeln (F, 'Try and find this when I''m finished !');
  close (f);
  { Now remove the file }
  Erase (f);
end.
```

---

### 37.9.61 Error

Synopsis: Generate run-time error

Declaration: `procedure Error(RunTimeError: TRuntimeError)`

Visibility: default

Description: `Error` generates a run-time error with an exit code corresponding to `RunTimeError`. This function is implemented for Delphi compatibility, and is not used by the Free Pascal Run-Time Library.

See also: `RunError` ([1371](#)), `Halt` ([1303](#))

### 37.9.62 Exclude

Synopsis: Exclude element from a set if it is present.

Declaration: `procedure Exclude(var S: TSetType; E: TSetElement)`

Visibility: default

Description: `Exclude` removes `E` from the set `S` if it is included in the set. `E` should be of the same type as the base type of the set `S`.

Thus, the two following statements do the same thing:

```
S:=S-[E];
Exclude(S,E);
```

Errors: If the type of the element `E` is not equal to the base type of the set `S`, the compiler will generate an error.

See also: `Include` ([1307](#))

**Listing:** `./refex/ex111.pp`

---

```

program Example111;

{ Program to demonstrate the Include/Exclude functions }

Type
  TEnumA = (aOne,aTwo,aThree);
  TEnumAs = Set of TEnumA;

Var
  SA : TEnumAs;

Procedure PrintSet(S : TEnumAs);

var
  B : Boolean;

procedure DoEI(A : TEnumA; Desc : String);

begin
  If A in S then
    begin
      If B then
        Write(' ');
    
```

```

        B:=True;
        Write( Desc );
    end;
end;

begin
    Write( ' [ ' );
    B:=False;
    DoEl(aOne, 'aOne');
    DoEl(aTwo, 'aTwo');
    DoEl(aThree, 'aThree');
    Writeln( ' ] ')
end;

begin
    SA:=[];
    Include(SA,aOne);
    PrintSet(SA);
    Include(SA,aThree);
    PrintSet(SA);
    Exclude(SA,aOne);
    PrintSet(SA);
    Exclude(SA,aTwo);
    PrintSet(SA);
    Exclude(SA,aThree);
    PrintSet(SA);
end.

```

---

### 37.9.63 Exit

Synopsis: Exit current subroutine.

Declaration: `procedure Exit(const X: TAnyType)`  
`procedure Exit`

Visibility: default

Description: `Exit` exits the current subroutine, and returns control to the calling routine. If invoked in the main program routine, exit stops the program. The optional argument `X` allows to specify a return value, in the case `Exit` is invoked in a function. The function result will then be equal to `X`.

Errors: None.

See also: `Halt` ([1303](#))

**Listing:** `./refex/ex21.pp`

---

**Program** `Example21`;

*{ Program to demonstrate the Exit function. }*

**Procedure** `DoAnExit (Yes : Boolean);`

*{ This procedure demonstrates the normal Exit }*

```

begin
    Writeln ( 'Hello from DoAnExit ! ');
    If Yes then

```

---

```

    begin
    Writeln ( 'Bailing out early. ');
        exit;
    end;
    Writeln ( 'Continuing to the end. ');
end;

Function Positive (Which : Integer) : Boolean;

{ This function demonstrates the extra FPC feature of Exit :
  You can specify a return value for the function }

begin
    if Which>0 then
        exit (True)
    else
        exit (False);
end;

begin
    { This call will go to the end }
    DoAnExit (False);
    { This call will bail out early }
    DoAnExit (True);
    if Positive (-1) then
        Writeln ( 'The compiler is nuts, -1 is not positive. ')
    else
        Writeln ( 'The compiler is not so bad, -1 seems to be negative. ');
end.

```

---

### 37.9.64 exp

Synopsis: Exponentiate

Declaration: `function exp(d: ValReal) : ValReal`

Visibility: default

Description: Exp returns the exponent of X, i.e. the number e to the power X.

Errors: None.

See also: Ln ([1318](#)), Power ([1209](#))

**Listing:** ./refex/ex22.pp

---

**Program** Example22;

```

{ Program to demonstrate the Exp function. }

begin
    Writeln (Exp(1):8:2); { Should print 2.72 }
end.

```

---

### 37.9.65 FilePos

Synopsis: Get position in file

Declaration: `function FilePos(var f: File) : Int64`

Visibility: default

Description: `Filepos` returns the current record position of the file-pointer in file `F`. It cannot be invoked with a file of type `Text`. A compiler error will be generated if this is attempted.

Errors: Depending on the state of the `{SI}` switch, a runtime error can be generated if there is an error. In the `{SI-}` state, use `IOResult` to check for errors.

See also: `Filesize` ([1291](#))

**Listing:** `./refex/ex23.pp`

**Program** `Example23;`

---

```

{ Program to demonstrate the FilePos function. }

Var F : File of Longint;
    L,FP : longint;

begin
  { Fill a file with data :
    Each position contains the position ! }
  Assign (F, 'test.tmp');
  Rewrite (F);
  For L:=0 to 100 do
    begin
      FP:=FilePos(F);
      Write (F,FP);
    end;
  Close (F);
  Reset (F);
  { If all goes well, nothing is displayed here. }
  While not (Eof(F)) do
    begin
      FP:=FilePos (F);
      Read (F,L);
      if L<>FP then
        WriteLn ( 'Something wrong: Got ',L,' on pos ',FP);
    end;
  Close (F);
  Erase (f);
end.

```

---

### 37.9.66 FileSize

Synopsis: Size of file

Declaration: `function FileSize(var f: File) : Int64`

Visibility: default

Description: `Filesize` returns the total number of records in file `F`. It cannot be invoked with a file of type `Text`. (under linux and unix, this also means that it cannot be invoked on pipes). If `F` is empty, 0 is returned.

Errors: Depending on the state of the `{SI}` switch, a runtime error can be generated if there is an error. In the `{SI-}` state, use `IOResult` to check for errors.

See also: `Filepos` ([1291](#))

**Listing:** `./refex/ex24.pp`

---

**Program** `Example24;`

```
{ Program to demonstrate the FileSize function. }

Var F : File Of byte;
    L : File Of Longint;

begin
  Assign (F,paramstr(1));
  Reset (F);
  Writeln ('File size in bytes : ',FileSize(F));
  Close (F);
  Assign (L,paramstr (1));
  Reset (L);
  Writeln ('File size in Longints : ',FileSize(L));
  Close (f);
end.
```

---

### 37.9.67 FillByte

Synopsis: Fill memory region with 8-bit pattern

Declaration: `procedure FillByte(var x;count: SizeInt;value: Byte)`

Visibility: default

Description: `FillByte` fills the memory starting at `X` with `Count` bytes with value equal to `Value`. This is useful for quickly zeroing out a memory location. When the size of the memory location to be filled out is a multiple of 2 bytes, it is better to use `Fillword` ([1294](#)), and if it is a multiple of 4 bytes it is better to use `FillDWord` ([1293](#)), these routines are optimized for their respective sizes.

Errors: No checking on the size of `X` is done.

See also: `Fillchar` ([1293](#)), `FillDWord` ([1293](#)), `Fillword` ([1294](#)), `Move` ([1322](#))

**Listing:** `./refex/ex103.pp`

---

**Program** `Example103;`

```
{ Program to demonstrate the FillByte function. }

Var S : String[10];
    I : Byte;

begin
  For i:=10 downto 0 do
    begin
      { Fill S with i bytes }
      FillChar (S,SizeOf(S),32);
      { Set Length }
      SetLength(S,i);
    end;
  end;
```

```

    Writeln (s, '*');
end;
end.

```

---

### 37.9.68 FillChar

Synopsis: Fill memory region with certain character

Declaration: `procedure FillChar(var x; count: SizeInt; Value: Byte)`  
`procedure FillChar(var x; count: SizeInt; Value: Boolean)`  
`procedure FillChar(var x; count: SizeInt; Value: Char)`

Visibility: default

Description: `Fillchar` fills the memory starting at `X` with `Count` bytes or characters with value equal to `Value`.

Errors: No checking on the size of `X` is done.

See also: `Fillword` ([1294](#)), `Move` ([1322](#)), `FillByte` ([1292](#)), `FillDWord` ([1293](#))

**Listing:** `./refex/ex25.pp`

**Program** `Example25`;

*{ Program to demonstrate the FillChar function. }*

```

Var S : String[10];
    I : Byte;
begin
  For i:=10 downto 0 do
    begin
      { Fill S with i spaces }
      FillChar (S, SizeOf(S), ' ');
      { Set Length }
      SetLength(S, I);
      Writeln (s, '*');
    end;
end.

```

---

### 37.9.69 FillDWord

Synopsis: Fill memory region with 32-bit pattern

Declaration: `procedure FillDWord(var x; count: SizeInt; value: DWord)`

Visibility: default

Description: `Fillword` fills the memory starting at `X` with `Count` `DWords` with value equal to `Value`. A `DWord` is 4 bytes in size.

Errors: No checking on the size of `X` is done.

See also: `FillByte` ([1292](#)), `Fillchar` ([1293](#)), `Fillword` ([1294](#)), `Move` ([1322](#))

**Listing:** `./refex/ex104.pp`

---

```

Program Example104;

{ Program to demonstrate the FillDWord function. }

      Const
      ArraySize = 1000;

Var
  S : Array [1..ArraySize] of DWord;
  I : longint;

begin
  FillDWord(S, ArraySize, 0);
  For I:=1 to ArraySize do
    If S[I]<>0 then
      WriteLn( 'Position ', i, ' not zeroed out' );
end.

```

---

### 37.9.70 FillQWord

Synopsis: Fill memory range with QWord (64-bit) values

Declaration: `procedure FillQWord(var x; count: SizeInt; value: QWord)`

Visibility: default

Description: `FillQWord` fills the memory location of `x` with `Count` times `value`. The size of the filled memory location is therefor `8*count` bytes.

Errors: No checks are made to see if `X` actually has a minimum size of `(Count*8)` bytes. Therefor, other variables can be overwritten or the memory may be out of the accessible memory for the program. In the latter case a run-error or exception may be triggered.

See also: `FillChar` ([1293](#)), `FillWord` ([1294](#))

### 37.9.71 FillWord

Synopsis: Fill memory region with 16-bit pattern

Declaration: `procedure FillWord(var x; count: SizeInt; Value: Word)`

Visibility: default

Description: `Fillword` fills the memory starting at `X` with `Count` words with value equal to `Value`. A word is 2 bytes in size.

Errors: No checking on the size of `X` is done.

See also: `Fillchar` ([1293](#)), `Move` ([1322](#))

**Listing:** `./refex/ex76.pp`

---

```

Program Example76;

{ Program to demonstrate the FillWord function. }

Var W : Array [1..100] of Word;

```



---

```

begin
  { Quick initialization of array W }
    FillWord (W,100,0);
end.

```

---

### 37.9.72 FindResource

**Synopsis:** Locate a resource and return a handle to it.

**Declaration:**

```

function FindResource (ModuleHandle: TFPResourceHMODULE;
                      ResourceName: PChar; ResourceType: PChar)
                      : TFPResourceHandle
function FindResource (ModuleHandle: TFPResourceHMODULE;
                      ResourceName: AnsiString; ResourceType: AnsiString)
                      : TFPResourceHandle

```

**Visibility:** default

**Description:** FindResource searches for a resource with name ResourceName and of type ResourceType in the executable or library identified by ModuleHandle. It returns a TResourceHandle which can be used to load the resource with LoadResource (1319).

**Errors:** None. In case the resource was not found, 0 is returned.

**See also:** FreeResource (1298), LoadResource (1319), SizeofResource (1381), LockResource (1320), UnlockResource (1396), FreeResource (1298)

### 37.9.73 FindResourceEx

**Synopsis:** Find a resource based on type, name, language

**Declaration:**

```

function FindResourceEx (ModuleHandle: TFPResourceHMODULE;
                        ResourceType: PChar; ResourceName: PChar;
                        Language: Word) : TFPResourceHandle
function FindResourceEx (ModuleHandle: TFPResourceHMODULE;
                        ResourceType: AnsiString;
                        ResourceName: AnsiString; Language: Word)
                        : TFPResourceHandle

```

**Visibility:** default

**Description:** FindResourceEx looks in module ModuleHandle for a resource of type ResourceType and name ResourceName with language ID Language. Both ResourceName and ResourceName can be specified as a null-terminated array of characters, or as an AnsiString.

If the requested language/sublanguage is not found, then the search is conducted

1. with only primary language.
2. with the neutral language (LANG\_NEUTRAL)
3. with the english language

If none of these has returned a match, then the first available language is returned.

If a match is found, a handle to the resource is returned. If none is found, an empty handle (nil or 0) is returned.

**Errors:** None.

**37.9.74 float\_raise**

Synopsis: Raise floating point exception

Declaration: `procedure float_raise(i: ShortInt)`

Visibility: default

Description: `float_raise` raises the floating point exceptions specified by `softfloat_exception_flags` (1257).

See also: `softfloat_exception_flags` (1257), `softfloat_exception_mask` (1257)

**37.9.75 Flush**

Synopsis: Write file buffers to disk

Declaration: `procedure Flush(var t: Text)`

Visibility: default

Description: `Flush` empties the internal buffer of an opened file `F` and writes the contents to disk. The file is `\textit{not}` closed as a result of this call.

Errors: Depending on the state of the `{SI}` switch, a runtime error can be generated if there is an error. In the `{SI-}` state, use `IOResult` to check for errors.

See also: `Close` (1269)

**Listing:** `./refex/ex26.pp`

**Program** `Example26;`

*{ Program to demonstrate the Flush function. }*

**Var** `F : Text;`

**begin**

*{ Assign F to standard output }*

`Assign (F, '');`

**Rewrite** `(F);`

**Writeln** `(F, 'This line is written first , but appears later !');`

*{ At this point the text is in the internal pascal buffer ,  
and not yet written to standard output }*

**Writeln** `( 'This line appears first , but is written later !');`

*{ A writeln to 'output' always causes a flush – so this text is  
written to screen }*

**Flush** `(f);`

*{ At this point , the text written to F is written to screen. }*

**Write** `(F, 'Finishing ');`

`Close (f); { Closing a file always causes a flush first }`

**Writeln** `( 'off.');`

**end.**

**37.9.76 FlushThread**

Synopsis: Flush all standard files

Declaration: `procedure FlushThread`

Visibility: default

Description: `FlushThread` flushes any buffers from standard file descriptors such as standard input/output/error. It should normally not be called by user code, but is executed when a thread exits.

See also: `EndThread` ([1284](#))

### 37.9.77 FPower10

Declaration: `function FPower10(val: Extended; Power: LongInt) : Extended`

Visibility: default

### 37.9.78 frac

Synopsis: Return fractional part of floating point value.

Declaration: `function frac(d: ValReal) : ValReal`

Visibility: default

Description: `Frac` returns the non-integer part of X.

Errors: None.

See also: `Round` ([1369](#)), `Int` ([1312](#))

**Listing:** `./refex/ex27.pp`

---

**Program** `Example27;`

*{ Program to demonstrate the Frac function. }*

**Var** `R : Real;`

**begin**

`WriteLn (Frac (123.456):0:3); { Prints 0.456 }`

`WriteLn (Frac (-123.456):0:3); { Prints -0.456 }`

**end.**

---

### 37.9.79 Freemem

Synopsis: Release allocated memory

Declaration: `procedure Freemem(p: pointer; Size: PtrUInt)`  
`function Freemem(p: pointer) : PtrUInt`

Visibility: default

Description: `Freemem` releases the memory occupied by the pointer P, of size Count (in bytes), and returns it to the heap. P should point to the memory allocated to a dynamic variable.

Errors: An error will occur when P doesn't point to the heap.

See also: `Getmem` ([1299](#)), `New` ([1323](#)), `Dispose` ([1281](#))

**Listing:** `./refex/ex28.pp`

---

**Program** Example28;

*{ Program to demonstrate the FreeMem and GetMem functions. }*

```

    Var P : Pointer;
    MM : Longint;

begin
    { Get memory for P }
    GetMem (P,80);
    FillChar (P^,80,' ');
    FreeMem (P,80);
end.
```

---

### 37.9.80 Freememory

Synopsis: Alias for FreeMem ([1297](#))

Declaration: `procedure Freememory(p: pointer;Size: PtrUInt)`  
`function Freememory(p: pointer) : PtrUInt`

Visibility: default

Description: FreeMemory is an alias for FreeMem ([1297](#)).

See also: FreeMem ([1297](#))

### 37.9.81 FreeResource

Synopsis: Free a loaded resource

Declaration: `function FreeResource(ResData: TFPResourceHGLOBAL) : LongBool`

Visibility: default

Description: FreeResource unloads the resource identified by ResData from memory. The resource must have been loaded by LoadResource ([1319](#)). It returns True if the operation was succesful, False otherwise.

Errors: On error, False is returned.

See also: FindResource ([1295](#)), LoadResource ([1319](#)), SizeofResource ([1381](#)), LockResource ([1320](#)), UnlockResource ([1396](#)), FreeResource ([1298](#))

### 37.9.82 GetCurrentThreadId

Synopsis: Return the id of the currently running thread.

Declaration: `function GetCurrentThreadId : TThreadId`

Visibility: default

Description: GetCurrentThreadId returns the ID of the currently running thread. It can be used in calls such as KillThread ([1316](#)) or ThreadSetPriority ([1392](#))

Errors: None.

See also: KillThread ([1316](#)), ThreadSetPriority ([1392](#))

### 37.9.83 getdir

Synopsis: Return the current directory

Declaration: `procedure getdir(drivenr: Byte;var dir: shortstring)`  
`procedure getdir(drivenr: Byte;var dir: ansistring)`

Visibility: default

Description: `Getdir` returns in `dir` the current directory on the drive `drivenr`, where {`drivenr`} is 1 for the first floppy drive, 3 for the first hard disk etc. A value of 0 returns the directory on the current disk. On linux and unix systems, `drivenr` is ignored, as there is only one directory tree.

Errors: An error is returned under dos, if the drive requested isn't ready.

See also: `Chdir` ([1268](#))

**Listing:** `./refex/ex29.pp`

---

**Program** `Example29;`

*{ Program to demonstrate the GetDir function. }*

**Var** `S : String;`

**begin**

`GetDir (0,S);`

`Writeln ('Current directory is : ',S);`

**end.**

---

### 37.9.84 GetFPCHeapStatus

Synopsis: Return FPC heap manager status information

Declaration: `function GetFPCHeapStatus : TFPCHeapStatus`

Visibility: default

Description: Return FPC heap manager status information

Errors:

### 37.9.85 GetHeapStatus

Synopsis: Return the memory manager heap status.

Declaration: `function GetHeapStatus : THeapStatus`

Visibility: default

### 37.9.86 GetMem

Synopsis: Allocate new memory on the heap

Declaration: `procedure Getmem(out p: pointer;Size: PtrUInt)`  
`function GetMem(size: PtrUInt) : pointer`

Visibility: default

**Description:** `Getmem` reserves `Size` bytes memory on the heap, and returns a pointer to this memory in `p`. If no more memory is available, `nil` is returned.

For an example, see `Freemem` ([1297](#)).

**Errors:** None.

**See also:** `Freemem` ([1297](#)), `Dispose` ([1281](#)), `New` ([1323](#))

### 37.9.87 `GetMemory`

**Synopsis:** Alias for `GetMem` ([1299](#))

**Declaration:** `procedure Getmemory(out p: pointer; Size: PtrUInt)`  
`function GetMemory(size: PtrUInt) : pointer`

**Visibility:** default

**Description:** `Getmemory` is an alias for `GetMem` ([1299](#)).

**See also:** `GetMem` ([1299](#))

### 37.9.88 `GetMemoryManager`

**Synopsis:** Return current memory manager

**Declaration:** `procedure GetMemoryManager(var MemMgr: TMemoryManager)`

**Visibility:** default

**Description:** `GetMemoryManager` stores the current Memory Manager record in `MemMgr`.

For an example, see the programmer's guide.

**Errors:** None.

**See also:** `SetMemoryManager` ([1376](#)), `IsMemoryManagerSet` ([1316](#))

### 37.9.89 `GetProcessID`

**Synopsis:** Get the current process ID

**Declaration:** `function GetProcessID : SizeUInt`

**Visibility:** default

**Description:** `GetProcessID` returns the current process ID. The meaning of the return value of this call is system dependent.

**Errors:** None.

**See also:** `GetThreadID` ([1301](#))

### 37.9.90 GetResourceManager

Synopsis: Return the currently active resource manager

Declaration: `procedure GetResourceManager (var Manager: TResourceManager)`

Visibility: default

Description: `GetResourceManager` returns the currently active resource manager record in `Manager`. There is always an active resource manager record.

Errors: None.

See also: `TResourceManager` ([1248](#)), `SetResourceManager` ([1376](#))

### 37.9.91 GetThreadID

Synopsis: Get the current Thread ID.

Declaration: `function GetThreadID : TThreadID`

Visibility: default

Description: `GetThreadID` returns the current process ID. The meaning of the return value of this call is system dependent.

See also: `GetProcessID` ([1300](#))

### 37.9.92 GetThreadManager

Synopsis: Return the current thread manager

Declaration: `function GetThreadManager (var TM: TThreadManager) : Boolean`

Visibility: default

Description: `GetThreadManager` returns the currently used thread manager in `TM`.

For more information about thread programming, see the programmer's guide.

See also: `SetThreadManager` ([1378](#)), `TThreadManager` ([1250](#))

### 37.9.93 GetUnicodeStringManager

Synopsis: Return a copy of the currently active unicodetring manager.

Declaration: `procedure GetUnicodeStringManager (var Manager: TUnicodeStringManager)`

Visibility: default

Description: `GetUnicodeStringManager` returns a copy of the currently active unicode string manager in `Old`

UnicodeStrings are implemented in different ways on different platforms. Therefore, the Free Pascal Runtime library has no fixed implementation of widestring routines. Instead, it defines a `UnicodeStringManager` record, with callbacks that can be set to an implementation which is most efficient on the current platform. On windows, standard Windows routines will be used. On Unix and Linux, an implementation based on the C library is available (in unit `cwstring`).

It is possible to implement a custom unicodetring manager, optimized for the current application, without having to recompile the complete Run-Time Library.

See also: `SetUnicodeStringManager` ([1378](#)), `TUnicodeStringManager` ([1251](#))

**37.9.94 GetVariantManager**

Synopsis: Return the current variant manager.

Declaration: `procedure GetVariantManager(var VarMgr: tvariantmanager)`

Visibility: default

Description: `GetVariantManager` returns the current variant manager in `varmgr`.

See also: `IsVariantManagerSet` ([1209](#)), `SetVariantManager` ([1379](#))

**37.9.95 GetWideStringManager**

Synopsis: Return a copy of the currently active widestring manager.

Declaration: `procedure GetWideStringManager(var Manager: TUnicodeStringManager)`

Visibility: default

Description: `GetWideStringManager` returns a copy of the currently active heap manager in `Old`

WideStrings are implemented in different ways on different platforms. Therefore, the Free Pascal Runtime library has no fixed implementation of widestring routines. Instead, it defines a WideString manager record, with callbacks that can be set to an implementation which is most efficient on the current platform. On windows, standard Windows routines will be used. On Unix and Linux, an implementation based on the C library is available (in unit `cwstring`).

It is possible to implement a custom widestring manager, optimized for the current application, without having to recompile the complete Run-Time Library.

See also: `SetWideStringManager` ([1379](#)), `TWideStringManager` ([1254](#))

**37.9.96 get\_caller\_addr**

Synopsis: Return the address of the caller.

Declaration: `function get_caller_addr(framebp: pointer) : pointer`

Visibility: default

Description: `get_caller_frame` returns a pointer to address ( the return address) of the caller of the routine which has as frame `framebp`.

See also: `get_frame` ([1303](#)), `get_caller_frame` ([1302](#)), `Dump_Stack` ([1283](#))

**37.9.97 get\_caller\_frame**

Synopsis: Return the frame pointer of the caller

Declaration: `function get_caller_frame(framebp: pointer) : pointer`

Visibility: default

Description: `get_caller_frame` returns a pointer to the frame of the caller of the routine which has as frame `framebp`.

See also: `get_caller_addr` ([1302](#)), `get_frame` ([1303](#)), `Dump_Stack` ([1283](#))



**37.9.98 get\_cmdline**

Declaration: `function get_cmdline : PChar`

Visibility: default

**37.9.99 get\_frame**

Synopsis: Return the current frame

Declaration: `function get_frame : pointer`

Visibility: default

Description: `get_frame` returns a pointer to the current stack frame.

See also: `get_caller_addr` ([1302](#)), `get_caller_frame` ([1302](#))

**37.9.100 halt**

Synopsis: Stop program execution.

Declaration: `procedure halt (errnum: LongInt)`  
`procedure halt`

Visibility: default

Description: `Halt` stops program execution and returns control to the calling program. The optional argument `Errnum` specifies an exit value. If omitted, zero is returned.

Errors: None.

See also: `Exit` ([1289](#))

**Listing:** `./refex/ex30.pp`

---

**Program** `Example30`;

*{ Program to demonstrate the Halt function. }*

```
begin
  Writeln ('Before Halt. ');
  Halt (1); { Stop with exit code 1 }
  Writeln ('After Halt doesn't get executed. ');
end.
```

---

**37.9.101 hexStr**

Synopsis: Convert integer value to string with hexadecimal representation.

Declaration: `function hexStr (Val: LongInt; cnt: Byte) : shortstring`  
`function hexStr (Val: Int64; cnt: Byte) : shortstring`  
`function hexStr (Val: qword; cnt: Byte) : shortstring`  
`function hexStr (Val: Pointer) : shortstring`

Visibility: default

**Description:** `HexStr` returns a string with the hexadecimal representation of `Value`. The string has exactly `cnt` characters. (i.e. only the `cnt` rightmost nibbles are taken into account) To have a complete representation of a Longint-type value, 8 nibbles are needed, i.e. `cnt=8`.

**Errors:** None.

See also: `Str` ([1383](#)), `Val` ([1399](#)), `BinStr` ([1265](#))

**Listing:** `./refex/ex81.pp`

---

```
Program example81 ;

{ Program to demonstrate the HexStr function }

Const Value = 45678;

Var I : longint;

begin
  For I:=1 to 10 do
    Writeln ( HexStr(Value, I));
end.
```

---

### 37.9.102 hi

**Synopsis:** Return high byte/word of value.

**Declaration:**

```
function hi(b: Byte) : Byte
function hi(i: Integer) : Byte
function hi(w: Word) : Byte
function hi(l: LongInt) : Word
function hi(l: DWord) : Word
function hi(i: Int64) : DWord
function hi(q: QWord) : DWord
```

**Visibility:** default

**Description:** `Hi` returns the high byte or word from `X`, depending on the size of `X`. If the size of `X` is 4, then the high word is returned. If the size is 2 then the high byte is returned. `Hi` cannot be invoked on types of size 1, such as byte or char.

**Errors:** None

See also: `Lo` ([1319](#))

**Listing:** `./refex/ex31.pp`

---

```
Program Example31 ;

{ Program to demonstrate the Hi function. }

var
  L : Longint;
  W : Word;

begin
  L:=1 Shl 16;      { = $10000 }
```

---

```

W:=1 Shl 8;      { = $100 }
Writeln (Hi(L)); { Prints 1 }
Writeln (Hi(W)); { Prints 1 }
end.

```

---

### 37.9.103 High

Synopsis: Return highest index of open array or enumerated

Declaration: `function High(Arg: TypeOrVariable) : TOrdinal`

Visibility: default

Description: The return value of `High` depends on it's argument:

- 1.If the argument is an ordinal type, `High` returns the highest value in the range of the given ordinal type.
- 2.If the argument is an array type or an array type variable then `High` returns the highest possible value of it's index.
- 3.If the argument is an open array identifier in a function or procedure, then `High` returns the highest index of the array, as if the array has a zero-based index.
- 4.If the argument is a set type then it returns the highest value of the underlying ordinal type.

The return type is always the same type as the type of the argument (This can lead to some nasty surprises !).

Errors: None.

See also: [Low \(1320\)](#), [Ord \(1354\)](#), [Pred \(1357\)](#), [Succ \(1386\)](#)

**Listing:** `./refex/ex80.pp`

---

**Program** `example80;`

*{ Example to demonstrate the High and Low functions. }*

```

Type TEnum = ( North , East , South , West );
          TRange = 14..55;
          TArray = Array [2..10] of Longint;

```

```

Function Average (Row : Array of Longint) : Real;

```

```

Var I : longint;
      Temp : Real;

```

```

begin
  Temp := Row[0];
  For I := 1 to High(Row) do
    Temp := Temp + Row[I];
  Average := Temp / (High(Row)+1);
end;

```

```

Var A : TEnum;
      B : TRange;
      C : TArray;

```

```

    I : longint;

begin
    Writeln ('TEnum goes from : ', Ord(Low(TEnum)), ' to ', Ord(high(TEnum)), '.');
        Writeln ('A goes from : ', Ord(Low(A)), ' to ', Ord(high(A)), '.');
    Writeln ('TRange goes from : ', Ord(Low(TRange)), ' to ', Ord(high(TRange)), '.');
    Writeln ('B goes from : ', Ord(Low(B)), ' to ', Ord(high(B)), '.');
    Writeln ('TArray index goes from : ', Ord(Low(TArray)), ' to ', Ord(high(TArray)), '.');
    Writeln ('C index goes from : ', Low(C), ' to ', high(C), '.');
    For I:=Low(C) to High(C) do
        C[i]:=I;
    Writeln ('Average : ', Average(c));
    Write ('Type of return value is always same as type of argument:');
    Writeln (high (high (word)));
end.

```

---

### 37.9.104 HINSTANCE

Synopsis: Windows compatibility type for use in resources

Declaration: `function HINSTANCE : TFPResourceHMODULE`

Visibility: default

Description: This is an opaque type.

### 37.9.105 Inc

Synopsis: Increase value of integer variable

Declaration: `procedure Inc(var X: TOrdinal)`  
`procedure Inc(var X: TOrdinal; Increment: TOrdinal)`

Visibility: default

Description: `Inc` increases the value of `X` with `Increment`. If `Increment` isn't specified, then 1 is taken as a default.

Errors: If range checking is on, then A range check can occur, or an overflow error, when an attempt is made to increase `X` over its maximum value.

See also: `Dec` ([1278](#))

**Listing:** `./refex/ex32.pp`

---

**Program** Example32;

*{ Program to demonstrate the Inc function. }*

**Const**

```

C : Cardinal  = 1;
L : Longint   = 1;
I : Integer   = 1;
W : Word      = 1;
B : Byte      = 1;
SI : ShortInt = 1;
CH : Char     = 'A';

```

---

```

begin
  Inc (C);      { C:=2      }
                Inc (L,5);  { L:=6      }
  Inc (I,-3);   { I:=-2     }
  Inc (W,3);    { W:=4      }
  Inc (B,100);  { B:=101    }
  Inc (SI,-3);  { SI:=-2    }
  Inc (CH,1);   { ch:='B'   }
end.

```

---

### 37.9.106 Include

Synopsis: Include element in set if it was not yet present.

Declaration: `procedure Include (var S: TSetType; E: TSetElement)`

Visibility: default

Description: `Include` includes `E` in the set `S` if it is not yet part of the set. `E` should be of the same type as the base type of the set `S`.

Thus, the two following statements do the same thing:

```

S:=S+[E];
Include (S, E);

```

For an example, see `Exclude` ([1288](#))

Errors: If the type of the element `E` is not equal to the base type of the set `S`, the compiler will generate an error.

See also: `Exclude` ([1288](#))

### 37.9.107 IndexByte

Synopsis: Search for a byte in a memory range.

Declaration: `function IndexByte (const buf; len: SizeInt; b: Byte) : SizeInt`

Visibility: default

Description: `IndexByte` searches the memory at `buf` for maximally `len` positions for the byte `b` and returns it's position if it found one. If `b` is not found then -1 is returned. The position is zero-based.

Errors: `Buf` and `Len` are not checked to see if they are valid values.

See also: `IndexChar` ([1308](#)), `IndexDWord` ([1309](#)), `IndexWord` ([1310](#)), `CompareByte` ([1270](#))

**Listing:** `./refex/ex105.pp`

---

**Program** `Example105;`

```

{ Program to demonstrate the IndexByte function. }

```

**Const**

```

  ArraySize = 256;

```

```

MaxValue = 256;

Var
  Buffer : Array[1..ArraySize] of Byte;
  I,J : longint;
      K : Byte;

begin
  Randomize;
  For I:=1 To ArraySize do
    Buffer[I]:=Random(MaxValue);
  For I:=1 to 10 do
    begin
      K:=Random(MaxValue);
      J:=IndexByte(Buffer,ArraySize,K);
      if J=-1 then
        WriteLn('Value ',K,' was not found in buffer.')
      else
        WriteLn('Found ',K,' at position ',J,' in buffer');
      end;
    end.

```

---

### 37.9.108 IndexChar

Synopsis: Search for a character in a memory range.

Declaration: `function IndexChar(const buf;len: SizeInt;b: Char) : SizeInt`

Visibility: default

Description: `IndexChar` searches the memory at `buf` for maximally `len` positions for the character `b` and returns it's position if it found one. If `b` is not found then -1 is returned. The position is zero-based. The `IndexChar0` variant stops looking if a null character is found, and returns -1 in that case.

Errors: `Buf` and `Len` are not checked to see if they are valid values.

See also: `IndexByte` ([1307](#)), `IndexDWord` ([1309](#)), `IndexWord` ([1310](#)), `CompareChar` ([1271](#))

**Listing:** `./refex/ex108.pp`

---

**Program** Example108;

*{ Program to demonstrate the IndexChar function. }*

**Const**

```

  ArraySize = 1000;
  MaxValue = 26;
```

**Var**

```

  Buffer : Array[1..ArraySize] of Char;
  I,J : longint;
  K : Char;
```

**begin**

```

  Randomize;
  For I:=1 To ArraySize do
    Buffer[I]:=chr(Ord('A')+Random(MaxValue));
  For I:=1 to 10 do
```

---

```

begin
K:=chr(Ord('A')+Random(MaxValue));
J:=IndexChar(Buffer,ArraySize,K);
if J=-1 then
WriteLn('Value ',K,' was not found in buffer.')
else
WriteLn('Found ',K,' at position ',J,' in buffer');
end;
end.

```

---

### 37.9.109 IndexChar0

Synopsis: Return index of a character in null-terminated array of char.

Declaration: `function IndexChar0(const buf;len: SizeInt;b: Char) : SizeInt`

Visibility: default

Description: `IndexChar0` returns the index of the character `b` in the null-terminated array `Buf`. At most `len` characters will be searched, or the null character if it is encountered first. If the character is not found, -1 is returned.

Errors: On error, -1 is returned.

See also: `IndexByte` ([1307](#)), `IndexChar` ([1308](#)), `IndexWord` ([1310](#)), `IndexDWord` ([1309](#)), `CompareChar0` ([1273](#))

### 37.9.110 IndexDWord

Synopsis: Search for a DWord value in a memory range.

Declaration: `function IndexDWord(const buf;len: SizeInt;b: DWord) : SizeInt`

Visibility: default

Description: `IndexChar` searches the memory at `buf` for maximally `len` positions for the DWord `DW` and returns it's position if it found one. If `DW` is not found then -1 is returned. The position is zero-based.

Errors: `Buf` and `Len` are not checked to see if they are valid values.

See also: `IndexByte` ([1307](#)), `IndexChar` ([1308](#)), `IndexWord` ([1310](#)), `CompareDWord` ([1273](#))

**Listing:** `./refex/ex106.pp`

---

**Program** `Example106;`

*{ Program to demonstrate the IndexDWord function. }*

**Const**

```

ArraySize = 1000;
MaxValue = 1000;

```

**Var**

```

Buffer : Array[1..ArraySize] of DWord;
I,J : longint;
K : DWord;

```

**begin**

```

Randomize;

```

---

```

For I:=1 To ArraySize do
  Buffer[I]:=Random(MaxValue);
For I:=1 to 10 do
  begin
    K:=Random(MaxValue);
    J:=IndexDWord(Buffer, ArraySize, K);
    if J=-1 then
      Writeln('Value ', K, ' was not found in buffer.')
    else
      Writeln('Found ', K, ' at position ', J, ' in buffer');
    end;
  end.

```

---

### 37.9.111 IndexQWord

Synopsis: Return the position of a QWord in a memory range

Declaration: `function IndexQWord(const buf; len: SizeInt; b: QWord) : SizeInt`

Visibility: default

Description: `IndexQWord` checks the first `len` qwords starting at `Buf`, and returns the position (zero-based) of `b`. If `b` does not appear in the first `len` qwords, then -1 is returned.

Note that the search is done on QWord boundaries, but that the address of `buf` need not be on a QWord boundary.

Errors: No check is done to see whether the indicated memory range is valid. If it is not, a run-error or exception may be triggered.

See also: `IndexDWord` ([1309](#))

### 37.9.112 Indexword

Synopsis: Search for a WORD value in a memory range.

Declaration: `function Indexword(const buf; len: SizeInt; b: Word) : SizeInt`

Visibility: default

Description: `IndexChar` searches the memory at `buf` for maximally `len` positions for the Word `W` and returns it's position if it found one. If `W` is not found then -1 is returned.

Errors: `Buf` and `Len` are not checked to see if they are valid values.

See also: `IndexByte` ([1307](#)), `IndexDWord` ([1309](#)), `IndexChar` ([1308](#)), `CompareWord` ([1274](#))

**Listing:** `./refex/ex107.pp`

---

**Program** `Example107;`

*{ Program to demonstrate the IndexWord function. }*

**Const**

`ArraySize = 1000;`  
  `MaxValue = 1000;`

**Var**



```

Buffer : Array[1..ArraySize] of Word;
I,J : longint;
K : Word;

begin
  Randomize;
  For I:=1 To ArraySize do
    Buffer[I]:=Random(MaxValue);
  For I:=1 to 10 do
    begin
      K:=Random(MaxValue);
      J:=IndexWord(Buffer,ArraySize,K);
      if J=-1 then
        WriteLn('Value ',K,' was not found in buffer.')
      else
        WriteLn('Found ',K,' at position ',J,' in buffer');
      end;
    end.

```

---

### 37.9.113 InitCriticalSection

Synopsis: Initialize a critical section

Declaration: `procedure InitCriticalSection(var cs: TRTLCriticalSection)`

Visibility: default

Description: `InitCriticalSection` initializes a critical section CS for use. Before using a critical section with `EnterCriticalSection` ([1284](#)) or `LeaveCriticalSection` ([1317](#)) the critical section should be initialized with `InitCriticalSection`.

When a critical section is no longer used, it should be disposed of with `DoneCriticalSection` ([1282](#))

See also: `DoneCriticalSection` ([1282](#)), `EnterCriticalSection` ([1284](#)), `LeaveCriticalSection` ([1317](#))

### 37.9.114 InitThread

Synopsis: Initialize a thread

Declaration: `procedure InitThread(stklen: SizeUInt)`

Visibility: default

Description: Do not use, this is used internally by the thread manager.

### 37.9.115 InitThreadVars

Synopsis: Initialize threadvars

Declaration: `procedure InitThreadVars(RelocProc: Pointer)`

Visibility: default

Description: This routine should be called when threading is started. It is called by the compiler and should never be called manually, only from a thread manager.

Errors: None.

See also: `TThreadManager` ([1250](#)), `TThreadManager.InitThreadVar` ([1250](#))

**37.9.116 Insert**

Synopsis: Insert one string in another.

Declaration: `procedure Insert(const source: shortstring; var s: shortstring;  
index: SizeInt)  
procedure Insert(source: Char; var s: shortstring; index: SizeInt)  
procedure Insert(const Source: AnsiString; var S: AnsiString;  
Index: SizeInt)  
procedure Insert(const Source: UnicodeString; var S: UnicodeString;  
Index: SizeInt)  
procedure Insert(const Source: WideString; var S: WideString;  
Index: SizeInt)`

Visibility: default

Description: `Insert` inserts string `Source` in string `S`, at position `Index`, shifting all characters after `Index` to the right. The resulting string is truncated at 255 characters, if needed. (i.e. for shortstrings)

Errors: None.

See also: `Delete` ([1280](#)), `Copy` ([1277](#)), `Pos` ([1356](#))

**Listing:** `./refex/ex33.pp`

---

**Program** `Example33;`

`{ Program to demonstrate the Insert function. }`

`Var S : String;`

`begin`

`S:= 'Free Pascal is difficult to use !';`

`Insert ( 'NOT ', S, pos('difficult', S));`

`writeln (s);`

`end.`

---

**37.9.117 int**

Synopsis: Calculate integer part of floating point value.

Declaration: `function int(d: ValReal) : ValReal`

Visibility: default

Description: `Int` returns the integer part of any Real `X`, as a Real.

Errors: None.

See also: `Frac` ([1297](#)), `Round` ([1369](#))

**Listing:** `./refex/ex34.pp`

---

**Program** `Example34;`

`{ Program to demonstrate the Int function. }`

`begin`

---

```

Writeln (Int(123.456):0:1); { Prints 123.0 }
Writeln (Int(-123.456):0:1); { Prints -123.0 }
end.

```

---

### 37.9.118 InterlockedCompareExchange

Synopsis: Conditional exchange

**Declaration:**

```

function InterlockedCompareExchange(var Target: LongInt;
                                     NewValue: LongInt;Comperand: LongInt)
                                     : LongInt
function InterlockedCompareExchange(var Target: Pointer;
                                     NewValue: Pointer;Comperand: Pointer)
                                     : Pointer
function InterlockedCompareExchange(var Target: Cardinal;
                                     NewValue: Cardinal;
                                     Comperand: Cardinal) : Cardinal

```

Visibility: default

**Description:** `InterlockedCompareExchange` does an compare-and-exchange operation on the specified values in a thread-safe way. The function compares `Target` and `Comperand` and exchanges `Target` with `NewValue` if `Target` and `Comperand` are equal. It returns the old value of `Target`. This is done in a thread-safe way, i.e., only one processor is accessing the `Target` variable at a time.

Errors: None.

See also: `InterLockedDecrement` ([1313](#)), `InterLockedIncrement` ([1314](#)), `InterLockedExchange` ([1313](#)), `InterLockedExchangeAdd` ([1314](#))

### 37.9.119 InterLockedDecrement

Synopsis: Thread-safe decrement

**Declaration:**

```

function InterLockedDecrement(var Target: LongInt) : LongInt
function InterLockedDecrement(var Target: Pointer) : Pointer
function InterLockedDecrement(var Target: Cardinal) : Cardinal

```

Visibility: default

**Description:** `InterLockedDecrement` decrements `Target` with 1 and returns the result. This is done in a thread-safe way. (i.e. only one processor is accessing the variable at a time).

Errors: None.

See also: `InterLockedIncrement` ([1314](#)), `InterLockedExchange` ([1313](#)), `InterLockedExchangeAdd` ([1314](#)), `InterlockedCompareExchange` ([1313](#))

### 37.9.120 InterLockedExchange

Synopsis: Exchange 2 integers in a thread-safe way

**Declaration:** `function InterLockedExchange (var Target: LongInt; Source: LongInt)  
: LongInt  
function InterLockedExchange (var Target: Pointer; Source: Pointer)  
: Pointer  
function InterLockedExchange (var Target: Cardinal; Source: Cardinal)  
: Cardinal`

**Visibility:** default

**Description:** `InterLockedExchange` stores `Source` in `Target` and returns the old value of `Target`. This is done in a thread-safe way, i.e., only one processor is accessing the `Target` variable at a time.

**Errors:** None.

**See also:** `InterLockedDecrement` ([1313](#)), `InterLockedIncrement` ([1314](#)), `InterLockedExchangeAdd` ([1314](#)), `InterlockedCompareExchange` ([1313](#))

### 37.9.121 InterLockedExchangeAdd

**Synopsis:** Thread-safe add and exchange of 2 values

**Declaration:** `function InterLockedExchangeAdd (var Target: LongInt; Source: LongInt)  
: LongInt  
function InterLockedExchangeAdd (var Target: Pointer; Source: Pointer)  
: Pointer  
function InterLockedExchangeAdd (var Target: Cardinal; Source: Cardinal)  
: Cardinal`

**Visibility:** default

**Description:** `InterlockedDecrement` adds to `Target` the value of `Source` in a thread-safe way, and returns the old value of `Target`. This is done in a thread-safe way, i.e., only one processor is accessing the `Target` variable at a time.

**Errors:** None.

**See also:** `InterLockedDecrement` ([1313](#)), `InterLockedIncrement` ([1314](#)), `InterLockedExchange` ([1313](#)), `InterlockedCompareExchange` ([1313](#))

### 37.9.122 InterLockedIncrement

**Synopsis:** Thread-safe increment

**Declaration:** `function InterLockedIncrement (var Target: LongInt) : LongInt  
function InterLockedIncrement (var Target: Pointer) : Pointer  
function InterLockedIncrement (var Target: Cardinal) : Cardinal`

**Visibility:** default

**Description:** `InterLockedIncrement` increments `Target` with 1 and returns the result. This is done in a thread-safe way (i.e. only one processor is accessing the variable at a time).

**Errors:** None.

**See also:** `InterLockedDecrement` ([1313](#)), `InterLockedExchange` ([1313](#)), `InterLockedExchangeAdd` ([1314](#)), `InterlockedCompareExchange` ([1313](#))

**37.9.123 IOResult**

Synopsis: Return result of last file IO operation

Declaration: `function IOResult : Word`

Visibility: default

Description: IOResult contains the result of any input/output call, when the `{\$i-}` compiler directive is active, disabling IO checking. When the flag is read, it is reset to zero. If IOResult is zero, the operation completed successfully. If non-zero, an error occurred. The following errors can occur:

dos errors :

- 2**File not found.
- 3**Path not found.
- 4**Too many open files.
- 5**Access denied.
- 6**Invalid file handle.
- 12**Invalid file-access mode.
- 15**Invalid disk number.
- 16**Cannot remove current directory.
- 17**Cannot rename across volumes.

I/O errors :

- 100**Error when reading from disk.
- 101**Error when writing to disk.
- 102**File not assigned.
- 103**File not open.
- 104**File not opened for input.
- 105**File not opened for output.
- 106**Invalid number.

Fatal errors :

- 150**Disk is write protected.
- 151**Unknown device.
- 152**Drive not ready.
- 153**Unknown command.
- 154**CRC check failed.
- 155**Invalid drive specified..
- 156**Seek error on disk.
- 157**Invalid media type.
- 158**Sector not found.
- 159**Printer out of paper.
- 160**Error when writing to device.
- 161**Error when reading from device.
- 162**Hardware failure.

Errors: None.

**Listing:** ./refex/ex35.pp

---

**Program** Example35;

```

        { Program to demonstrate the IOResult function. }

Var F : text;

begin
    Assign (f,paramstr(1));
    {$i-}
    Reset (f);
    {$i+}
    If IOresult<>0 then
        writeln ('File ',paramstr(1),' doesn't exist')
    else
        writeln ('File ',paramstr(1),' exists');
end.

```

---

### 37.9.124 IsMemoryManagerSet

**Synopsis:** Is the memory manager set

**Declaration:** function IsMemoryManagerSet : Boolean

**Visibility:** default

**Description:** IsMemoryManagerSet will return True if the memory manager has been set to another value than the system heap manager, it will return False otherwise.

**Errors:** None.

**See also:** SetMemoryManager ([1376](#)), GetMemoryManager ([1300](#))

### 37.9.125 Is\_IntResource

**Synopsis:** Check whether a resource is an internal resource

**Declaration:** function Is\_IntResource(aStr: PChar) : Boolean

**Visibility:** default

**Description:** Is\_IntResource returns True if the resource type is internal (system predefined) resource or false if it is a user-defined resource type.

**Errors:** None.

### 37.9.126 KillThread

**Synopsis:** Kill a running thread

**Declaration:** function KillThread(threadHandle: TThreadID) : DWord

**Visibility:** default

**Description:** `KillThread` causes a running thread to be aborted. The thread is identified by its handle or ID `threadHandle`.

The function returns zero if successful. A nonzero return value indicates failure.

**Errors:** If a failure occurred, a nonzero result is returned. The meaning is system dependent.

**See also:** `WaitForThreadTerminate` ([1401](#)), `EndThread` ([1284](#)), `SuspendThread` ([1387](#))

### 37.9.127 LeaveCriticalSection

**Synopsis:** Leave a critical section

**Declaration:** `procedure LeaveCriticalSection(var cs: TRTLCriticalSection)`

**Visibility:** default

**Description:** `LeaveCriticalSection` signals that the current thread is exiting the critical section CS it has entered with `EnterCriticalSection` ([1284](#)).

The critical section must have been initialized with `InitCriticalSection` ([1311](#)) prior to a call to `EnterCriticalSection` and `LeaveCriticalSection`.

**See also:** `InitCriticalSection` ([1311](#)), `DoneCriticalSection` ([1282](#)), `EnterCriticalSection` ([1284](#))

### 37.9.128 Length

**Synopsis:** Returns length of a string.

**Declaration:** `function Length(S: AStringType) : Integer`  
`function Length(A: DynArrayType) : Integer`

**Visibility:** default

**Description:** `Length` returns the length of the string `S`, which is limited to 255 for shortstrings. If the string `S` is empty, 0 is returned.

*Note:* The length of the string `S` is stored in `S[0]` for shortstrings only. The `Length` function should always be used on ansistrings and widestrings.

For dynamical arrays, the function returns the number of elements in the array.

`Length` also supports arguments of type `PChar` and `PWideChar`, in which case it is identical to the `StrLen` and `WStrLen` functions, respectively. In this case, the function actually calculates the length of the null-terminated string, and its execution time is proportional to the string length because the terminating null character is searched through a linear scan.

**Errors:** None.

**See also:** `Pos` ([1356](#))

**Listing:** `./refex/ex36.pp`

---

**Program** `Example36`;

*{ Program to demonstrate the Length function. }*

**Var** `S : String;`  
`I : Integer;`

**begin**

---

```

S:= '';
for i:=1 to 10 do
begin
  S:=S+ '*';
  Writeln (Length(S):2, ' : ',s);
end;
end.

```

---

### 37.9.129 LEtoN

Synopsis: Convert Little Endian-ordered integer to Native-ordered integer

Declaration: function LEtoN(const AValue: SmallInt) : SmallInt  
 function LEtoN(const AValue: Word) : Word  
 function LEtoN(const AValue: LongInt) : LongInt  
 function LEtoN(const AValue: DWord) : DWord  
 function LEtoN(const AValue: Int64) : Int64  
 function LEtoN(const AValue: QWord) : QWord

Visibility: default

Description: LETON will rearrange the bytes in a Little-Endian number to the native order for the current processor. That is, for a little-endian processor, it will do nothing, and for a big-endian processor, it will invert the order of the bytes.

See also: BEtoN ([1265](#)), NtoBE ([1323](#)), NtoLE ([1324](#))

### 37.9.130 Ln

Synopsis: Calculate logarithm

Declaration: function ln(d: ValReal) : ValReal

Visibility: default

Description: Ln returns the natural logarithm of the Real parameter X. X must be positive.

Errors: An run-time error will occur when X is negative.

See also: Exp ([1290](#)), Power ([1209](#))

**Listing:** ./refex/ex37.pp

---

**Program** Example37;

*{ Program to demonstrate the Ln function. }*

```

begin
  Writeln (Ln(1));      { Prints 0 }
  Writeln (Ln(Exp(1))); { Prints 1 }
end.

```

---



**37.9.131 lo**

Synopsis: Return low byte/word of value.

Declaration: `function lo(B: Byte) : Byte`  
`function lo(i: Integer) : Byte`  
`function lo(w: Word) : Byte`  
`function lo(l: LongInt) : Word`  
`function lo(l: DWord) : Word`  
`function lo(i: Int64) : DWord`  
`function lo(q: QWord) : DWord`

Visibility: default

Description: `Lo` returns the low byte of its argument if this is of type `Integer` or `Word`. It returns the low word of its argument if this is of type `Longint` or `Cardinal`.

Errors: None.

See also: `Ord` ([1354](#)), `Chr` ([1269](#)), `Hi` ([1304](#))

**Listing:** `./refex/ex38.pp`

---

**Program** `Example38;`

*{ Program to demonstrate the Lo function. }*

**Var** `L : Longint;`  
`W : Word;`

**begin**  
`L := (1 Shl 16) + (1 Shl 4); { $10010 }`  
`WriteLn (Lo(L)); { Prints 16 }`  
`W := (1 Shl 8) + (1 Shl 4); { $110 }`  
`WriteLn (Lo(W)); { Prints 16 }`  
**end.**

---

**37.9.132 LoadResource**

Synopsis: Load a resource for use

Declaration: `function LoadResource(ModuleHandle: TFPResourceHMODULE;`  
`ResHandle: TFPResourceHandle) : TFPResourceHGLOBAL`

Visibility: default

Description: `LoadResource` loads a resource identified by `ResHandle` from a module identified by `ModuleHandle` into memory. It returns a handle to the resource.

Loaded resources must be unloaded again using the `FreeResource` ([1298](#)) function.

Errors: On error, 0 is returned.

See also: `FindResource` ([1295](#)), `FreeResource` ([1298](#)), `SizeofResource` ([1381](#)), `LockResource` ([1320](#)), `UnlockResource` ([1396](#)), `FreeResource` ([1298](#))

### 37.9.133 LockResource

Synopsis: Lock a resource

Declaration: `function LockResource(ResData: TFPResourceHGLOBAL) : Pointer`

Visibility: default

Description: `LockResource` locks a resource previously loaded by `LoadResource` into memory. This means that any attempt to modify the resource will fail while it is locked. The function returns a pointer to the resource location in memory.

The resource can be freed again using the `UnlockResource` (1396) function.

Errors: if the function fails, `Nil` is returned.

See also: `FindResource` (1295), `FreeResource` (1298), `SizeofResource` (1381), `LoadResource` (1319), `UnlockResource` (1396), `FreeResource` (1298)

### 37.9.134 longjmp

Synopsis: Jump to address.

Declaration: `procedure longjmp(var S: jmp_buf; value: LongInt)`

Visibility: default

Description: `LongJump` jumps to the address in the `envjmp_buf`, and restores the registers that were stored in it at the corresponding `SetJump` (1374) call. In effect, program flow will continue at the `SetJump` call, which will return `value` instead of 0. If a value equal to zero is passed, it will be converted to 1 before passing it on. The call will not return, so it must be used with extreme care. This can be used for error recovery, for instance when a segmentation fault occurred.

For an example, see `SetJump` (1374)

Errors: None.

See also: `SetJump` (1374)

### 37.9.135 Low

Synopsis: Return lowest index of open array or enumerated

Declaration: `function Low(Arg: TypeOrVariable) : TOrdinal`

Visibility: default

Description: The return value of `Low` depends on it's argument:

- 1.If the argument is an ordinal type, `Low` returns the lowest value in the range of the given ordinal type.
- 2.If the argument is an array type or an array type variable then `Low` returns the lowest possible value of it's index.
- 3.If the argument is an open array identifier in a function or procedure, then `Low` returns the lowest element of the array, which is always zero.
- 4.If the argument is a set type then it returns the lowest value of the underlying ordinal type.

The return type is always the same type as the type of the argument.

for an example, see `High` (1305).

Errors: None.

See also: High ([1305](#)), Ord ([1354](#)), Pred ([1357](#)), Succ ([1386](#))

### 37.9.136 lowerCase

Synopsis: Return lowercase version of a string.

Declaration: `function lowerCase(const s: shortstring) : shortstring; Overload`  
`function lowerCase(c: Char) : Char; Overload`  
`function lowercase(const s: ansistring) : ansistring`

Visibility: default

Description: `Lowercase` returns the lowercase version of its argument `C`. If its argument is a string, then the complete string is converted to lowercase. The type of the returned value is the same as the type of the argument.

Errors: None.

See also: `Uppcase` ([1397](#))

**Listing:** `./refex/ex73.pp`

---

**program** `Example73`;

*{ Program to demonstrate the Lowercase function. }*

**var** `c:char`;

**begin**

**for** `c:= 'A' to 'Z' do`

**write** (`lowercase(c)`);

**Writeln**;

**Writeln** (`Lowercase('ABCDEFGHIJKLMNOPQRSTUVWXYZ')`);

**end.**

---

### 37.9.137 MakeLangID

Synopsis: Create a language ID

Declaration: `function MakeLangID(primary: Word;sub: Word) : Word`

Visibility: default

Description: `MakeLangID` creates a language ID from the `primary` and `sub` language IDs.

### 37.9.138 MemSize

Synopsis: Return the size of a memory block.

Declaration: `function MemSize(p: pointer) : PtrUInt`

Visibility: default

Description: `MemSize` returns the size of a memory block on the heap.

Errors: Passing an invalid pointer may lead to run-time errors (access violations).

See also: `GetMem` ([1299](#)), `FreeMem` ([1297](#))

**37.9.139 mkdir**

Synopsis: Create a new directory.

Declaration: `procedure mkdir(const s: String); Overload`

Visibility: default

Description: `Mkdir` creates a new directory `S`.

For an example, see `Rmdir` ([1366](#)).

Errors: Depending on the state of the `{SI}` switch, a runtime error can be generated if there is an error. In the `{SI-}` state, use `IOResult` to check for errors.

See also: `Chdir` ([1268](#)), `Rmdir` ([1366](#))

**37.9.140 Move**

Synopsis: Move data from one location in memory to another

Declaration: `procedure Move(const source; var dest; count: SizeInt)`

Visibility: default

Description: `Move` moves `Count` bytes from `Source` to `Dest`.

Errors: If either `Dest` or `Source` is outside the accessible memory for the process, then a run-time error will be generated.

See also: `Fillword` ([1294](#)), `Fillchar` ([1293](#))

**Listing:** `./refex/ex42.pp`

---

**Program** `Example42;`

*{ Program to demonstrate the Move function. }*

**Var** `S1,S2 : String [30];`

**begin**

`S1:= 'Hello World !';`

`S2:= 'Bye, bye !';`

`Move (S1,S2,Sizeof(S1));`

`WriteLn (S2);`

**end.**

---

**37.9.141 MoveChar0**

Synopsis: Move data till first zero character

Declaration: `procedure MoveChar0(const buf1; var buf2; len: SizeInt)`

Visibility: default

Description: `MoveChar0` moves `Count` bytes from `buf1` to `buf2`, and stops moving if a zero character is found.

Errors: No checking is done to see if `Count` stays within the memory allocated to the process.

See also: [Move \(1322\)](#)

**Listing:** ./refex/ex109.pp

**Program** Example109;

*{ Program to demonstrate the MoveChar0 function. }*

**Var**

Buf1, Buf2 : **Array**[1..80] **of** char;  
I : longint;

**begin**

Randomize;

**For** I:=low(buf1) **to** high(buf1) **do**

Buf1[I]:=chr(Random(16)+Ord('A'));

Writeln('Original buffer');

writeln(Buf1);

Buf1[Random(80)+1]:=#0;

MoveChar0(Buf1, Buf2, 80);

Writeln('Randomly zero-terminated Buffer');

Writeln(Buf2);

**end.**

### 37.9.142 New

**Synopsis:** Dynamically allocate memory for variable

**Declaration:** procedure New(var P: Pointer)  
procedure New(var P: Pointer; Cons: TProcedure)

**Visibility:** default

**Description:** New allocates a new instance of the type pointed to by P, and puts the address in P. If P is an object, then it is possible to specify the name of the constructor with which the instance will be created.

For an example, see [Dispose \(1281\)](#).

**Errors:** If not enough memory is available, Nil will be returned.

See also: [Dispose \(1281\)](#), [Freemem \(1297\)](#), [Getmem \(1299\)](#)

### 37.9.143 NtoBE

**Synopsis:** Convert Native-ordered integer to a Big Endian-ordered integer

**Declaration:** function NtoBE(const AValue: SmallInt) : SmallInt  
function NtoBE(const AValue: Word) : Word  
function NtoBE(const AValue: LongInt) : LongInt  
function NtoBE(const AValue: DWord) : DWord  
function NtoBE(const AValue: Int64) : Int64  
function NtoBE(const AValue: QWord) : QWord

**Visibility:** default

**Description:** NtoBE will rearrange the bytes in a natively-ordered number to the Big-Endian order. That is, for a Little-Endian processor, it will invert the order of the bytes and for a big-endian processor, it will do nothing.

See also: BEtoN ([1265](#)), LEtoN ([1318](#)), NtoLE ([1324](#))

### 37.9.144 NtoLE

Synopsis: Convert Native-ordered integer to a Little Endian-ordered integer

Declaration: `function NtoLE(const AValue: SmallInt) : SmallInt`  
`function NtoLE(const AValue: Word) : Word`  
`function NtoLE(const AValue: LongInt) : LongInt`  
`function NtoLE(const AValue: DWord) : DWord`  
`function NtoLE(const AValue: Int64) : Int64`  
`function NtoLE(const AValue: QWord) : QWord`

Visibility: default

Description: `NTOLE` will rearrange the bytes in a natively-ordered number to the little-Endian order. That is, for a Big-Endian processor, it will invert the order of the bytes and for a Little-Endian processor, it will do nothing.

See also: BEtoN ([1265](#)), LEtoN ([1318](#)), NtoBE ([1323](#))

### 37.9.145 Null

Synopsis: Null variant

Declaration: `function Null : Variant`

Visibility: default

### 37.9.146 OctStr

Synopsis: Convert integer to a string with octal representation.

Declaration: `function OctStr(Val: LongInt;cnt: Byte) : shortstring`  
`function OctStr(Val: Int64;cnt: Byte) : shortstring`  
`function OctStr(Val: qword;cnt: Byte) : shortstring`

Visibility: default

Description: `OctStr` returns a string with the octal representation of `Value`. The string has exactly `cnt` characters.

Errors: None.

See also: `Str` ([1383](#)), `Val` ([1399](#)), `BinStr` ([1265](#)), `HexStr` ([1303](#))

**Listing:** `./refex/ex112.pp`

---

**Program** `example112;`

*{ Program to demonstrate the OctStr function }*

**Const** `Value = 45678;`

**Var** `I : longint;`

**begin**

---

```

For I:=1 to 10 do
  Writeln ( OctStr(Value,I));
For I:=1 to 16 do
  Writeln ( OctStr(I,3));
end.

```

---

### 37.9.147 odd

Synopsis: Is a value odd or even ?

Declaration: `function odd(l: LongInt) : Boolean`  
`function odd(l: LongWord) : Boolean`  
`function odd(l: Int64) : Boolean`  
`function odd(l: QWord) : Boolean`

Visibility: default

Description: Odd returns True if X is odd, or False otherwise.

Errors: None.

See also: Abs ([1258](#)), Ord ([1354](#))

**Listing:** ./refex/ex43.pp

---

```

Program Example43;

{ Program to demonstrate the Odd function. }

begin
  If Odd(1) Then
    Writeln ( 'Everything OK with 1 !');
  If Not Odd(2) Then
    Writeln ( 'Everything OK with 2 !');
end.

```

---

### 37.9.148 Ofs

Synopsis: Return offset of a variable.

Declaration: `function Ofs(var X) : LongInt`

Visibility: default

Description: Ofs returns the offset of the address of a variable. This function is only supported for compatibility. In Free Pascal, it returns always the complete address of the variable, since Free Pascal is a 32 bit compiler.

Errors: None.

See also: DSeg ([1282](#)), CSeg ([1278](#)), Seg ([1374](#)), Ptr ([1358](#))

**Listing:** ./refex/ex44.pp

---

```

Program Example44;

{ Program to demonstrate the Ofs function. }

Var W : Pointer;

                begin
    W:= Pointer(Ofs(W)); { W contains its own offset. }
end.

```

---

### 37.9.149 operator \*(variant, variant): variant

Synopsis: Implement multiplication (\*) operation on variants.

Declaration: `operator operator *(variant, variant): variant(const op1: variant;  
const op2: variant)  
: variant`

Visibility: default

Description: The implementation of the multiplication \* operation is delegated to the variant manager with operation `opMultiply`.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: `operator /(variant, variant): variant` ([1327](#))

### 37.9.150 operator \*\*(variant, variant): variant

Synopsis: Implement power (\*\*) operation on variants.

Declaration: `operator operator **(variant, variant): variant(const op1: variant;  
const op2: variant)  
: variant`

Visibility: default

Description: The implementation of the power \*\* operation is delegated to the variant manager with operation `opPower`.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: `operator *(variant, variant): variant` ([1326](#))

### 37.9.151 operator +(variant, variant): variant

Synopsis: Implement addition (+) operation on variants.

Declaration: `operator operator +(variant, variant): variant(const op1: variant;  
const op2: variant)  
: variant`

Visibility: default



**Description:** The implementation of the addition + operation is delegated to the variant manager with operation `opAdd`.

**Errors:** Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

**See also:** operator `-(variant, variant): variant` ([1327](#))

### 37.9.152 operator `-(variant): variant`

**Synopsis:** Implement `-` (unary minus, negation) operation on variants.

**Declaration:** `operator operator -(variant): variant(const op: variant) : variant`

**Visibility:** `default`

**Description:** The implementation of the unary minus `-` operation is delegated to the variant manager with operation `varNeg`.

**Errors:** Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

**See also:** operator `-(variant, variant): variant` ([1327](#))

### 37.9.153 operator `-(variant, variant): variant`

**Synopsis:** Implement subtraction `-` operation on variants.

**Declaration:** `operator operator -(variant, variant): variant(const op1: variant;  
const op2: variant)  
: variant`

**Visibility:** `default`

**Description:** The implementation of the subtraction `-` operation is delegated to the variant manager with operation `opSubtract`.

**Errors:** Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

**See also:** operator `-(variant, variant): variant` ([1327](#))

### 37.9.154 operator `/(variant, variant): variant`

**Synopsis:** Implement division `/` operation on variants.

**Declaration:** `operator operator /(variant, variant): variant(const op1: variant;  
const op2: variant)  
: variant`

**Visibility:** `default`

**Description:** The implementation of the division `/` operation is delegated to the variant manager with operation `opDivide`.

**Errors:** Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

**See also:** operator `*(variant, variant): variant` ([1326](#))

### 37.9.155 operator :=(ansistring): olevariant

Synopsis:

Declaration: `operator operator :=(ansistring): olevariant(const source: ansistring)  
: olevariant`

Visibility: default

Description:

Errors:

### 37.9.156 operator :=(ansistring): variant

Synopsis:

Declaration: `operator operator :=(ansistring): variant(const source: ansistring)  
: variant`

Visibility: default

Description:

Errors:

### 37.9.157 operator :=(Boolean): olevariant

Synopsis:

Declaration: `operator operator :=(Boolean): olevariant(const source: Boolean)  
: olevariant`

Visibility: default

Description:

Errors:

### 37.9.158 operator :=(Boolean): variant

Synopsis:

Declaration: `operator operator :=(Boolean): variant(const source: Boolean) : variant`

Visibility: default

Description:

Errors:

### 37.9.159 operator :=(Byte): olevariant

Synopsis:

Declaration: `operator operator :=(Byte): olevariant(const source: Byte) : olevariant`

Visibility: default

Description:

Errors:

### 37.9.160 operator :=(Byte): variant

Synopsis:

Declaration: `operator operator :=(Byte) : variant(const source: Byte) : variant`

Visibility: default

Description:

Errors:

### 37.9.161 operator :=(Char): olevariant

Synopsis:

Declaration: `operator operator :=(Char) : olevariant(const source: Char) : olevariant`

Visibility: default

Description:

Errors:

### 37.9.162 operator :=(Char): variant

Synopsis:

Declaration: `operator operator :=(Char) : variant(const source: Char) : variant`

Visibility: default

Description:

Errors:

### 37.9.163 operator :=(comp): olevariant

Declaration: `operator operator :=(comp) : olevariant(const source: comp) : olevariant`

Visibility: default

### 37.9.164 operator :=(comp): variant

Declaration: `operator operator :=(comp) : variant(const source: comp) : variant`

Visibility: default

### 37.9.165 operator :=(currency): olevariant

Synopsis:

Declaration: `operator operator :=(currency) : olevariant(const source: currency)  
: olevariant`

Visibility: default

Description:

Errors:

### 37.9.166 operator :=(currency): variant

Synopsis:

Declaration: `operator operator :=(currency): variant(const source: currency)  
: variant`

Visibility: default

Description:

Errors:

### 37.9.167 operator :=(double): olevariant

Synopsis:

Declaration: `operator operator :=(double): olevariant(const source: double)  
: olevariant`

Visibility: default

Description:

Errors:

### 37.9.168 operator :=(double): variant

Synopsis:

Declaration: `operator operator :=(double): variant(const source: double) : variant`

Visibility: default

Description:

Errors:

### 37.9.169 operator :=(DWord): olevariant

Synopsis:

Declaration: `operator operator :=(DWord): olevariant(const source: DWord)  
: olevariant`

Visibility: default

Description:

Errors:

### 37.9.170 operator :=(DWord): variant

Synopsis:

Declaration: `operator operator :=(DWord): variant(const source: DWord) : variant`

Visibility: default

Description:

Errors:

### 37.9.171 operator :=(extended): olevariant

Declaration: `operator operator :=(extended): olevariant(const source: extended)  
: olevariant`

Visibility: default

### 37.9.172 operator :=(extended): variant

Declaration: `operator operator :=(extended): variant(const source: extended)  
: variant`

Visibility: default

### 37.9.173 operator :=(Int64): olevariant

Synopsis:

Declaration: `operator operator :=(Int64): olevariant(const source: Int64)  
: olevariant`

Visibility: default

Description:

Errors:

### 37.9.174 operator :=(Int64): variant

Synopsis:

Declaration: `operator operator :=(Int64): variant(const source: Int64) : variant`

Visibility: default

Description:

Errors:

### 37.9.175 operator :=(longbool): olevariant

Synopsis:

Declaration: `operator operator :=(longbool): olevariant(const source: longbool)  
: olevariant`

Visibility: default

Description:

Errors:

### 37.9.176 operator :=(longbool): variant

Synopsis:

Declaration: `operator operator :=(longbool): variant(const source: longbool)  
: variant`

Visibility: default

Description:

Errors:

### 37.9.177 operator :=(LongInt): olevariant

Synopsis:

Declaration: `operator operator :=(LongInt): olevariant(const source: LongInt)  
: olevariant`

Visibility: default

Description:

Errors:

### 37.9.178 operator :=(LongInt): variant

Synopsis:

Declaration: `operator operator :=(LongInt): variant(const source: LongInt) : variant`

Visibility: default

Description:

Errors:

### 37.9.179 operator :=(olevariant): ansistring

Synopsis:

Declaration: `operator operator :=(olevariant): ansistring(const source: olevariant)  
: ansistring`

Visibility: default

Description:

Errors:

### 37.9.180 operator :=(olevariant): Boolean

Synopsis:

Declaration: `operator operator :=(olevariant): Boolean(const source: olevariant)  
: Boolean`

Visibility: default

Description:

Errors:

### 37.9.181 operator :=(olevariant): Byte

Synopsis:

Declaration: `operator operator :=(olevariant): Byte(const source: olevariant) : Byte`

Visibility: default

Description:

Errors:

### 37.9.182 operator :=(olevariant): Char

Synopsis:

Declaration: `operator operator :=(olevariant): Char(const source: olevariant) : Char`

Visibility: default

Description:

Errors:

### 37.9.183 operator :=(olevariant): comp

Declaration: `operator operator :=(olevariant): comp(const source: olevariant) : comp`

Visibility: default

### 37.9.184 operator :=(olevariant): currency

Synopsis:

Declaration: `operator operator :=(olevariant): currency(const source: olevariant)  
: currency`

Visibility: default

Description:

Errors:

### 37.9.185 operator :=(olevariant): double

Synopsis:

Declaration: `operator operator :=(olevariant): double(const source: olevariant)  
: double`

Visibility: default

Description:

Errors:

### 37.9.186 operator :=(olevariant): DWord

Synopsis:

Declaration: `operator operator :=(olevariant): DWord(const source: olevariant)  
: DWord`

Visibility: default

Description:

Errors:

### 37.9.187 operator :=(olevariant): extended

Declaration: `operator operator :=(olevariant): extended(const source: olevariant)  
: extended`

Visibility: default

### 37.9.188 operator :=(olevariant): Int64

Synopsis:

Declaration: `operator operator :=(olevariant): Int64(const source: olevariant)  
: Int64`

Visibility: default

Description:

Errors:

### 37.9.189 operator :=(olevariant): longbool

Synopsis:

Declaration: `operator operator :=(olevariant): longbool(const source: olevariant)  
: longbool`

Visibility: default

Description:

Errors:



### 37.9.190 operator :=(olevariant): LongInt

Synopsis:

Declaration: `operator operator :=(olevariant): LongInt(const source: olevariant)  
: LongInt`

Visibility: default

Description:

Errors:

### 37.9.191 operator :=(olevariant): qword

Synopsis:

Declaration: `operator operator :=(olevariant): qword(const source: olevariant)  
: qword`

Visibility: default

Description:

Errors:

### 37.9.192 operator :=(olevariant): Real

Declaration: `operator operator :=(olevariant): Real(const source: olevariant) : Real`

Visibility: default

### 37.9.193 operator :=(olevariant): ShortInt

Synopsis:

Declaration: `operator operator :=(olevariant): ShortInt(const source: olevariant)  
: ShortInt`

Visibility: default

Description:

Errors:

### 37.9.194 operator :=(olevariant): shortstring

Synopsis:

Declaration: `operator operator :=(olevariant): shortstring(const source: olevariant)  
: shortstring`

Visibility: default

Description:

Errors:

### 37.9.195 operator :=(olevariant): single

Declaration: `operator operator :=(olevariant): single(const source: olevariant)  
: single`

Visibility: default

### 37.9.196 operator :=(olevariant): SmallInt

Synopsis:

Declaration: `operator operator :=(olevariant): SmallInt(const source: olevariant)  
: SmallInt`

Visibility: default

Description:

Errors:

### 37.9.197 operator :=(olevariant): TDateTime

Synopsis:

Declaration: `operator operator :=(olevariant): TDateTime(const source: olevariant)  
: TDateTime`

Visibility: default

Description:

Errors:

### 37.9.198 operator :=(olevariant): TError

Synopsis:

Declaration: `operator operator :=(olevariant): TError(const source: olevariant)  
: TError`

Visibility: default

Description:

Errors:

### 37.9.199 operator :=(olevariant): UnicodeString

Declaration: `operator operator :=(olevariant): UnicodeString  
(const source: olevariant)  
: UnicodeString`

Visibility: default

### 37.9.200 operator :=(olevariant): variant

Synopsis:

Declaration: `operator operator :=(olevariant): variant(const source: olevariant)  
: variant`

Visibility: default

Description:

Errors:

### 37.9.201 operator :=(olevariant): widechar

Synopsis:

Declaration: `operator operator :=(olevariant): widechar(const source: olevariant)  
: widechar`

Visibility: default

Description:

Errors:

### 37.9.202 operator :=(olevariant): widestring

Synopsis:

Declaration: `operator operator :=(olevariant): widestring(const source: olevariant)  
: widestring`

Visibility: default

Description:

Errors:

### 37.9.203 operator :=(olevariant): Word

Synopsis:

Declaration: `operator operator :=(olevariant): Word(const source: olevariant) : Word`

Visibility: default

Description:

Errors:

### 37.9.204 operator :=(olevariant): wordbool

Synopsis:

Declaration: `operator operator :=(olevariant): wordbool(const source: olevariant)  
: wordbool`

Visibility: default

Description:

Errors:

### 37.9.205 operator :=(qword): olevariant

Synopsis:

Declaration: `operator operator :=(qword): olevariant(const source: qword)  
: olevariant`

Visibility: default

Description:

Errors:

### 37.9.206 operator :=(qword): variant

Synopsis:

Declaration: `operator operator :=(qword): variant(const source: qword) : variant`

Visibility: default

Description:

Errors:

### 37.9.207 operator :=(Real): olevariant

Declaration: `operator operator :=(Real): olevariant(const source: Real) : olevariant`

Visibility: default

### 37.9.208 operator :=(Real): variant

Declaration: `operator operator :=(Real): variant(const source: Real) : variant`

Visibility: default

### 37.9.209 operator :=(real48): double

Synopsis:

Declaration: `operator operator :=(real48): double(b: real48) : double`

Visibility: default

Description:

Errors:

### 37.9.210 operator :=(real48): extended

Declaration: `operator operator :=(real48): extended(b: real48) : extended`

Visibility: default

### 37.9.211 operator :=(ShortInt): olevariant

Synopsis:

Declaration: `operator operator :=(ShortInt): olevariant(const source: ShortInt)  
: olevariant`

Visibility: default

Description:

Errors:

### 37.9.212 operator :=(ShortInt): variant

Synopsis:

Declaration: `operator operator :=(ShortInt): variant(const source: ShortInt)  
: variant`

Visibility: default

Description:

Errors:

### 37.9.213 operator :=(shortstring): olevariant

Synopsis:

Declaration: `operator operator :=(shortstring): olevariant(const source: shortstring)  
: olevariant`

Visibility: default

Description:

Errors:

### 37.9.214 operator :=(shortstring): variant

Synopsis:

Declaration: `operator operator :=(shortstring): variant(const source: shortstring)  
: variant`

Visibility: default

Description:

Errors:

### 37.9.215 operator :=(single): olevariant

Declaration: `operator operator :=(single): olevariant(const source: single)  
: olevariant`

Visibility: default

### 37.9.216 operator :=(single): variant

Declaration: `operator operator :=(single): variant(const source: single) : variant`

Visibility: default

### 37.9.217 operator :=(SmallInt): olevariant

Synopsis:

Declaration: `operator operator :=(SmallInt): olevariant(const source: SmallInt)  
: olevariant`

Visibility: default

Description:

Errors:

### 37.9.218 operator :=(SmallInt): variant

Synopsis:

Declaration: `operator operator :=(SmallInt): variant(const source: SmallInt)  
: variant`

Visibility: default

Description:

Errors:

### 37.9.219 operator :=(TDateTime): olevariant

Synopsis:

Declaration: `operator operator :=(TDateTime): olevariant(const source: TDateTime)  
: olevariant`

Visibility: default

Description:

Errors:

### 37.9.220 operator :=(TDateTime): variant

Synopsis:

Declaration: `operator operator :=(TDateTime): variant(const source: TDateTime)  
: variant`

Visibility: default

Description:

Errors:

### 37.9.221 operator :=(TError): olevariant

Synopsis:

Declaration: `operator operator :=(TError): olevariant(const source: TError)  
: olevariant`

Visibility: default

Description:

Errors:

### 37.9.222 operator :=(TError): variant

Synopsis:

Declaration: `operator operator :=(TError): variant(const source: TError) : variant`

Visibility: default

Description:

Errors:

### 37.9.223 operator :=(UCS4String): variant

Declaration: `operator operator :=(UCS4String): variant(const source: UCS4String)  
: variant`

Visibility: default

### 37.9.224 operator :=(UnicodeString): olevariant

Declaration: `operator operator :=(UnicodeString): olevariant  
(const source: UnicodeString)  
: olevariant`

Visibility: default

### 37.9.225 operator :=(UnicodeString): variant

Declaration: `operator operator :=(UnicodeString): variant`  
`(const source: UnicodeString)`  
`: variant`

Visibility: default

### 37.9.226 operator :=(UTF8String): variant

Declaration: `operator operator :=(UTF8String): variant` `(const source: UTF8String)`  
`: variant`

Visibility: default

### 37.9.227 operator :=(variant): ansistring

Synopsis:

Declaration: `operator operator :=(variant): ansistring` `(const source: variant)`  
`: ansistring`

Visibility: default

Description:

Errors:

### 37.9.228 operator :=(variant): Boolean

Synopsis:

Declaration: `operator operator :=(variant): Boolean` `(const source: variant) : Boolean`

Visibility: default

Description:

Errors:

### 37.9.229 operator :=(variant): Byte

Synopsis:

Declaration: `operator operator :=(variant): Byte` `(const source: variant) : Byte`

Visibility: default

Description:

Errors:



### 37.9.230 operator :=(variant): Char

Synopsis:

Declaration: `operator operator :=(variant): Char(const source: variant) : Char`

Visibility: default

Description:

Errors:

### 37.9.231 operator :=(variant): comp

Declaration: `operator operator :=(variant): comp(const source: variant) : comp`

Visibility: default

### 37.9.232 operator :=(variant): currency

Synopsis:

Declaration: `operator operator :=(variant): currency(const source: variant)  
: currency`

Visibility: default

Description:

Errors:

### 37.9.233 operator :=(variant): double

Synopsis:

Declaration: `operator operator :=(variant): double(const source: variant) : double`

Visibility: default

Description:

Errors:

### 37.9.234 operator :=(variant): DWord

Synopsis:

Declaration: `operator operator :=(variant): DWord(const source: variant) : DWord`

Visibility: default

Description:

Errors:

### 37.9.235 operator :=(variant): extended

Declaration: `operator operator :=(variant): extended(const source: variant)  
: extended`

Visibility: default

### 37.9.236 operator :=(variant): Int64

Synopsis:

Declaration: `operator operator :=(variant): Int64(const source: variant) : Int64`

Visibility: default

Description:

Errors:

### 37.9.237 operator :=(variant): longbool

Synopsis:

Declaration: `operator operator :=(variant): longbool(const source: variant)  
: longbool`

Visibility: default

Description:

Errors:

### 37.9.238 operator :=(variant): LongInt

Synopsis:

Declaration: `operator operator :=(variant): LongInt(const source: variant) : LongInt`

Visibility: default

Description:

Errors:

### 37.9.239 operator :=(variant): olevariant

Synopsis:

Declaration: `operator operator :=(variant): olevariant(const source: variant)  
: olevariant`

Visibility: default

Description:

Errors:

#### **37.9.240 operator :=(variant): qword**

Synopsis:

Declaration: `operator operator :=(variant): qword(const source: variant) : qword`

Visibility: default

Description:

Errors:

#### **37.9.241 operator :=(variant): Real**

Declaration: `operator operator :=(variant): Real(const source: variant) : Real`

Visibility: default

#### **37.9.242 operator :=(variant): ShortInt**

Synopsis:

Declaration: `operator operator :=(variant): ShortInt(const source: variant)  
: ShortInt`

Visibility: default

Description:

Errors:

#### **37.9.243 operator :=(variant): shortstring**

Synopsis:

Declaration: `operator operator :=(variant): shortstring(const source: variant)  
: shortstring`

Visibility: default

Description:

Errors:

#### **37.9.244 operator :=(variant): single**

Declaration: `operator operator :=(variant): single(const source: variant) : single`

Visibility: default

### 37.9.245 operator :=(variant): SmallInt

Synopsis:

Declaration: `operator operator :=(variant): SmallInt(const source: variant)  
: SmallInt`

Visibility: default

Description:

Errors:

### 37.9.246 operator :=(variant): TDateTime

Synopsis:

Declaration: `operator operator :=(variant): TDateTime(const source: variant)  
: TDateTime`

Visibility: default

Description:

Errors:

### 37.9.247 operator :=(variant): TError

Synopsis:

Declaration: `operator operator :=(variant): TError(const source: variant) : TError`

Visibility: default

Description:

Errors:

### 37.9.248 operator :=(variant): unicodestring

Declaration: `operator operator :=(variant): unicodestring(const source: variant)  
: unicodestring`

Visibility: default

### 37.9.249 operator :=(variant): UTF8String

Declaration: `operator operator :=(variant): UTF8String(const source: variant)  
: UTF8String`

Visibility: default

### 37.9.250 operator :=(variant): widechar

Synopsis:

Declaration: `operator operator :=(variant): widechar(const source: variant)  
: widechar`

Visibility: default

Description:

Errors:

### 37.9.251 operator :=(variant): widestring

Synopsis:

Declaration: `operator operator :=(variant): widestring(const source: variant)  
: widestring`

Visibility: default

Description:

Errors:

### 37.9.252 operator :=(variant): Word

Synopsis:

Declaration: `operator operator :=(variant): Word(const source: variant) : Word`

Visibility: default

Description:

Errors:

### 37.9.253 operator :=(variant): wordbool

Synopsis:

Declaration: `operator operator :=(variant): wordbool(const source: variant)  
: wordbool`

Visibility: default

Description:

Errors:

### 37.9.254 operator :=(widechar): olevariant

Synopsis:

Declaration: `operator operator :=(widechar): olevariant(const source: widechar)  
: olevariant`

Visibility: default

Description:

Errors:

### 37.9.255 operator :=(widechar): variant

Synopsis:

Declaration: `operator operator :=(widechar): variant(const source: widechar)  
: variant`

Visibility: default

Description:

Errors:

### 37.9.256 operator :=(widestring): olevariant

Synopsis:

Declaration: `operator operator :=(widestring): olevariant(const source: widestring)  
: olevariant`

Visibility: default

Description:

Errors:

### 37.9.257 operator :=(widestring): variant

Synopsis:

Declaration: `operator operator :=(widestring): variant(const source: widestring)  
: variant`

Visibility: default

Description:

Errors:

### 37.9.258 operator :=(Word): olevariant

Synopsis:

Declaration: `operator operator :=(Word): olevariant(const source: Word) : olevariant`

Visibility: default

Description:

Errors:

### 37.9.259 operator :=(Word): variant

Synopsis:

Declaration: `operator operator :=(Word): variant(const source: Word) : variant`

Visibility: default

Description:

Errors:

### 37.9.260 operator :=(wordbool): olevariant

Synopsis:

Declaration: `operator operator :=(wordbool): olevariant(const source: wordbool)  
: olevariant`

Visibility: default

Description:

Errors:

### 37.9.261 operator :=(wordbool): variant

Synopsis:

Declaration: `operator operator :=(wordbool): variant(const source: wordbool)  
: variant`

Visibility: default

Description:

Errors:

### 37.9.262 operator <(variant, variant): Boolean

Synopsis: Implement < (less than) operation on variants.

Declaration: `operator operator <(variant, variant): Boolean(const op1: variant;  
const op2: variant)  
: Boolean`

Visibility: default

Description: The implementation of the "less than" comparison (<) operation is delegated to the variant manager with operation `opcmplt`.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: operator `>(variant, variant): variant` ([1209](#))

### 37.9.263 operator `<=(variant, variant): Boolean`

Synopsis: Implement `<=` (less than or equal) operation on variants.

Declaration: 

```
operator operator <=(variant, variant): Boolean(const op1: variant;
                                                    const op2: variant)
                                                    : Boolean
```

Visibility: default

Description: The implementation of the "less than or equal" comparison (<=) operation is delegated to the variant manager with operation `opcmple`.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: operator `<(variant, variant): variant` ([1209](#))

### 37.9.264 operator `=(variant, variant): Boolean`

Synopsis: Implement `=` (equality) operation on variants.

Declaration: 

```
operator operator =(variant, variant): Boolean(const op1: variant;
                                                const op2: variant)
                                                : Boolean
```

Visibility: default

Description: The implementation of the equality (=) operation is delegated to the variant manager with operation `opcmpeq`.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: operator `<(variant, variant): variant` ([1209](#))

### 37.9.265 operator `>(variant, variant): Boolean`

Synopsis: Implement `>` (greater than) operation on variants.

Declaration: 

```
operator operator >(variant, variant): Boolean(const op1: variant;
                                                const op2: variant)
                                                : Boolean
```

Visibility: default

Description: The implementation of the "greater than" comparison (>) operation is delegated to the variant manager with operation `opcmpgt`.



**Errors:** Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: operator <(variant, variant): variant ([1209](#))

### 37.9.266 operator >=(variant, variant): Boolean

**Synopsis:** Implement >= (greater than or equal) operation on variants.

**Declaration:** `operator operator >=(variant, variant): Boolean(const op1: variant;  
const op2: variant)  
: Boolean`

**Visibility:** default

**Description:** The implementation of the "greater than or equal" comparison (>=) operation is delegated to the variant manager with operation `opcmpge`.

**Errors:** Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: operator <(variant, variant): variant ([1209](#))

### 37.9.267 operator and(variant, variant): variant

**Synopsis:** Implement logical/binary and operation on variants

**Declaration:** `operator operator and(variant, variant): variant(const op1: variant;  
const op2: variant)  
: variant`

**Visibility:** default

**Description:** The implementation of the and operation is delegated to the variant manager with operation `opand`.

**Errors:** Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: operator or(variant, variant): variant ([1352](#)), operator xor(variant, variant): variant ([1353](#)), operator not(variant): variant ([1352](#))

### 37.9.268 operator div(variant, variant): variant

**Synopsis:** Implement div (integer division) operation on variants.

**Declaration:** `operator operator div(variant, variant): variant(const op1: variant;  
const op2: variant)  
: variant`

**Visibility:** default

**Description:** The implementation of the integer division `Div` operation is delegated to the variant manager with operation `opintdivide`.

**Errors:** Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: operator mod(variant, variant): variant ([1352](#))

**37.9.269 operator mod(variant, variant): variant**

Synopsis: Implement `mod` (modulo) operation on variants.

Declaration: `operator operator mod(variant, variant): variant(const op1: variant;  
const op2: variant)  
: variant`

Visibility: default

Description: The implementation of the modulo `Mod` operation is delegated to the variant manager with operation `opModulus`.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: `operator div(variant, variant): variant` ([1351](#))

**37.9.270 operator not(variant): variant**

Synopsis: Implement logical/binary `not` operation on variants

Declaration: `operator operator not(variant): variant(const op: variant) : variant`

Visibility: default

Description: The implementation of the `not` operation is delegated to the variant manager with operation `opnot`.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: `operator and(variant, variant): variant` ([1351](#)), `operator or(variant, variant): variant` ([1352](#)), `operator xor(variant, variant): variant` ([1353](#))

**37.9.271 operator or(variant, variant): variant**

Synopsis: Implement logical/binary `or` operation on variants

Declaration: `operator operator or(variant, variant): variant(const op1: variant;  
const op2: variant)  
: variant`

Visibility: default

Description: The implementation of the `or` operation is delegated to the variant manager with operation `opor`.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: `operator and(variant, variant): variant` ([1351](#)), `operator xor(variant, variant): variant` ([1353](#)), `operator not(variant): variant` ([1352](#))

**37.9.272 operator shl(variant, variant): variant**

Synopsis: Implement binary `shl` operation on variants.

Declaration: `operator operator shl(variant, variant): variant(const op1: variant;  
const op2: variant)  
: variant`

Visibility: default

Description: The implementation of the `shl` operation is delegated to the variant manager with operation `opshiftright`.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: `operator shr(variant, variant): variant` ([1353](#))

**37.9.273 operator shr(variant, variant): variant**

Synopsis: Implement binary `shr` operation on variants.

Declaration: `operator operator shr(variant, variant): variant(const op1: variant;  
const op2: variant)  
: variant`

Visibility: default

Description: The implementation of the `shr` operation is delegated to the variant manager with operation `opshiftright`.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: `operator shl(variant, variant): variant` ([1353](#))

**37.9.274 operator xor(variant, variant): variant**

Synopsis: Implement logical/binary `xor` operation on variants

Declaration: `operator operator xor(variant, variant): variant(const op1: variant;  
const op2: variant)  
: variant`

Visibility: default

Description: The implementation of the `xor` operation is delegated to the variant manager with operation `opxor`.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: `operator or(variant, variant): variant` ([1352](#)), `operator and(variant, variant): variant` ([1351](#)), `operator not(variant): variant` ([1352](#))

**37.9.275 Ord**

Synopsis: Return ordinal value of an ordinal type.

Declaration: `function Ord(X: TOrdinal) : LongInt`

Visibility: default

Description: `Ord` returns the Ordinal value of a ordinal-type variable `X`.

Historical note:

Originally, Pascal did not have typecasts and `ord` was a necessary function in order to do certain operations on non-integer ordinal types. With the arrival of typecasting a generic approach became possible, making `ord` mostly obsolete. However `ord` is not considered deprecated and remains in wide use today.

Errors: None.

See also: `Chr` ([1269](#)), `Succ` ([1386](#)), `Pred` ([1357](#)), `High` ([1305](#)), `Low` ([1320](#))

**Listing:** `./refex/ex45.pp`

**Program** `Example45`;

*{ Program to demonstrate the Ord, Pred, Succ functions. }*

**Type**

`TEnum = (Zero, One, Two, Three, Four);`

**Var**

`X : Longint;`

`Y : TEnum;`

**begin**

`X:=125;`

`WriteLn (Ord(X)); { Prints 125 }`

`X:=Pred(X);`

`WriteLn (Ord(X)); { prints 124 }`

`Y:= One;`

`WriteLn (Ord(y)); { Prints 1 }`

`Y:=Succ(Y);`

`WriteLn (Ord(Y)); { Prints 2 }`

**end.**

**37.9.276 Pack**

Synopsis: Create packed array from normal array

Declaration: `procedure Pack(const A: UnpackedArrayType; StartIndex: TIndexType;  
out Z: PackedArrayType)`

Visibility: default

Description: `Pack` will copy the elements of an unpacked array (`A`) to a packed array (`Z`). It will start the copy at the index denoted by `StartIndex`. The type of the index variable `StartIndex` must match the type of the index of `A`. The elements are always transferred to the beginning of the packed array `Z`. (i.e. it starts at `Low(Z)`).

Obviously, the type of the elements of the arrays `A` and `Z` must match.

See also: `unpack` ([1397](#))

**37.9.277 Paramcount**

Synopsis: Return number of command-line parameters passed to the program.

Declaration: `function Paramcount : LongInt`

Visibility: default

Description: `Paramcount` returns the number of command-line arguments. If no arguments were given to the running program, 0 is returned.

Errors: None.

See also: `Paramstr` ([1355](#))

**Listing:** `./refex/ex46.pp`

---

**Program** `Example46`;

```
{ Program to demonstrate the ParamCount and ParamStr functions. }
Var
  I : Longint;

begin
  Writeln (paramstr(0), ' : Got ', ParamCount, ' command-line parameters: ');
  For i:=1 to ParamCount do
    Writeln (ParamStr (i));
end.
```

---

**37.9.278 ParamStr**

Synopsis: Return value of a command-line argument.

Declaration: `function ParamStr(l: LongInt) : String`

Visibility: default

Description: `Paramstr` returns the `L`-th command-line argument. `L` must be between 0 and `Paramcount`, these values included. The zeroth argument is the path and file name with which the program was started.

The command-line parameters will be truncated to a length of 255, even though the operating system may support bigger command-lines. The `Objpas` unit (used in `objfpc` or `delphi` mode) defines versions of `Paramstr` which return the full-length command-line arguments, using `ansistrings`.

In the interest of portability, the `ParamStr` function tries to behave the same on all operating systems: like the original `ParamStr` function in Turbo Pascal. This means even on Unix, `paramstr(0)` returns the full path to the program executable. A notable exception is Mac OS X, where the return value depends on how the application was started. It may be that just the name of the application is returned (in case of a command-line launch)

In general, it's a bad idea to rely on the location of the binary. Often, this goes against best OS practices. Configuration data should (or can) not be stored next to the binary, but on designated locations. What locations these are, is very much operating system dependent. Therefore, `ParamStr(0)` should be used with care.

For an example, see `Paramcount` ([1355](#)).

Errors: None.

See also: `Paramcount` ([1355](#))



```

function Pos(w: UnicodeString;const v: Variant) : SizeInt
function Pos(v: Variant;const c: Char) : SizeInt
function Pos(v: Variant;const s: ShortString) : SizeInt
function Pos(v: Variant;const a: AnsiString) : SizeInt
function Pos(v: Variant;const w: WideString) : SizeInt
function Pos(v: Variant;const w: UnicodeString) : SizeInt
function Pos(v1: Variant;const v2: Variant) : SizeInt

```

Visibility: default

Description: `Pos` returns the index of `Substr` in `S`, if `S` contains `Substr`. In case `Substr` isn't found, 0 is returned. The search is case-sensitive.

Errors: None

See also: `Length` ([1317](#)), `Copy` ([1277](#)), `Delete` ([1280](#)), `Insert` ([1312](#))

**Listing:** `./refex/ex48.pp`

---

**Program** `Example48`;

*{ Program to demonstrate the Pos function. }*

**Var**

`S : String;`

**begin**

`S:= 'The first space in this sentence is at position : ';`

`Writeln (S,pos(' ',S));`

`S:= 'The last letter of the alphabet doesn't appear in this sentence ';`

`If (Pos ('Z',S)=0) and (Pos ('z',S)=0) then`

`Writeln (S);`

**end.**

---

### 37.9.281 `Pred`

Synopsis: Return previous element for an ordinal type.

Declaration: `function Pred(X: TOrdinal) : TOrdinal`

Visibility: default

Description: `Pred` returns the element that precedes the element that was passed to it. If it is applied to the first value of the ordinal type, and the program was compiled with range checking on (`{ $R+ }`), then a run-time error will be generated.

for an example, see `Ord` ([1354](#))

Errors: Run-time error 201 is generated when the result is out of range.

See also: `Ord` ([1354](#)), `Pred` ([1357](#)), `High` ([1305](#)), `Low` ([1320](#))

### 37.9.282 `prefetch`

Synopsis: Prefetch a memory location

Declaration: `procedure prefetch(const mem)`

Visibility: default

Description: `Prefetch` can be used to optimize the CPU behaviour by already loading a memory location. It is mainly used as a hint for those processors that support it.

Errors: None.

### 37.9.283 ptr

Synopsis: Combine segment and offset to pointer

Declaration: `function ptr(sel: LongInt; off: LongInt) : farpointer`

Visibility: default

Description: `Ptr` returns a pointer, pointing to the address specified by segment `Sel` and offset `Off`.

Remark:

1. In the 32-bit flat-memory model supported by Free Pascal, this function is obsolete.
2. The returned address is simply the offset.

Errors: None.

See also: `Addr` ([1259](#))

Listing: `./refex/ex59.pp`

Program Example59;

```
{ Program to demonstrate the Ptr (compability) function.
}
```

```
type pString = ^String;
```

```
Var P : pString;
    S : String;
```

```
begin
  S:= 'Hello , World !';
  P:=pString(Ptr(Seg(S),Longint(Ofs(S))));
  {P now points to S !}
  Writeln (P^);
end.
```

### 37.9.284 RaiseList

Synopsis: List of currently raised exceptions.

Declaration: `function RaiseList : PExceptObject`

Visibility: default

Description: `RaiseList` returns a pointer to the list of currently raised exceptions (i.e. a pointer to the first exception block).

Errors:



**37.9.285 Random**

Synopsis: Generate random number

Declaration: `function Random(l: LongInt) : LongInt`  
`function Random(l: Int64) : Int64`  
`function Random : extended`

Visibility: default

Description: `Random` returns a random number larger or equal to 0 and strictly less than `L`. If the argument `L` is omitted, a Real number between 0 and 1 is returned. (0 included, 1 excluded)

Errors: None.

See also: `Randomize` ([1359](#))

**Listing:** `./refex/ex49.pp`

**Program** `Example49`;

*{ Program to demonstrate the Random and Randomize functions. }*

**Var** `I, Count, guess : Longint;`  
`R : Real;`

**begin**

`Randomize`; *{ This way we generate a new sequence every time  
the program is run }*

`Count:=0;`

**For** `i:=1 to 1000 do`

`If Random>0.5 then inc(Count);`

`WriteLn ( 'Generated ', Count, ' numbers > 0.5 ' );`

`WriteLn ( 'out of 1000 generated numbers. ' );`

`count:=0;`

**For** `i:=1 to 5 do`

`begin`

`write ( 'Guess a number between 1 and 5 : ' );`

`readln(Guess);`

`If Guess=Random(5)+1 then inc(count);`

`end;`

`WriteLn ( 'You guessed ', Count, ' out of 5 correct. ' );`

**end.**

**37.9.286 Randomize**

Synopsis: Initialize random number generator

Declaration: `procedure Randomize`

Visibility: default

Description: `Randomize` initializes the random number generator of Free Pascal, by giving a value to `Randseed`, calculated with the system clock.

For an example, see `Random` ([1359](#)).

Errors: None.

See also: `Random` ([1359](#))

**37.9.287 Read**

Synopsis: Read from a text file into variable

Declaration: `procedure Read(var F: Text; Args: Arguments)`  
`procedure Read(Args: Arguments)`

Visibility: default

Description: `Read` reads one or more values from a file `F`, and stores the result in `V1`, `V2`, etc.; If no file `F` is specified, then standard input is read. If `F` is of type `Text`, then the variables `V1`, `V2` etc. must be of type `Char`, `Integer`, `Real`, `String`. If `F` is a typed file, then each of the variables must be of the type specified in the declaration of `F`. Untyped files are not allowed as an argument.

In earlier versions of FPC, it was also allowed to read `Pchar` null-terminated strings, but this has been removed, since there is no buffer checking possible.

Errors: If no data is available, a run-time error is generated. This behavior can be controlled with the `{SI}` compiler switch.

See also: `ReadLn` ([1361](#)), `Blockread` ([1266](#)), `Write` ([1402](#)), `Blockwrite` ([1267](#))

**Listing:** `./refex/ex50.pp`

---

**Program** `Example50`;

*{ Program to demonstrate the Read(Ln) function. }*

```

Var S : String;
      C : Char;
      F : File of char;

begin
  Assign (F, 'ex50.pp');
  Reset (F);
  C:= 'A';
  Writeln ('The characters before the first space in ex50.pp are : ');
  While not Eof(f) and (C<> ' ') do
    Begin
      Read (F,C);
      Write (C);
    end;
  Writeln;
  Close (F);
  Writeln ('Type some words. An empty line ends the program. ');
  repeat
    ReadLn (S);
  until S= '';
end.
```

---

**37.9.288 ReadBarrier**

Synopsis: Memory Read Barrier

Declaration: `procedure ReadBarrier`

Visibility: default

**Description:** `ReadBarrier` is a low-level instruction to force a read barrier in the CPU: all memory reads before the instruction will be finished before this instruction, before memory reads after the instruction occur.

See also: `ReadDependencyBarrier` ([1361](#)), `ReadWriteBarrier` ([1362](#)), `WriteBarrier` ([1403](#))

### 37.9.289 `ReadDependencyBarrier`

**Synopsis:** Memory Read Dependency Barrier

**Declaration:** `procedure ReadDependencyBarrier`

**Visibility:** default

**Description:** `ReadDependencyBarrier` is a low-level instruction to force a read barrier in the CPU: all memory reads (loads) depending on previous loads are separate from the ones following the instruction.

See also: `ReadBarrier` ([1360](#)), `ReadWriteBarrier` ([1362](#)), `WriteBarrier` ([1403](#))

### 37.9.290 `ReadLn`

**Synopsis:** Read from a text file into variable and goto next line

**Declaration:** `procedure ReadLn (var F: Text; Args: Arguments)`  
`procedure ReadLn (Args: Arguments)`

**Visibility:** default

**Description:** `Read` reads one or more values from a file `F`, and stores the result in `V1`, `V2`, etc. After that it goes to the next line in the file. The end of the line is marked by the `LineEnding` character sequence (which is platform dependent). The end-of-line marker is not considered part of the line and is ignored.

If no file `F` is specified, then standard input is read. The variables `V1`, `V2` etc. must be of type `Char`, `Integer`, `Real`, `String` or `PChar`.

For an example, see `Read` ([1360](#)).

**Errors:** If no data is available, a run-time error is generated. This behavior can be controlled with the `{SI}` compiler switch.

See also: `Read` ([1360](#)), `Blockread` ([1266](#)), `Write` ([1402](#)), `Blockwrite` ([1267](#))

### 37.9.291 `ReadStr`

**Synopsis:** Read variables from a string

**Declaration:** `procedure ReadStr (const S: String; Args: Arguments)`

**Visibility:** default

**Description:** `ReadStr` behaves like `Read` ([1360](#)), except that it reads its input from the string variable `S` instead of a file. Semantically, the `ReadStr` call is equivalent to writing the string to a file using the `Write` call, and then reading them into the various arguments `Arg` using the `Read` call from the same file:

```

var
  F : Text;
begin
  Rewrite(F);
  Write(F,S);
  Close(F);
  Reset(F);
  Read(F,Args);
  Close(F);
end;

```

Obviously, the `ReadStr` call does not use a temporary file.

`ReadStr` is defined in the ISO Extended Pascal standard. More information on the allowed arguments and the behaviour of the arguments can be found in the description of `Read` (1360).

See also: `Read` (1360), `WriteStr` (1404), `Write` (1402)

### 37.9.292 ReadWriteBarrier

Synopsis: Memory read/write barrier

Declaration: `procedure ReadWriteBarrier`

Visibility: default

Description: `ReadWriteBarrier` is a low-level instruction to force a read/write barrier in the CPU: both read (Loads) and write (stores) operations before and after the barrier are separate.

See also: `ReadBarrier` (1360), `ReadDependencyBarrier` (1361), `WriteBarrier` (1403)

### 37.9.293 Real2Double

Synopsis: Convert Turbo Pascal style real to double.

Declaration: `function Real2Double(r: real48) : double`

Visibility: default

Description: The `Real2Double` function converts a Turbo Pascal style real (6 bytes long) to a native Free Pascal double type. It can be used e.g. to read old binary TP files with FPC and convert them to Free Pascal binary files.

Note that the assignment operator has been overloaded so a `Real48` type can be assigned directly to a double or extended.

Errors: None.

**Listing:** `./refex/ex110.pp`

---

```

program Example110;

```

```

  { Program to demonstrate the Real2Double function. }

```

```

Var

```

```

  i : integer;
  R : Real48;
  D : Double;

```

```

E : Extended;
F : File of Real48;

begin
    Assign(F, 'reals.dat');
    Reset(f);
    For I:=1 to 10 do
        begin
            Read(F,R);
            D:=Real2Double(R);
            Writeln('Real ',i,' : ',D);
            D:=R;
            Writeln('Real (direct to double) ',i,' : ',D);
            E:=R;
            Writeln('Real (direct to Extended) ',i,' : ',E);
        end;
    Close(f);
end.

```

---

### 37.9.294 ReAllocMem

Synopsis: Re-allocate memory on the heap

Declaration: `function ReAllocMem(var p: pointer;Size: PtrUInt) : pointer`

Visibility: default

Description: `ReAllocMem` resizes the memory pointed to by `P` so it has size `Size`. The value of `P` may change during this operation. The contents of the memory pointed to by `P` (if any) will be copied to the new location, but may be truncated if the newly allocated memory block is smaller in size. If a larger block is allocated, only the used memory is initialized, extra memory will not be zeroed out.

Note that `P` may be `nil`, in that case the behaviour of `ReAllocMem` is equivalent to `Getmem`.

See also: `GetMem` ([1299](#)), `FreeMem` ([1297](#))

### 37.9.295 ReAllocMemory

Synopsis: Alias for `ReAllocMem` ([1363](#))

Declaration: `function ReAllocMemory(var p: pointer;Size: PtrUInt) : pointer`

Visibility: default

Description: `ReAllocMemory` is an alias for `ReAllocMem` ([1363](#)).

See also: `ReAllocMem` ([1363](#))

### 37.9.296 ReleaseExceptionObject

Synopsis: Decrease the reference count of the current exception object.

Declaration: `procedure ReleaseExceptionObject`

Visibility: default

**Description:** `ReleaseExceptionObject` decreases the reference count of the current exception object. This should be called whenever a reference to the exception object was obtained via the `AcquireExceptionObject` (1258) call.

Calling this method is only valid within an `except` block.

**Errors:** If there is no current exception object, a run-time error 231 will occur.

See also: `AcquireExceptionObject` (1258)

### 37.9.297 Rename

**Synopsis:** Rename file on disk

**Declaration:**

```

procedure Rename(var f: File; const s: String)
procedure Rename(var f: File; p: PChar)
procedure Rename(var f: File; c: Char)
procedure Rename(var t: Text; const s: String)
procedure Rename(var t: Text; p: PChar)
procedure Rename(var t: Text; c: Char)

```

**Visibility:** default

**Description:** `Rename` changes the name of the assigned file `F` to `S`. `F` must be assigned, but not opened.

**Errors:** Depending on the state of the `{SI}` switch, a runtime error can be generated if there is an error. In the `{SI-}` state, use `IOResult` to check for errors.

See also: `Erase` (1287)

**Listing:** `./refex/ex77.pp`

---

**Program** `Example77`;

```

{ Program to demonstrate the Rename function. }
Var F : Text;

begin
  Assign (F, paramstr(1));
  Rename (F, paramstr(2));
end.

```

---

### 37.9.298 Reset

**Synopsis:** Open file for reading

**Declaration:**

```

procedure Reset(var f: File; l: LongInt)
procedure Reset(var f: File)
procedure Reset(var f: TypedFile)
procedure Reset(var t: Text)

```

**Visibility:** default

**Description:** `Reset` opens a file `F` for reading. `F` can be any file type. If `F` is a text file, or refers to standard I/O (e.g. `”) then it is opened read-only, otherwise it is opened using the mode specified in filemode. If F is an untyped file, the record size can be specified in the optional parameter L. A default value of 128 is used. File sharing is not taken into account when calling Reset.`

**Errors:** Depending on the state of the `{SI}` switch, a runtime error can be generated if there is an error. In the `{SI-}` state, use `IOResult` to check for errors.

See also: [Rewrite \(1365\)](#), [Assign \(1262\)](#), [Close \(1269\)](#), [Append \(1260\)](#)

**Listing:** `./refex/ex51.pp`

---

```

Program Example51;

{ Program to demonstrate the Reset function. }

Function FileExists (Name : String) : boolean;

Var F : File;

begin
  { $i- }
  Assign (F, Name);
  Reset (F);
  { $!+ }
  FileExists := (IOResult=0) and (Name<>' ');
  Close (f);
end;

begin
  If FileExists (Paramstr(1)) then
    Writeln ('File found')
  else
    Writeln ('File NOT found');
end.

```

---

### 37.9.299 ResumeThread

**Synopsis:** Resume a suspended thread.

**Declaration:** `function ResumeThread(threadHandle: TThreadID) : DWord`

**Visibility:** default

**Description:** `ResumeThread` causes a suspended thread (using `SuspendThread (1387)`) to resume its execution. The thread is identified with its handle or ID `threadHandle`.

The function returns zero if successful. A nonzero return value indicates failure.

**Errors:** If a failure occurred, a nonzero result is returned. The meaning is system dependent.

See also: [SuspendThread \(1387\)](#), [KillThread \(1316\)](#)

### 37.9.300 Rewrite

**Synopsis:** Open file for writing

**Declaration:** `procedure Rewrite(var f: File; l: LongInt)`  
`procedure Rewrite(var f: File)`  
`procedure Rewrite(var f: TypedFile)`  
`procedure Rewrite(var t: Text)`

**Visibility:** default

**Description:** `Rewrite` opens a file `F` for writing. `F` can be any file type. If `F` is an untyped or typed file, then it is opened for reading and writing. If `F` is an untyped file, the record size can be specified in the optional parameter `L`. Default a value of 128 is used. if `Rewrite` finds a file with the same name as `F`, this file is truncated to length 0. If it doesn't find such a file, a new file is created. Contrary to Turbo Pascal, Free Pascal opens the file with mode `fmoutput`. If it should be opened in `fminout` mode, an extra call to `Reset` (1364) is needed. File sharing is not taken into account when calling `Rewrite`.

**Errors:** Depending on the state of the `{SI}` switch, a runtime error can be generated if there is an error. In the `{SI-}` state, use `IOResult` to check for errors.

See also: `Reset` (1364), `Assign` (1262), `Close` (1269), `Flush` (1296), `Append` (1260)

**Listing:** `./refex/ex52.pp`

**Program** `Example52`;

*{ Program to demonstrate the Rewrite function. }*

**Var** `F : File`;  
     `I : longint`;

**begin**

`Assign (F, 'Test.tmp');`  
     *{ Create the file. Recordsize is 4 }*  
     `Rewrite (F, Sizeof(I));`  
     **For** `I:=1 to 10 do`  
         `BlockWrite (F,I,1);`  
     `close (f);`  
     *{ F contains now a binary representation of*  
         *10 longints going from 1 to 10 }*

**end.**

### 37.9.301 rmdir

**Synopsis:** Remove directory when empty.

**Declaration:** `procedure rmdir(const s: String);` Overload

**Visibility:** default

**Description:** `Rmdir` removes the directory `S`.

**Errors:** Depending on the state of the `{SI}` switch, a runtime error can be generated if there is an error. In the `{SI-}` state, use `IOResult` to check for errors.

See also: `Chdir` (1268), `Mkdir` (1322)

**Listing:** `./refex/ex53.pp`

**Program** `Example53`;

*{ Program to demonstrate the Mkdir and Rmdir functions. }*

**Const** `D : String[8] = 'TEST.DIR';`

**Var** `S : String`;



```

begin
  Writeln ( 'Making directory ',D);
  Mkdir (D);
  Writeln ( 'Changing directory to ',D);
  ChDir (D);
  GetDir (0,S);
  Writeln ( 'Current Directory is : ',S);
  Writeln ( 'Going back');
  ChDir ( '.. ');
  Writeln ( 'Removing directory ',D);
  Rmdir (D);
end.

```

---

### 37.9.302 RolByte

Synopsis: Rotate bits of a byte value to the left

Declaration: `function RolByte(const AValue: Byte) : Byte`  
`function RolByte(const AValue: Byte;Dist: Byte) : Byte`

Visibility: default

Description: `RolByte` rotates the bits of the byte `AValue` with `Dist` positions to the left. If `Dist` is not specified, then 1 is assumed.

Errors: None.

See also: `RorByte` ([1368](#)), `RolWord` ([1368](#)), `RolDWord` ([1367](#)), `RolQWord` ([1367](#))

### 37.9.303 RolDWord

Synopsis: Rotate bits of a DWord (cardinal) value to the left

Declaration: `function RolDWord(const AValue: DWord) : DWord`  
`function RolDWord(const AValue: DWord;Dist: Byte) : DWord`

Visibility: default

Description: `RolDWord` rotates the bits of the DWord (cardinal) `AValue` with `Dist` positions to the left. If `Dist` is not specified, then 1 is assumed.

Errors: None.

See also: `RolByte` ([1367](#)), `RolWord` ([1368](#)), `RorDWord` ([1368](#)), `RolQWord` ([1367](#))

### 37.9.304 RolQWord

Synopsis: Rotate bits of a QWord (64-bit) value to the left

Declaration: `function RolQWord(const AValue: QWord) : QWord`  
`function RolQWord(const AValue: QWord;Dist: Byte) : QWord`

Visibility: default

Description: `RorQWord` rotates the bits of the QWord (64-bit) `AValue` with `Dist` positions to the left. If `Dist` is not specified, then 1 is assumed.

Errors: None.

See also: [RolByte \(1367\)](#), [RolWord \(1368\)](#), [RolDWord \(1367\)](#), [RorQWord \(1369\)](#)

### 37.9.305 RolWord

Synopsis: Rotate bits of a word value to the left

Declaration: `function RolWord(const AValue: Word) : Word`  
`function RolWord(const AValue: Word;Dist: Byte) : Word`

Visibility: default

Description: `RolWord` rotates the bits of the word `AValue` with `Dist` positions to the right. If `Dist` is not specified, then 1 is assumed.

Errors: None.

See also: [RolByte \(1367\)](#), [RorWord \(1369\)](#), [RolDWord \(1367\)](#), [RolQWord \(1367\)](#)

### 37.9.306 RorByte

Synopsis: Rotate bits of a byte value to the right

Declaration: `function RorByte(const AValue: Byte) : Byte`  
`function RorByte(const AValue: Byte;Dist: Byte) : Byte`

Visibility: default

Description: `RorByte` rotates the bits of the byte `AValue` with `Dist` positions to the right. If `Dist` is not specified, then 1 is assumed.

Errors: None.

See also: [RolByte \(1367\)](#), [RorWord \(1369\)](#), [RorDWord \(1368\)](#), [RorQWord \(1369\)](#)

### 37.9.307 RorDWord

Synopsis: Rotate bits of a DWord (cardinal) value to the right

Declaration: `function RorDWord(const AValue: DWord) : DWord`  
`function RorDWord(const AValue: DWord;Dist: Byte) : DWord`

Visibility: default

Description: `RorDWord` rotates the bits of the DWord (cardinal) `AValue` with `Dist` positions to the right. If `Dist` is not specified, then 1 is assumed.

Errors: None.

See also: [RorByte \(1368\)](#), [RolDWord \(1367\)](#), [RorWord \(1369\)](#), [RorQWord \(1369\)](#)

**37.9.308 RorQWord**

Synopsis: Rotate bits of a QWord (64-bit) value to the right

Declaration: `function RorQWord(const AValue: QWord) : QWord`  
`function RorQWord(const AValue: QWord;Dist: Byte) : QWord`

Visibility: default

Description: `RorQWord` rotates the bits of the QWord (64-bit) `AValue` with `Dist` positions to the right. If `Dist` is not specified, then 1 is assumed.

Errors: None.

See also: `RorByte` ([1368](#)), `RorWord` ([1369](#)), `RorDWord` ([1368](#)), `RolQWord` ([1367](#))

**37.9.309 RorWord**

Synopsis: Rotate bits of a word value to the right

Declaration: `function RorWord(const AValue: Word) : Word`  
`function RorWord(const AValue: Word;Dist: Byte) : Word`

Visibility: default

Description: `RorWord` rotates the bits of the word `AValue` with `Dist` positions to the right. If `Dist` is not specified, then 1 is assumed.

Errors: None.

See also: `RorByte` ([1368](#)), `RolWord` ([1368](#)), `RorDWord` ([1368](#)), `RorQWord` ([1369](#))

**37.9.310 round**

Synopsis: Round floating point value to nearest integer number.

Declaration: `function round(d: ValReal) : Int64`

Visibility: default

Description: `Round` rounds `X` to the closest integer, which may be bigger or smaller than `X`.

In the case of .5, the algorithm uses "banker's rounding": .5 values are always rounded towards the even number.

Errors: None.

See also: `Frac` ([1297](#)), `Int` ([1312](#)), `Trunc` ([1392](#))

**Listing:** `./refex/ex54.pp`

**Program** `Example54`;

*{ Program to demonstrate the Round function. }*

**begin**

```
WriteLn (Round(1234.56)); { Prints 1235 }
WriteLn (Round(-1234.56)); { Prints -1235 }
WriteLn (Round(12.3456)); { Prints 12 }
WriteLn (Round(-12.3456)); { Prints -12 }
```

```

WriteIn (Round(2.5));      { Prints 2 (down) }
WriteIn (Round(3.5));      { Prints 4 (up)   }

end.

```

---

### 37.9.311 RTLEventCreate

**Synopsis:** Create a new RTL event

**Declaration:** `function RTLEventCreate : PRTLEvent`

**Visibility:** default

**Description:** `RTLEventCreate` creates and initializes a new RTL event. RTL events are used to notify other threads that a certain condition is met, and to notify other threads of condition changes (conditional variables).

The function returns an initialized RTL event, which must be disposed of with `RTLEventdestroy` ([1370](#))

`RTLEvent` is used mainly for the `synchronize` method.

See also: `RTLEventDestroy` ([1370](#)), `RTLEventSetEvent` ([1371](#)), `RTLEventReSetEvent` ([1370](#)), `RTLEventWaitFor` ([1371](#))

### 37.9.312 RTLeventdestroy

**Synopsis:** Destroy a RTL Event

**Declaration:** `procedure RTLeventdestroy(state: PRTLEvent)`

**Visibility:** default

**Description:** `RTLeventdestroy` destroys the RTL event `State`. After a call to `RTLeventdestroy`, the `State` RTL event may no longer be used.

See also: `RTLEventCreate` ([1370](#)), `RTLEventResetEvent` ([1370](#)), `RTLEventSetEvent` ([1371](#))

### 37.9.313 RTLeventResetEvent

**Synopsis:** Reset an event

**Declaration:** `procedure RTLeventResetEvent(state: PRTLEvent)`

**Visibility:** default

**Description:** `RTLeventResetEvent` resets the event: this should be used to undo the signaled state of an event. Resetting an event that is not set (or was already reset) has no effect.

See also: `RTLEventCreate` ([1370](#)), `RTLEventDestroy` ([1370](#)), `RTLEventSetEvent` ([1371](#)), `RTLEventWaitFor` ([1371](#))

### 37.9.314 RTLeventSetEvent

Synopsis: Notify threads of the event.

Declaration: `procedure RTLeventSetEvent (state: PRTLEvent)`

Visibility: default

Description: `RTLeventSetEvent` notifies other threads which are listening, that the event has occurred.

See also: `RTLEventCreate` ([1370](#)), `RTLEventResetEvent` ([1370](#)), `RTLEventDestroy` ([1370](#)), `RTLEventWaitFor` ([1371](#))

### 37.9.315 RTLeventsync

Synopsis: Obsolete. Don't use

Declaration: `procedure RTLeventsync (m: trtlmethod; p: TProcedure)`

Visibility: default

Description: `RTLeventsync` is obsolete, don't use it.

### 37.9.316 RTLeventWaitFor

Synopsis: Wait for an event.

Declaration: `procedure RTLeventWaitFor (state: PRTLEvent)`  
`procedure RTLeventWaitFor (state: PRTLEvent; timeout: LongInt)`

Visibility: default

Description: `RTLeventWaitFor` suspends the thread till the event occurs. The event will occur when another thread calls `RTLEventSetEvent` ([1371](#)) on `State`.

By default, the thread will be suspended indefinitely. However, if `TimeOut` is specified, then the thread will resume after timeout milliseconds have elapsed.

See also: `RTLEventCreate` ([1370](#)), `RTLEventDestroy` ([1370](#)), `RTLEventSetEvent` ([1371](#)), `RTLEventWaitFor` ([1371](#))

### 37.9.317 RunError

Synopsis: Generate a run-time error.

Declaration: `procedure RunError (w: Word)`  
`procedure RunError`

Visibility: default

Description: `Runerror` stops the execution of the program, and generates a run-time error `ErrorCode`.

Errors: None.

See also: `Exit` ([1289](#)), `Halt` ([1303](#))

**Listing:** `./refex/ex55.pp`

---

**Program** Example55;

*{ Program to demonstrate the RunError function. }*

**begin**

*{ The program will stop and emit a run-error 106 }*

**RunError** (106);

**end.**

---

### 37.9.318 Seek

Synopsis: Set file position

Declaration: `procedure Seek(var f: File; Pos: Int64)`

Visibility: default

Description: `Seek` sets the file-pointer for file `F` to record `Nr. Count`. The first record in a file has `Count=0`. `F` can be any file type, except `Text`. If `F` is an untyped file, with no record size specified in `Reset` (1364) or `Rewrite` (1365), 128 is assumed.

Errors: Depending on the state of the `{SI}` switch, a runtime error can be generated if there is an error. In the `{SI-}` state, use `IOResult` to check for errors.

See also: `Eof` (1286), `SeekEof` (1373), `SeekEoln` (1373)

**Listing:** ./refex/ex56.pp

---

**Program** Example56;

*{ Program to demonstrate the Seek function. }*

**Var**

**F : File;**

**l, j : longint;**

**begin**

*{ Create a file and fill it with data }*

**Assign** (F, 'test.tmp');

**Rewrite**(F); *{ Create file }*

**Close**(f);

**FileMode**:=2;

**ReSet** (F, **Sizeof**(i)); *{ Opened read/write }*

**For** l:=0 **to** 10 **do**

**BlockWrite** (F, l, 1);

*{ Go Back to the beginning of the file }*

**Seek**(F, 0);

**For** l:=0 **to** 10 **do**

**begin**

**BlockRead** (F, j, 1);

**If** j<>l **then**

**WriteLn** ('Error: expected ', i, ', got ', j);

**end;**

**Close** (f);

**end.**

---

**37.9.319 SeekEOF**

Synopsis: Set file position to end of file

Declaration: `function SeekEOF (var t: Text) : Boolean`  
`function SeekEOF : Boolean`

Visibility: default

Description: `SeekEof` returns `True` if the file-pointer is at the end of the file. It ignores all whitespace. Calling this function has the effect that the file-position is advanced until the first non-whitespace character or the end-of-file marker is reached.

If the end-of-file marker is reached, `True` is returned. Otherwise, `False` is returned.

If the parameter `F` is omitted, standard `Input` is assumed.

**Remark:** The `SeekEOF` function can only be used on real textfiles: when assigning the file to other kinds of (virtual) text files, the function may fail, although it will perform a number of tests to guard against wrong usage.

Errors: A run-time error is generated if the file `F` isn't opened.

See also: `Eof` ([1286](#)), `SeekEoln` ([1373](#)), `Seek` ([1372](#))

**Listing:** `./refex/ex57.pp`

---

**Program** `Example57`;

```
{ Program to demonstrate the SeekEof function. }
Var C : Char;

begin
  { this will print all characters from standard input except
    Whitespace characters. }
  While Not SeekEof do
    begin
      Read (C);
      Write (C);
    end;
end.
```

---

**37.9.320 SeekEOLn**

Synopsis: Set file position to end of line

Declaration: `function SeekEOLn (var t: Text) : Boolean`  
`function SeekEOLn : Boolean`

Visibility: default

Description: `SeekEoln` returns `True` if the file-pointer is at the end of the current line. It ignores all whitespace. Calling this function has the effect that the file-position is advanced until the first non-whitespace character or the end-of-line marker is reached. If the end-of-line marker is reached, `True` is returned. Otherwise, `False` is returned. The end-of-line marker is defined as `#10`, the `LineFeed` character. If the parameter `F` is omitted, standard `Input` is assumed.

Errors: A run-time error is generated if the file `F` isn't opened.

See also: `Eof` ([1286](#)), `SeekEof` ([1373](#)), `Seek` ([1372](#))

**Listing:** ./refex/ex58.pp

**Program** Example58;

---

```
{ Program to demonstrate the SeekEoln function. }
Var
  C : Char;

begin
  { This will read the first line of standard output and print
    all characters except whitespace. }
  While not SeekEoln do
    Begin
      Read (c);
      Write (c);
    end;
end.
```

---

### 37.9.321 Seg

Synopsis: Return segment

Declaration: `function Seg(var X) : LongInt`

Visibility: default

Description: `Seg` returns the segment of the address of a variable. This function is only supported for compatibility. In Free Pascal, it returns always 0, since Free Pascal uses a flat 32/64 bit memory model. In such a memory model segments have no meaning.

Errors: None.

See also: `DSeg` ([1282](#)), `CSeg` ([1278](#)), `Ofs` ([1325](#)), `Ptr` ([1358](#))

**Listing:** ./refex/ex60.pp

**Program** Example60;

---

```
{ Program to demonstrate the Seg function. }
Var
  W : Word;

begin
  W:=Seg(W); { W contains its own Segment}
end.
```

---

### 37.9.322 Setjmp

Synopsis: Save current execution point.

Declaration: `function Setjmp(var S: jmp_buf) : LongInt`

Visibility: default

Description: `SetJmp` fills `env` with the necessary data for a jump back to the point where it was called. It returns zero if called in this way. If the function returns nonzero, then it means that a call to `LongJmp` ([1320](#)) with `env` as an argument was made somewhere in the program.



Errors: None.

See also: LongJump ([1320](#))

**Listing:** ./refex/ex79.pp

---

```

program example79;

  { Program to demonstrate the setjmp, longjmp functions }

  procedure dojmp(var env : jmp_buf; value : longint);

  begin
    value:=2;
    Writeln ( 'Going to jump !');
    { This will return to the setjmp call,
      and return value instead of 0 }
    longjmp(env,value);
  end;

  var env : jmp_buf;

  begin
    if setjmp(env)=0 then
      begin
        writeln ( 'Passed first time.' );
        dojmp(env,2);
      end
    else
      writeln ( 'Passed second time.' );
    end.
  
```

---

### 37.9.323 SetLength

Synopsis: Set length of a string.

**Declaration:** `procedure SetLength(var S: AStringType; Len: Integer)`  
`procedure SetLength(var A: DynArrayType; Len: Integer)`

Visibility: default

**Description:** SetLength sets the length of the string S to Len. S can be an ansistring, a short string or a widestring. For ShortStrings, Len can maximally be 255. For AnsiStrings it can have any value. For AnsiString strings, SetLength { \em must } be used to set the length of the string.

In the case of a dynamical array A, setlength sets the number of elements. The elements are numbered from index 0, so the count runs from 0 to Len-1. If Zero is specified, the array is cleared.

Errors: None.

See also: Length ([1317](#))

**Listing:** ./refex/ex85.pp

---

```

Program Example85;

  { Program to demonstrate the SetLength function. }
  
```

---

---

```

Var S : String;

begin
    FillChar(S[1],100,#32);
    Setlength(S,100);
    Writeln ('"',S,'"');
end.

```

---

### 37.9.324 SetMemoryManager

Synopsis: Set a memory manager

Declaration: `procedure SetMemoryManager(const MemMgr: TMemoryManager)`

Visibility: default

Description: `SetMemoryManager` sets the current memory manager record to `MemMgr`.

For an example, see the programmer's guide.

Errors: None.

See also: `GetMemoryManager` ([1300](#)), `IsMemoryManagerSet` ([1316](#))

### 37.9.325 SetResourceManager

Synopsis: Set the resource manager

Declaration: `procedure SetResourceManager(const New: TResourceManager)`

Visibility: default

Description: `SetResourceManager` sets the active resource manager to `Manager`. After a call to `SetResourceManager`, the functions in the `Manager` record will be used to handle resources.

Note that it is not supported to change resource managers on-the-fly: any resources or information about resources obtained should be discarded prior to a call to `SetResourceManager`. Typically, `SetResourceManager` should be called once, at program startup.

Errors: None.

See also: `TResourceManager` ([1248](#)), `GetResourceManager` ([1301](#))

### 37.9.326 SetString

Synopsis: Set length of a string and copy buffer.

Declaration: `procedure SetString(out S: AnsiString;Buf: PChar;Len: SizeInt)`  
`procedure SetString(out S: Shortstring;Buf: PChar;Len: SizeInt)`  
`procedure SetString(out S: UnicodeString;Buf: PUnicodeChar;Len: SizeInt)`  
`procedure SetString(out S: UnicodeString;Buf: PChar;Len: SizeInt)`  
`procedure SetString(out S: WideString;Buf: PWideChar;Len: SizeInt)`  
`procedure SetString(out S: WideString;Buf: PChar;Len: SizeInt)`

Visibility: default

**Description:** `SetString` sets the length of the string `S` to `Len` and if `Buf` is non-nil, copies `Len` characters from `Buf` into `S`. `S` can be an ansistring, a short string or a widestring. For `ShortStrings`, `Len` can maximally be 255.

**Errors:** None.

**See also:** `SetLength` ([1375](#))

### 37.9.327 SetTextBuf

**Synopsis:** Set size of text file internal buffer

**Declaration:** `procedure SetTextBuf(var f: Text; var Buf)`  
`procedure SetTextBuf(var f: Text; var Buf; Size: SizeInt)`

**Visibility:** default

**Description:** `SetTextBuf` assigns an I/O buffer to a text file. The new buffer is located at `Buf` and is `Size` bytes long. If `Size` is omitted, then `SizeOf (Buf)` is assumed. The standard buffer of any text file is 128 bytes long. For heavy I/O operations this may prove too slow. The `SetTextBuf` procedure allows to set a bigger buffer for the I/O of the application, thus reducing the number of system calls, and thus reducing the load on the system resources. The maximum size of the newly assigned buffer is 65355 bytes.

**Remark:**

- Never assign a new buffer to an opened file. A new buffer can be assigned immediately after a call to `Rewrite` ([1365](#)), `Reset` ([1364](#)) or `Append`, but not after the file was read from/written to. This may cause loss of data. If a new buffer must be assigned after read/write operations have been performed, the file should be flushed first. This will ensure that the current buffer is emptied.
- Take care that the assigned buffer is always valid. If a local variable is assigned as a buffer, then after the program exits the local program block, the buffer will no longer be valid, and stack problems may occur.

**Errors:** No checking on `Size` is done.

**See also:** `Assign` ([1262](#)), `Reset` ([1364](#)), `Rewrite` ([1365](#)), `Append` ([1260](#))

**Listing:** `./refex/ex61.pp`

---

**Program** Example61 ;

*{ Program to demonstrate the SetTextBuf function. }*

**Var**

`Fin, Fout : Text;`  
`Ch : Char;`  
`Bufin, Bufout : Array[1..10000] of byte;`

**begin**

`Assign (Fin, paramstr(1));`  
`Reset (Fin);`  
`Assign (Fout, paramstr(2));`  
`Rewrite (Fout);`  
*{ This is harmless before IO has begun }*  
*{ Try this program again on a big file ,*  
*after commenting out the following 2*

---

```

    lines and recompiling it. }
SetTextBuf ( Fin , Bufin );
SetTextBuf ( Fout , Bufout );
    While not eof( Fin ) do
    begin
    Read ( Fin , ch );
    write ( Fout , ch );
    end;
    Close ( Fin );
    Close ( Fout );
end .

```

---

### 37.9.328 SetTextLineEnding

Synopsis: Set the end-of-line character for the given text file.

Declaration: `procedure SetTextLineEnding( var f: Text; Ending: String)`

Visibility: default

Description: `SetTextLineEnding` sets the end-of-line character for the text file `F` to `Ending`. By default, this is the string indicated by `DefaultTextLineBreakStyle` ([1212](#)).

Errors: None.

See also: `DefaultTextLineBreakStyle` ([1212](#)), `TTextLineBreakStyle` ([1249](#))

### 37.9.329 SetThreadManager

Synopsis: Set the thread manager, optionally return the current thread manager.

Declaration: `function SetThreadManager( const NewTM: TThreadManager;  
var OldTM: TThreadManager ) : Boolean`  
`function SetThreadManager( const NewTM: TThreadManager ) : Boolean`

Visibility: default

Description: `SetThreadManager` sets the thread manager to `NewTM`. If `OldTM` is given, `SetThreadManager` uses it to return the previously used thread manager.

The function returns `True` if the threadmanager was set succesfully, `False` if an error occurred.

For more information about thread programming, see the programmer's guide.

Errors: If an error occurred cleaning up the previous manager, or an error occurred initializing the new manager, `False` is returned.

See also: `GetThreadManager` ([1301](#)), `TThreadManager` ([1250](#))

### 37.9.330 SetUnicodeStringManager

Synopsis: Set the unicodestring manager

Declaration: `procedure SetUnicodeStringManager( const New: TUnicodeStringManager)`  
`procedure SetUnicodeStringManager( const New: TUnicodeStringManager;  
var Old: TUnicodeStringManager)`

Visibility: default

**Description:** `SetUnicodeStringManager` sets the current unicodestring manager to `New`. Optionally, it returns the currently active widestring manager in `Old`.

UnicodeStrings are implemented in different ways on different platforms. Therefore, the Free Pascal Runtime library has no fixed implementation of widestring routines. Instead, it defines a UnicodeString manager record, with callbacks that can be set to an implementation which is most efficient on the current platform. On windows, standard Windows routines will be used. On Unix and Linux, an implementation based on the C library is available (in unit `cwstring`).

It is possible to implement a custom unicodestring manager, optimized for the current application, without having to recompile the complete Run-Time Library.

Errors:

See also: `TUnicodeStringManager` ([1251](#))

### 37.9.331 SetVariantManager

**Synopsis:** Set the current variant manager.

**Declaration:** `procedure SetVariantManager(const VarMgr: tvariantmanager)`

**Visibility:** default

**Description:** `SetVariantManager` sets the variant manager to `varmgr`.

See also: `IsVariantManagerSet` ([1209](#)), `GetVariantManager` ([1302](#))

### 37.9.332 SetWideStringManager

**Synopsis:** Set the widestring manager

**Declaration:** `procedure SetWideStringManager(const New: TUnicodeStringManager)`  
`procedure SetWideStringManager(const New: TUnicodeStringManager;`  
`var Old: TUnicodeStringManager)`

**Visibility:** default

**Description:** `SetWideStringManager` sets the current widestring manager to `New`. Optionally, it returns the currently active widestring manager in `Old`.

WideStrings are implemented in different ways on different platforms. Therefore, the Free Pascal Runtime library has no fixed implementation of widestring routines. Instead, it defines a WideString manager record, with callbacks that can be set to an implementation which is most efficient on the current platform. On windows, standard Windows routines will be used. On Unix and Linux, an implementation based on the C library is available (in unit `cwstring`).

It is possible to implement a custom widestring manager, optimized for the current application, without having to recompile the complete Run-Time Library.

Errors:

See also: `TWideStringManager` ([1254](#))

**37.9.333 ShortCompareText**

Synopsis: Compare 2 shortstrings

Declaration: `function ShortCompareText(const S1: shortstring; const S2: shortstring) : SizeInt`

Visibility: default

Description: `ShortCompareText` compares two shortstrings, S1 and S2, and returns the following result:

<0 if S1 < S2.  
 0 if S1 = S2.  
 >0 if S1 > S2.

The comparison of the two strings is case-insensitive. The function does not take internationalization settings into account, it simply compares ASCII values.

Errors: None.

See also: `#rtl.sysutils.CompareText` ([1467](#))

**37.9.334 sin**

Synopsis: Calculate sine of angle

Declaration: `function sin(d: ValReal) : ValReal`

Visibility: default

Description: `Sin` returns the sine of its argument X, where X is an angle in radians. If the absolute value of the argument is larger than 2<sup>63</sup>, then the result is undefined.

Errors: None.

See also: `Cos` ([1277](#)), `Pi` ([1356](#)), `Exp` ([1290](#)), `Ln` ([1318](#))

**Listing:** `./refex/ex62.pp`

---

**Program** Example62;

*{ Program to demonstrate the Sin function. }*

```
begin
  Writeln (Sin(Pi):0:1); { Prints 0.0 }
  Writeln (Sin(Pi/2):0:1); { Prints 1.0 }
end.
```

---

**37.9.335 SizeOf**

Synopsis: Return size of a variable or type.

Declaration: `function SizeOf(X: TAnyType) : LongInt`

Visibility: default

Description: `SizeOf` returns the size, in bytes, of any variable or type-identifier.

**Remark:** This isn't really a RTL function. Its result is calculated at compile-time, and hard-coded in the executable.

Errors: None.

See also: `Addr` ([1259](#))

**Listing:** `./refex/ex63.pp`

---

**Program** `Example63`;

```
{ Program to demonstrate the SizeOf function. }
Var
  I : Longint;
  S : String [10];

begin
  Writeln (SizeOf(I)); { Prints 4 }
  Writeln (SizeOf(S)); { Prints 11 }
end.
```

---

### 37.9.336 `SizeofResource`

Synopsis: Return the size of a particular resource

Declaration: `function SizeofResource (ModuleHandle: TFPResourceHMODULE;  
ResHandle: TFPResourceHandle) : LongWord`

Visibility: default

Description: `SizeOfResource` returns the size of the resource identified by `ResHandle` in module identified by `ModuleHandle`. `ResHandle` should be obtained from a call to `LoadResource` ([1319](#))

Errors: In case of an error, 0 is returned.

See also: `FindResource` ([1295](#)), `FreeResource` ([1298](#)), `LoadResource` ([1319](#)), `LockResource` ([1320](#)), `UnlockResource` ([1396](#)), `FreeResource` ([1298](#))

### 37.9.337 `Space`

Synopsis: Return a string of spaces

Declaration: `function Space (b: Byte) : shortstring`

Visibility: default

Description: `Space` returns a shortstring with length `B`, consisting of spaces.

See also: `StringOfChar` ([1384](#))

**37.9.338 Sptr**

Synopsis: Return current stack pointer

Declaration: `function Sptr : Pointer`

Visibility: default

Description: `Sptr` returns the current stack pointer.

Errors: None.

See also: `SSeg` ([1383](#))

**Listing:** `./refex/ex64.pp`

---

```

program Example64;

  { Program to demonstrate the sptr function. }

  var p: ptnuint;

  begin
    p:=ofs(sptr); { P Contains now the current stack position. }
  end.

```

---

**37.9.339 sqr**

Synopsis: Calculate the square of a value.

Declaration: `function sqr(l: LongInt) : LongInt`  
`function sqr(l: Int64) : Int64`  
`function sqr(l: QWord) : QWord`  
`function sqr(d: ValReal) : ValReal`

Visibility: default

Description: `Sqr` returns the square of its argument X.

Errors: None.

See also: `Sqrt` ([1383](#)), `Ln` ([1318](#)), `Exp` ([1290](#))

**Listing:** `./refex/ex65.pp`

---

```

Program Example65;

  { Program to demonstrate the Sqr function. }
  Var i : Integer;

  begin
    For i:=1 to 10 do
      writeln (Sqr(i):3);
  end.

```

---



**37.9.340 sqrt**

Synopsis: Calculate the square root of a value

Declaration: `function sqrt (d: ValReal) : ValReal`

Visibility: default

Description: `Sqrt` returns the square root of its argument `X`, which must be positive.

Errors: If `X` is negative, then a run-time error is generated.

See also: `Sqr` ([1382](#)), `Ln` ([1318](#)), `Exp` ([1290](#))

**Listing:** `./refex/ex66.pp`

---

**Program** `Example66;`

*{ Program to demonstrate the Sqrt function. }*

```
begin
  WriteLn ( Sqrt(4):0:3); { Prints 2.000 }
  WriteLn ( Sqrt(2):0:3); { Prints 1.414 }
end.
```

---

**37.9.341 Sseg**

Synopsis: Return stack segment register value.

Declaration: `function Sseg : Word`

Visibility: default

Description: `SSeg` returns the Stack Segment. This function is only supported for compatibility reasons, as `Sptr` returns the correct contents of the stackpointer.

Errors: None.

See also: `Sptr` ([1382](#))

**Listing:** `./refex/ex67.pp`

---

**Program** `Example67;`

*{ Program to demonstrate the SSeg function. }*

**Var** `W : Longint;`

```
begin
  W:=SSeg;
end.
```

---

**37.9.342 Str**

Synopsis: Convert a numerical value to a string.

Declaration: `procedure Str (var X: TNumericType; var S: String)`

Visibility: default

**Description:** `Str` returns a string which represents the value of `X`. `X` can be any numerical type. The actual declaration of `Str` is not according to pascal syntax, and should be

```
procedure Str(var X: TNumericType[:NumPlaces[:Decimals]];var S: String)
```

Where the optional `NumPlaces` and `Decimals` specifiers control the formatting of the string: `NumPlaces` gives the total width of the string, and `Decimals` the number of decimals after the decimal separator char.

Errors: None.

See also: `Val` ([1399](#))

**Listing:** `./refex/ex68.pp`

---

**Program** `Example68`;

```
{ Program to demonstrate the Str function. }
```

```
Var S : String;
```

```
Function IntToStr (I : Longint) : String;
```

```
Var S : String;
```

```
begin
```

```
  Str (I,S);
```

```
  IntToStr:=S;
```

```
end;
```

```
begin
```

```
  S:= '*' + IntToStr(-233) + '*' ;
```

```
  Writeln (S);
```

```
end.
```

---

### 37.9.343 StringOfChar

**Synopsis:** Return a string consisting of 1 character repeated N times.

**Declaration:** `function StringOfChar(c: Char;l: SizeInt) : AnsiString`

**Visibility:** `default`

**Description:** `StringOfChar` creates a new `String` of length `l` and fills it with the character `c`.

It is equivalent to the following calls:

```
SetLength(StringOfChar,l);
```

```
FillChar(Pointer(StringOfChar)^,Length(StringOfChar),c);
```

Errors: None.

See also: `SetLength` ([1375](#))

**Listing:** `./refex/ex97.pp`

---

```

Program Example97;

{$H+}

{ Program to demonstrate the StringOfChar function. }

Var S : String;

begin
  S:=StringOfChar(' ',40)+'Aligned at column 41.';
  WriteLn(s);
end.

```

---

### 37.9.344 StringToPPChar

**Synopsis:** Split string in list of null-terminated strings

**Declaration:** `function StringToPPChar(var S: AnsiString; ReserveEntries: Integer) : PPChar`  
`function StringToPPChar(S: PChar; ReserveEntries: Integer) : PPChar`

**Visibility:** default

**Description:** `StringToPPChar` splits the string `S` in words, replacing any whitespace with zero characters. It returns a pointer to an array of `pchars` that point to the first letters of the words in `S`. This array is terminated by a `Nil` pointer.

The function does *not* add a zero character to the end of the string unless it ends on whitespace.

The function reserves memory on the heap to store the array of `PChar`; The caller is responsible for freeing this memory.

This function is only available on certain platforms.

**Errors:** None.

**See also:** `ArrayStringToPPchar` ([1261](#))

### 37.9.345 StringToUnicodeChar

**Synopsis:** Convert an ansistring to a null-terminated array of unicode characters.

**Declaration:** `function StringToUnicodeChar(const Src: AnsiString; Dest: PUnicodeChar; DestSize: SizeInt) : PUnicodeChar`

**Visibility:** default

**Description:** `StringToUnicodeChar` converts the ansistring `S` to a unicodestring and places the result in `Dest`. The size of the memory location pointed to by `Dest` must be given in `DestSize`. If the result string is longer than the available size, the result string will be truncated.

The function always returns `Dest`.

**Errors:** No check is performed to see whether `Dest` points to a valid memory location.

**See also:** `UnicodeCharToString` ([1395](#)), `UnicodeCharLenToString` ([1394](#))

**37.9.346 StringToWideChar**

Synopsis: Convert a string to an array of widechars.

Declaration: `function StringToWideChar(const Src: AnsiString; Dest: PWideChar;  
DestSize: SizeInt) : PWideChar`

Visibility: default

Description: `StringToWideChar` converts an ansistring `Src` to a null-terminated array of `WideChars`. The destination for this array is pointed to by `Dest`, and contains room for at least `DestSize` widechars.

Errors: No validity checking is performed on `Dest`.

See also: `WideCharToString` ([1401](#)), `WideCharToStrVar` ([1402](#)), `WideCharLenToStrVar` ([1401](#)), `WideCharLenToString` ([1401](#))

**37.9.347 strlen**

Synopsis: Length of a null-terminated string.

Declaration: `function strlen(p: PChar) : LongInt`

Visibility: default

Description: Returns the length of the null-terminated string `P`.

Errors: None.

**37.9.348 strpas**

Synopsis: Convert a null-terminated string to a shortstring.

Declaration: `function strpas(p: PChar) : shortstring`

Visibility: default

Description: Converts a null terminated string in `P` to a Pascal string, and returns this string. The string is truncated at 255 characters.

Errors: None.

**37.9.349 Succ**

Synopsis: Return next element of ordinal type.

Declaration: `function Succ(X: TOrdinal) : TOrdinal`

Visibility: default

Description: `Succ` returns the element that succeeds the element that was passed to it. If it is applied to the last value of the ordinal type, and the program was compiled with range checking on (`{ $R+ }`), then a run-time error will be generated.

for an example, see `Ord` ([1354](#)).

Errors: Run-time error 201 is generated when the result is out of range.

See also: `Ord` ([1354](#)), `Pred` ([1357](#)), `High` ([1305](#)), `Low` ([1320](#))

**37.9.350 SuspendThread**

Synopsis: Suspend a running thread.

Declaration: `function SuspendThread(threadHandle: TThreadID) : DWord`

Visibility: default

Description: `SuspendThread` suspends a running thread. The thread is identified with its handle or ID `threadHandle`.

The function returns zero if successful. A nonzero return value indicates failure.

Errors: If a failure occurred, a nonzero result is returned. The meaning is system dependent.

See also: `ResumeThread` ([1365](#)), `KillThread` ([1316](#))

**37.9.351 Swap**

Synopsis: Swap high and low bytes/words of a variable

Declaration: `function swap(X: Word) : Word`  
`function Swap(X: Integer) : Integer`  
`function swap(X: LongInt) : LongInt`  
`function Swap(X: Cardinal) : Cardinal`  
`function Swap(X: QWord) : QWord`  
`function swap(X: Int64) : Int64`

Visibility: default

Description: `Swap` swaps the high and low order bytes of `X` if `X` is of type `Word` or `Integer`, or swaps the high and low order words of `X` if `X` is of type `Longint` or `Cardinal`. The return type is the type of `X`

Errors: None.

See also: `Lo` ([1319](#)), `Hi` ([1304](#))

**Listing:** `./refex/ex69.pp`

---

**Program** `Example69;`

```
{ Program to demonstrate the Swap function. }
Var W : Word;
    L : Longint;

begin
  W:=$1234;
  W:=Swap(W);
  if W<>$3412 then
    writeln ('Error when swapping word !');
  L:=$12345678;
  L:=Swap(L);
  if L<>$56781234 then
    writeln ('Error when swapping Longint !');
end.
```

---

**37.9.352 SwapEndian**

Synopsis: Swap endianness of the argument

Declaration: `function SwapEndian(const AValue: SmallInt) : SmallInt`  
`function SwapEndian(const AValue: Word) : Word`  
`function SwapEndian(const AValue: LongInt) : LongInt`  
`function SwapEndian(const AValue: DWord) : DWord`  
`function SwapEndian(const AValue: Int64) : Int64`  
`function SwapEndian(const AValue: QWord) : QWord`

Visibility: default

Description: `SwapEndian` will swap the endianness of the bytes in its argument.

Errors: None.

See also: `hi` ([1304](#)), `lo` ([1319](#)), `swap` ([1387](#)), `BEToN` ([1265](#)), `NToBE` ([1323](#)), `NToLE` ([1324](#)), `LEToN` ([1318](#))

**37.9.353 SysAllocMem**

Synopsis: System memory manager: Allocate memory

Declaration: `function SysAllocMem(size: PtrUInt) : Pointer`

Visibility: default

Description: `SysFreeMemSize` is the system memory manager implementation for `AllocMem` ([1260](#))

See also: `AllocMem` ([1260](#))

**37.9.354 SysAssert**

Synopsis: Standard Assert failure implementation

Declaration: `procedure SysAssert(const Msg: ShortString; const FName: ShortString;`  
`LineNo: LongInt; ErrorAddr: Pointer)`

Visibility: default

Description: `SysAssert` is the standard implementation of the assertion failed code. It is the default value of the `AssertErrorProc` constant. It will print the assert message `Msg` together with the filename `FName` and linenumber `LineNo` to standard error output (`StdErr`) and will halt the program with exit code 227. The error address `ErrorAddr` is ignored.

See also: `AssertErrorProc` ([1212](#))

**37.9.355 SysBackTraceStr**

Synopsis: Format an address suitable for inclusion in a backtrace

Declaration: `function SysBackTraceStr(Addr: Pointer) : ShortString`

Visibility: default

Description: `SysBackTraceStr` will create a string representation of the address `Addr`, suitable for inclusion in a stack backtrace.

Errors: None.

### 37.9.356 SysFreemem

Synopsis: System memory manager free routine.

Declaration: `function SysFreemem(p: pointer) : PtrUInt`

Visibility: default

Description: `SysFreemem` is the system memory manager implementation for `FreeMem` ([1297](#))

See also: `FreeMem` ([1297](#))

### 37.9.357 SysFreememSize

Synopsis: System memory manager free routine.

Declaration: `function SysFreememSize(p: pointer; Size: PtrUInt) : PtrUInt`

Visibility: default

Description: `SysFreemSize` is the system memory manager implementation for `FreeMem` ([1297](#))

See also: `MemSize` ([1321](#))

### 37.9.358 SysGetFPCHeapStatus

Synopsis: Return the status of the FPC heapmanager

Declaration: `function SysGetFPCHeapStatus : TFPCHeapStatus`

Visibility: default

Description: `SysGetFPCHeapStatus` returns the status of the default FPC heapmanager. It is set as the default value of the corresponding `GetFPCHeapStatus` ([1299](#)) function.

Errors: None. The result of this function is bogus information if the current heapmanager is not the standard FPC heapmanager.

See also: `GetFPCHeapStatus` ([1299](#))

### 37.9.359 SysGetHeapStatus

Synopsis: System implementation of `GetHeapStatus` ([1299](#))

Declaration: `function SysGetHeapStatus : THeapStatus`

Visibility: default

Description: `SysGetHeapStatus` is the system implementation of the `GetHeapStatus` ([1299](#)) call.

See also: `GetHeapStatus` ([1299](#))

### 37.9.360 SysGetmem

Synopsis: System memory manager memory allocator.

Declaration: `function SysGetmem(Size: PtrUInt) : Pointer`

Visibility: default

Description: `SysGetmem` is the system memory manager implementation for `GetMem` ([1299](#))

See also: `GetMem` ([1299](#)), `GetMemory` ([1300](#))

### 37.9.361 SysInitExceptions

Synopsis: Initialize exceptions.

Declaration: `procedure SysInitExceptions`

Visibility: default

Description: `SysInitExceptions` initializes the exception system. This procedure should never be called directly, it is taken care of by the RTL.

### 37.9.362 SysInitFPU

Synopsis: Initialize the FPU

Declaration: `procedure SysInitFPU`

Visibility: default

Description: `SysInitFPU` initializes (resets) the floating point unit, if one is available. It is called for instance when a new thread is started.

See also: `BeginThread` ([1265](#))

### 37.9.363 SysInitStdIO

Synopsis: Initialize standard input and output.

Declaration: `procedure SysInitStdIO`

Visibility: default

Description: `SysInitStdIO` initializes the standard input and output files: Output ([1256](#)), Input ([1256](#)) and StdErr ([1257](#)). This routine is called by the initialization code of the system unit, there should be no need to call it directly.

### 37.9.364 SysMemSize

Synopsis: System memory manager: free size.

Declaration: `function SysMemSize(p: pointer) : PtrUInt`

Visibility: default

Description: `SysFreeMemSize` is the system memory manager implementation for `MemSize` ([1321](#))

See also: `MemSize` ([1321](#))

### 37.9.365 SysReAllocMem

Synopsis: System memory manager: Reallocate memory

Declaration: `function SysReAllocMem(var p: pointer; size: PtrUInt) : Pointer`

Visibility: default

Description: `SysReallocMem` is a help routine for the system memory manager implementation for `ReAllocMem` ([1363](#)).

See also: `ReAllocMem` ([1363](#))



**37.9.366 SysResetFPU**

Synopsis: Reset the floating point unit.

Declaration: `procedure SysResetFPU`

Visibility: default

Description: `SysResetFPU` resets the floating point unit. There should normally be no need to call this unit; the compiler itself takes care of this.

**37.9.367 SysSetCtrlBreakHandler**

Synopsis: System CTRL-C handler

Declaration: `function SysSetCtrlBreakHandler(Handler: TCtrlBreakHandler)  
: TCtrlBreakHandler`

Visibility: default

Description: `SysSetCtrlBreakHandler` sets the CTRL-C handler to the `Handler` callback, and returns the previous value of the handler.

See also: `TCtrlBreakHandler` ([1243](#))

**37.9.368 SysTryResizeMem**

Synopsis: System memory manager: attempt to resize memory.

Declaration: `function SysTryResizeMem(var p: pointer; size: PtrUInt) : Boolean`

Visibility: default

Description: `SysTryResizeMem` is a help routine for the system memory manager implementation for `ReAllocMem` ([1363](#)), `SysReAllocMem` ([1390](#))

See also: `SysReAllocMem` ([1390](#)), `ReAllocMem` ([1363](#))

**37.9.369 ThreadGetPriority**

Synopsis: Return the priority of a thread.

Declaration: `function ThreadGetPriority(threadHandle: TThreadID) : LongInt`

Visibility: default

Description: `ThreadGetPriority` returns the priority of thread `TThreadID` to `Prio`. The returned priority is a value between -15 and 15.

Errors: None.

See also: `ThreadSetPriority` ([1392](#))

**37.9.370 ThreadSetPriority**

Synopsis: Set the priority of a thread.

Declaration: `function ThreadSetPriority(threadHandle: TThreadID; Prio: LongInt)  
: Boolean`

Visibility: default

Description: `ThreadSetPriority` sets the priority of thread `TThreadID` to `Prio`. Priority is a value between -15 and 15.

Errors: None.

See also: `ThreadGetPriority` ([1391](#))

**37.9.371 ThreadSwitch**

Synopsis: Signal possibility of thread switch

Declaration: `procedure ThreadSwitch`

Visibility: default

Description: `ThreadSwitch` signals the operating system that the thread should be suspended and that another thread should be executed.

This call is a hint only, and may be ignored.

See also: `SuspendThread` ([1387](#)), `ResumeThread` ([1365](#)), `KillThread` ([1316](#))

**37.9.372 trunc**

Synopsis: Truncate a floating point value.

Declaration: `function trunc(d: ValReal) : Int64`

Visibility: default

Description: `Trunc` returns the integer part of `X`, which is always smaller than (or equal to) `X` in absolute value.

Errors: None.

See also: `Frac` ([1297](#)), `Int` ([1312](#)), `Round` ([1369](#))

**Listing:** `./refex/ex70.pp`

---

**Program** `Example70;`

*{ Program to demonstrate the Trunc function. }*

```
begin
  Writeln (Trunc(123.456)); { Prints 123 }
  Writeln (Trunc(-123.456)); { Prints -123 }
  Writeln (Trunc(12.3456)); { Prints 12 }
  Writeln (Trunc(-12.3456)); { Prints -12 }
end.
```

---

**37.9.373 Truncate**

Synopsis: Truncate the file at position

Declaration: `procedure Truncate(var F: File)`

Visibility: default

Description: `Truncate` truncates the (opened) file `F` at the current file position.

Errors: Depending on the state of the `{SI}` switch, a runtime error can be generated if there is an error. In the `{SI-}` state, use `IOResult` to check for errors.

See also: `Append` ([1260](#)), `Filepos` ([1291](#)), `Seek` ([1372](#))

**Listing:** `./refex/ex71.pp`

---

**Program** `Example71`;

*{ Program to demonstrate the Truncate function. }*

```

Var F : File of longint;
      I, L : Longint;

begin
  Assign (F, 'test.tmp');
  Rewrite (F);
  For I:=1 to 10 Do
    Write (F, I);
  Writeln ('Filesize before Truncate : ', FileSize(F));
  Close (f);
  Reset (F);
  Repeat
    Read (F, I);
  Until i=5;
  Truncate (F);
  Writeln ('Filesize after Truncate : ', FileSize(F));
  Close (f);
end.

```

---

**37.9.374 TryEnterCriticalSection**

Synopsis: Try entering a critical section

Declaration: `function TryEnterCriticalSection(var cs: TRTLCriticalSection) : LongInt`

Visibility: default

Description: `TryEnterCriticalSection` attempts to enter critical section `cs`. It returns at once. The return value is zero if another thread owns the critical section, or nonzero if the current thread already owns or successfully obtained the critical section.

**37.9.375 UCS4StringToUnicodeString**

Synopsis: Convert a UCS-4 encoded string to a unicode string

Declaration: `function UCS4StringToUnicodeString(const s: UCS4String) : UnicodeString`

Visibility: default

Description: `UCS4StringToUnicodeString` converts the UCS-4 encoded string `S` to a unicode string and returns the resulting string.

This function requires the widestring manager.

Errors:

See also: `UnicodeStringToUCS4String` ([1395](#))

### 37.9.376 UCS4StringToWideString

Synopsis:

Declaration: `function UCS4StringToWideString(const s: UCS4String) : WideString`

Visibility: default

Description:

Errors:

### 37.9.377 Unassigned

Synopsis: Unassigned variant.

Declaration: `function Unassigned : Variant`

Visibility: default

### 37.9.378 UnicodeCharLenToString

Synopsis: Convert a memory buffer with unicode characters to an ansistring

Declaration: `function UnicodeCharLenToString(S: PUnicodeChar; Len: SizeInt)  
: AnsiString`

Visibility: default

Description: `UnicodeCharLenToString` converts the unicode characters in buffer `S` with at most `len` bytes length, to an ansistring and returns the result.

This function requires the use of a widestring manager.

Errors: No checking is done to see if the pointer `S` or length `len` are valid.

See also: `StringToUnicodeChar` ([1385](#)), `UnicodeCharToString` ([1395](#))

### 37.9.379 UnicodeCharLenToStrVar

Synopsis: Convert a memory buffer with unicode characters to an ansistring

Declaration: `procedure UnicodeCharLenToStrVar(Src: PUnicodeChar; Len: SizeInt;  
out Dest: AnsiString)`

Visibility: default

**Description:** `UnicodeCharLenToString` converts the unicode characters in buffer `S` with at most `len` bytes length, to an ansistring and returns the result in `Dest`

This function does the same as `UnicodeCharLenToString` (1394).

**Errors:** No checking is done to see if the pointer `S` or length `len` are valid.

**See also:** `StringToUnicodeChar` (1385), `UnicodeCharToString` (1395), `UnicodeCharLenToString` (1394), `UnicodeCharToStrVar` (1395)

### 37.9.380 UnicodeCharToString

**Synopsis:** Convert unicode character to string

**Declaration:** `function UnicodeCharToString(S: PUnicodeChar) : AnsiString`

**Visibility:** default

**Description:** `UnicodeCharToString` converts a null-word-terminated array of unicode characters in `S` to an `AnsiString` value. It simply calls `UnicodeCharLenToString` (1394) with the length of the string `S`.

This function requires the use of a widestring manager.

**Errors:** No checking is done to see if the pointer `S` is valid.

**See also:** `StringToUnicodeChar` (1385), `UnicodeCharLenToString` (1394), `WidestringManager` (1257)

### 37.9.381 UnicodeCharToStrVar

**Synopsis:** Convert a null-terminated memory buffer with unicode characters to an ansistring

**Declaration:** `procedure UnicodeCharToStrVar(S: PUnicodeChar; out Dest: AnsiString)`

**Visibility:** default

**Description:** `UnicodeCharLenToString` converts the unicode characters in buffer `S` up to the first null word, to an ansistring and returns the result in `Dest`

This function does the same as `UnicodeCharToString` (1395).

**Errors:** No checking is done to see if the pointer `S` is valid.

**See also:** `StringToUnicodeChar` (1385), `UnicodeCharToString` (1395), `UnicodeCharLenToString` (1394), `UnicodeCharToString` (1395)

### 37.9.382 UnicodeStringToUCS4String

**Synopsis:** Convert a unicode string to a UCS-4 string.

**Declaration:** `function UnicodeStringToUCS4String(const s: UnicodeString) : UCS4String`

**Visibility:** default

**Description:** `UnicodeStringToUCS4String` converts a unicode string `S` to a UCS-4 encoded string, and returns the resulting string.

This function requires the widestring manager.

**See also:** `UCS4StringToUnicodeString` (1393)

**37.9.383 UnicodeToUtf8**

Synopsis:

Declaration: `function UnicodeToUtf8 (Dest: PChar; Source: PUnicodeChar;  
   MaxBytes: SizeInt) : SizeInt`  
`function UnicodeToUtf8 (Dest: PChar; MaxDestBytes: SizeUInt;  
   Source: PUnicodeChar; SourceChars: SizeUInt)  
   : SizeUInt`  
`function UnicodeToUtf8 (Dest: PChar; Source: PWideChar; MaxBytes: SizeInt)  
   : SizeInt`  
`function UnicodeToUtf8 (Dest: PChar; MaxDestBytes: SizeUInt;  
   Source: PWideChar; SourceChars: SizeUInt)  
   : SizeUInt`

Visibility: default

Description:

Errors:

**37.9.384 UniqueString**

Synopsis: Make sure reference count of string is 1

Declaration: `procedure UniqueString (var S: AnsiString)`  
`procedure UniqueString (var S: UnicodeString)`  
`procedure UniqueString (var S: WideString)`

Visibility: default

Description: `UniqueString` ensures that the ansistring `S` has reference count 1. It makes a copy of `S` if this is necessary, and returns the copy in `S`

Errors: None.

**37.9.385 UnlockResource**

Synopsis: Unlock a previously locked resource

Declaration: `function UnlockResource (ResData: TFPResourceHGLOBAL) : LongBool`

Visibility: default

Description: `UnlockResource` unlocks a previously locked resource. Note that this function does not exist on windows, it's only needed on other platforms.

Errors: The function returns `False` if it failed.

See also: `FindResource` ([1295](#)), `FreeResource` ([1298](#)), `SizeofResource` ([1381](#)), `LoadResource` ([1319](#)), `lockResource` ([1320](#)), `FreeResource` ([1298](#))

**37.9.386 UnPack**

Synopsis: Create unpacked array from packed array

Declaration: `procedure UnPack(const Z: PackedArrayType; out A: UnpackedArrayType;  
                                  StartIndex: TIndexType)`

Visibility: default

Description: `UnPack` will copy the elements of a packed array (Z) to an unpacked array (A). All elements in Z are copied to A, starting at index `StartIndex` in A. The type of the index variable `StartIndex` must match the type of the index of A.

Obviously, the type of the elements of the arrays A and Z must match.

See also: `Pack` ([1354](#))

**37.9.387 upCase**

Synopsis: Convert a string to all uppercase.

Declaration: `function upCase(const s: shortstring) : shortstring  
              function upCase(c: Char) : Char  
              function upcase(const s: ansistring) : ansistring  
              function UpCase(const s: UnicodeString) : UnicodeString  
              function UpCase(c: UnicodeChar) : UnicodeChar  
              function UpCase(const s: WideString) : WideString`

Visibility: default

Description: `UpCase` returns the uppercase version of its argument C. If its argument is a string, then the complete string is converted to uppercase. The type of the returned value is the same as the type of the argument.

Errors: None.

See also: `Lowercase` ([1321](#))

**Listing:** `./refex/ex72.pp`

---

```

program Example72;

  { Program to demonstrate the upcase function. }

  var c:char;

  begin
    for c:= 'a' to 'z' do
      write(upcase(c));
      Writeln;
      { This doesn't work in TP, but it does in Free Pascal }
      Writeln(upcase('abcdefghijklmnopqrstuvwxy' ));
  end.
```

---

**37.9.388 UTF8Decode**

Synopsis: Convert a wstring to a UTF-8 encoded unicode string

Declaration: `function UTF8Decode(const s: UTF8String) : UnicodeString`

Visibility: default

Description: `UTF8Decode` converts the wstring `S` to a UTF-8 encoded unicode string and returns the resulting string. It calls the low-level `Utf8ToUnicode` (1398) function to do the actual work.

For this function to work, a wstring manager must be installed.

See also: `UTF8Encode` (1398), `Utf8ToAnsi` (1398), `SetWideStringManager` (1379), `Utf8ToUnicode` (1398)

**37.9.389 UTF8Encode**

Synopsis: Convert a UTF-8 encoded unicode string to a wstring

Declaration: `function UTF8Encode(const s: Ansistring) : UTF8String`  
`function UTF8Encode(const s: UnicodeString) : UTF8String`  
`function UTF8Encode(const s: WideString) : UTF8String`

Visibility: default

Description: `UTF8Encode` converts the UTF-8 encoded unicode string `S` to a wstring and returns the resulting string. It calls the low-level `UnicodeToUTF8` (1396) function to do the actual work.

For this function to work, a wstring manager must be installed.

See also: `UTF8Decode` (1398), `Utf8ToAnsi` (1398), `UnicodeToUtf8` (1396), `SetWideStringManager` (1379)

**37.9.390 Utf8ToAnsi**

Synopsis: Convert a UTF-8 encoded unicode string to an ansistring

Declaration: `function Utf8ToAnsi(const s: UTF8String) : ansistring`

Visibility: default

Description: `Utf8ToAnsi` converts an utf8-encode unicode string to an ansistring. It converts the string to a wstring and then converts the wstring to an ansistring.

For this function to work, a wstring manager must be installed.

Errors:

See also: `UTF8Encode` (1398), `UTF8Decode` (1398), `SetWideStringManager` (1379)

**37.9.391 Utf8ToUnicode**

Synopsis: Convert a buffer with UTF-8 characters to wstring characters

Declaration: `function Utf8ToUnicode(Dest: PUnicodeChar;Source: PChar;`  
`MaxChars: SizeInt) : SizeInt`  
`function Utf8ToUnicode(Dest: PUnicodeChar;MaxDestChars: SizeUInt;`  
`Source: PChar;SourceBytes: SizeUInt) : SizeUInt`  
`function Utf8ToUnicode(Dest: PWideChar;Source: PChar;MaxChars: SizeInt)`  
`: SizeInt`  
`function Utf8ToUnicode(Dest: PWideChar;MaxDestChars: SizeUInt;`  
`Source: PChar;SourceBytes: SizeUInt) : SizeUInt`



Visibility: default

**Description:** `Utf8ToUnicode` converts the buffer in `Source` with a length of `SourceBytes` or for a maximum length of `MaxChars` (or `MaxDestChars`) widestring characters to the buffer pointed to by `Dest`.

The function returns the number of copied widestring characters.

For this function to work, a widestring manager must be installed.

**Errors:** On error, -1 is returned.

See also: `UTF8Encode` ([1398](#)), `UTF8Decode` ([1398](#)), `Utf8ToAnsi` ([1398](#)), `SetWideStringManager` ([1379](#))

### 37.9.392 Val

**Synopsis:** Calculate numerical/enumerated value of a string.

**Declaration:** `procedure Val(const S: String; var V; var Code: Word)`

Visibility: default

**Description:** `Val` converts the value represented in the string `S` to a numerical value or an enumerated value, and stores this value in the variable `V`, which can be of type `Longint`, `Real` and `Byte` or any enumerated type. If the conversion isn't successful, then the parameter `Code` contains the index of the character in `S` which prevented the conversion. The string `S` is allowed to contain spaces in the beginning.

The string `S` can contain a number in decimal, hexadecimal, binary or octal format, as described in the language reference. For enumerated values, the string must be the name of the enumerated value. The name is searched case insensitively.

The conversion to enumerated exists only as of version 2.3.1 (or later) of the compiler.

**Errors:** If the conversion doesn't succeed, the value of `Code` indicates the position where the conversion went wrong. The value of `V` is then undefined.

See also: `Str` ([1383](#))

**Listing:** `./refex/ex74.pp`

**Program** `Example74`;

```
{ Program to demonstrate the Val function. }
Var I, Code : Integer;

begin
  Val (ParamStr (1), I, Code);
  If Code <> 0 then
    Writeln ('Error at position ', code, ' : ', Paramstr(1)[Code])
  else
    Writeln ('Value : ', I);
end.
```

### 37.9.393 VarArrayGet

**Synopsis:**

**Declaration:** `function VarArrayGet(const A: Variant; const Indices: Array of LongInt) : Variant`

Visibility: default

Description:

Errors:

### 37.9.394 VarArrayPut

Synopsis: Put a value in a single cell of a variant array

Declaration: `procedure VarArrayPut (var A: Variant; const Value: Variant;  
const Indices: Array of LongInt)`

Visibility: default

Description: `VarArrayPut` puts `Value` in the variant array `A` at the location indicated by `Indices`. Thus the statement

```
VarArrayPut (A, B, [2, 1]);
```

is equivalent to

```
A [2, 1] := B;
```

The difference is that the previous is usable when the amount of indices is not known at compile time.

Errors: If the number of indices is wrong (or out of range) an exception may be raised.

See also: `VarArrayGet` ([1399](#))

### 37.9.395 VarArrayRedim

Synopsis: Redimension a variant array

Declaration: `procedure VarArrayRedim (var A: Variant; HighBound: SizeInt)`

Visibility: default

Description: `VarArrayRedim` re-sizes the first dimension of the variant array `A`, giving it a new high bound `HighBound`. Obviously, `A` must be a variant array for this function to work.

Errors:

### 37.9.396 VarCast

Synopsis: Cast a variant to a certain type

Declaration: `procedure VarCast (var dest: variant; const source: variant;  
vartype: LongInt)`

Visibility: default

Description: `VarCast` converts the variant in `Source` to the type indicated in `VarType` and returns the result in `dest`. The `VarType` must be one of the pre-defined `VarNNN` constants.

Errors: If the conversion is not possible because the value cannot be correctly casted, then a run-time error or an exception may occur.

**37.9.397 WaitForThreadTerminate**

Synopsis: Wait for a thread to terminate.

Declaration: `function WaitForThreadTerminate(threadHandle: TThreadID;  
TimeoutMs: LongInt) : DWord`

Visibility: default

Description: `WaitForThreadTerminate` waits for a thread to finish its execution. The thread is identified by its handle or ID `threadHandle`. If the thread does not exit within `TimeoutMs` milliseconds, the function will return with an error value.

The function returns the exit code of the thread.

See also: `EndThread` ([1284](#)), `KillThread` ([1316](#))

**37.9.398 WideCharLenToString**

Synopsis: Convert a length-limited array of widechar to an ansistring

Declaration: `function WideCharLenToString(S: PWideChar; Len: SizeInt) : AnsiString`

Visibility: default

Description: `WideCharLenToString` converts at most `Len` widecharacters from the null-terminated widechar array `S` to an ansistring, and returns the ansistring.

Errors: No validity checking is performed on `S`. Passing an invalid pointer may lead to access violations.

See also: `StringToWideChar` ([1386](#)), `WideCharToString` ([1401](#)), `WideCharToStrVar` ([1402](#)), `WideCharLenToStrVar` ([1401](#))

**37.9.399 WideCharLenToStrVar**

Synopsis: Convert a length-limited array of widechar to an ansistring

Declaration: `procedure WideCharLenToStrVar(Src: PWideChar; Len: SizeInt;  
out Dest: AnsiString)`

Visibility: default

Description: `WideCharLenToString` converts at most `Len` widecharacters from the null-terminated widechar array `Src` to an ansistring, and returns the ansistring in `Dest`.

Errors: No validity checking is performed on `Src`. Passing an invalid pointer may lead to access violations.

See also: `StringToWideChar` ([1386](#)), `WideCharToString` ([1401](#)), `WideCharToStrVar` ([1402](#)), `WideCharLenToString` ([1401](#))

**37.9.400 WideCharToString**

Synopsis: Convert a null-terminated array of widechar to an ansistring

Declaration: `function WideCharToString(S: PWideChar) : AnsiString`

Visibility: default

Description: `WideCharToString` converts the null-terminated widechar array `S` to an ansistring, and returns the ansistring.

**Errors:** No validity checking is performed on `Src`. Passing an invalid pointer, or an improperly terminated array may lead to access violations.

See also: [StringToWideChar \(1386\)](#), [WideCharToStrVar \(1402\)](#), [WideCharLenToStrVar \(1401\)](#), [WideCharLenToString \(1401\)](#)

### 37.9.401 WideCharToStrVar

**Synopsis:** Convert a null-terminated array of widechar to an ansistring

**Declaration:** `procedure WideCharToStrVar(S: PWideChar;out Dest: AnsiString)`

**Visibility:** default

**Description:** `WideCharToString` converts the null-terminated widechar array `S` to an ansistring, and returns the ansistring in `Dest`.

**Errors:** No validity checking is performed on `S`. Passing an invalid pointer, or an improperly terminated array may lead to access violations.

See also: [StringToWideChar \(1386\)](#), [WideCharToString \(1401\)](#), [WideCharToStrVar \(1402\)](#), [WideCharLenToString \(1401\)](#)

### 37.9.402 WideStringToUCS4String

**Synopsis:** Convert a widestring to a UCS-4 encoded string.

**Declaration:** `function WideStringToUCS4String(const s: WideString) : UCS4String`

**Visibility:** default

**Description:** Convert a widestring to a UCS-4 encoded string.

**Errors:**

### 37.9.403 Write

**Synopsis:** Write variable to a text file

**Declaration:** `procedure Write(Args: Arguments)`  
`procedure Write(var F: Text;Args: Arguments)`

**Visibility:** default

**Description:** `Write` writes the contents of the variables `V1`, `V2` etc. to the file `F`. `F` can be a typed file, or a `Text` file. If `F` is a typed file, then the variables `V1`, `V2` etc. must be of the same type as the type in the declaration of `F`. Untyped files are not allowed. If the parameter `F` is omitted, standard output is assumed. If `F` is of type `Text`, then the necessary conversions are done such that the output of the variables is in human-readable format. This conversion is done for all numerical types. Strings are printed exactly as they are in memory, as well as `PChar` types. The format of the numerical conversions can be influenced through the following modifiers: `OutputVariable : NumChars [ : Decimals ]` This will print the value of `OutputVariable` with a minimum of `NumChars` characters, from which `Decimals` are reserved for the decimals. If the number cannot be represented with `NumChars` characters, `NumChars` will be increased, until the representation fits. If the representation requires less than `NumChars` characters then the output is filled up with spaces, to the left of the generated string, thus resulting in a right-aligned representation. If no formatting is specified, then the number is written using its natural length, with nothing in front of it if it's positive, and a minus sign if it's negative. Real numbers are, by default, written in scientific notation.

**Errors:** If an error occurs, a run-time error is generated. This behavior can be controlled with the `{SI}` switch.

See also: [WriteLn \(1403\)](#), [Read \(1360\)](#), [ReadLn \(1361\)](#), [Blockwrite \(1267\)](#)

### 37.9.404 WriteBarrier

**Synopsis:** Memory write barrier

**Declaration:** `procedure WriteBarrier`

**Visibility:** default

**Description:** `WriteBarrier` is a low-level instruction to force a write barrier in the CPU: write (store) operations before and after the barrier are separate.

See also: [ReadBarrier \(1360\)](#), [ReadDependencyBarrier \(1361\)](#), [ReadWriteBarrier \(1362\)](#)

### 37.9.405 WriteLn

**Synopsis:** Write variable to a text file and append newline

**Declaration:** `procedure Writeln(Args: Arguments)`  
`procedure WriteLn(var F: Text; Args: Arguments)`

**Visibility:** default

**Description:** `WriteLn` does the same as `Write (1402)` for text files, and emits a Carriage Return - LineFeed character pair after that. If the parameter `F` is omitted, standard output is assumed. If no variables are specified, a Carriage Return - LineFeed character pair is emitted, resulting in a new line in the file `F`.

**Remark:** Under linux and unix, the Carriage Return character is omitted, as customary in Unix environments.

**Errors:** If an error occurs, a run-time error is generated. This behavior can be controlled with the `{SI}` switch.

See also: [Write \(1402\)](#), [Read \(1360\)](#), [ReadLn \(1361\)](#), [Blockwrite \(1267\)](#)

**Listing:** `./refex/ex75.pp`

---

**Program** Example75;

```
{ Program to demonstrate the Write(Ln) function. }
```

---

```
Var
  F : File of Longint;
  L : Longint;

begin
  Write ( 'This is on the first line ! '); { No CR/LF pair! }
  Writeln ( 'And this too... ');
  Writeln ( 'But this is already on the second line... ');
  Assign ( f, 'test.tmp' );
  Rewrite ( f );
  For L:=1 to 10 do
    write ( F,L ); { No writeln allowed here ! }
  Close ( f );
end.
```

---

### 37.9.406 WriteStr

Synopsis: Write variables to a string

Declaration: `procedure WriteStr(out S: String; Args: Arguments)`

Visibility: default

Description: `WriteStr` behaves like `Write` (1402), except that it stores its output in the string variable `S` instead of a file. Semantically, the `WriteStr` call is equivalent to writing the arguments to a file using the `Write` call, and then reading them into `S` using the `Read` call from the same file:

```

var
  F : Text;
begin
  Rewrite(F);
  Write(F, Args);
  Close(F);
  Reset(F);
  Read(F, S);
  Close(F);
end;

```

Obviously, the `WriteStr` call does not use a temporary file.

`WriteStr` is defined in the ISO Extended Pascal standard. More information on the allowed arguments and the possible formatting can be found in the description of `Write` (1402).

See also: `Write` (1402), `ReadStr` (1361), `Read` (1360)

## 37.10 IDispatch

### 37.10.1 Description

`IDispatch` is the pascal definition of the Windows Dispatch interface definition.

### 37.10.2 Method overview

Page	Property	Description
<a href="#">1405</a>	<code>GetIDsOfNames</code>	Return IDs of named procedures
<a href="#">1405</a>	<code>GetTypeInfo</code>	Return type information about properties
<a href="#">1404</a>	<code>GetTypeInfoCount</code>	Return number of properties.
<a href="#">1405</a>	<code>Invoke</code>	Invoke a dispatch method

### 37.10.3 IDispatch.GetTypeInfoCount

Synopsis: Return number of properties.

Declaration: `function GetTypeInfoCount(out count: LongInt) : HRESULT`

Visibility: default

### 37.10.4 IDispatch.GetTypeInfo

Synopsis: Return type information about properties

Declaration: `function GetTypeInfo(Index: LongInt; LocaleID: LongInt; out TypeInfo)  
: HRESULT`

Visibility: default

### 37.10.5 IDispatch.GetIDsOfNames

Synopsis: Return IDs of named procedures

Declaration: `function GetIDsOfNames(const iid: TGuid; names: Pointer;  
NameCount: LongInt; LocaleID: LongInt;  
DispIDs: Pointer) : HRESULT`

Visibility: default

Description: Return the ID of a procedure.

### 37.10.6 IDispatch.Invoke

Synopsis: Invoke a dispatch method

Declaration: `function Invoke(DispID: LongInt; const iid: TGuid; LocaleID: LongInt;  
Flags: Word; var params; VarResult: pointer;  
ExcepInfo: pointer; ArgErr: pointer) : HRESULT`

Visibility: default

## 37.11 IEnumerable

### 37.11.1 Description

`IEnumerable` can be used to get an enumerator from a class. If a class implements `IEnumerable`, it can return an enumerator interface `IEnumerator` ([1406](#)).

### 37.11.2 Method overview

Page	Property	Description
<a href="#">1405</a>	<code>GetEnumerator</code>	Return an enumerator interface for this class

### 37.11.3 IEnumerable.GetEnumerator

Synopsis: Return an enumerator interface for this class

Declaration: `function GetEnumerator : IEnumerator`

Visibility: default

Description: `GetEnumerator` returns a new `IEnumerator` ([1406](#)) interface for this class. This is called by the compiler whenever a `for in` loop is encountered in the source code to retrieve the enumerator instance.

See also: `IEnumerator` ([1406](#))

## 37.12 IEnumerator

### 37.12.1 Description

`IEnumerator` is the interface needed by the `For ... in ...` language construct, when operating on classes. It contains all methods that the compiler needs to implement a loop.

A `for in` loop like the following:

```
For O in MyObject do
  begin
    // do things
  end;
```

is treated by the compiler as equivalent to the following code:

```
Var
  I : IEnumerator;
  O : TObject;

begin
  I:=MyObject.GetEnumerator;
  While I.MoveNext do
    begin
      O:=I.GetCurrent;
      // Do things
    end;
end.
```

Any class that implements the `IEnumerable` interface must be able to return an `IEnumerator` instance for the compiler to use in a `For in` loop.

### 37.12.2 Method overview

Page	Property	Description
<a href="#">1406</a>	<code>GetCurrent</code>	Returns the current element in the iteration cycle
<a href="#">1407</a>	<code>MoveNext</code>	Move to the next value
<a href="#">1407</a>	<code>Reset</code>	Reset the pointer

### 37.12.3 Property overview

Page	Property	Access	Description
<a href="#">1407</a>	<code>Current</code>	<code>r</code>	Return the current item

### 37.12.4 IEnumerator.GetCurrent

**Synopsis:** Returns the current element in the iteration cycle

**Declaration:** `function GetCurrent : TObject`

**Visibility:** default

**Description:** `GetCurrent` should return the object instance representing the current value in the `for in` loop. `GetCurrent` will always be called immediatly after `MoveNext` ([1209](#)) returned `True`.



**Remark:** The actual return type of the interface should not necessarily be `TObject`, it can be any type. The compiler will check the actual return type with the type of the loop variable, and they should match.

See also: `IEnumerator.MoveNext` (1407), `IEnumerator.Reset` (1407)

### 37.12.5 `IEnumerator.MoveNext`

Synopsis: Move to the next value

Declaration: `function MoveNext : Boolean`

Visibility: default

Description: `MoveNext` should move the current item pointer to the next available item. It should return `True` if an item is available, `False` if no more items are available. The first time it is called It will be called at the beginning of the for loop, so it should position the enumerator on the first value (if there is one). After `MoveNext` has returned `True`, `IEnumerator.GetCurrent` (1406) will be called to retrieve the item.

See also: `IEnumerator.Reset` (1407), `IEnumerator.GetCurrent` (1406)

### 37.12.6 `IEnumerator.Reset`

Synopsis: Reset the pointer

Declaration: `procedure Reset`

Visibility: default

Description: `Reset` can be implemented to put the pointer at the start of the list. It is not mandatory to implement this method, the compiler does not use it.

See also: `IEnumerator.GetCurrent` (1406), `IEnumerator.MoveNext` (1407)

### 37.12.7 `IEnumerator.Current`

Synopsis: Return the current item

Declaration: `Property Current : TObject`

Visibility: default

Access: Read

Description: `Current` simply is the redefinition of `GetCurrent` (1209) as a property. It is read-only.

See also: `GetCurrent` (1209), `IEnumerator.MoveNext` (1407)

## 37.13 `IInvokable`

### 37.13.1 Description

`IInvokable` is a descendent of `IInterface` (1234), compiled in the `{ $M+ }` state, so Run-Time Type Information (RTTI) is generated for it.

## 37.14 IUnknown

### 37.14.1 Description

IUnknown is defined by windows. It's the basic interface which all COM objects must implement. The definition does not contain any code.

### 37.14.2 Method overview

Page	Property	Description
<a href="#">1408</a>	<code>\_AddRef</code>	Increase reference count of the interface
<a href="#">1408</a>	<code>\_Release</code>	Decrease reference count of the interface
<a href="#">1408</a>	<code>QueryInterface</code>	Return pointer to VMT table of interface

### 37.14.3 IUnknown.QueryInterface

Synopsis: Return pointer to VMT table of interface

Declaration: `function QueryInterface(const iid: TGuid;out obj) : LongInt`

Visibility: default

### 37.14.4 IUnknown.\_AddRef

Synopsis: Increase reference count of the interface

Declaration: `function _AddRef : LongInt`

Visibility: default

See also: `IUnknown._Release` ([1408](#))

### 37.14.5 IUnknown.\_Release

Synopsis: Decrease reference count of the interface

Declaration: `function _Release : LongInt`

Visibility: default

See also: `IUnknown._AddRef` ([1408](#))

## 37.15 TAggregatedObject

### 37.15.1 Description

TAggregatedObject implements an object whose lifetime is governed by an external object (or interface). It does not implement the IUnknown interface by itself, but delegates all methods to the controller object, as exposed in the Controller ([1409](#)) property. In effect, the reference count of the aggregated object is the same as that of it's controller, and additionally, all interfaces of the controller are exposed by the aggregated object.

Note that the aggregated object maintains a non-counted reference to the controller.

Aggregated objects should be used when using delegation to implement reference counted objects: the delegated interfaces can be implemented safely by TAggregatedObject descendents.

### 37.15.2 Method overview

Page	Property	Description
<a href="#">1409</a>	Create	Create a new instance of TAggregatedObject

### 37.15.3 Property overview

Page	Property	Access	Description
<a href="#">1409</a>	Controller	r	Controlling instance

### 37.15.4 TAggregatedObject.Create

Synopsis: Create a new instance of TAggregatedObject

Declaration: `constructor Create(const aController: IUnknown)`

Visibility: public

Description: Create creates a new instance of TAggregatedObject on the heap, and stores a reference to aController, so it can be exposed in the Controller ([1409](#)) property.

Errors: If not enough memory is present on the heap, an exception will be raised. If the aController is Nil, exceptions will occur when any of the TAggregatedObject methods (actually, the IUnknown methods) are used.

See also: TAggregatedObject.Controller ([1409](#))

### 37.15.5 TAggregatedObject.Controller

Synopsis: Controlling instance

Declaration: `Property Controller : IUnknown`

Visibility: public

Access: Read

Description: Controller exposes the controlling object, with all interfaces it has.

The value of the controller is set when the TAggregatedObject instance is created.

See also: TAggregatedObject.Create ([1409](#))

## 37.16 TContainedObject

### 37.16.1 Description

TContainedObject is the base class for contained objects, i.e. objects that do not implement a reference counting mechanism themselves, but are owned by some other object which handles the reference counting mechanism. It implements the IUnknown interface and, more specifically, the QueryInterface method of IUnknown.

## 37.17 TInterfacedObject

### 37.17.1 Description

TInterfacedObject is a descendent of TObject (1411) which implements the IUnknown (1408) interface. It can be used as a base class for all classes which need reference counting.

### 37.17.2 Method overview

Page	Property	Description
<a href="#">1410</a>	AfterConstruction	Handle reference count properly.
<a href="#">1410</a>	BeforeDestruction	Check reference count.
<a href="#">1410</a>	NewInstance	Create a new instance

### 37.17.3 Property overview

Page	Property	Access	Description
<a href="#">1411</a>	RefCount	r	Return the current reference count

### 37.17.4 TInterfacedObject.AfterConstruction

Synopsis: Handle reference count properly.

Declaration: `procedure AfterConstruction; Override`

Visibility: `public`

Description: `AfterConstruction` overrides the basic method in TObject and adds some additional reference count handling.

Errors: None.

See also: TInterfacedObject.BeforeDestruction ([1410](#))

### 37.17.5 TInterfacedObject.BeforeDestruction

Synopsis: Check reference count.

Declaration: `procedure BeforeDestruction; Override`

Visibility: `public`

Description: `AfterConstruction` overrides the basic method in TObject and adds a reference count check: if the reference count is not zero, an error occurs.

Errors: A runtime-error 204 will be generated if the reference count is nonzero when the object is destroyed.

See also: TInterfacedObject.AfterConstruction ([1410](#))

### 37.17.6 TInterfacedObject.NewInstance

Synopsis: Create a new instance

Declaration: `function NewInstance : TObject; Override`

Visibility: `public`

**Description:** `NewInstance` initializes a new instance of `TInterfacedObject` ([1410](#))

**Errors:** None.

### 37.17.7 TInterfacedObject.RefCount

**Synopsis:** Return the current reference count

**Declaration:** `Property RefCount : LongInt`

**Visibility:** `public`

**Access:** `Read`

**Description:** `RefCount` returns the current reference count. This reference count cannot be manipulated, except through the methods of `IUnknown` ([1408](#)). When it reaches zero, the class instance is destroyed.

**See also:** `IUnknown` ([1408](#))

## 37.18 TObject

### 37.18.1 Description

`TObject` is the parent root class for all classes in Object Pascal. If a class has no parent class explicitly declared, it is dependent on `TObject`. `TObject` introduces class methods that deal with the class' type information, and contains all necessary methods to create an instance at runtime, and to dispatch messages to the correct method (both string and integer messages).

**37.18.2 Method overview**

Page	Property	Description
<a href="#">1417</a>	<code>AfterConstruction</code>	Method called after the constructor was called.
<a href="#">1418</a>	<code>BeforeDestruction</code>	Method called before the destructor is called.
<a href="#">1415</a>	<code>ClassInfo</code>	Return a pointer to the type information for this class.
<a href="#">1415</a>	<code>ClassName</code>	Return the current class name.
<a href="#">1415</a>	<code>ClassNameIs</code>	Check whether the class name equals the given name.
<a href="#">1416</a>	<code>ClassParent</code>	Return the parent class.
<a href="#">1415</a>	<code>ClassType</code>	Return a "class of" pointer for the current class
<a href="#">1414</a>	<code>CleanupInstance</code>	Finalize the class instance.
<a href="#">1412</a>	<code>Create</code>	<code>TObject</code> Constructor
<a href="#">1414</a>	<code>DefaultHandler</code>	Default handler for integer message handlers.
<a href="#">1418</a>	<code>DefaultHandlerStr</code>	Default handler for string messages.
<a href="#">1413</a>	<code>Destroy</code>	<code>TObject</code> destructor.
<a href="#">1418</a>	<code>Dispatch</code>	Dispatch an integer message
<a href="#">1418</a>	<code>DispatchStr</code>	Dispatch a string message.
<a href="#">1420</a>	<code>Equals</code>	Check if two objects are equal.
<a href="#">1417</a>	<code>FieldAddress</code>	Return the address of a field.
<a href="#">1414</a>	<code>Free</code>	Check for <code>Nil</code> and call destructor.
<a href="#">1413</a>	<code>FreeInstance</code>	Clean up instance and free the memory reserved for the instance.
<a href="#">1421</a>	<code>GetHashCode</code>	Return a hash code for the object
<a href="#">1419</a>	<code>GetInterface</code>	Return a reference to an interface
<a href="#">1419</a>	<code>GetInterfaceByStr</code>	Return an interface based on its GUID
<a href="#">1419</a>	<code>GetInterfaceEntry</code>	Return the interface table entry by GUID
<a href="#">1420</a>	<code>GetInterfaceEntryByStr</code>	Return the interface table entry by string
<a href="#">1420</a>	<code>GetInterfaceTable</code>	Return a pointer to the table of implemented interfaces for a class
<a href="#">1416</a>	<code>InheritsFrom</code>	Check whether class is an ancestor.
<a href="#">1414</a>	<code>InitInstance</code>	Initialize a new class instance.
<a href="#">1416</a>	<code>InstanceSize</code>	Return the size of an instance.
<a href="#">1417</a>	<code>MethodAddress</code>	Return the address of a method
<a href="#">1417</a>	<code>MethodName</code>	Return the name of a method.
<a href="#">1413</a>	<code>newinstance</code>	Allocate memory on the heap for a new instance
<a href="#">1413</a>	<code>SafeCallException</code>	Handle exception object
<a href="#">1416</a>	<code>StringMessageTable</code>	Return a pointer to the string message table.
<a href="#">1421</a>	<code>ToString</code>	Return a string representation for the object
<a href="#">1420</a>	<code>UnitName</code>	Unit name

**37.18.3 TObject.Create**

Synopsis: `TObject` Constructor

Declaration: `constructor Create`

Visibility: `public`

Description: `Create` creates a new instance of `TObject`. Currently it does nothing. It is also not virtual, so there is in principle no need to call it directly.

See also: `TObject.Destroy` ([1413](#))

### 37.18.4 TObject.Destroy

Synopsis: TObject destructor.

Declaration: destructor Destroy; Virtual

Visibility: public

Description: Destroy is the destructor of TObject. It will clean up the memory assigned to the instance. Descendent classes should override destroy if they want to do additional clean-up. No other destructor should be implemented.

It is bad programming practice to call Destroy directly. It is better to call the Free (1414) method, because that one will check first if Self is different from Nil.

To clean up an instance and reset the reference to the instance, it is best to use the FreeAndNil (1512) function.

See also: TObject.Create (1412), TObject.Free (1414)

### 37.18.5 TObject.newinstance

Synopsis: Allocate memory on the heap for a new instance

Declaration: function newInstance : TObject; Virtual

Visibility: public

Description: NewInstance allocates memory on the heap for a new instance of the current class. If the memory was allocated, the class will be initialized by a call to InitInstance (1414). The function returns the newly initialized instance.

Errors: If not enough memory is available, a Nil pointer may be returned, or an exception may be raised.

See also: TObject.Create (1412), TObject.InitInstance (1414), TObject.InstanceSize (1416), TObject.FreeInstance (1413)

### 37.18.6 TObject.FreeInstance

Synopsis: Clean up instance and free the memory reserved for the instance.

Declaration: procedure FreeInstance; Virtual

Visibility: public

Description: FreeInstance cleans up an instance of the current class, and releases the heap memory occupied by the class instance.

See also: TObject.Destroy (1413), TObject.InitInstance (1414), TObject.NewInstance (1413)

### 37.18.7 TObject.SafeCallException

Synopsis: Handle exception object

Declaration: function SafeCallException(exceptobject: TObject; exceptaddr: pointer)  
: LongInt; Virtual

Visibility: public

Description: SafeCallException should be overridden to handle exceptions in a method marked with the savecall directive. The implementation in TObject simply returns zero.

### 37.18.8 TObject.DefaultHandler

Synopsis: Default handler for integer message handlers.

Declaration: `procedure DefaultHandler(var message); Virtual`

Visibility: public

Description: `DefaultHandler` is the default handler for messages. If a message has an unknown message ID (i.e. does not appear in the table with integer message handlers), then it will be passed to `DefaultHandler` by the `Dispatch` (1418) method.

Errors:

See also: `TObject.Dispatch` (1418), `TObject.DefaultHandlerStr` (1418)

### 37.18.9 TObject.Free

Synopsis: Check for Nil and call destructor.

Declaration: `procedure Free`

Visibility: public

Description: `Free` will check the `Self` pointer and calls `Destroy` (1413) if it is different from Nil. This is a safer method than calling `Destroy` directly. If a reference to the object must be reset as well (a recommended technique), then the function `FreeAndNil` (1512) should be called.

Errors: None.

See also: `TObject.Destroy` (1413), `#rtl.sysutils.freeandnil` (1512)

### 37.18.10 TObject.InitInstance

Synopsis: Initialize a new class instance.

Declaration: `function InitInstance(instance: pointer) : TObject`

Visibility: public

Description: `InitInstance` initializes the memory pointer to by `Instance`. This means that the VMT is initialized, and the interface pointers are set up correctly. The function returns the newly initialized instance.

See also: `TObject.NewInstance` (1413), `TObject.Create` (1412)

### 37.18.11 TObject.CleanupInstance

Synopsis: Finalize the class instance.

Declaration: `procedure CleanupInstance`

Visibility: public

Description: `CleanUpInstance` finalizes the instance, i.e. takes care of all reference counted objects, by decreasing their reference count by 1, and freeing them if their count reaches zero.

Normally, `CleanupInstance` should never be called, it is called automatically when the object is freed with it's constructor.

Errors: None.

See also: `TObject.Destroy` (1413), `TObject.Free` (1414), `TObject.InitInstance` (1414)



### 37.18.12 TObject.ClassType

Synopsis: Return a "class of" pointer for the current class

Declaration: `function ClassType : TClass`

Visibility: public

Description: `ClassType` returns a `TClass` (1243) class type reference for the current class.

See also: `TClass` (1243), `TObject.ClassInfo` (1415), `TObject.ClassName` (1415)

### 37.18.13 TObject.ClassInfo

Synopsis: Return a pointer to the type information for this class.

Declaration: `function ClassInfo : pointer`

Visibility: public

Description: `ClassInfo` returns a pointer to the type information for this class. This pointer can be used in the various type information routines.

### 37.18.14 TObject.ClassName

Synopsis: Return the current class name.

Declaration: `function ClassName : shortstring`

Visibility: public

Description: `ClassName` returns the class name for the current class, in all-uppercase letters. To check for the class name, use the `ClassNameIs` (1415) class method.

Errors: None.

See also: `TObject.ClassInfo` (1415), `TObject.ClassType` (1415), `TObject.ClassNameIs` (1415)

### 37.18.15 TObject.ClassNameIs

Synopsis: Check whether the class name equals the given name.

Declaration: `function ClassNameIs(const name: String) : Boolean`

Visibility: public

Description: `ClassNameIs` checks whether `Name` equals the class name. It takes of case sensitivity, i.e. it converts both names to uppercase before comparing.

See also: `TObject.ClassInfo` (1415), `TObject.ClassType` (1415), `TObject.ClassName` (1415)

**37.18.16 TObject.ClassParent**

Synopsis: Return the parent class.

Declaration: `function ClassParent : TClass`

Visibility: public

Description: `ClassParent` returns the class of the parent class of the current class. This is always different from `Nil`, except for `TObject`.

Errors: None.

See also: `TObject.ClassInfo` (1415), `TObject.ClassType` (1415), `TObject.ClassName` (1415)

**37.18.17 TObject.InstanceSize**

Synopsis: Return the size of an instance.

Declaration: `function InstanceSize : SizeInt`

Visibility: public

Description: `InstanceSize` returns the number of bytes an instance takes in memory. This is Just the memory occupied by the class structure, and does not take into account any additional memory that might be allocated by the constructor of the class.

Errors: None.

See also: `TObject.InitInstance` (1414), `TObject.ClassName` (1415), `TObject.ClassInfo` (1415), `TObject.ClassType` (1415)

**37.18.18 TObject.InheritsFrom**

Synopsis: Check whether class is an ancestor.

Declaration: `function InheritsFrom(aClass: TClass) : Boolean`

Visibility: public

Description: `InheritsFrom` returns `True` if `AClass` is an ancestor class from the current class, and returns `false` if it is not.

Errors:

See also: `TObject.ClassName` (1415), `TObject.ClassInfo` (1415), `TObject.ClassType` (1415), `TClass` (1243)

**37.18.19 TObject.StringMessageTable**

Synopsis: Return a pointer to the string message table.

Declaration: `function StringMessageTable : pstringmessagetable`

Visibility: public

Description: `StringMessageTable` returns a pointer to the string message table, which can be used to look up methods for dispatching a string message. It is used by the `DispatchStr` (1418) method.

Errors: If there are no string message handlers, `nil` is returned.

See also: `TObject.DispatchStr` (1418), `TObject.Dispatch` (1418)

### 37.18.20 TObject.MethodAddress

Synopsis: Return the address of a method

Declaration: `function MethodAddress(const name: shortstring) : pointer`

Visibility: public

Description: `MethodAddress` returns the address of a method, searching the method by its name. The `Name` parameter specifies which method should be taken. The search is conducted in a case-insensitive manner.

Errors: If no matching method is found, `Nil` is returned.

See also: `TObject.MethodName` ([1417](#)), `TObject.FieldAddress` ([1417](#))

### 37.18.21 TObject.MethodName

Synopsis: Return the name of a method.

Declaration: `function MethodName(address: pointer) : shortstring`

Visibility: public

Description: `MethodName` searches the VMT for a method with the specified address and returns the name of the method.

Errors: If no method with the matching address is found, an empty string is returned.

See also: `TObject.MethodAddress` ([1417](#)), `TObject.FieldAddress` ([1417](#))

### 37.18.22 TObject.FieldAddress

Synopsis: Return the address of a field.

Declaration: `function FieldAddress(const name: shortstring) : pointer`

Visibility: public

Description: `FieldAddress` returns the address of the field with name `name`. The address is the address of the field in the current class instance.

Errors: If no field with the specified name is found, `Nil` is returned.

See also: `TObject.MethodAddress` ([1417](#)), `TObject.MethodName` ([1417](#))

### 37.18.23 TObject.AfterConstruction

Synopsis: Method called after the constructor was called.

Declaration: `procedure AfterConstruction; Virtual`

Visibility: public

Description: `AfterConstruction` is a method called after the constructor was called. It does nothing in the implementation of `TObject` and must be overridden by descendent classes to provide specific behaviour that is executed after the constructor has finished executing. (for instance, call an event handler)

Errors: None.

See also: `TObject.BeforeDestruction` ([1418](#)), `TObject.Create` ([1412](#))

### 37.18.24 TObject.BeforeDestruction

Synopsis: Method called before the destructor is called.

Declaration: `procedure BeforeDestruction; Virtual`

Visibility: `public`

Description: `BeforeDestruction` is a method called before the destructor is called. It does nothing in the implementation of `TObject` and must be overridden by descendent classes to provide specific behaviour that is executed before the destructor has finished executing. (for instance, call an event handler)

Errors: None.

See also: `TObject.AfterConstruction` ([1417](#)), `TObject.Destroy` ([1413](#)), `TObject.Free` ([1414](#))

### 37.18.25 TObject.DefaultHandlerStr

Synopsis: Default handler for string messages.

Declaration: `procedure DefaultHandlerStr(var message); Virtual`

Visibility: `public`

Description: `DefaultHandlerStr` is called for string messages which have no handler associated with them in the string message handler table. The implementation of `DefaultHandlerStr` in `TObject` does nothing and must be overridden by descendent classes to provide specific message handling behaviour.

See also: `TObject.DispatchStr` ([1418](#)), `TObject.Dispatch` ([1418](#)), `TObject.DefaultHandler` ([1414](#))

### 37.18.26 TObject.Dispatch

Synopsis: Dispatch an integer message

Declaration: `procedure Dispatch(var message); Virtual`

Visibility: `public`

Description: `Dispatch` looks in the message handler table for a handler that handles `message`. The message is identified by the first dword (cardinal) in the message structure.

If no matching message handler is found, the message is passed to the `DefaultHandler` ([1414](#)) method, which can be overridden by descendent classes to add custom handling of messages.

See also: `TObject.DispatchStr` ([1418](#)), `TObject.DefaultHandler` ([1414](#))

### 37.18.27 TObject.DispatchStr

Synopsis: Dispatch a string message.

Declaration: `procedure DispatchStr(var message); Virtual`

Visibility: `public`

Description: `DispatchStr` extracts the message identifier from `Message` and checks the message handler table to see if a handler for the message is found, and calls the handler, passing along the message. If no handler is found, the default `DefaultHandlerStr` ([1418](#)) is called.

Errors: None.

See also: [TObject.DefaultHandlerStr \(1418\)](#), [TObject.Dispatch \(1418\)](#), [TObject.DefaultHandler \(1414\)](#)

### 37.18.28 TObject.GetInterface

Synopsis: Return a reference to an interface

Declaration: `function GetInterface(const iid: TGuid;out obj) : Boolean`  
`function GetInterface(const iidstr: shortstring;out obj) : Boolean`

Visibility: public

Description: `GetInterface` scans the interface tables and returns a reference to the interface `iid`. The reference is stored in `Obj` which should be an interface reference. It returns `True` if the interface was found, `False` if not.

The reference count of the interface is increased by this call.

Errors: If no interface was found, `False` is returned.

See also: [TObject.GetInterfaceByStr \(1419\)](#)

### 37.18.29 TObject.GetInterfaceByStr

Synopsis: Return an interface based on its GUID

Declaration: `function GetInterfaceByStr(const iidstr: shortstring;out obj) : Boolean`

Visibility: public

Description: `GetInterfaceByStr` returns in `obj` a pointer to the interface identified by `iidstr`. The function returns `True` if the interface is indeed implemented by the class, or `False` otherwise.

The `iidstr` is the unique GUID by which the interface was declared.

Errors: The function returns false if the requested interface is not implemented.

See also: [TObject.GetInterfaceEntry \(1419\)](#), [TObject.GetInterfaceEntryByStr \(1420\)](#)

### 37.18.30 TObject.GetInterfaceEntry

Synopsis: Return the interface table entry by GUID

Declaration: `function GetInterfaceEntry(const iid: TGuid) : pinterfaceentry`

Visibility: public

Description: `GetInterfaceEntry` returns the internal interface table entry for the interface identified by `iid` (the GUID used in the declaration of the interface). If the interface is not implemented by the class, the function returns `Nil`.

See also: [TObject.GetInterfaceByStr \(1419\)](#), [TObject.GetInterfaceEntryByStr \(1420\)](#)

**37.18.31 TObject.GetInterfaceEntryByStr**

Synopsis: Return the interface table entry by string

Declaration: `function GetInterfaceEntryByStr(const iidstr: shortstring)  
: pinterfaceentry`

Visibility: public

Description: `GetInterfaceEntryByStr` returns the internal interface table entry for the interface identified by `iidstr` (A string representation of the GUID used in the declaration of the interface). If the interface is not implemented by the class, the function returns `Nil`.

See also: `TObject.GetInterfaceByStr` (1419), `TObject.GetInterfaceEntry` (1419)

**37.18.32 TObject.GetInterfaceTable**

Synopsis: Return a pointer to the table of implemented interfaces for a class

Declaration: `function GetInterfaceTable : pinterfacetable`

Visibility: public

Description: `GetInterfaceTable` returns a pointer to the internal table of implemented interfaces for a class. The result will always point to a valid address, if the class implements no interfaces the `EntryCount` field of the interface table will be zero.

See also: `TObject.GetInterfaceByStr` (1419), `TObject.GetInterfaceEntry` (1419)

**37.18.33 TObject.UnitName**

Synopsis: Unit name

Declaration: `function UnitName : ansistring`

Visibility: public

Description: `UnitName` returns the unit name in which the class was defined. The name is obtained from the class definition data the compiler generates for each class.

**37.18.34 TObject.Equals**

Synopsis: Check if two objects are equal.

Declaration: `function Equals(Obj: TObject) : Boolean; Virtual`

Visibility: public

Description: `Equals` returns `True` if the object instance pointer (`Self`) equals the instance pointer `Obj`. Descendent classes can override to check properties etc. in case the instance pointers are different.

See also: `TObject.GetHashCode` (1421), `TObject.ToString` (1421)

### 37.18.35 TObject.GetHashCode

Synopsis: Return a hash code for the object

Declaration: `function GetHashCode : PtrInt; Virtual`

Visibility: `public`

Description: `GetHashCode` should return a hash code for the object. By default, the numerical (integer) address of `Self` is returned.

Descendent classes can use this to generate better suitable values to be used in a hash table.

See also: `TObject.ToString` ([1421](#)), `TObject.Equals` ([1420](#))

### 37.18.36 TObject.ToString

Synopsis: Return a string representation for the object

Declaration: `function ToString : ansistring; Virtual`

Visibility: `public`

Description: `ToString` returns by default the class name of the object. It is useful during sending of debug messages.

Descendent classes can override this method to give a better description of the object than just the class name.

See also: `TObject.GetHashCode` ([1421](#)), `TObject.Equals` ([1420](#))

Table 37.5:

Name	Description
Addr (1259)	Return address of variable
Assigned (1263)	Check if a pointer is valid
CompareByte (1270)	Compare 2 memory buffers byte per byte
CompareChar (1271)	Compare 2 memory buffers byte per byte
CompareDWord (1273)	Compare 2 memory buffers byte per byte
CompareWord (1274)	Compare 2 memory buffers byte per byte
CSeg (1278)	Return code segment
Dispose (1281)	Free dynamically allocated memory
DSeg (1282)	Return data segment
FillByte (1292)	Fill memory region with 8-bit pattern
FillChar (1293)	Fill memory region with certain character
FillDWord (1293)	Fill memory region with 32-bit pattern
FillQWord (1294)	Fill memory region with 64-bit pattern
FillWord (1294)	Fill memory region with 16-bit pattern
Freemem (1297)	Release allocated memory
Getmem (1299)	Allocate new memory
GetMemoryManager (1300)	Return current memory manager
High (1305)	Return highest index of open array or enumerated
IndexByte (1307)	Find byte-sized value in a memory range
IndexChar (1308)	Find char-sized value in a memory range
IndexDWord (1309)	Find DWord-sized (32-bit) value in a memory range
IndexQWord (1310)	Find QWord-sized value in a memory range
IndexWord (1310)	Find word-sized value in a memory range
IsMemoryManagerSet (1316)	Is the memory manager set
Low (1320)	Return lowest index of open array or enumerated
Move (1322)	Move data from one location in memory to another
MoveChar0 (1322)	Move data till first zero character
New (1323)	Dynamically allocate memory for variable
Ofs (1325)	Return offset of variable
Ptr (1358)	Combine segment and offset to pointer
ReAllocMem (1363)	Resize a memory block on the heap
Seg (1374)	Return segment
SetMemoryManager (1376)	Set a memory manager
Sptr (1382)	Return current stack pointer
SSeg (1383)	Return stack segment register value



Table 37.6:

Name	Description
Append (1260)	Open a file in append mode
Assign (1262)	Assign a name to a file
Blockread (1266)	Read data from a file into memory
Blockwrite (1267)	Write data from memory to a file
Close (1269)	Close a file
Eof (1286)	Check for end of file
Eoln (1286)	Check for end of line
Erase (1287)	Delete file from disk
Filepos (1291)	Position in file
Filesize (1291)	Size of file
Flush (1296)	Write file buffers to disk
IOresult (1315)	Return result of last file IO operation
Read (1360)	Read from file into variable
Readln (1361)	Read from file into variable and goto next line
Rename (1364)	Rename file on disk
Reset (1364)	Open file for reading
Rewrite (1365)	Open file for writing
Seek (1372)	Set file position
SeekEof (1373)	Set file position to end of file
SeekEoln (1373)	Set file position to end of line
SetTextBuf (1377)	Set size of file buffer
Truncate (1393)	Truncate the file at position
Write (1402)	Write variable to file
WriteLn (1403)	Write variable to file and append newline

Table 37.7: Enumeration values for type `tinterfaceentrytype`

Value	Explanation
<code>etFieldValue</code>	Field value
<code>etStandard</code>	Standard entry
<code>etStaticMethodResult</code>	Static method
<code>etVirtualMethodResult</code>	Virtual method

Table 37.8: Enumeration values for type TRuntimeError

Value	Explanation
reAccessViolation	Access Violation
reAssertionFailed	Assertion failed error
reCodesetConversion	Code set conversion error
reControlBreak	User pressed CTRL-C
reDivByZero	Division by zero error
reExternalException	An external exception occurred
reIntfCastError	Interface typecast error
reIntOverflow	Integer overflow error
reInvalidCast	Invalid (class) typecast error
reInvalidOp	Invalid operation error
reInvalidPtr	Invalid pointer error
reNone	No error
reOutOfMemory	Out of memory error
reOverflow	Overflow error
rePrivInstruction	Privileged instruction error
reQuit	Quit signal error
reRangeError	Range check error
reSafeCallError	Safecall (IDispInterface) error
reStackOverflow	Stack overflow error
reUnderflow	Underflow error
reVarArrayBounds	Variant array bounds error
reVarArrayCreate	Variant array creation error
reVarDispatch	Variant Dispatch error.
reVarInvalidOp	Invalid variant operation error
reVarNotArray	Variant is not an array error.
reVarTypeCast	Invalid typecase from variant
reZeroDivide	Division by zero error

Table 37.9: Enumeration values for type TTextLineBreakStyle

Value	Explanation
tlbsCR	Carriage-return (#13, Mac-OS style)
tlbsCRLF	Carriage-return, line-feed (#13#30, Windows style)
tlbsLF	Line-feed only (#10, unix style)

Table 37.10: Enumeration values for type tvarop

Value	Explanation
opadd	Variant operation: Addition.
opand	Variant operation: Binary AND operation
opcmpeq	Variant operation: Compare equal.
opcmpge	Variant operation: Compare larger than or equal
opcmpgt	Variant operation: Compare larger than
opcmple	Variant operation: Compare less than or equal to
opcmplt	Variant operation: Compare less than.
opcmpne	Variant operation: Compare not equal
opcompare	Variant operation: Compare
opdivide	Variant operation: division
opintdivide	Variant operation: integer divide
opmodulus	Variant operation: Modulus
opmultiply	Variant operation: multiplication
opnegate	Variant operation: negation.
opnot	Variant operation: Binary NOT operation.
opor	Variant operation: Binary OR operation
oppower	Variant operation: Power
opshiftleft	Variant operation: Shift left
opshiftright	Variant operation: Shift right
opsubtract	Variant operation: Substraction
opxor	Variant operation: binary XOR operation.

## Chapter 38

# Reference for unit 'sysutils'

### 38.1 Used units

Table 38.1: Used units by unit 'sysutils'

Name	Page
errors	<a href="#">1426</a>
sysconst	<a href="#">1426</a>
Unix	<a href="#">1426</a>
Unixtype	<a href="#">1426</a>

### 38.2 Overview

This documentation describes the `sysutils` unit. The `sysutils` unit was started by Gertjan Schouten, and completed by Michael Van Canneyt. It aims to be compatible to the Delphi `sysutils` unit, but in contrast with the latter, it is designed to work on multiple platforms. It is implemented on all supported platforms.

### 38.3 Localization support

Localization support depends on various constants and structures being initialized correctly. On Windows and OS/2 this is done automatically: a widestring manager is installed by default which helps taking care of the current locale when performing various operations on strings. The various internationalization settings (date/time format, currency, language etc) are also initialized correctly on these platforms.

On unixes, the widestring support is in a separate unit: `cwstring`, which loads the various needed functions from the C library. It should be added manually to the uses clause of your program. No initialization settings are applied by this unit, these must be initialized separately for the moment.

## 38.4 Miscellaneous conversion routines

Functions for various conversions.

Table 38.2:

Name	Description
BCDToInt (1462)	Convert BCD number to integer
CompareMem (1465)	Compare two memory regions
FloatToStrF (1500)	Convert float to formatted string
FloatToStr (1499)	Convert float to string
FloatToText (1502)	Convert float to string
FormatFloat (1511)	Format a floating point value
GetDirs (1514)	Split string in list of directories
IntToHex (1521)	return hexadecimal representation of integer
IntToStr (1521)	return decumal representation of integer
StrToIntDef (1553)	Convert string to integer with default value
StrToInt (1552)	Convert string to integer
StrToFloat (1551)	Convert string to float
TextToFloat (1557)	Convert null-terminated string to float

## 38.5 Date/time routines

Functions for date and time handling.

## 38.6 FileName handling routines

Functions for file manipulation.

## 38.7 File input/output routines

Functions for reading/writing to file.

## 38.8 PChar related functions

Most PChar functions are the same as their counterparts in the STRINGS unit. The following functions are the same :

1. StrCat (1534) : Concatenates two PChar strings.
2. StrComp (1535) : Compares two PChar strings.
3. StrCopy (1535) : Copies a PChar string.
4. StrECopy (1536) : Copies a PChar string and returns a pointer to the terminating null byte.
5. StrEnd (1537) : Returns a pointer to the terminating null byte.

Table 38.3:

Name	Description
<code>DateTimeToFileDate</code> (1470)	Convert <code>DateTime</code> type to file date
<code>DateTimeToStr</code> (1471)	Construct string representation of <code>DateTime</code>
<code>DateTimeToString</code> (1471)	Construct string representation of <code>DateTime</code>
<code>DateTimeToSystemTime</code> (1472)	Convert <code>DateTime</code> to system time
<code>DateTimeToTimeStamp</code> (1473)	Convert <code>DateTime</code> to timestamp
<code>DateToStr</code> (1473)	Construct string representation of date
<code>Date</code> (1470)	Get current date
<code>DayOfWeek</code> (1474)	Get day of week
<code>DecodeDate</code> (1475)	Decode <code>DateTime</code> to year month and day
<code>DecodeTime</code> (1475)	Decode <code>DateTime</code> to hours, minutes and seconds
<code>EncodeDate</code> (1479)	Encode year, day and month to <code>DateTime</code>
<code>EncodeTime</code> (1480)	Encode hours, minutes and seconds to <code>DateTime</code>
<code>FormatDateTime</code> (1510)	Return string representation of <code>DateTime</code>
<code>IncMonth</code> (1520)	Add 1 to month
<code>IsLeapYear</code> (1522)	Determine if year is leap year
<code>MSecsToTimeStamp</code> (1526)	Convert nr of milliseconds to timestamp
<code>Now</code> (1527)	Get current date and time
<code>StrToDateTime</code> (1549)	Convert string to <code>DateTime</code>
<code>StrToDate</code> (1548)	Convert string to date
<code>StrToTime</code> (1554)	Convert string to time
<code>SystemTimeToDateTime</code> (1557)	Convert system time to datetime
<code>TimeStampToDateTime</code> (1559)	Convert time stamp to <code>DateTime</code>
<code>TimeStampToMSecs</code> (1559)	Convert Timestamp to number of millicseconds
<code>TimeToStr</code> (1560)	return string representation of Time
<code>Time</code> (1558)	Get current tyme

6. `StrIComp` (1538) : Case insensitive compare of 2 `PChar` strings.
7. `StrLCat` (1540) : Appends at most `L` characters from one `PChar` to another `PChar`.
8. `StrLComp` (1540) : Case sensitive compare of at most `L` characters of 2 `PChar` strings.
9. `StrLCopy` (1541) : Copies at most `L` characters from one `PChar` to another.
10. `StrLen` (1542) : Returns the length (exclusive terminating null byte) of a `PChar` string.
11. `StrLIComp` (1543) : Case insensitive compare of at most `L` characters of 2 `PChar` strings.
12. `StrLower` (1543) : Converts a `PChar` to all lowercase letters.
13. `StrMove` (1544) : Moves one `PChar` to another.
14. `StrNew` (1544) : Makes a copy of a `PChar` on the heap, and returns a pointer to this copy.
15. `StrPos` (1546) : Returns the position of one `PChar` string in another?
16. `StrRScan` (1546) : returns a pointer to the last occurrence of on `PChar` string in another one.
17. `StrScan` (1547) : returns a pointer to the first occurrence of on `PChar` string in another one.
18. `StrUpper` (1556) : Converts a `PChar` to all uppercase letters.

The subsequent functions are different from their counterparts in `STRINGS`, although the same examples can be used.

## 38.9 Date and time formatting characters

Various date and time formatting routines accept a format string, to format the date and or time. The following characters can be used to control the date and time formatting:

**c** shortdateformat + ' ' + longtimeformat

**d** day of month

**dd** day of month (leading zero)

**ddd** day of week (abbreviation)

**dddd** day of week (full)

**dddddd** shortdateformat

**ddddddd** longdateformat

**m** month

**mm** month (leading zero)

**mmm** month (abbreviation)

**mmmm** month (full)

**y** year (2 digits)

**yy** year (two digits)

**yyyy** year (with century)

**h** hour

**hh** hour (leading zero)

**n** minute

**nn** minute (leading zero)

**s** second

**ss** second (leading zero)

**t** shorttimeformat

**tt** longtimeformat

**am/pm** use 12 hour clock and display am and pm accordingly

**a/p** use 12 hour clock and display a and p accordingly

**/** insert date separator

**:** insert time separator

**"xx"** literal text

**'xx'** literal text

**z** milliseconds

## 38.10 Formatting strings

Functions for formatting strings.

## 38.11 String functions

Functions for handling strings.

## 38.12 Constants, types and variables

### 38.12.1 Constants

```
ConfigExtension : String = '.cfg'
```

`ConfigExtension` is the default extension used by the `GetAppConfigFile` (1513) call. It can be set to any valid extension for the current OS.

```
DateDelta = 693594
```

Days between 1/1/0001 and 12/31/1899

```
DriveDelim = DriveSeparator
```

`DriveDelim` refers to the system unit's `DriveSeparator` constant, it is for Delphi compatibility only.

```
EmptyStr : String = ''
```

Empty String Constant

```
EmptyWideStr : WideString = ''
```

Empty wide string.

```
faAnyFile = $00000003f
```

Use this attribute in the `FindFirst` (1496) call to find all matching files.

```
faArchive = $000000020
```

Attribute of a file, meaning the file has the archive bit set. Used in `TSearchRec` (1441) and `FindFirst` (1496)

```
faDirectory = $000000010
```

Attribute of a file, meaning the file is a directory. Used in `TSearchRec` (1441) and `FindFirst` (1496)

```
faHidden = $000000002
```



Attribute of a file, meaning the file is read-only. Used in TSearchRec (1441) and FindFirst (1496)

```
faReadOnly = $00000001
```

Attribute of a file, meaning the file is read-only. Used in TSearchRec (1441) and FindFirst (1496)

```
faSymLink = $00000040
```

faSymLink means the file (as returned e.g. by FindFirst (1496)/FindNext (1497)), is a symlink. It's ignored under Windows.

```
faSysFile = $00000004
```

Attribute of a file, meaning the file is a system file. Used in TSearchRec (1441) and FindFirst (1496)

```
faVolumeId = $00000008
```

Attribute of a file, meaning the file contains the volume ID. Used in TSearchRec (1441) and FindFirst (1496)

```
feInvalidHandle : THandle = THandle(-1)
```

feInvalidHandle is the return value of FileOpen (1492) in case of an error.

```
filerecnamelength = 255
```

filerecnamelength describes the length of the FileRec (1437) filename field.

```
fmOpenRead = $0000
```

fmOpenRead is used in the FileOpen (1492) call to open a file in read-only mode.

```
fmOpenReadWrite = $0002
```

fmOpenReadWrite is used in the FileOpen (1492) call to open a file in read-write mode.

```
fmOpenWrite = $0001
```

fmOpenWrite is used in the FileOpen (1492) call to open a file in write-only mode.

```
fmShareCompat = $0000
```

fmOpenShareCompat is used in the FileOpen (1492) call OR-ed together with one of fmOpenReadWrite (1431), fmOpenRead (1431) or fmOpenWrite (1431), to open a file in a sharing modus that is equivalent to sharing implemented in MS-DOS.

```
fmShareDenyNone = $0040
```

fmOpenShareExclusive is used in the FileOpen (1492) call OR-ed together with one of fmOpenReadWrite (1431), fmOpenRead (1431) or fmOpenWrite (1431), to open a file so other processes can read/write the file as well.

```
fmShareDenyRead = $0030
```

`fmOpenShareRead` is used in the `FileOpen` (1492) call OR-ed together with one of `fmOpenReadWrite` (1431), `fmOpenRead` (1431) or `fmOpenWrite` (1431), to open a file so other processes cannot read from it.

This constant only works on Windows, because other operating systems do not support this constants.

```
fmShareDenyWrite = $0020
```

`fmOpenShareWrite` is used in the `FileOpen` (1492) call OR-ed together with one of `fmOpenReadWrite` (1431), `fmOpenRead` (1431) or `fmOpenWrite` (1431), to open a file so other processes cannot write to it, they can only read.

```
fmShareExclusive = $0010
```

`fmOpenShareExclusive` is used in the `FileOpen` (1492) call OR-ed together with one of `fmOpenReadWrite` (1431), `fmOpenRead` (1431) or `fmOpenWrite` (1431), to open a file exclusively.

```
fsFromBeginning = 0
```

`fsFromBeginning` is used to indicate in the `FileSeek` (1494) call that a seek operation should be started at the start of the file.

```
fsFromCurrent = 1
```

`fsFromBeginning` is used to indicate in the `FileSeek` (1494) call that a seek operation should be started at the current position in the file.

```
fsFromEnd = 2
```

`fsFromBeginning` is used to indicate in the `FileSeek` (1494) call that a seek operation should be started at the last position in the file.

```
GUID_NULL : TGuid = '{00000000-0000-0000-0000-000000000000}'
```

**NULL GUID constant**

```
HexDisplayPrefix : String = '$'
```

`HexDisplayPrefix` is used by the formatting routines to indicate that the number which follows the prefix is in Hexadecimal notation.

```
HoursPerDay = 24
```

**Number of hours in a day.**

```
JulianEpoch = TDateTime(-2415018.5)
```

**Starting point of the Julian calendar**

```
LeadBytes : Set of Char = []
```

LeadBytes contains the set of bytes that serve as lead byte in a MBCS string.

MaxCurrency : Currency = 922337203685477.0000

Maximum currency value

MaxDateTime : TDateTime = 2958465.99999

Maximum TDateTime value.

MAX\_PATH = MaxPathLen

MAX\_PATH is the maximum number of characters that a filename (including path) can contain on the current operating system.

MinCurrency : Currency = -922337203685477.0000

Minimum Currency value

MinDateTime : TDateTime = -693593.0

Minimum TDateTime value.

MinsPerDay = HoursPerDay\*MinsPerHour

Number of minutes per day.

MinsPerHour = 60

Number of minutes per hour.

MonthDays : Array[Boolean] of TDayTable = ((31,28,31,30,31,30,31,31,30,31,30,31), (31

Array with number of days in the months for leap and non-leap years.

MSecsPerDay = SecsPerDay\*MSecsPerSec

Number of milliseconds per day

MSecsPerSec = 1000

Number of milliseconds per second

NullStr : PString = @EmptyStr

Pointer to an empty string

PathDelim = DirectorySeparator

PathDelim refers to the system unit's DirectorySeparator constant, it is for Delphi compatibility only.

`PathSep = PathSeparator`

`PathSep` refers to the system unit's `PathSeparator` constant, it is for Delphi compatibility only.

`pfBCB4Produced = $08000000`

Not used in Free Pascal.

`pfDelphi4Produced = $0C000000`

Not used in Free Pascal.

`pfDesignOnly = $00000002`

Package is a design-time only package

`pfExeModule = $00000000`

Package is an executable

`pfIgnoreDupUnits = $00000008`

Ignore duplicate units in package

`pfLibraryModule = $80000000`

Package is a library

`pfModuleTypeMask = $C0000000`

Mask for module type flags

`pfNeverBuild = $00000001`

Never-build flag was specified when compiling package

`pfPackageModule = $40000000`

Package is a real package (not exe)

`pfProducerMask = $0C000000`

Mask for producer flags

`pfProducerUndefined = $04000000`

Not used in Free Pascal.

`pfRunOnly = $00000004`

Package is a run-time only package

pfV3Produced = \$000000000

Not used in Free Pascal.

RTL\_SIGBUS = 4

Bus error signal number (Unix only)

RTL\_SIGDEFAULT = -1

Default signal handler (Unix only)

RTL\_SIGFPE = 1

Floating Point Error signal number (Unix only)

RTL\_SIGILL = 3

Illegal instruction signal number (Unix only)

RTL\_SIGINT = 0

INTERRUPT signal number (Unix only)

RTL\_SIGLAST = RTL\_SIGQUIT

Last signal number (Unix only)

RTL\_SIGQUIT = 5

QUIT signal number (Unix only)

RTL\_SIGSEGV = 2

Segmentation fault signal number (Unix only)

SecsPerDay = MinsPerDay\*SecsPerMin

Number of seconds per day

SecsPerMin = 60

Number of seconds per minute

SwitchChars = ['-']

The characters in this set will be used by the FindCmdLineSwitch ([1496](#)) function to determine whether a command-line argument is a switch (an option) or a value. If the first character of an argument is in SwitchChars, it will be considered an option or switch.

SysConfigDir : String = ''

`SysConfigDir` is the default system configuration directory. It is set at application startup by the `sysutils` initialization routines.

This directory may be returned by the `GetAppConfigDir` (1513) call on some systems.

`TextRecBufSize = 256`

Buffer size of text file record.

`TextRecNameLength = 256`

Length of text file record filename field

`ufImplicitUnit = $10`

Unit was implicitly imported into package (did not appear in package contains list)

`ufMainUnit = $01`

Unit is the main unit of the package

`ufOrgWeakUnit = $08`

Unit is the original weak packaged unit

`ufPackageUnit = $02`

Unit is a packaged unit (appeared in package contains list)

`ufWeakPackageUnit = ufPackageUnit or ufWeakUnit`

Weak (original or not) packaged unit

`ufWeakUnit = $04`

Unit is a weak packaged unit

`UnixDateDelta = Trunc(UnixEpoch)`

Number of days between 1.1.1900 and 1.1.1970

`UnixEpoch = JulianEpoch+TDateTime(2440587.5)`

Starting point of the unix calendar (1/1/1970)

### 38.12.2 Types

`EHeapException = EHeapMemoryError`

`EHeapMemoryError` is raised when an error occurs in the heap management routines.

```
ExceptClass = Class of Exception
```

ExceptClass is a [Exception \(1577\)](#) class reference.

```
FileRec = packed record
  Handle : THandle;
  Mode : LongInt;
  RecSize : SizeInt;
  _private : Array[1..3*SizeOf(SizeInt)+5*SizeOf(pointer)] of Byte;
  UserData : Array[1..32] of Byte;
  name : Array[0..filerecnamelength] of Char;
end
```

FileRec describes a untyped file. This record is made available so it can be used to implement drivers for other than the normal file system file records.

```
Int64Rec = packed record
end
```

Int64Rec can be used to extract the parts of a Int64: the high and low cardinal, or a zero-based array of 4 words, or a zero based array of 8 bytes. Note that the meaning of the High and Low parts are different on various CPUs.

```
LongRec = packed record
end
```

LongRec can be used to extract the parts of an long Integer: the high and low word, or the 4 separate bytes as a zero-based array of bytes. Note that the meaning of High and Low parts are different on various CPUs.

```
PByteArray = ^TByteArray
```

Generic pointer to TByteArray ([1438](#)). Use to access memory regions as a byte array.

```
PDayTable = ^TDayTable
```

Pointer to TDayTable type.

```
PString = ^String
```

Pointer to a ansistring

```
PSysCharSet = ^TSysCharSet
```

Pointer to TSysCharSet ([1441](#)) type.

```
PWordarray = ^TWordArray
```

Generic pointer to TWordArray ([1442](#)). Use to access memory regions as a word array.

```
TByteArray = Array[0..32767] of Byte
```

TByteArray is a generic array definition, mostly for use as a base type of the PByteArray (1437) type.

```
TCreateGUIDFunc = function(out GUID: TGUID) : Integer
```

TCreateGUIDFunc is the prototype for a GUID creation handler. On return, the GUID argument should contain a new (unique) GUID. The return value of the function should be zero for success, nonzero for failure.

```
TDayTable = Array[1..12] of Word
```

Array of day names.

```
TEventType = (etCustom, etInfo, etWarning, etError, etDebug)
```

TEventType is a type to be used by logging mechanisms (in particular, the TCustomApplication and TEventLog classes. It can be used to filter events, and write only certain types of event to the event log.

```
TExecuteFlags= Set of (ExecInheritsHandles)
```

TExecuteFlags is a set of flags to influence the behaviour of the ExecuteProcess (1482) call.

```
TextBuf = Array[0..TextRecBufSize-1] of Char
```

TextBuf is the type for the default buffer in TextRec (1438)

```
TextRec = packed record
  Handle : THandle;
  Mode : LongInt;
  bufsize : SizeInt;
  _private : SizeInt;
  bufpos : SizeInt;
  bufend : SizeInt;
  bufptr : ^TextBuf;
  openfunc : pointer;
  inoutfunc : pointer;
  flushfunc : pointer;
  closefunc : pointer;
  UserData : Array[1..32] of Byte;
  name : Array[0..textrecnamelength-1] of Char;
  LineEnd : TLineEndStr;
  buffer : TextBuf;
end
```

TextRec describes a text file. This record is made available so it can be used to implement drivers for other than the normal file system file records.

To implement a driver, an Assign procedure must be implemented, which fills in the various fields of the record. Most notably, the callback functions must be filled in appropriately. After this, the normal file operations will handle all necessary calls to the various callbacks.



```
TFilename = String
```

TFileName is used in the TSearchRec (1441) definition.

```
TFileRec = FileRec
```

Alias for FileRec (1437) for Delphi compatibility.

```
TFloatFormat = (ffGeneral, ffExponent, ffFixed, ffNumber, ffCurrency)
```

TFloatFormat is used to determine how a float value should be formatted in the FloatToText (1502) function.

```
TFloatRec = record
  Exponent : Integer;
  Negative : Boolean;
  Digits : Array[0..18] of Char;
end
```

TFloatRec is used to describe a floating point value by the FloatToDecimal (1498) function.

```
TFloatValue = (fvExtended, fvCurrency, fvSingle, fvReal, fvDouble, fvComp)
```

TFloatValue determines which kind of value should be returned in the (untyped) buffer used by the TextToFloat (1557) function.

```
TFormatSettings = record
  CurrencyFormat : Byte;
  NegCurrFormat : Byte;
  ThousandSeparator : Char;
  DecimalSeparator : Char;
  CurrencyDecimals : Byte;
  DateSeparator : Char;
  TimeSeparator : Char;
  ListSeparator : Char;
  CurrencyString : String;
  ShortDateFormat : String;
  LongDateFormat : String;
  TimeAMString : String;
  TimePMString : String;
  ShortTimeFormat : String;
  LongTimeFormat : String;
  ShortMonthNames : TMonthNameArray;
  LongMonthNames : TMonthNameArray;
  ShortDayNames : TWeekNameArray;
  LongDayNames : TWeekNameArray;
  TwoDigitYearCenturyWindow : Word;
end
```

TFormatSettings is a record that contains a copy of all variables which determine formatting in the various string formatting routines. It is used to pass local copies of these values to the various formatting routines in a thread-safe way.

TGetAppNameEvent = function : String

This callback type is used by the OnGetApplicationName (1444) to return an alternative application name.

TGetTempDirEvent = function(Global: Boolean) : String

Function prototype for OnGetTempDir (1444) handler.

TGetTempFileEvent = function(const Dir: String;const Prefix: String)  
: String

Function prototype for OnGetTempFile (1444) handler.

TGetVendorNameEvent = function : String

TGetVendorNameEvent is the function prototype for the OnGetVendorName (1445) callback, used by the VendorName (1568) function.

THandle = System.THandle

THandle refers to the definition of THandle in the system unit, and is provided for backward compatibility only.

TIntegerSet = Set of

TIntegerSet is a generic integer subrange set definition whose size fits in a single integer.

TLineEndStr =

TLineEndStr is used in the TextRec (1438) record to indicate the end-of-line sequence for a text file.

TMbcsByteType = (mbSingleByte,mbLeadByte,mbTrailByte)

Type of multi-byte character set.

TMonthNameArray = Array[1..12] of String

TMonthNameArray is used in the month long and short name arrays.

TProcedure = procedure

TProcedure is a general definition of a procedural callback.

TReplaceFlags= Set of (rfReplaceAll,rfIgnoreCase)

TReplaceFlags determines the behaviour of the StringReplace (1539) function.

```

TSearchRec = record
  Time : LongInt;
  Size : Int64;
  Attr : LongInt;
  Name : TFilename;
  ExcludeAttr : LongInt;
  FindHandle : Pointer;
  Mode : TMode;
  PathOnly : AnsiString;
end

```

TSearchRec is a search handle description record. It is initialized by a call to FindFirst (1496) and can be used to do subsequent calls to FindNext (1497). It contains the result of these function calls. It must be used to close the search sequence with a call to FindClose (1496).

**Remark:** Not all fields of this record should be used. Some of the fields are for internal use only. (PathOnly for example, is only provided for Kylix compatibility)

```
TSignalState = (ssNotHooked, ssHooked, ssOverridden)
```

TSignalState indicates the state of a signal handler in a unix system for a particular signal.

```
TSysCharSet = Set of Char
```

Generic set of characters type.

```

TSysLocale = record
  DefaultLCID : Integer;
  PriLangID : Integer;
  SubLangID : Integer;
end

```

TSysLocale describes the current locale. If Fareast or MBCS is True, then the current locale uses a Multi-Byte Character Set. If MiddleEast or RightToLeft is True then words and sentences are read from right to left.

```
TTerminateProc = function : Boolean
```

TTerminateProc is the procedural type which should be used when adding exit procedures.

```
TTextRec = TextRec
```

Alias for TextRec (1438) for Delphi compatibility.

```

TTimeStamp = record
  Time : Integer;
  Date : Integer;
end

```

TTimeStamp contains a timestamp, with the date and time parts specified as separate TDateTime values.

```
TWeekNameArray = Array[1..7] of String
```

TWeekNameArray is used in the day long and short name arrays.

```
TWordArray = Array[0..16383] of Word
```

TWordArray is a generic array definition, mostly for use as a base type of the PWordArray (1437) type.

```
WordRec = packed record
  Lo : Byte;
  Hi : Byte;
end
```

LongRec can be used to extract the parts of a word: the high and low byte. Note that the meaning of the High and Low parts are different on various CPUs.

### 38.12.3 Variables

```
CurrencyDecimals : Byte
```

CurrencyDecimals is the number of decimals to be used when formatting a currency. It is used by the float formatting routines. The initialization routines of the SysUtils unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

```
CurrencyFormat : Byte
```

CurrencyFormat is the default format string for positive currencies. It is used by the float formatting routines. The initialization routines of the SysUtils unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

```
CurrencyString : String
```

CurrencyString is the currency symbol for the current locale. It is used by the float formatting routines. The initialization routines of the SysUtils unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

```
DateSeparator : Char
```

DateSeparator is the character used by various date/time conversion routines as the character that separates the day from the month and the month from the year in a date notation. It is used by the date formatting routines. The initialization routines of the SysUtils unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

```
DecimalSeparator : Char
```

DecimalSeparator is used to display the decimal symbol in floating point numbers or currencies. It is used by the float formatting routines. The initialization routines of the SysUtils unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

`DefaultFormatSettings : TFormatSettings = (CurrencyFormat:1;NegCurrFormat:5;Thousand`

`DefaultFormatSettings` contains the default settings for all type of formatting constants. If no thread-specific values are specified when a formatting function is called, this record is used as a default.

All other formatting constants refer to the fields of this variable using absolute addressing.

`FalseBoolStrs : Array of String`

`FalseBoolStrs` contains the strings that will result in a `False` return value by `StrToBool` (1547).

`ListSeparator : Char`

`ListSeparator` is the character used in lists of values. It is locale dependent.

`LongDateFormat : String`

`LongDateFormat` contains a template to format a date in a long format. It is used by the date formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

`LongDayNames : TWeekNameArray`

`LongDayNames` is an array with the full names of days. It is used by the date formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

`LongMonthNames : TMonthNameArray`

`LongMonthNames` is an array with the full names of months. It is used by the date formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

`LongTimeFormat : String`

`LongTimeFormat` contains a template to format a time in full notation. It is used by the time formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

`NegCurrFormat : Byte`

`CurrencyFormat` is the default format string for negative currencies. It is used by the float formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default:

- 0** Left parenthesis, currency symbol, amount, right parenthesis. Ex: (\$1.2)
- 1** Negative sign, currency symbol, amount. Ex: -\$1.2
- 2** Monetary symbol, negative sign, amount. Ex: \$-1.2
- 3** Monetary symbol, amount, negative sign. Ex: \$1.2-

- 4 Left parenthesis, amount, currency symbol, right parenthesis. Ex: (1.2\$)
- 5 Negative sign, amount, currency symbol. Ex: -1.2\$
- 5 6Amount, negative sign, currency symbol. Ex: 1.2-\$
- 5 7Amount, currency symbol, negative sign. Ex: 1.2\$-
- 5 8Negative sign, amount, space, currency symbol (as #5, adding a space before the currency symbol). Ex: -1.2 \$
- 9 Negative sign, currency symbol, space, amount (as #1, adding a space after the currency symbol). Ex: -\$ 1.2
- 10 Amount, space, currency symbol, negative sign (as #7, adding a space before the currency symbol). Ex: 1.2 \$-
- 11 Monetary symbol, space, amount, negative sign (as #3, adding a space after the currency symbol). Ex: \$ 1.2-
- 12 Monetary symbol, space, negative sign, amount (as #2, adding a space after the currency symbol). Ex: \$ -1.2
- 13 Amount, negative sign, space, currency symbol (as #6, adding a space before the currency symbol). Ex: 1.2- \$
- 14 Left parenthesis, currency symbol, space, amount, right parenthesis (as #0, adding a space after the currency symbol). Ex: (\$ 1.2)
- 15 Left parenthesis, amount, space, currency symbol, right parenthesis (as ##4, adding a space before the currency symbol). Ex: (1.2 \$)

`OnCreateGUID : TCreateGUIDFunc = nil`

`OnCreateGUID` can be set to point to a custom routine that creates GUID values. If set, the `CreateGUID` (1468) function will use it to obtain a GUID value. If it is not set, a default implementation using random values will be used to create the unique value. The function should return a valid GUID in the `GUID` parameter, and should return zero in case of success.

`OnGetApplicationName : TGetAppNameEvent`

By default, the configuration file routines `GetAppConfigDir` (1513) and `GetAppConfigFile` (1513) use a default application name to construct a directory or filename. This callback can be used to provide an alternative application name.

Since the result of this callback will be used to construct a filename, care should be taken that the returned name does not contain directory separator characters or characters that cannot appear in a filename.

`OnGetTempDir : TGetTempDirEvent`

`OnGetTempDir` can be used to provide custom behaviour for the `GetTempDir` (1517) function. Note that the returned name should have a trailing directory delimiter character.

`OnGetTempFile : TGetTempFileEvent`

`OnGetTempDir` can be used to provide custom behaviour for the `GetTempFileName` (1517) function. Note that the values for `Prefix` and `Dir` should be observed.

`OnGetVendorName : TGetVendorNameEvent`

`OnGetVendorName` is the callback used by the `VendorName` (1568) function. It should be set to a handler that returns the vendor of the application.

`OnShowException : procedure(Msg: ShortString)`

`OnShowException` is the callback that `ShowException` (1532) uses to display a message in a GUI application. For GUI applications, this variable should always be set. Note that no memory may be available when this callback is called, so the callback should already have all resources it needs, when the callback is set.

`ShortDateFormat : String`

`ShortDateFormat` contains a template to format a date in a short format. It is used by the date formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

`ShortDayNames : TWeekNameArray`

`ShortDayNames` is an array with the abbreviated names of days. It is used by the date formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

`ShortMonthNames : TMonthNameArray`

`ShortMonthNames` is an array with the abbreviated names of months. It is used by the date formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

`ShortTimeFormat : String`

`ShortTimeFormat` contains a template to format a time in a short notation. It is used by the time formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

`SysLocale : TSysLocale`

`SysLocale` is initialized by the initialization code of the `SysUtils` unit. For an explanation of the fields, see `TSysLocale` (1441)

`ThousandSeparator : Char`

`ThousandSeparator` is used to separate groups of thousands in floating point numbers or currencies. It is used by the float formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

`TimeAMString : String`

`TimeAMString` is used to display the AM symbol in the time formatting routines. It is used by the time formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

`TimePMString` : `String`

`TimePMString` is used to display the PM symbol in the time formatting routines. It is used by the time formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

`TimeSeparator` : `Char`

`TimeSeparator` is used by the time formatting routines to separate the hours from the minutes and the minutes from the seconds. It is used by the time formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

`TrueBoolStrs` : `Array of String`

`TrueBoolStrs` contains the strings that will result in a `True` return value by `StrToBool` ([1547](#)).

`TwoDigitYearCenturyWindow` : `Word`

Window to determine what century 2 digit years are in.

## 38.13 Procedures and functions

### 38.13.1 AbandonSignalHandler

Synopsis: Abandon the signal handler

Declaration: `procedure AbandonSignalHandler(RtlSigNum: Integer)`

Visibility: `default`

Description: `AbandonSignalHandler` tells the system routines that they should not re-install the signal handler for signal `RtlSigNum` under any circumstances. Normally, signal handlers are re-set when they are called. If `AbandonSignalHandler` has been called for a signal that is handled by the system code, the signal will not be re-set again.

### 38.13.2 Abort

Synopsis: Abort program execution.

Declaration: `procedure Abort`

Visibility: `default`

Description: `Abort` raises an `EAbort` ([1571](#)) exception.

See also: `Abort` ([1446](#))



### 38.13.3 AddDisk

Synopsis: Add a disk to the list of known disks (Unix only)

Declaration: `function AddDisk(const path: String) : Byte`

Visibility: default

Description: On Unix-like platforms both the `DiskFree` (1477) and `DiskSize` (1478) functions need a file on the specified drive, since is required for the `statfs` system call.

These filenames are set in `drivestr[0..26]`, and the first 4 have been preset to :

**Disk 0** ' . ' default drive - hence current directory is used.

**Disk 1** ' /fd0/ . ' floppy drive 1.

**Disk 2** ' /fd1/ . ' floppy drive 2.

**Disk 3** ' / ' C: equivalent of DOS is the root partition.

Drives 4..26 can be set by your own applications with the `AddDisk` call.

The `AddDisk` call adds `Path` to the names of drive files, and returns the number of the disk that corresponds to this drive. If you add more than 21 drives, the count is wrapped to 4.

Errors: None.

See also: `DiskFree` (1477), `DiskSize` (1478)

### 38.13.4 AddTerminateProc

Synopsis: Add a procedure to the exit chain.

Declaration: `procedure AddTerminateProc(TermProc: TTerminateProc)`

Visibility: default

Description: `AddTerminateProc` adds `TermProc` to the list of exit procedures. When the program exits, the list of exit procedures is run over, and all procedures are called one by one, in the reverse order that they were added to the exit chain.

Errors: If no memory is available on the heap, an exception may be raised.

See also: `TTerminateProc` (1441), `CallTerminateProcs` (1464)

### 38.13.5 AdjustLineBreaks

Synopsis: Convert possible line-endings to the currently valid line ending.

Declaration: `function AdjustLineBreaks(const S: String) : String`  
`function AdjustLineBreaks(const S: String; Style: TTextLineBreakStyle)`  
`: String`

Visibility: default

Description: `AdjustLineBreaks` will change all occurrences of `#13` and `#10` characters with the correct line-ending characters for the current platform. This is `#13#10` on Windows and Dos. On Unix-like platforms, this is `#10` and for Mac OS X it is `#13`.

Errors: None.

See also: [AnsiCompareStr \(1448\)](#), [AnsiCompareText \(1449\)](#)

**Listing:** ./sysutex/ex48.pp

---

**Program** Example48;

*{ This program demonstrates the AdjustLineBreaks function }*

**Uses** sysutils;

**Const**

S = 'This is a string '#13'with embedded'#10'linefeed and'+  
#13'CR characters';

**Begin**

WriteLn ( AdjustLineBreaks(S));

**End.**

---

### 38.13.6 AnsiCompareFileName

Synopsis: Compare 2 filenames.

**Declaration:** function AnsiCompareFileName(const S1: String;const S2: String)  
: SizeInt

Visibility: default

**Description:** AnsiCompareFileName compares 2 filenames S1 and S2, and returns

< 0 if S1 < S2.

= 0 if S1 = S2.

> 0 if S1 > S2.

The function actually checks FileNameCaseSensitive and returns the result of AnsiCompareStr (1448) or AnsiCompareText (1449) depending on whether FileNameCaseSensitive is True or False

Errors: None.

See also: [AnsiCompareStr \(1448\)](#), [AnsiCompareText \(1449\)](#), [AnsiLowerCaseFileName \(1452\)](#)

### 38.13.7 AnsiCompareStr

Synopsis: Compare 2 ansistrings, case sensitive, ignoring accents characters.

**Declaration:** function AnsiCompareStr(const S1: String;const S2: String) : Integer

Visibility: default

**Description:** AnsiCompareStr compares two strings and returns the following result:

< 0 if S1 < S2.

0 if S1 = S2.

> 0 if S1 > S2.

The comparison takes into account Ansi characters, i.e. it takes care of strange accented characters. Contrary to `AnsiCompareText` (1449), the comparison is case sensitive.

**Remark:** A widestring manager must be installed in order for this function to work correctly with various character sets.

Errors: None.

See also: `AdjustLineBreaks` (1447), `AnsiCompareText` (1449)

**Listing:** ./sysutex/ex49.pp

**Program** Example49;

```
{ This program demonstrates the AnsiCompareStr function }
{$H+}
```

**Uses** sysutils;

**Procedure** TestIt (S1,S2 : **String**);

**Var** R : Longint;

**begin**

  R:=**AnsiCompareStr**(S1,S2);

**Write** ( '',S1,' " is ' );

**If** R<0 **then**

**write** ( 'less than ' )

**else If** R=0 **then**

**Write** ( 'equal to ' )

**else**

**Write** ( 'larger than ' );

**WriteLn** ( '',S2,' ' );

**end**;

**Begin**

  Testit('One string','One smaller string');

  Testit('One string','one string');

  Testit('One string','One string');

  Testit('One string','One tall string');

**End.**

### 38.13.8 AnsiCompareText

Synopsis: Compare 2 ansistrings, case insensitive, ignoring accents characters.

Declaration: `function AnsiCompareText(const S1: String;const S2: String) : Integer`

Visibility: default

Description: `AnsiCompareText` compares two strings and returns the following result:

<0if S1<S2.

0if S1=S2.

>0if S1>S2.

the comparison takes into account Ansi characters, i.e. it takes care of strange accented characters. Contrary to `AnsiCompareStr` (1448), the comparison is case insensitive.

**Remark:** A widestring manager must be installed in order for this function to work correctly with various character sets.

Errors: None.

See also: `AdjustLineBreaks` (1447), `AnsiCompareText` (1449)

**Listing:** ./sysutex/ex50.pp

---

**Program** Example49;

```
{ This program demonstrates the AnsiCompareText function }
{$H+}
```

**Uses** sysutils;

**Procedure** TestIt (S1,S2 : **String**);

**Var** R : Longint;

**begin**

  R:=**AnsiCompareText**(S1,S2);

**Write** ( '',S1,' " is ' );

**If** R<0 **then**

**write** ( 'less than ' )

**else If** R=0 **then**

**Write** ( 'equal to ' )

**else**

**Write** ( 'larger than ' );

**Writeln** ( '',S2,' ' );

**end**;

**Begin**

  Testit('One string','One smaller string');

  Testit('One string','one string');

  Testit('One string','One string');

  Testit('One string','One tall string');

**End.**

---

### 38.13.9 AnsiDequotedStr

Synopsis:

**Declaration:** `function AnsiDequotedStr(const S: String;AQuote: Char) : String`

  Visibility: default

**Description:**

  Errors:

### 38.13.10 AnsiExtractQuotedStr

Synopsis: Removes the first quoted string from a string.

**Declaration:** `function AnsiExtractQuotedStr(var Src: PChar; Quote: Char) : String`

**Visibility:** default

**Description:** `AnsiExtractQuotedStr` returns the first quoted string in `Src`, and deletes the result from `Src`. The resulting string has with `Quote` characters removed from the beginning and end of the string (if they are present), and double `Quote` characters replaced by a single `Quote` characters. As such, it reverses the action of `AnsiQuotedStr` (1453).

**Errors:** None.

**See also:** `AnsiQuotedStr` (1453)

**Listing:** `./sysutex/ex51.pp`

---

**Program** Example51;

*{ This program demonstrates the AnsiQuotedStr function }*

**Uses** sysutils;

**Var** S : AnsiString;

**Begin**

S := 'He said "Hello" and walked on';

S := AnsiQuotedStr(Pchar(S), '"');

**WriteLn** (S);

**WriteLn** (AnsiExtractQuotedStr(Pchar(S), '"'));

**End.**

---

### 38.13.11 AnsiLastChar

**Synopsis:** Return a pointer to the last character of a string.

**Declaration:** `function AnsiLastChar(const S: String) : PChar`

**Visibility:** default

**Description:** This function returns a pointer to the last character of S.

**Remark:** A widestring manager must be installed in order for this function to work correctly with various character sets. If none is installed, this function is the same as `@S[Length[S]]`.

**Errors:** None.

**See also:** `AnsiStrLastChar` (1455)

**Listing:** `./sysutex/ex52.pp`

---

**Program** Example52;

*{ This program demonstrates the AnsiLastChar function }*

**Uses** sysutils;

**Var** S : AnsiString;

L : Longint;

**Begin**

---

```

S:= 'This is an ansistring.';
Writeln ( 'Last character of S is : ',AnsiLastChar(S));
L:= Longint( AnsiLastChar(S)) - Longint(@S[1])+1;
Writeln ( 'Length of S is : ',L);
End.

```

---

### 38.13.12 AnsiLowerCase

Synopsis: Return a lowercase version of a string.

Declaration: `function AnsiLowerCase(const s: String) : String`

Visibility: default

Description: `AnsiLowerCase` converts the string `S` to lowercase characters and returns the resulting string. It takes into account the operating system language settings when doing this, so special characters are converted correctly as well.

**Remark:** A widestring manager must be installed in order for this function to work correctly with various character sets.

Errors: None.

See also: `AnsiUpperCase` ([1460](#)), `AnsiStrLower` ([1458](#)), `AnsiStrUpper` ([1459](#))

**Listing:** `./sysutex/ex53.pp`

---

**Program** Example53;

*{ This program demonstrates the AnsiLowerCase function }*

**Uses** sysutils;

**Procedure** Testit (S : **String**);

**begin**

**Writeln** (S, ' -> ',AnsiLowerCase(S))

**end**;

**Begin**

Testit( 'AN UPPERCASE STRING');

Testit( 'Some mixed STring');

Testit( 'a lowercase string');

**End.**

---

### 38.13.13 AnsiLowerCaseFileName

Synopsis: Convert filename to lowercase.

Declaration: `function AnsiLowerCaseFileName(const s: String) : String`

Visibility: default

Description: `AnsiLowerCaseFileName` simply returns the result of

`AnsiLowerCase(S);`

See also: `AnsiLowerCase` ([1452](#)), `AnsiCompareFileName` ([1448](#)), `AnsiUpperCaseFileName` ([1460](#))

**38.13.14 AnsiPos**

Synopsis: Return Position of one anstring in another.

Declaration: `function AnsiPos(const substr: String;const s: String) : SizeInt`

Visibility: default

Description: `AnsiPos` does the same as the standard `Pos` function.

See also: `AnsiStrPos` ([1458](#)), `AnsiStrScan` ([1459](#)), `AnsiStrRScan` ([1459](#))

**38.13.15 AnsiQuotedStr**

Synopsis: Return a quoted version of a string.

Declaration: `function AnsiQuotedStr(const S: String;Quote: Char) : String`

Visibility: default

Description: `AnsiQuotedString` quotes the string `S` and returns the result. This means that it puts the `Quote` character at both the beginning and end of the string and replaces any occurrence of `Quote` in `S` with 2 `Quote` characters. The action of `AnsiQuotedString` can be reversed by `AnsiExtractQuotedStr` ([1450](#)).

For an example, see `AnsiExtractQuotedStr` ([1450](#))

Errors: None.

See also: `AnsiExtractQuotedStr` ([1450](#))

**38.13.16 AnsiSameStr**

Synopsis: Checks whether 2 strings are the same (case sensitive)

Declaration: `function AnsiSameStr(const s1: String;const s2: String) : Boolean`

Visibility: default

Description: `SameText` calls `AnsiCompareStr` ([1448](#)) with `S1` and `S2` as parameters and returns `True` if the result of that call is zero, or `False` otherwise.

**Remark:** A widestring manager must be installed in order for this function to work correctly with various character sets.

Errors: None.

See also: `AnsiCompareStr` ([1448](#)), `SameText` ([1531](#)), `AnsiSameText` ([1453](#))

**38.13.17 AnsiSameText**

Synopsis: Checks whether 2 strings are the same (case insensitive)

Declaration: `function AnsiSameText(const s1: String;const s2: String) : Boolean`

Visibility: default

Description: `SameText` calls `AnsiCompareText` ([1449](#)) with `S1` and `S2` as parameters and returns `True` if the result of that call is zero, or `False` otherwise.

Errors:

See also: `AnsiCompareText` ([1449](#)), `SameText` ([1531](#)), `AnsiSameStr` ([1453](#))

**38.13.18 AnsiStrComp**

Synopsis: Compare two null-terminated strings. Case sensitive.

Declaration: `function AnsiStrComp(S1: PChar; S2: PChar) : Integer`

Visibility: default

Description: `AnsiStrComp` compares 2 `PChar` strings, and returns the following result:

```
<0if S1<S2.
0if S1=S2.
>0if S1>S2.
```

The comparison of the two strings is case-sensitive.

**Remark:** A widestring manager must be installed in order for this function to work correctly with various character sets.

Errors: None.

See also: `AnsiCompareText` ([1449](#)), `AnsiCompareStr` ([1448](#))

**Listing:** `./sysutex/ex54.pp`

---

**Program** Example54;

*{ This program demonstrates the AnsiStrComp function }*

**Uses** sysutils;

**Procedure** TestIt (S1,S2 : Pchar);

**Var** R : Longint;

**begin**

  R:=AnsiStrComp(S1,S2);

**Write** ( ' ', S1, ' is ' );

**If** R<0 **then**

**write** ( 'less than ' )

**else If** R=0 **then**

**Write** ( 'equal to ' )

**else**

**Write** ( 'larger than ' );

**Writeln** ( ' ', S2, ' ' );

**end**;

**Begin**

  Testit( 'One string ', 'One smaller string ' );

  Testit( 'One string ', 'one string ' );

  Testit( 'One string ', 'One string ' );

  Testit( 'One string ', 'One tall string ' );

**End.**

---

**38.13.19 AnsiStrlComp**

Synopsis: Compare two null-terminated strings. Case insensitive.



**Declaration:** `function AnsiStrIComp(S1: PChar;S2: PChar) : Integer`

**Visibility:** default

**Description:** `AnsiStrIComp` compares 2 `PChar` strings, and returns the following result:

```
<0if S1<S2.
0if S1=S2.
>0if S1>S2.
```

The comparison of the two strings is case-insensitive.

**Remark:** A widestring manager must be installed in order for this function to work correctly with various character sets.

**Errors:** None.

See also: `AnsiCompareText` ([1449](#)), `AnsiCompareStr` ([1448](#))

**Listing:** `./sysutex/ex55.pp`

---

**Program** Example55;

*{ This program demonstrates the AnsiStrIComp function }*

**Uses** sysutils;

**Procedure** TestIt (S1,S2 : Pchar);

**Var** R : Longint;

**begin**

  R:=AnsiStrIComp(S1,S2);

**Write** ( ' ',S1,' is ' );

**If** R<0 **then**

**write** ( 'less than ' )

**else If** R=0 **then**

**Write** ( 'equal to ' )

**else**

**Write** ( 'larger than ' );

**WriteLn** ( ' ',S2,' ' );

**end**;

**Begin**

  Testit( 'One string ', 'One smaller string ' );

  Testit( 'One string ', 'one string ' );

  Testit( 'One string ', 'One string ' );

  Testit( 'One string ', 'One tall string ' );

**End.**

---

### 38.13.20 AnsiStrLastChar

**Synopsis:** Return a pointer to the last character of a string.

**Declaration:** `function AnsiStrLastChar(Str: PChar) : PChar`

**Visibility:** default

Description: Return a pointer to the last character of the null-terminated string.

**Remark:** A widestring manager must be installed in order for this function to work correctly with various character sets. If none is installed, this function is the same as `@S[Length[S]]`.

Errors: None.

See also: `AnsiCompareText` (1449), `AnsiCompareStr` (1448)

**Listing:** `./sysutex/ex56.pp`

---

**Program** `Example56`;

*{ This program demonstrates the AnsiStrLComp function }*

**Uses** `sysutils`;

**Procedure** `TestIt` (`S1,S2 : Pchar`; `L : longint`);

**Var** `R : Longint`;

**begin**

`R:=AnsiStrLComp(S1,S2,L);`

`Write ('First ',L,' characters of "',S1,'" are ');`

`If R<0 then`

`write ('less than ')`

`else If R=0 then`

`Write ('equal to ')`

`else`

`Write ('larger than ');`

`WriteLn ('those of "',S2,'"');`

`end;`

**Begin**

`Testit('One string','One smaller string',255);`

`Testit('One string','One String',4);`

`Testit('One string','1 string',0);`

`Testit('One string','One string.',9);`

**End.**

---

### 38.13.21 AnsiStrLComp

Synopsis: Compare a limited number of characters of 2 strings

Declaration: `function AnsiStrLComp(S1: PChar;S2: PChar;MaxLen: cardinal) : Integer`

Visibility: default

Description: `AnsiStrLComp` functions the same as `AnsiStrComp` (1454), but compares at most `MaxLen` characters. If the first `MaxLen` characters in both strings are the same, then zero is returned.

Note that this function processes embedded null characters, treating them as a normal character.

Errors: None.

See also: `AnsiStrComp` (1454), `AnsiStrIComp` (1454), `AnsiStrLComp` (1457)

**38.13.22 AnsiStrLIComp**

**Synopsis:** Compares a given number of characters of a string, case insensitive.

**Declaration:** `function AnsiStrLIComp(S1: PChar;S2: PChar;MaxLen: cardinal) : Integer`

**Visibility:** default

**Description:** `AnsiStrLIComp` compares the first `Maxlen` characters of 2 `PChar` strings, `S1` and `S2`, and returns the following result:

`<0` if `S1<S2`.

`0` if `S1=S2`.

`>0` if `S1>S2`.

The comparison of the two strings is case-insensitive.

**Remark:** A widestring manager must be installed in order for this function to work correctly with various character sets.

**Errors:** None.

See also: `AnsiCompareText` ([1449](#)), `AnsiCompareStr` ([1448](#))

**Listing:** `./sysutex/ex57.pp`

---

**Program** `Example57`;

*{ This program demonstrates the AnsiStrLIComp function }*

**Uses** `sysutils`;

**Procedure** `TestIt (S1,S2 : Pchar; L : longint);`

**Var** `R : Longint;`

**begin**

`R:=AnsiStrLIComp(S1,S2,L);`

`Write ('First ',L,' characters of "',S1,'" are ');`

`If R<0 then`

`write ('less than ')`

`else If R=0 then`

`Write ('equal to ')`

`else`

`Write ('larger than ');`

`WriteLn ('those of "',S2,'"');`

`end;`

**Begin**

`Testit('One string','One smaller string',255);`

`Testit('ONE STRING','one String',4);`

`Testit('One string','1 STRING',0);`

`Testit('One STRING','one string.',9);`

**End.**

---

**38.13.23 AnsiStrLower**

**Synopsis:** Convert a null-terminated string to all-lowercase characters.

**Declaration:** `function AnsiStrLower(Str: PChar) : PChar`

**Visibility:** default

**Description:** `AnsiStrLower` converts the `PChar` `Str` to lowercase characters and returns the resulting `pchar`.

Note that `Str` itself is modified, not a copy, as in the case of `AnsiLowerCase` (1452). It takes into account the operating system language settings when doing this, so special characters are converted correctly as well.

**Remark:** A widestring manager must be installed in order for this function to work correctly with various character sets.

**Errors:** None.

See also: `AnsiStrUpper` (1459), `AnsiLowerCase` (1452)

**Listing:** `./sysutex/ex59.pp`

---

**Program** Example59;

*{ This program demonstrates the AnsiStrLower function }*

**Uses** sysutils;

**Procedure** Testit (S : Pchar);

**begin**

**WriteLn** (S, ' -> ', AnsiStrLower(S))

**end**;

**Begin**

    Testit('AN UPPERCASE STRING');

    Testit('Some mixed STring');

    Testit('a lowercase string');

**End.**

---

**38.13.24 AnsiStrPos**

**Synopsis:** Return position of one null-terminated substring in another

**Declaration:** `function AnsiStrPos(str: PChar; substr: PChar) : PChar`

**Visibility:** default

**Description:** `AnsiStrPos` returns a pointer to the first occurrence of `SubStr` in `Str`. If `SubStr` does not occur in `Str` then `Nil` is returned.

**Errors:** An access violation may occur if either `Str` or `SubStr` point to invalid memory.

See also: `AnsiPos` (1453), `AnsiStrScan` (1459), `AnsiStrRScan` (1459)

### 38.13.25 AnsiStrRScan

Synopsis: Find last occurrence of a character in a null-terminated string.

Declaration: `function AnsiStrRScan(Str: PChar;Chr: Char) : PChar`

Visibility: default

Description: `AnsiStrPos` returns a pointer to the *last* occurrence of the character `Chr` in `Str`. If `Chr` does not occur in `Str` then `Nil` is returned.

Errors: An access violation may occur if `Str` points to invalid memory.

See also: `AnsiPos` ([1453](#)), `AnsiStrScan` ([1459](#)), `AnsiStrPos` ([1458](#))

### 38.13.26 AnsiStrScan

Synopsis: Find first occurrence of a character in a null-terminated string.

Declaration: `function AnsiStrScan(Str: PChar;Chr: Char) : PChar`

Visibility: default

Description: `AnsiStrPos` returns a pointer to the *first* occurrence of the character `Chr` in `Str`. If `Chr` does not occur in `Str` then `Nil` is returned.

Errors: An access violation may occur if `Str` points to invalid memory.

See also: `AnsiPos` ([1453](#)), `AnsiStrScan` ([1459](#)), `AnsiStrPos` ([1458](#))

### 38.13.27 AnsiStrUpper

Synopsis: Convert a null-terminated string to all-uppercase characters.

Declaration: `function AnsiStrUpper(Str: PChar) : PChar`

Visibility: default

Description: `AnsiStrUpper` converts the `PCharStr` to uppercase characters and returns the resulting string. Note that `Str` itself is modified, not a copy, as in the case of `AnsiUpperCase` ([1460](#)). It takes into account the operating system language settings when doing this, so special characters are converted correctly as well.

**Remark:** A widestring manager must be installed in order for this function to work correctly with various character sets.

Errors: None.

See also: `AnsiUpperCase` ([1460](#)), `AnsiStrLower` ([1458](#)), `AnsiLowerCase` ([1452](#))

**Listing:** `./sysutex/ex60.pp`

---

**Program** `Example60;`

`{ This program demonstrates the AnsiStrUpper function }`

**Uses** `sysutils;`

**Procedure** `Testit (S : Pchar);`

```

begin
  WriteLn (S, ' -> ', AnsiStrUpper(S))
end;

                                Begin
  Testit('AN UPPERCASE STRING');
  Testit('Some mixed STring');
  Testit('a lowercase string');
End.

```

---

### 38.13.28 AnsiUpperCase

Synopsis: Return an uppercase version of a string, taking into account special characters.

Declaration: `function AnsiUpperCase(const s: String) : String`

Visibility: default

Description: `AnsiUpperCase` converts the string `S` to uppercase characters and returns the resulting string. It takes into account the operating system language settings when doing this, so special characters are converted correctly as well.

**Remark:** A widestring manager must be installed in order for this function to work correctly with various character sets.

Errors: None.

See also: `AnsiStrUpper` ([1459](#)), `AnsiStrLower` ([1458](#)), `AnsiLowerCase` ([1452](#))

**Listing:** `./sysutex/ex61.pp`

**Program** `Example60`;

*{ This program demonstrates the AnsiUpperCase function }*

**Uses** `sysutils`;

**Procedure** `Testit (S : String)`;

```

begin
  WriteLn (S, ' -> ', AnsiUpperCase(S))
end;

```

```

Begin
  Testit('AN UPPERCASE STRING');
  Testit('Some mixed STring');
  Testit('a lowercase string');
End.

```

---

### 38.13.29 AnsiUpperCaseFileName

Synopsis: Convert filename to uppercase.

Declaration: `function AnsiUpperCaseFileName(const s: String) : String`

Visibility: default

Description: `AnsiUpperCaseFileName` simply returns the result of

```
AnsiUpperCase(S);
```

See also: `AnsiUpperCase` ([1460](#)), `AnsiCompareFileName` ([1448](#)), `AnsiLowerCaseFileName` ([1452](#))

### 38.13.30 AppendStr

Synopsis: Append one ansistring to another.

Declaration: `procedure AppendStr(var Dest: String; const S: String)`

Visibility: default

Description: `AppendStr` appends `S` to `Dest`.

This function is provided for Delphi compatibility only, since it is completely equivalent to `Dest := Dest + S`.

Errors: None.

See also: `AssignStr` ([1462](#)), `NewStr` ([1526](#)), `DisposeStr` ([1478](#))

**Listing:** `./sysutex/ex62.pp`

---

**Program** `Example62`;

*{ This program demonstrates the AppendStr function }*

**Uses** `sysutils`;

**Var** `S : AnsiString`;

**Begin**

`S := 'This is an ';`

`AppendStr(S, 'AnsiString');`

`WriteLn ('S = "', S, '"');`

**End.**

---

### 38.13.31 ApplicationName

Synopsis: Return a default application name

Declaration: `function ApplicationName : String`

Visibility: default

Description: `ApplicationName` returns the name of the current application. Standard this is equal to the result of `ParamStr(0)`, but it can be customized by setting the `OnGetApplicationName` ([1444](#)) callback.

Note that the returned value is only the name portion. It does not contain any path or file extension.

Errors: None.

See also: `GetAppConfigDir` ([1513](#)), `OnGetApplicationName` ([1444](#)), `GetAppConfigFile` ([1513](#)), `ConfigExtension` ([1430](#))

**38.13.32 AssignStr**

Synopsis: Assigns an anstring to a null-terminated string.

Declaration: `procedure AssignStr(var P: PString; const S: String)`

Visibility: default

Description: `AssignStr` allocates `S` to `P`. The old value of `P` is disposed of.

This function is provided for Delphi compatibility only. `AnsiStrings` are managed on the heap and should be preferred to the mechanism of dynamically allocated strings.

Errors: None.

See also: `NewStr` ([1526](#)), `AppendStr` ([1461](#)), `DisposeStr` ([1478](#))

**Listing:** `./sysutex/ex63.pp`

---

**Program** Example63;

*{ This program demonstrates the AssignStr function }*  
*{ \$H+ }*

**Uses** sysutils;

**Var** P : PString;

**Begin**

P:=**NewStr**('A first AnsiString');  
**WriteLn** ('Before: P = "', P^, '"');  
**AssignStr**(P, 'A Second anstring');  
**WriteLn** ('After : P = "', P^, '"');  
**DisposeStr**(P);

**End.**

---

**38.13.33 BCDToInt**

Synopsis: Convert a BCD coded integer to a normal integer.

Declaration: `function BCDToInt(Value: Integer) : Integer`

Visibility: default

Description: `BCDToInt` converts a BCD coded integer to a normal integer.

Errors: None.

See also: `StrToInt` ([1552](#)), `IntToStr` ([1521](#))

**Listing:** `./sysutex/ex64.pp`

---

**Program** Example64;

*{ This program demonstrates the BCDToInt function }*

**Uses** sysutils;

**Procedure** Testit ( L : longint);  
**begin**



---

```

    WriteLn (L, ' -> ',BCDToInt(L));
end;

Begin
    Testit(100);
    Testit(1000);
End.

```

---

### 38.13.34 Beep

Synopsis: Sound the system bell.

Declaration: `procedure Beep`

Visibility: default

Description: `Beep` sounds the system bell, if one is available.

Errors: This routine may not be implemented on all platforms.

### 38.13.35 BoolToStr

Synopsis: Convert a boolean value to a string.

Declaration: `function BoolToStr(B: Boolean;UseBoolStrs: Boolean) : String`  
`function BoolToStr(B: Boolean;const TrueS: String;const FalseS: String)`  
`: String`

Visibility: default

Description: `BoolToStr` converts the boolean `B` to one of the strings ' TRUE' or ' FALSE'

Errors: None.

See also: `StrToBool` ([1547](#))

### 38.13.36 ByteToCharIndex

Synopsis: Convert a character index in Bytes to an Index in characters

Declaration: `function ByteToCharIndex(const S: String;Index: Integer) : Integer`

Visibility: default

Description: `ByteToCharIndex` returns the index (in characters) of the `Index`-th byte in `S`.

Errors: This function does not take into account MBCS yet.

See also: `CharToByteLen` ([1465](#)), `ByteToCharLen` ([1464](#))

### 38.13.37 ByteToCharLen

Synopsis: Convert a length in bytes to a length in characters.

Declaration: `function ByteToCharLen(const S: String;MaxLen: Integer) : Integer`

Visibility: default

Description: `ByteToCharLen` returns the number of bytes in `S`, but limits the result to `MaxLen`

Errors: This function does not take into account MBCS yet.

See also: `CharToByteLen` ([1465](#)), `ByteToCharIndex` ([1463](#))

### 38.13.38 ByteType

Synopsis: Return the type of byte in an ansistring for a multi-byte character set

Declaration: `function ByteType(const S: String;Index: Integer) : TMbcsByteType`

Visibility: default

Description: `ByteType` returns the type of byte in the ansistring `S` at (1-based) position `Index`.

Errors: No checking on the index is performed.

See also: `TMbcsByteType` ([1440](#)), `StrByteType` ([1534](#))

### 38.13.39 CallTerminateProcs

Synopsis: Call the exit chain procedures.

Declaration: `function CallTerminateProcs : Boolean`

Visibility: default

Description: `CallTerminateProcs` is run on program exit. It executes all terminate procedures that were added to the exit chain with `AddTerminateProc` ([1447](#)), and does this in reverse order.

Errors: If one of the exit procedure raises an exception, it is *not* caught, and the remaining exit procedures will not be executed.

See also: `TTerminateProc` ([1441](#)), `AddTerminateProc` ([1447](#))

### 38.13.40 ChangeFileExt

Synopsis: Change the extension of a filename.

Declaration: `function ChangeFileExt(const FileName: String;const Extension: String)  
: String`

Visibility: default

Description: `ChangeFileExt` changes the file extension in `FileName` to `Extension`. The extension `Extension` includes the starting `.` (dot). The previous extension of `FileName` are all characters after the last `.`, the `.` character included.

If `FileName` doesn't have an extension, `Extension` is just appended.

Errors: None.

See also: `ExtractFileName` ([1485](#)), `ExtractFilePath` ([1485](#)), `ExpandFileName` ([1483](#))

### 38.13.41 CharToByteLen

**Synopsis:** Convert a length in characters to a length in bytes.

**Declaration:** `function CharToByteLen(const S: String;MaxLen: Integer) : Integer`

**Visibility:** default

**Description:** `CharToByteLen` returns the number of bytes in `S`, but limits the result to `MaxLen`

**Errors:** This function does not take into account MBCS yet.

See also: `ByteToCharLen` ([1464](#)), `ByteToCharIndex` ([1463](#))

### 38.13.42 CompareMem

**Synopsis:** Compare two memory areas.

**Declaration:** `function CompareMem(P1: Pointer;P2: Pointer;Length: cardinal) : Boolean`

**Visibility:** default

**Description:** `CompareMem` compares, byte by byte, 2 memory areas pointed to by `P1` and `P2`, for a length of `L` bytes.

It returns the following values:

<0 if at some position the byte at `P1` is less than the byte at the same position at `P2`.

0 if all `L` bytes are the same.

>0 if at some position the byte at `P1` is greater than the byte at the same position at `P2`.

**Errors:**

### 38.13.43 CompareMemRange

**Synopsis:** Compare 2 memory locations

**Declaration:** `function CompareMemRange(P1: Pointer;P2: Pointer;Length: cardinal)  
: Integer`

**Visibility:** default

**Description:** `CompareMemRange` compares the 2 memory locations pointed to by `P1` and `P2` byte per byte. It stops comparing after `Length` bytes have been compared, or when it has encountered 2 different bytes. The result is then

>0 if a byte in range `P1` was found that is bigger than the corresponding byte in range `P2`.

0 if all bytes in range `P1` are the same as the corresponding bytes in range `P2`.

<0 if a byte in range `P1` was found that is less than the corresponding byte in range `P2`.

**Errors:** None.

See also: `SameText` ([1531](#))



**38.13.45 CompareText**

Synopsis: Compare 2 ansistrings case insensitive.

Declaration: `function CompareText (const S1: String; const S2: String) : Integer`

Visibility: default

Description: CompareText compares two strings, S1 and S2, and returns the following result:

```
<0if S1<S2.
0if S1=S2.
>0if S1>S2.
```

The comparison of the two strings is case-insensitive. The function does not take internationalization settings into account, it simply compares ASCII values.

Errors: None.

See also: [AnsiCompareText \(1449\)](#), [AnsiCompareStr \(1448\)](#), [CompareStr \(1466\)](#)

**Listing:** ./sysutex/ex66.pp

---

**Program** Example66;

```
{ This program demonstrates the CompareText function }
{$H+}
```

**Uses** sysutils;

**Procedure** TestIt (S1,S2 : **String**);

**Var** R : Longint;

**begin**

  R:=CompareText(S1,S2);

**Write** ( '',S1,' is ');

**If** R<0 **then**

**write** ( 'less than ')

**else If** R=0 **then**

**Write** ( 'equal to ')

**else**

**Write** ( 'larger than ');

**WriteLn** ( '',S2,' ');

**end**;

**Begin**

  Testit('One string','One smaller string');

  Testit('One string','one string');

  Testit('One string','One string');

  Testit('One string','One tall string');

**End.**

---

**38.13.46 ComposeDateTime**

Synopsis: Add a date and time

Declaration: `function ComposeDateTime (Date: TDateTime; Time: TDateTime) : TDateTime`

Visibility: default

Description: `ComposeDateTime` correctly adds `Date` and `Time`, also for dates before 1899-12-31. For dates after this date, it is just the mathematical addition.

Errors: None.

See also: `EncodeDateTime` ([1426](#))

### 38.13.47 CreateDir

Synopsis: Create a new directory

Declaration: `function CreateDir(const NewDir: String) : Boolean`

Visibility: default

Description: `CreateDir` creates a new directory with name `NewDir`. If the directory doesn't contain an absolute path, then the directory is created below the current working directory.

The function returns `True` if the directory was successfully created, `False` otherwise.

Errors: In case of an error, the function returns `False`.

See also: `RemoveDir` ([1528](#))

**Listing:** `./sysutex/ex26.pp`

---

**Program** `Example26`;

```
{ This program demonstrates the CreateDir and RemoveDir functions }
{ Run this program twice in the same directory }
```

**Uses** `sysutils`;

**Begin**

```
  If Not DirectoryExists('NewDir') then
    If Not CreateDir('NewDir') Then
      Writeln('Failed to create directory !')
    else
      Writeln('Created "NewDir" directory')
  Else
    If Not RemoveDir('NewDir') Then
      Writeln('Failed to remove directory !')
    else
      Writeln('Removed "NewDir" directory');
```

**End.**

---

### 38.13.48 CreateGUID

Synopsis: Create a new GUID

Declaration: `function CreateGUID(out GUID: TGUID) : Integer`

Visibility: default

**Description:** `CreateGUID` can be called to create a new GUID (Globally Unique Identifier) value. The function returns the new GUID value in `GUID` and returns zero in case the GUID was created successfully. If no GUID was created, a nonzero error code is returned.

The default mechanism for creating a new GUID is system dependent. If operating system support is available, it is used. If none is available, a default implementation using random numbers is used.

The `OnCreateGUID` callback can be set to hook a custom mechanism behind the `CreateGUID` function. This can be used to let the GUID be created by an external GUID creation library.

**Errors:** On error, a nonzero return value is returned.

**See also:** `GUIDCase` ([1518](#)), `IsEqualGUID` ([1522](#)), `StringToGUID` ([1539](#)), `TryStringToGUID` ([1563](#)), `GUIDToString` ([1518](#))

### 38.13.49 CurrentYear

**Synopsis:** Return the current year

**Declaration:** `function CurrentYear : Word`

**Visibility:** default

**Description:** `CurrentYear` returns the current year as a 4-digit number.

**Errors:** None.

**See also:** `Date` ([1470](#)), `Time` ([1558](#)), `Now` ([1527](#))

### 38.13.50 CurrToStr

**Synopsis:** Convert a currency value to a string.

**Declaration:** `function CurrToStr(Value: Currency) : String`  
`function CurrToStr(Value: Currency;`  
`const FormatSettings: TFormatSettings) : String`

**Visibility:** default

**Description:** `CurrToStr` will convert a currency value to a string with a maximum of 15 digits, and precision 2. Calling `CurrToStr` is equivalent to calling `FloatToStrF` ([1500](#)):

```
FloatToStrF(Value, ffNumber, 15, 2);
```

**Errors:** None.

**See also:** `FloatToStrF` ([1500](#)), `StrToCurr` ([1548](#))

### 38.13.51 CurrToStrF

**Synopsis:** Format a currency to a string

**Declaration:** `function CurrToStrF(Value: Currency; Format: TFloatFormat;`  
`Digits: Integer) : String`  
`function CurrToStrF(Value: Currency; Format: TFloatFormat;`  
`Digits: Integer;`  
`const FormatSettings: TFormatSettings) : String`

Visibility: default

Description: `CurrToStrF` formats the currency `Value` according to the value in `Format`, using the number of digits specified in `Digits`, and a precision of 19. This function simply calls `FloatToStrF` (1500).

See also: `FloatToStrF` (1500)

### 38.13.52 Date

Synopsis: Return the current date.

Declaration: `function Date : TDateTime`

Visibility: default

Description: `Date` returns the current date in `TDateTime` format.

Errors: None.

See also: `Time` (1558), `Now` (1527)

**Listing:** `./sysutex/ex1.pp`

---

**Program** `Example1`;

*{ This program demonstrates the Date function }*

**uses** `sysutils`;

**Var** `YY,MM,DD : Word`;

**Begin**

`WriteLn ( 'Date : ',Date );`

`DeCodeDate ( Date,YY,MM,DD );`

`WriteLn ( format ( 'Date is (DD/MM/YY): %d/%d/%d ',[dd,mm,yy] ) );`

**End.**

---

### 38.13.53 DateTimeToFileDate

Synopsis: Convert a `TDateTime` value to a file age (integer)

Declaration: `function DateTimeToFileDate(DateTime: TDateTime) : LongInt`

Visibility: default

Description: `DateTimeToFileDate` function converts a date/time indication in `TDateTime` format to a file-date function, such as returned for instance by the `FileAge` (1486) function.

Errors: None.

See also: `Time` (1558), `Date` (1470), `FileDateToDateTime` (1488), `DateTimeToSystemTime` (1472), `Date-TimeToTimeStamp` (1473)

**Listing:** `./sysutex/ex2.pp`



---

**Program** Example2;

*{ This program demonstrates the DateTimeToFileDate function }*

**Uses** sysutils;

**Begin**

**WriteLn** ( 'FileTime of now would be: ', **DateTimeToFileDate** (**Now**));

**End.**

---

### 38.13.54 DateTimeToStr

**Synopsis:** Converts a `TDateTime` value to a string using a predefined format.

**Declaration:** `function DateTimeToStr(DateTime: TDateTime) : String`  
`function DateTimeToStr(DateTime: TDateTime;`  
`const FormatSettings: TFormatSettings) : String`

**Visibility:** default

**Description:** `DateTimeToStr` returns a string representation of `DateTime` using the formatting specified in `LongDateTimeFormat`. It corresponds to a call to `FormatDateTime('c', DateTime)` (see [formatchars \(1429\)](#)).

**Errors:** None.

**See also:** `FormatDateTime` ([1510](#))

**Listing:** `./sysutex/ex3.pp`

---

**Program** Example3;

*{ This program demonstrates the DateTimeToStr function }*

**Uses** sysutils;

**Begin**

**WriteLn** ( 'Today is : ', **DateTimeToStr**(**Now**));

**WriteLn** ( 'Today is : ', **FormatDateTime**( 'c', **Now**));

**End.**

---

### 38.13.55 DateTimeToString

**Synopsis:** Converts a `TDateTime` value to a string with a given format.

**Declaration:** `procedure DateTimeToString(out Result: String; const FormatStr: String;`  
`const DateTime: TDateTime)`  
`procedure DateTimeToString(out Result: String; const FormatStr: String;`  
`const DateTime: TDateTime;`  
`const FormatSettings: TFormatSettings)`

**Visibility:** default

**Description:** `DateTimeToString` returns in `Result` a string representation of `DateTime` using the formatting specified in `FormatStr`. for a list of characters that can be used in the `FormatStr` formatting string, see [formatchars \(1429\)](#).

Errors: In case a wrong formatting character is found, an `EConvertError` is raised.

See also: `FormatDateTime` ([1510](#)), `formatchars` ([1429](#))

**Listing:** ./sysutex/ex4.pp

---

**Program** Example4;

*{ This program demonstrates the DateTimeToString function }*

**Uses** sysutils;

**Procedure** today (Fmt : **string**);

**Var** S : AnsiString;

**begin**

**DateTimeToString** (S,Fmt,**Date**);

**WriteLn** (S);

**end**;

**Procedure** Now (Fmt : **string**);

**Var** S : AnsiString;

**begin**

**DateTimeToString** (S,Fmt,**Time**);

**WriteLn** (S);

**end**;

**Begin**

    Today ( ' "Today is " dddd dd mmmm y ' );

    Today ( ' "Today is " d mmm yy ' );

    Today ( ' "Today is " d/mmm/yy ' );

**Now** ( ' ' 'The time is ' 'am/pmh:n:s ' );

**Now** ( ' ' 'The time is ' 'hh:nn:ssam/pm ' );

**Now** ( ' ' 'The time is ' 'tt ' );

**End.**

---

### 38.13.56 DateTimeToSystemTime

**Synopsis:** Converts a `TDateTime` value to a `systemtime` structure.

**Declaration:** `procedure DateTimeToSystemTime(DateTime: TDateTime;`  
`out SystemTime: TSystemTime)`

**Visibility:** default

**Description:** `DateTimeToSystemTime` converts a date/time pair in `DateTime`, with `TDateTime` format to a system time `SystemTime`.

**Errors:** None.

See also: `DateTimeToFileDate` ([1470](#)), `SystemTimeToDateTime` ([1557](#)), `DateTimeToTimeStamp` ([1473](#))

**Listing:** ./sysutex/ex5.pp

---

**Program** Example5;

*{ This program demonstrates the DateTimeToSystemTime function }*

**Uses** sysutils;

**Var** ST : TSystemTime;

**Begin**

DateTimeToSystemTime(**Now**,ST);

**With** St **do**

**begin**

**Writeln** ( 'Today is ',year,'/',month,'/',Day);

**Writeln** ( 'The time is ',Hour,':',minute,':',Second,'.',',MilliSecond);

**end**;

**End.**

---

### 38.13.57 DateTimeToTimeStamp

**Synopsis:** Converts a TDateTime value to a TimeStamp structure.

**Declaration:** function DateTimeToTimeStamp(DateTime: TDateTime) : TTimeStamp

**Visibility:** default

**Description:** DateTimeToSystemTime converts a date/time pair in DateTime, with TDateTime format to a TTimeStamp format.

**Errors:** None.

**See also:** DateTimeToFileDate ([1470](#)), SystemTimeToDateTime ([1557](#)), DateTimeToSystemTime ([1472](#))

**Listing:** ./sysutex/ex6.pp

---

**Program** Example6;

*{ This program demonstrates the DateTimeToTimeStamp function }*

**Uses** sysutils;

**Var** TS : TTimeStamp;

**Begin**

TS:=DateTimeToTimeStamp (**Now**);

**With** TS **do**

**begin**

**Writeln** ( 'Now is ',time,' millisecond past midnight');

**Writeln** ( 'Today is ',Date,' days past 1/1/0001');

**end**;

**End.**

---

### 38.13.58 DateToStr

**Synopsis:** Converts a TDateTime value to a date string with a predefined format.

**Declaration:** `function DateToStr(Date: TDateTime) : String`  
`function DateToStr(Date: TDateTime;`  
`const FormatSettings: TFormatSettings) : String`

**Visibility:** default

**Description:** `DateToStr` converts `Date` to a string representation. It uses `ShortDateFormat` as it's formatting string. It is hence completely equivalent to a `FormatDateTime('dddd', Date)`.

**Errors:** None.

See also: `TimeToStr` ([1560](#)), `DateTimeToStr` ([1471](#)), `FormatDateTime` ([1510](#)), `StrToDate` ([1548](#))

**Listing:** `./sysutex/ex7.pp`

---

**Program** `Example7;`

`{ This program demonstrates the DateToStr function }`

**Uses** `sysutils;`

**Begin**

`WriteIn (Format ( 'Today is: %s' ,[DateToStr (Date)]));`

**End.**

---

### 38.13.59 DayOfWeek

**Synopsis:** Returns the day of the week.

**Declaration:** `function DayOfWeek(DateTime: TDateTime) : Integer`

**Visibility:** default

**Description:** `DayOfWeek` returns the day of the week from `DateTime`. Sunday is counted as day 1, Saturday is counted as day 7. The result of `DayOfWeek` can serve as an index to the `LongDayNames` constant array, to retrieve the name of the day.

**Errors:** None.

See also: `Date` ([1470](#)), `DateToStr` ([1473](#))

**Listing:** `./sysutex/ex8.pp`

---

**Program** `Example8;`

`{ This program demonstrates the DayOfWeek function }`

**Uses** `sysutils;`

**Begin**

`WriteIn ( 'Today 's day is ',LongDayNames[DayOfWeek (Date)]);`

**End.**

---

**38.13.60 DecodeDate**

Synopsis: Decode a TDateTime to a year,month,day triplet

Declaration: `procedure DecodeDate(Date: TDateTime;out Year: Word;out Month: Word;  
out Day: Word)`

Visibility: default

Description: DecodeDate decodes the Year, Month and Day stored in Date, and returns them in the Year, Month and Day variables.

Errors: None.

See also: EncodeDate ([1479](#)), DecodeTime ([1475](#))

**Listing:** ./sysutex/ex9.pp

---

**Program** Example9;

*{ This program demonstrates the DecodeDate function }*

**Uses** sysutils;

**Var** YY,MM,DD : Word;

**Begin**

**DecodeDate**( Date ,YY,MM,DD);

**WriteIn** ( **Format** ( 'Today is %d/%d/%d' ,[dd,mm,yy] ));

**End.**

---

**38.13.61 DecodeDateFully**

Synopsis: Decode a date with additional date of the week.

Declaration: `function DecodeDateFully(const DateTime: TDateTime;out Year: Word;  
out Month: Word;out Day: Word;out DOW: Word)  
: Boolean`

Visibility: default

Description: DecodeDateFully, like DecodeDate ([1475](#)), decodes DateTime in its parts and returns these in Year, Month, Day but in addition returns the day of the week in DOW.

Errors: None.

See also: EncodeDate ([1479](#)), TryEncodeDate ([1562](#)), DecodeDate ([1475](#))

**38.13.62 DecodeTime**

Synopsis: Decode a TDateTime to a hour,minute,second,millisecond quartet

Declaration: `procedure DecodeTime(Time: TDateTime;out Hour: Word;out Minute: Word;  
out Second: Word;out MilliSecond: Word)`

Visibility: default

Description: DecodeDate decodes the hours, minutes, second and milliseconds stored in Time, and returns them in the Hour, Minute and Second and MilliSecond variables.

Errors: None.

See also: EncodeTime ([1480](#)), DecodeDate ([1475](#))

**Listing:** ./sysutex/ex10.pp

---

**Program** Example10;

*{ This program demonstrates the DecodeTime function }*

**Uses** sysutils;

**Var** HH,MM,SS,MS: Word;

**Begin**

    DecodeTime(Time,HH,MM,SS,MS);

    WriteLn (format('The time is %d:%d:%d.%d',[hh,mm,ss,ms]));

**End.**

---

### 38.13.63 DeleteFile

Synopsis: Delete a file from the filesystem.

Declaration: function DeleteFile(const FileName: String) : Boolean

Visibility: default

Description: DeleteFile deletes file FileName from disk. The function returns True if the file was successfully removed, False otherwise.

Errors: On error, False is returned.

See also: FileCreate ([1487](#)), FileExists ([1489](#))

**Listing:** ./sysutex/ex31.pp

---

**Program** Example31;

*{ This program demonstrates the DeleteFile function }*

**Uses** sysutils;

**Var**

    Line : **String**;

    F,I : Longint;

**Begin**

    F:= FileCreate('test.txt');

    Line:= 'Some string line.'#10;

**For** I:=1 **to** 10 **do**

        FileWrite (F,Line[I],Length(Line));

    FileClose(F);

    DeleteFile('test.txt');

**End.**

---

**38.13.64 DirectoryExists**

Synopsis: Check whether a directory exists in the file system.

Declaration: `function DirectoryExists(const Directory: String) : Boolean`

Visibility: default

Description: `DirectoryExists` checks whether `Directory` exists in the filesystem and is actually a directory. If this is the case, the function returns `True`, otherwise `False` is returned.

See also: `FileExists` ([1489](#))

**38.13.65 DiskFree**

Synopsis: Return the amount of free disk space

Declaration: `function DiskFree(drive: Byte) : Int64`

Visibility: default

Description: `DiskFree` returns the free space (in bytes) on disk `Drive`. `Drive` is the number of the disk drive:

**0**for the current drive.

**1**for the first floppy drive.

**2**for the second floppy drive.

**3**for the first hard-disk partition.

**4-26**for all other drives and partitions.

**Remark:** Under Linux, and Unix in general, the concept of disk is different than the dos one, since the filesystem is seen as one big directory tree. For this reason, the `DiskFree` and `DiskSize` ([1478](#)) functions must be mimicked using filenames that reside on the partitions. For more information, see `AddDisk` ([1447](#)).

Errors: On error, `-1` is returned.

See also: `DiskSize` ([1478](#)), `AddDisk` ([1447](#))

**Listing:** `./sysutex/ex27.pp`

---

**Program** `Example27`;

*{ This program demonstrates the DiskFree function }*

**Uses** `sysutils`;

**Begin**

`Write ('Size of current disk : ', DiskSize(0));`

`WriteLn (' (= ', DiskSize(0) div 1024, 'k) ');`

`Write ('Free space of current disk : ', Diskfree(0));`

`WriteLn (' (= ', Diskfree(0) div 1024, 'k) ');`

**End.**

---

### 38.13.66 DiskSize

Synopsis: Return the total amount of disk space.

Declaration: `function DiskSize(drive: Byte) : Int64`

Visibility: default

Description: `DiskSize` returns the size (in bytes) of disk `Drive`. `Drive` is the number of the disk drive:

- `0` for the current drive.
- `1` for the first floppy drive.
- `2` for the second floppy drive.
- `3` for the first hard-disk partition.
- `4-26` for all other drives and partitions.

**Remark:** Under Linux, and Unix in general, the concept of disk is different than the dos one, since the filesystem is seen as one big directory tree. For this reason, the `DiskFree` (1477) and `DiskSize` functions must be mimicked using filenames that reside on the partitions. For more information, see `AddDisk` (1447)

For an example, see `DiskFree` (1477).

Errors: On error, `-1` is returned.

See also: `DiskFree` (1477), `AddDisk` (1447)

### 38.13.67 DisposeStr

Synopsis: Dispose an anstring from the heap.

Declaration: `procedure DisposeStr(S: PString); Overload`  
`procedure DisposeStr(S: PShortString); Overload`

Visibility: default

Description: `DisposeStr` removes the dynamically allocated string `S` from the heap, and releases the occupied memory.

This function is provided for Delphi compatibility only. `AnsiStrings` are managed on the heap and should be preferred to the mechanism of dynamically allocated strings.

For an example, see `DisposeStr` (1478).

Errors: None.

See also: `NewStr` (1526), `AppendStr` (1461), `AssignStr` (1462)

### 38.13.68 DoDirSeparators

Synopsis: Convert known directory separators to the current directory separator.

Declaration: `procedure DoDirSeparators(var FileName: String)`

Visibility: default

Description: This function replaces all known directory separators in `FileName` to the directory separator character for the current system. The list of known separators is specified in the `DirSeparators` (1426) constant.



Errors: None.

See also: ExtractFileName ([1485](#)), ExtractFilePath ([1485](#))

**Listing:** ./sysutex/ex32.pp

---

**Program** Example32;

*{ This program demonstrates the DoDirSeparators function }*  
*{ \$H+ }*

**Uses** sysutils;

**Procedure** Testit (F : **String**);

**begin**

**WriteIn** ( 'Before : ', F);

    DoDirSeparators (F);

**WriteIn** ( 'After : ', F);

**end**;

**Begin**

    Testit ( GetCurrentDir );

    Testit ( 'c:\pp\bin\win32' );

    Testit ( '/usr/lib/fpc' );

    Testit ( '\usr\lib\fpc' );

**End.**

---

### 38.13.69 EncodeDate

**Synopsis:** Encode a Year,Month,Day to a TDateTime value.

**Declaration:** function EncodeDate (Year: Word;Month: Word;Day: Word) : TDateTime

**Visibility:** default

**Description:** EncodeDate encodes the Year, Month and Day variables to a date in TDateTime format. It does the opposite of the DecodeDate ([1475](#)) procedure.

The parameters must lie withing valid ranges (boundaries included):

**Year** must be between 1 and 9999.

**Month** must be within the range 1-12.

**Days** must be between 1 and 31.

**Errors:** In case one of the parameters is out of it's valid range, an EConvertError ([1572](#)) exception is raised.

See also: EncodeTime ([1480](#)), DecodeDate ([1475](#))

**Listing:** ./sysutex/ex11.pp

---

**Program** Example11;

*{ This program demonstrates the EncodeDate function }*

**Uses** sysutils;

**Var** YY,MM,DD : Word;

```

Begin
  DecodeDate ( Date ,YY,MM,DD);
                                     WriteLn ( 'Today is : ',FormatDateTime ( 'dd mmm yyyy ',EnCodeDate(Y
End.

```

---

### 38.13.70 EncodeTime

Synopsis: Encode a Hour,Min,Sec,millisecond to a TDateTime value.

Declaration: `function EncodeTime(Hour: Word;Minute: Word;Second: Word;  
MilliSecond: Word) : TDateTime`

Visibility: default

Description: EncodeTime encodes the Hour,Minute,Second,MilliSecond variables to a TDateTime format result. It does the opposite of the DecodeTime (1475) procedure.

The parameters must have a valid range (boundaries included):

**Hour** must be between 0 and 23.

**Minute,second** must both be between 0 and 59.

**Millisecond** must be between 0 and 999.

Errors: In case one of the parameters is out of it's valid range, an EConvertError (1572) exception is raised.

See also: EncodeDate (1479), DecodeTime (1475)

**Listing:** ./sysutex/ex12.pp

---

**Program** Example12;

*{ This program demonstrates the EncodeTime function }*

**Uses** sysutils;

**Var** Hh,MM,SS,MS : Word;

**Begin**

**DeCodeTime** ( **Time**,Hh,MM,SS,MS);

**WriteLn** ( 'Present Time is : ',**FormatDateTime**( 'hh:mm:ss ',**EnCodeTime** (Hh,MM,SS,MS)));

**End.**

---

### 38.13.71 ExceptAddr

Synopsis: Current exception address.

Declaration: `function ExceptAddr : Pointer`

Visibility: default

Description: ExceptAddr returns the address from the currently treated exception object when an exception is raised, and the stack is unwound.

See also: ExceptObject (1481), ExceptionErrorMessage (1481), ShowException (1532)

### 38.13.72 ExceptFrameCount

Synopsis: Number of frames included in an exception backtrace

Declaration: `function ExceptFrameCount : LongInt`

Visibility: default

Description: `ExceptFrameCount` returns the number of frames that are included in an exception stack frame backtrace. The function returns 0 if there is currently no exception being handled. (i.e. it only makes sense to call this function in an `finally..end` or `except..end` block.

Errors: None.

See also: `ExceptFrames` ([1481](#)), `ExceptAddr` ([1480](#)), `ExceptObject` ([1481](#)), `ExceptProc` ([1426](#))

### 38.13.73 ExceptFrames

Synopsis:

Declaration: `function ExceptFrames : PPointer`

Visibility: default

Description:

Errors:

See also: `ExceptFrameCount` ([1481](#)), `ExceptAddr` ([1480](#)), `ExceptObject` ([1481](#)), `ExceptProc` ([1426](#))

### 38.13.74 ExceptionErrorMessage

Synopsis: Return a message describing the exception.

Declaration: `function ExceptionErrorMessage(ExceptObject: TObject;  
   ExceptAddr: Pointer; Buffer: PChar;  
   Size: Integer) : Integer`

Visibility: default

Description: `ExceptionErrorMessage` creates a string that describes the exception object `ExceptObject` at address `ExceptAddr`. It can be used to display exception messages. The string will be stored in the memory pointed to by `Buffer`, and will at most have `Size` characters.

The routine checks whether `ExceptObject` is a `Exception` ([1577](#)) object or not, and adapts the output accordingly.

See also: `ExceptObject` ([1481](#)), `ExceptAddr` ([1480](#)), `ShowException` ([1532](#))

### 38.13.75 ExceptObject

Synopsis: Current Exception object.

Declaration: `function ExceptObject : TObject`

Visibility: default

Description: `ExceptObject` returns the currently treated exception object when an exception is raised, and the stack is unwound.

Errors: If there is no exception, the function returns `Nil`

See also: `ExceptAddr` ([1480](#)), `ExceptionErrorMessage` ([1481](#)), `ShowException` ([1532](#))

### 38.13.76 ExcludeTrailingBackslash

Synopsis: Strip trailing directory separator from a pathname, if needed.

Declaration: `function ExcludeTrailingBackslash(const Path: String) : String`

Visibility: default

Description: `ExcludeTrailingBackslash` is provided for backwards compatibility with Delphi. Use `ExcludeTrailingPathDelimiter` (1482) instead.

See also: `IncludeTrailingPathDelimiter` (1519), `ExcludeTrailingPathDelimiter` (1482), `PathDelim` (1433), `IsPathDelimiter` (1523)

### 38.13.77 ExcludeTrailingPathDelimiter

Synopsis: Strip trailing directory separator from a pathname, if needed.

Declaration: `function ExcludeTrailingPathDelimiter(const Path: String) : String`

Visibility: default

Description: `ExcludeTrailingPathDelimiter` removes the trailing path delimiter character (`PathDelim` (1433)) from `Path` if it is present, and returns the result.

See also: `ExcludeTrailingBackslash` (1482), `IncludeTrailingPathDelimiter` (1519), `PathDelim` (1433), `IsPathDelimiter` (1523)

### 38.13.78 ExecuteProcess

Synopsis: Execute another process (program).

Declaration: 

```
function ExecuteProcess(const Path: AnsiString;
                        const ComLine: AnsiString; Flags: TExecuteFlags)
                        : Integer
function ExecuteProcess(const Path: AnsiString;
                        const ComLine: Array of AnsiString;
                        Flags: TExecuteFlags) : Integer
```

Visibility: default

Description: `ExecuteProcess` will execute the program in `Path`, passing it the arguments in `ComLine`. `ExecuteProcess` will then wait for the program to finish, and will return the exit code of the executed program. In case `ComLine` is a single string, it will be split out in an array of strings, taking into account common whitespace and quote rules.

Errors: In case the program could not be executed or an other error occurs, an `EOSError` (1575) exception will be raised.

See also: `EOSError` (1575)

### 38.13.79 ExeSearch

Synopsis: Search for an executable

Declaration: `function ExeSearch(const Name: String; const DirList: String) : String`

Visibility: default

**Description:** `ExeSearch` searches for an executable `Name` in the list of directories `DirList` (a list of directories, separator by `PathSeparator` (1224)). If the current OS also searches implicitly in the current working directory, the current directory is searched in the first place.

If the executable is found, then the full path of the executable is returned. If it is not found, an empty string is returned.

No check is performed whether the found file is actually executable.

See also: `FileSearch` (1493)

### 38.13.80 ExpandFileName

**Synopsis:** Expand a relative filename to an absolute filename.

**Declaration:** `function ExpandFileName(const FileName: String) : String`

**Visibility:** default

**Description:** `ExpandFileName` expands the filename to an absolute filename. It changes all directory separator characters to the one appropriate for the system first.

**Errors:** None.

See also: `ExtractFileName` (1485), `ExtractFilePath` (1485), `ExtractFileDir` (1484), `ExtractFileDrive` (1484), `ExtractFileExt` (1485), `ExtractRelativePath` (1486)

**Listing:** `./sysutex/ex33.pp`

---

**Program** `Example33`;

*{ This program demonstrates the ExpandFileName function }*

**Uses** `sysutils`;

**Procedure** `Testit (F : String)`;

**begin**

`WriteLn (F, ' expands to : ', ExpandFileName(F));`  
**end**;

**Begin**

`Testit('ex33.pp');`  
    `Testit(ParamStr(0));`  
    `Testit('/pp/bin/win32/ppc386');`  
    `Testit('\pp\bin\win32\ppc386');`  
    `Testit('');`

**End.**

---

### 38.13.81 ExpandUNCFileName

**Synopsis:** Expand a relative filename to an absolute UNC filename.

**Declaration:** `function ExpandUNCFileName(const FileName: String) : String`

**Visibility:** default

**Description:** `ExpandUNCFileName` runs `ExpandFileName` (1483) on `FileName` and then attempts to replace the driveletter by the name of a shared disk.

Errors: None.

See also: [ExtractFileName \(1485\)](#), [ExtractFilePath \(1485\)](#), [ExtractFileDir \(1484\)](#), [ExtractFileDrive \(1484\)](#), [ExtractFileExt \(1485\)](#), [ExtractRelativePath \(1486\)](#)

### 38.13.82 ExtractFileDir

Synopsis: Extract the drive and directory part of a filename.

Declaration: `function ExtractFileDir(const FileName: String) : String`

Visibility: default

Description: `ExtractFileDir` returns only the directory part of `FileName`, including a driveletter. The directory name has NO ending directory separator, in difference with [ExtractFilePath \(1485\)](#).

Errors: None.

See also: [ExtractFileName \(1485\)](#), [ExtractFilePath \(1485\)](#), [ExtractFileDir \(1484\)](#), [ExtractFileDrive \(1484\)](#), [ExtractFileExt \(1485\)](#), [ExtractRelativePath \(1486\)](#)

**Listing:** `./sysutex/ex34.pp`

---

**Program** Example34;

*{ This program demonstrates the ExtractFileName function }*  
*{ \$H+ }*

**Uses** sysutils;

**Procedure** Testit(F : **String**);

**begin**

**Writeln** ( 'FileName : ', F);  
**Writeln** ( 'Has Name : ', **ExtractFileName**(F));  
**Writeln** ( 'Has Path : ', **ExtractFilePath**(F));  
**Writeln** ( 'Has Extension : ', **ExtractFileExt**(F));  
**Writeln** ( 'Has Directory : ', **ExtractFileDir**(F));  
**Writeln** ( 'Has Drive : ', **ExtractFileDrive**(F));

**end**;

**Begin**

Testit ( **Paramstr**(0));  
Testit ( '/usr/local/bin/mysqld' );  
Testit ( 'c:\pp\bin\win32\ppc386.exe' );  
Testit ( '/pp/bin/win32/ppc386.exe' );

**End.**

---

### 38.13.83 ExtractFileDrive

Synopsis: Extract the drive part from a filename.

Declaration: `function ExtractFileDrive(const FileName: String) : String`

Visibility: default

Description: `ExtractFileDrive` extracts the drive letter from a filename. Note that some operating systems do not support drive letters.

For an example, see [ExtractFileDir \(1484\)](#).

Errors:

See also: [ExtractFileName \(1485\)](#), [ExtractFilePath \(1485\)](#), [ExtractFileDir \(1484\)](#), [ExtractFileDrive \(1484\)](#), [ExtractFileExt \(1485\)](#), [ExtractRelativePath \(1486\)](#)

### 38.13.84 ExtractFileExt

Synopsis: Return the extension from a filename.

Declaration: `function ExtractFileExt(const FileName: String) : String`

Visibility: default

Description: `ExtractFileExt` returns the extension (including the `.` (dot) character) of `FileName`.

For an example, see [ExtractFileDir \(1484\)](#).

Errors: None.

See also: [ExtractFileName \(1485\)](#), [ExtractFilePath \(1485\)](#), [ExtractFileDir \(1484\)](#), [ExtractFileDrive \(1484\)](#), [ExtractFileExt \(1485\)](#), [ExtractRelativePath \(1486\)](#)

### 38.13.85 ExtractFileName

Synopsis: Extract the filename part from a full path filename.

Declaration: `function ExtractFileName(const FileName: String) : String`

Visibility: default

Description: `ExtractFileName` returns the filename part from `FileName`. The filename consists of all characters after the last directory separator character (`'/'` or `'\'`) or drive letter.

The full filename can always be reconstructed by concatenating the result of [ExtractFilePath \(1485\)](#) and `ExtractFileName`.

For an example, see [ExtractFileDir \(1484\)](#).

Errors: None.

See also: [ExtractFileName \(1485\)](#), [ExtractFilePath \(1485\)](#), [ExtractFileDir \(1484\)](#), [ExtractFileDrive \(1484\)](#), [ExtractFileExt \(1485\)](#), [ExtractRelativePath \(1486\)](#)

### 38.13.86 ExtractFilePath

Synopsis: Extract the path from a filename.

Declaration: `function ExtractFilePath(const FileName: String) : String`

Visibility: default

Description: `ExtractFilePath` returns the path part (including driveletter) from `FileName`. The path consists of all characters before the last directory separator character (`'/'` or `'\'`), including the directory separator itself. In case there is only a drive letter, that will be returned.

The full filename can always be reconstructed by concatenating the result of `ExtractFilePath` and [ExtractFileName \(1485\)](#).

For an example, see [ExtractFileDir \(1484\)](#).

Errors: None.

See also: [ExtractFileName \(1485\)](#), [ExtractFilePath \(1485\)](#), [ExtractFileDir \(1484\)](#), [ExtractFileDrive \(1484\)](#), [ExtractFileExt \(1485\)](#), [ExtractRelativePath \(1486\)](#)

### 38.13.87 ExtractRelativepath

Synopsis: Extract a relative path from a filename, given a base directory.

Declaration: `function ExtractRelativepath(const BaseName: String;  
const DestName: String) : String`

Visibility: default

Description: `ExtractRelativePath` constructs a relative path to go from `BaseName` to `DestName`. If `DestName` is on another drive (Not on Unix-like platforms) then the whole `Destname` is returned.

*Note:* This function does not exist in the Delphi unit.

Errors: None.

See also: `ExtractFileName` (1485), `ExtractFilePath` (1485), `ExtractFileDir` (1484), `ExtractFileDrive` (1484), `ExtractFileExt` (1485)

**Listing:** ./sysutex/ex35.pp

---

**Program** Example35;

*{ This program demonstrates the ExtractRelativePath function }*

**Uses** sysutils;

**Procedure** Testit (FromDir, ToDir : **String**);

**begin**

**Write** ( 'From " ', FromDir, '" to " ', ToDir, '" via " ' );

**WriteLn** ( ExtractRelativePath(FromDir, ToDir), ' " ' );

**end**;

**Begin**

    Testit ( '/pp/src/compiler ', '/pp/bin/win32/ppc386 ' );

    Testit ( '/pp/bin/win32/ppc386 ', '/pp/src/compiler ' );

    Testit ( 'e:/pp/bin/win32/ppc386 ', 'd:/pp/src/compiler ' );

    Testit ( 'e:\pp\bin\win32\ppc386 ', 'd:\pp\src\compiler ' );

**End.**

---

### 38.13.88 ExtractShortPathName

Synopsis: Returns a 8.3 path name

Declaration: `function ExtractShortPathName(const FileName: String) : String`

Visibility: default

Description: `ExtractShortPathName` returns a 8.3 compliant filename that represents the same file as `FileName`. On platforms other than windows, this is `FileName` itself.

See also: `ExtractFilePath` (1485), `ExtractFileName` (1485)

### 38.13.89 FileAge

Synopsis: Return the timestamp of a file.

Declaration: `function FileAge(const FileName: String) : LongInt`



Visibility: default

Description: `FileAge` returns the last modification time of file `FileName`. The `FileDate` format can be transformed to `TDateTime` format with the `FileDateToDateTime` (1488) function.

Errors: In case of errors, `-1` is returned.

See also: `FileDateToDateTime` (1488), `FileExists` (1489), `FileGetAttr` (1490)

**Listing:** `./sysutex/ex36.pp`

---

**Program** `Example36`;

*{ This program demonstrates the FileAge function }*

**Uses** `sysutils`;

**Var** `S` : `TDateTime`;  
       `fa` : `Longint`;

**Begin**  
       `fa := FileAge( 'ex36.pp' );`  
       **If** `Fa <> -1` **then**  
           **begin**  
               `S := FileDateToDateTime( fa );`  
               `WriteLn ( 'I'm from ', DateTimeToStr(S) )`  
           **end**;

**End.**

---

### 38.13.90 FileClose

Synopsis: Close a file handle.

Declaration: `procedure FileClose(Handle: THandle)`

Visibility: default

Description: `FileClose` closes the file handle `Handle`. After this call, attempting to read or write from the handle will result in an error.

For an example, see `FileCreate` (1487)

Errors: None.

See also: `FileCreate` (1487), `FileWrite` (1495), `FileOpen` (1492), `FileRead` (1493), `FileTruncate` (1495), `FileSeek` (1494)

### 38.13.91 FileCreate

Synopsis: Create a new file and return a handle to it.

Declaration: `function FileCreate(const FileName: String) : THandle`  
               `function FileCreate(const FileName: String; Mode: Integer) : THandle`

Visibility: default

**Description:** `FileCreate` creates a new file with name `FileName` on the disk and returns a file handle which can be used to read or write from the file with the `FileRead` (1493) and `FileWrite` (1495) functions.

If a file with name `FileName` already existed on the disk, it is overwritten.

The optional `Mode` parameter only has an effect under unix, where it can be used to set the mode (read, write, execute, sticky bit, setgid and setuid flags) of the created file to the specified custom value. On other platfors, the `Mode` parameter is ignored.

**Errors:** If an error occurs (e.g. disk full or non-existent path), the function returns `-1`.

**See also:** `FileClose` (1487), `FileWrite` (1495), `FileOpen` (1492), `FileRead` (1493), `FileTruncate` (1495), `FileSeek` (1494)

**Listing:** `./sysutex/ex37.pp`

---

**Program** `Example37`;

*{ This program demonstrates the FileCreate function }*

**Uses** `sysutils`;

**Var** `I,J,F` : `Longint`;

**Begin**

```

F:=FileCreate ( 'test.dat' );
If F=-1 then
  Halt (1);
For I:=0 to 100 do
  FileWrite (F,I,SizeOf(i));
FileClose (f);
F:=FileOpen ( 'test.dat',fmOpenRead);
For I:=0 to 100 do
  begin
    FileRead (F,J,SizeOf(J));
    If J<>I then
      Writeln ( 'Mismatch at file position ',I)
    end;
  FileSeek (F,0,fsFromBeginning);
  Randomize;
  Repeat
    FileSeek (F,Random(100)*4,fsFromBeginning);
    FileRead (F,J,SizeOf(J));
    Writeln ( 'Random read : ',j);
  Until J>80;
  FileClose (F);
  F:=FileOpen ( 'test.dat',fmOpenWrite);
  I:=50*SizeOf (Longint);
  If FileTruncate (F,I) then
    Writeln ( 'Successfully truncated file to ',I,' bytes.' );
  FileClose (F);
End.
```

---

### 38.13.92 FileDateToDateTime

**Synopsis:** Convert a `FileDate` value to a `TDateTime` value.

**Declaration:** `function FileDateToDateTime (Filedate: LongInt) : TDateTime`

Visibility: default

**Description:** `FileDateToDateTime` converts the date/time encoded in `filedate` to a `TDateTime` encoded form. It can be used to convert date/time values returned by the `FileAge` (1486) or `FindFirst` (1496)/`FindNext` (1497) functions to `TDateTime` form.

Errors: None.

See also: `DateTimeToFileDate` (1470)

**Listing:** `./sysutex/ex13.pp`

---

**Program** `Example13`;

*{ This program demonstrates the FileDateToDateTime function }*

**Uses** `sysutils`;

**Var**

`ThisAge` : `Longint`;

**Begin**

`Write` ( 'ex13.pp created on : ' );

`ThisAge` := `FileAge` ( 'ex13.pp' );

`WriteLn` ( `DateTimeToStr` ( `FileDateToDateTime` ( `ThisAge` ) ) );

**End.**

---

### 38.13.93 FileExists

**Synopsis:** Check whether a file exists in the filesystem.

**Declaration:** `function FileExists(const FileName: String) : Boolean`

Visibility: default

**Description:** `FileExists` returns `True` if a file with name `FileName` exists on the disk, `False` otherwise. On windows, this function will return `False` if a directory is passed as `FileName`. On unices, passing a directory name will result in `True`. The rationale is that on unix, a directory is a file as well.

Errors: None.

See also: `FileAge` (1486), `FileGetAttr` (1490), `FileSetAttr` (1494)

**Listing:** `./sysutex/ex38.pp`

---

**Program** `Example38`;

*{ This program demonstrates the FileExists function }*

**Uses** `sysutils`;

**Begin**

**If** `FileExists` ( `ParamStr` ( 0 ) ) **Then**

`WriteLn` ( 'All is well, I seem to exist.' );

**End.**

---

**38.13.94 FileGetAttr**

Synopsis: Return attributes of a file.

Declaration: `function FileGetAttr(const FileName: String) : LongInt`

Visibility: default

Description: `FileGetAttr` returns the attribute settings of file `FileName`. The attribute is a OR-ed combination of the following constants:

**faReadOnly**The file is read-only.

**faHidden**The file is hidden. (On unix, this means that the filename starts with a dot)

**faSysFile**The file is a system file (On unix, this means that the file is a character, block or FIFO file).

**faVolumeId**Volume Label. Not possible under unix.

**faDirectory**File is a directory.

**faArchive**file is an archive. Not possible on Unix

Errors: In case of error, -1 is returned.

See also: `FileSetAttr` ([1494](#)), `FileAge` ([1486](#)), `FileGetDate` ([1491](#))

**Listing:** `./sysutex/ex40.pp`

---

**Program** Example40;

*{ This program demonstrates the FileGetAttr function }*

**Uses** sysutils;

**Procedure** Testit (**Name** : **String**);

**Var** F : Longint;

**Begin**

  F := **FileGetAttr**(Name);

**If** F <> -1 **then**

**begin**

**WriteLn** ( 'Testing : ', Name);

**If** (F and faReadOnly) <> 0 **then**

**WriteLn** ( 'File is ReadOnly');

**If** (F and faHidden) <> 0 **then**

**WriteLn** ( 'File is hidden');

**If** (F and faSysFile) <> 0 **then**

**WriteLn** ( 'File is a system file');

**If** (F and faVolumeID) <> 0 **then**

**WriteLn** ( 'File is a disk label');

**If** (F and faArchive) <> 0 **then**

**WriteLn** ( 'File is artchive file');

**If** (F and faDirectory) <> 0 **then**

**WriteLn** ( 'File is a directory');

**end**

**else**

**WriteLn** ( 'Error reading attributes of ', Name);

**end**;

**begin**

  testit ( 'ex40.pp');

---

```

testit ( ParamStr(0));
testit ( '. ');
testit ( '/ ');

```

**End.**

---

### 38.13.95 FileGetDate

**Synopsis:** Return the file time of an opened file.

**Declaration:** `function FileGetDate(Handle: THandle) : LongInt`

**Visibility:** default

**Description:** `FileGetdate` returns the filetype of the opened file with filehandle `Handle`. It is the same as `FileAge` ([1486](#)), with this difference that `FileAge` only needs the file name, while `FilegetDate` needs an open file handle.

**Errors:** On error, -1 is returned.

**See also:** `FileAge` ([1486](#))

**Listing:** `./sysutex/ex39.pp`

---

**Program** `Example39;`

*{ This program demonstrates the FileGetDate function }*

**Uses** `sysutils;`

**Var** `F,D : Longint;`

**Begin**

```

F:= FileCreate( 'test.dat' );
D:= FileGetDate(F);
WriteLn ( 'File created on ', DateTimeToStr( FileDateToDateTime(D)));
FileClose(F);
DeleteFile( 'test.dat' );

```

**End.**

---

### 38.13.96 FileIsReadOnly

**Synopsis:** Check whether a file is read-only.

**Declaration:** `function FileIsReadOnly(const FileName: String) : Boolean`

**Visibility:** default

**Description:** `FileIsReadOnly` checks whether `FileName` exists in the filesystem and is a read-only file. If this is the case, the function returns `True`, otherwise `False` is returned.

**See also:** `FileExists` ([1489](#))

### 38.13.97 FileOpen

Synopsis: Open an existing file and return a filehandle

Declaration: `function FileOpen(const FileName: String; Mode: Integer) : THandle`

Visibility: default

Description: `FileOpen` opens a file with name `FileName` with mode `Mode`. `Mode` can be one of the following constants:

**`fmOpenRead`**Open file in read-only mode

**`fmOpenWrite`**Open file in write-only mode

**`fmOpenReadWrite`**Open file in read/write mode.

Under Windows and Unix, the above mode can be or-ed with one of the following sharing/locking flags:

**`fmShareCompat`**Open file in DOS share-compatibility mode

**`fmShareExclusive`**Lock file for exclusive use

**`fmShareDenyWrite`**Lock file so other processes can only read.

**`fmShareDenyRead`**Lock file so other processes cannot read.

**`fmShareDenyNone`**Do not lock file.

If the file has been successfully opened, it can be read from or written to (depending on the `Mode` parameter) with the `FileRead` (1493) and `FileWrite` functions.

**Remark:** Remark that you cannot open a file if it doesn't exist yet, i.e. it will not be created for you. If you want to create a new file, or overwrite an old one, use the `FileCreate` (1487) function.

There are some limitations to the sharing modes.

- 1.Sharing modes are only available on Unix and Windows platforms.
- 2.Unix only support sharing modes as of 2.4.0.
- 3.`fmShareDenyRead` only works under Windows at this time, and will always result in an error on Unix platforms because its file locking APIs do not support this concept.
- 4.File locking is advisory on Unix platforms. This means that the locks are only checked when a file is opened using a file locking mode. In other cases, existing locks are simply ignored. In particular, this means that `fmShareDenyNone` has no effect under Unix, because this can only be implemented as "use no locking" on those platforms. As a result, opening a file using this mode will always succeed under Unix as far as the locking is concerned, even if the file has already been opened using `fmShareExclusive`.
- 5.Under Solaris, closing a single file handle associated with a file will result in all locks on that file (even via other handles) being destroyed due to the behaviour of the underlying API (`fcntl`). Because of the same reason, on Solaris you cannot use `fmShareDenyWrite` in combination with `fmOpenWrite`, nor `fmShareExclusive` in combination with `fmOpenRead` although both work with `fmOpenReadWrite`.

For an example, see `FileCreate` (1487)

Errors: On Error, -1 is returned.

See also: `fmOpenRead` (1431), `fmOpenWrite` (1431), `fmOpenReadWrite` (1431), `fmShareDenyWrite` (1432), `fmShareExclusive` (1432), `fmShareDenyRead` (1432), `fmShareDenyNone` (1431), `fmShareCompat` (1431), `FileClose` (1487), `FileWrite` (1495), `FileCreate` (1487), `FileRead` (1493), `FileTruncate` (1495), `FileSeek` (1494)

**38.13.98 FileRead**

Synopsis: Read data from a filehandle in a buffer.

Declaration: `function FileRead(Handle: THandle;out Buffer;Count: LongInt) : LongInt`

Visibility: default

Description: `FileRead` reads `Count` bytes from file-handle `Handle` and stores them into `Buffer`. `Buffer` must be at least `Count` bytes long. No checking on this is performed, so be careful not to overwrite any memory. `Handle` must be the result of a `FileOpen` (1492) call.

The function returns the number of bytes actually read, or -1 on error.

For an example, see `FileCreate` (1487)

Errors: On error, -1 is returned.

See also: `FileClose` (1487), `FileWrite` (1495), `FileCreate` (1487), `FileOpen` (1492), `FileTruncate` (1495), `FileSeek` (1494)

**38.13.99 FileSearch**

Synopsis: Search for a file in a path.

Declaration: `function FileSearch(const Name: String;const DirList: String; ImplicitCurrentDir: Boolean) : String`

Visibility: default

Description: `FileSearch` looks for the file `Name` in `DirList`, where `dirlist` is a list of directories, separated by semicolons or colons. It returns the full filename of the first match found.

Errors: On error, an empty string is returned.

See also: `ExpandFileName` (1483), `FindFirst` (1496)

**Listing:** `./sysutex/ex41.pp`

---

**Program** `Example41`;

*{ Program to demonstrate the FileSearch function. }*

**Uses** `Sysutils`;

**Const**

```
{ $ifdef unix }
  FN = 'find';
  P = './bin:/usr/bin';
{ $else }
  FN = 'find.exe';
  P = 'c:\dos;c:\windows;c:\windows\system;c:\windows\system32';
{ $endif }
```

**begin**

```
  WriteLn ('find is in : ',FileSearch (FN,P));
end.
```

---

**38.13.100 FileSeek**

Synopsis: Set the current file position on a file handle.

Declaration: `function FileSeek(Handle: THandle; FOffset: LongInt; Origin: LongInt) : LongInt`  
`function FileSeek(Handle: THandle; FOffset: Int64; Origin: LongInt) : Int64`

Visibility: default

Description: `FileSeek` sets the file pointer on position `Offset`, starting from `Origin`. `Origin` can be one of the following values:

**fsFromBeginning** `Offset` is relative to the first byte of the file. This position is zero-based. i.e. the first byte is at offset 0.

**fsFromCurrent** `Offset` is relative to the current position.

**fsFromEnd** `Offset` is relative to the end of the file. This means that `Offset` can only be zero or negative in this case.

If successful, the function returns the new file position, relative to the beginning of the file.

**Remark:** The abovementioned constants do not exist in Delphi.

Errors: On error, -1 is returned.

See also: `FileClose` ([1487](#)), `FileWrite` ([1495](#)), `FileCreate` ([1487](#)), `FileOpen` ([1492](#)), `FileRead` ([1493](#)), `FileTruncate` ([1495](#))

**Listing:** `./sysutex/ex42.pp`

**Program** `Example42;`

*{ This program demonstrates the FileSetAttr function }*

**Uses** `sysutils;`

**Begin**

`If FileSetAttr ('ex40.pp', faReadOnly or faHidden)=0 then`  
`Writeln ('Successfully made file hidden and read-only.')`  
`else`  
`Writeln ('Couldn't make file hidden and read-only.');`

**End.**

**38.13.101 FileSetAttr**

Synopsis: Set the attributes of a file.

Declaration: `function FileSetAttr(const Filename: String; Attr: LongInt) : LongInt`

Visibility: default

Description: `FileSetAttr` sets the attributes of `FileName` to `Attr`. If the function was successful, 0 is returned, -1 otherwise. `Attr` can be set to an OR-ed combination of the pre-defined `faXXX` constants.

This function is not implemented on Unixes.

Errors: On error, -1 is returned (always on Unixes).

See also: `FileGetAttr` ([1490](#)), `FileGetDate` ([1491](#)), `FileSetDate` ([1495](#))



**38.13.102 FileSetDate**

Synopsis: Set the date of a file.

Declaration: `function FileSetDate(Handle: THandle; Age: LongInt) : LongInt`  
`function FileSetDate(const FileName: String; Age: LongInt) : LongInt`

Visibility: default

Description: `FileSetDate` sets the file date of the open file with handle `Handle` or to `Age`, where `Age` is a DOS date-and-time stamp value.

Alternatively, the filename may be specified with the `FileName` argument. This variant of the call is mandatory on unices, since there is no OS support for setting a file timestamp based on a handle. (the handle may not be a real file at all).

The function returns zero if successful.

Errors: On Unix, the handle variant always returns -1, since this is impossible to implement. On Windows and DOS, a negative error code is returned.

**38.13.103 FileTruncate**

Synopsis: Truncate an open file to a given size.

Declaration: `function FileTruncate(Handle: THandle; Size: Int64) : Boolean`

Visibility: default

Description: `FileTruncate` truncates the file with handle `Handle` to `Size` bytes. The file must have been opened for writing prior to this call. The function returns `True` is successful, `False` otherwise.

For an example, see `FileCreate` (1487).

Errors: On error, the function returns `False`.

See also: `FileClose` (1487), `FileWrite` (1495), `FileCreate` (1487), `FileOpen` (1492), `FileRead` (1493), `FileSeek` (1494)

**38.13.104 FileWrite**

Synopsis: Write data from a buffer to a given filehandle.

Declaration: `function FileWrite(Handle: THandle; const Buffer; Count: LongInt)`  
`: LongInt`

Visibility: default

Description: `FileWrite` writes `Count` bytes from `Buffer` to the file with handle `Handle`. Prior to this call, the file must have been opened for writing. `Buffer` must be at least `Count` bytes large, or a memory access error may occur.

The function returns the number of bytes written, or -1 in case of an error.

For an example, see `FileCreate` (1487).

Errors: In case of error, -1 is returned.

See also: `FileClose` (1487), `FileCreate` (1487), `FileOpen` (1492), `FileRead` (1493), `FileTruncate` (1495), `FileSeek` (1494)

**38.13.105 FindClose**

Synopsis: Close a find handle

Declaration: `procedure FindClose(var F: TSearchRec)`

Visibility: default

Description: `FindClose` ends a series of `FindFirst` (1496)/`FindNext` (1497) calls, and frees any memory used by these calls. It is *absolutely* necessary to do this call, or huge memory losses may occur.

For an example, see `FindFirst` (1496).

Errors: None.

See also: `FindFirst` (1496), `FindNext` (1497)

**38.13.106 FindCmdLineSwitch**

Synopsis: Check whether a certain switch is present on the command-line.

Declaration: `function FindCmdLineSwitch(const Switch: String;  
                                  const Chars: TSysCharSet; IgnoreCase: Boolean)  
                                  : Boolean  
function FindCmdLineSwitch(const Switch: String; IgnoreCase: Boolean)  
                                  : Boolean  
function FindCmdLineSwitch(const Switch: String) : Boolean`

Visibility: default

Description: `FindCmdLineSwitch` will check all command-line arguments for the presence of the option `Switch`. It will return `True` if it was found, `False` otherwise. Characters that appear in `Chars` (default is `SwitchChars` (1435)) are assumed to indicate an option (switch). If the parameter `IgnoreCase` is `True`, case will be ignored when looking for the switch. Default is to search case sensitive.

Errors: None.

See also: `SwitchChars` (1435)

**38.13.107 FindFirst**

Synopsis: Start a file search and return a findhandle

Declaration: `function FindFirst(const Path: String; Attr: LongInt;  
                          out Rslt: TSearchRec) : LongInt`

Visibility: default

Description: `FindFirst` looks for files that match the name (possibly with wildcards) in `Path` and extra attributes `Attr`. It then fills up the `Rslt` record with data gathered about the file. It returns 0 if a file matching the specified criteria is found, a nonzero value (-1 on Unix-like platforms) otherwise.

`Attr` is an or-ed combination of the following constants:

**faReadOnly** The file is read-only.

**faHidden** The file is hidden. (On unix, this means that the filename starts with a dot)

**faSysFile** The file is a system file (On unix, this means that the file is a character, block or FIFO file).

**faVolumeId** Drive volume Label. Not possible under unix.

**faDirectory**File is a directory.

**faArchive**file is an archive. Not possible on Unix

It is a common misconception that `Attr` specifies a set of attributes which must be matched in order for a file to be included in the list. This is not so: The value of `Attr` specifies *additional* attributes, this means that the returned files are either normal files or have an attribute which is present in `Attr`.

Specifically: specifying `faDirectory` as a value for `Attr` does not mean that only directories will be returned. Normal files *and* directories will be returned.

The `Rslt` record can be fed to subsequent calls to `FindNext`, in order to find other files matching the specifications.

**Remark:** A `FindFirst` call must *always* be followed by a `FindClose` (1496) call with the same `Rslt` record. Failure to do so will result in memory loss.

Errors: On error the function returns -1 on Unix-like platforms, a nonzero error code on Windows.

See also: `FindClose` (1496), `FindNext` (1497)

**Listing:** ./sysutex/ex43.pp

**Program** Example43;

*{ This program demonstrates the FindFirst function }*

**Uses** SysUtils;

**Var** Info : TSearchRec;  
Count : Longint;

**Begin**

Count:=0;

**If** FindFirst ( '\*',faAnyFile **and** faDirectory ,Info)=0 **then**  
begin

Repeat

Inc(Count);

**With** Info **do**

begin

**If** (Attr **and** faDirectory) = faDirectory **then**

Write('Dir : ');

WriteLn (Name:40,Size:15);

end;

**Until** FindNext(info)<>0;

end;

FindClose(Info);

WriteLn ( 'Finished search. Found ',Count,' matches');

**End.**

### 38.13.108 FindNext

Synopsis: Find the next entry in a findhandle.

Declaration: function FindNext(var Rslt: TSearchRec) : LongInt

Visibility: default

**Description:** `FindNext` finds a next occurrence of a search sequence initiated by `FindFirst`. If another record matching the criteria in `Rslt` is found, 0 is returned, a nonzero constant is returned otherwise.

**Remark:** The last `FindNext` call must *always* be followed by a `FindClose` call with the same `Rslt` record. Failure to do so will result in memory loss.

For an example, see `FindFirst` (1496)

**Errors:** On error (no more file is found), a nonzero constant is returned.

See also: `FindFirst` (1496), `FindClose` (1496)

### 38.13.109 FloattoCurr

**Synopsis:** Convert a float to a Currency value.

**Declaration:** `function FloattoCurr(const Value: Extended) : Currency`

**Visibility:** default

**Description:** `FloatToCurr` converts the `Value` floating point value to a `Currency` value. It checks whether `Value` is in the valid range of currencies (determined by `MinCurrency` (1433) and `MaxCurrency` (1433)). If not, an `EConvertError` (1572) exception is raised.

**Errors:** If `Value` is out of range, an `EConvertError` (1572) exception is raised.

See also: `EConvertError` (1572), `TryFloatToCurr` (1563), `MinCurrency` (1433), `MaxCurrency` (1433)

### 38.13.110 FloatToDateTime

**Synopsis:** Convert a float to a TDateTime value.

**Declaration:** `function FloatToDateTime(const Value: Extended) : TDateTime`

**Visibility:** default

**Description:** `FloatToDateTime` converts the `Value` floating point value to a `TDateTime` value. It checks whether `Value` is in the valid range of dates (determined by `MinDateTime` (1433) and `MaxDateTime` (1433)). If not, an `EConvertError` (1572) exception is raised.

**Errors:** If `Value` is out of range, an `EConvertError` (1572) exception is raised.

See also: `EConvertError` (1572), `MinDateTime` (1433), `MaxDateTime` (1433)

### 38.13.111 FloatToDecimal

**Synopsis:** Convert a float value to a TFloatRec value.

**Declaration:**

```

procedure FloatToDecimal(out Result: TFloatRec; const Value;
                        ValueType: TFloatValue; Precision: Integer;
                        Decimals: Integer)
procedure FloatToDecimal(out Result: TFloatRec; Value: Extended;
                        Precision: Integer; Decimals: Integer)

```

**Visibility:** default

**Description:** `FloatToDecimal` converts the float `Value` to a float description in the `Result.TFloatRec` (1439) format. It will store `Precision` digits in the `Digits` field, of which at most `Decimal` decimals.

Errors: None.

See also: TFloatRec ([1439](#))

### 38.13.112 FloatToStr

Synopsis: Convert a float value to a string using a fixed format.

**Declaration:**

```
function FloatToStr(Value: Double) : String
function FloatToStr(Value: Double;const FormatSettings: TFormatSettings)
    : String
function FloatToStr(Value: Single) : String
function FloatToStr(Value: Single;const FormatSettings: TFormatSettings)
    : String
function FloatToStr(Value: Currency) : String
function FloatToStr(Value: Currency;
    const FormatSettings: TFormatSettings) : String
function FloatToStr(Value: Comp) : String
function FloatToStr(Value: Comp;const FormatSettings: TFormatSettings)
    : String
function FloatToStr(Value: Int64) : String
function FloatToStr(Value: Int64;const FormatSettings: TFormatSettings)
    : String
```

Visibility: default

**Description:** FloatToStr converts the floating point variable Value to a string representation. It will choose the shortest possible notation of the two following formats:

**Fixed format** will represent the string in fixed notation,

**Decimal format** will represent the string in scientific notation.

More information on these formats can be found in FloatToStrF ([1500](#)). FloatToStr is completely equivalent to the following call:

```
FloatToStrF(Value, ffGeneral, 15, 0);
```

Errors: None.

See also: FloatToStrF ([1500](#)), FormatFloat ([1511](#)), StrToFloat ([1551](#))

**Listing:** ./sysutex/ex67.pp

---

**Program** Example67;

```
{ This program demonstrates the FloatToStr function }
```

**Uses** sysutils;

**Procedure** Testit (Value : Extended);

**begin**

```
    WriteLn (Value, ' -> ', FloatToStr (Value));
```

```
    WriteLn (-Value, ' -> ', FloatToStr (-Value));
```

**end**;

```

Begin
  Testit (0.0);
  Testit (1.1);
  Testit (1.1e-3);
                                Testit (1.1e-20);
  Testit (1.1e-200);
  Testit (1.1e+3);
  Testit (1.1e+20);
  Testit (1.1e+200);
End.

```

---

### 38.13.113 FloatToStrF

**Synopsis:** Convert a float value to a string using a given format.

**Declaration:**

```

function FloatToStrF(Value: Double;format: TFloatFormat;
                    Precision: Integer;Digits: Integer) : String
function FloatToStrF(Value: Double;format: TFloatFormat;
                    Precision: Integer;Digits: Integer;
                    const FormatSettings: TFormatSettings) : String
function FloatToStrF(Value: Single;format: TFloatFormat;
                    Precision: Integer;Digits: Integer) : String
function FloatToStrF(Value: Single;format: TFloatFormat;
                    Precision: Integer;Digits: Integer;
                    const FormatSettings: TFormatSettings) : String
function FloatToStrF(Value: Comp;format: TFloatFormat;
                    Precision: Integer;Digits: Integer) : String
function FloatToStrF(Value: Comp;format: TFloatFormat;
                    Precision: Integer;Digits: Integer;
                    const FormatSettings: TFormatSettings) : String
function FloatToStrF(Value: Currency;format: TFloatFormat;
                    Precision: Integer;Digits: Integer) : String
function FloatToStrF(Value: Currency;format: TFloatFormat;
                    Precision: Integer;Digits: Integer;
                    const FormatSettings: TFormatSettings) : String
function FloatToStrF(Value: Int64;format: TFloatFormat;
                    Precision: Integer;Digits: Integer) : String
function FloatToStrF(Value: Int64;format: TFloatFormat;
                    Precision: Integer;Digits: Integer;
                    const FormatSettings: TFormatSettings) : String

```

**Visibility:** default

**Description:** FloatToStrF converts the floating point number value to a string representation, according to the settings of the parameters Format, Precision and Digits.

The meaning of the Precision and Digits parameter depends on the Format parameter. The format is controlled mainly by the Format parameter. It can have one of the following values:

**ffcurrencyMoney** format. Value is converted to a string using the global variables CurrencyString, CurrencyFormat and NegCurrFormat. The Digits paramater specifies the number of digits following the decimal point and should be in the range -1 to 18. If Digits equals -1, CurrencyDecimals is assumed. The Precision parameter is ignored.

**ffExponentScientific** format. Value is converted to a string using scientific notation: 1 digit before the decimal point, possibly preceded by a minus sign if Value is negative. The number of digits after the decimal point is controlled by Precision and must lie in the range 0 to 15.

**ffFixed**Fixed point format. Value is converted to a string using fixed point notation. The result is composed of all digits of the integer part of Value, preceded by a minus sign if Value is negative. Following the integer part is DecimalSeparator and then the fractional part of Value, rounded off to Digits numbers. If the number is too large then the result will be in scientific notation.

**ffGeneral**General number format. The argument is converted to a string using ffExponent or ffFixed format, depending on which one gives the shortest string. There will be no trailing zeroes. If Value is less than 0.00001 or if the number of decimals left of the decimal point is larger than Precision then scientific notation is used, and Digits is the minimum number of digits in the exponent. Otherwise Digits is ignored.

**ffnumber**Is the same as ffFixed, except that thousand separators are inserted in the resulting string.

Errors: None.

See also: FloatToStr ([1499](#)), FloatToText ([1502](#))

**Listing:** ./sysutex/ex68.pp

**Program** Example68;

*{ This program demonstrates the FloatToStrF function }*

**Uses** sysutils;

**Const** Fmt : **Array** [TFloatFormat] **of** **string**[10] =  
           ('general', 'exponent', 'fixed', 'number', 'Currency');

**Procedure** Testit (Value : Extended);

**Var** I, J : longint;  
       FF : TFloatFormat;

**begin**

**For** I:=5 **to** 15 **do**

**For** J:=1 **to** 4 **do**

**For** FF:=ffgeneral **to** ffcurrency **do**

**begin**

**Write** (Value, '(Prec: ', I:2, ', Dig: ', J, ', fmt: ', Fmt[ff], ') : ');

**Writeln** (FloatToStrF(Value, FF, I, J));

**Write** (-Value, '(Prec: ', I:2, ', Dig: ', J, ', fmt: ', Fmt[ff], ') : ');

**Writeln** (FloatToStrF(-Value, FF, I, J));

**end**;

**end**;

**Begin**

  Testit (1.1);

  Testit (1.1E1);

  Testit (1.1E-1);

  Testit (1.1E5);

  Testit (1.1E-5);

  Testit (1.1E10);

  Testit (1.1E-10);

  Testit (1.1E15);

  Testit (1.1E-15);

  Testit (1.1E100);

  Testit (1.1E-100);

**End.**

**38.13.114 FloatToText**

Synopsis: Return a string representation of a float, with a given format.

Declaration: `function FloatToText (Buffer: PChar; Value: Extended; format: TFloatFormat;  
Precision: Integer; Digits: Integer) : LongInt  
function FloatToText (Buffer: PChar; Value: Extended; format: TFloatFormat;  
Precision: Integer; Digits: Integer;  
const FormatSettings: TFormatSettings) : LongInt`

Visibility: default

Description: `FloatToText` converts the floating point variable `Value` to a string representation and stores it in `Buffer`. The conversion is governed by `format`, `Precision` and `Digits`. more information on these parameters can be found in `FloatToStrF` (1500). `Buffer` should point to enough space to hold the result. No checking on this is performed.

The result is the number of characters that was copied in `Buffer`.

Errors: None.

See also: `FloatToStr` (1499), `FloatToStrF` (1500)

**Listing:** ./sysutex/ex69.pp

---

**Program** Example68;

*{ This program demonstrates the FloatToStrF function }*

**Uses** sysutils;

**Const** Fmt : **Array** [TFloatFormat] **of** **string**[10] =  
( 'general', 'exponent', 'fixed', 'number', 'Currency' );

**Procedure** Testit ( Value : Extended );

**Var** I, J : longint;  
FF : TFloatFormat;  
S : ShortString;

**begin**

For I:=5 to 15 do

For J:=1 to 4 do

For FF:=ffgeneral to ffcurrency do

**begin**

**Write** ( Value, '(Prec: ', I:2, ', Dig: ', J, ', fmt : ', Fmt[ff], ') : ' );

SetLength(S, **FloatToText** (@S[1], Value, FF, I, J));

**WriteLn** (S);

**Write** ( -Value, '(Prec: ', I:2, ', Dig: ', J, ', fmt : ', Fmt[ff], ') : ' );

SetLength(S, **FloatToText** (@S[1], -Value, FF, I, J));

**WriteLn** (S);

**end**;

**end**;

**Begin**

Testit (1.1);

Testit (1.1E1);

Testit (1.1E-1);

Testit (1.1E5);

Testit (1.1E-5);



---

```

Testit (1.1E10);
Testit (1.1E-10);
Testit (1.1E15);
Testit (1.1E-15);
Testit (1.1E100);
Testit (1.1E-100);
End.

```

---

### 38.13.115 FloatToTextFmt

**Synopsis:** Convert a float value to a string using a given mask.

**Declaration:** `function FloatToTextFmt(Buffer: PChar; Value: Extended; format: PChar; FormatSettings: TFormatSettings) : Integer`  
`function FloatToTextFmt(Buffer: PChar; Value: Extended; format: PChar) : Integer`

**Visibility:** default

**Description:** `FloatToTextFmt` returns a textual representation of `Value` in the memory location pointed to by `Buffer`. it uses the formatting specification in `Format` to do this. The return value is the number of characters that were written in the buffer.

For a list of valid formatting characters, see `FormatFloat` ([1511](#))

**Errors:** No length checking is performed on the buffer. The buffer should point to enough memory to hold the complete string. If this is not the case, an access violation may occur.

See also: `FormatFloat` ([1511](#))

### 38.13.116 FmtStr

**Synopsis:** Format a string with given arguments.

**Declaration:** `procedure FmtStr(var Res: String; const Fmt: String; const args: Array of const)`  
`procedure FmtStr(var Res: String; const Fmt: String; const args: Array of const; const FormatSettings: TFormatSettings)`

**Visibility:** default

**Description:** `FmtStr` calls `Format` ([1504](#)) with `Fmt` and `Args` as arguments, and stores the result in `Res`. For more information on how the resulting string is composed, see `Format` ([1504](#)).

**Errors:** In case of error, a `EConvertError` exception is raised.

See also: `Format` ([1504](#)), `FormatBuf` ([1509](#))

**Listing:** `./sysutex/ex70.pp`

---

**Program** `Example70`;

*{ This program demonstrates the FmtStr function }*

**Uses** `sysutils`;

---

```
Var S : AnsiString;
```

```
Begin
```

```
  S:= '';
```

```
                                FmtStr (S, 'For some nice examples of fomatting see %s.', [ 'Format' ]
```

```
                                WriteLn (S);
```

```
End.
```

---

### 38.13.117 ForceDirectories

Synopsis: Create a chain of directories

Declaration: `function ForceDirectories(const Dir: String) : Boolean`

Visibility: default

Description: `ForceDirectories` tries to create any missing directories in `Dir` till the whole path in `Dir` exists. It returns `True` if `Dir` already existed or was created succesfully. If it failed to create any of the parts, `False` is returned.

### 38.13.118 Format

Synopsis: Format a string with given arguments.

Declaration: `function Format(const Fmt: String; const Args: Array of const) : String`  
`function Format(const Fmt: String; const Args: Array of const;`  
`const FormatSettings: TFormatSettings) : String`

Visibility: default

Description: `Format` replaces all placeholders in `Fmt` with the arguments passed in `Args` and returns the resulting string. A placeholder looks as follows:

```
'%' [[Index] ':' ] ['-' ] [Width] ['.' Precision] ArgType
```

elements between single quotes must be typed as shown without the quotes, and elements between square brackets [ ] are optional. The meaning of the different elements is shown below:

'%' starts the placeholder. If you want to insert a literal % character, then you must insert two of them : %%.

**Index** ':' takes the `Index`-th element in the argument array as the element to insert. If `index` is omitted, then the zeroth argument is taken.

'-' tells `Format` to left-align the inserted text. The default behaviour is to right-align inserted text. This can only take effect if the `Width` element is also specified.

**Width** the inserted string must have at least have `Width` characters. If not, the inserted string will be padded with spaces. By default, the string is left-padded, resulting in a right-aligned string. This behaviour can be changed by the '-' character.

'.' **Precision** Indicates the precision to be used when converting the argument. The exact meaning of this parameter depends on `ArgType`.

The `Index`, `Width` and `Precision` parameters can be replaced by `*`, in which case their value will be read from the next element in the `Args` array. This value must be an integer, or an `EConvertError` exception will be raised.

The argument type is determined from `ArgType`. It can have one of the following values (case insensitive):

**D**Decimal format. The next argument in the `Args` array should be an integer. The argument is converted to a decimal string. If precision is specified, then the string will have at least `Precision` digits in it. If needed, the string is (left) padded with zeroes.

**E**Scientific format. The next argument in the `Args` array should be a Floating point value. The argument is converted to a decimal string using scientific notation, using `FloatToStrF` (1500), where the optional precision is used to specify the total number of decimals. (default a value of 15 is used). The exponent is formatted using maximally 3 digits.

In short, the `E` specifier formats it's argument as follows:

```
FloatToStrF (Argument, ffExponent, Precision, 3)
```

**F**Fixed point format. The next argument in the `Args` array should be a floating point value. The argument is converted to a decimal string, using fixed notation (see `FloatToStrF` (1500)). `Precision` indicates the number of digits following the decimal point.

In short, the `F` specifier formats it's argument as follows:

```
FloatToStrF (Argument, ffFixed, fFixed, 9999, Precision)
```

**G**General number format. The next argument in the `Args` array should be a floating point value. The argument is converted to a decimal string using fixed point notation or scientific notation, depending on which gives the shortest result. `Precision` is used to determine the number of digits after the decimal point.

In short, the `G` specifier formats it's argument as follows:

```
FloatToStrF (Argument, ffGeneral, Precision, 3)
```

**M**Currency format. the next argument in the `var{Args}` array must be a floating point value. The argument is converted to a decimal string using currency notation. This means that fixed-point notation is used, but that the currency symbol is appended. If precision is specified, then then it overrides the `CurrencyDecimals` global variable used in the `FloatToStrF` (1500)

In short, the `M` specifier formats it's argument as follows:

```
FloatToStrF (Argument, ffCurrency, 9999, Precision)
```

**N**Number format. This is the same as fixed point format, except that thousand separators are inserted in the resulting string.

**P**Pointer format. The next argument in the `Args` array must be a pointer (typed or untyped). The pointer value is converted to a string of length 8, representing the hexadecimal value of the pointer.

**S**String format. The next argument in the `Args` array must be a string. The argument is simply copied to the result string. If `Precision` is specified, then only `Precision` characters are copied to the result string.

**U**Unsigned decimal format. The next argument in the `Args` array should be an unsigned integer. The argument is converted to a decimal string. If precision is specified, then the string will have at least `Precision` digits in it. If needed, the string is (left) padded with zeroes.

**X**hexadecimal format. The next argument in the `Args` array must be an integer. The argument is converted to a hexadecimal string with just enough characters to contain the value of the integer. If `Precision` is specified then the resulting hexadecimal representation will have at least `Precision` characters in it (with a maximum value of 32).

**Errors:** In case of error, an `EConversionError` exception is raised. Possible errors are:

- 1.Errors in the format specifiers.
- 2.The next argument is not of the type needed by a specifier.

3.The number of arguments is not sufficient for all format specifiers.

See also: `FormatBuf` ([1509](#))

**Listing:** `./sysutex/ex71.pp`

**Program** `example71;`

`{ $mode objfpc }`

`{ This program demonstrates the Format function }`

**Uses** `sysutils;`

**Var** `P : Pointer;`  
`fmt,S : string;`

**Procedure** `TestInteger;`

**begin**

**Try**

`Fmt:= '%d' ;S:=Format (Fmt,[10]);writeln (Fmt:12,' => ',s);`  
`Fmt:= ' [%%]' ;S:=Format (Fmt,[10]);writeln (Fmt:12,' => ',s);`  
`Fmt:= '%10d' ;S:=Format (Fmt,[10]);writeln (Fmt:12,' => ',s);`  
`fmt:= '%.4d' ;S:=Format (fmt,[10]);writeln (Fmt:12,' => ',s);`  
`Fmt:= '%10.4d' ;S:=Format (Fmt,[10]);writeln (Fmt:12,' => ',s);`  
`Fmt:= '%0:d' ;S:=Format (Fmt,[10]);writeln (Fmt:12,' => ',s);`  
`Fmt:= '%0:10d' ;S:=Format (Fmt,[10]);writeln (Fmt:12,' => ',s);`  
`Fmt:= '%0:10.4d' ;S:=Format (Fmt,[10]);writeln (Fmt:12,' => ',s);`  
`Fmt:= '%0:-10d' ;S:=Format (Fmt,[10]);writeln (Fmt:12,' => ',s);`  
`Fmt:= '%0:-10.4d' ;S:=Format (fmt,[10]);writeln (Fmt:12,' => ',s);`  
`Fmt:= '%[-*.d]' ;S:=Format (fmt,[4,5,10]);writeln (Fmt:12,' => ',s);`

**except**

**On** `E : Exception do`

**begin**

`WriteLn ( 'Exception caught : ',E.Message);`

**end;**

**end;**

`writeln ( 'Press enter ');`

`readln;`

**end;**

**Procedure** `TestHexadecimal;`

**begin**

**try**

`Fmt:= '%x' ;S:=Format (Fmt,[10]);writeln (Fmt:12,' => ',s);`  
`Fmt:= '%10x' ;S:=Format (Fmt,[10]);writeln (Fmt:12,' => ',s);`  
`Fmt:= '%10.4x' ;S:=Format (Fmt,[10]);writeln (Fmt:12,' => ',s);`  
`Fmt:= '%0:x' ;S:=Format (Fmt,[10]);writeln (Fmt:12,' => ',s);`  
`Fmt:= '%0:10x' ;S:=Format (Fmt,[10]);writeln (Fmt:12,' => ',s);`  
`Fmt:= '%0:10.4x' ;S:=Format (Fmt,[10]);writeln (Fmt:12,' => ',s);`  
`Fmt:= '%0:-10x' ;S:=Format (Fmt,[10]);writeln (Fmt:12,' => ',s);`  
`Fmt:= '%0:-10.4x' ;S:=Format (fmt,[10]);writeln (Fmt:12,' => ',s);`  
`Fmt:= '%[-*.x]' ;S:=Format (fmt,[4,5,10]);writeln (Fmt:12,' => ',s);`

**except**

**On** `E : Exception do`

**begin**

`WriteLn ( 'Exception caught : ',E.Message);`

```

        end;

        writeln ( 'Press enter' );
        readln;
    end;

Procedure TestPointer;

begin
    P:= Pointer(1234567);
    try
        Fmt:= '[0x%p]'; S:= Format ( Fmt,[P]); writeln (Fmt:12, ' => ',s);
        Fmt:= '[0x%10p]'; S:= Format ( Fmt,[P]); writeln (Fmt:12, ' => ',s);
        Fmt:= '[0x%10.4p]'; S:= Format ( Fmt,[P]); writeln (Fmt:12, ' => ',s);
        Fmt:= '[0x%0:p]'; S:= Format ( Fmt,[P]); writeln (Fmt:12, ' => ',s);
        Fmt:= '[0x%0:10p]'; S:= Format ( Fmt,[P]); writeln (Fmt:12, ' => ',s);
        Fmt:= '[0x%0:10.4p]'; S:= Format ( Fmt,[P]); writeln (Fmt:12, ' => ',s);
        Fmt:= '[0x%0:-10p]'; S:= Format ( Fmt,[P]); writeln (Fmt:12, ' => ',s);
        Fmt:= '[0x%0:-10.4p]'; S:= Format ( fmt,[P]); writeln (Fmt:12, ' => ',s);
        Fmt:= '[%-*.p]'; S:= Format ( fmt,[4,5,P]); writeln (Fmt:12, ' => ',s);
    except
        On E : Exception do
            begin
                Writeln ( 'Exception caught : ',E.Message);
            end;
    end;
    writeln ( 'Press enter' );
    readln;
end;

Procedure TestString;

begin
    try
        Fmt:= '[%s]'; S:= Format(fmt,[ 'This is a string' ]); Writeln(fmt:12, '=> ',s);
        fmt:= '[%0:s]'; s:= Format(fmt,[ 'This is a string' ]); Writeln(fmt:12, '=> ',s);
        fmt:= '[%0:18s]'; s:= Format(fmt,[ 'This is a string' ]); Writeln(fmt:12, '=> ',s);
        fmt:= '[%0:-18s]'; s:= Format(fmt,[ 'This is a string' ]); Writeln(fmt:12, '=> ',s);
        fmt:= '[%0:18.12s]'; s:= Format(fmt,[ 'This is a string' ]); Writeln(fmt:12, '=> ',s);
        fmt:= '[%-*.s]'; s:= Format(fmt,[18,12, 'This is a string' ]); Writeln(fmt:12, '=> ',s);
    except
        On E : Exception do
            begin
                Writeln ( 'Exception caught : ',E.Message);
            end;
    end;
    writeln ( 'Press enter' );
    readln;
end;

Procedure TestExponential;

begin
    Try
        Fmt:= '[%e]'; S:= Format ( Fmt,[1.234]); writeln (Fmt:12, ' => ',s);
        Fmt:= '[%10e]'; S:= Format ( Fmt,[1.234]); writeln (Fmt:12, ' => ',s);
        Fmt:= '[%10.4e]'; S:= Format ( Fmt,[1.234]); writeln (Fmt:12, ' => ',s);
        Fmt:= '[%0:e]'; S:= Format ( Fmt,[1.234]); writeln (Fmt:12, ' => ',s);

```

```

Fmt:= '%0:10e';S:=Format (Fmt,[1.234]);writeln (Fmt:12,' => ',s);
Fmt:= '%0:10.4e';S:=Format (Fmt,[1.234]);writeln (Fmt:12,' => ',s);
Fmt:= '%0:-10e';S:=Format (Fmt,[1.234]);writeln (Fmt:12,' => ',s);
Fmt:= '%0:-10.4e';S:=Format (Fmt,[1.234]);writeln (Fmt:12,' => ',s);
Fmt:= '%-*.e';S:=Format (Fmt,[4,5,1.234]);writeln (Fmt:12,' => ',s);
except
  On E : Exception do
    begin
      writeln ('Exception caught : ',E.Message);
    end;
end;
writeln ('Press enter');
readln;
end;

```

**Procedure** TestNegativeExponential;

```

begin
  Try
    Fmt:= '%e';S:=Format (Fmt,[-1.234]);writeln (Fmt:12,' => ',s);
    Fmt:= '%10e';S:=Format (Fmt,[-1.234]);writeln (Fmt:12,' => ',s);
    Fmt:= '%10.4e';S:=Format (Fmt,[-1.234]);writeln (Fmt:12,' => ',s);
    Fmt:= '%0:e';S:=Format (Fmt,[-1.234]);writeln (Fmt:12,' => ',s);
    Fmt:= '%0:10e';S:=Format (Fmt,[-1.234]);writeln (Fmt:12,' => ',s);
    Fmt:= '%0:10.4e';S:=Format (Fmt,[-1.234]);writeln (Fmt:12,' => ',s);
    Fmt:= '%0:-10e';S:=Format (Fmt,[-1.234]);writeln (Fmt:12,' => ',s);
    Fmt:= '%0:-10.4e';S:=Format (Fmt,[-1.234]);writeln (Fmt:12,' => ',s);
    Fmt:= '%-*.e';S:=Format (Fmt,[4,5,-1.234]);writeln (Fmt:12,' => ',s);
  except
    On E : Exception do
      begin
        writeln ('Exception caught : ',E.Message);
      end;
    end;
  end;
  writeln ('Press enter');
  readln;
end;

```

**Procedure** TestSmallExponential;

```

begin
  Try
    Fmt:= '%e';S:=Format (Fmt,[0.01234]);writeln (Fmt:12,' => ',s);
    Fmt:= '%10e';S:=Format (Fmt,[0.01234]);writeln (Fmt:12,' => ',s);
    Fmt:= '%10.4e';S:=Format (Fmt,[0.01234]);writeln (Fmt:12,' => ',s);
    Fmt:= '%0:e';S:=Format (Fmt,[0.01234]);writeln (Fmt:12,' => ',s);
    Fmt:= '%0:10e';S:=Format (Fmt,[0.01234]);writeln (Fmt:12,' => ',s);
    Fmt:= '%0:10.4e';S:=Format (Fmt,[0.01234]);writeln (Fmt:12,' => ',s);
    Fmt:= '%0:-10e';S:=Format (Fmt,[0.0123]);writeln (Fmt:12,' => ',s);
    Fmt:= '%0:-10.4e';S:=Format (Fmt,[0.01234]);writeln (Fmt:12,' => ',s);
    Fmt:= '%-*.e';S:=Format (Fmt,[4,5,0.01234]);writeln (Fmt:12,' => ',s);
  except
    On E : Exception do
      begin
        writeln ('Exception caught : ',E.Message);
      end;
    end;
  end;
  writeln ('Press enter');
end;

```

```

    readln;

                                end;

Procedure TestSmallNegExponential;

begin
    Try
        Fmt:= '[%e]'; S:=Format (Fmt,[ -0.01234]); writeln (Fmt:12, ' => ',s);
        Fmt:= '[%10e]'; S:=Format (Fmt,[ -0.01234]); writeln (Fmt:12, ' => ',s);
        Fmt:= '[%10.4e]'; S:=Format (Fmt,[ -0.01234]); writeln (Fmt:12, ' => ',s);
        Fmt:= '[%0:e]'; S:=Format (Fmt,[ -0.01234]); writeln (Fmt:12, ' => ',s);
        Fmt:= '[%0:10e]'; S:=Format (Fmt,[ -0.01234]); writeln (Fmt:12, ' => ',s);
        Fmt:= '[%0:10.4e]'; S:=Format (Fmt,[ -0.01234]); writeln (Fmt:12, ' => ',s);
        Fmt:= '[%0:-10e]'; S:=Format (Fmt,[ -0.01234]); writeln (Fmt:12, ' => ',s);
        Fmt:= '[%0:-10.4e]'; S:=Format (Fmt,[ -0.01234]); writeln (Fmt:12, ' => ',s);
        Fmt:= '[%-*.e]'; S:=Format (Fmt,[4,5, -0.01234]); writeln (Fmt:12, ' => ',s);
    except
        On E : Exception do
            begin
                Writeln ( 'Exception caught : ',E.Message);
            end;
        end;
        writeln ( 'Press enter ');
        readln;
    end;

    begin
        TestInteger;
        TestHexadecimal;
        TestPointer;
        TestExponential;
        TestNegativeExponential;
        TestSmallExponential;
        TestSmallNegExponential;
        teststring;
    end.

```

---

### 38.13.119 FormatBuf

**Synopsis:** Format a string with given arguments and store the result in a buffer.

**Declaration:**

```

function FormatBuf(var Buffer;BufLen: Cardinal;const Fmt;
                  fmtLen: Cardinal;const Args: Array of const)
                  : Cardinal
function FormatBuf(var Buffer;BufLen: Cardinal;const Fmt;
                  fmtLen: Cardinal;const Args: Array of const;
                  const FormatSettings: TFormatSettings) : Cardinal

```

**Visibility:** default

**Description:** FormatBuf calls Format (1504) and stores the result in Buf.

See also: Format (1504)

**Listing:** ./sysutex/ex72.pp

**Program** Example72;

---

```

{ This program demonstrates the FormatBuf function }

Uses sysutils;

Var
  S : ShortString;

Const
  Fmt : ShortString = 'For some nice examples of fomatting see %s.';

Begin
  S:= '';
  SetLength(S, FormatBuf (S[1], 255, Fmt[1], Length(Fmt), [ 'Format' ]));
  WriteLn (S);
End.

```

---

### 38.13.120 FormatCurr

Synopsis: Format a currency

**Declaration:** `function FormatCurr(const Format: String; Value: Currency) : String`  
`function FormatCurr(const Format: String; Value: Currency;`  
`const FormatSettings: TFormatSettings) : String`

Visibility: default

**Description:** `FormatCurr` formats the currency `Value` according to the formatting rule in `Format`, and returns the resulting string.

For an explanation of the formatting characters, see `FormatFloat` (1511).

See also: `FormatFloat` (1511), `FloatToText` (1502)

### 38.13.121 FormatDateTime

Synopsis: Return a string representation of a `TDateTime` value with a given format.

**Declaration:** `function FormatDateTime(const FormatStr: String; DateTime: TDateTime)`  
`: String`  
`function FormatDateTime(const FormatStr: String; DateTime: TDateTime;`  
`const FormatSettings: TFormatSettings) : String`

Visibility: default

**Description:** `FormatDateTime` formats the date and time encoded in `DateTime` according to the formatting given in `FormatStr`. The complete list of formatting characters can be found in `formatchars` (1429).

**Errors:** On error (such as an invalid character in the formatting string), and `EConvertError` exception is raised.

See also: `DateTimeToStr` (1471), `DateToStr` (1473), `TimeToStr` (1560), `StrToDateTime` (1549)

**Listing:** `./sysutex/ex14.pp`



---

```

Program Example14;

{ This program demonstrates the FormatDateTime function }

Uses sysutils;

Var ThisMoment : TDateTime;

Begin
  ThisMoment:=Now;
  WriteLn ( 'Now : ',FormatDateTime( 'hh:nn ',ThisMoment));
  WriteLn ( 'Now : ',FormatDateTime( 'DD MM YYYY',ThisMoment));
  WriteLn ( 'Now : ',FormatDateTime( 'c',ThisMoment));
End.

```

---

### 38.13.122 FormatFloat

**Synopsis:** Format a float according to a certain mask.

**Declaration:** `function FormatFloat(const Format: String;Value: Extended) : String`  
`function FormatFloat(const Format: String;Value: Extended;`  
`const FormatSettings: TFormatSettings) : String`

**Visibility:** default

**Description:** `FormatFloat` formats the floating-point value given by `Value` using the format specifications in `Format`. The format specifier can give format specifications for positive, negative or zero values (separated by a semicolon).

If the format specifier is empty or the value needs more than 18 digits to be correctly represented, the result is formatted with a call to `FloatToStrF` (1500) with the `ffGeneral` format option.

The following format specifiers are supported:

**0** is a digit place holder. If there is a corresponding digit in the value being formatted, then it replaces the 0. If not, the 0 is left as-is.

**#** is also a digit place holder. If there is a corresponding digit in the value being formatted, then it replaces the #. If not, it is removed. by a space.

**.** determines the location of the decimal point. Only the first '.' character is taken into account. If the value contains digits after the decimal point, then it is replaced by the value of the `DecimalSeparator` character.

**,** determines the use of the thousand separator character in the output string. If the format string contains one or more ',' characters, then thousand separators will be used. The `ThousandSeparator` character is used.

**E+** determines the use of scientific notation. If 'E+' or 'E-' (or their lowercase counterparts) are present then scientific notation is used. The number of digits in the output string is determined by the number of 0 characters after the 'E+'

**;** This character separates sections for positive, negative, and zero numbers in the format string.

**Errors:** If an error occurs, an exception is raised.

**See also:** `FloatToStr` (1499)

**Listing:** `./sysutex/ex89.pp`

---

**Program** Example89;

*{ This program demonstrates the FormatFloat function }*

**Uses** sysutils;

**Const**

```
NrFormat=9;
FormatStrings : Array[1..NrFormat] of string = (
  ' ',
  '0',
  '0.00',
  '###',
  '##0.00',
  '##0.00;(#,##0.00)',
  '##0.00;;Zero',
  '0.000E+00',
  '###E-0');
```

```
NrValue = 5;
```

```
FormatValues : Array[1..NrValue] of Double =
  (1234, -1234, 0.5, 0, -0.5);
```

```
Width = 12;
```

```
FWidth = 20;
```

**Var**

```
I, J : Integer;
```

```
S : String;
```

**begin**

```
Write('Format':FWidth);
```

```
For I:=1 to NrValue do
```

```
  Write(FormatValues[I]:Width:2);
```

```
WriteLn;
```

```
For I:=1 to NrFormat do
```

```
  begin
```

```
    Write(FormatStrings[I]:FWidth);
```

```
    For J:=1 to NrValue do
```

```
      begin
```

```
        S:=FormatFloat(FormatStrings[I],FormatValues[J]);
```

```
        Write(S:Width);
```

```
      end;
```

```
    WriteLn;
```

```
  end;
```

**End.**

---

### 38.13.123 FreeAndNil

Synopsis: Free object if needed, and set object reference to Nil

Declaration: procedure FreeAndNil(var obj)

Visibility: default

Description: FreeAndNil will free the object in Obj and will set the reference in Obj to Nil. The reference is set to Nil first, so if an exception occurs in the destructor of the object, the reference will be Nil anyway.

Errors: Exceptions that occur during the destruction of `Obj` are not caught.

### 38.13.124 `GetAppConfigDir`

Synopsis: Return the appropriate directory for the application's configuration files.

Declaration: `function GetAppConfigDir(Global: Boolean) : String`

Visibility: default

Description: `GetAppConfigDir` returns the name of a directory in which the application should store its configuration files on the current OS. If the parameter `Global` is `True` then the directory returned is a global directory, i.e. valid for all users on the system. If the parameter `Global` is false, then the directory is specific for the user who is executing the program. On systems that do not support multi-user environments, these two directories may be the same.

The directory which is returned is the name of the directory where the application is supposed to store files. This does not mean that the directory exists, or that the user can write in this directory (especially if `Global=True`). It just returns the name of the appropriate location. Also note that the returned name does not contain a ending path delimiter.

On systems where the operating system provides a call to determine this location, this call will be used. On systems where there is no such call, an algorithm is used which reflects common practice on that system.

The application name is deduced from the binary name via the `ApplicationName` (1461) call, but can be configured by means of the `OnGetApplicationName` (1444) callback.

Errors: None.

See also: `GetAppConfigFile` (1513), `ApplicationName` (1461), `OnGetApplicationName` (1444), `CreateDir` (1468), `SysConfigDir` (1436)

### 38.13.125 `GetAppConfigFile`

Synopsis: Return an appropriate name for an application configuration file.

Declaration: `function GetAppConfigFile(Global: Boolean) : String`

`function GetAppConfigFile(Global: Boolean;SubDir: Boolean) : String`

Visibility: default

Description: `GetAppConfigFile` returns the name of a file in which the application can store its configuration parameters. The `Global` parameter determines whether it is a global configuration file (value `True`) or a personal configuration file (value `False`). The parameter `SubDir`, in case it is set to `True`, will insert the name of a directory before the filename. This can be used in case the application needs to store other data than configuration data in an application-specific directory. Default behaviour is to set this to `False`. The default file extension of the returned file is: `.cfg`

No assumptions should be made about the existence or writeability of this file, or the directory where the file should reside.

On systems where the operating system provides a call to determine the location of configuration files, this call will be used. On systems where there is no such call, an algorithm is used which reflects common practice on that system.

The application name is deduced from the binary name via the `ApplicationName` (1461) call, but can be configured by means of the `OnGetApplicationName` (1444) callback.

Errors: None.

See also: [GetAppConfigDir \(1513\)](#), [OnGetApplicationName \(1444\)](#), [ApplicationName \(1461\)](#), [CreateDir \(1468\)](#), [ConfigExtension \(1430\)](#), [SysConfigDir \(1436\)](#)

### 38.13.126 GetCurrentDir

Synopsis: Return the current working directory of the application.

Declaration: `function GetCurrentDir : String`

Visibility: default

Description: `GetCurrentDir` returns the current working directory.

Errors: None.

See also: [SetCurrentDir \(1531\)](#), [DiskFree \(1477\)](#), [DiskSize \(1478\)](#)

**Listing:** `./sysutex/ex28.pp`

---

**Program** `Example28;`

*{ This program demonstrates the GetCurrentDir function }*

**Uses** `sysutils;`

**Begin**

`WriteLn ( 'Current Directory is : ',GetCurrentDir);`

**End.**

---

### 38.13.127 GetDirs

Synopsis: Return a list of directory names from a path.

Declaration: `function GetDirs(var DirName: String;var Dirs: Array of pchar) : LongInt`

Visibility: default

Description: `GetDirs` splits `DirName` in a null-byte separated list of directory names, `Dirs` is an array of `PChars`, pointing to these directory names. The function returns the number of directories found, or -1 if none were found. `DirName` must contain only `OSDirSeparator` as Directory separator chars.

Errors: None.

See also: [ExtractRelativePath \(1486\)](#)

**Listing:** `./sysutex/ex45.pp`

---

**Program** `Example45;`

*{ This program demonstrates the GetDirs function }*  
*{ \$H+ }*

**Uses** `sysutils;`

**Var**  `Dirs : Array[0..127] of pchar;`  
`I,Count : longint;`  
`Dir,NewDir : String;`

---

```

Begin
  Dir:=GetCurrentDir;
  WriteLn ( 'Dir : ',Dir);

  NewDir:= '';

  count:=GetDirs ( Dir , Dirs );
  For I:=0 to Count-1 do
    begin
      NewDir:=NewDir+ '/' +StrPas ( Dirs [ I ] );
      WriteLn ( NewDir );
    end;
End.

```

---

### 38.13.128 GetEnvironmentString

Synopsis: Return an environment variable by index.

Declaration: `function GetEnvironmentString(Index: Integer) : String`

Visibility: default

Description: `GetEnvironmentString` returns the Index-th environment variable. The index is 1 based, and is bounded from above by the result of `GetEnvironmentVariableCount` ([1515](#)).

For an example, `GetEnvironmentVariableCount` ([1515](#)).

**Remark:** Note that on Windows, environment strings can start with an equal sign (=). This is a trick used to pass the current working directory to a newly created proces. In this case, extracting the variable name as the characters before the first equal sign will result in an empty name.

Errors: If there is no environment, an empty string is returned.

See also: `GetEnvironmentVariable` ([1515](#)), `GetEnvironmentVariableCount` ([1515](#))

### 38.13.129 GetEnvironmentVariable

Synopsis: Return the value of an environment variable.

Declaration: `function GetEnvironmentVariable(const EnvVar: String) : String`

Visibility: default

Description: `GetEnvironmentVariable` returns the value of the EnvVar environment variable. If the specified variable does not exist or EnvVar is empty, an empty string is returned.

See also: `GetEnvironmentString` ([1515](#)), `GetEnvironmentVariableCount` ([1515](#))

### 38.13.130 GetEnvironmentVariableCount

Synopsis: Return the number of variables in the environment.

Declaration: `function GetEnvironmentVariableCount : Integer`

Visibility: default

Description: `GetEnvironmentVariableCount` returns the number of variables in the environment. The number is 1 based, but the result may be zero if there are no environment variables.

Errors: If there is no environment, -1 may be returned.

See also: `GetEnvironmentString` ([1515](#)), `GetEnvironmentVariable` ([1515](#))

**Listing:** `./sysutex/ex92.pp`

---

```
{ $h+ }
program example92;

{ This program demonstrates the
  GetEnvironmentVariableCount function }

uses sysutils;

Var
  I : Integer;

begin
  For I:=1 to GetEnvironmentVariableCount do
    WriteLn(i:3, ' : ', GetEnvironmentString(i));
end.
```

---

### 38.13.131 GetFileHandle

**Synopsis:** Extract OS handle from an untyped file or text file.

**Declaration:** `function GetFileHandle(var f: File) : LongInt`  
`function GetFileHandle(var f: Text) : LongInt`

**Visibility:** default

**Description:** `GetFileHandle` returns the operating system handle for the file descriptor F. It can be used in various file operations which are not directly supported by the pascal language.

### 38.13.132 GetLastOSError

**Synopsis:** Return the last code from the OS.

**Declaration:** `function GetLastOSError : Integer`

**Visibility:** default

**Description:** `GetLastOSError` returns the error code from the last operating system call. It does not reset this code. In general, it should be called when an operating system call reported an error condition. In that case, `GetLastOSError` gives extended information about the error.

No assumptions should be made about the resetting of the error code by subsequent OS calls. This may be platform dependent.

See also: `RaiseLastOSError` ([1528](#))

### 38.13.133 GetLocalTime

**Synopsis:** Get the local time.

**Declaration:** `procedure GetLocalTime(var SystemTime: TSystemTime)`

**Visibility:** default

**Description:** `GetLocalTime` returns the system time in a `TSystemTime` (1426) format.

Errors: None.

See also: [Now \(1527\)](#), [Date \(1470\)](#), [Time \(1558\)](#), [TSystemTime \(1426\)](#)

### 38.13.134 GetModuleName

**Synopsis:** Return the name of the current module

**Declaration:** `function GetModuleName (Module: HMODULE) : String`

Visibility: default

**Description:** `GetModuleName` returns the name of the current module. On windows, this is the name of the executable when executed in an executable, or the name of the library when executed in a library.

On all other platforms, the result is always empty, since they provide no such functionality.

### 38.13.135 GetTempDir

### Synopsis: Return name of system's temporary directory

```
Declaration: function GetTempDir(Global: Boolean) : String
              function GetTempDir : String
```

Visibility: default

**Description:** `GetTempDir` returns the temporary directory of the system. If `Global` is `True` (the default value) it returns the system temporary directory, if it is `False` then a directory private to the user is returned. The returned name will end with a directory delimiter character.

These directories may be the same. No guarantee is made that this directory exists or is writeable by the user.

The `OnGetTempDir` (1444) handler may be set to provide custom handling of this routine: One could implement callbacks which take into consideration frameworks like KDE or GNOME, and return a different value from the default system implementation.

**Errors:** On error, an empty string is returned.

See also: [OnGetTempDir \(1444\)](#), [GetTempFileName \(1517\)](#)

### 38.13.136 GetTempFileName

**Synopsis:** Return the name of a temporary file.

```
Declaration: function GetTempFileName(const Dir: String;const Prefix: String)
                : String
function GetTempFileName : String
function GetTempFileName(Dir: PChar;Prefix: PChar;uUnique: DWORD;
                TempFileName: PChar) : DWORD
```

Visibility: default

**Description:** `GetTempFileName` returns the name of a temporary file in directory `Dir`. The name of the file starts with `Prefix`.

If `Dir` is empty, the value returned by `GetTempDir` is used, and if `Prefix` is empty, 'TMP' is used.

The `OnGetTempFile` (1444) handler may be set to provide custom handling of this routine: One could implement callbacks which take into consideration frameworks like KDE or GNOME, and return a different value from the default system implementation.

**Errors:** On error, an empty string is returned.

**See also:** `GetTempDir` (1517), `OnGetTempFile` (1444)

### 38.13.137 GetUserDir

**Synopsis:** Returns the current user's home directory.

**Declaration:** `function GetUserDir : String`

**Visibility:** default

**Description:** `GetUserDir` returns the home directory of the current user. On Unix-like systems (that includes Mac OS X), this is the value of the HOME environment variable. On Windows, this is the PROFILE special folder. On all other platforms, the application installation directory is returned.

If non-empty, it contains a trailing path delimiter.

**See also:** `GetAppConfigDir` (1513)

### 38.13.138 GuidCase

**Synopsis:** Return the index of a GUID in an array of GUID values

**Declaration:** `function GuidCase(const GUID: TGUID;const List: Array of TGUID)  
: Integer`

**Visibility:** default

**Description:** `GuidCase` returns the index of GUID in the array `List`, where 0 denotes the first element in the list. If GUID is not present in the list, -1 is returned.

**See also:** `IsEqualGUID` (1522)

### 38.13.139 GUIDToString

**Synopsis:** Convert a TGUID to a string representation.

**Declaration:** `function GUIDToString(const GUID: TGUID) : String`

**Visibility:** default

**Description:** `GUIDToString` converts the GUID identifier in `GUID` to a string representation in the form

{XXXXXXXX-XXXX-XXXX-XXXX-XXXXXXXXXXXX}

Where each X is a hexadecimal digit.

**Errors:** None.

**See also:** `Supports` (1556), `#rtl.system.TGUID` (1245), `StringToGUID` (1539), `IsEqualGuid` (1522)



**38.13.140 HookSignal**

Synopsis: Hook a specified signal

Declaration: `procedure HookSignal(RtlSigNum: Integer)`

Visibility: default

Description: `HookSignal` installs the RTL default signal handler for signal `RtlSigNum`. It does not check whether the signal is already handled, and should therefor only be called if `InquireSignal` returns `ssNotHooked`.

**38.13.141 IncAMonth**

Synopsis: Increase a date with a certain amount of months

Declaration: `procedure IncAMonth(var Year: Word; var Month: Word; var Day: Word; NumberOfMonths: Integer)`

Visibility: default

Description: `IncAMonth` increases the date as specified by `Year`, `Month`, `Day` with `NumberOfMonths`. It takes care of the number of days in a month when calculating the result.

This function does the same as `IncMonth` (1520), but operates on an already decoded date.

See also: `IncMonth` (1520)

**38.13.142 IncludeTrailingBackslash**

Synopsis: Add trailing directory separator to a pathname, if needed.

Declaration: `function IncludeTrailingBackslash(const Path: String) : String`

Visibility: default

Description: `IncludeTrailingBackslash` is provided for backwards compatibility with Delphi. Use `IncludeTrailingPathDelimiter` (1519) instead.

See also: `IncludeTrailingPathDelimiter` (1519), `ExcludeTrailingPathDelimiter` (1482), `PathDelim` (1433), `IsPathDelimiter` (1523)

**38.13.143 IncludeTrailingPathDelimiter**

Synopsis: Add trailing directory separator to a pathname, if needed.

Declaration: `function IncludeTrailingPathDelimiter(const Path: String) : String`

Visibility: default

Description: `IncludeTrailingPathDelimiter` adds a trailing path delimiter character (`PathDelim` (1433)) to `Path` if none is present yet, and returns the result.

If `Path` is empty, a path delimiter is returned, for Delphi compatibility.

See also: `IncludeTrailingBackslash` (1519), `ExcludeTrailingPathDelimiter` (1482), `PathDelim` (1433), `IsPathDelimiter` (1523)

**38.13.144 IncMonth**

Synopsis: Increases the month in a `TDateTime` value with a given amount.

Declaration: `function IncMonth(const DateTime: TDateTime;NumberOfMonths: Integer) : TDateTime`

Visibility: default

Description: `IncMonth` increases the month number in `DateTime` with `NumberOfMonths`. It wraps the result as to get a month between 1 and 12, and updates the year accordingly. `NumberOfMonths` can be negative, and can be larger than 12 (in absolute value).

Errors: None.

See also: `Date` ([1470](#)), `Time` ([1558](#)), `Now` ([1527](#))

**Listing:** `./sysutex/ex15.pp`

**Program** `Example15;`

*{ This program demonstrates the IncMonth function }*

**Uses** `sysutils;`

**Var** `ThisDay : TDateTime;`

**Begin**

```
ThisDay:=Date;
WriteLn ( 'ThisDay : ',DateToStr ( ThisDay ));
WriteLn ( '6 months ago : ',DateToStr ( IncMonth ( ThisDay , -6)));
WriteLn ( '6 months from now : ',DateToStr ( IncMonth ( ThisDay , 6)));
WriteLn ( '12 months ago : ',DateToStr ( IncMonth ( ThisDay , -12)));
WriteLn ( '12 months from now : ',DateToStr ( IncMonth ( ThisDay , 12)));
WriteLn ( '18 months ago : ',DateToStr ( IncMonth ( ThisDay , -18)));
WriteLn ( '18 months from now : ',DateToStr ( IncMonth ( ThisDay , 18)));
End.
```

**38.13.145 InquireSignal**

Synopsis: Check whether a signal handler is set (unix only)

Declaration: `function InquireSignal(RtlSigNum: Integer) : TSignalState`

Visibility: default

Description: `RtlSigNum` will check whether the signal `RtlSigNum` is being handled, and by whom. It returns a `TSignalState` result to report the state of the signal, which can be one of the following values:

**ssNotHooked** No signal handler is set for the signal.

**ssHooked** A signal handler is set by the RTL code for the signal.

**ssOverridden** A signal handler was set for the signal by third-party code.

This routine works by resetting the signal handlers, so it is risky to call.

**38.13.146 IntToHex**

Synopsis: Convert an integer value to a hexadecimal string.

Declaration: `function IntToHex(Value: Integer; Digits: Integer) : String`  
`function IntToHex(Value: Int64; Digits: Integer) : String`  
`function IntToHex(Value: QWord; Digits: Integer) : String`

Visibility: default

Description: `IntToHex` converts `Value` to a hexadecimal string representation. The result will contain at least `Digits` characters. If `Digits` is less than the needed number of characters, the string will NOT be truncated. If `Digits` is larger than the needed number of characters, the result is padded with zeroes.

Errors: None.

See also: `IntToStr` ([1521](#))

**Listing:** `./sysutex/ex73.pp`

---

**Program** `Example73;`

*{ This program demonstrates the IntToHex function }*

**Uses** `sysutils;`

**Var** `I : longint;`

**Begin**

**For** `I:=0 to 31 do`

**begin**

**WriteLn** (`IntToHex(1 shl I,8)`);

**WriteLn** (`IntToHex(15 shl I,8)`)

**end;**

**End.**

---

**38.13.147 IntToStr**

Synopsis: Convert an integer value to a decimal string.

Declaration: `function IntToStr(Value: Integer) : String`  
`function IntToStr(Value: Int64) : String`  
`function IntToStr(Value: QWord) : String`

Visibility: default

Description: `IntToStr` converts `Value` to its string representation. The resulting string has only as much characters as needed to represent the value. If the value is negative a minus sign is prepended to the string.

Errors: None.

See also: `IntToHex` ([1521](#)), `StrToInt` ([1552](#))

**Listing:** `./sysutex/ex74.pp`

---

```

Program Example74;

{ This program demonstrates the IntToStr function }

Uses sysutils;

Var I : longint;

Begin
  For I:=0 to 31 do
    begin
      WriteLn (IntToStr(1 shl I));
      WriteLn (IntToStr(15 shl I));
    end;
End.

```

---

### 38.13.148 IsDelimiter

**Synopsis:** Check whether a given string is a delimiter character.

**Declaration:** `function IsDelimiter(const Delimiters: String; const S: String;  
Index: Integer) : Boolean`

**Visibility:** default

**Description:** `IsDelimiter` checks whether the `Index`-th character in the string `S` is a delimiter character as passed in `Delimiters`. If `Index` is out of range, `False` is returned.

**Errors:** None.

See also: `LastDelimiter` ([1524](#))

### 38.13.149 IsEqualGUID

**Synopsis:** Check whether two `TGUID` variables are equal.

**Declaration:** `function IsEqualGUID(const guid1: TGUID; const guid2: TGUID) : Boolean`

**Visibility:** default

**Description:** `IsEqualGUID` checks whether `guid1` and `guid2` are equal, and returns `True` if this is the case, or `False` otherwise.

**Errors:**

See also: `Supports` ([1556](#)), `#rtl.system.TGUID` ([1245](#)), `StringToGUID` ([1539](#)), `GuidToString` ([1518](#))

### 38.13.150 IsLeapYear

**Synopsis:** Determine whether a year is a leap year.

**Declaration:** `function IsLeapYear(Year: Word) : Boolean`

**Visibility:** default

**Description:** `IsLeapYear` returns `True` if `Year` is a leap year, `False` otherwise.

Errors: None.

See also: IncMonth ([1520](#)), Date ([1470](#))

**Listing:** ./sysutex/ex16.pp

---

**Program** Example16;

*{ This program demonstrates the IsLeapYear function }*

**Uses** sysutils;

**Var** YY,MM,dd : Word;

**Procedure** TestYear (Y : Word);

**begin**

**WriteLn** (Y, ' is leap year : ', IsLeapYear(Y));  
**end**;

**Begin**

**DeCodeDate** (Date, YY,mm,dd);  
    TestYear(yy);  
    TestYear(2000);  
    TestYear(1900);  
    TestYear(1600);  
    TestYear(1992);  
    TestYear(1995);

**End.**

---

### 38.13.151 IsPathDelimiter

**Synopsis:** Is the character at the given position a pathdelimiter ?

**Declaration:** function IsPathDelimiter(const Path: String; Index: Integer) : Boolean

**Visibility:** default

**Description:** IsPathDelimiter returns True if the character at position Index equals PathDelim ([1433](#)), i.e. if it is a path delimiter character for the current platform.

**Errors:** IncludeTrailingPathDelimiter ([1519](#)) ExcludeTrailingPathDelimiter ([1482](#)) PathDelim ([1433](#))

### 38.13.152 IsValidIdent

**Synopsis:** Check whether a string is a valid identifier name.

**Declaration:** function IsValidIdent(const Ident: String) : Boolean

**Visibility:** default

**Description:** IsValidIdent returns True if Ident can be used as a component name. It returns False otherwise. Ident must consist of a letter or underscore, followed by a combination of letters, numbers or underscores to be a valid identifier.

**Errors:** None.

**Listing:** ./sysutex/ex75.pp

**Program** Example75;

```
{ This program demonstrates the IsValidIdent function }
```

**Uses** sysutils;

```
Procedure Testit (S : String);
```

**begin**

**Write** ( ' " ' ,S, ' " is ' );

**If not IsValidIdent(S) then**

```
Write( 'NOT' );
```

```
WriteIn ( 'a valid identifier');
```

end ;

## Begin

```
Testit ( '_MyObj' );
```

```
Testit ( 'My__Obj1' );
```

```
Testit ( 'My_1_Obj' );
```

```
Testit ( '1MyObject' );
```

```
Testit ( 'My@Object' );
```

```
Testit ( 'M123' );
```

**End .**

### 38.13.153 LastDelimiter

**Synopsis:** Return the last occurrence of a set of delimiters in a string.

```
Declaration: function LastDelimiter(const Delimiters: String;const S: String)
                                     : Integer
```

Visibility: default

**Description:** LastDelimiter returns the *last* occurrence of any character in the set Delimiters in the string S.

Errors:

**Listing:** ./sysutex/ex88.pp

**Program** example88;

```
{ This program demonstrates the LastDelimiter function }
```

```
uses SysUtils;
```

**begin**

```
WriteIn( LastDelimiter( '\.: ', 'c:\filename.ext' ));
```

end.

### 38.13.154 LeftStr

**Synopsis:** Return a number of characters starting at the left of a string.

**Declaration:** `function LeftStr(const S: String; Count: Integer) : String`

Visibility: default

Description: `LeftStr` returns the `Count` leftmost characters of `S`. It is equivalent to a call to `Copy (S, 1, Count)`.

Errors: None.

See also: `RightStr` (1530), `TrimLeft` (1561), `TrimRight` (1562), `Trim` (1560)

**Listing:** ./sysutex/ex76.pp

---

**Program** Example76;

*{ This program demonstrates the LeftStr function }*

**Uses** sysutils;

**Begin**

**WriteLn** ( `LeftStr ( 'abcdefghijklmnopqrstuvwxyz', 20)`);

**WriteLn** ( `LeftStr ( 'abcdefghijklmnopqrstuvwxyz', 15)`);

**WriteLn** ( `LeftStr ( 'abcdefghijklmnopqrstuvwxyz', 1)`);

**WriteLn** ( `LeftStr ( 'abcdefghijklmnopqrstuvwxyz', 200)`);

**End.**

---

### 38.13.155 LoadStr

Synopsis: Load a string from the resource tables.

Declaration: `function LoadStr (Ident: Integer) : String`

Visibility: default

Description: This function is not yet implemented. resources are not yet supported.

Errors:

### 38.13.156 LowerCase

Synopsis: Return a lowercase version of a string.

Declaration: `function LowerCase (const s: String) : String; Overload`  
`function LowerCase (const V: variant) : String; Overload`

Visibility: default

Description: `LowerCase` returns the lowercase equivalent of `S`. Ansi characters are not taken into account, only ASCII codes below 127 are converted. It is completely equivalent to the lowercase function of the system unit, and is provided for compatiibility only.

Errors: None.

See also: `AnsiLowerCase` (1452), `UpperCase` (1567), `AnsiUpperCase` (1460)

**Listing:** ./sysutex/ex77.pp

**Program** Example77;

```
{ This program demonstrates the LowerCase function }
```

```
Uses sysutils;
```

## Begin

```
WriteIn (LowerCase( 'THIS WILL COME out all LoWeRcAsE ! ' ));
```

End.

### 38.13.157 MSecsToTimeStamp

: Convert a number of milliseconds to a `TDatetime` value.

```
:function MSecsToTimeStamp(MSecs: Comp) : TTimeStamp
```

: default

`MSecsTiTimeStamp` converts the given number of milliseconds to a `TTimeStamp` date/time notation.

Use `TTimeStamp` variables if you need to keep very precise track of time.

: None.

: TimeStampToMSecs (1559), DateTimeToTimeStamp (1473)

**Listing:** ./sysutex/ex17.pp

**Program** Example17;

```
{ This program demonstrates the MSecsToTimeStamp function }
```

```
Uses sysutils;
```

```
Var MS : Comp;
```

```
TS : TTimeStamp;
```

```
DT : TDateTime;
```

**Begin**

```
TS:= DateTimeToTimeStamp(Now);
```

```
WriteIn ( 'Now in days since 1/1/0001      : ',TS.Date);
```

```
WriteIn ( 'Now in millisecs since midnight : ',TS.Time);
```

```
MS:=TimeStampToMSecs (TS);
```

```
WriteIn ( 'Now in millisecs since 1/1/0001 : ',MS);
```

```
MS:=MS-1000*3600*2;
```

TS := MSecsToTimeStamp (MS) ;

```
DT:=TimeStampToDateTime(TS);
```

```
WriteIn ( 'Now minus 1 day : ',DateTimeToStr(DT));
```

**End.**

### 38.13.158 NewStr

: Allocate a new ansistring on the heap.

```
:function NewStr(const S: String) : PString; Overload
```



Visibility: default

Description: `NewStr` assigns a new dynamic string on the heap, copies `S` into it, and returns a pointer to the newly assigned string.

This function is obsolete, and shouldn't be used any more. The `AnsiString` mechanism also allocates ansistrings on the heap, and should be preferred over this mechanism.

For an example, see `AssignStr` (1462).

Errors: If not enough memory is present, an `EOutOfMemory` exception will be raised.

See also: `AssignStr` (1462), `DisposeStr` (1478)

### 38.13.159 Now

Synopsis: Returns the current date and time.

Declaration: `function Now : TDateTime`

Visibility: default

Description: `Now` returns the current date and time. It is equivalent to `Date+Time`.

Errors: None.

See also: `Date` (1470), `Time` (1558)

**Listing:** `./sysutex/ex18.pp`

---

**Program** `Example18`;

*{ This program demonstrates the Now function }*

**Uses** `sysutils`;

**Begin**

`WriteLn ( 'Now : ', DateTimeToStr(Now) );`

**End.**

---

### 38.13.160 OutOfMemoryError

Synopsis: Raise an `EOutOfMemory` exception

Declaration: `procedure OutOfMemoryError`

Visibility: default

Description: `OutOfMemoryError` raises an `EOutOfMemory` (1575) exception, with an exception object that has been allocated on the heap at program startup. The program should never create an `EOutOfMemory` (1575) exception, but always call this routine.

See also: `EOutOfMemory` (1575)

**38.13.161 QuotedStr**

Synopsis: Return a quotes version of a string.

Declaration: `function QuotedStr(const S: String) : String`

Visibility: default

Description: `QuotedStr` returns the string `S`, quoted with single quotes. This means that `S` is enclosed in single quotes, and every single quote in `S` is doubled. It is equivalent to a call to `AnsiQuotedStr(S, "'")`.

Errors: None.

See also: `AnsiQuotedStr` ([1453](#)), `AnsiExtractQuotedStr` ([1450](#))

**Listing:** `./sysutex/ex78.pp`

---

**Program** `Example78`;

*{ This program demonstrates the QuotedStr function }*

**Uses** `sysutils`;

**Var** `S` : `AnsiString`;

**Begin**

`S := 'He said ''Hello'' and walked on';`

`Writeln (S);`

`Writeln (' becomes');`

`Writeln (QuotedStr(S));`

**End.**

---

**38.13.162 RaiseLastError**

Synopsis: Raise an exception with the last Operating System error code.

Declaration: `procedure RaiseLastError`

Visibility: default

Description: `RaiseLastError` raises an `EOSError` ([1575](#)) exception with the error code returned by `GetLastError`. If the Error code is nonzero, then the corresponding error message will be returned. If the error code is zero, a standard message will be returned.

Errors: This procedure may not be implemented on all platforms. If it is not, then a normal Exception ([1577](#)) will be raised.

See also: `EOSError` ([1575](#)), `GetLastError` ([1516](#)), Exception ([1577](#))

**38.13.163 RemoveDir**

Synopsis: Remove a directory from the filesystem.

Declaration: `function RemoveDir(const Dir: String) : Boolean`

Visibility: default

For an example, see `CreateDir` (1468).

On Error, False is returned

### Program Example44 :

**Uses** sysutils:

## Begin

### Replace the date part of a date/time stamp

default

ReplaceTime (1530)

### 38.13.166 ReplaceTime

Synopsis: Replace the time part

```
Declaration: procedure ReplaceTime(var dati: TDateTime; NewTime: TDateTime)
```

Visibility: default

**Description:** ReplaceTime replaces the time part in `dateTime` with `NewTime`. The date part remains untouched.

Errors:

### 38.13.167 RightStr

**Synopsis:** Return a number of characters from a string, starting at the end.

**Declaration:** `function RightStr(const S: String; Count: Integer) : String`

Visibility: default

**Description:** RightStr returns the Count rightmost characters of S. It is equivalent to a call to Copy (S, Length (S) +1-Count, Count).

If Count is larger than the actual length of S only the real length will be used.

Errors: None.

See also: LeftStr (1524), Trim (1560), TrimLeft (1561), TrimRight (1562)

**Listing:** ./sysutex/ex79.pp

---

**Program** Example79;

```
{ This program demonstrates the RightStr function }
```

**Uses** sysutils;

## Begin

```
WriteIn (RightStr( 'abcdefghijklmnopqrstuvwxyz',20));
```

```
WriteIn ( RightStr ( 'abcdefghijklmnopqrstuvwxyz', 15));
```

```
WriteIn ( RightStr ( 'abcdefghijklmnopqrstuvwxyz' , 1 ));
```

```
WriteIn ( RightStr ( ' abcdefghijklmnopqrstuvwxyz ',200));
```

**End.**

### 38.13.168 SafeLoadLibrary

## Synopsis: Load a library safely

```
Declaration: function SafeLoadLibrary(const FileName: AnsiString; ErrorMode: DWord)
            : HMODULE
```

Visibility: default

**Description:** SafeLoadLibrary saves and restores some registers before and after issuing a call to LoadLibrary.

Errors: None.

### 38.13.169 SameFileName

Synopsis: Are two filenames referring to the same file ?

Declaration: `function SameFileName(const S1: String;const S2: String) : Boolean`

Visibility: default

Description: `SameFileName` returns `True` if calling `AnsiCompareFileName` (1448) with arguments `S1` and `S2` returns 0, and returns `False` otherwise.

Errors: None.

See also: `AnsiCompareFileName` (1448)

### 38.13.170 SameText

Synopsis: Checks whether 2 strings are the same (case insensitive)

Declaration: `function SameText(const s1: String;const s2: String) : Boolean`

Visibility: default

Description: `SameText` calls `CompareText` (1467) with `S1` and `S2` as parameters and returns `True` if the result of that call is zero, or `False` otherwise.

Errors: None.

See also: `CompareText` (1467), `AnsiSameText` (1453), `AnsiSameStr` (1453)

### 38.13.171 SetCurrentDir

Synopsis: Set the current directory of the application.

Declaration: `function SetCurrentDir(const NewDir: String) : Boolean`

Visibility: default

Description: `SetCurrentDir` sets the current working directory of your program to `NewDir`. It returns `True` if the function was successfull, `False` otherwise.

Errors: In case of error, `False` is returned.

See also: `GetCurrentDir` (1514)

### 38.13.172 SetDirSeparators

Synopsis: Set the directory separators to the known directory separators.

Declaration: `function SetDirSeparators(const FileName: String) : String`

Visibility: default

Description: `SetDirSeparators` returns `FileName` with all possible `DirSeparators` replaced by `OSDirSeparator`.

Errors: None.

See also: `ExpandFileName` (1483), `ExtractFilePath` (1485), `ExtractFileDir` (1484)

**Listing:** ./sysutex/ex47.pp

---

**Program** Example47;

*{ This program demonstrates the SetDirSeparators function }*

**Uses** sysutils;

**Begin**

**WriteLn** ( SetDirSeparators ( '/pp\bin\win32\ppc386' ));

**End.**

---

### 38.13.173 ShowException

**Synopsis:** Show the current exception to the user.

**Declaration:** procedure ShowException(ExceptObject: TObject; ExceptAddr: Pointer)

**Visibility:** default

**Description:** ShowException shows a message stating that a ExceptObject was raised at address ExceptAddr.

It uses ExceptionErrorMessage (1481) to create the message, and is aware of the fact whether the application is a console application or a GUI application. For a console application, the message is written to standard error output. For a GUI application, OnShowException (1445) is executed.

**Errors:** If, for a GUI application, OnShowException (1445) is not set, no message will be displayed to the user.

The exception message can be at most 255 characters long: It is possible that no memory can be allocated on the heap, so ansistrings are not available, so a shortstring is used to display the message.

**See also:** ExceptObject (1481), ExceptAddr (1480), ExceptionErrorMessage (1481)

### 38.13.174 Sleep

**Synopsis:** Suspend execution of a program for a certain time.

**Declaration:** procedure Sleep(milliseconds: Cardinal)

**Visibility:** default

**Description:** Sleep suspends the execution of the program for the specified number of milliseconds (milliseconds).

After the specified period has expired, program execution resumes.

**Remark:** The indicated time is not exact, i.e. it is a minimum time. No guarantees are made as to the exact duration of the suspension.

### 38.13.175 SScanf

**Synopsis:** Scan a string for substrings and return the substrings

**Declaration:** function SScanf(const s: String; const fmt: String;  
const Pointers: Array of Pointer) : Integer

**Visibility:** default

**Description:** SScanF scans the string S for the elements specified in Fmt, and returns the elements in the pointers in Pointers. The Fmt can contain placeholders of the form %X where X can be one of the following characters:

**d**Placeholder for a decimal number.

**f**Placeholder for a floating point number (an extended)

**s**Placeholder for a string of arbitrary length.

**c**Placeholder for a single character

The `Pointers` array contains a list of pointers, each pointer should point to a memory location of a type that corresponds to the type of placeholder in that position:

**d**A pointer to an integer.

**f**A pointer to an extended.

**s**A pointer to an ansistring.

**c**A pointer to a single character.

Errors: No error checking is performed on the type of the memory location.

See also: `Format` ([1504](#))

### 38.13.176 StrAlloc

Synopsis: Allocate a null-terminated string on the heap.

Declaration: `function StrAlloc(Size: cardinal) : PChar`

Visibility: default

Description: `StrAlloc` reserves memory on the heap for a string with length `Len`, terminating `#0` included, and returns a pointer to it.

Additionally, `StrAlloc` allocates 4 extra bytes to store the size of the allocated memory. Therefore this function is NOT compatible with the `StrAlloc` ([1167](#)) function of the `Strings` unit.

For an example, see `StrBufSize` ([1533](#)).

Errors: None.

See also: `StrBufSize` ([1533](#)), `StrDispose` ([1536](#)), `#rtl.strings.StrAlloc` ([1167](#))

### 38.13.177 StrBufSize

Synopsis: Return the size of a null-terminated string allocated on the heap.

Declaration: `function StrBufSize(Str: PChar) : SizeUInt`

Visibility: default

Description: `StrBufSize` returns the memory allocated for `Str`. This function ONLY gives the correct result if `Str` was allocated using `StrAlloc` ([1533](#)).

Errors: If no more memory is available, a runtime error occurs.

See also: `StrAlloc` ([1533](#)), `StrDispose` ([1536](#))

**Listing:** `./sysutex/ex46.pp`

---

**Program** Example46;

```
{ This program demonstrates the StrBufSize function }
{$H+}
```

**Uses** sysutils;

**Const** S = 'Some nice string';

**Var** P : Pchar;

**Begin**

```
P:= StrAlloc (Length(S)+1);
```

```
StrPCopy(P,S);
```

```
Write (P, ' has length ',length(S));
```

```
Writeln ( ' and buffer size ',StrBufSize(P));
```

```
StrDispose(P);
```

**End.**

---

### 38.13.178 StrByteType

**Synopsis:** Return the type of byte in a null-terminated string for a multi-byte character set

**Declaration:** function StrByteType(Str: PChar; Index: Cardinal) : TmbcsByteType

**Visibility:** default

**Description:** StrByteType returns the type of byte in the null-terminated string Str at (0-based) position Index.

**Errors:** No checking on the index is performed.

**See also:** TmbcsByteType ([1440](#)), ByteType ([1464](#))

### 38.13.179 strcat

**Synopsis:** Concatenate 2 null-terminated strings.

**Declaration:** function strcat(dest: pchar; source: pchar) : pchar

**Visibility:** default

**Description:** Attaches Source to Dest and returns Dest.

**Errors:** No length checking is performed.

**See also:** StrLCat ([1540](#))

**Listing:** ./stringex/ex11.pp

---

**Program** Example11;

**Uses** strings;

```
{ Program to demonstrate the StrCat function. }
```

**Const** P1 : PChar = 'This is a PChar String.';



---

```

Var P2 : PChar;

                                begin
    P2:= StrAlloc ( StrLen(P1)*2+1);
    StrMove (P2,P1,StrLen(P1)+1); { P2=P1 }
    StrCat (P2,P1);                { Append P2 once more }
    WriteLn ( 'P2 : ',P2);
    StrDispose(P2);
end.

```

---

### 38.13.180 StrCharLength

Synopsis: Return the length of a null-terminated string in characters.

Declaration: `function StrCharLength(const Str: PChar) : Integer`

Visibility: default

Description: `StrCharLength` returns the length of the null-terminated string `Str` (a widestring) in characters (not in bytes). It uses the widestring manager to do this.

### 38.13.181 strcmp

Synopsis: Compare 2 null-terminated strings, case sensitive.

Declaration: `function strcmp(str1: pchar;str2: pchar) : SizeInt`

Visibility: default

Description: Compares the null-terminated strings `S1` and `S2`. The result is

- A negative `Longint` when `S1<S2`.
- 0 when `S1=S2`.
- A positive `Longint` when `S1>S2`.

For an example, see `StrLComp` ([1540](#)).

Errors: None.

See also: `StrLComp` ([1540](#)), `StrIComp` ([1538](#)), `StrLComp` ([1543](#))

### 38.13.182 strcpy

Synopsis: Copy a null-terminated string

Declaration: `function strcpy(dest: pchar;source: pchar) : pchar`

Visibility: default

Description: Copy the null terminated string in `Source` to `Dest`, and returns a pointer to `Dest`. `Dest` needs enough room to contain `Source`, i.e. `StrLen(Source)+1` bytes.

Errors: No length checking is performed.

See also: `StrPCopy` ([1545](#)), `StrLCopy` ([1541](#)), `StrECopy` ([1536](#))

**Listing:** ./stringex/ex4.pp

**Program** Example4;

---

```

                                Uses strings;

{ Program to demonstrate the StrCopy function. }

Const P : PChar = 'This is a PCHAR string.';

var PP : PChar;

begin
  PP:=StrAlloc (Strlen(P)+1);
  StrCopy (PP,P);
  If StrComp (PP,P)<>0 then
    Writeln ( 'Oh-oh problems ... ' )
  else
    Writeln ( 'All is well : PP=',PP);
  StrDispose(PP);
end.

```

---

### 38.13.183 StrDispose

**Synopsis:** Dispose of a null-terminated string on the heap.

**Declaration:** procedure StrDispose(Str: PChar)

**Visibility:** default

**Description:** StrDispose frees any memory allocated for Str. This function will only function correctly if Str has been allocated using StrAlloc (1533) from the SysUtils unit.

For an example, see StrBufSize (1533).

**Errors:** If an invalid pointer is passed, or a pointer not allocated with StrAlloc, an error may occur.

**See also:** StrBufSize (1533), StrAlloc (1533), StrDispose (1536)

### 38.13.184 strecopy

**Synopsis:** Copy a null-terminated string, return a pointer to the end.

**Declaration:** function strecopy(dest: pchar;source: pchar) : pchar

**Visibility:** default

**Description:** Copies the Null-terminated string in Source to Dest, and returns a pointer to the end (i.e. the terminating Null-character) of the copied string.

**Errors:** No length checking is performed.

**See also:** StrLCopy (1541), StrCopy (1535)

**Listing:** ./stringex/ex6.pp

---

**Program** Example6;

**Uses** strings;

*{ Program to demonstrate the StrECopy function. }*

**Const** P : PChar = 'This is a PCHAR string.';

**Var** PP : PChar;

**begin**

PP:= StrAlloc (StrLen(P)+1);

**If** Longint(StrECopy(PP,P)) – Longint(PP) <> StrLen(P) **then**

**WriteLn** ('Something is wrong here !')

**else**

**WriteLn** ('PP= ',PP);

**StrDispose**(PP);

**end.**

---

### 38.13.185 strend

Synopsis: Return a pointer to the end of a null-terminated string

Declaration: `function strend(p: pchar) : pchar`

Visibility: default

Description: Returns a pointer to the end of P. (i.e. to the terminating null-character.

Errors: None.

See also: StrLen ([1542](#))

**Listing:** ./stringex/ex7.pp

---

**Program** Example6;

**Uses** strings;

*{ Program to demonstrate the StrEnd function. }*

**Const** P : PChar = 'This is a PCHAR string.';

**begin**

**If** Longint(StrEnd(P)) – Longint(P) <> StrLen(P) **then**

**WriteLn** ('Something is wrong here !')

**else**

**WriteLn** ('All is well..');

**end.**

---

### 38.13.186 StrFmt

Synopsis: Format a string with given arguments, store the result in a buffer.

**Declaration:** `function StrFmt (Buffer: PChar;Fmt: PChar;const args: Array of const)  
: PChar  
function StrFmt (Buffer: PChar;Fmt: PChar;const Args: Array of const;  
const FormatSettings: TFormatSettings) : PChar`

**Visibility:** default

**Description:** `StrFmt` will format `fmt` with `Args`, as the `Format` (1504) function does, and it will store the result in `Buffer`. The function returns `Buffer`. `Buffer` should point to enough space to contain the whole result.

**Errors:** for a list of errors, see `Format` (1504).

**See also:** `StrLFmt` (1542), `FmtStr` (1503), `Format` (1504), `FormatBuf` (1509)

**Listing:** `./sysutex/ex80.pp`

---

**Program** `Example80;`

*{ This program demonstrates the StrFmt function }*

**Uses** `sysutils;`

**Var** `S : AnsiString;`

**Begin**

`SetLength(S,80);`

**WriteLn** (`StrFmt` (`@S[1]`, 'For some nice examples of fomatting see %s.', ['Format']));

**End.**

---

### 38.13.187 stricmp

**Synopsis:** Compare 2 null-terminated strings, case insensitive.

**Declaration:** `function stricmp(str1: pchar;str2: pchar) : SizeInt`

**Visibility:** default

**Description:** Compares the null-terminated strings `S1` and `S2`, ignoring case. The result is

- A negative `Longint` when `S1<S2`.
- 0 when `S1=S2`.
- A positive `Longint` when `S1>S2`.

**Errors:** None.

**See also:** `StrLComp` (1540), `StrComp` (1535), `StrLComp` (1543)

**Listing:** `./stringex/ex8.pp`

---

**Program** `Example8;`

**Uses** `strings;`

*{ Program to demonstrate the StrLComp function. }*

**Const** `P1 : PChar = 'This is the first string.';`

---

```

    P2 : PChar = 'This is the second string.';

Var L : Longint;

                                begin
Write ( 'P1 and P2 are ');
If StrComp (P1,P2)<>0 then write ( 'NOT ');
write ( 'equal. The first ');
L:=1;
While StrLComp(P1,P2,L)=0 do inc (L);
dec(L);
WriteLn (L, ' characters are the same. ');
end.

```

---

### 38.13.188 StringReplace

Synopsis: Replace occurrences of one substring with another in a string.

Declaration: `function StringReplace(const S: String;const OldPattern: String;  
const NewPattern: String;Flags: TReplaceFlags)  
: String`

Visibility: default

Description: `StringReplace` searches the string `S` for occurrences of the string `OldPattern` and, if it is found, replaces it with `NewPattern`. It returns the resulting string. The behaviour of `StringReplace` can be runed with `Flags`, which is of type `TReplaceFlags` (1440). Standard behaviour is to replace only the first occurrence of `OldPattern`, and to search case sensitively.

Errors: None.

See also: `TReplaceFlags` (1440)

### 38.13.189 StringToGUID

Synopsis: Convert a string to a native `TGUID` type.

Declaration: `function StringToGUID(const S: String) : TGUID`

Visibility: default

Description: `StringToGUID` converts the string `S` to a valid GUID. The string `S` should be of the form

```
{XXXXXXXX-XXXX-XXXX-XXXX-XXXXXXXXXXXX}
```

Where each `X` is a hexadecimal digit. The dashes and braces are required.

Errors: In case `S` contains an invalid GUID representation, a `EConvertError` (1572) exception is raised.

See also: `Supports` (1556), `#rtl.system.TGUID` (1245), `GUIDToString` (1518), `IsEqualGuid` (1522)

**38.13.190 strlcat**

Synopsis: Concatenate 2 null-terminated strings, with length boundary.

Declaration: `function strlcat(dest: pchar;source: pchar;l: SizeInt) : pchar`

Visibility: default

Description: Adds MaxLen characters from Source to Dest, and adds a terminating null-character. Returns Dest.

Errors: None.

See also: StrCat ([1534](#))

**Listing:** ./stringex/ex12.pp

---

**Program** Example12;

**Uses** strings;

*{ Program to demonstrate the StrLCat function. }*

**Const** P1 : PChar = '1234567890';

**Var** P2 : PChar;

**begin**

P2:=StrAlloc (StrLen(P1)\*2+1);

P2^:=#0; { Zero length }

StrCat (P2,P1);

StrLCat (P2,P1,5);

WriteLn ( 'P2 = ',P2);

StrDispose(P2)

**end.**

---

**38.13.191 strlcomp**

Synopsis: Compare limited number of characters of 2 null-terminated strings

Declaration: `function strlcomp(str1: pchar;str2: pchar;l: SizeInt) : SizeInt`

Visibility: default

Description: Compares maximum L characters of the null-terminated strings S1 and S2. The result is

- A negative Longint when S1<S2.
- 0 when S1=S2.
- A positive Longint when S1>S2.

Errors: None.

See also: StrComp ([1535](#)), StrIComp ([1538](#)), StrLComp ([1543](#))

**Listing:** ./stringex/ex8.pp

---

```

Program Example8;

Uses strings;

{ Program to demonstrate the StrLComp function. }

Const P1 : PChar = 'This is the first string.';
        P2 : PChar = 'This is the second string.';

Var L : Longint;

begin
  Write ( 'P1 and P2 are ');
  If StrComp (P1,P2)<>0 then write ( 'NOT ');
  write ( 'equal. The first ');
  L:=1;
  While StrLComp(P1,P2,L)=0 do inc (L);
  dec(L);
  WriteLn (L, ' characters are the same. ');
end.

```

---

### 38.13.192 strlcopy

Synopsis: Copy a null-terminated string, limited in length.

Declaration: `function strlcopy(dest: pchar;source: pchar;maxlen: SizeInt) : pchar`

Visibility: default

Description: Copies MaxLen characters from Source to Dest, and makes Dest a null terminated string.

Errors: No length checking is performed.

See also: StrCopy ([1535](#)), StrECopy ([1536](#))

**Listing:** ./stringex/ex5.pp

---

```

Program Example5;

Uses strings;

{ Program to demonstrate the StrLCopy function. }

Const P : PChar = '123456789ABCDEF';

var PP : PChar;

begin
  PP:=StrAlloc(11);
  WriteLn ( 'First 10 characters of P : ',StrLCopy (PP,P,10));
  StrDispose(PP);
end.

```

---

**38.13.193 strlen**

Synopsis: Length of a null-terminated string.

Declaration: `function strlen(p: pchar) : sizeint`

Visibility: default

Description: Returns the length of the null-terminated string P.

Errors: None.

See also: `StrNew` ([1544](#))

**Listing:** `./stringex/ex1.pp`

---

**Program** `Example1;`

**Uses** `strings;`

*{ Program to demonstrate the StrLen function. }*

**Const** `P : PChar = 'This is a constant pchar string';`

**begin**

`Writeln ( 'P          : ',p);`

`Writeln ( 'length(P) : ',StrLen(P));`

**end.**

---

**38.13.194 StrLFmt**

Synopsis: Format a string with given arguments, but with limited length.

Declaration: `function StrLFmt(Buffer: PChar;Maxlen: Cardinal;Fmt: PChar;  
                          const args: Array of const) : Pchar  
function StrLFmt(Buffer: PChar;Maxlen: Cardinal;Fmt: PChar;  
                          const args: Array of const;  
                          const FormatSettings: TFormatSettings) : Pchar`

Visibility: default

Description: `StrLFmt` will format `fmt` with `Args`, as the `Format` ([1504](#)) function does, and it will store maximally `Maxlen` characters of the result in `Buffer`. The function returns `Buffer`. `Buffer` should point to enough space to contain `MaxLen` characters.

Errors: for a list of errors, see `Format` ([1504](#)).

See also: `StrFmt` ([1537](#)), `FmtStr` ([1503](#)), `Format` ([1504](#)), `FormatBuf` ([1509](#))

**Listing:** `./sysutex/ex81.pp`

---

**Program** `Example80;`

*{ This program demonstrates the StrFmt function }*

**Uses** `sysutils;`

**Var** `S : AnsiString;`



**Begin**

```

SetLength(S,80);
WriteLn (StrLFmt (@S[1],80,'For some nice examples of fomatting see %s.',['Format']));
End.
```

---

**38.13.195 strlicomp**

Synopsis: Compare limited number of characters in 2 null-terminated strings, ignoring case.

Declaration: `function strlicomp(str1: pchar;str2: pchar;l: SizeInt) : SizeInt`

Visibility: default

Description: Compares maximum L characters of the null-terminated strings S1 and S2, ignoring case. The result is

- A negative Longint when S1<S2.
- 0 when S1=S2.
- A positive Longint when S1>S2.

For an example, see StrIComp ([1538](#))

Errors: None.

See also: StrLComp ([1540](#)), StrComp ([1535](#)), StrIComp ([1538](#))

**38.13.196 strlower**

Synopsis: Convert null-terminated string to all-lowercase.

Declaration: `function strlower(p: pchar) : pchar`

Visibility: default

Description: Converts P to an all-lowercase string. Returns P.

Errors: None.

See also: StrUpper ([1556](#))

**Listing:** ./stringex/ex14.pp

---

**Program** Example14;

**Uses** strings;

*{ Program to demonstrate the StrLower and StrUpper functions. }*

**Const**

```

P1 : PChar = 'THIS IS AN UPPERCASE PCHAR STRING';
P2 : PChar = 'this is a lowercase string';
```

**begin**

```

WriteLn ( 'Uppercase : ',StrUpper(P2));
StrLower (P1);
WriteLn ( 'Lowercase : ',P1);
end.
```

---

**38.13.197 strmove**

Synopsis: Move a null-terminated string to new location.

Declaration: `function strmove(dest: pchar;source: pchar;l: SizeInt) : pchar`

Visibility: default

Description: Copies `MaxLen` characters from `Source` to `Dest`. No terminating null-character is copied. Returns `Dest`

Errors: None.

See also: `StrLCopy` ([1541](#)), `StrCopy` ([1535](#))

**Listing:** `./stringex/ex10.pp`

---

**Program** `Example10;`

**Uses** `strings;`

*{ Program to demonstrate the StrMove function. }*

**Const** `P1 : PCHAR = 'This is a pchar string.';`

**Var** `P2 : Pchar;`

**begin**

`P2:= StrAlloc (StrLen(P1)+1);`

`StrMove (P2,P1,StrLen(P1)+1); { P2:=P1 }`

`WriteLn ( 'P2 = ',P2);`

`StrDispose(P2);`

**end.**

---

**38.13.198 strnew**

Synopsis: Allocate room for new null-terminated string.

Declaration: `function strnew(p: pchar) : pchar`

Visibility: default

Description: Copies `P` to the Heap, and returns a pointer to the copy.

Errors: Returns `Nil` if no memory was available for the copy.

See also: `StrCopy` ([1535](#)), `StrDispose` ([1536](#))

**Listing:** `./stringex/ex16.pp`

---

**Program** `Example16;`

**Uses** `strings;`

*{ Program to demonstrate the StrNew function. }*

**Const** `P1 : PChar = 'This is a PChar string';`

---

```

var P2 : PChar;

begin
  P2:=StrNew (P1);
                                If P1=P2 then
    writeln ( 'This can''t be happening ... ')
  else
    writeln ( 'P2 : ',P2);
  StrDispose(P2);
end.

```

---

### 38.13.199 StrNextChar

Synopsis: Returns a pointer to the location of the next empty character in a null-terminated string

Declaration: `function StrNextChar(const Str: PChar) : PChar`

Visibility: default

Description: `StrNextChar` returns a pointer to the null-character that terminates the string `Str`

Errors: if `Str` is not properly terminated, an access violation may occur.

### 38.13.200 StrPas

Synopsis: Convert a null-terminated string to an ansistring.

Declaration: `function StrPas(Str: PChar) : String`

Visibility: default

Description: Converts a null terminated string in `Str` to an `Ansistring`, and returns this string. This string is NOT truncated at 255 characters as is the

Errors: None.

See also: `StrPCopy` ([1545](#)), `StrPLCopy` ([1546](#))

### 38.13.201 StrPCopy

Synopsis: Copy an ansistring to a null-terminated string.

Declaration: `function StrPCopy(Dest: PChar;Source: String) : PChar`

Visibility: default

Description: `StrPCopy` Converts the `Ansistring` in `Source` to a Null-terminated string, and copies it to `Dest`. `Dest` needs enough room to contain the string `Source`, i.e. `Length(Source)+1` bytes.

Errors: No checking is performed to see whether `Dest` points to enough memory to contain `Source`.

See also: `StrPLCopy` ([1546](#)), `StrPas` ([1545](#))

**38.13.202 StrPLCopy**

Synopsis: Copy a limited number of characters from an ansistring to a null-terminated string.

Declaration: `function StrPLCopy(Dest: PChar; Source: String; MaxLen: SizeUInt) : PChar`

Visibility: default

Description: `StrPLCopy` Converts maximally `MaxLen` characters of the Ansistring in `Source` to a Null-terminated string, and copies it to `Dest`. `Dest` needs enough room to contain the characters.

Errors: No checking is performed to see whether `Dest` points to enough memory to contain `L` characters of `Source`.

See also: `StrPCopy` ([1545](#))

**38.13.203 strpos**

Synopsis: Find position of one null-terminated substring in another.

Declaration: `function strpos(str1: pchar; str2: pchar) : pchar`

Visibility: default

Description: Returns a pointer to the first occurrence of `S2` in `S1`. If `S2` does not occur in `S1`, returns `Nil`.

Errors: None.

See also: `StrScan` ([1547](#)), `StrRScan` ([1546](#))

**Listing:** `./stringex/ex15.pp`

---

**Program** `Example15;`

**Uses** `strings;`

*{ Program to demonstrate the StrPos function. }*

**Const** `P : PChar = 'This is a PChar string.';`

`S : PChar = 'is';`

**begin**

`Writeln ('Position of ''is'' in P : ', sizeint(StrPos(P,S)) - sizeint(P));`

`end.`

---

**38.13.204 strscan**

Synopsis: Find last occurrence of a character in a null-terminated string.

Declaration: `function strscan(p: pchar; c: Char) : pchar`

Visibility: default

Description: Returns a pointer to the last occurrence of the character `C` in the null-terminated string `P`. If `C` does not occur, returns `Nil`.

For an example, see `StrScan` ([1547](#)).

Errors: None.

See also: `StrScan` ([1547](#)), `StrPos` ([1546](#))

**38.13.205 strscan**

Synopsis: Find first occurrence of a character in a null-terminated string.

Declaration: `function strscan(p: pchar; c: Char) : pchar`

Visibility: default

Description: Returns a pointer to the first occurrence of the character C in the null-terminated string P. If C does not occur, returns Nil.

Errors: None.

See also: StrRScan ([1546](#)), StrPos ([1546](#))

**Listing:** ./stringex/ex13.pp

---

**Program** Example13;

**Uses** strings;

*{ Program to demonstrate the StrScan and StrRScan functions. }*

**Const** P : PChar = 'This is a PCHAR string.';  
           S : Char = 's' ;

**begin**

**WriteLn** ('P, starting from first ''s'' : ', **StrScan**(P,s));

**WriteLn** ('P, starting from last ''s'' : ', **StrRScan**(P,s));

**end.**

---

**38.13.206 StrToBool**

Synopsis: Convert a string to a boolean value

Declaration: `function StrToBool(const S: String) : Boolean`

Visibility: default

Description: StrToBool will convert the string S to a boolean value. The string S can contain one of 'True', 'False' (case is ignored) or a numerical value. If it contains a numerical value, 0 is converted to False, all other values result in True. If the string S contains no valid boolean, then an EConvertError ([1572](#)) exception is raised.

Errors: On error, an EConvertError ([1572](#)) exception is raised.

See also: BoolToStr ([1463](#))

**38.13.207 StrToBoolDef**

Synopsis: Convert string to boolean value, returning default in case of error

Declaration: `function StrToBoolDef(const S: String; Default: Boolean) : Boolean`

Visibility: default

Description: StrToBoolDef tries to convert the string S to a boolean value, and returns the boolean value in case of success. In case S does not contain a valid boolean string, Default is returned.

See also: StrToBool ([1547](#)), TryStrToBool ([1564](#))

**38.13.208 StrToCurr**

Synopsis: Convert a string to a currency value

Declaration: `function StrToCurr(const S: String) : Currency`  
`function StrToCurr(const S: String;`  
`const FormatSettings: TFormatSettings) : Currency`

Visibility: default

Description: `StrToCurr` converts a string to a currency value and returns the value. The string should contain a valid currency amount, without currency symbol. If the conversion fails, an `EConvertError` (1572) exception is raised.

Errors: On error, an `EConvertError` (1572) exception is raised.

See also: `CurrToStr` (1469), `StrToCurrDef` (1548)

**38.13.209 StrToCurrDef**

Synopsis: Convert a string to a currency value, using a default value

Declaration: `function StrToCurrDef(const S: String; Default: Currency) : Currency`  
`function StrToCurrDef(const S: String; Default: Currency;`  
`const FormatSettings: TFormatSettings) : Currency`

Visibility: default

Description: `StrToCurrDef` converts a string to a currency value and returns the value. The string should contain a valid currency amount, without currency symbol. If the conversion fails, the fallback `Default` value is returned.

Errors: On error, the `Default` value is returned.

See also: `CurrToStr` (1469), `StrToCurr` (1548)

**38.13.210 StrToDate**

Synopsis: Convert a date string to a `TDateTime` value.

Declaration: `function StrToDate(const S: ShortString) : TDateTime`  
`function StrToDate(const S: AnsiString) : TDateTime`  
`function StrToDate(const S: ShortString; separator: Char) : TDateTime`  
`function StrToDate(const S: AnsiString; separator: Char) : TDateTime`  
`function StrToDate(const S: ShortString; const useformat: String;`  
`separator: Char) : TDateTime`  
`function StrToDate(const S: AnsiString; const useformat: String;`  
`separator: Char) : TDateTime`  
`function StrToDate(const S: PChar; Len: Integer; const useformat: String;`  
`separator: Char) : TDateTime`

Visibility: default

Description: `StrToDate` converts the string `S` to a `TDateTime` date value. The Date must consist of 1 to three digits, separated by the `DateSeparator` character. If two numbers are given, they are supposed to form the day and month of the current year. If only one number is given, it is supposed to represent the day of the current month. (This is *not* supported in Delphi)

The order of the digits (y/m/d, m/d/y, d/m/y) is determined from the `ShortDateFormat` variable.

**Errors:** On error (e.g. an invalid date or invalid character), an `EConvertError` exception is raised.

See also: [StrToTime \(1554\)](#), [DateToStr \(1473\)](#), [TimeToStr \(1560\)](#)

**Listing:** ./sysutex/ex19.pp

### Program Example19;

```
{ This program demonstrates the StrToDate function }
```

**Uses** `sysutils`;

```
Procedure TestStr (S : String);
```

**begin**

```
WriteLn (S, ' : ', DateToStr (StrToDate (S)));  
end;
```

## Begin

```

WriteIn ( 'ShortDateFormat ', ShortDateFormat );
TestStr ( DateTimeToStr ( Date ) );
TestStr ( '05'+DateSeparator+'05'+DateSeparator+'1999' );
TestStr ( '5'+DateSeparator+'5' );
TestStr ( '5' );
End.

```

### 38.13.211 StrToDateDef

### Synopsis: Convert string to date, returning a default value

```

Declaration: function StrToDateDef(const S: ShortString;const Defvalue: TDateTime)
              : TDateTime
function StrToDateDef(const S: ShortString;const Defvalue: TDateTime;
                      separator: Char) : TDateTime
function StrToDateDef(const S: AnsiString;const Defvalue: TDateTime)
              : TDateTime
function StrToDateDef(const S: AnsiString;const Defvalue: TDateTime;
                      separator: Char) : TDateTime

```

Visibility: default

**Description:** `StrToDateDef` tries to convert the string `S` to a valid `TDateTime` date value, and returns `DefValue` if `S` does not contain a valid date indication.

Errors: None.

See also: [StrToDate \(1548\)](#), [TryStrToDate \(1564\)](#), [StrToTimeDef \(1555\)](#)

### 38.13.212 StrToDateTime

**Synopsis:** Convert a date/time string to a `TDateTime` value.

```
Declaration: function StrToDateTime(const S: String) : TDateTime
function StrToDateTime(const s: ShortString;
                        const UseFormat: TFormatSettings) : TDateTime
function StrToDateTime(const s: AnsiString;
                        const UseFormat: TFormatSettings) : TDateTime
```

Visibility: default

**Description:** `StrToDateTime` converts the string `S` to a `TDateTime` date and time value. The date and time parts must be separated by a space.

For the date part, the same restrictions apply as for the `StrToDate` (1548) function: The Date must consist of 1 to three numbers, separated by the `DateSeparator` character. If two numbers are given, they are supposed to form the day and month of the current year. If only one number is given, it is supposed to represent the day of the current month. (This is *not* supported in Delphi)

The order of the 3 numbers (y/m/d, m/d/y, d/m/y) is determined from the `ShortDateFormat` variable.

**Errors:** On error (e.g. an invalid date or invalid character), an `EConvertError` exception is raised.

See also: `StrToDate` (1548), `StrToTime` (1554), `DateTimeToStr` (1471)

**Listing:** ./sysutex/ex20.pp

---

**Program** Example20;

*{ This program demonstrates the StrToDateTime function }*

**Uses** sysutils;

**Procedure** TestStr (S : **String**);

**begin**

**WriteIn** (S, ' : ', **DateTimeToStr**(**StrToDateTime**(S)));  
**end**;

**Begin**

**WriteIn** ( 'ShortDateFormat ', ShortDateFormat );  
    **TestStr**(**DateTimeToStr**(**Now**));  
    **TestStr**( '05-05-1999 15:50 ' );  
    **TestStr**( '5-5 13:30 ' );  
    **TestStr**( '5 1:30PM' );  
**End**.

---

### 38.13.213 StrToDateTimeDef

**Synopsis:** Convert string to date/time, returning a default value

**Declaration:** `function StrToDateTimeDef(const S: ShortString;`  
  `const Defvalue: TDateTime) : TDateTime`  
          `function StrToDateTimeDef(const S: AnsiString;const Defvalue: TDateTime)`  
  `: TDateTime`

Visibility: default

**Description:** `StrToDateTimeDef` tries to convert the string `S` to a valid `TDateTime` date and time value, and returns `DefValue` if `S` does not contain a valid date-time indication.

**Errors:** None.

See also: `StrToTimeDef` (1555), `StrToDateDef` (1549), `TryStrToDateTime` (1565), `StrToDateTime` (1549)



**38.13.214 StrToFloat**

**Synopsis:** Convert a string to a floating-point value.

**Declaration:** `function StrToFloat(const S: String) : Extended`  
`function StrToFloat(const S: String;`  
`const FormatSettings: TFormatSettings) : Extended`

**Visibility:** default

**Description:** `StrToFloat` converts the string `S` to a floating point value. `S` should contain a valid string representation of a floating point value (either in decimal or scientific notation). The `thousandseparator` character may however not be used.

Up to and including version 2.2.2 of the compiler, if the string contains a decimal value, then the decimal separator character can either be a '.' or the value of the `DecimalSeparator` variable.

As of version 2.3.1, the string may contain only the `DecimalSeparator` character. The dot ('.') can no longer be used instead of the `DecimalSeparator`.

**Errors:** If the string `S` doesn't contain a valid floating point string, then an exception will be raised.

See also: `TextToFloat` ([1557](#)), `FloatToStr` ([1499](#)), `FormatFloat` ([1511](#)), `StrToInt` ([1552](#))

**Listing:** `./sysutex/ex90.pp`

**Program** `Example90;`

```
{ This program demonstrates the StrToFloat function }
{$mode objfpc}
{$h+ }
```

**Uses** `SysUtils;`

**Const**

```
NrValues = 5;
TestStr : Array[1..NrValues] of string =
    ('1,1', '-0,2', '1,2E-4', '0', '1E4');
```

**Procedure** `Testit;`

**Var**

```
I : Integer;
E : Extended;
```

**begin**

```
  WriteLn('Using DecimalSeparator : ', DecimalSeparator);
  For I:=1 to NrValues do
    begin
      WriteLn('Converting : ', TestStr[I]);
      Try
        E:=StrToFloat(TestStr[I]);
        WriteLn('Converted value : ', E);
      except
        On E : Exception do
          WriteLn('Exception when converting : ', E.Message);
      end;
    end;
  end;
```

**end;**

**Begin**

---

```

DecimalSeparator:= ',';
Testit;

                                DecimalSeparator:= '.';
Testit;
End.
```

---

### 38.13.215 StrToFloatDef

Synopsis: Convert a string to a float, with a default value.

Declaration: `function StrToFloatDef(const S: String;const Default: Extended) : Extended`  
`function StrToFloatDef(const S: String;const Default: Extended; const FormatSettings: TFormatSettings) : Extended`

Visibility: default

Description: `StrToFloatDef` tries to convert the string `S` to a floating point value, and returns this value. If the conversion fails for some reason, the value `Default` is returned instead.

Errors: None. On error, the `Default` value is returned.

### 38.13.216 StrToInt

Synopsis: Convert a string to an integer value.

Declaration: `function StrToInt(const s: String) : Integer`

Visibility: default

Description: `StrToInt` will convert the string `Sto` to an integer. If the string contains invalid characters or has an invalid format, then an `EConvertError` is raised.

To be successfully converted, a string can contain a combination of numerical characters, possibly preceded by a minus sign (-). Spaces are not allowed.

Errors: In case of error, an `EConvertError` is raised.

See also: `IntToStr` ([1521](#)), `StrToIntDef` ([1553](#))

**Listing:** `./sysutex/ex82.pp`

---

**Program** `Example82;`

`{ $mode objfpc }`

`{ This program demonstrates the StrToInt function }`

**Uses** `sysutils;`

**Begin**

```

Writeln ( StrToInt( '1234' ));
Writeln ( StrToInt( '-1234' ));
Writeln ( StrToInt( '0' ));
Try
  Writeln ( StrToInt( '12345678901234567890' ));
except
  On E : EConvertError do
```

```

        WriteLn ( 'Invalid number encountered' );
    end;
End.

```

---

### 38.13.217 StrToInt64

Synopsis: Convert a string to an Int64 value.

Declaration: `function StrToInt64(const s: String) : Int64`

Visibility: default

Description: `StrToInt64` converts the string `S` to a `Int64` value, and returns this value. The string can only contain numerical characters, and optionally a minus sign as the first character. Whitespace is not allowed.

Hexadecimal values (starting with the `$` character) are supported.

Errors: On error, a `EConvertError` ([1572](#)) exception is raised.

See also: `TryStrToInt64` ([1566](#)), `StrToInt64Def` ([1553](#)), `StrToInt` ([1552](#)), `TryStrToInt` ([1566](#)), `StrToIntDef` ([1553](#))

### 38.13.218 StrToInt64Def

Synopsis: Convert a string to an Int64 value, with a default value

Declaration: `function StrToInt64Def(const S: String; Default: Int64) : Int64`

Visibility: default

Description: `StrToInt64Def` tries to convert the string `S` to a `Int64` value, and returns this value. If the conversion fails for some reason, the value `Default` is returned instead.

Errors: None. On error, the `Default` value is returned.

See also: `StrToInt64` ([1553](#)), `TryStrToInt64` ([1566](#)), `StrToInt` ([1552](#)), `TryStrToInt` ([1566](#)), `StrToIntDef` ([1553](#))

### 38.13.219 StrToIntDef

Synopsis: Convert a string to an integer value, with a default value.

Declaration: `function StrToIntDef(const S: String; Default: Integer) : Integer`

Visibility: default

Description: `StrToIntDef` will convert a string to an integer. If the string contains invalid characters or has an invalid format, then `Default` is returned.

To be successfully converted, a string can contain a combination of numerical characters, possibly preceded by a minus sign (`-`). Spaces are not allowed.

Errors: None.

See also: `IntToStr` ([1521](#)), `StrToInt` ([1552](#))

**Listing:** `./sysutex/ex83.pp`

---

```

Program Example82;

{$mode objfpc}

{ This program demonstrates the StrToInt function }

               Uses sysutils;

Begin
  WriteLn ( StrToIntDef( '1234' ,0));
  WriteLn ( StrToIntDef( '-1234' ,0));
  WriteLn ( StrToIntDef( '0' ,0));
  Try
    WriteLn ( StrToIntDef( '12345678901234567890' ,0));
  except
    On E : EConvertError do
      WriteLn ( 'Invalid number encountered' );
  end;
End.

```

---

### 38.13.220 StrToQWord

**Synopsis:** Convert a string to a QWord.

**Declaration:** `function StrToQWord(const s: String) : QWord`

**Visibility:** default

**Description:** `TryStrToQWord` converts the string `S` to a valid QWord (unsigned 64-bit) value, and returns the result.

**Errors:** If the string `S` does not contain a valid QWord value, a `EConvertError` ([1572](#)) exception is raised.

**See also:** `TryStrToQWord` ([1566](#)), `StrToQWordDef` ([1554](#)), `StrToInt64` ([1553](#)), `StrToInt` ([1552](#))

### 38.13.221 StrToQWordDef

**Synopsis:** Try to convert a string to a QWord, returning a default value in case of failure.

**Declaration:** `function StrToQWordDef(const S: String;Default: QWord) : QWord`

**Visibility:** default

**Description:** `StrToQWordDef` tries to convert the string `S` to a valid QWord (unsigned 64-bit) value, and returns the result. If the conversion fails, the function returns the value passed in `Def`.

**See also:** `StrToQWord` ([1554](#)), `TryStrToQWord` ([1566](#)), `StrToInt64Def` ([1553](#)), `StrToIntDef` ([1553](#))

### 38.13.222 StrToTime

**Synopsis:** Convert a time string to a `TDateTime` value.

**Declaration:** `function StrToTime(const S: Shortstring) : TDateTime`  
`function StrToTime(const S: Ansistring) : TDateTime`  
`function StrToTime(const S: ShortString;separator: Char) : TDateTime`  
`function StrToTime(const S: AnsiString;separator: Char) : TDateTime`

```
function StrToTime(const S: PChar; Len: Integer; separator: Char)
    : TDateTime
```

Visibility: default

**Description:** `StrToTime` converts the string `S` to a `TDateTime` time value. The time must consist of 1 to 4 digits, separated by the `TimeSeparator` character. If two numbers are given, they are supposed to form the hour and minutes.

**Errors:** On error (e.g. an invalid date or invalid character), an `EConvertError` exception is raised.

See also: `StrToDate` ([1548](#)), `StrToDateTime` ([1549](#)), `TimeToStr` ([1560](#))

**Listing:** `./sysutex/ex21.pp`

---

**Program** `Example21`;

*{ This program demonstrates the StrToTime function }*

**Uses** `sysutils`;

**Procedure** `TestStr` (`S` : **String**);

**begin**

**WriteLn** (`S`, ' : ', `TimeToStr(StrToTime(S))`);

**end**;

**Begin**

`teststr (TimeToStr(Time));`  
    `teststr ('12:00');`  
    `teststr ('15:30');`  
    `teststr ('3:30PM');`

**End.**

---

### 38.13.223 StrToTimeDef

**Synopsis:** Convert string to time, returning a default value

**Declaration:**

```
function StrToTimeDef(const S: ShortString; const Defvalue: TDateTime)
    : TDateTime
function StrToTimeDef(const S: ShortString; const Defvalue: TDateTime;
    separator: Char) : TDateTime
function StrToTimeDef(const S: AnsiString; const Defvalue: TDateTime)
    : TDateTime
function StrToTimeDef(const S: AnsiString; const Defvalue: TDateTime;
    separator: Char) : TDateTime
```

Visibility: default

**Description:** `StrToTimeDef` tries to convert the string `S` to a valid `TDateTime` time value, and returns `DefValue` if `S` does not contain a valid time indication.

**Errors:** None.

See also: `StrToTime` ([1554](#)), `TryStrToTime` ([1566](#)), `StrToDateDef` ([1549](#))

**38.13.224 strupper**

Synopsis: Convert null-terminated string to all-uppercase

Declaration: `function strupper(p: pchar) : pchar`

Visibility: default

Description: Converts P to an all-uppercase string. Returns P.

For an example, see `StrLower` ([1543](#))

Errors: None.

See also: `StrLower` ([1543](#))

**38.13.225 Supports**

Synopsis: Check whether a class or given interface supports an interface

```
Declaration: function Supports(const Instance: IInterface; const IID: TGUID; out Intf)
              : Boolean; Overload
function Supports(const Instance: TObject; const IID: TGUID; out Intf)
              : Boolean; Overload
function Supports(const Instance: TObject; const IID: Shortstring;
              out Intf) : Boolean; Overload
function Supports(const Instance: IInterface; const IID: TGUID) : Boolean
              ; Overload
function Supports(const Instance: TObject; const IID: TGUID) : Boolean
              ; Overload
function Supports(const Instance: TObject; const IID: Shortstring)
              : Boolean; Overload
function Supports(const AClass: TClass; const IID: TGUID) : Boolean
              ; Overload
function Supports(const AClass: TClass; const IID: Shortstring) : Boolean
              ; Overload
```

Visibility: default

Description: `Supports` checks whether `Instance` supports the interface identified by `IID`. It returns `True` if it is supported, `False`. Optionally, a pointer to the interface is returned to `Intf`.

Errors: None.

See also: `StringToGUID` ([1539](#))

**38.13.226 SysErrorMessage**

Synopsis: Format a system error message.

Declaration: `function SysErrorMessage(ErrorCode: Integer) : String`

Visibility: default

Description: `SysErrorMessage` returns a string that describes the operating system error code `ErrorCode`.

Errors: This routine may not be implemented on all platforms.

See also: `EOSError` ([1575](#))

**38.13.227 SystemTimeToDateTime**

Synopsis: Convert a system time to a TDateTime value.

Declaration: `function SystemTimeToDateTime(const SystemTime: TSystemTime) : TDateTime`

Visibility: default

Description: `SystemTimeToDateTime` converts a TSystemTime record to a TDateTime style date/time indication.

Errors: None.

See also: `DateTimeToSystemTime` ([1472](#))

**Listing:** ./sysutex/ex22.pp

---

**Program** Example22;

*{ This program demonstrates the SystemTimeToDateTime function }*

**Uses** sysutils;

**Var** ST : TSystemTime;

**Begin**

  DateTimeToSystemTime(**Now**, ST);

**With** St **do**

**begin**

**WriteLn** ( 'Today is       ', year, '/', month, '/', Day);

**WriteLn** ( 'The time is ', Hour, ':', minute, ':', Second, '.', MilliSecond);

**end**;

**WriteLn** ( 'Converted : ', **DateTimeToStr**(SystemTimeToDateTime(ST)));

**End.**

---

**38.13.228 TextToFloat**

Synopsis: Convert a buffer to a float value.

Declaration: `function TextToFloat(Buffer: PChar; out Value: Extended) : Boolean`  
`function TextToFloat(Buffer: PChar; out Value: Extended;`  
`const FormatSettings: TFormatSettings) : Boolean`  
`function TextToFloat(Buffer: PChar; out Value; ValueType: TFloatValue)`  
`: Boolean`  
`function TextToFloat(Buffer: PChar; out Value; ValueType: TFloatValue;`  
`const FormatSettings: TFormatSettings) : Boolean`

Visibility: default

Description: `TextToFloat` converts the string in Buffer to a floating point value. Buffer should contain a valid stroing representation of a floating point value (either in decimal or scientific notation). If the buffer contains a decimal value, then the decimal separator character can either be a '.' or the value of the DecimalSeparator variable.

The function returns True if the conversion was successful.

Errors: If there is an invalid character in the buffer, then the function returns False

See also: `StrToFloat` ([1551](#)), `FloatToStr` ([1499](#)), `FormatFloat` ([1511](#))

**Listing:** ./sysutex/ex91.pp

---

```

Program Example91;

{ This program demonstrates the TextToFloat function }
{$mode objfpc}
{$h+ }

Uses SysUtils;

Const
  NrValues = 5;
  TestStr : Array [1..NrValues] of pchar =
    ( '1,1 ', '-0,2 ', '1,2E-4', '0 ', '1E4' );

Procedure Testit;

Var
  I : Integer;
  E : Extended;

begin
  Writeln('Using DecimalSeparator : ',DecimalSeparator);
  For I:=1 to NrValues do
    begin
      Writeln('Converting : ',TestStr[I]);
      If TextToFloat(TestStr[I],E) then
        Writeln('Converted value : ',E)
      else
        Writeln('Unable to convert value. ');
      end;
    end;

Begin
  DecimalSeparator:= ',';
  Testit;
  DecimalSeparator:= '.';
  Testit;
End.

```

---

### 38.13.229 Time

**Synopsis:** Returns the current time.

**Declaration:** function Time : TDateTime

**Visibility:** default

**Description:** Time returns the current time in TDateTime format. The date part of the TDateTimeValue is set to zero.

**Errors:** None.

**See also:** Now ([1527](#)), Date ([1470](#))

**Listing:** ./sysutex/ex23.pp



---

```

Program Example23;

{ This program demonstrates the Time function }

Uses sysutils;

Begin
  WriteLn ( 'The time is : ', TimeToStr(Time));
End.

```

---

### 38.13.230 TimeStampToDateTime

**Synopsis:** Convert a TimeStamp value to a TDateTime value.

**Declaration:** `function TimeStampToDateTime(const TimeStamp: TTimeStamp) : TDateTime`

**Visibility:** default

**Description:** TimeStampToDateTime converts TimeStamp to a TDateTime format variable. It is the inverse operation of DateTimeToTimeStamp ([1473](#)).

**Errors:** None.

**See also:** DateTimeToTimeStamp ([1473](#)), TimeStampToMSecs ([1559](#))

**Listing:** ./sysutex/ex24.pp

---

```

Program Example24;

{ This program demonstrates the TimeStampToDateTime function }

Uses sysutils;

Var TS : TTimeStamp;
    DT : TDateTime;

Begin
  TS:=DateTimeToTimeStamp (Now);
  With TS do
    begin
      WriteLn ( 'Now is ', time, ' millisecond past midnight');
      WriteLn ( 'Today is ', Date, ' days past 1/1/0001');
    end;
  DT:=TimeStampToDateTime(TS);
  WriteLn ( 'Together this is : ', DateTimeToStr(DT));
End.

```

---

### 38.13.231 TimeStampToMSecs

**Synopsis:** Converts a timestamp to a number of milliseconds.

**Declaration:** `function TimeStampToMSecs(const TimeStamp: TTimeStamp) : comp`

**Visibility:** default

**Description:** `TimeStampToMSecs` converts `TimeStamp` to the number of seconds since 1/1/0001.

Use `TTimeStamp` variables if you need to keep very precise track of time.

For an example, see `MSecsToTimeStamp` ([1526](#)).

**Errors:** None.

See also: `MSecsToTimeStamp` ([1526](#)), `TimeStampToDateTime` ([1559](#))

### 38.13.232 TimeToStr

**Synopsis:** Convert a `TDateTime` time to a string using a predefined format.

**Declaration:**

```
function TimeToStr(Time: TDateTime) : String
function TimeToStr(Time: TDateTime;
                  const FormatSettings: TFormatSettings) : String
```

**Visibility:** default

**Description:** `TimeToStr` converts the time in `Time` to a string. It uses the `ShortTimeFormat` variable to see what formatting needs to be applied. It is therefor entirely equivalent to a `FormatDateTime('t', Time)` call.

**Errors:** None.

**Listing:** `./sysutex/ex25.pp`

---

**Program** `Example25`;

*{ This program demonstrates the TimeToStr function }*

**Uses** `sysutils`;

**Begin**

`WriteLn ('The current time is : ', TimeToStr(Time));`

**End.**

---

### 38.13.233 Trim

**Synopsis:** Trim whitespace from the ends of a string.

**Declaration:**

```
function Trim(const S: String) : String
function Trim(const S: widestring) : widestring
```

**Visibility:** default

**Description:** `Trim` strips blank characters (spaces) at the beginning and end of `S` and returns the resulting string. Only #32 characters are stripped.

If the string contains only spaces, an empty string is returned.

**Errors:** None.

See also: `TrimLeft` ([1561](#)), `TrimRight` ([1562](#))

**Listing:** `./sysutex/ex84.pp`

---

```

Program Example84;

{ This program demonstrates the Trim function }

Uses sysutils;
                                     {$H+}

Procedure Testit (S : String);

begin
    WriteLn ( ' ', Trim(S), ' ');
end;

Begin
    Testit ( '  ha ha what gets lost ? ');
    Testit (#10#13'haha ');
    Testit ( ' ');
End.

```

---

### 38.13.234 TrimLeft

Synopsis: Trim whitespace from the beginning of a string.

Declaration: `function TrimLeft(const S: String) : String`  
`function TrimLeft(const S: widestring) : widestring`

Visibility: default

Description: `TrimLeft` strips blank characters (spaces) at the beginning of S and returns the resulting string. Only #32 characters are stripped. If the string contains only spaces, an empty string is returned.

Errors: None.

See also: `Trim` ([1560](#)), `TrimRight` ([1562](#))

**Listing:** ./sysutex/ex85.pp

---

```

Program Example85;

{ This program demonstrates the TrimLeft function }

Uses sysutils;
                                     {$H+}

Procedure Testit (S : String);

begin
    WriteLn ( ' ', TrimLeft(S), ' ');
end;

Begin
    Testit ( '  ha ha what gets lost ? ');
    Testit (#10#13'haha ');
    Testit ( ' ');
End.

```

---

**38.13.235 TrimRight**

Synopsis: Trim whitespace from the end of a string.

Declaration: `function TrimRight(const S: String) : String`  
`function TrimRight(const S: widestring) : widestring`

Visibility: default

Description: `Trim` strips blank characters (spaces) at the end of `S` and returns the resulting string. Only #32 characters are stripped. If the string contains only spaces, an empty string is returned.

Errors: None.

See also: `Trim` ([1560](#)), `TrimLeft` ([1561](#))

**Listing:** `./sysutex/ex86.pp`

---

**Program** `Example86`;

*{ This program demonstrates the TrimRight function }*

**Uses** `sysutils`;  
`{ $H+ }`

**Procedure** `Testit (S : String)`;

**begin**  
`WriteLn ( ' ', TrimRight(S), ' ' );`  
**end**;

**Begin**  
`Testit ( ' ha ha what gets lost ? ' );`  
`Testit (#10#13'haha ' );`  
`Testit ( ' ' );`  
**End.**

---

**38.13.236 TryEncodeDate**

Synopsis: Try to encode a date, and indicate success.

Declaration: `function TryEncodeDate(Year: Word;Month: Word;Day: Word;`  
`out Date: TDateTime) : Boolean`

Visibility: default

Description: `TryEncodeDate` will check the validity of the `Year`, `Month` and `Day` arguments, and if they are all valid, then they will be encoded as a `TDateTime` value and returned in `D`. The function will return `True` in this case. If an invalid argument is passed, then `False` will be returned.

Errors: None. If an error occurs during the encoding, `False` is returned.

See also: `EncodeDate` ([1479](#)), `DecodeDateFully` ([1475](#)), `DecodeDate` ([1475](#)), `TryEncodeTime` ([1563](#))

**38.13.237 TryEncodeTime**

Synopsis: Try to encode a time, and indicate success.

Declaration: `function TryEncodeTime(Hour: Word;Min: Word;Sec: Word;MSec: Word;  
out Time: TDateTime) : Boolean`

Visibility: default

Description: `TryEncodeTime` will check the validity of the `Hour`, `Min`, `Sec` and `MSec` arguments, and will encode them in a `TDateTime` value which is returned in `T`. If the arguments are valid, then `True` is returned, otherwise `False` is returned.

Errors: None. If an error occurs during the encoding, `False` is returned.

See also: `EncodeTime` ([1480](#)), `DecodeTime` ([1475](#)), `TryEncodeDate` ([1562](#))

**38.13.238 TryFloatToCurr**

Synopsis: Try to convert a float value to a currency value and report on success.

Declaration: `function TryFloatToCurr(const Value: Extended;var AResult: Currency)  
: Boolean`

Visibility: default

Description: `TryFloatToCurr` tries convert the `Value` floating point value to a `Currency` value. If successful, the function returns `True` and the resulting currency value is returned in `AResult`. It checks whether `Value` is in the valid range of currencies (determined by `MinCurrency` ([1433](#)) and `MaxCurrency` ([1433](#))). If not, `False` is returned.

Errors: If `Value` is out of range, `False` is returned.

See also: `FloatToCurr` ([1498](#)), `MinCurrency` ([1433](#)), `MaxCurrency` ([1433](#))

**38.13.239 TryStringToGUID**

Synopsis: Try to transform a string to a GUID

Declaration: `function TryStringToGUID(const S: String;out Guid: TGUID) : Boolean`

Visibility: default

Description: `TryStringToGUID` tries to convert the string `S` to a `TGUID` value, returned in `GUID`. It returns `True` if the conversion succeeds, and `False` if the string `S` does not contain a valid GUID notation. The string `S` must be 38 characters long, must start with `{` and end on `}`, and contain a valid GUID string (hex number grouped using 8-4-4-4-12 digits).

Errors: In case `S` does not contain a valid GUID number, `False` is returned.

See also: `StringToGUID` ([1539](#))

**38.13.240 TryStrToBool**

Synopsis: Try to convert a string to a boolean value

Declaration: `function TryStrToBool(const S: String;out Value: Boolean) : Boolean`

Visibility: default

Description: `TryStrToBool` tries to convert the string `S` to a boolean value, and returns this value in `Value`. In this case, the function returns `True`. If `S` does not contain a valid boolean string, the function returns `False`, and the contents of `Value` is indetermined.

Valid boolean string constants are in the `FalseBoolStrs` (1443) (for `False` values) and `TrueBoolStrs` (1446) (for `True` values) variables.

See also: `StrToBool` (1547), `StrToBoolDef` (1547)

**38.13.241 TryStrToCurr**

Synopsis: Try to convert a string to a currency

Declaration: `function TryStrToCurr(const S: String;out Value: Currency) : Boolean`  
`function TryStrToCurr(const S: String;out Value: Currency;`  
`const FormatSettings: TFormatSettings) : Boolean`

Visibility: default

Description: `TryStrToCurr` converts the string `S` to a currency value and returns the value in `Value`. The function returns `True` if it was successful, `False` if not. This is contrary to `StrToCurr` (1548), which raises an exception when the conversion fails.

The function takes into account locale information.

See also: `StrToCurr` (1548), `TextToFloat` (1557)

**38.13.242 TryStrToDate**

Synopsis: Try to convert a string with a date indication to a `TDateTime` value

Declaration: `function TryStrToDate(const S: ShortString;out Value: TDateTime)`  
`: Boolean`  
`function TryStrToDate(const S: AnsiString;out Value: TDateTime)`  
`: Boolean`  
`function TryStrToDate(const S: ShortString;out Value: TDateTime;`  
`separator: Char) : Boolean`  
`function TryStrToDate(const S: AnsiString;out Value: TDateTime;`  
`separator: Char) : Boolean`  
`function TryStrToDate(const S: ShortString;out Value: TDateTime;`  
`const useformat: String;separator: Char) : Boolean`  
`function TryStrToDate(const S: AnsiString;out Value: TDateTime;`  
`const useformat: String;separator: Char) : Boolean`  
`function TryStrToDate(const S: String;out Value: TDateTime;`  
`const FormatSettings: TFormatSettings) : Boolean`

Visibility: default

**Description:** `TryStrToDate` tries to convert the string `S` to a `TDateTime` date value, and stores the date in `Value`. The Date must consist of 1 to three digits, separated by the `DateSeparator` character. If two numbers are given, they are supposed to form the day and month of the current year. If only one number is given, it is supposed to represent the day of the current month. (This is *not* supported in Delphi)

The order of the digits (y/m/d, m/d/y, d/m/y) is determined from the `ShortDateFormat` variable.

The function returns `True` if the string contained a valid date indication, `False` otherwise.

See also: `StrToDate` (1548), `StrToTime` (1554), `TryStrToTime` (1566), `TryStrToDateTime` (1565), `DateToStr` (1473), `TimeToStr` (1560)

### 38.13.243 TryStrToDateTime

**Synopsis:** Try to convert a string with date/time indication to a `TDateTime` value

**Declaration:**

```
function TryStrToDateTime(const S: ShortString;out Value: TDateTime)
    : Boolean
function TryStrToDateTime(const S: AnsiString;out Value: TDateTime)
    : Boolean
function TryStrToDateTime(const S: String;out Value: TDateTime;
    const FormatSettings: TFormatSettings)
    : Boolean
```

**Visibility:** default

**Description:** `TryStrToDateTime` tries to convert the string `S` to a `TDateTime` date and time value, and stores the result in `Value`. The date must consist of 1 to three digits, separated by the `DateSeparator` character. If two numbers are given, they are supposed to form the day and month of the current year. If only one number is given, it is supposed to represent the day of the current month (This is *not* supported in Delphi). The time must consist of 1 to 4 digits, separated by the `TimeSeparator` character. If two numbers are given, they are supposed to form the hour and minutes.

The function returns `True` if the string contained a valid date and time indication, `False` otherwise.

See also: `TryStrToDate` (1564), `TryStrToTime` (1566), `StrToDateTime` (1549), `StrToTime` (1554), `DateToStr` (1473), `TimeToStr` (1560)

### 38.13.244 TryStrToFloat

**Synopsis:** Try to convert a string to a float.

**Declaration:**

```
function TryStrToFloat(const S: String;out Value: Single) : Boolean
function TryStrToFloat(const S: String;out Value: Single;
    const FormatSettings: TFormatSettings) : Boolean
function TryStrToFloat(const S: String;out Value: Double) : Boolean
function TryStrToFloat(const S: String;out Value: Double;
    const FormatSettings: TFormatSettings) : Boolean
```

**Visibility:** default

**Description:** `TryStrToFloat` tries to convert the string `S` to a floating point value, and stores the result in `Value`. It returns `True` if the operation was succesful, and `False` if it failed. This operation takes into account the system settings for floating point representations.

**Errors:** On error, `False` is returned.

See also: `StrToFloat` (1551)

**38.13.245 TryStrToInt**

Synopsis: Try to convert a string to an integer, and report on success.

Declaration: `function TryStrToInt(const s: String; out i: Integer) : Boolean`

Visibility: default

Description: `TryStrToInt` tries to convert the string `S` to an integer, and returns `True` if this was successful. In that case the converted integer is returned in `I`. If the conversion failed, (an invalid string, or the value is out of range) then `False` is returned.

Errors: None. On error, `False` is returned.

See also: `StrToInt` ([1552](#)), `TryStrToInt64` ([1566](#)), `StrToIntDef` ([1553](#)), `StrToInt64` ([1553](#)), `StrToInt64Def` ([1553](#))

**38.13.246 TryStrToInt64**

Synopsis: Try to convert a string to an int64 value, and report on success.

Declaration: `function TryStrToInt64(const s: String; out i: Int64) : Boolean`

Visibility: default

Description: `TryStrToInt64` tries to convert the string `S` to a `Int64` value, and returns this value in `I` if successful. If the conversion was successful, the function result is `True`, or `False` otherwise. The string can only contain numerical characters, and optionally a minus sign as the first character. Whitespace is not allowed.

Hexadecimal values (starting with the `$` character) are supported.

Errors: None. On error, `False` is returned.

See also: `StrToInt64` ([1553](#)), `StrToInt64Def` ([1553](#)), `StrToInt` ([1552](#)), `TryStrToInt` ([1566](#)), `StrToIntDef` ([1553](#))

**38.13.247 TryStrToQWord**

Synopsis: Try to convert a string to a QWord value, and report on success

Declaration: `function TryStrToQWord(const s: String; out Q: QWord) : Boolean`

Visibility: default

Description: `TryStrToQWord` tries to convert the string `S` to a valid `QWord` (unsigned 64-bit) value, and stores the result in `I`. If the conversion fails, the function returns `False`, else it returns `True`.

See also: `StrToQWord` ([1554](#)), `StrToQWordDef` ([1554](#)), `TryStrToInt64` ([1566](#)), `TryStrToInt` ([1566](#))

**38.13.248 TryStrToTime**

Synopsis: Try to convert a string with a time indication to a `TDateTime` value

```
Declaration: function TryStrToTime(const S: ShortString; out Value: TDateTime)
              : Boolean
function TryStrToTime(const S: AnsiString; out Value: TDateTime)
              : Boolean
function TryStrToTime(const S: ShortString; out Value: TDateTime;
              separator: Char) : Boolean
function TryStrToTime(const S: AnsiString; out Value: TDateTime;
```



```

        separator: Char) : Boolean
function TryStrToTime(const S: String;out Value: TDateTime;
        const FormatSettings: TFormatSettings) : Boolean

```

Visibility: default

**Description:** TryStrToTime tries to convert the string S to a TDateTime time value, and stores the result in Value. The time must consist of 1 to 4 digits, separated by the TimeSeparator character. If two numbers are given, they are supposed to form the hour and minutes.

The function returns True if the string contained a valid time indication, False otherwise.

See also: TryStrToDate ([1564](#)), TryStrToDateTime ([1565](#)), StrToDate ([1548](#)), StrToTime ([1554](#)), DateToStr ([1473](#)), TimeToStr ([1560](#))

### 38.13.249 UnhookSignal

**Synopsis:** UnHook a specified signal

**Declaration:** procedure UnhookSignal(RtlSigNum: Integer;OnlyIfHooked: Boolean)

Visibility: default

**Description:** UnHookSignal de-installs the RTL default signal handler for signal RtlSigNum. If OnlyIfHooked is True then UnhookSignal will first check if the signal was hooked by the RTL routines, and has not been overridden since.

### 38.13.250 UpperCase

**Synopsis:** Return an uppercase version of a string.

**Declaration:** function UpperCase(const s: String) : String

Visibility: default

**Description:** UpperCase returns the uppercase equivalent of S. Ansi characters are not taken into account, only ASCII codes below 127 are converted. It is completely equivalent to the UpCase function of the system unit, and is provided for compatibility only.

Errors: None.

See also: AnsiLowerCase ([1452](#)), LowerCase ([1525](#)), AnsiUpperCase ([1460](#))

**Listing:** ./sysutex/ex87.pp

---

**Program** Example87;

*{ This program demonstrates the UpperCase function }*

**Uses** sysutils;

**Begin**

    WriteLn (UpperCase('this will come OUT ALL uPpErCaSe !'));

**End.**

---

**38.13.251 VendorName**

Synopsis: Returns the application vendor name.

Declaration: `function VendorName : String`

Visibility: default

Description: `VendorName` returns the application vendor name. This function does not do anything by itself, but uses the `OnGetVendorName` (1445) callback to get the application vendor name.

Errors: If `OnGetVendorName` (1445) is not set, an empty string is returned.

See also: `OnGetVendorName` (1445), `TGetVendorNameEvent` (1440)

**38.13.252 WideCompareStr**

Synopsis: Compare two widestrings (case sensitive)

Declaration: `function WideCompareStr(const s1: WideString;const s2: WideString)  
: PtrInt`

Visibility: default

Description: `WideCompareStr` compares two widestrings and returns the following result:

< 0 if `S1 < S2`.

0 if `S1 = S2`.

> 0 if `S1 > S2`.

The comparison takes into account wide characters, i.e. it takes care of strange accented characters. Contrary to `WideCompareText` (1568), the comparison is case sensitive.

Errors: None.

See also: `WideCompareText` (1568), `WideSameStr` (1570), `WideSameText` (1570)

**38.13.253 WideCompareText**

Synopsis: Compare two widestrings (ignoring case).

Declaration: `function WideCompareText(const s1: WideString;const s2: WideString)  
: PtrInt`

Visibility: default

Description: `WideCompareStr` compares two widestrings and returns the following result:

< 0 if `S1 < S2`.

0 if `S1 = S2`.

> 0 if `S1 > S2`.

The comparison takes into account wide characters, i.e. it takes care of strange accented characters. Contrary to `WideCompareStr` (1568), the comparison is case insensitive.

Errors: None.

See also: `WideCompareStr` (1568), `WideSameStr` (1570), `WideSameText` (1570)

**38.13.254 WideFmtStr**

Synopsis: Widestring format

Declaration: `procedure WideFmtStr(var Res: WideString; const Fmt: WideString;  
                                   const args: Array of const)  
           procedure WideFmtStr(var Res: WideString; const Fmt: WideString;  
                                   const args: Array of const;  
                                   const FormatSettings: TFormatSettings)`

Visibility: default

Description: `WideFmtStr` formats `Args` according to the format string in `Fmt` and returns the resulting string in `Res`.

See also: `WideFormat` ([1569](#)), `WideFormatBuf` ([1569](#)), `Format` ([1504](#))

**38.13.255 WideFormat**

Synopsis: Format a wide string.

Declaration: `function WideFormat(const Fmt: WideString; const Args: Array of const)  
                                   : WideString  
           function WideFormat(const Fmt: WideString; const Args: Array of const;  
                                   const FormatSettings: TFormatSettings) : WideString`

Visibility: default

Description: `WideFormat` does the same as `Format` ([1504](#)) but accepts as a formatting string a `WideString`. The resulting string is also a `WideString`.

For more information about the used formatting characters, see the `Format` ([1504](#)) string.

See also: `Format` ([1504](#))

**38.13.256 WideFormatBuf**

Synopsis: Format widestring in a buffer.

Declaration: `function WideFormatBuf(var Buffer; BufLen: Cardinal; const Fmt;  
                                   fmtLen: Cardinal; const Args: Array of const)  
                                   : Cardinal  
           function WideFormatBuf(var Buffer; BufLen: Cardinal; const Fmt;  
                                   fmtLen: Cardinal; const Args: Array of const;  
                                   const FormatSettings: TFormatSettings) : Cardinal`

Visibility: default

Description: `WideFormatBuf` calls simply `WideFormat` ([1569](#)) with `Fmt` (with length `FmtLen` bytes) and stores maximum `BufLen` bytes in the buffer `buf`. It returns the number of copied bytes.

See also: `WideFmtStr` ([1569](#)), `WideFormat` ([1569](#)), `Format` ([1504](#)), `FormatBuf` ([1509](#))

**38.13.257 WideLowerCase**

Synopsis: Change a widestring to all-lowercase.

Declaration: `function WideLowerCase(const s: WideString) : WideString`

Visibility: default

Description: `WideLowerCase` converts the string `S` to lowercase characters and returns the resulting string. It takes into account the operating system language settings when doing this, so special characters are converted correctly as well.

**Remark:** On Unix-like platforms, a widestring manager must be installed for this function to work correctly.

Errors: None.

See also: `WideUpperCase` ([1570](#))

**38.13.258 WideSameStr**

Synopsis: Check whether two widestrings are the same (case sensitive)

Declaration: `function WideSameStr(const s1: WideString; const s2: WideString)  
: Boolean`

Visibility: default

Description: `WideSameStr` returns `True` if `WideCompareStr` ([1568](#)) returns 0 (zero), i.e. when `S1` and `S2` are the same string (taking into account case).

See also: `WideSameText` ([1570](#)), `WideCompareStr` ([1568](#)), `WideCompareText` ([1568](#)), `AnsiSameStr` ([1453](#))

**38.13.259 WideSameText**

Synopsis: Check whether two widestrings are the same (ignoring case)

Declaration: `function WideSameText(const s1: WideString; const s2: WideString)  
: Boolean`

Visibility: default

Description: `WideSameText` returns `True` if `WideCompareText` ([1568](#)) returns 0 (zero), i.e. when `S1` and `S2` are the same string (taking into account case).

See also: `WideSameStr` ([1570](#)), `WideCompareStr` ([1568](#)), `WideCompareText` ([1568](#)), `AnsiSameText` ([1453](#))

**38.13.260 WideUpperCase**

Synopsis: Change a widestring to all-lowercase.

Declaration: `function WideUpperCase(const s: WideString) : WideString`

Visibility: default

Description: `WideUpperCase` converts the string `S` to uppercase characters and returns the resulting string. It takes into account the operating system language settings when doing this, so special characters are converted correctly as well.

**Remark:** On Unix-like platforms, a widestring manager must be installed for this function to work correctly.

Errors: None.

See also: `WideLowerCase` ([1570](#))

### 38.13.261 WrapText

Synopsis: Word-wrap a text.

Declaration: 

```
function WrapText(const Line: String;const BreakStr: String;  
                const BreakChars: TSysCharSet;MaxCol: Integer) : String  
function WrapText(const Line: String;MaxCol: Integer) : String
```

Visibility: default

Description: `WrapText` does a wordwrap at column `MaxCol` of the string in `Line`. It breaks the string only at characters which are in `BreakChars` (default whitespace and hyphen) and inserts then the string `BreakStr` (default the lineending character for the current OS).

See also: `StringReplace` ([1539](#))

## 38.14 EAbort

### 38.14.1 Description

`Abort` is raised by the `Abort` ([1446](#)) procedure. It is not displayed in GUI applications, and serves only to immediatly abort the current procedure, and return control to the main program loop.

## 38.15 EAbstractError

### 38.15.1 Description

`EAbstractError` is raised when an abstract error occurs, i.e. when an unimplemented abstract method is called.

## 38.16 EAccessViolation

### 38.16.1 Description

`EAccessViolation` is raised when the OS reports an Access Violation, i.e. when invalid memory is accessed.

## 38.17 EAssertionFailed

### 38.17.1 Description

`EAssertionFailed` is raised when an application that is compiled with assertions, encounters an invalid assertion.

## 38.18 EBusError

### 38.18.1 Description

`EBusError` is raised in case of a bus error.

## 38.19 EControlC

### 38.19.1 Description

EControlC is raised when the user has pressed CTRL-C in a console application.

## 38.20 EConvertError

### 38.20.1 Description

EConvertError is raised by the various conversion routines in the SysUtils unit. The message will contain more specific error information.

## 38.21 EDivByZero

### 38.21.1 Description

EDivByZero is used when the operating system or CPU signals a division by zero error.

## 38.22 EExternal

### 38.22.1 Description

EExternal is the base exception for all external exceptions, as reported by the CPU or operating system, as opposed to internal exceptions, which are raised by the program itself. The SysUtils unit converts all operating system errors to descendants of EExternal.

## 38.23 EExternalException

### 38.23.1 Description

EExternalException is raised when an external routine raises an exception.

## 38.24 EFormatError

### 38.24.1 Description

EformatError is raised in case of an error in one of the various Format ([1504](#)) functions.

## 38.25 EHeapMemoryError

### 38.25.1 Description

EHeapMemoryError is raised when an error occurs in heap (dynamically allocated) memory.

### 38.25.2 Method overview

Page	Property	Description
<a href="#">1573</a>	<code>FreeInstance</code>	Free the exception instance

### 38.25.3 `EHeapMemoryError.FreeInstance`

Synopsis: Free the exception instance

Declaration: `procedure FreeInstance; Override`

Visibility: `public`

Description: `FreeInstance` checks whether the exception instance may be freed prior to calling the inherited `FreeInstance`. The exception is only freed in case of normal program shutdown, if a heap error occurred, the exception instance is not freed.

## 38.26 `EInOutError`

### 38.26.1 Description

`EInOutError` is raised when a IO routine of Free Pascal returns an error. The error is converted to an `EInOutError` only if the input/output checking feature of FPC is turned on. The error code of the input/output operation is returned in `ErrorCode` (??).

## 38.27 `EInterror`

### 38.27.1 Description

`EInterror` is used when the operating system or CPU signals an integer operation error, e.g., an overflow.

## 38.28 `EIntfCastError`

### 38.28.1 Description

`EIntfCastError` is raised when an invalid interface cast is encountered.

## 38.29 `EIntOverflow`

### 38.29.1 Description

`EIntOverflow` is used when the operating system or CPU signals a integer overflow error.

## 38.30 `EInvalidCast`

### 38.30.1 Description

`EInvalidCast` is raised when an invalid typecast error (using the `as` operator) is encountered.

### 38.31 EInvalidContainer

#### 38.31.1 Description

EInvalidContainer is not yet used by Free Pascal, and is provided for Delphi compatibility only.

### 38.32 EInvalidInsert

#### 38.32.1 Description

EInvalidInsert is not yet used by Free Pascal, and is provided for Delphi compatibility only.

### 38.33 EInvalidOp

#### 38.33.1 Description

EInvalidOp is raised when an invalid operation is encountered.

### 38.34 EInvalidPointer

#### 38.34.1 Description

EInvalidPointer is raised when an invalid heap pointer is used.

### 38.35 EMathError

#### 38.35.1 Description

EMathError is used when the operating system or CPU signals a floating point overflow error.

### 38.36 ENoThreadSupport

#### 38.36.1 Description

ENoThreadSupport is raised when some thread routines are invoked, and thread support was not enabled when the program was compiled.

### 38.37 ENoWideStringSupport

#### 38.37.1 Description

ENoWideStringSupport is the exception raised when a run-time 233 occurs, i.e. when widestring routines are called and the application does not contain widestring support.



## **38.38 EOSError**

### **38.38.1 Description**

`EOSError` is raised when some Operating System call fails. The `ErrorCode` (??) property contains the operating system error code.

## **38.39 EOutOfMemory**

### **38.39.1 Description**

`EOutOfMemory` occurs when memory can no longer be allocated on the heap. An instance of `EOutOfMemory` is allocated on the heap at program startup, so it is available when needed.

## **38.40 EOverflow**

### **38.40.1 Description**

`EOverflow` occurs when a float operation overflows. (i.e. result is too big to represent).

## **38.41 EPackageError**

### **38.41.1 Description**

`EPackageError` is not yet used by Free Pascal, and is provided for Delphi compatibility only.

## **38.42 EPrivilege**

### **38.42.1 Description**

`EPrivilege` is raised when the OS reports that an invalid instruction was executed.

## **38.43 EPropReadOnly**

### **38.43.1 Description**

`EPropReadOnly` is raised when an attempt is made to write to a read-only property.

## **38.44 EPropWriteOnly**

### **38.44.1 Description**

`EPropWriteOnly` is raised when an attempt is made to read from a write-only property.

## 38.45 ERangeError

### 38.45.1 Description

`ERangeError` is raised by the Free Pascal runtime library if range checking is on, and a range check error occurs.

## 38.46 ESafecallException

### 38.46.1 Description

`ESafecallException` is not yet used by Free Pascal, and is provided for Delphi compatibility only.

## 38.47 EStackOverflow

### 38.47.1 Description

`EStackOverflow` occurs when the stack has grown too big (e.g. by infinite recursion).

## 38.48 EUnderflow

### 38.48.1 Description

`EOverflow` occurs when a float operation underflows (i.e. result is too small to represent).

## 38.49 EVariantError

### 38.49.1 Description

`EVariantError` is raised by the internal variant routines.

### 38.49.2 Method overview

Page	Property	Description
<a href="#">1576</a>	<code>CreateCode</code>	Create an instance of <code>EVariantError</code> with a particular error code.

### 38.49.3 EVariantError.CreateCode

Synopsis: Create an instance of `EVariantError` with a particular error code.

Declaration: `constructor CreateCode (Code: LongInt)`

Visibility: default

Description: `CreateCode` calls the inherited constructor, and sets the `ErrCode` (??) property to `Code`.

See also: `EVariantError.ErrCode` (??)

## 38.50 Exception

### 38.50.1 Description

`Exception` is the base class for all exception handling routines in the RTL and FCL. While it is possible to raise an exception with any class descending from `TObject`, it is recommended to use `Exception` as the basis of exception class objects: the `Exception` class introduces properties to associate a message and a help context with the exception being raised. What is more, the `SysUtils` unit sets the necessary hooks to catch and display unhandled exceptions: in such cases, the message displayed to the end user, will be the message stored in the exception class.

### 38.50.2 Method overview

Page	Property	Description
<a href="#">1577</a>	<code>Create</code>	Constructs a new exception object with a given message.
<a href="#">1577</a>	<code>CreateFmt</code>	Constructs a new exception object and formats a new message.
<a href="#">1578</a>	<code>CreateFmtHelp</code>	Constructs a new exception object and sets the help context and formats the message
<a href="#">1578</a>	<code>CreateHelp</code>	Constructs a new exception object and sets the help context.
<a href="#">1578</a>	<code>CreateRes</code>	Constructs a new exception object and gets the message from a resource.
<a href="#">1578</a>	<code>CreateResFmt</code>	Constructs a new exception object and formats the message from a resource.
<a href="#">1579</a>	<code>CreateResFmtHelp</code>	Constructs a new exception object and sets the help context and formats the message from a resource
<a href="#">1579</a>	<code>CreateResHelp</code>	Constructs a new exception object and sets the help context and gets the message from a resource

### 38.50.3 Property overview

Page	Property	Access	Description
<a href="#">1579</a>	<code>HelpContext</code>	rw	Help context associated with the exception.
<a href="#">1579</a>	<code>Message</code>	rw	Message associated with the exception.

### 38.50.4 `Exception.Create`

Synopsis: Constructs a new exception object with a given message.

Declaration: `constructor Create(const msg: String)`

Visibility: `public`

Errors: Construction may fail if there is not enough memory on the heap.

See also: `Exception.CreateFmt` ([1577](#)), `Exception.Message` ([1579](#))

### 38.50.5 `Exception.CreateFmt`

Synopsis: Constructs a new exception object and formats a new message.

Declaration: `constructor CreateFmt(const msg: String; const args: Array of const)`

Visibility: `public`

Errors: Construction may fail if there is not enough memory on the heap.

See also: [Exception.Create \(1577\)](#), [Exception.Message \(1579\)](#), [Format \(1504\)](#)

### 38.50.6 Exception.CreateRes

Synopsis: Constructs a new exception object and gets the message from a resource.

Declaration: `constructor CreateRes (ResString: PString)`

Visibility: `public`

Errors: Construction may fail if there is not enough memory on the heap.

See also: [Exception.Create \(1577\)](#), [Exception.CreateFmt \(1577\)](#), [Exception.CreateResFmt \(1578\)](#), [Exception.Message \(1579\)](#)

### 38.50.7 Exception.CreateResFmt

Synopsis: Constructs a new exception object and formats the message from a resource.

Declaration: `constructor CreateResFmt (ResString: PString; const Args: Array of const)`

Visibility: `public`

Description: `CreateResFmt` does the same as [CreateFmt \(1577\)](#), but fetches the message from the resource string `ResString`.

Errors: Construction may fail if there is not enough memory on the heap.

See also: [Exception.Create \(1577\)](#), [Exception.CreateFmt \(1577\)](#), [Exception.CreateRes \(1578\)](#), [Exception.Message \(1579\)](#)

### 38.50.8 Exception.CreateHelp

Synopsis: Constructs a new exception object and sets the help context.

Declaration: `constructor CreateHelp (const Msg: String; AHelpContext: Integer)`

Visibility: `public`

Description: `CreateHelp` does the same as the [Create \(1577\)](#) constructor, but additionally stores `AHelpContext` in the `HelpContext (1579)` property.

See also: [Exception.Create \(1577\)](#)

### 38.50.9 Exception.CreateFmtHelp

Synopsis: Constructs a new exception object and sets the help context and formats the message

Declaration: `constructor CreateFmtHelp (const Msg: String; const Args: Array of const; AHelpContext: Integer)`

Visibility: `public`

Description: `CreateFmtHelp` does the same as the [CreateFmt \(1577\)](#) constructor, but additionally stores `AHelpContext` in the `HelpContext (1579)` property.

See also: [Exception.CreateFmt \(1577\)](#)

### 38.50.10 Exception.CreateResHelp

Synopsis: Constructs a new exception object and sets the help context and gets the message from a resource

Declaration: `constructor CreateResHelp(ResString: PString; AHelpContext: Integer)`

Visibility: public

Description: `CreateResHelp` does the same as the `CreateRes` (1578) constructor, but additionally stores `AHelpContext` in the `HelpContext` (1579) property.

See also: `Exception.CreateRes` (1578)

### 38.50.11 Exception.CreateResFmtHelp

Synopsis: Constructs a new exception object and sets the help context and formats the message from a resource

Declaration: `constructor CreateResFmtHelp(ResString: PString;  
const Args: Array of const;  
AHelpContext: Integer)`

Visibility: public

Description: `CreateResFmtHelp` does the same as the `CreateResFmt` (1578) constructor, but additionally stores `AHelpContext` in the `HelpContext` (1579) property.

See also: `Exception.CreateResFmt` (1578)

### 38.50.12 Exception.HelpContext

Synopsis: Help context associated with the exception.

Declaration: `Property HelpContext : LongInt`

Visibility: public

Access: Read, Write

Description: `HelpContext` is the help context associated with the exception, and can be used to provide context-sensitive help when the exception error message is displayed. It should be set in the exception constructor.

See also: `Exception.CreateHelp` (1578), `Exception.Message` (1579)

### 38.50.13 Exception.Message

Synopsis: Message associated with the exception.

Declaration: `Property Message : String`

Visibility: public

Access: Read, Write

Description: `Message` provides additional information about the exception. It is shown to the user in e.g. the `ShowException` (1532) routine, and should be set in the constructor when the exception is raised.

See also: `Exception.Create` (1577), `Exception.HelpContext` (1579)

## 38.51 EZeroDivide

### 38.51.1 Description

EZeroDivide occurs when a float division by zero occurs.

## 38.52 IReadWriteSync

### 38.52.1 Description

IReadWriteSync is an interface for synchronizing read/write operations. Writers are always guaranteed to have exclusive access: readers may or may not have simultaneous access, depending on the implementation.

### 38.52.2 Method overview

Page	Property	Description
<a href="#">1580</a>	BeginRead	Start a read operation.
<a href="#">1581</a>	BeginWrite	Start a write operation.
<a href="#">1580</a>	EndRead	End a read operation
<a href="#">1581</a>	EndWrite	End a write operation.

### 38.52.3 IReadWriteSync.BeginRead

Synopsis: Start a read operation.

Declaration: `procedure BeginRead`

Visibility: default

Description: `BeginRead` indicates that a read operation is about to be started. If a write operation is in progress, then the call will block until the write operation finished. Depending on the implementation the call may also block if another read operation is in progress.

After `BeginRead`, any write operation started with `BeginWrite` ([1581](#)) will block until `EndRead` ([1580](#)) is called.

See also: `IReadWriteSync.EndRead` ([1580](#)), `IReadWriteSync.BeginWrite` ([1581](#)), `IReadWriteSync.EndWrite` ([1581](#))

### 38.52.4 IReadWriteSync.EndRead

Synopsis: End a read operation

Declaration: `procedure EndRead`

Visibility: default

Description: `EndRead` signals the end of a read operation. If there was any blocked write operation, that will be unblocked by a call to `EndRead`.

See also: `IReadWriteSync.BeginRead` ([1580](#)), `IReadWriteSync.BeginWrite` ([1581](#)), `IReadWriteSync.EndWrite` ([1581](#))

### 38.52.5 IReadWriteSync.BeginWrite

Synopsis: Start a write operation.

Declaration: `function BeginWrite : Boolean`

Visibility: `default`

Description: `BeginWrite` signals the begin of a write operation. This call will block if any other read or write operation is currently in progress. It will resume only after all other read or write operations have finished.

See also: `IReadWriteSync.EndRead` ([1580](#)), `IReadWriteSync.EndWrite` ([1581](#)), `IReadWriteSync.BeginRead` ([1580](#))

### 38.52.6 IReadWriteSync.EndWrite

Synopsis: End a write operation.

Declaration: `procedure EndWrite`

Visibility: `default`

Description: `EndWrite` signals the end of a write operation. After the call to `EndWrite` any other read or write operations can start.

See also: `IReadWriteSync.EndRead` ([1580](#)), `IReadWriteSync.EndWrite` ([1581](#)), `IReadWriteSync.BeginRead` ([1580](#))

## 38.53 TMultiReadExclusiveWriteSynchronizer

### 38.53.1 Description

`TMultiReadExclusiveWriteSynchronizer` is a default implementation of the `IReadWriteSync` ([1580](#)) interface. It uses a single mutex to protect access to the read/write resource, resulting in a single thread having access to the resource.

### 38.53.2 Method overview

Page	Property	Description
<a href="#">1583</a>	<code>Beginread</code>	Request read access to the resource
<a href="#">1582</a>	<code>Beginwrite</code>	Request write access to the resource.
<a href="#">1581</a>	<code>Create</code>	Create a new instance of the <code>TMultiReadExclusiveWriteSynchronizer</code> class
<a href="#">1582</a>	<code>Destroy</code>	Destroys the <code>TMultiReadExclusiveWriteSynchronizer</code> instance
<a href="#">1583</a>	<code>Endread</code>	Release read access to the resource
<a href="#">1582</a>	<code>Endwrite</code>	Release write access to the resource

### 38.53.3 TMultiReadExclusiveWriteSynchronizer.Create

Synopsis: Create a new instance of the `TMultiReadExclusiveWriteSynchronizer` class

Declaration: `constructor Create; Virtual`

Visibility: `public`

**Description:** Create creates a new instance of `TMultiReadExclusiveWriteSynchronizer`. It initializes a `TRTLCriticalSection`.

**Errors:** None.

**See also:** `#rtl.system.TRITLCriticalSection` ([1248](#))

### 38.53.4 `TMultiReadExclusiveWriteSynchronizer.Destroy`

**Synopsis:** Destroys the `TMultiReadExclusiveWriteSynchronizer` instance

**Declaration:** `destructor Destroy; Override`

**Visibility:** `public`

**Description:** Create destroys the instance of `TMultiReadExclusiveWriteSynchronizer`. It frees the `TRTLCriticalSection` it initialized, and calls the inherited destructor.

**Errors:** None.

**See also:** `#rtl.system.TRITLCriticalSection` ([1248](#))

### 38.53.5 `TMultiReadExclusiveWriteSynchronizer.Beginwrite`

**Synopsis:** Request write access to the resource.

**Declaration:** `function Beginwrite : Boolean`

**Visibility:** `public`

**Description:** `Beginwrite` is the implementation of `IReadWriteSync.BeginWrite`. It simply enters the critical section, and returns `True`.

**Errors:** None.

**See also:** `IReadWriteSync.BeginWrite` ([1581](#)), `TMultiReadExclusiveWriteSynchronizer.EndWrite` ([1582](#))

### 38.53.6 `TMultiReadExclusiveWriteSynchronizer.Endwrite`

**Synopsis:** Release write access to the resource

**Declaration:** `procedure Endwrite`

**Visibility:** `public`

**Description:** `Beginwrite` is the implementation of `IReadWriteSync.EndWrite`. It simply leaves the critical section.

**Errors:** None.

**See also:** `IReadWriteSync.EndWrite` ([1581](#)), `TMultiReadExclusiveWriteSynchronizer.BeginWrite` ([1582](#))



### 38.53.7 TMultiReadExclusiveWriteSynchronizer.Beginread

Synopsis: Request read access to the resource

Declaration: `procedure Beginread`

Visibility: `public`

Description: `BeginRead` is the implementation of `IReadWriteSync.BeginRead`. It simply attempts to enter the critical section.

Errors: None.

See also: `IReadWriteSync.BeginRead` ([1580](#)), `TMultiReadExclusiveWriteSynchronizer.EndRead` ([1583](#))

### 38.53.8 TMultiReadExclusiveWriteSynchronizer.Endread

Synopsis: Release read access to the resource

Declaration: `procedure Endread`

Visibility: `public`

Description: `EndRead` is the implementation of `IReadWriteSync.EndRead`. It simply leaves the critical section.

Errors: None.

See also: `IReadWriteSync.EndRead` ([1580](#)), `TMultiReadExclusiveWriteSynchronizer.BeginRead` ([1583](#))

Table 38.4:

Name	Description
<a href="#">AnsiCompareFileName (1448)</a>	Compare 2 filenames
<a href="#">AnsiLowerCaseFileName (1452)</a>	Create lowercase filename
<a href="#">AnsiUpperCaseFileName (1460)</a>	Create uppercase filename
<a href="#">AddDisk (1447)</a>	Add disk to list of disk drives
<a href="#">ChangeFileExt (1464)</a>	Change extension of file name
<a href="#">CreateDir (1468)</a>	Create a directory
<a href="#">DeleteFile (1476)</a>	Delete a file
<a href="#">DiskFree (1477)</a>	Free space on disk
<a href="#">DiskSize (1478)</a>	Total size of disk
<a href="#">ExpandFileName (1483)</a>	Create full file name
<a href="#">ExpandUNCFileName (1483)</a>	Create full UNC file name
<a href="#">ExtractFileDir (1484)</a>	Extract drive and directory part of filename
<a href="#">ExtractFileDrive (1484)</a>	Extract drive part of filename
<a href="#">ExtractFileExt (1485)</a>	Extract extension part of filename
<a href="#">ExtractFileName (1485)</a>	Extract name part of filename
<a href="#">ExtractFilePath (1485)</a>	Extract path part of filename
<a href="#">ExtractRelativePath (1486)</a>	Construct relative path between two files
<a href="#">FileAge (1486)</a>	Return file age
<a href="#">FileDateToDateTime (1488)</a>	Convert file date to system date
<a href="#">FileExists (1489)</a>	Determine whether a file exists on disk
<a href="#">FileGetAttr (1490)</a>	Get attributes of file
<a href="#">FileGetDate (1491)</a>	Get date of last file modification
<a href="#">FileSearch (1493)</a>	Search for file in path
<a href="#">FileSetAttr (1494)</a>	Get file attributes
<a href="#">FileSetDate (1495)</a>	Get file dates
<a href="#">FindFirst (1496)</a>	Start finding a file
<a href="#">FindNext (1497)</a>	Find next file
<a href="#">GetCurrentDir (1514)</a>	Return current working directory
<a href="#">RemoveDir (1528)</a>	Remove a directory from disk
<a href="#">RenameFile (1529)</a>	Rename a file on disk
<a href="#">SameFileName (1531)</a>	Check whether 2 filenames are the same
<a href="#">SetCurrentDir (1531)</a>	Set current working directory
<a href="#">SetDirSeparators (1531)</a>	Set directory separator characters
<a href="#">FindClose (1496)</a>	Stop searching a file
<a href="#">DoDirSeparators (1478)</a>	Replace directory separator characters

Table 38.5:

Name	Description
<a href="#">FileCreate (1487)</a>	Create a file and return handle
<a href="#">FileOpen (1492)</a>	Open file and return handle
<a href="#">FileRead (1493)</a>	Read from file
<a href="#">FileSeek (1494)</a>	Set file position
<a href="#">FileTruncate (1495)</a>	Truncate file length
<a href="#">FileWrite (1495)</a>	Write to file
<a href="#">FileClose (1487)</a>	Close file handle

Table 38.6:

Name	Description
<a href="#">AdjustLineBreaks (1447)</a>	Convert line breaks to line breaks for system
<a href="#">FormatBuf (1509)</a>	Format a buffer
<a href="#">Format (1504)</a>	Format arguments in string
<a href="#">FmtStr (1503)</a>	Format buffer
<a href="#">QuotedStr (1528)</a>	Quote a string
<a href="#">StrFmt (1537)</a>	Format arguments in a string
<a href="#">StrLFmt (1542)</a>	Format maximum L characters in a string
<a href="#">TrimLeft (1561)</a>	Remove whitespace at the left of a string
<a href="#">TrimRight (1562)</a>	Remove whitespace at the right of a string
<a href="#">Trim (1560)</a>	Remove whitespace at both ends of a string

Table 38.7:

Name	Description
<a href="#">AnsiCompareStr (1448)</a>	Compare two strings
<a href="#">AnsiCompareText (1449)</a>	Compare two strings, case insensitive
<a href="#">AnsiExtractQuotedStr (1450)</a>	Removes quotes from string
<a href="#">AnsiLastChar (1451)</a>	Get last character of string
<a href="#">AnsiLowerCase (1452)</a>	Convert string to all-lowercase
<a href="#">AnsiQuotedStr (1453)</a>	Quotes a string
<a href="#">AnsiStrComp (1454)</a>	Compare strings case-sensitive
<a href="#">AnsiStrIComp (1454)</a>	Compare strings case-insensitive
<a href="#">AnsiStrLComp (1456)</a>	Compare L characters of strings case sensitive
<a href="#">AnsiStrLIComp (1457)</a>	Compare L characters of strings case insensitive
<a href="#">AnsiStrLastChar (1455)</a>	Get last character of string
<a href="#">AnsiStrLower (1458)</a>	Convert string to all-lowercase
<a href="#">AnsiStrUpper (1459)</a>	Convert string to all-uppercase
<a href="#">AnsiUpperCase (1460)</a>	Convert string to all-uppercase
<a href="#">AppendStr (1461)</a>	Append 2 strings
<a href="#">AssignStr (1462)</a>	Assign value of strings on heap
<a href="#">CompareStr (1466)</a>	Compare two strings case sensitive
<a href="#">CompareText (1467)</a>	Compare two strings case insensitive
<a href="#">DisposeStr (1478)</a>	Remove string from heap
<a href="#">IsValidIdent (1523)</a>	Is string a valid pascal identifier
<a href="#">LastDelimiter (1524)</a>	Last occurrence of character in a string
<a href="#">LeftStr (1524)</a>	Get first N characters of a string
<a href="#">LoadStr (1525)</a>	Load string from resources
<a href="#">LowerCase (1525)</a>	Convert string to all-lowercase
<a href="#">NewStr (1526)</a>	Allocate new string on heap
<a href="#">RightStr (1530)</a>	Get last N characters of a string
<a href="#">StrAlloc (1533)</a>	Allocate memory for string
<a href="#">StrBufSize (1533)</a>	Reserve memory for a string
<a href="#">StrDispose (1536)</a>	Remove string from heap
<a href="#">StrPas (1545)</a>	Convert PChar to pascal string
<a href="#">StrPCopy (1545)</a>	Copy pascal string
<a href="#">StrPLCopy (1546)</a>	Copy N bytes of pascal string
<a href="#">UpperCase (1567)</a>	Convert string to all-uppercase

Table 38.8: Enumeration values for type TEventType

Value	Explanation
etCustom	Custom log event, with application-specific meaning
etDebug	Debug message.
etError	Error condition message
etInfo	General information event message
etWarning	Warning message

Table 38.9: Enumeration values for type TFloatFormat

Value	Explanation
ffCurrency	Monetary format.
ffExponent	Scientific format.
ffFixed	Fixed point format.
ffGeneral	General number format.
ffNumber	Fixed point format with thousand separator

Table 38.10: Enumeration values for type TFloatValue

Value	Explanation
fvComp	Comp value
fvCurrency	Currency value
fvDouble	Double value
fvExtended	Extended value
fvReal	Real value
fvSingle	Single value

Table 38.11: Enumeration values for type TMbcsByteType

Value	Explanation
mbLeadByte	Uses lead-byte
mbSingleByte	Single bytes
mbTrailByte	Uses trailing byte

Table 38.12: Enumeration values for type TSignalState

Value	Explanation
ssHooked	A signal handler is set by the RTL code for the signal.
ssNotHooked	No signal handler is set for the signal.
ssOverridden	A signal handler was set for the signal by third-party code.

## Chapter 39

# Reference for unit 'types'

### 39.1 Overview

Starting with D6, types from Windows specific units that were needed in Kylix were extracted to this unit. So it mostly contains type of Windows origin that are needed in the VCL framework.

### 39.2 Constants, types and variables

#### 39.2.1 Constants

```
E_FAIL = HRESULT($80004005)
```

Defined for Delphi compatibility, this should not be used.

```
E_INVALIDARG = HRESULT($80070057)
```

Defined for Delphi compatibility, this should not be used.

```
GUID_NULL : TGUID = '{00000000-0000-0000-0000-000000000000}'
```

GUID\_NULL is the definition of the NULL (empty) GUID.

```
LOCK_EXCLUSIVE = 2
```

Defined for Delphi compatibility, this should not be used.

```
LOCK_ONLYONCE = 4
```

Defined for Delphi compatibility, this should not be used.

```
LOCK_WRITE = 1
```

Defined for Delphi compatibility, this should not be used.

```
RT_RCDATA = PChar(10)
```

Resource type RCDATA

STATFLAG\_DEFAULT = 0

Defined for Delphi compatibility, this should not be used.

STATFLAG\_NONAME = 1

Defined for Delphi compatibility, this should not be used.

STATFLAG\_NOOPEN = 2

Defined for Delphi compatibility, this should not be used.

STGTY\_LOCKBYTES = 3

Defined for Delphi compatibility, this should not be used.

STGTY\_PROPERTY = 4

Defined for Delphi compatibility, this should not be used.

STGTY\_STORAGE = 1

Defined for Delphi compatibility, this should not be used.

STGTY\_STREAM = 2

Defined for Delphi compatibility, this should not be used.

STG\_E\_ABNORMALAPIEXIT = HRESULT(\$800300FA)

Defined for Delphi compatibility, this should not be used.

STG\_E\_ACCESSDENIED = HRESULT(\$80030005)

Defined for Delphi compatibility, this should not be used.

STG\_E\_BADBASEADDRESS = HRESULT(\$80030110)

Defined for Delphi compatibility, this should not be used.

STG\_E\_CANTSAVE = HRESULT(\$80030103)

Defined for Delphi compatibility, this should not be used.

STG\_E\_DISKISWRITEPROTECTED = HRESULT(\$80030013)

Defined for Delphi compatibility, this should not be used.

STG\_E\_DOCFILECORRUPT = HRESULT(\$80030109)

Defined for Delphi compatibility, this should not be used.

STG\_E\_EXTANTMARSHALLINGS = HRESULT(\$80030108)

Defined for Delphi compatibility, this should not be used.

STG\_E\_FILEALREADYEXISTS = HRESULT(\$80030050)

Defined for Delphi compatibility, this should not be used.

STG\_E\_FILENOTFOUND = HRESULT(\$80030002)

Defined for Delphi compatibility, this should not be used.

STG\_E\_INCOMPLETE = HRESULT(\$80030201)

Defined for Delphi compatibility, this should not be used.

STG\_E\_INSUFFICIENTMEMORY = HRESULT(\$80030008)

Defined for Delphi compatibility, this should not be used.

STG\_E\_INUSE = HRESULT(\$80030100)

Defined for Delphi compatibility, this should not be used.

STG\_E\_INVALIDFLAG = HRESULT(\$800300FF)

Defined for Delphi compatibility, this should not be used.

STG\_E\_INVALIDFUNCTION = HRESULT(\$80030001)

Defined for Delphi compatibility, this should not be used.

STG\_E\_INVALIDHANDLE = HRESULT(\$80030006)

Defined for Delphi compatibility, this should not be used.

STG\_E\_INVALIDHEADER = HRESULT(\$800300FB)

Defined for Delphi compatibility, this should not be used.

STG\_E\_INVALIDNAME = HRESULT(\$800300FC)

Defined for Delphi compatibility, this should not be used.

STG\_E\_INVALIDPARAMETER = HRESULT(\$80030057)

Defined for Delphi compatibility, this should not be used.

STG\_E\_INVALIDPOINTER = HRESULT(\$80030009)

Defined for Delphi compatibility, this should not be used.

STG\_E\_LOCKVIOLATION = HRESULT(\$80030021)

Defined for Delphi compatibility, this should not be used.

STG\_E\_MEDIUMFULL = HRESULT(\$80030070)

Defined for Delphi compatibility, this should not be used.

STG\_E\_NOMOREFILES = HRESULT(\$80030012)

Defined for Delphi compatibility, this should not be used.

STG\_E\_NOTCURRENT = HRESULT(\$80030101)

Defined for Delphi compatibility, this should not be used.

STG\_E\_OLDDLL = HRESULT(\$80030105)

Defined for Delphi compatibility, this should not be used.

STG\_E\_OLDFORMAT = HRESULT(\$80030104)

Defined for Delphi compatibility, this should not be used.

STG\_E\_PATHNOTFOUND = HRESULT(\$80030003)

Defined for Delphi compatibility, this should not be used.

STG\_E\_PROPSETMISMATCHED = HRESULT(\$800300F0)

Defined for Delphi compatibility, this should not be used.

STG\_E\_READFAULT = HRESULT(\$8003001E)

Defined for Delphi compatibility, this should not be used.

STG\_E\_REVERTED = HRESULT(\$80030102)

Defined for Delphi compatibility, this should not be used.

STG\_E\_SEEKERROR = HRESULT(\$80030019)

Defined for Delphi compatibility, this should not be used.

STG\_E\_SHAREREQUIRED = HRESULT(\$80030106)

Defined for Delphi compatibility, this should not be used.

STG\_E\_SHAREVIOLATION = HRESULT(\$80030020)



Defined for Delphi compatibility, this should not be used.

STG\_E\_TERMINATED = HRESULT(\$80030202)

Defined for Delphi compatibility, this should not be used.

STG\_E\_TOOMANYOPENFILES = HRESULT(\$80030004)

Defined for Delphi compatibility, this should not be used.

STG\_E\_UNIMPLEMENTEDFUNCTION = HRESULT(\$800300FE)

Defined for Delphi compatibility, this should not be used.

STG\_E\_UNKNOWN = HRESULT(\$800300FD)

Defined for Delphi compatibility, this should not be used.

STG\_E\_WRITEFAULT = HRESULT(\$8003001D)

Defined for Delphi compatibility, this should not be used.

STG\_S\_BLOCK = \$00030201

Defined for Delphi compatibility, this should not be used.

STG\_S\_CONVERTED = \$00030200

Defined for Delphi compatibility, this should not be used.

STG\_S\_MONITORING = \$00030203

Defined for Delphi compatibility, this should not be used.

STG\_S\_RETRYNOW = \$00030202

Defined for Delphi compatibility, this should not be used.

STREAM\_SEEK\_CUR = 1

Defined for Delphi compatibility, this should not be used.

STREAM\_SEEK\_END = 2

Defined for Delphi compatibility, this should not be used.

STREAM\_SEEK\_SET = 0

Defined for Delphi compatibility, this should not be used.

### 39.2.2 Types

`ArgList = Pointer`

`ArgList` is defined for Delphi/Kylix compatibility and should not be used.

`DWORD = LongWord`

Alias for cardinal type

`FILETIME = _FILETIME`

Alias for the `_FILETIME` type

`Largeint = Int64`

`Largeint` is an alias for the `Int64` type defined in the system unit. This is an alias for Delphi/Kylix compatibility.

`LargeUint = qword`

`LargeUint` is an alias for the `QWord` type defined in the system unit. This is an alias for Delphi/Kylix compatibility.

`LARGE_INT = Largeint`

`LARGE_INT` is an alias for the `Int64` type defined in the system unit. This is an alias for Delphi/Kylix compatibility.

`LARGE_UINT = LargeUint`

`LARGE_UINT` is an alias for the `QWord` type defined in the system unit. This is an alias for Delphi/Kylix compatibility.

`PByte = System.PByte`

`PByte` is defined in the system unit. This is an alias for Delphi/Kylix compatibility.

`PCLSID = PGUID`

`PCLSID` is a pointer to a `TCLSID` type.

`PDisplay = Pointer`

`PDisplay` is defined for Delphi/Kylix compatibility and should not be used.

`PDouble = System.PDouble`

`PDouble` is defined in the system unit. This is an alias for Delphi/Kylix compatibility.

`PDWord = ^DWORD`

`PWord` is equivalent to the `PCardinal` type.

`PEvent` = `Pointer`

`PEvent` is defined for Delphi/Kylix compatibility and should not be used.

`PFileTime` = `^TFileTime`

**Pointer to `TFileTime` type**

`PLargeInt` = `^Largeint`

`PLargeInt` is an alias for the `PInt64` type defined in the system unit. This is an alias for Delphi/Kylix compatibility.

`PLargeUInt` = `^LargeUInt`

`PLargeUInt` is an alias for the `PQWord` type defined in the system unit. This is an alias for Delphi/Kylix compatibility.

`PLongint` = `System.PLongint`

`PLongint` is defined in the system unit. This is an alias for Delphi/Kylix compatibility.

`PoleStr` = `PWideChar`

`PoleStr` is a pointer to a (double) null-terminated array of `TChar` characters.

`PPoint` = `^TPoint`

`PPoint` is a typed pointer to the `TPoint` (1596) type.

`PPoleStr` = `^PoleStr`

`PPoleStr` is a typed pointer to a `PoleStr` variable.

`PRect` = `^TRect`

`PRect` is a typed pointer to the `TRect` (1596) type.

`PSize` = `^TSize`

`PSize` is a typed pointer to the `TSize` (1597) type.

`PSmallInt` = `System.PSmallInt`

`PSmallInt` is defined in the system unit. This is an alias for Delphi/Kylix compatibility.

`PSmallPoint` = `^TSmallPoint`

`PSmallPoint` is a typed pointer to the `TSmallPoint` (1597) record.

PStatStg = ^TStatStg

Pointer to TStatStg record.

PXrmOptionDescRec = ^TXrmOptionDescRec

PXrmOptionDescRec is defined for Delphi/Kylix compatibility and should not be used.

Region = Pointer

Region is defined for Delphi/Kylix compatibility and should not be used.

STATSTG = TStatStg

Alias for the TStatStg type.

tagPOINT = TPoint

tagPOINT is a simple alias for TPoint ([1596](#))

tagSIZE = TSize

tagSize is an alias for the TSize ([1597](#)) type.

```
tagSTATSTG = record
  pwcsName : POleStr;
  dwType : DWORD;
  cbSize : LARGE_UINT;
  mtime : TFileTime;
  ctime : TFileTime;
  atime : TFileTime;
  grfMode : DWORD;
  grfLocksSupported : DWORD;
  clsid : TCLSID;
  grfStateBits : DWORD;
  reserved : DWORD;
end
```

tagSTATSTG is used in the IStream.Stat ([1605](#)) call. It describes a storage medium (typically a file).

TBooleanDynArray = Array of Boolean

TBooleanDynArray is a standard definition of a dynamical array of booleans.

TByteDynArray = Array of Byte

TByteDynArray is a standard definition of a dynamical array of (8-bit, unsigned) bytes.

TCardinalDynArray = Array of Cardinal

TCardinalDynArray is a standard definition of a dynamical array of (32-bit, unsigned) cardinals.

TCLSID = TGUID

TCLSID is an alias for the #rtl.system.GUID (1209) type.

TDoubleDynArray = Array of Double

TSoubleDynArray is a standard definition of a dynamical array of doubles. (regular floating point type)

TDuplicates = (dupIgnore, dupAccept, dupError)

Table 39.1: Enumeration values for type TDuplicates

Value	Explanation
dupAccept	Accept duplicates, adding them to the list.
dupError	Raise an error when an attempt is made to add a duplicate.
dupIgnore	Ignore the new item, do not add it to the list.

TDuplicates can be used to indicate how a list structure acts on the addition of a duplicate item to the list.

**dupIgnore** Ignore the new item, do not add it to the list.

**dupAccept** Accept duplicates, adding them to the list.

**dupError** Raise an error when an attempt is made to add a duplicate.

TFileTime = \_FILETIME

Alias for the \_FILETIME type

TInt64DynArray = Array of Int64

TInt64DynArray is a standard definition of a dynamical array of (64-bit, signed) int64s.

TIntegerDynArray = Array of Integer

TIntegerDynArray is a standard definition of a dynamical array of (32-bit, signed) integers.

TListCallback = procedure(data: pointer; arg: pointer) of object

TListCallback is the prototype for a Foreach operation on a list. It will be called with as Data the pointer in the list, and Arg will contain the extra user data added to the Foreach call. It can be used in methods of objects; for a version that can be used as a global procedure, see TListStaticCallback (1596)

TListStaticCallback = procedure(data: pointer; arg: pointer)

`TListStaticCallback` is the prototype for a `Foreach` operation on a list. It will be called with as `Data` the pointer in the list, and `Arg` will contain the extra user data added to the `Foreach` call. It can be used in plain procedures; for a version that can be used as a method, see `TListCallback` (1595)

`TLongWordDynArray` = Array of `LongWord`

`TLongWordDynArray` is a standard definition of a dynamical array of (32-bit, unsigned) `LongWords`.

`TLeChar` = `WideChar`

`TLeChar` is an alias for the `WideChar` type, defined in the system unit.

```
TPoint = packed record
  X : LongInt;
  Y : LongInt;
end
```

`TPoint` is a generic definition of a point in a 2-dimensional discrete plane, where `X` indicates the horizontal position, and `Y` the vertical position (positions usually measured in pixels), and 0, 0 is the origin of the plane.

Usually, the origin is the upper-left corner of the screen, with `Y` increasing as one moves further down the screen - this is opposite to the mathematical view where `Y` increases as one moves upwards.

The coordinates are integers, (32-bit, signed) so the coordinate system runs from `-MaxInt` to `MaxInt`.

`TPointerDynArray` = Array of `Pointer`

Dynamic array of untyped pointers

`TQWordDynArray` = Array of `QWord`

`TQWordDynArray` is a standard definition of a dynamical array of (64-bit, unsigned) `QWords`.

```
TRect = packed record
end
```

`TRect` defines a rectangle in a discrete plane. It is described by the horizontal (`left`, `right`) or vertical (`top`, `Bottom`) positions (in pixels) of the edges, or, alternatively, by the coordinates of the top left (`TopLeft`) and bottom right (`BottomRight`) corners.

`TShortIntDynArray` = Array of `ShortInt`

`TShortintDynArray` is a standard definition of a dynamical array of (8-bit, signed) shortints.

`TSingleDynArray` = Array of `Single`

`TSingleDynArray` is a standard definition of a dynamical array of singles. (smallest floating point type)

```
TSize = packed record
  cx : LongInt;
  cy : LongInt;
end
```

TSize is a type to describe the size of a rectangular area, where cx is the width, cy is the height (in pixels) of the rectangle.

```
TSmallIntDynArray = Array of SmallInt
```

TSmallIntDynArray is a standard definition of a dynamical array of (16-bit, unsigned) integers.

```
TSmallPoint = packed record
  x : SmallInt;
  y : SmallInt;
end
```

TSmallPoint defines a point in a 2-dimensional plane, just like TPoint (1596), but the coordinates have a smaller range: The coordinates are smallints (16-bit, signed) and they run from -MaxSmallInt to maxSmallInt.

```
TStatStg = tagSTATSTG
```

TStatStg is a record type describing a storage medium. It is used in the IStream.Stat (1605) function.

```
TStringDynArray = Array of AnsiString
```

TStringDynArray is a standard definition of a dynamical array of AnsiStrings.

```
TWideStringDynArray = Array of WideString
```

TWideStringDynArray is a standard definition of a dynamical array of WideStrings.

```
TWordDynArray = Array of Word
```

TWordDynArray is a standard definition of a dynamical array of (16-bit, unsigned) words.

```
TXrmOptionDescRec = record
end
```

TXrmOptionDescRec is defined for Delphi/Kylix compatibility and should not be used.

```
Widget = Pointer
```

Widget is defined for Delphi/Kylix compatibility and should not be used.

```
WidgetClass = Pointer
```

WidgetClass is defined for Delphi/Kylix compatibility and should not be used.

XrmOptionDescRec = TXrmOptionDescRec

XrmOptionDescRec is defined for Delphi/Kylix compatibility and should not be used.

```
_FILETIME = packed record
  dwLowDateTime : DWORD;
  dwHighDateTime : DWORD;
end
```

\_FILETIME describes a file time stamp. It is defined for Delphi/Kylix compatibility and should not be used except when implementing or accessing the IStream interface. The TDateTime type should be used instead.

## 39.3 Procedures and functions

### 39.3.1 Bounds

Synopsis: Create a rectangle, given a position and size

Declaration: `function Bounds (ALeft: Integer; ATop: Integer; AWidth: Integer; AHeight: Integer) : TRect`

Visibility: default

Description: Bounds returns a TRect structure with the indicated position (Left=ALeft and Top=ATop) and size (Right=ALeft+AWidth and Bottom=ATop+AHeight)

See also: Rect (1600), PtInRect (1600), IntersectRect (1599), UnionRect (1601)

### 39.3.2 CenterPoint

Synopsis: Return the center point of a rectangle

Declaration: `function CenterPoint (const Rect: TRect) : TPoint`

Visibility: default

Description: CenterPoint returns the center point of the rectangle Rect.

See also: PtInRect (1600), IntersectRect (1599), IsRectEmpty (1599), OffsetRect (1599), InflateRect (1599), Size (1600), IsRectEmpty (1599)

### 39.3.3 EqualRect

Synopsis: Check if two rectangles are equal.

Declaration: `function EqualRect (const r1: TRect; const r2: TRect) : Boolean`

Visibility: default

Description: EqualRect returns True if the rectangles R1 and R2 are equal (i.e. have the position and size). If the rectangles differ, the function returns False

See also: Rect (1600), Bounds (1598), PtInRect (1600), IntersectRect (1599), UnionRect (1601), IsRectEmpty (1599), OffsetRect (1599), InflateRect (1599), Size (1600)



### 39.3.4 InflateRect

Synopsis: Increase the rectangle in size, keeping it centered

Declaration: `function InflateRect (var Rect: TRect; dx: Integer; dy: Integer) : Boolean`

Visibility: default

Description: `InflateRect` inflates the rectangle horizontally with `dx` pixels on each side, and vertically with `dy` pixels, thus keeping its center point on the same location. It returns `true` if the operation was succesfully, `False` if it was not (only possible if the address of `Rect` is `Nil`).

Errors:

See also: `PtinRect` (1600), `IntersectRect` (1599), `IsRectEmpty` (1599), `OffsetRect` (1599), `CenterPoint` (1598), `Size` (1600), `IsRectEmpty` (1599)

### 39.3.5 IntersectRect

Synopsis: Return the intersection of 2 rectangles

Declaration: `function IntersectRect (var Rect: TRect; const R1: TRect; const R2: TRect) : Boolean`

Visibility: default

Description: `IntersectRect` returns the intersection of the 2 rectangles `R1` and `R2` in `Rect`. It returns `True` if the 2 rectangles have an intersection, otherwise `False` is returned, and `Rect` is filled with zero.

See also: `PtinRect` (1600), `UnionRect` (1601), `IsRectEmpty` (1599), `OffsetRect` (1599), `InflateRect` (1599), `Size` (1600)

### 39.3.6 IsRectEmpty

Synopsis: Check whether a rectangle is empty

Declaration: `function IsRectEmpty (const Rect: TRect) : Boolean`

Visibility: default

Description: `IsRectEmpty` returns `true` if the rectangle is empty, i.e. has a zero or negative width or height.

See also: `PtinRect` (1600), `IntersectRect` (1599), `IsRectEmpty` (1599), `OffsetRect` (1599), `InflateRect` (1599), `Size` (1600)

### 39.3.7 OffsetRect

Synopsis: Offset the rectangle

Declaration: `function OffsetRect (var Rect: TRect; DX: Integer; DY: Integer) : Boolean`

Visibility: default

Description: `OffsetRect` offsets the rectangle `Rect` by a horizontal distance `DX` and a vertical distance `DY`. The operation returns `True` if the operation was successfull, `false` if it was not (only possible if the address of `Rect` is `Nil`).

See also: `PtinRect` (1600), `IntersectRect` (1599), `IsRectEmpty` (1599), `OffsetRect` (1599), `InflateRect` (1599), `Size` (1600), `IsRectEmpty` (1599)

### 39.3.8 Point

Synopsis: Create a point

Declaration: `function Point(x: Integer;y: Integer) : TPoint`

Visibility: default

Description: `Point` returns a `TPoint` structure with the given position (X, Y).

See also: `Rect` ([1600](#)), `PtInRect` ([1600](#))

### 39.3.9 PtInRect

Synopsis: Check whether a point is inside a rectangle.

Declaration: `function PtInRect(const Rect: TRect;const p: TPoint) : Boolean`

Visibility: default

Description: `PtInRect` returns `True` if `p` is located inside `Rect`, and `False` if it is located outside the rectangle.

**Remark:** Note that the bottom, right edges are not considered part of the rectangle, therefore a point located on one of these edges will not be considered part of the rectangle, meaning that for a record (10,10,100,100) the point (90,100) will not be considered part of the record, but 90, 0 will be.

See also: `IntersectRect` ([1599](#)), `UnionRect` ([1601](#)), `IsRectEmpty` ([1599](#)), `OffsetRect` ([1599](#)), `InflateRect` ([1599](#)), `Size` ([1600](#))

### 39.3.10 Rect

Synopsis: Create a rectangle record

Declaration: `function Rect(Left: Integer;Top: Integer;Right: Integer;Bottom: Integer)  
: TRect`

Visibility: default

Description: `Rect` returns a rectangle structure with the 4 members `Left`, `Top`, `Right` and `Bottom` as passed in the arguments.

See also: `Bounds` ([1598](#)), `PtInRect` ([1600](#)), `IntersectRect` ([1599](#)), `UnionRect` ([1601](#)), `IsRectEmpty` ([1599](#)), `OffsetRect` ([1599](#)), `InflateRect` ([1599](#)), `Size` ([1600](#))

### 39.3.11 Size

Synopsis: Return the size of the rectangle

Declaration: `function Size(AWidth: Integer;AHeight: Integer) : TSize`  
`function Size(ARect: TRect) : TSize`

Visibility: default

Description: `Size` returns a `TSize` record with the indicated `AWidth`, `AHeight`. In the case `ARect` is passed, the width and height are calculated (taking into account that the right, bottom are not considered part of the rectangle).

See also: `PtInRect` ([1600](#)), `IntersectRect` ([1599](#)), `IsRectEmpty` ([1599](#)), `OffsetRect` ([1599](#)), `InflateRect` ([1599](#)), `CenterPoint` ([1598](#)), `IsRectEmpty` ([1599](#))

### 39.3.12 UnionRect

Synopsis: Return the union of 2 rectangles.

Declaration: `function UnionRect (var Rect: TRect; const R1: TRect; const R2: TRect)  
: Boolean`

Visibility: default

Description: `UnionRect` returns the rectangle that encompasses both `R1` and `R2` in `Rect`. It returns `True` if the resulting rectangle is not empty, `False` if the result is an empty rectangle (in which case the result is filled with zeroes)

See also: `PtinRect` ([1600](#)), `IntersectRect` ([1599](#)), `IsRectEmpty` ([1599](#)), `OffsetRect` ([1599](#)), `InflateRect` ([1599](#)), `Size` ([1600](#))

## 39.4 IClassFactory

### 39.4.1 Description

`IClassFactory` is defined for Delphi/Kylix compatibility and should not be used.

### 39.4.2 Method overview

Page	Property	Description
<a href="#">1601</a>	<code>CreateInstance</code>	Create a new instance of an interface.
<a href="#">1601</a>	<code>LockServer</code>	Lock ActiveX server object.

### 39.4.3 IClassFactory.CreateInstance

Synopsis: Create a new instance of an interface.

Declaration: `function CreateInstance (const unkOuter: IUnknown; const riid: TGUID;  
out vObject) : HRESULT`

Visibility: default

Description: `IClassFactory.CreateInstance` is defined for Delphi/Kylix compatibility and should not be used.

### 39.4.4 IClassFactory.LockServer

Synopsis: Lock ActiveX server object.

Declaration: `function LockServer (fLock: LongBool) : HRESULT`

Visibility: default

Description: `IClassFactory.LockServer` is defined for Delphi/Kylix compatibility and should not be used.

## 39.5 ISequentialStream

### 39.5.1 Description

`ISequentialStream` is the interface for streams which only support sequential reading of chunks of data. It is defined for Delphi/Kylix compatibility and should not be used.

### 39.5.2 Method overview

Page	Property	Description
<a href="#">1602</a>	Read	Read data from the stream
<a href="#">1602</a>	Write	Write data to the stream

### 39.5.3 ISequentialStream.Read

Synopsis: Read data from the stream

Declaration: `function Read(pv: Pointer;cb: DWORD;pcbRead: PDWord) : HRESULT`

Visibility: default

Description: `Read` reads `cbCount` bytes from the stream into the memory pointed to by `pv` and returns the number of bytes read in `pcbread`. The result is zero for success or an error code.

See also: `ISequentialStream.Write` ([1602](#))

### 39.5.4 ISequentialStream.Write

Synopsis: Write data to the stream

Declaration: `function Write(pv: Pointer;cb: DWORD;pcbWritten: PDWord) : HRESULT`

Visibility: default

Description: `Write` writes `cbCount` bytes from the memory pointed to by `pv` to the stream and returns the number of bytes written in `pcbwritten`. The result is zero for success or an error code.

See also: `ISequentialStream.Read` ([1602](#))

## 39.6 IStream

### 39.6.1 Description

An abstract interface for an external (non pascal) stream, as defined in Microsoft COM interfaces

### 39.6.2 Method overview

Page	Property	Description
<a href="#">1605</a>	Clone	Clone the stream instance
<a href="#">1604</a>	Commit	Commit data to the stream
<a href="#">1603</a>	CopyTo	Copy data from one stream to another
<a href="#">1604</a>	LockRegion	Lock a region of bytes in the stream
<a href="#">1604</a>	Revert	Revert changes
<a href="#">1603</a>	Seek	Set the stream position
<a href="#">1603</a>	SetSize	Set the stream size
<a href="#">1605</a>	Stat	return information about the stream.
<a href="#">1604</a>	UnlockRegion	Unlocks a previously locked region of bytes in the stream

### 39.6.3 IStream.Seek

Synopsis: Set the stream position

Declaration: `function Seek(dlibMove: Largeint; dwOrigin: LongInt;  
out libNewPosition: Largeint) : HRESULT`

Visibility: default

Description: `Seek` sets the stream position at `dlibMove` bytes from `dwOrigin` (one of the `SEEK_*` constants) and returns the new absolute position in `libNewPosition`. The function returns zero on success, or an error code.

Errors: On error, a nonzero exit code is returned.

### 39.6.4 IStream.SetSize

Synopsis: Set the stream size

Declaration: `function SetSize(libNewSize: Largeint) : HRESULT`

Visibility: default

Description: `SetSize` sets the size of the stream to `libNewSize` bytes, if the stream allows it. On success, zero is returned.

Errors: On error, a nonzero exit code is returned.

### 39.6.5 IStream.CopyTo

Synopsis: Copy data from one stream to another

Declaration: `function CopyTo(stm: IStream; cb: Largeint; out cbRead: Largeint;  
out cbWritten: Largeint) : HRESULT`

Visibility: default

Description: `CopyTo` copies `cb` bytes from the stream to target stream `stm`. `cbRead` returns how many bytes were read from the stream, `cbwrite` returns how many bytes were actually written to the destination stream. The function returns zero on success.

Errors: On error, a nonzero exit code is returned.

### 39.6.6 IStream.Commit

Synopsis: Commit data to the stream

Declaration: `function Commit(grfCommitFlags: LongInt) : HRESULT`

Visibility: default

Description: `Commit` commits the data in the stream to the underlying medium. `Flags` is a set of options to control the commit operation (see MSDN for the possible flags).

Errors: On error, a nonzero exit code is returned.

### 39.6.7 IStream.Revert

Synopsis: Revert changes

Declaration: `function Revert : HRESULT`

Visibility: default

Description: `Revert` reverts all changes that were done to a transacted stream, i.e. all changes since the last commit. The function returns zero on success.

Errors: On error, a nonzero exit code is returned.

### 39.6.8 IStream.LockRegion

Synopsis: Lock a region of bytes in the stream

Declaration: `function LockRegion(libOffset: Largeint;cb: Largeint;  
dwLockType: LongInt) : HRESULT`

Visibility: default

Description: `LockRegion` locks a region of the storage, starting at `libOffset`, for `cbCount` bytes. The applied lock is of type `dwLockType`. The function returns zero if the lock was successfully applied.

Errors: On error, a nonzero exit code is returned.

### 39.6.9 IStream.UnlockRegion

Synopsis: Unlocks a previously locked region of bytes in the stream

Declaration: `function UnlockRegion(libOffset: Largeint;cb: Largeint;  
dwLockType: LongInt) : HRESULT`

Visibility: default

Description: `UnlockRegion` removes the lock on a region of the storage, starting at `libOffset`, for `cbCount` bytes. The lock must be of type `dwLockType`. The function returns zero if the lock was successfully removed.

Errors: On error, a nonzero exit code is returned.

### 39.6.10 IStream.Stat

Synopsis: return information about the stream.

Declaration: `function Stat(out statstg: TStatStg; grfStatFlag: LongInt) : HRESULT`

Visibility: default

Description: `Stat` returns information about the stream in `statstg`, taking into account the flags in `grfStatFlag` (one of the `STATFLAG_` constants). The function returns zero if the call was successful.

Errors: On error, a nonzero exit code is returned.

### 39.6.11 IStream.Clone

Synopsis: Clone the stream instance

Declaration: `function Clone(out stm: IStream) : HRESULT`

Visibility: default

Description: `Clone` returns an independent but initially equal copy of the stream in `stm`. The function returns zero if the call was successful.

Errors: On error, a nonzero exit code is returned.

## Chapter 40

# Reference for unit 'typinfo'

### 40.1 Used units

Table 40.1: Used units by unit 'typinfo'

Name	Page
sysutils	<a href="#">1426</a>

### 40.2 Overview

The `TypeInfo` unit contains many routines which can be used for the querying of the Run-Time Type Information (RTTI) which is generated by the compiler for classes that are compiled under the `{ $M+ }` switch. This information can be used to retrieve or set property values for published properties for totally unknown classes. In particular, it can be used to stream classes. The `TPersistent` class in the `Classes` unit is compiled in the `{ $M+ }` state and serves as the base class for all classes that need to be streamed.

The unit should be compatible to the Delphi 5 unit with the same name. The only calls that are still missing are the Variant calls, since Free Pascal does not support the variant type yet.

The examples in this chapter use a `rttiobj` auxiliary unit, which contains an object that has a published property for all supported types. It also contains some auxiliary routines and definitions. This unit is included in the documentation sources, in the directory `typinfex`.

### 40.3 Auxiliary functions

Other `typinfo` related functions.

### 40.4 Getting or setting property values

Functions to set or set a property's value.



Table 40.2:

Name	Description
<code>GetEnumName</code> (1615)	Get an enumerated type element name
<code>GetEnumValue</code> (1617)	Get ordinal number of an enumerated type, based on the name.
<code>GetEnumNameCount</code> (1616)	Get number of elements in an enumerated type.
<code>GetTypeData</code> (1629)	Skip type name and return a pointer to the type data
<code>SetToString</code> (1638)	Convert a set to its string representation
<code>StringToSet</code> (1640)	Convert a string representation of a set to a set

## 40.5 Examining published property information

Functions for retrieving or examining property information

## 40.6 Constants, types and variables

### 40.6.1 Constants

```
BooleanIdents : Array[Boolean] of String = ('False', 'True')
```

Names for boolean values

```
DotSep : String = '.'
```

Name separator character

```
OnGetPropValue : TGetPropValue = nil
```

This callback is set by the variants unit to enable reading of properties as a variant. If set, it is called by the `GetPropValue` (1627) function.

```
OnGetVariantprop : TGetVariantProp = nil
```

This callback is set by the variants unit to enable reading of variant properties. If set, it is called by the `GetVariantProp` (1630) function.

```
OnSetPropValue : TSetPropValue = nil
```

This callback is set by the variants unit to enable writing of properties as a variant. If set, it is called by the `SetPropValue` (1637) function.

```
OnSetVariantprop : TSetVariantProp = nil
```

This callback is set by the variants unit to enable writing of variant properties. If set, it is called by the `GetVariantProp` (1630) function.

```
ptConst = 3
```

Constant used in access method

Table 40.3:

Name	Description
<code>GetEnumProp</code> (1616)	Return the value of an enumerated type property
<code>GetFloatProp</code> (1617)	Return the value of a float property
<code>GetInt64Prop</code> (1618)	Return the value of an Int64 property
<code>GetMethodProp</code> (1620)	Return the value of a procedural type property
<code>GetObjectProp</code> (1622)	Return the value of an object property
<code>GetOrdProp</code> (1623)	Return the value of an ordinal type property
<code>GetProperty</code> (1627)	Return the value of a property as a variant
<code>GetSetProp</code> (1627)	Return the value of a set property
<code>GetStrProp</code> (1628)	Return the value of a string property
<code>GetWideStrProp</code> (1630)	Return the value of a widestring property
<code>GetVariantProp</code> (1630)	Return the value of a variant property
<code>SetEnumProp</code> (1634)	Set the value of an enumerated type property
<code>SetFloatProp</code> (1634)	Set the value of a float property
<code>SetInt64Prop</code> (1635)	Set the value of an Int64 property
<code>SetMethodProp</code> (1635)	Set the value of a procedural type property
<code>SetObjectProp</code> (1636)	Set the value of an object property
<code>SetOrdProp</code> (1636)	Set the value of an ordinal type property
<code>SetPropValue</code> (1637)	Set the value of a property through a variant
<code>SetSetProp</code> (1637)	Set the value of a set property
<code>SetStrProp</code> (1638)	Set the value of a string property
<code>SetWideStrProp</code> (1640)	Set the value of a widestring property
<code>SetVariantProp</code> (1639)	Set the value of a variant property

```
ptField = 0
```

Property acces directly from field

```
ptStatic = 1
```

Property acces via static method

```
ptVirtual = 2
```

Property acces via virtual method

```
tkAny = [Low(TTypeKind)..High(TTypeKind)]
```

Any property type

```
tkMethods = [tkMethod]
```

Only method properties. (event handlers)

```
tkProperties = tkAny-tkMethods-[tkUnknown]
```

Real properties. (not methods)

```
tkString = tkSString
```

Alias for the `tsSString` enumeration value

Table 40.4:

Name	Description
FindPropInfo (1614)	Getting property type information, With error checking.
GetPropInfo (1624)	Getting property type information, No error checking.
GetPropInfos (1625)	Find property information of a certain kind
GetObjectPropClass (1623)	Return the declared class of an object property
GetPropList (1626)	Get a list of all published properties
IsPublishedProp (1630)	Is a property published
IsStoredProp (1631)	Is a property stored
PropIsType (1632)	Is a property of a certain kind
PropType (1633)	Return the type of a property

## 40.6.2 Types

`PPropInfo = ^TPropInfo`

Pointer to `TPropInfo` (1612) record

`PPropList = ^TPropList`

Pointer to `TPropList` (1612)

`PTypeInfo = ^PTypeInfo`

Pointer to `PTypeInfo` (1609) pointer

`PTypeData = ^TTypeData`

Pointer to `TTypeData` (1612) record.

`PTypeInfo = ^TTypeInfo`

Pointer to `TTypeInfo` (1613) record

`PVmtFieldEntry = ^TVmtFieldEntry`

Pointer to `#rtl.typinfo.TVmtFieldEntry` (1614) type.

`PVmtFieldTable = ^TVmtFieldTable`

Pointer to `#rtl.typinfo.TVmtFieldTable` (??) type.

`ShortStringBase =`

`ShortStringBase` is the base definition of a short string.

`TFloatType = (ftSingle, ftDouble, ftExtended, ftComp, ftCurr)`

The size of a float type.

Table 40.5: Enumeration values for type TFloatType

Value	Explanation
ftComp	Comp-type float
ftCurr	Currency-type float
ftDouble	Double-sized float
ftExtended	Extended-size float
ftSingle	Single-sized float

```
TGetPropValue = function(Instance: TObject; const PropName: String;
                        PreferStrings: Boolean) : Variant
```

The callback function must return the property with name `PropName` of instance `Instance`. If `PreferStrings` is true, it should favour converting the property to a string value. The function needs to return the variant with the property value.

```
TGetVariantProp = function(Instance: TObject; PropInfo: PPropInfo)
                    : Variant
```

The callback function must return the variant property with name `PropName` of instance `Instance`.

```
TIntfFlag = (ifHasGuid, ifDispInterface, ifDispatch, ifHasStrGUID)
```

Table 40.6: Enumeration values for type TIntfFlag

Value	Explanation
ifDispatch	Interface is a dispatch interface
ifDispInterface	Interface is a dual dispatch interface
ifHasGuid	Interface has GUID identifier
ifHasStrGUID	Interface has a string GUID identifier

Type of interface.

```
TIntfFlags= Set of (ifDispatch, ifDispInterface, ifHasGuid, ifHasStrGUID)
```

Set of TIntfFlag ([1610](#)).

```
TIntfFlagsBase= Set of (ifDispatch, ifDispInterface, ifHasGuid,
                        ifHasStrGUID)
```

Set of TIntfFlag ([1610](#)).

```
TMethodKind = (mkProcedure, mkFunction, mkConstructor, mkDestructor,
               mkClassProcedure, mkClassFunction)
```

Method type description

```
TOrdType = (otSByte, otUByte, otSWord, otUWord, otSLong, otULong)
```

Table 40.7: Enumeration values for type TMethodKind

Value	Explanation
mkClassFunction	Class function
mkClassProcedure	Class procedure
mkConstructor	Class constructor
mkDestructor	Class Desctructor
mkFunction	Function method
mkProcedure	Procedure method.

Table 40.8: Enumeration values for type TOrdType

Value	Explanation
otSByte	Signed byte
otSLong	Signed longint
otSWord	Signed word
otUByte	Unsigned byte
otULong	Unsigned longing (Cardinal)
otUWord	Unsigned word

If the property is and ordinal type, then TOrdType determines the size and sign of the ordinal type:

```
TParamFlag = (pfVar, pfConst, pfArray, pfAddress, pfReference, pfOut)
```

TParamFlag describes a parameter.

```
TParamFlags= Set of (pfAddress, pfArray, pfConst, pfOut, pfReference, pfVar)
```

The kind of parameter for a method

```
TProcInfoProc = procedure (PropInfo: PPropInfo) of object
```

Property info callback method

```
TPropData = packed record
  PropCount : Word;
  PropList : record
    _alignmentdummy : ptring;
  end;
end
```

The TPropData record is not used, but is provided for completeness and compatibility with Delphi.

```
TPropInfo = packed record
  PropType : PTypeInfo;
  GetProc : Pointer;
  SetProc : Pointer;
  StoredProc : Pointer;
```

Table 40.9: Enumeration values for type TParamFlag

Value	Explanation
pfAddress	Parameter is passed by address
pfArray	Parameter is an array parameter
pfConst	Parameter is a const parameter (i.e. cannot be modified)
pfOut	Parameter is a string parameter
pfReference	Parameter is passed by reference
pfVar	Parameter is a var parameter (passed by reference)

```

Index : Integer;
Default : LongInt;
NameIndex : SmallInt;
PropProcs : Byte;
Name : ShortString;
end

```

The TPropInfo record describes one published property of a class. The property information of a class are stored as an array of TPropInfo records.

The Name field is stored not with 255 characters, but with just as many characters as required to store the name.

```
TPropList = Array[0..65535] of PPropInfo
```

Array of property information pointers

```
TSetPropValue = procedure(Instance: TObject; const PropName: String;
                           const Value: Variant)
```

The callback function must set the property with name PropName of instance Instance to Value.

```
TSetVariantProp = procedure(Instance: TObject; PropInfo: PPropInfo;
                             const Value: Variant)
```

The callback function must set the variant property with name PropName of instance to Value.

```
TTypeInfo = packed record
end
```

If the typeinfo kind is tkClass, then the property information follows the UnitName string, as an array of TPropInfo (1612) records.

```
TTypeInfo = record
  Kind : TTypeKind;
  Name : ShortString;
end
```

The `TypeInfo` function returns a pointer to a `TTypeInfo` record.

Note that the `Name` field is stored with as much bytes as needed to store the name, it is not padded to 255 characters. The type data immediately follows the `TTypeInfo` record as a `TTypeData` (1612) record.

```
TTypeKind = (tkUnknown,tkInteger,tkChar,tkEnumeration,tkFloat,tkSet,
             tkMethod,tkSString,tkLString,tkAString,tkWString,tkVariant,
             tkArray,tkRecord,tkInterface,tkClass,tkObject,tkWChar,
             tkBool,tkInt64,tkQWord,tkDynArray,tkInterfaceRaw,tkProcVar,
             tkUString,tkUChar)
```

Table 40.10: Enumeration values for type `TTypeKind`

Value	Explanation
<code>tkArray</code>	Array property.
<code>tkAString</code>	Ansistring property.
<code>tkBool</code>	Boolean property.
<code>tkChar</code>	Char property.
<code>tkClass</code>	Class property.
<code>tkDynArray</code>	Dynamical array property.
<code>tkEnumeration</code>	Enumeration type property.
<code>tkFloat</code>	Float property.
<code>tkInt64</code>	Int64 property.
<code>tkInteger</code>	Integer property.
<code>tkInterface</code>	Interface property.
<code>tkInterfaceRaw</code>	Raw interface property.
<code>tkLString</code>	Longstring property.
<code>tkMethod</code>	Method property.
<code>tkObject</code>	Object property.
<code>tkProcVar</code>	Procedural variable
<code>tkQWord</code>	QWord property.
<code>tkRecord</code>	Record property.
<code>tkSet</code>	Set property.
<code>tkSString</code>	Shortstring property.
<code>tkUChar</code>	Unicode character
<code>tkUnknown</code>	Unknown property type.
<code>tkUString</code>	Unicode string
<code>tkVariant</code>	Variant property.
<code>tkWChar</code>	Widechar property.
<code>tkWString</code>	Widestring property.

Type of a property.

```
TTypeKinds= Set of (tkArray,tkAString,tkBool,tkChar,tkClass,tkDynArray,
                    tkEnumeration,tkFloat,tkInt64,tkInteger,tkInterface,
                    tkInterfaceRaw,tkLString,tkMethod,tkObject,
                    tkProcVar,tkQWord,tkRecord,tkSet,tkSString,tkUChar,
                    tkUnknown,tkUString,tkVariant,tkWChar,tkWString)
```

Set of `TTypeKind` (1613) enumeration.

```

TVmtFieldEntry = packed record
  FieldOffset : PtrUInt;
  TypeIndex : Word;
  Name : ShortString;
end

```

TVmtFieldEntry records are generated by the compiler for all fields of a record or class that have RTTI associated with them. They describe the field as known to the compiler.

```

TVmtFieldTable = packed record
  Count : Word;
  ClassTab : Pointer;
  Fields : Array[0..0] of TVmtFieldEntry;
end

```

TVmtFieldTable describes the fields for which RTTI was generated. A TVmtFieldTable entry is generated by the compiler in the RTTI information, it is not something one creates manually. Basically it contains a list of TVmtFieldEntry (1614) values.

## 40.7 Procedures and functions

### 40.7.1 FindPropInfo

**Synopsis:** Return property information by property name.

**Declaration:**

```

function FindPropInfo(Instance: TObject; const PropName: String)
    : PPropInfo
function FindPropInfo(Instance: TObject; const PropName: String;
    AKinds: TTypeKinds) : PPropInfo
function FindPropInfo(AClass: TClass; const PropName: String) : PPropInfo
function FindPropInfo(AClass: TClass; const PropName: String;
    AKinds: TTypeKinds) : PPropInfo

```

**Visibility:** default

**Description:** FindPropInfo examines the published property information of a class and returns a pointer to the property information for property PropName. The class to be examined can be specified in one of two ways:

**AClass** a class pointer.

**Instance** an instance of the class to be investigated.

If the property does not exist, a EPropertyError exception will be raised. The GetPropInfo (1624) function has the same function as the FindPropInfo function, but returns Nil if the property does not exist.

**Errors:** Specifying an invalid property name in PropName will result in an EPropertyError exception.

**See also:** GetPropInfo (1624), GetPropList (1626), GetPropInfos (1625)

**Listing:** ./typinfex/ex14.pp



---

```

Program example13;

{ This program demonstrates the FindPropInfo function }

{$mode objfpc}

uses
    rttiobj , typinfo , sysutils ;

Var
    O : TMyTestObject;
    PT : PTypeData;
    PI : PPropInfo;
    I,J : Longint;
    PP : PPropList;
    prl : PPropInfo;

begin
    O:=TMyTestObject.Create;
    PI:=FindPropInfo(O, 'BooleanField');
    WriteLn('FindPropInfo(Instance, BooleanField) : ', PI^.Name);
    PI:=FindPropInfo(O.ClassType, 'ByteField');
    WriteLn('FindPropInfo(Class, ByteField) : ', PI^.Name);
    Write ('FindPropInfo(Class, NonExistingProp) : ');
    Try
        PI:=FindPropInfo(O, 'NonExistingProp');
    except
        On E: Exception do
            WriteLn('Caught exception "', E.ClassName, '" with message : ', E.Message);
    end;
    O.Free;
end.

```

---

### 40.7.2 GetEnumName

Synopsis: Return name of enumeration constant.

Declaration: `function GetEnumName(TypeInfo: PTypeInfo; Value: Integer) : String`

Visibility: default

Description: `GetEnumName` scans the type information for the enumeration type described by `TypeInfo` and returns the name of the enumeration constant for the element with ordinal value equal to `Value`.

If `Value` is out of range, the first element of the enumeration type is returned. The result is lower-cased, but this may change in the future.

This can be used in combination with `GetOrdProp` to stream a property of an enumerated type.

Errors: No check is done to determine whether `TypeInfo` really points to the type information for an enumerated type.

See also: `GetOrdProp` ([1623](#)), `GetEnumValue` ([1617](#))

**Listing:** `./typinfex/ex9.pp`

---

```

program example9;

{ This program demonstrates the GetEnumName, GetEnumValue functions }

{$mode objfpc}

uses rttiobj, typinfo;

Var
  O : TMyTestObject;
  TI : PTypeInfo;

begin
  O:=TMyTestObject.Create;
  TI:=GetPropInfo(O, 'MyEnumField')^.PropType;
  WriteLn('GetEnumName      : ',GetEnumName(TI,Ord(O.MyEnumField)));
  WriteLn('GetEnumValue(mefirst) : ',GetEnumName(TI,GetEnumValue(TI,'mefirst')));
  O.Free;
end.

```

---

### 40.7.3 GetEnumNameCount

**Synopsis:** Return number of names in an enumerated type

**Declaration:** `function GetEnumNameCount(enum1: PTypeInfo) : SizeInt`

**Visibility:** default

**Description:** `GetEnumNameCount` returns the number of values (names) in the enumerated type, described by `enum1`

**Errors:** No checking is done to see whether `Enum1` is really type information of an enumerated type.

**See also:** `GetEnumValue` ([1617](#)), `GetEnumName` ([1615](#))

### 40.7.4 GetEnumProp

**Synopsis:** Return the value of an enumeration type property.

**Declaration:** `function GetEnumProp(Instance: TObject;const PropName: String) : String`  
`function GetEnumProp(Instance: TObject;const PropInfo: PPropInfo)`  
`: String`

**Visibility:** default

**Description:** `GetEnumProp` returns the value of a property of an enumerated type and returns the name of the enumerated value for the object `Instance`. The property whose value must be returned can be specified by its property info in `PropInfo` or by its name in `PropName`

**Errors:** No check is done to determine whether `PropInfo` really points to the property information for an enumerated type. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

**See also:** `SetEnumProp` ([1634](#)), `GetOrdProp` ([1623](#)), `GetStrProp` ([1628](#)), `GetInt64Prop` ([1618](#)), `GetMethodProp` ([1620](#)), `GetSetProp` ([1627](#)), `GetObjectProp` ([1622](#)), `GetEnumProp` ([1616](#))

```

program example2;

{ This program demonstrates the GetEnumerator function }

{$mode objfpc}

uses rttiobj, typinfo;

Var
    O : TMyTestObject;
    PI : PPropInfo;
    TI : PTypeInfo;

begin
    O:=TMyTestObject.Create;
    PI:=GetPropInfo(O, 'MyEnumField');
    TI:=PI^.PropType;
    Writeln('Enum property      : ');
    Writeln('Value                      : ', GetEnumerator(TI, Ord(O.MyEnumField)));
    Writeln('Get (name)                       : ', GetEnumerator(O, 'MyEnumField'));
    Writeln('Get (propinfo)                   : ', GetEnumerator(O, PI));
    SetEnumProp(O, 'MyEnumField', 'meFirst');
    Writeln('Set (name, meFirst)              : ', GetEnumerator(TI, Ord(O.MyEnumField)));
    SetEnumProp(O, PI, 'meSecond');
    Writeln('Set (propinfo, meSecond)        : ', GetEnumerator(TI, Ord(O.MyEnumField)));
    O.Free;
end.

```

### Synopsis: Get ordinal value for enumerated type by name

Visibility: default

**Description:** `GetFloatProp` returns the value of the float property described by `PropInfo` or with name `Propname` for the object `Instance`. All float types are converted to extended.

**Errors:** No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid float property of `Instance`. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

**See also:** `SetFloatProp` (1634), `GetOrdProp` (1623), `GetStrProp` (1628), `GetInt64Prop` (1618), `GetMethodProp` (1620), `GetSetProp` (1627), `GetObjectProp` (1622), `GetEnumProp` (1616)

**Listing:** `./typinfex/ex4.pp`

---

```

program example4;

{ This program demonstrates the GetFloatProp function }

{$mode objfpc}

uses rttiobj, typinfo;

Var
  O : TMyTestObject;
  PI : PPropInfo;

begin
  O := TMyTestObject.Create;
  Writeln('Real property : ');
  PI := GetPropInfo(O, 'RealField');
  Writeln('Value           : ', O.RealField);
  Writeln('Get (name)        : ', GetFloatProp(O, 'RealField'));
  Writeln('Get (propinfo)       : ', GetFloatProp(O, PI));
  SetFloatProp(O, 'RealField', system.Pi);
  Writeln('Set (name, pi)       : ', O.RealField);
  SetFloatProp(O, PI, exp(1));
  Writeln('Set (propinfo, e)    : ', O.RealField);
  Writeln('Extended property : ');
  PI := GetPropInfo(O, 'ExtendedField');
  Writeln('Value           : ', O.ExtendedField);
  Writeln('Get (name)        : ', GetFloatProp(O, 'ExtendedField'));
  Writeln('Get (propinfo)     : ', GetFloatProp(O, PI));
  SetFloatProp(O, 'ExtendedField', system.Pi);
  Writeln('Set (name, pi)      : ', O.ExtendedField);
  SetFloatProp(O, PI, exp(1));
  Writeln('Set (propinfo, e)   : ', O.ExtendedField);
  O.Free;
end.

```

---

### 40.7.7 GetInt64Prop

**Synopsis:** return value of an Int64 property

**Declaration:** `function GetInt64Prop(Instance: TObject; PropInfo: PPropInfo) : Int64`  
`function GetInt64Prop(Instance: TObject; const PropName: String) : Int64`

Visibility: default

**Description:** Publishing of Int64 properties is not yet supported by Free Pascal. This function is provided for Delphi compatibility only at the moment.

`GetInt64Prop` returns the value of the property of type `Int64` that is described by `PropInfo` or with name `Propname` for the object `Instance`.

**Errors:** No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid `Int64` property of `Instance`. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception

See also: `SetInt64Prop` (1635), `GetOrdProp` (1623), `GetStrProp` (1628), `GetFloatProp` (1617), `GetMethodProp` (1620), `GetSetProp` (1627), `GetObjectProp` (1622), `GetEnumProp` (1616)

**Listing:** ./typinfex/ex15.pp

---

```

program example15;

{ This program demonstrates the GetInt64Prop function }

{$mode objfpc}

uses rttiobj , typinfo ;

Var
  O : TMyTestObject;
  PI : PPropInfo;

begin
  O:=TMyTestObject.Create;
  Writeln('Int64 property : ');
  PI:=GetPropInfo(O,'Int64Field');
  Writeln('Value           : ',O.Int64Field);
  Writeln('Get (name)       : ',GetInt64Prop(O,'Int64Field'));
  Writeln('Get (propinfo)    : ',GetInt64Prop(O,PI));
  SetInt64Prop(O,'Int64Field',12345);
  Writeln('Set (name,12345)   : ',O.Int64Field);
  SetInt64Prop(O,PI,54321);
  Writeln('Set (propinfo,54321) : ',O.Int64Field);
  O.Free;
end.

```

---

### 40.7.8 GetInterfaceProp

**Synopsis:** Return interface-typed property

**Declaration:**

```

function GetInterfaceProp(Instance: TObject;const PropName: String)
    : IInterface
function GetInterfaceProp(Instance: TObject;PropInfo: PPropInfo)
    : IInterface

```

**Visibility:** default

**Description:** `GetInterfaceProp` returns the interface which the property described by `PropInfo` or with name `Propname` points to for object `Instance`.

**Errors:** No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid method property of `Instance`. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: [SetInterfaceProp \(1635\)](#), [GetOrdProp \(1623\)](#), [GetStrProp \(1628\)](#), [GetFloatProp \(1617\)](#), [GetInt64Prop \(1618\)](#), [GetSetProp \(1627\)](#), [GetObjectProp \(1622\)](#), [GetEnumProp \(1616\)](#)

### 40.7.9 GetMethodProp

Synopsis: Return value of a method property

**Declaration:** `function GetMethodProp(Instance: TObject; PropInfo: PPropInfo) : TMethod`  
`function GetMethodProp(Instance: TObject; const PropName: String)`  
`: TMethod`

Visibility: default

**Description:** `GetMethodProp` returns the method the property described by `PropInfo` or with name `Propname` for object `Instance`. The return type `TMethod` is defined in the `SysUtils` unit as:

```
TMethod = packed record
  Code, Data: Pointer;
end;
```

`Data` points to the instance of the class with the method `Code`.

**Errors:** No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid method property of `Instance`. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: [SetMethodProp \(1635\)](#), [GetOrdProp \(1623\)](#), [GetStrProp \(1628\)](#), [GetFloatProp \(1617\)](#), [GetInt64Prop \(1618\)](#), [GetSetProp \(1627\)](#), [GetObjectProp \(1622\)](#), [GetEnumProp \(1616\)](#)

**Listing:** `./typinfex/ex6.pp`

---

```
program example6;

{ This program demonstrates the GetMethodProp function }

{$mode objfpc}

uses rttiobj, typinfo, sysutils;

Type
  TNotifyObject = Class(TObject)
    Procedure Notification1(Sender : TObject);
    Procedure Notification2(Sender : TObject);
  end;

Procedure TNotifyObject.Notification1(Sender : TObject);

begin
  Write('Received notification 1 of object with class: ');
  WriteLn(Sender.ClassName);
end;

Procedure TNotifyObject.Notification2(Sender : TObject);

begin
  Write('Received notification 2 of object with class: ');
  WriteLn(Sender.ClassName);
```

**end;**

**Var**

O : TMyTestObject;  
 PI : PPropInfo;  
 NO : TNotifyObject;  
 M : TMethod;

**Procedure** PrintMethod (**Const** M : TMethod);

**begin**

**If** (M.Data=Pointer(NO)) **Then**  
    **If** (M.Code=Pointer(@TNotifyObject.Notification1)) **then**  
      **WriteLn**( ' Notification1 ' )  
    **else If** (M.Code=Pointer(@TNotifyObject.Notification2)) **then**  
      **WriteLn**( ' Notification2 ' )  
    **else**  
      **begin**  
        **Write**( 'Unknown method adress (data: ' );  
        **Write**( hexStr( Longint(M.data) ,8));  
        **WriteLn**( ' ,code: ' ,hexstr( Longint(M.Code) ,8) , ' ' );  
      **end;**

**end;**

**begin**

O:=TMyTestObject.Create;  
 NO:=TNotifyObject.Create;  
 O.NotifyEvent:=@NO.Notification1;  
 PI:=GetPropInfo(O, 'NotifyEvent');  
**WriteLn**( 'Method property : ' );  
**Write**( 'Notifying : ' );  
 O.Notify;  
**Write**( 'Get (name) : ' );  
 M:=GetMethodProp(O, 'NotifyEvent');  
 PrintMethod(M);  
**Write**( 'Notifying : ' );  
 O.Notify;  
**Write**( 'Get (propinfo) : ' );  
 M:=GetMethodProp(O, PI);  
 PrintMethod(M);  
 M:=TMethod(@NO.Notification2);  
 SetMethodProp(O, 'NotifyEvent',M);  
**Write**( 'Set (name, Notification2) : ' );  
 M:=GetMethodProp(O, PI);  
 PrintMethod(M);  
**Write**( 'Notifying : ' );  
 O.Notify;  
**Write**( 'Set (propinfo, Notification1) : ' );  
 M:=TMethod(@NO.Notification1);  
 SetMethodProp(O, PI,M);  
 M:=GetMethodProp(O, PI);  
 PrintMethod(M);  
**Write**( 'Notifying : ' );  
 O.Notify;  
 O.Free;

**end.**

### 40.7.10 GetObjectProp

Synopsis: Return value of an object-type property.

Declaration: `function GetObjectProp(Instance: TObject; const PropName: String) : TObject`  
`function GetObjectProp(Instance: TObject; const PropName: String; MinClass: TClass) : TObject`  
`function GetObjectProp(Instance: TObject; PropInfo: PPropInfo) : TObject`  
`function GetObjectProp(Instance: TObject; PropInfo: PPropInfo; MinClass: TClass) : TObject`

Visibility: default

Description: `GetObjectProp` returns the object which the property described by `PropInfo` with name `Propname` points to for object `Instance`.

If `MinClass` is specified, then if the object is not descendent of class `MinClass`, then `Nil` is returned.

Errors: No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid method property of `Instance`. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `SetMethodProp` (1635), `GetOrdProp` (1623), `GetStrProp` (1628), `GetFloatProp` (1617), `GetInt64Prop` (1618), `GetSetProp` (1627), `GetObjectProp` (1622), `GetEnumProp` (1616)

**Listing:** `./typinfex/ex5.pp`

---

```
program example5;

{ This program demonstrates the GetObjectProp function }

{$mode objfpc}

uses rttiobj, typinfo;

Var
  O : TMyTestObject;
  PI : PPropInfo;
  NO1, NO2 : TNamedObject;

begin
  O := TMyTestObject.Create;
  NO1 := TNamedObject.Create;
  NO1.ObjectName := 'First named object';
  NO2 := TNamedObject.Create;
  NO2.ObjectName := 'Second named object';
  O.ObjField := NO1;
  Writeln('Object property : ');
  PI := GetPropInfo(O, 'ObjField');
  Write('Property class : ');
  Writeln(GetObjectPropClass(O, 'ObjField').ClassName);
  Write('Value : ');
  Writeln((O.ObjField as TNamedObject).ObjectName);
  Write('Get (name) : ');
  Writeln((GetObjectProp(O, 'ObjField') as TNamedObject).ObjectName);
  Write('Get (propinfo) : ');
  Writeln((GetObjectProp(O, PI, TObject) as TNamedObject).ObjectName);
  SetObjectProp(O, 'ObjField', NO2);
```



---

```

Write( 'Set (name,NO2)      : ');
WriteLn((O.ObjField as TNamedObject).ObjectName);
SetObjectProp(O,PI,NO1);
Write( 'Set (propinfo,NO1) : ');
WriteLn((O.ObjField as TNamedObject).ObjectName);
O.Free;
end.

```

---

### 40.7.11 GetObjectPropClass

Synopsis: Return class of property.

Declaration: `function GetObjectPropClass(Instance: TObject;const PropName: String) : TClass`  
`function GetObjectPropClass(AClass: TClass;const PropName: String) : TClass`

Visibility: default

Description: `GetObjectPropClass` returns the declared class of the property with name `PropName`. This may not be the actual class of the property value.

For an example, see `GetObjectProp` (1622).

Errors: No checking is done whether `Instance` is non-nil. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `SetMethodProp` (1635), `GetOrdProp` (1623), `GetStrProp` (1628), `GetFloatProp` (1617), `GetInt64Prop` (1618)

### 40.7.12 GetOrdProp

Synopsis: Get the value of an ordinal property

Declaration: `function GetOrdProp(Instance: TObject;PropInfo: PPropInfo) : Int64`  
`function GetOrdProp(Instance: TObject;const PropName: String) : Int64`

Visibility: default

Description: `GetOrdProp` returns the value of the ordinal property described by `PropInfo` or with name `PropName` for the object `Instance`. The value is returned as a longint, which should be typecasted to the needed type.

Ordinal properties that can be retrieved include:

**Integers and subranges of integers**The value of the integer will be returned.

**Enumerated types and subranges of enumerated types**The ordinal value of the enumerated type will be returned.

**Sets**If the base type of the set has less than 31 possible values. If a bit is set in the return value, then the corresponding element of the base ordinal class of the set type must be included in the set.

Errors: No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid ordinal property of `Instance`. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `SetOrdProp` (1636), `GetStrProp` (1628), `GetFloatProp` (1617), `GetInt64Prop` (1618), `GetMethodProp` (1620), `GetSetProp` (1627), `GetObjectProp` (1622), `GetEnumProp` (1616)

**Listing:** ./typinfex/ex1.pp

---

```

program example1;

{ This program demonstrates the GetOrdProp function }

{$mode objfpc}

uses rttiobj, typinfo;

Var
  O : TMyTestObject;
  PI : PPropInfo;

begin
  O:=TMyTestObject.Create;
  Writeln( 'Boolean property      : ');
  Writeln( 'Value                  : ',O.BooleanField);
  Writeln( 'Ord(Value)              : ',Ord(O.BooleanField));
  Writeln( 'Get (name)              : ',GetOrdProp(O, 'BooleanField'));
  PI:=GetPropInfo(O, 'BooleanField');
  Writeln( 'Get (propinfo)          : ',GetOrdProp(O, PI));
  SetOrdProp(O, 'BooleanField',Ord(False));
  Writeln( 'Set (name,false)         : ',O.BooleanField);
  SetOrdProp(O, PI,Ord(True));
  Writeln( 'Set (propinfo,true)      : ',O.BooleanField);
  O.Free;
end.

```

---

### 40.7.13 GetPropInfo

**Synopsis:** Return property type information, by property name.

**Declaration:**

```

function GetPropInfo(TypeInfo: PTypeInfo;const PropName: String)
    : PPropInfo
function GetPropInfo(TypeInfo: PTypeInfo;const PropName: String;
    AKinds: TTypeKinds) : PPropInfo
function GetPropInfo(Instance: TObject;const PropName: String)
    : PPropInfo
function GetPropInfo(Instance: TObject;const PropName: String;
    AKinds: TTypeKinds) : PPropInfo
function GetPropInfo(AClass: TClass;const PropName: String) : PPropInfo
function GetPropInfo(AClass: TClass;const PropName: String;
    AKinds: TTypeKinds) : PPropInfo

```

**Visibility:** default

**Description:** GetPropInfo returns a pointer to the TPropInfo record for a the PropName property of a class. The class to examine can be specified in one of three ways:

**Instance**An instance of the class.

**AClass**A class pointer to the class.

**TypeInfo**A pointer to the type information of the class.

In each of these three ways, if AKinds is specified, if the property has TypeKind which is not included in Akinds, Nil will be returned.

For an example, see most of the other functions.

Errors: If the property `PropName` does not exist, `Nil` is returned.

See also: `GetPropInfos` ([1625](#)), `GetPropList` ([1626](#))

#### 40.7.14 GetPropInfos

Synopsis: Return a list of published properties.

Declaration: `procedure GetPropInfos(TypeInfo: PTypeInfo; PropList: PPropList)`

Visibility: default

Description: `GetPropInfos` stores pointers to the property information of all published properties of a class with class info `TypeInfo` in the list pointed to by `PropList`. The `PropList` pointer must point to a memory location that contains enough space to hold all properties of the class and its parent classes.

Errors: No checks are done to see whether `PropList` points to a memory area that is big enough to hold all pointers.

See also: `GetPropInfo` ([1624](#)), `GetPropList` ([1626](#))

**Listing:** `./typinfex/ex12.pp`

---

**Program** `example12;`

*{ This program demonstrates the GetPropInfos function }*

**uses**

`rttiobj, typinfo;`

**Var**

`O : TMyTestObject;`

`PT : PTypeData;`

`PI : PTypeInfo;`

`I, J : Longint;`

`PP : PPropList;`

`pri : PPropInfo;`

**begin**

`O := TMyTestObject.Create;`

`PI := O.ClassInfo;`

`PT := GetTypeData(PI);`

`WriteLn('Property Count : ', PT^.PropCount);`

`GetMem(PP, PT^.PropCount * SizeOf(Pointer));`

`GetPropInfos(PI, PP);`

**For** `I := 0 to PT^.PropCount - 1 do`

**begin**

**With** `PP^[I]^ do`

**begin**

`Write('Property ', i + 1:3, ': ', name:30);`

`writeln(' Type : ', TypeName[typinfo.PropType(O, Name)]);`

**end;**

**end;**

`FreeMem(PP);`

`O.Free;`

**end.**

---

### 40.7.15 GetPropList

Synopsis: Return a list of a certain type of published properties.

Declaration: `function GetPropList (TypeInfo: PTypeInfo; TypeKinds: TTypeKinds;  
PropList: PPropList; Sorted: Boolean) : LongInt  
function GetPropList (TypeInfo: PTypeInfo; out PropList: PPropList)  
: SizeInt  
function GetPropList (AClass: TClass; out PropList: PPropList) : Integer  
function GetPropList (Instance: TObject; out PropList: PPropList)  
: Integer`

Visibility: default

Description: `GetPropList` stores pointers to property information of the class with class info `TypeInfo` for properties of kind `TypeKinds` in the list pointed to by `PropList`. `PropList` must contain enough space to hold all properties.

The function returns the number of pointers that matched the criteria and were stored in `PropList`.

Errors: No checks are done to see whether `PropList` points to a memory area that is big enough to hold all pointers.

See also: `GetPropInfos` (1625), `GetPropInfo` (1624)

**Listing:** ./typinfex/ex13.pp

**Program** example13;

*{ This program demonstrates the GetPropList function }*

**uses**

rttiobj, typinfo;

**Var**

O : TMyTestObject;  
PT : PTypeData;  
PI : PTypeInfo;  
I, J : Longint;  
PP : PPropList;  
prl : PPropInfo;

**begin**

O := TMyTestObject.Create;  
PI := O.ClassInfo;  
PT := GetTypeData(PI);  
WriteLn('Total property Count : ', PT^.PropCount);  
GetMem(PP, PT^.PropCount \* SizeOf(Pointer));  
J := GetPropList(PI, OrdinalTypes, PP);  
WriteLn('Ordinal property Count : ', J);  
For I := 0 to J - 1 do  
begin  
With PP^[I]^ do  
begin  
Write('Property ', i + 1:3, ': ', name:30);  
writeln('Type : ', TypeName[typinfo.PropType(O, Name)]);  
end;  
end;  
FreeMem(PP);

---

```
O. Free ;
end.
```

---

### 40.7.16 GetPropValue

Synopsis: Get property value as a string.

**Declaration:**

```
function GetPropValue(Instance: TObject;const PropName: String)
    : Variant
function GetPropValue(Instance: TObject;const PropName: String;
    PreferStrings: Boolean) : Variant
```

Visibility: default

**Description:** Due to missing Variant support, GetPropValue is not yet implemented. The declaration is provided for compatibility with Delphi.

Errors:

### 40.7.17 GetSetProp

Synopsis: Return the value of a set property.

**Declaration:**

```
function GetSetProp(Instance: TObject;const PropName: String) : String
function GetSetProp(Instance: TObject;const PropName: String;
    Brackets: Boolean) : String
function GetSetProp(Instance: TObject;const PropInfo: PPropInfo;
    Brackets: Boolean) : String
```

Visibility: default

**Description:** GetSetProp returns the contents of a set property as a string. The property to be returned can be specified by its name in PropName or by its property information in PropInfo.

The returned set is a string representation of the elements in the set as returned by SetToString (1638). The Brackets option can be used to enclose the string representation in square brackets.

**Errors:** No checking is done whether Instance is non-nil, or whether PropInfo describes a valid ordinal property of Instance. Specifying an invalid property name in PropName will result in an EPropertyError exception.

See also: SetSetProp (1637), GetStrProp (1628), GetFloatProp (1617), GetInt64Prop (1618), GetMethodProp (1620)

**Listing:** ./typinfex/ex7.pp

---

```
program example7;

{ This program demonstrates the GetSetProp function }

{$mode objfpc}

uses rttiobj, typinfo;

Var
  O : TMyTestObject;
  PI : PPropInfo;
```

---

```

Function SetAsString (ASet : TMyEnums) : String;

Var
  i : TmyEnum;

begin
  result := '';
  For i := mefirst to methird do
    If i in ASet then
      begin
        If (Result <> '') then
          Result := Result + ', ';
          Result := Result + MyEnumNames[i];
        end;
      end;

end;

Var
  S : TMyEnums;

begin
  O := TMyTestObject.Create;
  O.SetField := [mefirst, meSecond, meThird];
  Writeln ('Set property      : ');
  Writeln ('Value                                : ', SetAsString(O.SetField));
  Writeln ('Ord(Value)                            : ', Longint(O.SetField));
  Writeln ('Get (name)                             : ', GetSetProp(O, 'SetField'));
  PI := GetPropInfo(O, 'SetField');
  Writeln ('Get (propinfo)                          : ', GetSetProp(O, PI, false));
  S := [mefirst, meThird];
  SetOrdProp(O, 'SetField', Integer(S));
  Write ('Set (name,[mefirst, methird]) : ');
  Writeln (SetAsString(O.SetField));
  S := [meSecond];
  SetOrdProp(O, PI, Integer(S));
  Write ('Set (propinfo,[meSecond])      : ');
  Writeln (SetAsString(O.SetField));
  O.Free;
end.

```

---

### 40.7.18 GetStrProp

**Synopsis:** Return the value of a string property.

**Declaration:** `function GetStrProp(Instance: TObject; PropInfo: PPropInfo) : Ansistring`  
`function GetStrProp(Instance: TObject; const PropName: String) : String`

**Visibility:** default

**Description:** `GetStrProp` returns the value of the string property described by `PropInfo` or with name `PropName` for object `Instance`.

**Errors:** No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid string property of `Instance`. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

**See also:** `SetStrProp` ([1638](#)), `SetWideStrProp` ([1640](#)), `GetOrdProp` ([1623](#)), `GetFloatProp` ([1617](#)), `GetInt64Prop` ([1618](#)), `GetMethodProp` ([1620](#))



See also: [GetStrProp \(1628\)](#), [SetUnicodeStrProp \(1639\)](#)

### 40.7.21 GetVariantProp

Synopsis: Return the value of a variant property.

**Declaration:** `function GetVariantProp(Instance: TObject; PropInfo: PPropInfo) : Variant`  
`function GetVariantProp(Instance: TObject; const PropName: String)`  
`: Variant`

Visibility: default

**Description:** Due to missing Variant support, the `GetVariantProp` function is not yet implemented. Provided for Delphi compatibility only.

Errors:

See also: [SetVariantProp \(1639\)](#)

### 40.7.22 GetWideStrProp

Synopsis: Read a widestring property

**Declaration:** `function GetWideStrProp(Instance: TObject; PropInfo: PPropInfo)`  
`: WideString`  
`function GetWideStrProp(Instance: TObject; const PropName: String)`  
`: WideString`

Visibility: default

**Description:** `GetWideStrProp` returns the value of the widestring property described by `PropInfo` or with name `PropName` for object `Instance`.

**Errors:** No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid widestring property of `Instance`. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: [GetStrProp \(1628\)](#), [SetWideStrProp \(1640\)](#), [GetOrdProp \(1623\)](#), [GetFloatProp \(1617\)](#), [GetInt64Prop \(1618\)](#), [GetMethodProp \(1620\)](#)

### 40.7.23 IsPublishedProp

Synopsis: Check whether a published property exists.

**Declaration:** `function IsPublishedProp(Instance: TObject; const PropName: String)`  
`: Boolean`  
`function IsPublishedProp(AClass: TClass; const PropName: String)`  
`: Boolean`

Visibility: default

**Description:** `IsPublishedProp` returns true if a class has a published property with name `PropName`. The class can be specified in one of two ways:

**AClass** A class pointer to the class.

**Instance** An instance of the class.



**Errors:** No checks are done to ensure `Instance` or `AClass` are valid pointers. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `IsStoredProp` ([1631](#)), `PropIsType` ([1632](#))

**Listing:** `./typinfex/ex10.pp`

---

```

program example10;

{ This program demonstrates the IsPublishedProp function }

{$mode objfpc}

uses rttiobj, typinfo;

Var
  O : TMyTestObject;
  PI : PPropInfo;

begin
  O := TMyTestObject.Create;
  Writeln( 'Property tests      : ');
  Write( 'IsPublishedProp(O, BooleanField)      : ');
  Writeln( IsPublishedProp(O, 'BooleanField') );
  Write( 'IsPublishedProp(Class, BooleanField) : ');
  Writeln( IsPublishedProp(O.ClassType, 'BooleanField') );
  Write( 'IsPublishedProp(O, SomeField)        : ');
  Writeln( IsPublishedProp(O, 'SomeField') );
  Write( 'IsPublishedProp(Class, SomeField)    : ');
  Writeln( IsPublishedProp(O.ClassType, 'SomeField') );
  O.Free;
end.

```

---

#### 40.7.24 IsStoredProp

**Synopsis:** Check whether a property is stored.

**Declaration:** `function IsStoredProp(Instance: TObject; PropInfo: PPropInfo) : Boolean`  
`function IsStoredProp(Instance: TObject; const PropName: String)`  
`: Boolean`

**Visibility:** default

**Description:** `IsStoredProp` returns `True` if the `Stored` modifier evaluates to `True` for the property described by `PropInfo` or with name `PropName` for object `Instance`. It returns `False` otherwise. If the function returns `True`, this indicates that the property should be written when streaming the object `Instance`.

If there was no `stored` modifier in the declaration of the property, `True` will be returned.

**Errors:** No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid property of `Instance`. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `IsPublishedProp` ([1630](#)), `PropIsType` ([1632](#))

**Listing:** `./typinfex/ex11.pp`

---

```

program example11;

{ This program demonstrates the IsStoredProp function }

{$mode objfpc}

uses rttiobj, typinfo;

Var
  O : TMyTestObject;
  PI : PPropInfo;

begin
  O:=TMyTestObject.Create;
  Writeln('Stored tests      : ');
  Write('IsStoredProp(O, StoredIntegerConstFalse)    : ');
  Writeln(IsStoredProp(O, 'StoredIntegerConstFalse'));
  Write('IsStoredProp(O, StoredIntegerConstTrue)     : ');
  Writeln(IsStoredProp(O, 'StoredIntegerConstTrue'));
  Write('IsStoredProp(O, StoredIntegerMethod)         : ');
  Writeln(IsStoredProp(O, 'StoredIntegerMethod'));
  Write('IsStoredProp(O, StoredIntegerVirtualMethod) : ');
  Writeln(IsStoredProp(O, 'StoredIntegerVirtualMethod'));
  O.Free;
end.

```

---

### 40.7.25 PropIsType

**Synopsis:** Check the type of a published property.

**Declaration:**

```

function PropIsType(Instance: TObject; const PropName: String;
                    TypeKind: TTypeKind) : Boolean
function PropIsType(AClass: TClass; const PropName: String;
                    TypeKind: TTypeKind) : Boolean

```

**Visibility:** default

**Description:** PropIsType returns True if the property with name PropName has type TypeKind. It returns False otherwise. The class to be examined can be specified in one of two ways:

**AClass** A class pointer.

**Instance** An instance of the class.

**Errors:** No checks are done to ensure Instance or AClass are valid pointers. Specifying an invalid property name in PropName will result in an EPropertyError exception.

See also: IsPublishedProp ([1630](#)), IsStoredProp ([1631](#)), PropType ([1633](#))

**Listing:** ./typinfex/ex16.pp

---

```

program example16;

{ This program demonstrates the PropIsType function }

{$mode objfpc}

```

---

```

uses rttiobj , typinfo ;

Var
  O : TMyTestObject ;

begin
  O:= TMyTestObject . Create ;
  WriteIn( 'Property tests      : ' );
  Write( 'PropIsType(O, BooleanField , tkBool)      : ' );
  WriteIn( PropIsType(O, ' BooleanField ', tkBool ));
  Write( 'PropIsType(Class , BooleanField , tkBool) : ' );
  WriteIn( PropIsType(O, ClassType , ' BooleanField ', tkBool ));
  Write( 'PropIsType(O, ByteField , tkString)      : ' );
  WriteIn( PropIsType(O, ' ByteField ', tkString ));
  Write( 'PropIsType(Class , ByteField , tkString) : ' );
  WriteIn( PropIsType(O, ClassType , ' ByteField ', tkString ));
  O. Free ;
end.

```

---

### 40.7.26 PropType

**Synopsis:** Return the type of a property

**Declaration:** `function PropType(Instance: TObject; const PropName: String) : TTypeKind`  
`function PropType(AClass: TClass; const PropName: String) : TTypeKind`

**Visibility:** default

**Description:** `PropType` returns the type of the property `PropName` for a class. The class to be examined can be specified in one of 2 ways:

**AClass** A class pointer.

**Instance** An instance of the class.

**Errors:** No checks are done to ensure `Instance` or `AClass` are valid pointers. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `IsPublishedProp` ([1630](#)), `IsStoredProp` ([1631](#)), `PropIsType` ([1632](#))

**Listing:** `./typinfex/ex17.pp`

---

```

program example17 ;

{ This program demonstrates the PropType function }

{$mode objfpc}

uses rttiobj , typinfo ;

Var
  O : TMyTestObject ;

begin
  O:= TMyTestObject . Create ;
  WriteIn( 'Property tests      : ' );
  Write( 'PropType(O, BooleanField)      : ' );
  WriteIn( TypeName[ PropType(O, ' BooleanField ' ) ] );

```

---

```

Write ( 'PropType (Class , BooleanField ) : ' );
WriteIn (TypeNames [PropType (O. ClassType , ' BooleanField ' )]);
Write ( 'PropType (O, ByteField ) : ' );
WriteIn (TypeNames [PropType (O, ' ByteField ' )]);
Write ( 'PropType (Class , ByteField ) : ' );
WriteIn (TypeNames [PropType (O. ClassType , ' ByteField ' )]);
O. Free;
end.

```

---

### 40.7.27 SetEnumProp

Synopsis: Set value of an enumerated-type property

Declaration: `procedure SetEnumProp (Instance: TObject; const PropName: String;  
const Value: String)  
procedure SetEnumProp (Instance: TObject; const PropInfo: PPropInfo;  
const Value: String)`

Visibility: default

Description: `SetEnumProp` sets the property described by `PropInfo` or with name `PropName` to `Value`. `Value` must be a string with the name of the enumerate value, i.e. it can be used as an argument to `GetEnumValue` (1617).

For an example, see `GetEnumProp` (1616).

Errors: No checks are done to ensure `Instance` or `PropInfo` are valid pointers. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `GetEnumProp` (1616), `SetStrProp` (1638), `SetFloatProp` (1634), `SetInt64Prop` (1635), `SetMethodProp` (1635)

### 40.7.28 SetFloatProp

Synopsis: Set value of a float property.

Declaration: `procedure SetFloatProp (Instance: TObject; const PropName: String;  
Value: Extended)  
procedure SetFloatProp (Instance: TObject; PropInfo: PPropInfo;  
Value: Extended)`

Visibility: default

Description: `SetFloatProp` assigns `Value` to the property described by `PropInfo` or with name `Propname` for the object `Instance`.

For an example, see `GetFloatProp` (1617).

Errors: No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid float property of `Instance`. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `GetFloatProp` (1617), `SetOrdProp` (1636), `SetStrProp` (1638), `SetInt64Prop` (1635), `SetMethodProp` (1635)

### 40.7.29 SetInt64Prop

Synopsis: Set value of a Int64 property

Declaration: `procedure SetInt64Prop(Instance: TObject; PropInfo: PPropInfo;  
   const Value: Int64)  
           procedure SetInt64Prop(Instance: TObject; const PropName: String;  
   const Value: Int64)`

Visibility: default

Description: `SetInt64Prop` assigns `Value` to the property of type `Int64` that is described by `PropInfo` or with name `Propname` for the object `Instance`.

For an example, see `GetInt64Prop` (1618).

Errors: No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid `Int64` property of `Instance`. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `GetInt64Prop` (1618), `GetMethodProp` (1620), `SetOrdProp` (1636), `SetStrProp` (1638), `SetFloatProp` (1634)

### 40.7.30 SetInterfaceProp

Synopsis: Set interface-valued property

Declaration: `procedure SetInterfaceProp(Instance: TObject; const PropName: String;  
   const Value: IInterface)  
           procedure SetInterfaceProp(Instance: TObject; PropInfo: PPropInfo;  
   const Value: IInterface)`

Visibility: default

Description: `SetInterfaceProp` assigns `Value` to the the object property described by `PropInfo` or with name `Propname` for the object `Instance`.

Errors: No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid interface property of `Instance`. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `GetInterfaceProp` (1619), `SetObjectProp` (1636), `SetOrdProp` (1636), `SetStrProp` (1638), `SetFloatProp` (1634), `SetInt64Prop` (1635), `SetMethodProp` (1635)

### 40.7.31 SetMethodProp

Synopsis: Set the value of a method property

Declaration: `procedure SetMethodProp(Instance: TObject; PropInfo: PPropInfo;  
   const Value: TMethod)  
           procedure SetMethodProp(Instance: TObject; const PropName: String;  
   const Value: TMethod)`

Visibility: default

Description: `SetMethodProp` assigns `Value` to the method the property described by `PropInfo` or with name `Propname` for object `Instance`.

The type `TMethod` of the `Value` parameter is defined in the `SysUtils` unit as:

```
TMethod = packed record
  Code, Data: Pointer;
end;
```

Data should point to the instance of the class with the method Code.

For an example, see `GetMethodProp` (1620).

**Errors:** No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid method property of `Instance`. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `GetMethodProp` (1620), `SetOrdProp` (1636), `SetStrProp` (1638), `SetFloatProp` (1634), `SetInt64Prop` (1635)

### 40.7.32 SetObjectProp

**Synopsis:** Set the value of an object-type property.

**Declaration:**

```
procedure SetObjectProp(Instance: TObject; const PropName: String;
  Value: TObject)
procedure SetObjectProp(Instance: TObject; PropInfo: PPropInfo;
  Value: TObject)
```

**Visibility:** default

**Description:** `SetObjectProp` assigns `Value` to the the object property described by `PropInfo` or with name `Propname` for the object `Instance`.

For an example, see `GetObjectProp` (1622).

**Errors:** No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid object property of `Instance`. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `GetObjectProp` (1622), `SetOrdProp` (1636), `SetStrProp` (1638), `SetFloatProp` (1634), `SetInt64Prop` (1635), `SetMethodProp` (1635)

### 40.7.33 SetOrdProp

**Synopsis:** Set value of an ordinal property

**Declaration:**

```
procedure SetOrdProp(Instance: TObject; PropInfo: PPropInfo; Value: Int64)
procedure SetOrdProp(Instance: TObject; const PropName: String;
  Value: Int64)
```

**Visibility:** default

**Description:** `SetOrdProp` assigns `Value` to the the ordinal property described by `PropInfo` or with name `Propname` for the object `Instance`.

Ordinal properties that can be set include:

**Integers and subranges of integers** The actual value of the integer must be passed.

**Enumerated types and subranges of enumerated types** The ordinal value of the enumerated type must be passed.

**Subrange types** of integers or enumerated types. Here the ordinal value must be passed.

**Sets** If the base type of the set has less than 31 possible values. For each possible value; the corresponding bit of `Value` must be set.

For an example, see `GetOrdProp` ([1623](#)).

**Errors:** No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid ordinal property of `Instance`. No range checking is performed. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `GetOrdProp` ([1623](#)), `SetStrProp` ([1638](#)), `SetFloatProp` ([1634](#)), `SetInt64Prop` ([1635](#)), `SetMethodProp` ([1635](#))

### 40.7.34 SetPropValue

**Synopsis:** Set property value as variant

**Declaration:** `procedure SetPropValue(Instance: TObject; const PropName: String;  
const Value: Variant)`

**Visibility:** default

**Description:** Due to missing Variant support, this function is not yet implemented; it is provided for Delphi compatibility only.

**Errors:**

### 40.7.35 SetSetProp

**Synopsis:** Set value of set-typed property.

**Declaration:** `procedure SetSetProp(Instance: TObject; const PropName: String;  
const Value: String)  
procedure SetSetProp(Instance: TObject; const PropInfo: PPropInfo;  
const Value: String)`

**Visibility:** default

**Description:** `SetSetProp` sets the property specified by `PropInfo` or `PropName` for object `Instance` to `Value`. `Value` is a string which contains a comma-separated list of values, each value being a string-representation of the enumerated value that should be included in the set. The value should be accepted by the `StringToSet` ([1640](#)) function.

The value can be formed using the `SetToString` ([1638](#)) function.

For an example, see `GetSetProp` ([1627](#)).

**Errors:** No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid ordinal property of `Instance`. No range checking is performed. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `GetSetProp` ([1627](#)), `SetOrdProp` ([1636](#)), `SetStrProp` ([1638](#)), `SetFloatProp` ([1634](#)), `SetInt64Prop` ([1635](#)), `SetMethodProp` ([1635](#)), `SetToString` ([1638](#)), `StringToSet` ([1640](#))

### 40.7.36 SetStrProp

Synopsis: Set value of a string property

Declaration:

```

procedure SetStrProp(Instance: TObject; const PropName: String;
                    const Value: AnsiString)
procedure SetStrProp(Instance: TObject; PropInfo: PPropInfo;
                    const Value: Ansistring)

```

Visibility: default

Description: SetStrProp assigns Value to the string property described by PropInfo or with name Propname for object Instance.

For an example, see GetStrProp (1628)

Errors: No checking is done whether Instance is non-nil, or whether PropInfo describes a valid string property of Instance. Specifying an invalid property name in PropName will result in an EPropertyError exception.

See also: GetStrProp (1628), SetWideStrProp (1640), SetOrdProp (1636), SetFloatProp (1634), SetInt64Prop (1635), SetMethodProp (1635)

### 40.7.37 SetToString

Synopsis: Convert set to a string description

Declaration:

```

function SetToString(TypeInfo: PTypeInfo; Value: Integer;
                    Brackets: Boolean) : String
function SetToString(PropInfo: PPropInfo; Value: Integer;
                    Brackets: Boolean) : String
function SetToString(PropInfo: PPropInfo; Value: Integer) : String

```

Visibility: default

Description: SetToString takes an integer representation of a set (as received e.g. by GetOrdProp) and turns it into a string representing the elements in the set, based on the type information found in the PropInfo property information. By default, the string representation is not surrounded by square brackets. Setting the Brackets parameter to True will surround the string representation with brackets.

The function returns the string representation of the set.

Errors: No checking is done to see whether PropInfo points to valid property information.

See also: GetEnumName (1615), GetEnumValue (1617), StringToSet (1640)

**Listing:** ./typinfex/ex18.pp

---

```

program example18;

{ This program demonstrates the SetToString function }

{$mode objfpc}

uses rttiobj, typinfo;

Var
  O : TMyTestObject;
  PI : PPropInfo;

```



```

    I : longint;

begin
    O:= TMyTestObject.Create;
    PI:= GetPropInfo(O, 'SetField');
    O.SetField :=[ mefirst ,meSecond,meThird];
    I:=GetOrdProp(O, PI);
    WriteLn('Set property to string : ');
    WriteLn('Value  : ',SetToString(PI,I,False));
    O.SetField :=[ mefirst ,meSecond];
    I:=GetOrdProp(O, PI);
    WriteLn('Value  : ',SetToString(PI,I,True));
    I:=StringToSet(PI, 'mefirst');
    SetOrdProp(O,PI,I);
    I:=GetOrdProp(O, PI);
    WriteLn('Value  : ',SetToString(PI,I,False));
    I:=StringToSet(PI, '[mesecond, methird]');
    SetOrdProp(O,PI,I);
    I:=GetOrdProp(O, PI);
    WriteLn('Value  : ',SetToString(PI,I,True));
    O.Free;
end.

```

### 40.7.38 SetUnicodeStrProp

Synopsis: Set UnicodeString-valued property

Declaration: `procedure SetUnicodeStrProp(Instance: TObject;const PropName: String;  
const Value: UnicodeString)  
procedure SetUnicodeStrProp(Instance: TObject;PropInfo: PPropInfo;  
const Value: UnicodeString)`

Visibility: default

Description: `SetUnicodeStrProp` sets the UnicodeString property from Instance to Value, where the property is identified by the PropInfo pointer or the PropertyName.

Errors: If no property of the indicated name exists, or it is not of type unicodestring, an exception will occur.

See also: `SetStrProp` ([1638](#)), `GetUnicodeStrProp` ([1629](#))

### 40.7.39 SetVariantProp

Synopsis: Set value of a variant property

Declaration: `procedure SetVariantProp(Instance: TObject;const PropName: String;  
const Value: Variant)  
procedure SetVariantProp(Instance: TObject;PropInfo: PPropInfo;  
const Value: Variant)`

Visibility: default

Description: Due to missing Variant support, this function is not yet implemented. Provided for Delphi compatibility only.

Errors:

### 40.7.40 SetWideStrProp

Synopsis: Set a widestring property

Declaration: 

```
procedure SetWideStrProp(Instance: TObject; const PropName: String;
                        const Value: WideString)
procedure SetWideStrProp(Instance: TObject; PropInfo: PPropInfo;
                        const Value: WideString)
```

Visibility: default

Description: `SetWideStrProp` assigns `Value` to the widestring property described by `PropInfo` or with name `Propname` for object `Instance`.

Errors: No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid widestring property of `Instance`. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `GetWideStrProp` (1630), `SetStrProp` (1638), `SetOrdProp` (1636), `SetFloatProp` (1634), `SetInt64Prop` (1635), `SetMethodProp` (1635)

### 40.7.41 StringToSet

Synopsis: Convert string description to a set.

Declaration: 

```
function StringToSet(PropInfo: PPropInfo; const Value: String) : Integer
function StringToSet(TypeInfo: PTypeInfo; const Value: String) : Integer
```

Visibility: default

Description: `StringToSet` converts the string representation of a set in `Value` to a integer representation of the set, using the property information found in `PropInfo`. This property information should point to the property information of a set property. The function returns the integer representation of the set. (i.e, the set value, typecast to an integer)

The string representation can be surrounded with square brackets, and must consist of the names of the elements of the base type of the set. The base type of the set should be an enumerated type. The elements should be separated by commas, and may be surrounded by spaces. each of the names will be fed to the `GetEnumValue` (1617) function.

For an example, see `SetToString` (1638).

Errors: No checking is done to see whether `PropInfo` points to valid property information. If a wrong name is given for an enumerated value, then an `EPropertyError` will be raised.

See also: `GetEnumName` (1615), `GetEnumValue` (1617), `SetToString` (1638)

## 40.8 EPropertyConvertError

### 40.8.1 Description

`EPropertyConvertError` is not used in the Free Pascal implementation of the `typinfo` unit, but is declared for Delphi compatibility.

## **40.9 EPropertyError**

### **40.9.1 Description**

Exception raised in case of an error in one of the functions.

# Chapter 41

## Reference for unit 'Unix'

### 41.1 Used units

Table 41.1: Used units by unit 'Unix'

Name	Page
BaseUnix	<a href="#">101</a>
unixtype	<a href="#">1679</a>

### 41.2 Constants, types and variables

#### 41.2.1 Constants

`ARG_MAX = UnixType.ARG_MAX`

Maximum number of arguments to a program.

`fs_ext = $137d`

File system type (StatFS ([1676](#))): (ext) Extended

`fs_ext2 = $ef53`

File system type (StatFS ([1676](#))): (ext2) Second extended

`fs_iso = $9660`

File system type (StatFS ([1676](#))): ISO 9660

`fs_minix = $137f`

File system type (StatFS ([1676](#))): Minix

`fs_minix_30 = $138f`

File system type (StatFS (1676)): Minix 3.0

`fs_minix_V2 = 0x2468`

File system type (StatFS (1676)): Minix V2

`fs_msdos = 0x4d44`

File system type (StatFS (1676)): MSDOS (FAT)

`fs_nfs = 0x6969`

File system type (StatFS (1676)): NFS

`fs_old_ext2 = 0xef51`

File system type (StatFS (1676)): (ext2) Old second extended

`fs_proc = 0x9fa0`

File system type (StatFS (1676)): PROC fs

`fs_xia = 0x012FD16D`

File system type (StatFS (1676)): XIA

`IOctl_TCGETS = 0x5401`

IOCTL call number: get Terminal Control settings

`LOCK_EX = 2`

`FpFLock (1666)` Exclusive lock

`LOCK_NB = 4`

`FpFLock (1666)` Non-blocking operation

`LOCK_SH = 1`

`FpFLock (1666)` Shared lock

`LOCK_UN = 8`

`FpFLock (1666)` unlock

`MAP_FAILED = baseunix.MAP_FAILED`

Error return value for `mmap`: `mmap` operation failed.

`MAP_FIXED = baseunix.MAP_FIXED`

FpMMap (1642) map type: Interpret addr exactly

MAP\_PRIVATE = baseunix.MAP\_PRIVATE

FpMMap (1642) map type: Changes are private

MAP\_SHARED = baseunix.MAP\_SHARED

FpMMap (1642) map type: Share changes

MAP\_TYPE = baseunix.MAP\_TYPE

FpMMap (1642) map type: Bitmask for type of mapping

MS\_ASYNC = 1

Asynchronous operation flag for msync call

MS\_INVALIDATE = 2

Invalidate other mappings of file flag for msync call

MS\_SYNC = 4

Synchronous operation flag for msync call

NAME\_MAX = UnixType.NAME\_MAX

Maximum filename length.

Open\_Accmode = 3

Bitmask to determine access mode in open flags.

Open\_Append = 2shl9

File open mode: Append to file

Open\_Creat = 1shl6

File open mode: Create if file does not yet exist.

Open\_Direct = 4shl12

File open mode: Minimize caching effects

Open\_Directory = 2shl15

File open mode: File must be directory.

Open\_Excl = 2shl6

File open mode: Open exclusively

`Open_LargeFile = 1shl15`

File open mode: Open for 64-bit I/O

`Open_NDelay = Open_NonBlock`

File open mode: Alias for `Open_NonBlock` (1645)

`Open_NoCtty = 4shl6`

File open mode: No TTY control.

`Open_NoFollow = 4shl15`

File open mode: Fail if file is symbolic link.

`Open_NonBlock = 4shl9`

File open mode: Open in non-blocking mode

`Open_RdOnly = 0`

File open mode: Read only

`Open_RdWr = 2`

File open mode: Read/Write

`Open_Sync = 1shl12`

File open mode: Write to disc at once

`Open_Trunc = 1shl9`

File open mode: Truncate file to length 0

`Open_WrOnly = 1`

File open mode: Write only

`PATH_MAX = UnixType.PATH_MAX`

Maximum pathname length.

`PRIO_PGRP = UnixType.PRIO_PGRP`

`fpGetPriority` (1642) option: Get process group priority.

`PRIO_PROCESS = UnixType.PRIO_PROCESS`

`fpGetPriority` (1642) option: Get process priority.

`PRIO_USER = UnixType.PRIO_USER`

`fpGetPriority` (1642) option: Get user priority.

`PROT_EXEC = baseunix.PROT_EXEC`

`FpMMap` (1642) memory access: page can be executed

`PROT_NONE = baseunix.PROT_NONE`

`FpMMap` (1642) memory access: page can not be accessed

`PROT_READ = baseunix.PROT_READ`

`FpMMap` (1642) memory access: page can be read

`PROT_WRITE = baseunix.PROT_WRITE`

`FpMMap` (1642) memory access: page can be written

`P_IN = 1`

Input file descriptor of pipe pair.

`P_OUT = 2`

Output file descriptor of pipe pair.

`SIG_MAXSIG = UnixType.SIG_MAXSIG`

Maximum system signal number.

`STAT_IFBLK = $6000`

File (`#rtl.baseunix.stat` (135) record) mode: Block device

`STAT_IFCHR = $2000`

File (`#rtl.baseunix.stat` (135) record) mode: Character device

`STAT_IFDIR = $4000`

File (`#rtl.baseunix.stat` (135) record) mode: Directory

`STAT_IFIFO = $1000`

File (`#rtl.baseunix.stat` (135) record) mode: FIFO

`STAT_IFLNK = $a000`



File (#rtl.baseunix.stat (135) record) mode: Link

STAT\_IFMT = \$f000

File (#rtl.baseunix.stat (135) record) mode: File type bit mask

STAT\_IFREG = \$8000

File (#rtl.baseunix.stat (135) record) mode: Regular file

STAT\_IFSOCK = \$c000

File (#rtl.baseunix.stat (135) record) mode: Socket

STAT\_IRGRP = STAT\_IROTH sh13

File (#rtl.baseunix.stat (135) record) mode: Group read permission

STAT\_IROTH = \$4

File (#rtl.baseunix.stat (135) record) mode: Other read permission

STAT\_IRUSR = STAT\_IROTH sh16

File (#rtl.baseunix.stat (135) record) mode: Owner read permission

STAT\_IRWXG = STAT\_IRWXO sh13

File (#rtl.baseunix.stat (135) record) mode: Group permission bits mask

STAT\_IRWXO = \$7

File (#rtl.baseunix.stat (135) record) mode: Other permission bits mask

STAT\_IRWXU = STAT\_IRWXO sh16

File (#rtl.baseunix.stat (135) record) mode: Owner permission bits mask

STAT\_ISGID = \$0400

File (#rtl.baseunix.stat (135) record) mode: GID bit set

STAT\_ISUID = \$0800

File (#rtl.baseunix.stat (135) record) mode: UID bit set

STAT\_ISVTX = \$0200

File (#rtl.baseunix.stat (135) record) mode: Sticky bit set

STAT\_IWGRP = STAT\_IWOTH sh13

File (#rtl.baseunix.stat (135) record) mode: Group write permission

STAT\_IWOTH = \$2

File (#rtl.baseunix.stat (135) record) mode: Other write permission

STAT\_IWUSR = STAT\_IWOTH shl6

File (#rtl.baseunix.stat (135) record) mode: Owner write permission

STAT\_IXGRP = STAT\_IXOTH shl3

File (#rtl.baseunix.stat (135) record) mode: Others execute permission

STAT\_IXOTH = \$1

File (#rtl.baseunix.stat (135) record) mode: Others execute permission

STAT\_IXUSR = STAT\_IXOTH shl6

File (#rtl.baseunix.stat (135) record) mode: Others execute permission

SYS\_NMLN = UnixType.SYS\_NMLN

Max system name length.

Wait\_Any = -1

#rtl.baseunix.fpWaitPID (191): Wait on any process

Wait\_Clone = \$80000000

#rtl.baseunix.fpWaitPID (191): Wait on clone processes only.

Wait\_MyPGRP = 0

#rtl.baseunix.fpWaitPID (191): Wait processes from current process group

Wait\_NoHang = 1

#rtl.baseunix.fpWaitPID (191): Do not wait

Wait\_UnTraced = 2

#rtl.baseunix.fpWaitPID (191): Also report stopped but untraced processes

### 41.2.2 Types

`cbool = UnixType.cbool`

Boolean type

`cchar = UnixType.cchar`

Alias for `#rtl.UnixType.cchar` ([1681](#))

`cdouble = UnixType.cdouble`

Double precision real format.

`cfloat = UnixType.cfloat`

Floating-point real format

`cint = UnixType.cint`

C type: integer (natural size)

`cint16 = UnixType.cint16`

C type: 16 bits sized, signed integer.

`cint32 = UnixType.cint32`

C type: 32 bits sized, signed integer.

`cint64 = UnixType.cint64`

C type: 64 bits sized, signed integer.

`cint8 = UnixType.cint8`

C type: 8 bits sized, signed integer.

`clock_t = UnixType.clock_t`

Clock ticks type

`clong = UnixType.clong`

C type: long signed integer (double sized)

`clonglong = UnixType.clonglong`

C type: 64-bit (double long) signed integer.

`coff_t = UnixType.TOff`

character offset type.

```
cschar = UnixType.cschar
```

**Signed character type**

```
cshort = UnixType.cshort
```

**C type: short signed integer (half sized)**

```
csigned = UnixType.csigned
```

csigned is an alias for cint ([1649](#)).

```
csint = UnixType.csint
```

**Signed integer**

```
csize_t = UnixType.size_t
```

**Character size type.**

```
cslong = UnixType.cslong
```

The size is CPU dependent.

```
cslonglong = UnixType.cslonglong
```

cslonglong is an alias for clonglong ([1649](#)).

```
csshort = UnixType.csshort
```

**Short signed integer type**

```
cuchar = UnixType.cuchar
```

Alias for #rtl.UnixType.cuchar ([1682](#))

```
cuint = UnixType.cuint
```

**C type: unsigned integer (natural size)**

```
cuint16 = UnixType.cuint16
```

**C type: 16 bits sized, unsigned integer.**

```
cuint32 = UnixType.cuint32
```

**C type: 32 bits sized, unsigned integer.**

```
cuint64 = UnixType.cuint64
```

C type: 64 bits sized, unsigned integer.

```
cuint8 = UnixType.cuint8
```

C type: 8 bits sized, unsigned integer.

```
culong = UnixType.culong
```

C type: long unsigned integer (double sized)

```
culonglong = UnixType.culonglong
```

C type: 64-bit (double long) unsigned integer.

```
cunsigned = UnixType.cunsigned
```

Alias for `#rtl.unixtype.cunsigned` ([1683](#))

```
cushort = UnixType.cushort
```

C type: short unsigned integer (half sized)

```
dev_t = UnixType.dev_t
```

Device descriptor type.

```
gid_t = UnixType.gid_t
```

Group ID type.

```
ino_t = UnixType.ino_t
```

Inode type.

```
mode_t = UnixType.mode_t
```

Inode mode type.

```
nlink_t = UnixType.nlink_t
```

Number of links type.

```
off_t = UnixType.off_t
```

Offset type.

```
pbool = UnixType.pbool
```

Pointer to boolean type `cbool` ([1649](#))

```
pcchar = UnixType.pcchar
```

Alias for `#rtl.UnixType.pcchar` (1684)

`pcdouble = UnixType.pcdouble`

Pointer to `cdouble` (124) type.

`pcfloat = UnixType.pcfloating`

Pointer to `cfloat` (124) type.

`pcint = UnixType.pcint`

Pointer to `cInt` (1649) type.

`pcint16 = UnixType.pcint16`

Pointer to 16-bit signed integer type

`pcint32 = UnixType.pcint32`

Pointer to signed 32-bit integer type

`pcint64 = UnixType.pcint64`

Pointer to signed 64-bit integer type

`pcint8 = UnixType.pcint8`

Pointer to 8-bits signed integer type

`pClock = UnixType.pClock`

Pointer to `TClock` (1656) type.

`pclong = UnixType.pclong`

Pointer to `cLong` (1649) type.

`pclonglong = UnixType.pclonglong`

Pointer to `longlong` type.

`pcschar = UnixType.pcschar`

Pointer to character type `cschar` (1650).

`pcshort = UnixType.pcsshort`

Pointer to `cShort` (1650) type.

`pcsigned = UnixType.pcsigned`

Pointer to signed integer type `csigned` (1650).

```
pcsint = UnixType.pcsint
```

Pointer to signed integer type `csint` (1650)

```
pcsize_t = UnixType.psize_t
```

Pointer to character size type `pcsize_t`.

```
pcslong = UnixType.pcslong
```

Pointer of the signed long `clong` (1650)

```
pcslonglong = UnixType.pcslonglong
```

Pointer to Signed longlong type `clonglong` (1650)

```
pcsshort = UnixType.pcsshort
```

Pointer to short signed integer type `csshort` (1650)

```
pcuchar = UnixType.pcuchar
```

Alias for `#rtl.UnixType.pcuchar` (1685)

```
pcuint = UnixType.pcuint
```

Pointer to `cUInt` (1650) type.

```
pcuint16 = UnixType.pcuint16
```

Pointer to 16-bit unsigned integer type

```
pcuint32 = UnixType.pcuint32
```

Pointer to unsigned 32-bit integer type

```
pcuint64 = UnixType.pcuint64
```

Pointer to unsigned 64-bit integer type

```
pcuint8 = UnixType.pcuint8
```

Pointer to 8-bits unsigned integer type

```
pculong = UnixType.pculong
```

Pointer to `cuLong` (1651) type.

```
pculonglong = UnixType.pculonglong
```

Unsigned longlong type

`pcunsigned = UnixType.pcunsigned`

Alias for `#rtl.unixtype.pcunsigned` (1686)

`pcushort = UnixType.pcushort`

Pointer to `cuShort` (1651) type.

`pDev = UnixType.pDev`

Pointer to `TDev` (1656) type.

`pGid = UnixType.pGid`

Pointer to `TGid` (1656) type.

`pid_t = UnixType.pid_t`

Process ID type.

`pIno = UnixType.pIno`

Pointer to `TIno` (1656) type.

`pMode = UnixType.pMode`

Pointer to `TMode` (1656) type.

`pnLink = UnixType.pnLink`

Pointer to `TnLink` (1657) type.

`pOff = UnixType.pOff`

Pointer to `TOff` (1657) type.

`pPid = UnixType.pPid`

Pointer to `TPid` (1657) type.

`pSize = UnixType.pSize`

Pointer to `TSize` (1657) type.

`pSize_t = UnixType.pSize_t`

Pointer to type `Size_t`.

`pSocklen = UnixType.pSocklen`



Pointer to TSockLen (1657) type.

```
psSize = UnixType.psSize
```

Pointer to TsSize (1657) type

```
pthread_cond_t = UnixType.pthread_cond_t
```

Thread conditional variable type.

```
pthread_mutex_t = UnixType.pthread_mutex_t
```

Thread mutex type.

```
pthread_t = UnixType.pthread_t
```

Posix thread type.

```
pTime = UnixType.pTime
```

Pointer to TTime (1657) type.

```
ptimespec = UnixType.ptimespec
```

Pointer to timespec (1656) type.

```
ptimeval = UnixType.ptimeval
```

Pointer to timeval (1656) type.

```
ptime_t = UnixType.ptime_t
```

Pointer to time\_t (1656) type.

```
pUId = UnixType.pUId
```

Pointer to TUid (1657) type.

```
size_t = UnixType.size_t
```

Size specification type.

```
socklen_t = UnixType.socklen_t
```

Socket address length type.

```
ssize_t = UnixType.ssize_t
```

Small size type.

```
TClock = UnixType.TClock
```

Table 41.2: Enumeration values for type TFSearchOption

Value	Explanation
CurrentDirectoryFirst	Search the current directory first, before all directories in the search path.
CurrentDirectoryLast	Search the current directory last, after all directories in the search path
NoCurrentDirectory	Do not search the current directory unless it is specified in the search path.

Alias for clock\_t (1649) type.

TDev = UnixType.TDev

Alias for dev\_t (1651) type.

TFSearchOption = (NoCurrentDirectory, CurrentDirectoryFirst,  
CurrentDirectoryLast)

Describes the search strategy used by FSearch (1668)

TGid = UnixType.TGid

Alias for gid\_t (1651) type.

timespec = UnixType.timespec

Short time specification type.

timeval = UnixType.timeval

Time specification type.

time\_t = UnixType.time\_t

Time span type

TIno = UnixType.TIno

Alias for ino\_t (1651) type.

TIOctlRequest = UnixType.TIOctlRequest

Alias for the TIOctlRequest (1691) type in unixtypes

TMode = UnixType.TMode

Alias for mode\_t (1651) type.

TnLink = UnixType.TnLink

Alias for `nlink_t` (1651) type.

```
TOff = UnixType.TOff
```

Alias for `off_t` (1651) type.

```
TPid = UnixType.TPid
```

Alias for `pid_t` (1654) type.

```
Tpipe = baseunix.tfildes
```

Array describing a pipe pair of filedescriptors.

```
TSize = UnixType.TSize
```

Alias for `size_t` (1655) type

```
TSocklen = UnixType.TSocklen
```

Alias for `socklen_t` (1655) type.

```
TsSize = UnixType.TsSize
```

Alias for `ssize_t` (1655) type

```
tstatfs = UnixType.TStatFs
```

Record describing a file system in the `baseunix.fpstatfs` (1642) call.

```
TTime = UnixType.TTime
```

Alias for `TTime` (1657) type.

```
Ttimespec = UnixType.Ttimespec
```

Alias for `TimeSpec` (1656) type.

```
TTimeVal = UnixType.TTimeVal
```

Alias for `timeval` (1656) type.

```
TUId = UnixType.TUId
```

Alias for `uid_t` (1657) type.

```
uid_t = UnixType.uid_t
```

User ID type

### 41.2.3 Variables

`tzdaylight` : Boolean

Indicates whether daylight savings time is active.

`tzname` : Array[boolean] of pchar

Timezone name.

## 41.3 Procedures and functions

### 41.3.1 AssignPipe

Synopsis: Create a set of pipe file handlers

**Declaration:** `function AssignPipe(var pipe_in: cint;var pipe_out: cint) : cint`  
`function AssignPipe(var pipe_in: text;var pipe_out: text) : cint`  
`function AssignPipe(var pipe_in: File;var pipe_out: File) : cint`

Visibility: default

**Description:** `AssignPipe` creates a pipe, i.e. two file objects, one for input, one for output. What is written to `Pipe_out`, can be read from `Pipe_in`.

This call is overloaded. The in and out pipe can take three forms: an typed or untyped file, a text file or a file descriptor.

If a text file is passed then reading and writing from/to the pipe can be done through the usual `Readln(Pipe_in, ...)` and `Writeln(Pipe_out, ...)` procedures.

The function returns `True` if everything went succesfully, `False` otherwise.

**Errors:** In case the function fails and returns `False`, extended error information is returned by the `FpGetErrno` (154) function:

**sys\_enfile** Too many file descriptors for this process.

**sys\_enfile** The system file table is full.

See also: `POpen` (1672), `#rtl.baseunix.FpMkFifo` (163)

**Listing:** `./unixex/ex36.pp`

**Program** Example36;

*{ Program to demonstrate the AssignPipe function. }*

**Uses** BaseUnix, Unix;

**Var** pipi, pipo : Text;  
       s : **String**;

**begin**

**Writeln** ( 'Assigning Pipes.' );

**If** assignpipe(pipi, pipo) <> 0 **then**

**Writeln** ( 'Error assigning pipes !', fpgeterrno );

**Writeln** ( 'Writing to pipe, and flushing.' );

**Writeln** ( pipo, 'This is a textstring' ); close(pipo);

---

```

Writeln ( 'Reading from pipe.' );
While not eof(pipi) do
begin
  Readln ( pipi,s);
  Writeln ( 'Read from pipe : ',s);
end;
close ( pipi);
writeln ( 'Closed pipes.' );
writeln
end.

```

---

### 41.3.2 AssignStream

Synopsis: Assign stream for in and output to a program

Declaration: `function AssignStream(var StreamIn: text;var Streamout: text;`  
`const Prog: ansiString;`  
`const args: Array of ansistring) : cint`  
`function AssignStream(var StreamIn: text;var Streamout: text;`  
`var streamerr: text;const Prog: ansiString;`  
`const args: Array of ansistring) : cint`

Visibility: default

Description: `AssignStream` creates a 2 or 3 pipes, i.e. two (or three) file objects, one for input, one for output, (and one for standard error) the other ends of these pipes are connected to standard input and output (and standard error) of `Prog`. `Prog` is the path of a program (including path). The options for the program can be specified in `Args`.

What is written to `StreamOut`, will go to the standard input of `Prog`. Whatever is written by `Prog` to it's standard output can be read from `StreamIn`. Whatever is written by `Prog` to it's standard error read from `StreamErr`, if present.

Reading and writing happens through the usual `Readln(StreamIn,...)` and `Writeln (StreamOut,...)` procedures.

**Remark:** You should *not* use `Reset` or `Rewrite` on a file opened with `POpen`. This will close the file before re-opening it again, thereby closing the connection with the program.

The function returns the process ID of the spawned process, or -1 in case of error.

Errors: Extended error information is returned by the `FpGetErrno` ([154](#)) function.

**sys\_enfile** Too many file descriptors for this process.

**sys\_enfile** The system file table is full.

Other errors include the ones by the `fork` and `exec` programs

See also: `AssignPipe` ([1658](#)), `POpen` ([1672](#))

**Listing:** `./unixex/ex38.pp`

---

**Program** `Example38;`

*{ Program to demonstrate the AssignStream function. }*

**Uses** `BaseUnix, Unix;`

**Var** `Si, So : Text;`

---

```

S : String;
i : longint;

begin
  if not (paramstr(1)='-son') then
    begin
      Writeln ('Calling son');
      Assignstream (Si,So,'./ex38',[ '-son' ]);
      if fpgeterrno <> 0 then
        begin
          writeln ('AssignStream failed !');
          halt(1);
        end;
      Writeln ('Speaking to son');
      For i:=1 to 10 do
        begin
          writeln (so,'Hello son !');
          if ioresult <> 0 then writeln ('Can''t speak to son...');
        end;
      For i:=1 to 3 do writeln (so,'Hello chap !');
      close (so);
      while not eof(si) do
        begin
          readln (si,s);
          writeln ('Father: Son said : ',S);
        end;
      Writeln ('Stopped conversation');
      Close (Si);
      Writeln ('Put down phone');
    end
  Else
    begin
      Writeln ('This is the son ');
      While not eof (input) do
        begin
          readln (s);
          if pos ('Hello son !',S) <> 0 then
            Writeln ('Hello Dad !')
          else
            writeln ('Who are you ?');
          end;
        close (output);
      end
    end
end.

```

---

### 41.3.3 FpExecL

Synopsis: Execute process (using argument list, environment)

Declaration: `function FpExecL(const PathName: AnsiString;  
const S: Array of AnsiString) : cint`

Visibility: default

Description: `FpExecL` replaces the currently running program with the program, specified in `PathName`. `S` is an array of command options. The executable in `PathName` must be an absolute pathname. The current process' environment is passed to the program. On success, `FpExecL` does not return.

Errors: Extended error information is returned by the `FpGetErrno` (154) function:

**sys\_eaccess**File is not a regular file, or has no execute permission. A component of the path has no search permission.

**sys\_eperm**The file system is mounted *noexec*.

**sys\_e2big**Argument list too big.

**sys\_enoexec**The magic number in the file is incorrect.

**sys\_enoent**The file does not exist.

**sys\_enomem**Not enough memory for kernel, or to split command line.

**sys\_enotdir**A component of the path is not a directory.

**sys\_eLOOP**The path contains a circular reference (via symlinks).

See also: `#rtl.baseunix.fplexecve` (148), `FpExecv` (1663), `FpExecvp` (1664), `FpExecle` (1661), `FpExeclp` (1662), `#rtl.baseunix.FpFork` (151)

**Listing:** ./unixex/ex77.pp

---

**Program** Example77;

*{ Program to demonstrate the FPEXecL function. }*

**Uses** Unix, strings;

**begin**

*{ Execute 'ls -l', with current environment. }*  
*{ 'ls' is NOT looked for in PATH environment variable. }*  
 FPEXecL ( '/bin/ls', ['-l'] );

**end.**

---

### 41.3.4 FpExecLE

**Synopsis:** Execute process (using argument list, environment)

**Declaration:** `function FpExecLE(const PathName: AnsiString;  
                               const S: Array of AnsiString; MyEnv: ppchar) : cint`

**Visibility:** default

**Description:** `FpExecLE` replaces the currently running program with the program, specified in `PathName`. `S` is an array of command options. The executable in `PathName` must be an absolute pathname. The environment in `MyEnv` is passed to the program. On success, `FpExecLE` does not return.

Errors: Extended error information is returned by the `FpGetErrno` (154) function:

**sys\_eaccess**File is not a regular file, or has no execute permission. A component of the path has no search permission.

**sys\_eperm**The file system is mounted *noexec*.

**sys\_e2big**Argument list too big.

**sys\_enoexec**The magic number in the file is incorrect.

**sys\_enoent**The file does not exist.

**sys\_enomem**Not enough memory for kernel, or to split command line.

**sys\_enotdir**A component of the path is not a directory.

**sys\_eloop**The path contains a circular reference (via symlinks).

See also: #rtl.baseunix.fpexecve (148), FpExecv (1663), FpExecvp (1664), FpExecl (1660), FpExeclp (1662), #rtl.baseunix.FpFork (151)

**Listing:** ./unixex/ex11.pp

**Program** Example11;

*{ Program to demonstrate the Execl function. }*

**Uses** Unix, strings;

**begin**

*{ Execute 'ls -l', with current environment. }*  
*{ 'ls' is NOT looked for in PATH environment variable. }*  
*{ envp is defined in the system unit. }*  
 Execl ( '/bin/ls -l', envp );

**end.**

### 41.3.5 FpExecLP

**Synopsis:** Execute process (using argument list, environment; search path)

**Declaration:** function FpExecLP(const PathName: AnsiString;  
                               const S: Array of AnsiString) : cint

**Visibility:** default

**Description:** FpExecLP replaces the currently running program with the program, specified in PathName. S is an array of command options. The executable in PathName is searched in the path, if it isn't an absolute filename. The current environment is passed to the program. On success, FpExecLP does not return.

**Errors:** Extended error information is returned by the FpGetErrno (154) function:

**sys\_eaccess**File is not a regular file, or has no execute permission. A component of the path has no search permission.

**sys\_eperm**The file system is mounted *noexec*.

**sys\_e2big**Argument list too big.

**sys\_enoexec**The magic number in the file is incorrect.

**sys\_enoent**The file does not exist.

**sys\_enomem**Not enough memory for kernel, or to split command line.

**sys\_enotdir**A component of the path is not a directory.

**sys\_eloop**The path contains a circular reference (via symlinks).

See also: #rtl.baseunix.fpexecve (148), FpExecv (1663), FpExecvp (1664), FpExecl (1660), FpExeclp (1662), #rtl.baseunix.FpFork (151)

**Listing:** ./unixex/ex76.pp



---

**Program** Example76;

*{ Program to demonstrate the FpExeclp function. }*

**Uses** Unix , strings ;

**begin**

*{ Execute 'ls -l', with current environment. }*  
*{ 'ls' is looked for in PATH environment variable. }*  
*{ envp is defined in the system unit. }*  
 FpExeclp ( 'ls' , [ '-l' ] );

**end.**

---

### 41.3.6 FpExecLPE

**Synopsis:** Execute a program in the path, and pass it an environment

**Declaration:** function FpExecLPE(const PathName: AnsiString;  
                                   const S: Array of AnsiString;env: ppchar) : cint

**Visibility:** default

**Description:** FpExecLPE does the same as FpExecLP (1662), but additionally it specifies the environment for the new process in env, a pointer to a null-terminated array of null-terminated strings.

**Errors:** On success, this function does not return.

**See also:** FpExecLP (1662), FpExecLE (1661)

### 41.3.7 FpExecV

**Synopsis:** Execute process

**Declaration:** function FpExecV(const PathName: AnsiString;args: ppchar) : cint

**Visibility:** default

**Description:** FpExecV replaces the currently running program with the program, specified in PathName. It gives the program the options in args. This is a pointer to an array of pointers to null-terminated strings. The last pointer in this array should be nil. The current environment is passed to the program. On success, FpExecV does not return.

**Errors:** Extended error information is returned by the FpGetErrno (154) function:

**sys\_eaccess**File is not a regular file, or has no execute permission. A component of the path has no search permission.

**sys\_eperm**The file system is mounted *noexec*.

**sys\_e2big**Argument list too big.

**sys\_enoexec**The magic number in the file is incorrect.

**sys\_enoent**The file does not exist.

**sys\_enomem**Not enough memory for kernel.

**sys\_enotdir**A component of the path is not a directory.

**sys\_eloop**The path contains a circular reference (via symlinks).

See also: `#rtl.baseunix.fpexecve` ([148](#)), `FpExecvp` ([1664](#)), `FpExecle` ([1661](#)), `FpExecl` ([1660](#)), `FpExeclp` ([1662](#)), `#rtl.baseunix.FpFork` ([151](#))

**Listing:** `./unixex/ex8.pp`

---

**Program** `Example8`;

*{ Program to demonstrate the Execv function. }*

**Uses** `Unix`, `strings`;

**Const** `Arg0` : `PChar` = `'/bin/lS'`;  
           `Arg1` : `Pchar` = `'-l'`;

**Var** `PP` : `PPchar`;

**begin**

`GetMem` (`PP`, `3*SizeOf(Pchar)`);  
   `PP[0]` := `Arg0`;  
   `PP[1]` := `Arg1`;  
   `PP[3]` := `Nil`;  
   *{ Execute '/bin/lS -l', with current environment }*  
   `fpExecv` (`'/bin/lS'`, `pp`);

**end.**

---

### 41.3.8 FpExecVP

**Synopsis:** Execute process, search path

**Declaration:** `function FpExecVP(const PathName: AnsiString; args: ppchar) : cint`

**Visibility:** `default`

**Description:** `FpExecVP` replaces the currently running program with the program, specified in `PathName`. The executable in `path` is searched in the path, if it isn't an absolute filename. It gives the program the options in `args`. This is a pointer to an array of pointers to null-terminated strings. The last pointer in this array should be `nil`. The current environment is passed to the program. On success, `execvp` does not return.

**Errors:** Extended error information is returned by the `FpGetErrno` ([154](#)) function:

**sys\_eaccess** File is not a regular file, or has no execute permission. A component of the path has no search permission.

**sys\_eperm** The file system is mounted *noexec*.

**sys\_e2big** Argument list too big.

**sys\_enoexec** The magic number in the file is incorrect.

**sys\_enoent** The file does not exist.

**sys\_enomem** Not enough memory for kernel.

**sys\_enotdir** A component of the path is not a directory.

**sys\_eloop** The path contains a circular reference (via symlinks).

See also: `#rtl.baseunix.fpexecve` ([148](#)), `FpExecv` ([1663](#)), `FpExecle` ([1661](#)), `FpExecl` ([1660](#)), `FpExeclp` ([1662](#)), `#rtl.baseunix.FpFork` ([151](#))



**Listing:** ./unixex/ex79.pp

**Program** Example79;

*{ Program to demonstrate the FpExecVP function. }*

**Uses** Unix, strings;

**Const** Arg0 : PChar = 'ls';  
           Arg1 : Pchar = '-l';

**Var** PP : PPchar;

**begin**

**GetMem** (PP,3\***SizeOf**(Pchar));  
 PP[0]:=Arg0;  
 PP[1]:=Arg1;  
 PP[2]:= **Nil**;  
*{ Execute 'ls -l', with current environment. }*  
*{ 'ls' is looked for in PATH environment variable. }*  
 fpExecvp ('ls',pp);

**end.**

### 41.3.10 fpFlock

**Synopsis:** Lock a file (advisory lock)

**Declaration:** function fpFlock(var T: text;mode: cint) : cint  
                   function fpFlock(var F: File;mode: cint) : cint  
                   function fpFlock(fd: cint;mode: cint) : cint

**Visibility:** default

**Description:** FpFlock implements file locking. it sets or removes a lock on the file F. F can be of type Text or File, or it can be a linux filedescriptor (a longint) Mode can be one of the following constants :

**LOCK\_SH**sets a shared lock.

**LOCK\_EX**sets an exclusive lock.

**LOCK\_UN**unlocks the file.

**LOCK\_NB**This can be OR-ed together with the other. If this is done the application doesn't block when locking.

The function returns zero if successful, a nonzero return value indicates an error.

**Errors:** Extended error information is returned by the FpGetErrno ([154](#)) function:

See also: #rtl.baseunix.FpFcntl ([149](#)), FSync ([1670](#))

### 41.3.11 fpfStatFS

**Synopsis:** Retrieve filesystem information.

**Declaration:** function fpfStatFS(Fd: cint;Info: PStatFS) : cint

**Visibility:** default

**Description:** `fpStatFS` returns in `Info` information about the filesystem on which the open file descriptor `fd` resides. `Info` is of type `tstatfs`. The function returns 0 if the call was succesfull, or an error code if the call failed.

**Errors:** On error, a non-zero error code is returned

See also: `fpStatFS` ([1667](#)), `fpfStat` ([1642](#))

### 41.3.12 `fpfsync`

**Synopsis:** Flush cached data to disk

**Declaration:** `function fpfsync(fd: cint) : cint`

**Visibility:** default

**Description:** `fpfsync` forces the system to write all paged (in-memory) changes to file descriptor `fd` to disk. If the call was succesful, 0 is returned.

**Errors:** On error, a nonzero error-code is returned.

### 41.3.13 `fpgettimeofday`

**Synopsis:** Return kernel time of day in GMT

**Declaration:** `function fpgettimeofday(tp: timeval;tzp: timezone) : cint`

**Visibility:** default

**Description:** `FpGetTimeOfDay` returns the number of seconds since 00:00, January 1 1970, GMT in a `timeval` record. This time NOT corrected any way, not taking into account timezones, daylight savings time and so on.

It is simply a wrapper to the kernel system call.

**Errors:** None.

### 41.3.14 `fpStatFS`

**Synopsis:** Retrieve filesystem information.

**Declaration:** `function fpStatFS(Path: pchar;Info: PStatFS) : cint`

**Visibility:** default

**Description:** `fpStatFS` returns in `Info` information about the filesystem on which the file or path `Path` resides. `Info` is of type `tstatfs`. The function returns 0 if the call was succesfull, or an error code if the call failed.

**Errors:** On error, a non-zero error code is returned

See also: `fpFStatFS` ([1666](#)), `fpStat` ([1642](#))

### 41.3.15 fpSystem

Synopsis: Execute and feed command to system shell

Declaration: `function fpSystem(const Command: String) : cint`  
`function fpSystem(const Command: AnsiString) : cint`

Visibility: default

Description: `Shell` invokes the bash shell (`/bin/sh`), and feeds it the command `Command` (using the `-c` option). The function then waits for the command to complete, and then returns the exit status of the command, or 127 if it could not complete the `FpFork` (151) or `FpExecve` (148) calls.

Errors: Errors are reported in `fpErrNo` (101)

See also: `POpen` (1672), `Shell` (1674), `#rtl.baseunix.FpFork` (151), `#rtl.baseunix.fpexecve` (148)

**Listing:** `./unixex/ex80.pp`

---

```
program example56;

uses Unix;

{ Program to demonstrate the Shell function }

Var S : Longint;

begin
  Writeln ('Output of ls -l *.pp');
  S:=fpSystem('ls -l *.pp');
  Writeln ('Command exited with status : ',S);
end.
```

---

### 41.3.16 FSearch

Synopsis: Search for file in search path.

Declaration: `function FSearch(const path: AnsiString;dirlist: AnsiString;`  
`CurrentDirStrategy: TFSearchOption) : AnsiString`  
`function FSearch(const path: AnsiString;dirlist: AnsiString)`  
`: AnsiString`

Visibility: default

Description: `FSearch` searches in `DirList`, a colon separated list of directories, for a file named `Path`. It then returns a path to the found file.

The `CurrentDirStrategy` determines how the current directory is treated when searching:

**NoCurrentDirectory** Do not search the current directory unless it is specified in the search path.

**CurrentDirectoryFirstSearch** the current directory first, before all directories in the search path.

**CurrentDirectoryLastSearch** the current directory last, after all directories in the search path

It is mainly provided to mimic DOS search path behaviour. Default behaviour is to search the current directory first.

Errors: An empty string if no such file was found.

See also: `#rtl.unixutil.FNMatch` ([1696](#))

**Listing:** `./unixex/ex46.pp`

---

**Program** `Example46`;

*{ Program to demonstrate the FSearch function. }*

**Uses** `BaseUnix, Unix, Strings`;

**begin**

**WriteLn** ( 'ls is in : ', FSearch ( 'ls', **strpas**(fpGetenv( 'PATH' )) ));

**end.**

---

### 41.3.17 fStatFS

**Synopsis:** Retrieve filesystem information from a file descriptor.

**Declaration:** `function fStatFS(Fd: cint; var Info: tstatfs) : cint`

**Visibility:** `default`

**Description:** `fStatFS` returns in `Info` information about the filesystem on which the file with file descriptor `fd` resides. `Info` is of type `TStatFS` ([1692](#)).

The function returns zero if the call was succesful, a nonzero value is returned if the call failed.

**Errors:** Extended error information is returned by the `FpGetErrno` ([154](#)) function:

**sys\_enotdir** A component of `Path` is not a directory.

**sys\_einval** Invalid character in `Path`.

**sys\_enoent** `Path` does not exist.

**sys\_eaccess** Search permission is denied for component in `Path`.

**sys\_eloop** A circular symbolic link was encountered in `Path`.

**sys\_eio** An error occurred while reading from the filesystem.

See also: `StatFS` ([1676](#)), `#rtl.baseunix.FpLStat` ([161](#))

**Listing:** `./unixex/ex91.pp`

---

**program** `Example30`;

*{ Program to demonstrate the FSStat function. }*

**uses** `BaseUnix, Unix, UnixType`;

**var** `s : string`;

`fd : cint`;

`info : tstatfs`;

**begin**

**writeln** ( 'Info about current partition : ' );

`s := ' . ';`

**while** `s <> 'q'` **do**

**begin**

`Fd := fpOpen(S, O_RDONLY);`

---

```

if (fd >= 0) then
begin
  if fpstatfs (fd, @info) <> 0 then
  begin
    writeln('Fstat failed. Errno : ', fpgeterrno);
    halt (1);
  end;
  FpClose(fd);
  writeln;
  writeln('Result of fsstat on file ', s, '.');
  {$if defined(Linux) or defined(sunos)}
    // SysV like.
    writeln('fstype : ', info.fstype);
  {$else}
    // BSD like, incl Mac OS X.
    writeln('fstype : ', info.ftype);
  {$endif}

  writeln('bsize : ', info.bsize);
  writeln('bfree : ', info.bfree);
  writeln('bavail : ', info.bavail);
  writeln('files : ', info.files);
  writeln('ffree : ', info.ffree);
  {$ifdef FreeBSD}
    writeln('fsid : ', info.fsid[0]);
  {$else}
    writeln('fsid : ', info.fsid[0]);
  writeln('Namelen : ', info.namelen);
  {$endif}
  write('Type name of file to do fsstat. (q quits) : ');
  readln(s)

end;
end;
end.

```

---

### 41.3.18 fsync

Synopsis: Synchronize file's kernel data with disk.

Declaration: `function fsync(fd: cint) : cint`

Visibility: default

Description: `Fsync` synchronizes the kernel data for file `fd` (the cache) with the disk. The call will not return till all file data was written to disk.

If the call was succesfull, 0 is returned. On failure, a nonzero value is returned.

Errors: Extended error information is returned by the `FpGetErrno` ([154](#)) function:

See also: `FpFlock` ([1666](#))

### 41.3.19 GetDomainName

Synopsis: Return current domain name

Declaration: `function GetDomainName : String`



Visibility: default

Description: Get the domain name of the machine on which the process is running. An empty string is returned if the domain is not set.

Errors: None.

See also: `GetHostName` ([1671](#))

**Listing:** `./unixex/ex39.pp`

---

**Program** `Example39;`

*{ Program to demonstrate the GetDomainName function. }*

**Uses** `Unix;`

**begin**

**WriteLn** ( 'Domain name of this machine is : ', `GetDomainName` );

**end.**

---

### 41.3.20 `GetHostName`

Synopsis: Return host name

Declaration: `function GetHostName : String`

Visibility: default

Description: Get the hostname of the machine on which the process is running. An empty string is returned if hostname is not set.

Errors: None.

See also: `GetDomainName` ([1670](#))

**Listing:** `./unixex/ex40.pp`

---

**Program** `Example40;`

*{ Program to demonstrate the GetHostName function. }*

**Uses** `unix;`

**begin**

**WriteLn** ( 'Name of this machine is : ', `GetHostName` );

**end.**

---

### 41.3.21 `GetLocalTimezone`

Synopsis: Return local timzeone information

Declaration: `procedure GetLocalTimezone(timer: cint; var leap_correct: cint;`  
`var leap_hit: cint)`  
`procedure GetLocalTimezone(timer: cint)`

Visibility: default

**Description:** `GetLocalTimeZone` returns the local timezone information. It also initializes the `TZSeconds` variable, which is used to correct the epoch time to local time.

There should never be any need to call this function directly. It is called by the initialization routines of the Linux unit.

See also: `GetTimezoneFile` (1672), `ReadTimezoneFile` (1673)

### 41.3.22 GetTimezoneFile

**Synopsis:** Return name of timezone information file

**Declaration:** `function GetTimezoneFile : String`

**Visibility:** default

**Description:** `GetTimezoneFile` returns the location of the current timezone file. The location of file is determined as follows:

- 1.If `/etc/timezone` exists, it is read, and the contents of this file is returned. This should work on Debian systems.
- 2.If `/usr/lib/zoneinfo/localtime` exists, then it is returned. (this file is a symlink to the timezone file on SuSE systems)
- 3.If `/etc/localtime` exists, then it is returned. (this file is a symlink to the timezone file on RedHat systems)

**Errors:** If no file was found, an empty string is returned.

See also: `ReadTimezoneFile` (1673)

### 41.3.23 PClose

**Synopsis:** Close file opened with `POpen` (1672)

**Declaration:** `function PClose(var F: File) : cint`  
`function PClose(var F: text) : cint`

**Visibility:** default

**Description:** `PClose` closes a file opened with `POpen` (1672). It waits for the command to complete, and then returns the exit status of the command.

For an example, see `POpen` (1672)

**Errors:** Extended error information is returned by the `FpGetErrno` (154) function.

See also: `POpen` (1672)

### 41.3.24 POpen

**Synopsis:** Pipe file to standard input/output of program

**Declaration:** `function POpen(var F: text;const Prog: Ansistring;rw: Char) : cint`  
`function POpen(var F: File;const Prog: Ansistring;rw: Char) : cint`

**Visibility:** default

**Description:** `POpen` runs the command specified in `Prog`, and redirects the standard in or output of the command to the other end of the pipe `F`. The parameter `rw` indicates the direction of the pipe. If it is set to 'W', then `F` can be used to write data, which will then be read by the command from `stdin`. If it is set to 'R', then the standard output of the command can be read from `F`. `F` should be reset or rewritten prior to using it. `F` can be of type `Text` or `File`. A file opened with `POpen` can be closed with `Close`, but also with `PClose` (1672). The result is the same, but `PClose` returns the exit status of the command `Prog`.

**Errors:** Extended error information is returned by the `FpGetErrno` (154) function. Errors are essentially those of the `Execve`, `Dup` and `AssignPipe` commands.

See also: `AssignPipe` (1658), `PClose` (1672)

**Listing:** `./unixex/ex37.pp`

**Program** `Example37`;

*{ Program to demonstrate the Popen function. }*

**uses** `BaseUnix, Unix`;

**var** `f` : `text`;  
       `i` : `longint`;

**begin**

```

writeln ('Creating a shell script to which echoes its arguments');
writeln ('and input back to stdout');
assign (f, 'test21a');
rewrite (f);
writeln (f, '#!/bin/sh');
writeln (f, 'echo this is the child speaking.... ');
writeln (f, 'echo got arguments \'$*\');
writeln (f, 'cat');
writeln (f, 'exit 2');
writeln (f);
close (f);
fpchmod ('test21a', &755);
popen (f, './test21a arg1 arg2', 'W');
if fpgeterrno <> 0 then
    writeln ('error from POpen : errno : ', fpgeterrno);
for i := 1 to 10 do
    writeln (f, 'This is written to the pipe, and should appear on stdout. ');
Flush(f);
Writeln ('The script exited with status : ', PClose (f));
writeln;
writeln ('Press <return> to remove shell script. ');
readln;
assign (f, 'test21a');
erase (f)
end.
```

### 41.3.25 ReadTimezoneFile

**Synopsis:** Read the timezone file and initialize time routines

**Declaration:** `procedure ReadTimezoneFile(fn: String)`

Visibility: default

**Description:** `ReadTimeZoneFile` reads the timezone file `fn` and initializes the local time routines based on the information found there.

There should be no need to call this function. The initialization routines of the linux unit call this routine at unit startup.

Errors: None.

See also: `GetTimeZoneFile` (1672), `GetLocalTimezone` (1671)

### 41.3.26 SeekDir

Synopsis: Seek to position in directory

**Declaration:** `procedure SeekDir(p: pDir; loc: clong)`

Visibility: default

**Description:** `SeekDir` sets the directory pointer to the `loc`-th entry in the directory structure pointed to by `p`.

For an example, see `#rtl.baseunix.fpOpenDir` (168).

Errors: Extended error information is returned by the `FpGetErrno` (154) function:

See also: `#rtl.baseunix.fpCloseDir` (145), `#rtl.baseunix.fpReadDir` (172), `#rtl.baseunix.fpOpenDir` (168), `TellDir` (1677)

### 41.3.27 SelectText

Synopsis: Wait for event on text file.

**Declaration:** `function SelectText(var T: Text; TimeOut: ptimeval) : cint`  
`function SelectText(var T: Text; TimeOut: cint) : cint`

Visibility: default

**Description:** `SelectText` executes the `FpSelect` (175) call on a file of type `Text`. You can specify a timeout in `TimeOut`. The `SelectText` call determines itself whether it should check for read or write, depending on how the file was opened : With `Reset` it is checked for reading, with `Rewrite` and `Append` it is checked for writing.

Errors: See `#rtl.baseunix.FpSelect` (175). `SYS_EBADF` can also mean that the file wasn't opened.

See also: `#rtl.baseunix.FpSelect` (175)

### 41.3.28 Shell

Synopsis: Execute and feed command to system shell

**Declaration:** `function Shell(const Command: String) : cint`  
`function Shell(const Command: AnsiString) : cint`

Visibility: default

**Description:** `Shell` invokes the bash shell (`/bin/sh`), and feeds it the command `Command` (using the `-c` option). The function then waits for the command to complete, and then returns the exit status of the command, or 127 if it could not complete the `FpFork` (151) or `FpExecve` (148) calls.

Errors: Extended error information is returned by the `FpGetErrno` ([154](#)) function:

See also: `POpen` ([1672](#)), `FpSystem` ([1668](#)), `#rtl.baseunix.FpFork` ([151](#)), `#rtl.baseunix.fpexecve` ([148](#))

**Listing:** `./unixex/ex56.pp`

---

```

program example56;

uses Unix;

{ Program to demonstrate the Shell function }

Var S : Longint;

begin
  WriteLn ( 'Output of ls -l *.pp' );
  S:=Shell ( 'ls -l *.pp' );
  WriteLn ( 'Command exited with status : ',S);
end.

```

---

### 41.3.29 SigRaise

Synopsis: Raise a signal (send to current process)

Declaration: `procedure SigRaise(sig: Integer)`

Visibility: default

Description: `SigRaise` sends a `Sig` signal to the current process.

Errors: None.

See also: `#rtl.baseunix.FpKill` ([159](#)), `#rtl.baseunix.FpGetPid` ([156](#))

**Listing:** `./unixex/ex65.pp`

---

```

Program example64;

{ Program to demonstrate the SigRaise function. }

uses Unix, BaseUnix;

Var
  oa, na : PSigActionrec;

Procedure DoSig(sig : Longint); cdecl;

begin
  writeln ( 'Receiving signal: ', sig );
end;

begin
  new(na);
  new(oa);
  na^.sa_handler:= SigActionHandler (@DoSig);
  fillchar (na^.Sa_Mask, sizeof(na^.Sa_Mask), #0);
  na^.Sa_Flags:=0;
  { $ifdef Linux }

```

---

```

    // this member is linux only, and afaik even there arcane
    na^.Sa_Restorer:=Nil;
  {$endif}
  if fpSigAction(SigUshr1,na,oa)<>0 then
    begin
      writeln('Error: ',fpgeterrno);
      halt(1);
    end;
  Writeln('Sending USR1 (',sigusr1,') signal to self. ');
  SigRaise(sigusr1);
end.

```

---

### 41.3.30 StatFS

Synopsis: Retrieve filesystem information from a path.

Declaration: `function StatFS(Path: pchar;var Info: tstatfs) : cint`  
`function StatFS(Path: ansistring;var Info: tstatfs) : cint`

Visibility: default

Description: StatFS returns in Info information about the filesystem on which the file Path resides. Info is of type TStatFS ([1692](#)).

The function returns zero if the call was succesful, a nonzero value is returned if the call failed.

Errors: Extended error information is returned by the FpGetErrno ([154](#)) function:

**sys\_enotdir**A component of Path is not a directory.  
**sys\_einval**Invalid character in Path.  
**sys\_enoent**Path does not exist.  
**sys\_eaccess**Search permission is denied for component inPath.  
**sys\_eloop**A circular symbolic link was encountered in Path.  
**sys\_eio**An error occurred while reading from the filesystem.

See also: #rtl.baseunix.FpStat ([183](#)), #rtl.baseunix.FpLStat ([161](#))

**Listing:** ./unixex/ex91.pp

---

```

program Example30;

{ Program to demonstrate the FSStat function. }

uses BaseUnix, Unix, UnixType;

var s : string;
    fd : cint;
    info : tstatfs;

begin
  writeln('Info about current partition : ');
  s:= '.';
  while s<>'q' do
    begin
      Fd:=fpOpen(S,O_RDONLY);
      if (fd>=0) then

```

---

```

begin
  if fpstatfs (fd,@info)<>0 then
    begin
      writeln('Fstat failed. Errno : ',fpgeterrno);
      halt (1);
    end;
    FpClose(fd);
    writeln;
    writeln ('Result of fsstat on file ''',s, '''.');
    {$if defined(Linux) or defined(sunos)}
      // SysV like.
      writeln ('fstype   : ',info.fstype);
    {$else}
      // BSD like , incl Mac OS X.
      writeln ('fstype   : ',info.ftype);
    {$endif}

    writeln ('bsize    : ',info.bsize);
    writeln ('bfree     : ',info.bfree);
    writeln ('bavail    : ',info.bavail);
    writeln ('files     : ',info.files);
    writeln ('ffree     : ',info.ffree);
    {$ifdef FreeBSD}
      writeln ('fsid      : ',info.fsid[0]);
    {$else}
      writeln ('fsid      : ',info.fsid[0]);
    writeln ('Namelen   : ',info.namelen);
    {$endif}
    write ('Type name of file to do fsstat. (q quits) : ');
    readln (s)

  end;
end;
end.

```

---

### 41.3.31 Telldir

Synopsis: Return current location in a directory

Declaration: function Telldir(p: pDir) : TOff

Visibility: default

Description: Telldir returns the current location in the directory structure pointed to by p. It returns -1 on failure.

For an example, see #rtl.baseunix.fpOpenDir ([168](#)).

Errors:

See also: #rtl.baseunix.fpCloseDir ([145](#)), #rtl.baseunix.fpReadDir ([172](#)), #rtl.baseunix.fpOpenDir ([168](#)), SeekDir ([1674](#))

### 41.3.32 WaitProcess

Synopsis: Wait for process to terminate.

Declaration: function WaitProcess(Pid: cint) : cint

Visibility: default

**Description:** `WaitProcess` waits for process `PID` to exit. `WaitProcess` is equivalent to the `#rtl.baseunix.FpWaitPID` (191) call:

```
FpWaitPid(PID, @result, 0)
```

Handles of Signal interrupts (`errno=EINTR`), and returns the Exitcode of Process `PID` (`>=0`) or - Status if it was terminated

Errors: None.

See also: `#rtl.baseunix.FpWaitPID` (191), `#rtl.baseunix.WTERMSIG` (193), `#rtl.baseunix.WSTOPSIG` (193), `#rtl.baseunix.WIFEXITED` (192), `WIFSTOPPED` (1678), `#rtl.baseunix.WIFSIGNALLED` (193), `W_EXITCODE` (1678), `W_STOPCODE` (1678), `#rtl.baseunix.WEXITSTATUS` (192)

### 41.3.33 WIFSTOPPED

**Synopsis:** Check whether the process is currently stopped.

**Declaration:** `function WIFSTOPPED(Status: Integer) : Boolean`

Visibility: default

**Description:** `WIFSTOPPED` checks `Status` and returns `true` if the process is currently stopped. This is only possible if `WUNTRACED` was specified in the options of `FpWaitPID` (191).

See also: `#rtl.baseunix.FpWaitPID` (191), `WaitProcess` (1677), `#rtl.baseunix.WTERMSIG` (193), `#rtl.baseunix.WSTOPSIG` (193), `#rtl.baseunix.WIFEXITED` (192), `#rtl.baseunix.WIFSIGNALLED` (193), `W_EXITCODE` (1678), `W_STOPCODE` (1678), `#rtl.baseunix.WEXITSTATUS` (192)

### 41.3.34 W\_EXITCODE

**Synopsis:** Construct an exit status based on an return code and signal.

**Declaration:** `function W_EXITCODE(ReturnCode: Integer; Signal: Integer) : Integer`

Visibility: default

**Description:** `W_EXITCODE` combines `ReturnCode` and `Signal` to a status code fit for `WaitPid`.

See also: `#rtl.baseunix.FpWaitPID` (191), `WaitProcess` (1677), `#rtl.baseunix.WTERMSIG` (193), `#rtl.baseunix.WSTOPSIG` (193), `#rtl.baseunix.WIFEXITED` (192), `WIFSTOPPED` (1678), `#rtl.baseunix.WIFSIGNALLED` (193), `W_EXITCODE` (1678), `W_STOPCODE` (1678), `#rtl.baseunix.WEXITSTATUS` (192)

### 41.3.35 W\_STOPCODE

**Synopsis:** Construct an exit status based on a signal.

**Declaration:** `function W_STOPCODE(Signal: Integer) : Integer`

Visibility: default

**Description:** `W_STOPCODE` constructs an exit status based on `Signal`, which will cause `WIFSIGNALLED` (193) to return `True`

See also: `#rtl.baseunix.FpWaitPID` (191), `WaitProcess` (1677), `#rtl.baseunix.WTERMSIG` (193), `#rtl.baseunix.WSTOPSIG` (193), `#rtl.baseunix.WIFEXITED` (192), `WIFSTOPPED` (1678), `#rtl.baseunix.WIFSIGNALLED` (193), `W_EXITCODE` (1678), `#rtl.baseunix.WEXITSTATUS` (192)



# Chapter 42

## Reference for unit 'unixtype'

### 42.1 Overview

The `unixtype` unit contains the definitions of basic unix types. It was initially implemented by Marco van de Voort.

When porting to a new unix platform, this unit should be adapted to the sizes and conventions of the platform to which the compiler is ported.

### 42.2 Constants, types and variables

#### 42.2.1 Constants

`ARG_MAX = 131072`

Max number of command-line arguments.

`NAME_MAX = 255`

Max length (in bytes) of filename

`PATH_MAX = 4095`

Max length (in bytes) of pathname

`Prio_PGrp = 1`

`rtl.unix.fpGetPriority` ([1679](#)) option: Get process group priority.

`Prio_Process = 0`

`#rtl.unix.fpGetPriority` ([1642](#)) option: Get process priority.

`Prio_User = 2`

`#rtl.unix.fpGetPriority` ([1642](#)) option: Get user priority.

`SIG_MAXSIG = 128`

Maximum signal number.

`SYS_NMLN = 65`

Max system namelength

`_PTHREAD_MUTEX_ADAPTIVE_NP = 3`

Mutex options:

`_PTHREAD_MUTEX_DEFAULT = _PTHREAD_MUTEX_NORMAL`

Mutex options:

`_PTHREAD_MUTEX_ERRORCHECK = _PTHREAD_MUTEX_ERRORCHECK_NP`

Mutex options:

`_PTHREAD_MUTEX_ERRORCHECK_NP = 2`

Mutex options: double lock returns an error code.

`_PTHREAD_MUTEX_FAST_NP = _PTHREAD_MUTEX_ADAPTIVE_NP`

Mutex options: Fast mutex

`_PTHREAD_MUTEX_NORMAL = _PTHREAD_MUTEX_TIMED_NP`

Mutex options:

`_PTHREAD_MUTEX_RECURSIVE = _PTHREAD_MUTEX_RECURSIVE_NP`

Mutex options:

`_PTHREAD_MUTEX_RECURSIVE_NP = 1`

Mutex options: recursive mutex

`_PTHREAD_MUTEX_TIMED_NP = 0`

Mutex options: ?

## 42.2.2 Types

`cbool = longbool`

Boolean type

`cchar = cint8`

C type: 8-bit signed integer

`cdouble = double`

Double precision real format.

`cfloat = single`

Floating-point real format

`cint = cint32`

C type: integer (natural size)

`cint16 = SmallInt`

C type: 16 bits sized, signed integer.

`cint32 = LongInt`

C type: 32 bits sized, signed integer.

`cint64 = Int64`

C type: 64 bits sized, signed integer.

`cint8 = ShortInt`

C type: 8 bits sized, signed integer.

`clock_t = culong`

Clock ticks type

`clong = LongInt`

C type: long signed integer (double sized)

`clongdouble = extended`

Usually translates to an extended, but is CPU dependent.

`clonglong = cint64`

C type: 64-bit (double long) signed integer.

`cschar = cint8`

Signed character type

`cshort = cint16`

C type: short signed integer (half sized)

`csigned = cint`

`csigned` is an alias for `cint` ([1681](#)).

`csint = cint32`

**Signed integer**

`cslong = LongInt`

The size is CPU dependent.

`cslonglong = cint64`

`cslonglong` is an alias for `clonglong` ([1681](#)).

`csshort = cint16`

**Short signed integer type**

`cuchar = cuint8`

C type: 8-bit unsigned integer

`cuint = cuint32`

C type: unsigned integer (natural size)

`cuint16 = Word`

C type: 16 bits sized, unsigned integer.

`cuint32 = LongWord`

C type: 32 bits sized, unsigned integer.

`cuint64 = qword`

C type: 64 bits sized, unsigned integer.

`cuint8 = Byte`

C type: 8 bits sized, unsigned integer.

`culong = cardinal`

C type: long unsigned integer (double sized)

```
culonglong = cuint64
```

C type: 64-bit (double long) unsigned integer.

```
cunsigned = cuint
```

Alias for #rtl.unixtype.cuint ([1682](#))

```
cushort = cuint16
```

C type: short unsigned integer (half sized)

```
dev_t = cuint64
```

Device descriptor type.

```
gid_t = cuint32
```

Group ID type.

```
ino64_t = cuint64
```

ino64\_t is an inode type capable of containing 64-bit inodes.

```
ino_t = clong
```

Inode type.

```
ipc_pid_t = cushort
```

Process ID

```
kDev_t = cushort
```

Kernel device type

```
mbstate_t = record
  __count : cint;
  __value : mbstate_value_t;
end
```

This type should never be used directly.

```
mbstate_value_t = record
end
```

This type should never be used directly. It is part of the mbstate\_t ([1683](#)) type.

```
mode_t = cuint32
```

Inode mode type.

```
nlink_t = cuint32
```

Number of links type.

```
off64_t = cint64
```

64-bit offset type.

```
off_t = cint
```

Offset type.

```
pcbool = ^cbool
```

Pointer to boolean type cbool ([1680](#))

```
pcchar = ^cchar
```

Pointer to #rtl.UnixType.cchar ([1681](#))

```
pcdouble = ^cdouble
```

Pointer to cdouble ([1681](#)) type.

```
pcfloat = ^cfloat
```

Pointer to cfloat ([1681](#)) type.

```
pcint = ^cint
```

Pointer to cInt ([1681](#)) type.

```
pcint16 = ^cint16
```

Pointer to 16-bit signed integer type

```
pcint32 = ^cint32
```

Pointer to signed 32-bit integer type

```
pcint64 = ^cint64
```

Pointer to signed 64-bit integer type

```
pcint8 = ^cint8
```

Pointer to 8-bits signed integer type

```
pClock = ^clock_t
```

Pointer to TClock (1690) type.

```
pclong = ^clong
```

Pointer to cLong (1681) type.

```
pclongdouble = ^clongdouble
```

Pointer to the long double type clongdouble (1681)

```
pclonglong = ^clonglong
```

Pointer to longlong type.

```
pcschar = ^cschar
```

Pointer to character type cschar (1681).

```
pcshort = ^cshort
```

Pointer to cShort (1682) type.

```
pcsigned = ^csigned
```

Pointer to signed integer type csigned (1682).

```
pcsint = ^csint
```

Pointer to signed integer type csint (1682)

```
pcslong = ^cslong
```

Pointer of the signed long cslong (1682)

```
pcslonglong = ^cslonglong
```

Pointer to Signed longlong type cslonglong (1682)

```
pcsshort = ^csshort
```

Pointer to short signed integer type csshort (1682)

```
pcuchar = ^cuchar
```

Pointer to #rtl.UnixType.cuchar (1682)

```
pcuint = ^cuint
```

Pointer to cUInt (1682) type.

```
pcuint16 = ^cuint16
```

Pointer to 16-bit unsigned integer type

```
pcuint32 = ^cuint32
```

Pointer to unsigned 32-bit integer type

```
pcuint64 = ^cuint64
```

Pointer to unsigned 64-bit integer type

```
pcuint8 = ^cuint8
```

Pointer to 8-bits unsigned integer type

```
pculong = ^culong
```

Pointer to cuLong (1682) type.

```
pculonglong = ^culonglong
```

Unsigned longlong type

```
pcunsigned = ^cunsigned
```

Pointer to #rtl.unixtype.cunsigned (1683)

```
pcushort = ^cushort
```

Pointer to cuShort (1683) type.

```
pDev = ^dev_t
```

Pointer to TDev (1690) type.

```
pGid = ^gid_t
```

Pointer to TGid (1690) type.

```
pid_t = cint
```

Process ID type.

```
pIno = ^ino_t
```

Pointer to TIno (1691) type.

```
pIno64 = ^ino64_t
```

Pointer to ino64\_t (1683)

```
pkDev = ^kDev_t
```



Pointer to TkDev (1691) type.

```
pmbstate_t = ^mbstate_t
```

Pointer to mbstate\_t (1679) type

```
pMode = ^mode_t
```

Pointer to TMode (1691) type.

```
pnLink = ^nlink_t
```

Pointer to TnLink (1691) type.

```
pOff = ^off_t
```

Pointer to TOff (1691) type.

```
pOff64 = ^off64_t
```

Pointer to off64\_t type

```
pPid = ^pid_t
```

Pointer to TPid (1691) type.

```
pSize = ^size_t
```

Pointer to TSize (1691) type.

```
psize_t = pSize
```

Pointer to size\_t (1679) type.

```
pSockLen = ^socklen_t
```

Pointer to TSockLen (1691) type.

```
pSSize = ^ssize_t
```

Pointer to TsSize (1691) type

```
PStatFS = ^TStatfs
```

Pointer to TStatFS (1692) type.

```
pthread_attr_t = record
  __detachstate : cint;
  __schedpolicy : cint;
  __schedparam : sched_param;
  __inheritsched : cint;
```

```

__scope : cint;
__guardsize : size_t;
__stackaddr_set : cint;
__stackaddr : pointer;
__stacksize : size_t;
end

```

`pthread_attr_t` describes the thread attributes. It should be considered an opaque record, the names of the fields can change anytime. Use the appropriate functions to set the thread attributes.

```

pthread_condattr_t = record
__dummy : cint;
end

```

`pthread_condattr_t` describes the attributes of a thread mutex. It should be considered an opaque record, the names of the fields can change anytime.

```

pthread_cond_t = record
__c_lock : _pthread_fastlock;
__c_waiting : pointer;
__padding : Array[0..48-1-sizeof(_pthread_fastlock)-sizeof(pointer)-sizeof(clonglong)];
__align : clonglong;
end

```

`pthread_cond_t` describes a thread conditional variable. It should be considered an opaque record, the names of the fields can change anytime.

```

pthread_key_t = cuint

```

Thread local storage key (opaque)

```

pthread_mutexattr_t = record
__mutexkind : cint;
end

```

`pthread_mutexattr_t` describes the attributes of a thread mutex. It should be considered an opaque record, the names of the fields can change anytime.

```

pthread_mutex_t = record
__m_reserved : cint;
__m_count : cint;
__m_owner : pointer;
__m_kind : cint;
__m_lock : _pthread_fastlock;
end

```

`_pthread_mutex_t` describes a thread mutex. It should be considered an opaque record, the names of the fields can change anytime.

```
pthread_rwlockattr_t = record
  __lockkind : cint;
  __pshared : cint;
end
```

`pthread_rwlockattr_t` describes the attributes of a lock. It should be considered an opaque record, the names of the fields can change anytime.

```
pthread_rwlock_t = record
  __rw_readers : cint;
  __rw_writer : pointer;
  __rw_read_waiting : pointer;
  __rw_write_waiting : pointer;
  __rw_kind : cint;
  __rw_pshared : cint;
end
```

`pthread_rwlock_t` describes a lock. It should be considered an opaque record, the names of the fields can change anytime.

```
pthread_t = culong
```

Thread description record

```
pTime = ^time_t
```

Pointer to TTime (1692) type.

```
ptimespec = ^timespec
```

Pointer to timespec (1690) record.

```
ptimeval = ^timeval
```

Pointer to timeval (1690) record.

```
ptime_t = ^time_t
```

Pointer to time\_t (1691) type.

```
pUId = ^uid_t
```

Pointer to TUid (1692) type.

```
pwchar_t = ^wchar_t
```

Pointer to wchar\_t (1679) type.

```
sched_param = record
  __sched_priority : cint;
end
```

Scheduling parameter description record.

```
sem_t = record
  __sem_lock : _pthread_fastlock;
  __sem_value : cint;
  __sem_waiting : pointer;
end
```

`sem_t` describes a thread semaphore. It should be considered an opaque record, the names of the fields can change anytime.

```
size_t = cuint32
```

Size specification type.

```
socklen_t = cuint32
```

Socket address length type.

```
ssize_t = cint32
```

Small size type.

```
TClock = clock_t
```

Alias for `clock_t` (1681) type.

```
TDev = dev_t
```

Alias for `dev_t` (1683) type.

```
TGid = gid_t
```

Alias for `gid_t` (1683) type.

```
timespec = packed record
  tv_sec : time_t;
  tv_nsec : clong;
end
```

Record specifying time interval.

```
timeval = packed record
  tv_sec : time_t;
  tv_usec : clong;
end
```

Time specification type.

`time_t = clong`

Time span type

`TIno = ino_t`

Alias for `ino_t` (1683) type.

`TIno64 = ino64_t`

Alias for `ino64_t` (1683)

`TIOCtlRequest = cint`

Opaque type used in `FpIOCtl` (158)

`TkDev = kDev_t`

Alias for `kDev_t` (1683) type.

`TMode = mode_t`

Alias for `mode_t` (1684) type.

`TnLink = nlink_t`

Alias for `nlink_t` (1684) type.

`TOff = off_t`

Alias for `off_t` (1684) type.

`TOff64 = off64_t`

Alias for `off64_t` type.

`TPid = pid_t`

Alias for `pid_t` (1686) type.

`TSize = size_t`

Alias for `size_t` (1690) type

`TSockLen = socklen_t`

Alias for `socklen_t` (1690) type.

`TSSize = ssize_t`

Alias for `ssize_t` (1690) type

```

TStatfs = packed record
  fstype : cint;
  bsize : cint;
  blocks : culong;
  bfree : culong;
  bavail : culong;
  files : culong;
  ffree : culong;
  fsid : Array[0..1] of cint;
  namelen : cint;
  frsize : cint;
  spare : Array[0..4] of cint;
end

```

Record describing a file system in the `baseunix.fpstatfs` (1679) call.

```
TTime = time_t
```

Alias for `TTime` (1692) type.

```
TTimeSpec = timespec
```

Alias for `TimeSpec` (1690) type.

```
TTimeVal = timeval
```

Alias for `TimeVal` (1690) record.

```
TUId = uid_t
```

Alias for `uid_t` (1692) type.

```
uid_t = cuint32
```

User ID type

```
wchar_t = cint32
```

Wide character type.

```
wint_t = cint32
```

Wide character size type.

```

_pthread_fastlock = record
  __status : clong;
  __spinlock : cint;
end

```

`_pthread_fastlock` describes a thread mutex. It should be considered an opaque record, the names of the fields can change anytime.

## Chapter 43

# Reference for unit 'unixutil'

### 43.1 Overview

The UnixUtil unit contains some of the routines that were present in the old Linux unit, but which do not really belong in the unix ([1642](#)) or baseunix ([101](#)) units.

Most of the functions described here have cross-platform counterparts in the SysUtils ([1426](#)) unit. It is therefore recommended to use that unit.

### 43.2 Constants, types and variables

#### 43.2.1 Types

`ComStr =`

Command-line string type.

`DirStr =`

Filename directory part string type.

`ExtStr =`

Filename extension part string type.

`NameStr =`

Filename name part string type.

`PathStr =`

Filename full path string type.

#### 43.2.2 Variables

`Tzseconds : LongInt`

Seconds west of GMT

## 43.3 Procedures and functions

### 43.3.1 ArrayStringToPPchar

**Synopsis:** Convert an array of string to an array of null-terminated strings

**Declaration:** `function ArrayStringToPPchar(const S: Array of AnsiString;  
reserveentries: LongInt) : ppchar`

**Visibility:** default

**Description:** `ArrayStringToPPchar` creates an array of null-terminated strings that point to strings which are the same as the strings in the array `S`. The function returns a pointer to this array. The array and the strings it contains must be disposed of after being used, because it they are allocated on the heap.

The `ReserveEntries` parameter tells `ArrayStringToPPchar` to allocate room at the end of the array for another `ReserveEntries` entries.

**Errors:** If not enough memory is available, an error may occur.

See also: `StringToPPChar` ([1699](#))

### 43.3.2 Basename

**Synopsis:** Return basename of a file

**Declaration:** `function Basename(const path: PathStr;const suf: PathStr) : PathStr`

**Visibility:** default

**Description:** Returns the filename part of `Path`, stripping off `Suf` if it exists. The filename part is the whole name if `Path` contains no slash, or the part of `Path` after the last slash. The last character of the result is not a slash, unless the directory is the root directory.

**Errors:** None.

See also: `DirName` ([1695](#))

**Listing:** `./unutilx/ex48.pp`

---

**Program** `Example48;`

*{ Program to demonstrate the BaseName function. }*

**Uses** `Dos, Unix, UnixUtil;`

**Var** `S : String;`

**begin**

`S:=FExpand(Paramstr(0));`

`Writeln ('This program is called : ',Basename(S,' '));`

**end.**

---



### 43.3.3 Dirname

Synopsis: Extract directory part from filename

Declaration: `function Dirname(const path: PathStr) : PathStr`

Visibility: default

Description: Returns the directory part of `Path`. The directory is the part of `Path` before the last slash, or empty if there is no slash. The last character of the result is not a slash, unless the directory is the root directory.

Errors: None.

See also: `BaseName` ([1694](#))

**Listing:** `./unutilx/ex47.pp`

---

**Program** `Example47;`

*{ Program to demonstrate the DirName function. }*

**Uses** `Dos, Unix, UnixUtil;`

**Var** `S : String;`

**begin**

`S:=FExpand(Paramstr(0));`

`WriteLn ('This program is in directory : ', Dirname(S));`

**end.**

---

### 43.3.4 EpochToLocal

Synopsis: Convert epoch time to local time

Declaration: `procedure EpochToLocal(epoch: LongInt; var year: Word; var month: Word; var day: Word; var hour: Word; var minute: Word; var second: Word)`

Visibility: default

Description: Converts the epoch time (=Number of seconds since 00:00:00, January 1, 1970, corrected for your time zone) to local date and time.

This function takes into account the timzone settings of your system.

Errors: None

See also: `LocalToEpoch` ([1698](#))

**Listing:** `./unutilx/ex3.pp`

---

**Program** `Example3;`

*{ Program to demonstrate the EpochToLocal function. }*

**Uses** `BaseUnix, Unix, UnixUtil;`

**Var** `Year, month, day, hour, minute, seconds : Word;`

---

```

begin
  EpochToLocal ( FTime, Year, month, day, hour, minute, seconds );
  Writeln ( 'Current date : ', Day:2, '/', Month:2, '/', Year:4 );
  Writeln ( 'Current time : ', Hour:2, ':', minute:2, ':', seconds:2 );
end.

```

---

### 43.3.5 FNMatch

Synopsis: Check whether filename matches wildcard specification

Declaration: `function FNMatch(const Pattern: String; const Name: String) : Boolean`

Visibility: default

Description: `FNMatch` returns `True` if the filename in `Name` matches the wildcard pattern in `Pattern`, `False` otherwise.

`Pattern` can contain the wildcards `*` (match zero or more arbitrary characters) or `?` (match a single character).

Errors: None.

See also: `#rtl.unix.FSearch` ([1668](#))

**Listing:** `./unutilx/ex69.pp`

---

**Program** Example69;

*{ Program to demonstrate the FNMatch function. }*

**Uses** unixutil;

**Procedure** TestMatch(Pattern, Name : String);

```

begin
  Write ( ' ', Name, ' " ');
  If FNMatch ( Pattern, Name) then
    Write ( ' matches ')
  else
    Write ( ' does not match ');
  Writeln( ' ', Pattern, ' ". ');
end;

begin
  TestMatch( '*', 'FileName' );
  TestMatch( '.*', 'FileName' );
  TestMatch( '*a*', 'FileName' );
  TestMatch( '?ile*', 'FileName' );
  TestMatch( '??', 'FileName' );
  TestMatch( '.?', 'FileName' );
  TestMatch( '?a*', 'FileName' );
  TestMatch( '??*me?', 'FileName' );
end.

```

---

### 43.3.6 FSplit

Synopsis: Split filename into path, name and extension

Declaration: `procedure FSplit(const Path: PathStr; var Dir: DirStr; var Name: NameStr;  
var Ext: ExtStr)`

Visibility: default

Description: `FSplit` splits a full file name into 3 parts : A Path, a Name and an extension (in `ext`). The extension is taken to be all letters after the last dot (.).

Errors: None.

See also: `#rtl.unix.FSearch` ([1668](#))

**Listing:** `./unutilx/ex67.pp`

---

**Program** `Example67;`

`uses UnixUtil;`

`{ Program to demonstrate the FSplit function. }`

`var`

`Path, Name, Ext : string;`

`begin`

`FSplit(ParamStr(1), Path, Name, Ext);`

`WriteLn('Split ', ParamStr(1), ' in:');`

`WriteLn('Path : ', Path);`

`WriteLn('Name : ', Name);`

`WriteLn('Extension : ', Ext);`

`end.`

---

### 43.3.7 GetFS

Synopsis: Return file selector

Declaration: `function GetFS(var T: Text) : LongInt`  
`function GetFS(var F: File) : LongInt`

Visibility: default

Description: `GetFS` returns the file selector that the kernel provided for your file. In principle you don't need this file selector. Only for some calls it is needed, such as the `#rtl.baseunix.fpSelect` ([175](#)) call or so.

Errors: In case the file was not opened, then -1 is returned.

See also: `#rtl.baseunix.fpSelect` ([175](#))

**Listing:** `./unutilx/ex34.pp`

---

**Program** `Example33;`

`{ Program to demonstrate the SelectText function. }`

`Uses Unix;`

---

```

Var tv : TimeVal;

begin
  Writeln ( 'Press the <ENTER> to continue the program.' );
  { Wait until File descriptor 0 (=Input) changes }
  SelectText ( Input, nil );
  { Get rid of <ENTER> in buffer }
  readln;
  Writeln ( 'Press <ENTER> key in less than 2 seconds...' );
  tv.tv_sec:=2;
  tv.tv_sec:=0;
  if SelectText ( Input, @tv) > 0 then
    Writeln ( 'Thank you !' )
  else
    Writeln ( 'Too late !' );
end.

```

---

### 43.3.8 GregorianToJulian

Synopsis: Converts a gregorian date to a julian date

Declaration: `function GregorianToJulian(Year: LongInt; Month: LongInt; Day: LongInt)  
: LongInt`

Visibility: default

Description: `GregorianToJulian` takes a gregorian date and converts it to a Julian day.

Errors: None.

See also: `JulianToGregorian` ([1698](#))

### 43.3.9 JulianToGregorian

Synopsis: Converts a julian date to a gregorian date

Declaration: `procedure JulianToGregorian(JulianDN: LongInt; var Year: Word;  
var Month: Word; var Day: Word)`

Visibility: default

Description: `JulianToGregorian` takes a julian day and converts it to a gregorian date. (Start of the Julian Date count is from 0 at 12 noon 1 JAN -4712 (4713 BC),)

Errors: None.

See also: `GregorianToJulian` ([1698](#))

### 43.3.10 LocalToEpoch

Synopsis: Convert local time to epoch (unix) time

Declaration: `function LocalToEpoch(year: Word; month: Word; day: Word; hour: Word;  
minute: Word; second: Word) : LongInt`

Visibility: default

Description: Converts the Local time to epoch time (=Number of seconds since 00:00:00 , January 1, 1970 ).

Errors: None

See also: EpochToLocal ([1695](#))

**Listing:** ./unutilx/ex4.pp

---

**Program** Example4;

*{ Program to demonstrate the LocalToEpoch function. }*

**Uses** UnixUtil;

**Var** year , month , day , hour , minute , second : Word;

**begin**

```

Write ( 'Year      : ' ); readln (Year);
Write ( 'Month     : ' ); readln (Month);
Write ( 'Day       : ' ); readln (Day);
Write ( 'Hour      : ' ); readln (Hour);
Write ( 'Minute    : ' ); readln (Minute);
Write ( 'Seonds    : ' ); readln (Second);
Write ( 'This is   : ' );
Write ( LocalToEpoch (year , month , day , hour , minute , second ) );
Writeln ( ' seconds past 00:00 1/1/1980 ' );

```

**end.**

---

### 43.3.11 StringToPPChar

Synopsis: Split string in list of null-terminated strings

**Declaration:** function StringToPPChar (S: PChar; ReserveEntries: Integer) : ppchar  
function StringToPPChar (var S: String; ReserveEntries: Integer) : ppchar  
function StringToPPChar (var S: AnsiString; ReserveEntries: Integer)  
: ppchar

Visibility: default

**Description:** StringToPPChar splits the string S in words, replacing any whitespace with zero characters. It returns a pointer to an array of pchars that point to the first letters of the words in S. This array is terminated by a Nil pointer.

The function does *not* add a zero character to the end of the string unless it ends on whitespace.

The function reserves memory on the heap to store the array of PChar; The caller is responsible for freeing this memory.

This function can be called to create arguments for the various Exec calls.

Errors: None.

See also: ArrayStringToPPchar ([1694](#)), #rtl.baseunix.FpExecve ([148](#))

**Listing:** ./unutilx/ex70.pp

---

**Program** Example70;

*{ Program to demonstrate the StringToPPchar function. }*

---

**Uses** UnixUtil;

**Var** S : **String**;  
    P : PPChar;  
    I : longint;

**begin**  
    *// remark whitespace at end.*  
    S:= 'This is a string with words. ';  
    P:=StringToPPChar(S,0);  
    I:=0;  
    **While** P[I]<>Nil **do**  
        **begin**  
            **Writeln**( 'Word ',i, ' : ',P[ i ] );  
            **Inc**( I );  
        **end**;  
    **FreeMem**(P, i\***SizeOf**(Pchar));  
**end.**

---

## Chapter 44

# Reference for unit 'video'

### 44.1 Overview

The `Video` unit implements a screen access layer which is system independent. It can be used to write on the screen in a system-independent way, which should be optimal on all platforms for which the unit is implemented.

The working of the `Video` is simple: After calling `InitVideo` (1716), the array `VideoBuf` contains a representation of the video screen of size `ScreenWidth*ScreenHeight`, going from left to right and top to bottom when walking the array elements: `VideoBuf[0]` contains the character and color code of the top-left character on the screen. `VideoBuf[ScreenWidth]` contains the data for the character in the first column of the second row on the screen, and so on.

To write to the 'screen', the text to be written should be written to the `VideoBuf` array. Calling `UpdateScreen` (1720) will then cp the text to the screen in the most optimal way. (an example can be found further on).

The color attribute is a combination of the foreground and background color, plus the blink bit. The bits describe the various color combinations:

**bits 0-3** The foreground color. Can be set using all color constants.

**bits 4-6** The background color. Can be set using a subset of the color constants.

**bit 7** The blinking bit. If this bit is set, the character will appear blinking.

Each possible color has a constant associated with it, see the constants section for a list of constants.

The foreground and background color can be combined to a color attribute with the following code:

```
Attr:=ForeGroundColor + (BackGroundColor shl 4);
```

The color attribute can be logically or-ed with the blink attribute to produce a blinking character:

```
Attr:=Attr or blink;
```

But not all drivers may support this.

The contents of the `VideoBuf` array may be modified: This is 'writing' to the screen. As soon as everything that needs to be written in the array is in the `VideoBuf` array, calling `UpdateScreen` will copy the contents of the array screen to the screen, in a manner that is as efficient as possible.

The updating of the screen can be prohibited to optimize performance; To this end, the `LockScreenUpdate` (1717) function can be used: This will increment an internal counter. As long as the counter differs from zero, calling `UpdateScreen` (1720) will not do anything. The counter can be lowered with `UnlockScreenUpdate` (1719). When it reaches zero, the next call to `UpdateScreen` (1720) will actually update the screen. This is useful when having nested procedures that do a lot of screen writing.

The video unit also presents an interface for custom screen drivers, thus it is possible to override the default screen driver with a custom screen driver, see the `SetVideoDriver` (1719) call. The current video driver can be retrieved using the `GetVideoDriver` (1714) call.

**Remark:** The video unit should *not* be used together with the CRT unit. Doing so will result in very strange behaviour, possibly program crashes.

## 44.2 Examples utility unit

The examples in this section make use of the unit `vidutil`, which contains the `TextOut` function. This function writes a text to the screen at a given location. It looks as follows:

## 44.3 Writing a custom video driver

Writing a custom video driver is not difficult, and generally means implementing a couple of functions, which should be registered with the `SetVideoDriver` (1719) function. The various functions that can be implemented are located in the `TVideoDriver` (1708) record:

```
TVideoDriver = Record
  InitDriver      : Procedure;
  DoneDriver      : Procedure;
  UpdateScreen    : Procedure (Force : Boolean);
  ClearScreen     : Procedure;
  SetVideoMode    : Function (Const Mode : TVideoMode) : Boolean;
  GetVideoModeCount : Function : Word;
  GetVideoModeData : Function (Index : Word; Var Data : TVideoMode) : Boolean;
  SetCursorPos    : procedure (NewCursorX, NewCursorY: Word);
  GetCursorType   : function : Word;
  SetCursorType   : procedure (NewType: Word);
  GetCapabilities : Function : Word;
end;
```

Not all of these functions must be implemented. In fact, the only absolutely necessary function to write a functioning driver is the `UpdateScreen` function. The general calls in the `Video` unit will check which functionality is implemented by the driver.

The functionality of these calls is the same as the functionality of the calls in the video unit, so the expected behaviour can be found in the previous section. Some of the calls, however, need some additional remarks.

**InitDriver** Called by `InitVideo`, this function should initialize any data structures needed for the functionality of the driver, maybe do some screen initializations. The function is guaranteed to be called only once; It can only be called again after a call to `DoneVideo`. The variables `ScreenWidth` and `ScreenHeight` should be initialized correctly after a call to this function, as the `InitVideo` call will initialize the `VideoBuf` and `OldVideoBuf` arrays based on their values.



**DoneDriver** This should clean up any structures that have been initialized in the `InitDriver` function. It should possibly also restore the screen as it was before the driver was initialized. The `VideoBuf` and `OldVideoBuf` arrays will be disposed of by the general `DoneVideo` call.

**UpdateScreen** This is the only required function of the driver. It should update the screen based on the `VideoBuf` array's contents. It can optimize this process by comparing the values with values in the `OldVideoBuf` array. After updating the screen, the `UpdateScreen` procedure should update the `OldVideoBuf` by itself. If the `Force` parameter is `True`, the whole screen should be updated, not just the changed values.

**ClearScreen** If there is a faster way to clear the screen than to write spaces in all character cells, then it can be implemented here. If the driver does not implement this function, then the general routines will write spaces in all video cells, and will call `UpdateScreen(True)`.

**SetVideoMode** Should set the desired video mode, if available. It should return `True` if the mode was set, `False` if not.

**GetVideoModeCount** Should return the number of supported video modes. If no modes are supported, this function should not be implemented; the general routines will return 1. (for the current mode)

**GetVideoModeData** Should return the data for the `Index`-th mode; `Index` is zero based. The function should return true if the data was returned correctly, false if `Index` contains an invalid index. If this is not implemented, then the general routine will return the current video mode when `Index` equals 0.

**GetCapabilities** If this function is not implemented, zero (i.e. no capabilities) will be returned by the general function.

The following unit shows how to override a video driver, with a driver that writes debug information to a file. The unit can be used in any of the demonstration programs, by simply including it in the `uses` clause. Setting `DetailedVideoLogging` to `True` will create a more detailed log (but will also slow down functioning)

## 44.4 Constants, types and variables

### 44.4.1 Constants

`Black = 0`

Black color attribute

`Blink = 128`

Blink attribute

`Blue = 1`

Blue color attribute

`Brown = 6`

Brown color attribute

`cpBlink = $0002`

**Video driver supports blink attribute**

`cpChangeCursor = $0020`

**Video driver supports changing cursor shape.**

`cpChangeFont = $0008`

**Video driver supports changing screen font.**

`cpChangeMode = $0010`

**Video driver supports changing mode**

`cpColor = $0004`

**Video driver supports color**

`cpUnderLine = $0001`

**Video driver supports underline attribute**

`crBlock = 2`

**Block cursor**

`crHalfBlock = 3`

**Half block cursor**

`crHidden = 0`

**Hide cursor**

`crUnderLine = 1`

**Underline cursor**

`Cyan = 3`

**Cyan color attribute**

`DarkGray = 8`

**Dark gray color attribute**

`errOk = 0`

**No error**

```
ErrorCode : LongInt = ErrOK
```

Error code returned by the last operation.

```
ErrorHandler : TErrorHandler = @DefaultErrorHandler
```

The `ErrorHandler` variable can be set to a custom-error handling function. It is set by default to the `DefaultErrorHandler` (1711) function.

```
ErrorInfo : Pointer = nil
```

Pointer to extended error information.

```
errVioBase = 1000
```

Base value for video errors

```
errVioInit = errVioBase+1
```

Video driver initialization error.

```
errVioNoSuchMode = errVioBase+3
```

Invalid video mode

```
errVioNotSupported = errVioBase+2
```

Unsupported video function

```
FVMaxWidth = 240
```

Maximum screen buffer width.

```
Green = 2
```

Green color attribute

```
iso_codepages = [iso01,iso02,iso03,iso04,iso05,iso06,iso07,iso08,iso09,iso10,iso13,i
```

`iso_codepages` is a set containing all code pages that use an ISO encoding.

```
LightBlue = 9
```

Light Blue color attribute

```
LightCyan = 11
```

Light cyan color attribute

```
LightGray = 7
```

Light gray color attribute

```
LightGreen = 10
```

Light green color attribute

```
LightMagenta = 13
```

Light magenta color attribute

```
LightRed = 12
```

Light red color attribute

```
LowAscii = true
```

On some systems, the low 32 values of the DOS code page are necessary for the ASCII control codes and cannot be displayed by programs. If LowAscii is true, you can use the low 32 ASCII values. If it is false, you must avoid using them.

LowAscii can be implemented either through a constant, variable or property. You should under no circumstances assume that you can write to LowAscii, or take its address.

```
Magenta = 5
```

Magenta color attribute

```
NoExtendedFrame = false
```

The VT100 character set only has line drawing characters consisting of a single line. If this value is true, the line drawing characters with two lines will be automatically converted to single lines.

NoExtendedFrame can be implemented either through a constant, variable or property. You should under no circumstances assume that you can write to NoExtendedFrame, or take its address.

```
Red = 4
```

Red color attribute

```
ScreenHeight : Word = 0
```

Current screen height

```
ScreenWidth : Word = 0
```

Current screen Width

```
vga_codepages = [cp437, cp850, cp852, cp866]
```

vga\_codepages is a set containing all code pages that can be considered a normal vga font (as in use on early VGA cards) Note that KOI8-R has line drawing characters in wrong place.

`vioOK = 0`

No errors occurred

`White = 15`

White color attribute

`Yellow = 14`

Yellow color attribute

### 44.4.2 Types

`PVideoBuf = ^TVideoBuf`

Pointer type to `TVideoBuf` ([1707](#))

`PVideoCell = ^TVideoCell`

Pointer type to `TVideoCell` ([1708](#))

`PVideoMode = ^TVideoMode`

Pointer to `TVideoMode` ([1709](#)) record.

`Tencoding = (cp437, cp850, cp852, cp866, koi8r, iso01, iso02, iso03, iso04, iso05, iso06, iso07, iso08, iso09, iso10, iso13, iso14, iso15, utf8)`

This type is available under Unix-like operating systems only.

`TErrorHandler = function(Code: LongInt; Info: Pointer)  
: TErrorHandlerReturnValue`

The `TErrorHandler` function is used to register an own error handling function. It should be used when installing a custom error handling function, and must return one of the above values.

`Code` should contain the error code for the error condition, and the `Info` parameter may contain any data type specific to the error code passed to the function.

`TErrorHandlerReturnValue = (errRetry, errAbort, errContinue)`

Type used to report and respond to error conditions

`TVideoBuf = Array[0..32759] of TVideoCell`

The `TVideoBuf` type represents the screen.

`TVideoCell = Word`

Table 44.1: Enumeration values for type Tencoding

Value	Explanation
cp437	Codepage 437
cp850	Codepage 850
cp852	Codepage 852
cp866	Codepage 866
iso01	ISO 8859-1
iso02	ISO 8859-2
iso03	ISO 8859-3
iso04	ISO 8859-4
iso05	ISO 8859-5
iso06	ISO 8859-6
iso07	ISO 8859-7
iso08	ISO 8859-8
iso09	ISO 8859-9
iso10	ISO 8859-10
iso13	ISO 8859-13
iso14	ISO 8859-14
iso15	ISO 8859-15
koi8r	KOI8-R codepage
utf8	UTF-8 encoding

Table 44.2: Enumeration values for type TErrorHandlerReturnValue

Value	Explanation
errAbort	abort and return error code
errContinue	abort without returning an errorcode.
errRetry	retry the operation

TVideoCell describes one character on the screen. One of the bytes contains the color attribute with which the character is drawn on the screen, and the other byte contains the ASCII code of the character to be drawn. The exact position of the different bytes in the record is operating system specific. On most little-endian systems, the high byte represents the color attribute, while the low-byte represents the ASCII code of the character to be drawn.

```

TVideoDriver = record
  InitDriver : procedure;
  DoneDriver : procedure;
  UpdateScreen : procedure(Force: Boolean);
  ClearScreen : procedure;
  SetVideoMode : function(const Mode: TVideoMode) : Boolean;
  GetVideoModeCount : function : Word;
  GetVideoModeData : function(Index: Word;var Data: TVideoMode) : Boolean;
  SetCursorPos : procedure(NewCursorX: Word;NewCursorY: Word);
  GetCursorType : function : Word;
  SetCursorType : procedure(NewType: Word);
  GetCapabilities : function : Word;
end

```

`TVideoDriver` record can be used to install a custom video driver, with the `SetVideoDriver` (1719) call.

An explanation of all fields can be found there.

```
TVideoMode = record
  Col : Word;
  Row : Word;
  Color : Boolean;
end
```

The `TVideoMode` record describes a videomode. Its fields are self-explaining: `Col`, `Row` describe the number of columns and rows on the screen for this mode. `Color` is `True` if this mode supports colors, or `False` if not.

```
TVideoModeSelector = function(const VideoMode: TVideoMode;
                               Params: LongInt) : Boolean
```

Video mode selection callback prototype.

### 44.4.3 Variables

```
CursorLines : Byte
```

`CursorLines` is a bitmask which determines which cursor lines are visible and which are not. Each set bit corresponds to a cursorline being shown.

This variable is not supported on all platforms, so it should be used sparingly.

```
CursorX : Word
```

Current horizontal position in the screen where items will be written.

```
CursorY : Word
```

Current vertical position in the screen where items will be written.

```
external_codepage : Tencoding
```

This variable is for internal use only and should not be used.

```
internal_codepage : Tencoding
```

This variable is for internal use only and should not be used.

```
OldVideoBuf : PVideoBuf
```

The `OldVideoBuf` contains the state of the video screen after the last screen update. The `UpdateScreen` (1720) function uses this array to decide which characters on screen should be updated, and which not.

Note that the `OldVideoBuf` array may be ignored by some drivers, so it should not be used. The Array is in the interface section of the video unit mainly so drivers that need it can make use of it.

`ScreenColor : Boolean`

`ScreenColor` indicates whether the current screen supports colors.

`VideoBuf : PVideoBuf`

`VideoBuf` forms the heart of the `Video` unit: This variable represents the physical screen. Writing to this array and calling `UpdateScreen` (1720) will write the actual characters to the screen.

`VideoBufSize : LongInt`

Current size of the video buffer pointed to by `VideoBuf` (1710)

## 44.5 Procedures and functions

### 44.5.1 ClearScreen

Synopsis: Clear the video screen.

Declaration: `procedure ClearScreen`

Visibility: default

Description: `ClearScreen` clears the entire screen, and calls `UpdateScreen` (1720) after that. This is done by writing spaces to all character cells of the video buffer in the default color (lightgray on black, color attribute `\$07`).

Errors: None.

See also: `InitVideo` (1716), `UpdateScreen` (1720)

**Listing:** `./videoex/ex3.pp`

---

```

program testvideo ;

uses video , keyboard , vidutil ;

Var
  i : longint ;
  k : TKeyEvent ;

begin
  InitVideo ;
  InitKeyboard ;
  For i:=1 to 10 do
    TextOut(i,i, 'Press any key to clear screen');
    UpdateScreen(false);
    K:=GetKeyEvent;
    ClearScreen;
    TextOut(1,1, 'Cleared screen. Press any key to end');
    UpdateScreen(true);
    K:=GetKeyEvent;
    DoneKeyBoard;
    DoneVideo;
end.

```

---



### 44.5.2 DefaultErrorHandler

Synopsis: Default error handling routine.

Declaration: `function DefaultErrorHandler (AErrorCode: LongInt; AErrorInfo: Pointer)  
: TErrorHandlerReturnValue`

Visibility: default

Description: `DefaultErrorHandler` is the default error handler used by the video driver. It simply sets the error code `AErrorCode` and `AErrorInfo` in the global variables `ErrorCode` and `ErrorInfo` and returns `errContinue`.

Errors: None.

### 44.5.3 DoneVideo

Synopsis: Disable video driver.

Declaration: `procedure DoneVideo`

Visibility: default

Description: `DoneVideo` disables the Video driver if the video driver is active. If the videodriver was already disabled or not yet initialized, it does nothing. Disabling the driver means it will clean up any allocated resources, possibly restore the screen in the state it was before `InitVideo` was called. Particularly, the `VideoBuf` and `OldVideoBuf` arrays are no longer valid after a call to `DoneVideo`.

The `DoneVideo` should always be called if `InitVideo` was called. Failing to do so may leave the screen in an unusable state after the program exits.

For an example, see most other functions.

Errors: Normally none. If the driver reports an error, this is done through the `ErrorCode` variable.

See also: `InitVideo` ([1716](#))

### 44.5.4 GetCapabilities

Synopsis: Get current driver capabilities.

Declaration: `function GetCapabilities : Word`

Visibility: default

Description: `GetCapabilities` returns the capabilities of the current driver. It is an or-ed combination of the following constants:

**cpUnderLine** Video driver supports underline attribute

**cpBlink** Video driver supports blink attribute

**cpColor** Video driver supports color

**cpChangeFont** Video driver supports changing screen font.

**cpChangeMode** Video driver supports changing mode

**cpChangeCursor** Video driver supports changing cursor shape.

Note that the video driver should not yet be initialized to use this function. It is a property of the driver.

Errors: None.

See also: [GetCursorType \(1712\)](#), [GetVideoDriver \(1714\)](#)

**Listing:** ./videoex/ex4.pp

---

**Program** Example4;

*{ Program to demonstrate the GetCapabilities function. }*

**Uses** video;

**Var**

W: Word;

**Procedure** TestCap(Cap: Word; Msg : **String**);

**begin**

**Write**(Msg, ' : ');

**If** (W **and** Cap=Cap) **then**

**Writeln**( 'Yes' )

**else**

**Writeln**( 'No' );

**end**;

**begin**

W:= GetCapabilities;

**Writeln**( 'Video driver supports following functionality' );

    TestCap(cpUnderLine, 'Underlined characters');

    TestCap(cpBlink, 'Blinking characters');

    TestCap(cpColor, 'Color characters');

    TestCap(cpChangeFont, 'Changing font');

    TestCap(cpChangeMode, 'Changing video mode');

    TestCap(cpChangeCursor, 'Changing cursor shape');

**end**.

---

### 44.5.5 GetCursorType

Synopsis: Get screen cursor type

Declaration: `function GetCursorType : Word`

Visibility: default

Description: `GetCursorType` returns the current cursor type. It is one of the following values:

**crHidden**Hide cursor

**crUnderLine**Underline cursor

**crBlock**Block cursor

**crHalfBlock**Half block cursor

Note that not all drivers support all types of cursors.

Errors: None.

See also: [SetCursorType \(1718\)](#), [GetCapabilities \(1711\)](#)

**Listing:** ./videoex/ex5.pp

**Program** Example5;

*{ Program to demonstrate the GetCursorType function. }*

**Uses** video, keyboard, vidutil;

**Const**

CursorTypes : **Array**[crHidden..crHalfBlock] **of string** =  
('Hidden', 'UnderLine', 'Block', 'HalfBlock');

**begin**

InitVideo;  
InitKeyboard;  
TextOut(1,1, 'Cursor type: '+CursorTypes[GetCursorType]);  
TextOut(1,2, 'Press any key to exit.');

UpdateScreen(False);  
GetKeyEvent;  
DoneKeyboard;  
DoneVideo;

**end.**

#### 44.5.6 GetLockScreenCount

Synopsis: Get the screen lock update count.

Declaration: function GetLockScreenCount : Integer

Visibility: default

Description: GetLockScreenCount returns the current lock level. When the lock level is zero, a call to UpdateScreen (1720) will actually update the screen.

Errors: None.

See also: LockScreenUpdate (1717), UnlockScreenUpdate (1719), UpdateScreen (1720)

**Listing:** ./videoex/ex6.pp

**Program** Example6;

*{ Program to demonstrate the GetLockScreenCount function. }*

**Uses** video, keyboard, vidutil;

**Var**

I : Longint;  
S : **String**;

**begin**

InitVideo;  
InitKeyboard;  
TextOut(1,1, 'Press key till new text appears.');

UpdateScreen(False);

**Randomize**;  
**For** I:=0 **to** Random(10)+1 **do**  
LockScreenUpdate;

---

```

I:=0;
While GetLockScreenCount<>0 do
begin
  Inc(I);
  Str(I,S);
  UnlockScreenUpdate;
  GetKeyEvent;
  TextOut(1,1,'UnLockScreenUpdate had to be called '+S+' times');
  UpdateScreen(False);
end;
TextOut(1,2,'Press any key to end. ');
UpdateScreen(False);
GetKeyEvent;
DoneKeyboard;
DoneVideo;
end.

```

---

### 44.5.7 GetVideoDriver

Synopsis: Get a copy of the current video driver.

Declaration: `procedure GetVideoDriver(var Driver: TVideoDriver)`

Visibility: default

Description: `GetVideoDriver` returns the currently active video driver record in `Driver`. It can be used to clone the current video driver, or to override certain parts of it using the `SetVideoDriver` (1719) call.

Errors: None.

See also: `SetVideoDriver` (1719)

### 44.5.8 GetVideoMode

Synopsis: Return current video mode

Declaration: `procedure GetVideoMode(var Mode: TVideoMode)`

Visibility: default

Description: `GetVideoMode` returns the settings of the currently active video mode. The `row`, `col` fields indicate the dimensions of the current video mode, and `Color` is true if the current video supports colors.

See also: `SetVideoMode` (1719), `GetVideoModeData` (1716)

**Listing:** `./videoex/ex7.pp`

---

**Program** Example7;

*{ Program to demonstrate the GetVideoMode function. }*

**Uses** video, keyboard, vidutil;

**Var**

  M : TVideoMode;  
  S : **String**;

---

```

begin
  InitVideo;
  InitKeyboard;
  GetVideoMode(M);
  if M.Color then
    TextOut(1,1,'Current mode has color')
  else
    TextOut(1,1,'Current mode does not have color');
  Str(M.Row,S);
  TextOut(1,2,'Number of rows    : '+S);
  Str(M.Col,S);
  TextOut(1,3,'Number of columns : '+S);
  Textout(1,4,'Press any key to exit. ');
  UpdateScreen(False);
  GetKeyEvent;
  DoneKeyboard;
  DoneVideo;
end.

```

---

### 44.5.9 GetVideoModeCount

Synopsis: Get the number of video modes supported by the driver.

Declaration: `function GetVideoModeCount : Word`

Visibility: default

Description: `GetVideoModeCount` returns the number of video modes that the current driver supports. If the driver does not support switching of modes, then 1 is returned.

This function can be used in conjunction with the `GetVideoModeData` (1716) function to retrieve data for the supported video modes.

Errors: None.

See also: `GetVideoModeData` (1716), `GetVideoMode` (1714)

**Listing:** `./videoex/ex8.pp`

---

**Program** Example8;

*{ Program to demonstrate the GetVideoModeCount function. }*

**Uses** video, keyboard, vidutil;

**Procedure** DumpMode (M : TVideoMode; Index : Integer);

**Var**

S : String;

**begin**

```

  Str(Index:2,S);
  inc(Index);
  TextOut(1,Index,'Data for mode '+S+' : ');
  if M.Color then
    TextOut(19,Index,'    color,')
  else

```

---

```

    TextOut(19,Index,'No color,');
    Str(M.Row:3,S);
    TextOut(28,Index,S+' rows');
    Str(M.Col:3,S);
    TextOut(36,Index,S+' columns');
end;

Var
    i,Count : Integer;
    m : TVideoMode;

begin
    InitVideo;
    InitKeyboard;
    Count:=GetVideoModeCount;
    For I:=1 to Count do
        begin
            GetVideoModeData(I-1,M);
            DumpMode(M,I-1);
        end;
    TextOut(1,Count+1,'Press any key to exit');
    UpdateScreen(False);
    GetKeyEvent;
    DoneKeyboard;
    DoneVideo;
end.

```

---

#### 44.5.10 GetVideoModeData

Synopsis: Get the specifications for a video mode

Declaration: `function GetVideoModeData(Index: Word;var Data: TVideoMode) : Boolean`

Visibility: default

Description: `GetVideoModeData` returns the characteristics of the `Index`-th video mode in `Data`. `Index` is zero based, and has a maximum value of `GetVideoModeCount-1`. If the current driver does not support setting of modes (`GetVideoModeCount=1`) and `Index` is zero, the current mode is returned.

The function returns `True` if the mode data was retrieved successfully, `False` otherwise.

For an example, see `GetVideoModeCount` ([1715](#)).

Errors: In case `Index` has a wrong value, `False` is returned.

See also: `GetVideoModeCount` ([1715](#)), `SetVideoMode` ([1719](#)), `GetVideoMode` ([1714](#))

#### 44.5.11 InitVideo

Synopsis: Initialize video driver.

Declaration: `procedure InitVideo`

Visibility: default

Description: `InitVideo` initializes the video subsystem. If the video system was already initialized, it does nothing. After the driver has been initialized, the `VideoBuf` and `OldVideoBuf` pointers are

initialized, based on the `ScreenWidth` and `ScreenHeight` variables. When this is done, the screen is cleared.

For an example, see most other functions.

Errors: if the driver fails to initialize, the `ErrorCode` variable is set.

See also: `DoneVideo` (1711)

### 44.5.12 LockScreenUpdate

Synopsis: Prevent further screen updates.

Declaration: `procedure LockScreenUpdate`

Visibility: `default`

Description: `LockScreenUpdate` increments the screen update lock count with one. As long as the screen update lock count is not zero, `UpdateScreen` (1720) will not actually update the screen.

This function can be used to optimize screen updating: If a lot of writing on the screen needs to be done (by possibly unknown functions), calling `LockScreenUpdate` before the drawing, and `UnlockScreenUpdate` (1719) after the drawing, followed by a `UpdateScreen` (1720) call, all writing will be shown on screen at once.

For an example, see `GetLockScreenCount` (1713).

Errors: None.

See also: `UpdateScreen` (1720), `UnlockScreenUpdate` (1719), `GetLockScreenCount` (1713)

### 44.5.13 SetCursorPos

Synopsis: Set write cursor position.

Declaration: `procedure SetCursorPos (NewCursorX: Word; NewCursorY: Word)`

Visibility: `default`

Description: `SetCursorPos` positions the cursor on the given position: Column `NewCursorX` and row `NewCursorY`. The origin of the screen is the upper left corner, and has coordinates `(0, 0)`.

The current position is stored in the `CursorX` and `CursorY` variables.

Errors: None.

See also: `SetCursorType` (1718)

**Listing:** `./videoex/ex2.pp`

---

```
program example2;
```

```
uses video , keyboard ;
```

```
Var
```

```
  P,PP,D : Integer ;
  K: TKeyEvent;
```

```
  Procedure PutSquare (P : INteger ; C : Char);
```

```
  begin
```

---

```

    VideoBuf^[P]:=Ord(C)+($07 shl 8);
    VideoBuf^[P+ScreenWidth]:=Ord(c)+($07 shl 8);
    VideoBuf^[P+1]:=Ord(c)+($07 shl 8);
    VideoBuf^[P+ScreenWidth+1]:=Ord(c)+($07 shl 8);
end;

begin
    InitVideo;
    InitKeyBoard;
    P:=0;
    PP:=-1;
    Repeat
        If PP<>-1 then
            PutSquare(PP, ' ');
            PutSquare(P, '#');
            SetCursorPos(P Mod ScreenWidth, P div ScreenWidth);
            UpdateScreen(False);
            PP:=P;
        Repeat
            D:=0;
            K:=TranslateKeyEvent(GetKeyEvent);
            Case GetKeyEventCode(K) of
                kbdLeft : If (P Mod ScreenWidth)<>0 then
                    D:=-1;
                kbdUp : If P>=ScreenWidth then
                    D:=-ScreenWidth;
                kbdRight : If ((P+2) Mod ScreenWidth)<>0 then
                    D:=1;
                kbdDown : if (P<(VideoBufSize div 2)-(ScreenWidth*2)) then
                    D:=ScreenWidth;
            end;
        Until (D<>0) or (GetKeyEventChar(K)='q');
        P:=P+D;
    until GetKeyEventChar(K)='q';
    DoneKeyBoard;
    DoneVideo;
end.

```

---

#### 44.5.14 SetCursorType

Synopsis: Set cursor type

Declaration: `procedure SetCursorType(NewType: Word)`

Visibility: default

Description: `SetCursorType` sets the cursor to the type specified in `NewType`.

**crHidden** Hide cursor

**crUnderLine** Underline cursor

**crBlock** Block cursor

**crHalfBlock** Half block cursor

Errors: None.

See also: `SetCursorPos` ([1717](#))



### 44.5.15 SetVideoDriver

Synopsis: Install a new video driver.

Declaration: `function SetVideoDriver(const Driver: TVideoDriver) : Boolean`

Visibility: default

Description: `SetVideoDriver` sets the videodriver to be used to `Driver`. If the current videodriver is initialized (after a call to `InitVideo`) then it does nothing and returns `False`.

A new driver can only be installed if the previous driver was not yet activated (i.e. before a call to `InitVideo` (1716)) or after it was deactivated (i.e after a call to `DoneVideo`).

For more information about installing a videodriver, see `viddriver` (1702).

For an example, see the section on writing a custom video driver.

Errors: If the current driver is initialized, then `False` is returned.

See also: `viddriver` (1702)

### 44.5.16 SetVideoMode

Synopsis: Set current video mode.

Declaration: `function SetVideoMode(const Mode: TVideoMode) : Boolean`

Visibility: default

Description: `SetVideoMode` sets the video mode to the mode specified in `Mode`:

If the call was succesful, then the screen will have `Col` columns and `Row` rows, and will be displaying in color if `Color` is `True`.

The function returns `True` if the mode was set succesfully, `False` otherwise.

Note that the video mode may not always be set. E.g. a console on Linux or a telnet session cannot always set the mode. It is important to check the error value returned by this function if it was not succesful.

The mode can be set when the video driver has not yet been initialized (i.e. before `InitVideo` (1716) was called) In that case, the video mode will be stored, and after the driver was initialized, an attempt will be made to set the requested mode. Changing the video driver before the call to `InitVideo` will clear the stored video mode.

To know which modes are valid, use the `GetVideoModeCount` (1715) and `GetVideoModeData` (1716) functions. To retrieve the current video mode, use the `GetVideoMode` (1714) procedure.

Errors: If the specified mode cannot be set, then `errVioNoSuchMode` may be set in `ErrorCode`

See also: `GetVideoModeCount` (1715), `GetVideoModeData` (1716), `GetVideoMode` (1714)

### 44.5.17 UnlockScreenUpdate

Synopsis: Unlock screen update.

Declaration: `procedure UnlockScreenUpdate`

Visibility: default

**Description:** `UnlockScreenUpdate` decrements the screen update lock count with one if it is larger than zero. When the lock count reaches zero, the `UpdateScreen` (1720) will actually update the screen. No screen update will be performed as long as the screen update lock count is nonzero. This mechanism can be used to increase screen performance in case a lot of writing is done.

It is important to make sure that each call to `LockScreenUpdate` (1717) is matched by exactly one call to `UnlockScreenUpdate`.

For an example, see `GetLockScreenCount` (1713).

Errors: None.

See also: `LockScreenUpdate` (1717), `GetLockScreenCount` (1713), `UpdateScreen` (1720)

### 44.5.18 UpdateScreen

**Synopsis:** Update physical screen with internal screen image.

**Declaration:** `procedure UpdateScreen(Force: Boolean)`

**Visibility:** default

**Description:** `UpdateScreen` synchronizes the actual screen with the contents of the `VideoBuf` internal buffer.

The parameter `Force` specifies whether the whole screen has to be redrawn (`Force=True`) or only parts that have changed since the last update of the screen.

The `Video` unit keeps an internal copy of the screen as it last wrote it to the screen (in the `OldVideoBuf` array). The current contents of `VideoBuf` are examined to see what locations on the screen need to be updated. On slow terminals (e.g. a linux telnet session) this mechanism can speed up the screen redraw considerably.

On platforms where mouse cursor visibility is not guaranteed to be preserved during screen updates this routine has to restore the mouse cursor after the update (usually by calling `HideMouse` from unit `Mouse` before the real update and `ShowMouse` afterwards).

For an example, see most other functions.

Errors: None.

See also: `ClearScreen` (1710)

# Chapter 45

## Reference for unit 'wincrt'

### 45.1 Overview

The `wincrt` unit provides some auxiliary routines for use with the `graph` (617) unit, namely keyboard support. It has no connection with the `crt` (409) unit, nor with the Turbo-Pascal for Windows `WinCrt` unit. As such, it should not be used by end users. Refer to the `crt` (409) unit instead.

### 45.2 Constants, types and variables

#### 45.2.1 Variables

`directvideo` : `Boolean`

On windows, this variable is ignored.

`lastmode` : `Word`

Is supposed to contain the last used video mode, but is actually unused.

### 45.3 Procedures and functions

#### 45.3.1 `delay`

Synopsis: Pause program execution

Declaration: `procedure delay(ms: Word)`

Visibility: `default`

Description: `Delay` stops program execution for the indicated number `ms` of milliseconds.

See also: `sound` (1722), `nosound` (1722)

#### 45.3.2 `keypressed`

Synopsis: Check if a key was pressed.

**Declaration:** `function keypressed : Boolean`

**Visibility:** `default`

**Description:** `KeyPressed` returns `True` if the user pressed a key, or `False` if not. It does not wait for the user to press a key.

**See also:** `readkey` ([1722](#))

### 45.3.3 `nosound`

**Synopsis:** Stop the speaker

**Declaration:** `procedure nosound`

**Visibility:** `default`

**Description:** `NoSound` does nothing, windows does not support this.

**See also:** `sound` ([1722](#))

### 45.3.4 `readkey`

**Synopsis:** Read a key from the keyboard

**Declaration:** `function readkey : Char`

**Visibility:** `default`

**Description:** `ReadKey` reads a key from the keyboard, and returns the ASCII value of the key, or the scancode of the key in case it is a special key.

The function waits until a key is pressed.

**See also:** `KeyPressed` ([1721](#))

### 45.3.5 `sound`

**Synopsis:** Sound PC speaker

**Declaration:** `procedure sound(hz: Word)`

**Visibility:** `default`

**Description:** `Sound` sounds the PC speaker. It emits a tone with frequency `Hz` for 500 milliseconds. (the time argument is required by the windows API)

**See also:** `nosound` ([1722](#))

### 45.3.6 `textmode`

**Synopsis:** Set indicated text mode

**Declaration:** `procedure textmode(mode: Integer)`

**Visibility:** `default`

**Description:** `TextMode` does nothing.

# Chapter 46

## Reference for unit 'x86'

### 46.1 Used units

Table 46.1: Used units by unit 'x86'

Name	Page
BaseUnix	<a href="#">101</a>

### 46.2 Overview

The x86 unit contains some of the routines that were present in the 1.0.X Linux unit, and which were Intel (PC) architecture specific.

These calls have been preserved for compatibility, but should be considered deprecated: they are not portable and may not even work on future linux versions.

### 46.3 Procedures and functions

#### 46.3.1 fplOperm

Synopsis: Set permission on IO ports

Declaration: `function fplOperm(From: Cardinal; Num: Cardinal; Value: cint) : cint`

Visibility: default

Description: `fplOperm` sets permissions on `Num` ports starting with port `From` to `Value`. The function returns zero if the call was successful, a nonzero value otherwise.

Note:

- This works ONLY as root.
- Only the first `0x03ff` ports can be set.
- When doing a `FpFork` ([151](#)), the permissions are reset. When doing a `FpExecVE` ([148](#)) they are kept.

Errors: Extended error information can be retrieved with `FpGetErrno` ([154](#))

### 46.3.2 fpIoPL

Synopsis: Set I/O privilege level

Declaration: `function fpIoPL(Level: cint) : cint`

Visibility: default

Description: `FpIoPL` sets the I/O privilege level. It is intended for completeness only, one should normally not use it.

### 46.3.3 ReadPort

Synopsis: Read data from a PC port

Declaration: `procedure ReadPort (Port: LongInt; var Value: Byte)`  
`procedure ReadPort (Port: LongInt; var Value: LongInt)`  
`procedure ReadPort (Port: LongInt; var Value: Word)`

Visibility: default

Description: `ReadPort` reads one Byte, Word or Longint from port `Port` into `Value`.

Note that you need permission to read a port. This permission can be set by the root user with the `FpIOPerm` (1723) call.

Errors: In case of an error (not enough permissions read this port), runtime 216 (*Access Violation*) will occur.

See also: `FpIOPerm` (1723), `ReadPortB` (1724), `ReadPortW` (1725), `ReadPortL` (1725), `WritePort` (1725), `WritePortB` (1726), `WritePortL` (1726), `WritePortW` (1726)

### 46.3.4 ReadPortB

Synopsis: Read bytes from a PC port

Declaration: `function ReadPortB (Port: LongInt) : Byte`  
`procedure ReadPortB (Port: LongInt; var Buf; Count: LongInt)`

Visibility: default

Description: The procedural form of `ReadPortB` reads `Count` bytes from port `Port` and stores them in `Buf`. There must be enough memory allocated at `Buf` to store `Count` bytes.

The functional form of `ReadPortB` reads 1 byte from port `B` and returns the byte that was read.

Note that you need permission to read a port. This permission can be set by the root user with the `FpIOPerm` (1723) call.

Errors: In case of an error (not enough permissions read this port), runtime 216 (*Access Violation*) will occur.

See also: `FpIOPerm` (1723), `ReadPort` (1724), `ReadPortW` (1725), `ReadPortL` (1725), `WritePort` (1725), `WritePortB` (1726), `WritePortL` (1726), `WritePortW` (1726)

### 46.3.5 ReadPortL

Synopsis: Read longints from a PC port

Declaration: `function ReadPortL(Port: LongInt) : LongInt`  
`procedure ReadPortL(Port: LongInt; var Buf; Count: LongInt)`

Visibility: default

Description: The procedural form of `ReadPortL` reads `Count` longints from port `Port` and stores them in `Buf`. There must be enough memory allocated at `Buf` to store `Count` Longints.

The functional form of `ReadPortL` reads 1 longint from port `B` and returns the longint that was read.

Note that you need permission to read a port. This permission can be set by the root user with the `FpIOPerm` (1723) call.

Errors: In case of an error (not enough permissions read this port), runtime 216 (*Access Violation*) will occur.

See also: `FpIOPerm` (1723), `ReadPort` (1724), `ReadPortW` (1725), `ReadPortB` (1724), `WritePort` (1725), `WritePortB` (1726), `WritePortL` (1726), `WritePortW` (1726)

### 46.3.6 ReadPortW

Synopsis: Read Words from a PC port

Declaration: `function ReadPortW(Port: LongInt) : Word`  
`procedure ReadPortW(Port: LongInt; var Buf; Count: LongInt)`

Visibility: default

Description: The procedural form of `ReadPortW` reads `Count` words from port `Port` and stores them in `Buf`. There must be enough memory allocated at `Buf` to store `Count` words.

The functional form of `ReadPortW` reads 1 word from port `B` and returns the word that was read.

Note that you need permission to read a port. This permission can be set by the root user with the `FpIOPerm` (1723) call.

Errors: In case of an error (not enough permissions read this port), runtime 216 (*Access Violation*) will occur.

See also: `FpIOPerm` (1723), `ReadPort` (1724), `ReadPortB` (1724), `ReadPortL` (1725), `WritePort` (1725), `WritePortB` (1726), `WritePortL` (1726), `WritePortW` (1726)

### 46.3.7 WritePort

Synopsis: Write data to PC port

Declaration: `procedure WritePort(Port: LongInt; Value: Byte)`  
`procedure WritePort(Port: LongInt; Value: LongInt)`  
`procedure WritePort(Port: LongInt; Value: Word)`

Visibility: default

Description: `WritePort` writes `Value` – 1 byte, `Word` or `longint` – to port `Port`.

**Remark:** You need permission to write to a port. This permission can be set with root permission with the `FpIOPerm` (1723) call.

**Errors:** In case of an error (not enough permissions to write to this port), runtime 216 (*Access Violation*) will occur.

See also: [FpIOPerm \(1723\)](#), [WritePortB \(1726\)](#), [WritePortL \(1726\)](#), [WritePortW \(1726\)](#), [ReadPortB \(1724\)](#), [ReadPortL \(1725\)](#), [ReadPortW \(1725\)](#)

### 46.3.8 WritePortB

**Synopsis:** Write byte to PC port

**Declaration:** `procedure WritePortB(Port: LongInt; Value: Byte)`  
`procedure WritePortB(Port: LongInt; var Buf; Count: LongInt)`

**Visibility:** default

**Description:** The first form of `WritePortB` writes 1 byte to port `Port`. The second form writes `Count` bytes from `Buf` to port `Port`.

**Remark:** You need permission to write to a port. This permission can be set with root permission with the [FpIOPerm \(1723\)](#) call.

**Errors:** In case of an error (not enough permissions to write to this port), runtime 216 (*Access Violation*) will occur.

See also: [FpIOPerm \(1723\)](#), [WritePort \(1725\)](#), [WritePortL \(1726\)](#), [WritePortW \(1726\)](#), [ReadPortB \(1724\)](#), [ReadPortL \(1725\)](#), [ReadPortW \(1725\)](#)

### 46.3.9 WritePortL

**Synopsis:** Write longint to PC port.

**Declaration:** `procedure WritePortL(Port: LongInt; Value: LongInt)`  
`procedure WritePortL(Port: LongInt; var Buf; Count: LongInt)`

**Visibility:** default

**Description:** The first form of `WritePortB` writes 1 byte to port `Port`. The second form writes `Count` bytes from `Buf` to port `Port`.

**Remark:** You need permission to write to a port. This permission can be set with root permission with the [FpIOPerm \(1723\)](#) call.

**Errors:** In case of an error (not enough permissions to write to this port), runtime 216 (*Access Violation*) will occur.

See also: [FpIOPerm \(1723\)](#), [WritePort \(1725\)](#), [WritePortB \(1726\)](#), [WritePortW \(1726\)](#), [ReadPortB \(1724\)](#), [ReadPortL \(1725\)](#), [ReadPortW \(1725\)](#)

### 46.3.10 WritePortW

**Synopsis:** Write Word to PC port

**Declaration:** `procedure WritePortW(Port: LongInt; Value: Word)`  
`procedure WritePortW(Port: LongInt; var Buf; Count: LongInt)`

**Visibility:** default



**Description:** The first form of `WritePortB` writes 1 byte to port `Port`. The second form writes `Count` bytes from `Buf` to port `Port`.

**Remark:** You need permission to write to a port. This permission can be set with root permission with the `FpIOPerm` (1723) call.

**Errors:** In case of an error (not enough permissions to write to this port), runtime 216 (*Access Violation*) will occur.

**See also:** `FpIOPerm` (1723), `WritePort` (1725), `WritePortL` (1726), `WritePortB` (1726), `ReadPortB` (1724), `ReadPortL` (1725), `ReadPortW` (1725)