

Free Component Library (FCL):  
Reference guide.

---

Reference guide for FCL units.  
Document version 2.1  
July 2012

Michaël Van Canneyt

---

# Contents

0.1	Overview	54
<b>1</b>	<b>Reference for unit 'ascii85'</b>	<b>55</b>
1.1	Used units	55
1.2	Overview	55
1.3	Constants, types and variables	55
1.3.1	Types	55
1.4	TASCII85DecoderStream	55
1.4.1	Description	55
1.4.2	Method overview	56
1.4.3	Property overview	56
1.4.4	TASCII85DecoderStream.Create	56
1.4.5	TASCII85DecoderStream.Decode	56
1.4.6	TASCII85DecoderStream.Close	57
1.4.7	TASCII85DecoderStream.ClosedP	57
1.4.8	TASCII85DecoderStream.Destroy	57
1.4.9	TASCII85DecoderStream.Read	57
1.4.10	TASCII85DecoderStream.Seek	58
1.4.11	TASCII85DecoderStream.BExpectBoundary	58
1.5	TASCII85EncoderStream	58
1.5.1	Method overview	58
1.5.2	Property overview	58
1.5.3	TASCII85EncoderStream.Create	58
1.5.4	TASCII85EncoderStream.Destroy	59
1.5.5	TASCII85EncoderStream.Write	59
1.5.6	TASCII85EncoderStream.Width	59
1.5.7	TASCII85EncoderStream.Boundary	59
1.6	TASCII85RingBuffer	59
1.6.1	Description	59
1.6.2	Method overview	59
1.6.3	Property overview	59

1.6.4	TASCII85RingBuffer.Write . . . . .	59
1.6.5	TASCII85RingBuffer.Read . . . . .	60
1.6.6	TASCII85RingBuffer.FillCount . . . . .	60
1.6.7	TASCII85RingBuffer.Size . . . . .	60
<b>2</b>	<b>Reference for unit 'AVL_Tree'</b>	<b>61</b>
2.1	Used units . . . . .	61
2.2	Overview . . . . .	61
2.3	TAVLTree . . . . .	61
2.3.1	Description . . . . .	61
2.3.2	Method overview . . . . .	62
2.3.3	Property overview . . . . .	62
2.3.4	TAVLTree.Find . . . . .	62
2.3.5	TAVLTree.FindKey . . . . .	63
2.3.6	TAVLTree.FindSuccessor . . . . .	63
2.3.7	TAVLTree.FindPrecessor . . . . .	63
2.3.8	TAVLTree.FindLowest . . . . .	63
2.3.9	TAVLTree.FindHighest . . . . .	64
2.3.10	TAVLTree.FindNearest . . . . .	64
2.3.11	TAVLTree.FindPointer . . . . .	64
2.3.12	TAVLTree.FindLeftMost . . . . .	64
2.3.13	TAVLTree.FindRightMost . . . . .	65
2.3.14	TAVLTree.FindLeftMostKey . . . . .	65
2.3.15	TAVLTree.FindRightMostKey . . . . .	65
2.3.16	TAVLTree.FindLeftMostSameKey . . . . .	65
2.3.17	TAVLTree.FindRightMostSameKey . . . . .	66
2.3.18	TAVLTree.Add . . . . .	66
2.3.19	TAVLTree.Delete . . . . .	66
2.3.20	TAVLTree.Remove . . . . .	66
2.3.21	TAVLTree.RemovePointer . . . . .	67
2.3.22	TAVLTree.MoveDataLeftMost . . . . .	67
2.3.23	TAVLTree.MoveDataRightMost . . . . .	67
2.3.24	TAVLTree.Clear . . . . .	67
2.3.25	TAVLTree.FreeAndClear . . . . .	68
2.3.26	TAVLTree.FreeAndDelete . . . . .	68
2.3.27	TAVLTree.ConsistencyCheck . . . . .	68
2.3.28	TAVLTree.WriteReportToStream . . . . .	68
2.3.29	TAVLTree.ReportAsString . . . . .	69
2.3.30	TAVLTree.SetNodeManager . . . . .	69
2.3.31	TAVLTree.Create . . . . .	69

2.3.32	TAVLTree.Destroy	69
2.3.33	TAVLTree.OnCompare	69
2.3.34	TAVLTree.Count	70
2.4	TAVLTreeNode	70
2.4.1	Description	70
2.4.2	Method overview	70
2.4.3	TAVLTreeNode.Clear	70
2.4.4	TAVLTreeNode.TreeDepth	70
2.5	TAVLTreeNodeMemManager	70
2.5.1	Description	70
2.5.2	Method overview	71
2.5.3	Property overview	71
2.5.4	TAVLTreeNodeMemManager.DisposeNode	71
2.5.5	TAVLTreeNodeMemManager.NewNode	71
2.5.6	TAVLTreeNodeMemManager.Clear	71
2.5.7	TAVLTreeNodeMemManager.Create	72
2.5.8	TAVLTreeNodeMemManager.Destroy	72
2.5.9	TAVLTreeNodeMemManager.MinimumFreeNode	72
2.5.10	TAVLTreeNodeMemManager.MaximumFreeNodeRatio	72
2.5.11	TAVLTreeNodeMemManager.Count	73
2.6	TBaseAVLTreeNodeManager	73
2.6.1	Method overview	73
2.6.2	TBaseAVLTreeNodeManager.DisposeNode	73
2.6.3	TBaseAVLTreeNodeManager.NewNode	73
<b>3</b>	<b>Reference for unit 'base64'</b>	<b>74</b>
3.1	Used units	74
3.2	Overview	74
3.3	Constants, types and variables	74
3.3.1	Types	74
3.4	EBase64DecodingException	75
3.4.1	Description	75
3.5	TBase64DecodingStream	75
3.5.1	Description	75
3.5.2	Method overview	75
3.5.3	Property overview	75
3.5.4	TBase64DecodingStream.Create	75
3.5.5	TBase64DecodingStream.Reset	76
3.5.6	TBase64DecodingStream.Read	76
3.5.7	TBase64DecodingStream.Seek	76

3.5.8	TBase64DecodingStream.EOF	77
3.5.9	TBase64DecodingStream.Mode	77
3.6	TBase64EncodingStream	77
3.6.1	Description	77
3.6.2	Method overview	77
3.6.3	TBase64EncodingStream.Create	77
3.6.4	TBase64EncodingStream.Destroy	78
3.6.5	TBase64EncodingStream.Write	78
3.6.6	TBase64EncodingStream.Seek	78
<b>4</b>	<b>Reference for unit 'BlowFish'</b>	<b>79</b>
4.1	Used units	79
4.2	Overview	79
4.3	Constants, types and variables	79
4.3.1	Constants	79
4.3.2	Types	79
4.4	EBlowFishError	80
4.4.1	Description	80
4.5	TBlowFish	80
4.5.1	Description	80
4.5.2	Method overview	80
4.5.3	TBlowFish.Create	80
4.5.4	TBlowFish.Encrypt	80
4.5.5	TBlowFish.Decrypt	81
4.6	TBlowFishDeCryptStream	81
4.6.1	Description	81
4.6.2	Method overview	81
4.6.3	TBlowFishDeCryptStream.Read	81
4.6.4	TBlowFishDeCryptStream.Seek	82
4.7	TBlowFishEncryptStream	82
4.7.1	Description	82
4.7.2	Method overview	82
4.7.3	TBlowFishEncryptStream.Destroy	82
4.7.4	TBlowFishEncryptStream.Write	82
4.7.5	TBlowFishEncryptStream.Seek	83
4.7.6	TBlowFishEncryptStream.Flush	83
4.8	TBlowFishStream	83
4.8.1	Description	83
4.8.2	Method overview	84
4.8.3	Property overview	84

4.8.4	TBlowFishStream.Create . . . . .	84
4.8.5	TBlowFishStream.Destroy . . . . .	84
4.8.6	TBlowFishStream.BlowFish . . . . .	84
<b>5</b>	<b>Reference for unit 'bufstream'</b>	<b>86</b>
5.1	Used units . . . . .	86
5.2	Overview . . . . .	86
5.3	Constants, types and variables . . . . .	86
5.3.1	Constants . . . . .	86
5.4	TBufStream . . . . .	86
5.4.1	Description . . . . .	86
5.4.2	Method overview . . . . .	87
5.4.3	Property overview . . . . .	87
5.4.4	TBufStream.Create . . . . .	87
5.4.5	TBufStream.Destroy . . . . .	87
5.4.6	TBufStream.Buffer . . . . .	87
5.4.7	TBufStream.Capacity . . . . .	88
5.4.8	TBufStream.BufferPos . . . . .	88
5.4.9	TBufStream.BufferSize . . . . .	88
5.5	TReadBufStream . . . . .	89
5.5.1	Description . . . . .	89
5.5.2	Method overview . . . . .	89
5.5.3	TReadBufStream.Seek . . . . .	89
5.5.4	TReadBufStream.Read . . . . .	89
5.6	TWriteBufStream . . . . .	89
5.6.1	Description . . . . .	89
5.6.2	Method overview . . . . .	90
5.6.3	TWriteBufStream.Destroy . . . . .	90
5.6.4	TWriteBufStream.Seek . . . . .	90
5.6.5	TWriteBufStream.Write . . . . .	90
<b>6</b>	<b>Reference for unit 'CacheCls'</b>	<b>91</b>
6.1	Used units . . . . .	91
6.2	Overview . . . . .	91
6.3	Constants, types and variables . . . . .	91
6.3.1	Resource strings . . . . .	91
6.3.2	Types . . . . .	91
6.4	ECacheError . . . . .	92
6.4.1	Description . . . . .	92
6.5	TCache . . . . .	92
6.5.1	Description . . . . .	92

6.5.2	Method overview	93
6.5.3	Property overview	93
6.5.4	TCache.Create	93
6.5.5	TCache.Destroy	93
6.5.6	TCache.Add	93
6.5.7	TCache.AddNew	94
6.5.8	TCache.FindSlot	94
6.5.9	TCache.IndexOf	94
6.5.10	TCache.Remove	95
6.5.11	TCache.Data	95
6.5.12	TCache.MRUSlot	95
6.5.13	TCache.LRUSlot	96
6.5.14	TCache.SlotCount	96
6.5.15	TCache.Slots	96
6.5.16	TCache.OnIsDataEqual	96
6.5.17	TCache.OnFreeSlot	97
<b>7</b>	<b>Reference for unit 'contnrs'</b>	<b>98</b>
7.1	Used units	98
7.2	Overview	98
7.3	Constants, types and variables	98
7.3.1	Constants	98
7.3.2	Types	99
7.4	Procedures and functions	102
7.4.1	RSHash	102
7.5	EDuplicate	102
7.5.1	Description	102
7.6	EKeyNotFound	102
7.6.1	Description	102
7.7	TBucketList	102
7.7.1	Description	102
7.7.2	Method overview	103
7.7.3	TBucketList.Create	103
7.8	TClassList	103
7.8.1	Description	103
7.8.2	Method overview	103
7.8.3	Property overview	103
7.8.4	TClassList.Add	103
7.8.5	TClassList.Extract	104
7.8.6	TClassList.Remove	104

7.8.7	TClassList.IndexOf	104
7.8.8	TClassList.First	105
7.8.9	TClassList.Last	105
7.8.10	TClassList.Insert	105
7.8.11	TClassList.Items	105
7.9	TComponentList	106
7.9.1	Description	106
7.9.2	Method overview	106
7.9.3	Property overview	106
7.9.4	TComponentList.Destroy	106
7.9.5	TComponentList.Add	106
7.9.6	TComponentList.Extract	107
7.9.7	TComponentList.Remove	107
7.9.8	TComponentList.IndexOf	107
7.9.9	TComponentList.First	108
7.9.10	TComponentList.Last	108
7.9.11	TComponentList.Insert	108
7.9.12	TComponentList.Items	108
7.10	TCustomBucketList	109
7.10.1	Description	109
7.10.2	Method overview	109
7.10.3	Property overview	109
7.10.4	TCustomBucketList.Destroy	109
7.10.5	TCustomBucketList.Clear	109
7.10.6	TCustomBucketList.Add	110
7.10.7	TCustomBucketList.Assign	110
7.10.8	TCustomBucketList.Exists	110
7.10.9	TCustomBucketList.Find	110
7.10.10	TCustomBucketList.ForEach	111
7.10.11	TCustomBucketList.Remove	111
7.10.12	TCustomBucketList.Data	111
7.11	TFPCustomHashTable	111
7.11.1	Description	111
7.11.2	Method overview	112
7.11.3	Property overview	112
7.11.4	TFPCustomHashTable.Create	112
7.11.5	TFPCustomHashTable.CreateWith	112
7.11.6	TFPCustomHashTable.Destroy	113
7.11.7	TFPCustomHashTable.ChangeTableSize	113
7.11.8	TFPCustomHashTable.Clear	113



7.11.9	TFPCustomHashTable.Delete	114
7.11.10	TFPCustomHashTable.Find	114
7.11.11	TFPCustomHashTable.IsEmpty	114
7.11.12	TFPCustomHashTable.HashFunction	114
7.11.13	TFPCustomHashTable.Count	115
7.11.14	TFPCustomHashTable.HashTableSize	115
7.11.15	TFPCustomHashTable.HashTable	115
7.11.16	TFPCustomHashTable.VoidSlots	116
7.11.17	TFPCustomHashTable.LoadFactor	116
7.11.18	TFPCustomHashTable.AVGChainLen	116
7.11.19	TFPCustomHashTable.MaxChainLength	116
7.11.20	TFPCustomHashTable.NumberOfCollisions	117
7.11.21	TFPCustomHashTable.Density	117
7.12	TFPDataHashTable	117
7.12.1	Description	117
7.12.2	Method overview	117
7.12.3	Property overview	118
7.12.4	TFPDataHashTable.Add	118
7.12.5	TFPDataHashTable.Items	118
7.13	TFPHashList	118
7.13.1	Description	118
7.13.2	Method overview	119
7.13.3	Property overview	119
7.13.4	TFPHashList.Create	119
7.13.5	TFPHashList.Destroy	119
7.13.6	TFPHashList.Add	120
7.13.7	TFPHashList.Clear	120
7.13.8	TFPHashList.NameOfIndex	120
7.13.9	TFPHashList.HashOfIndex	120
7.13.10	TFPHashList.GetNextCollision	121
7.13.11	TFPHashList.Delete	121
7.13.12	TFPHashList.Error	121
7.13.13	TFPHashList.Expand	121
7.13.14	TFPHashList.Extract	122
7.13.15	TFPHashList.IndexOf	122
7.13.16	TFPHashList.Find	122
7.13.17	TFPHashList.FindIndexOf	122
7.13.18	TFPHashList.FindWithHash	123
7.13.19	TFPHashList.Rename	123
7.13.20	TFPHashList.Remove	123

7.13.21	TFPHashList.Pack	123
7.13.22	TFPHashList.ShowStatistics	124
7.13.23	TFPHashList.ForEachCall	124
7.13.24	TFPHashList.Capacity	124
7.13.25	TFPHashList.Count	124
7.13.26	TFPHashList.Items	125
7.13.27	TFPHashList.List	125
7.13.28	TFPHashList.Strs	125
7.14	TFPHashObject	125
7.14.1	Description	125
7.14.2	Method overview	126
7.14.3	Property overview	126
7.14.4	TFPHashObject.CreateNotOwned	126
7.14.5	TFPHashObject.Create	126
7.14.6	TFPHashObject.ChangeOwner	126
7.14.7	TFPHashObject.ChangeOwnerAndName	127
7.14.8	TFPHashObject.Rename	127
7.14.9	TFPHashObject.Name	127
7.14.10	TFPHashObject.Hash	127
7.15	TFPHashObjectList	128
7.15.1	Method overview	128
7.15.2	Property overview	128
7.15.3	TFPHashObjectList.Create	128
7.15.4	TFPHashObjectList.Destroy	128
7.15.5	TFPHashObjectList.Clear	129
7.15.6	TFPHashObjectList.Add	129
7.15.7	TFPHashObjectList.NameOfIndex	129
7.15.8	TFPHashObjectList.HashOfIndex	130
7.15.9	TFPHashObjectList.GetNextCollision	130
7.15.10	TFPHashObjectList.Delete	130
7.15.11	TFPHashObjectList.Expand	130
7.15.12	TFPHashObjectList.Extract	131
7.15.13	TFPHashObjectList.Remove	131
7.15.14	TFPHashObjectList.IndexOf	131
7.15.15	TFPHashObjectList.Find	131
7.15.16	TFPHashObjectList.FindIndexOf	132
7.15.17	TFPHashObjectList.FindWithHash	132
7.15.18	TFPHashObjectList.Rename	132
7.15.19	TFPHashObjectList.FindInstanceOf	132
7.15.20	TFPHashObjectList.Pack	133

---

7.15.21	TFPHashObjectList.ShowStatistics	133
7.15.22	TFPHashObjectList.ForEachCall	133
7.15.23	TFPHashObjectList.Capacity	133
7.15.24	TFPHashObjectList.Count	134
7.15.25	TFPHashObjectList.OwnsObjects	134
7.15.26	TFPHashObjectList.Items	134
7.15.27	TFPHashObjectList.List	134
7.16	TFPObjectHashTable	135
7.16.1	Description	135
7.16.2	Method overview	135
7.16.3	Property overview	135
7.16.4	TFPObjectHashTable.Create	135
7.16.5	TFPObjectHashTable.CreateWith	135
7.16.6	TFPObjectHashTable.Add	136
7.16.7	TFPObjectHashTable.Items	136
7.16.8	TFPObjectHashTable.OwnsObjects	136
7.17	TFPObjectList	137
7.17.1	Description	137
7.17.2	Method overview	137
7.17.3	Property overview	137
7.17.4	TFPObjectList.Create	137
7.17.5	TFPObjectList.Destroy	138
7.17.6	TFPObjectList.Clear	138
7.17.7	TFPObjectList.Add	138
7.17.8	TFPObjectList.Delete	138
7.17.9	TFPObjectList.Exchange	139
7.17.10	TFPObjectList.Expand	139
7.17.11	TFPObjectList.Extract	139
7.17.12	TFPObjectList.Remove	140
7.17.13	TFPObjectList.IndexOf	140
7.17.14	TFPObjectList.FindInstanceOf	140
7.17.15	TFPObjectList.Insert	140
7.17.16	TFPObjectList.First	141
7.17.17	TFPObjectList.Last	141
7.17.18	TFPObjectList.Move	141
7.17.19	TFPObjectList.Assign	142
7.17.20	TFPObjectList.Pack	142
7.17.21	TFPObjectList.Sort	142
7.17.22	TFPObjectList.ForEachCall	142
7.17.23	TFPObjectList.Capacity	143

7.17.24	TFPObjectList.Count	143
7.17.25	TFPObjectList.OwnsObjects	143
7.17.26	TFPObjectList.Items	144
7.17.27	TFPObjectList.List	144
7.18	TFPStringHashTable	144
7.18.1	Description	144
7.18.2	Method overview	144
7.18.3	Property overview	144
7.18.4	TFPStringHashTable.Add	144
7.18.5	TFPStringHashTable.Items	145
7.19	THTCustomNode	145
7.19.1	Description	145
7.19.2	Method overview	145
7.19.3	Property overview	145
7.19.4	THTCustomNode.CreateWith	145
7.19.5	THTCustomNode.HasKey	146
7.19.6	THTCustomNode.Key	146
7.20	THTDataNode	146
7.20.1	Description	146
7.20.2	Property overview	146
7.20.3	THTDataNode.Data	146
7.21	THTObjectNode	147
7.21.1	Description	147
7.21.2	Property overview	147
7.21.3	THTObjectNode.Data	147
7.22	THTOwnedObjectNode	147
7.22.1	Description	147
7.22.2	Method overview	147
7.22.3	THTOwnedObjectNode.Destroy	147
7.23	THTStringNode	148
7.23.1	Description	148
7.23.2	Property overview	148
7.23.3	THTStringNode.Data	148
7.24	TObjectBucketList	148
7.24.1	Description	148
7.24.2	Method overview	148
7.24.3	Property overview	148
7.24.4	TObjectBucketList.Add	148
7.24.5	TObjectBucketList.Remove	149
7.24.6	TObjectBucketList.Data	149

7.25	TObjectList	149
7.25.1	Description	149
7.25.2	Method overview	149
7.25.3	Property overview	150
7.25.4	TObjectList.create	150
7.25.5	TObjectList.Add	150
7.25.6	TObjectList.Extract	150
7.25.7	TObjectList.Remove	151
7.25.8	TObjectList.IndexOf	151
7.25.9	TObjectList.FindInstanceOf	151
7.25.10	TObjectList.Insert	152
7.25.11	TObjectList.First	152
7.25.12	TObjectList.Last	152
7.25.13	TObjectList.OwnsObjects	152
7.25.14	TObjectList.Items	153
7.26	TObjectQueue	153
7.26.1	Method overview	153
7.26.2	TObjectQueue.Push	153
7.26.3	TObjectQueue.Pop	153
7.26.4	TObjectQueue.Peek	154
7.27	TObjectStack	154
7.27.1	Description	154
7.27.2	Method overview	154
7.27.3	TObjectStack.Push	154
7.27.4	TObjectStack.Pop	154
7.27.5	TObjectStack.Peek	155
7.28	TOrderedList	155
7.28.1	Description	155
7.28.2	Method overview	155
7.28.3	TOrderedList.Create	155
7.28.4	TOrderedList.Destroy	155
7.28.5	TOrderedList.Count	156
7.28.6	TOrderedList.AtLeast	156
7.28.7	TOrderedList.Push	156
7.28.8	TOrderedList.Pop	157
7.28.9	TOrderedList.Peek	157
7.29	TQueue	157
7.29.1	Description	157
7.30	TStack	157
7.30.1	Description	157

<b>8</b>	<b>Reference for unit 'CustApp'</b>	<b>158</b>
8.1	Used units	158
8.2	Overview	158
8.3	Constants, types and variables	158
8.3.1	Types	158
8.3.2	Variables	159
8.4	TCustomApplication	159
8.4.1	Description	159
8.4.2	Method overview	159
8.4.3	Property overview	160
8.4.4	TCustomApplication.Create	160
8.4.5	TCustomApplication.Destroy	160
8.4.6	TCustomApplication.HandleException	160
8.4.7	TCustomApplication.Initialize	161
8.4.8	TCustomApplication.Run	161
8.4.9	TCustomApplication.ShowException	161
8.4.10	TCustomApplication.Terminate	162
8.4.11	TCustomApplication.FindOptionIndex	162
8.4.12	TCustomApplication.GetOptionValue	162
8.4.13	TCustomApplication.HasOption	163
8.4.14	TCustomApplication.CheckOptions	163
8.4.15	TCustomApplication.GetEnvironmentList	164
8.4.16	TCustomApplication.Log	164
8.4.17	TCustomApplication.ExeName	164
8.4.18	TCustomApplication.HelpFile	165
8.4.19	TCustomApplication.Terminated	165
8.4.20	TCustomApplication.Title	165
8.4.21	TCustomApplication.OnException	166
8.4.22	TCustomApplication.ConsoleApplication	166
8.4.23	TCustomApplication.Location	166
8.4.24	TCustomApplication.Params	166
8.4.25	TCustomApplication.ParamCount	167
8.4.26	TCustomApplication.EnvironmentVariable	167
8.4.27	TCustomApplication.OptionChar	167
8.4.28	TCustomApplication.CaseSensitiveOptions	168
8.4.29	TCustomApplication.StopOnException	168
<b>9</b>	<b>Reference for unit 'daemonapp'</b>	<b>169</b>
9.1	Used units	169
9.2	Overview	169

---

9.3	Daemon application architecture	170
9.4	Constants, types and variables	170
9.4.1	Resource strings	170
9.4.2	Types	171
9.4.3	Variables	173
9.5	Procedures and functions	174
9.5.1	Application	174
9.5.2	DaemonError	174
9.5.3	RegisterDaemonApplicationClass	174
9.5.4	RegisterDaemonClass	175
9.5.5	RegisterDaemonMapper	175
9.6	EDaemon	175
9.6.1	Description	175
9.7	TCustomDaemon	175
9.7.1	Description	175
9.7.2	Method overview	175
9.7.3	Property overview	176
9.7.4	TCustomDaemon.LogMessage	176
9.7.5	TCustomDaemon.ReportStatus	176
9.7.6	TCustomDaemon.Definition	176
9.7.7	TCustomDaemon.DaemonThread	177
9.7.8	TCustomDaemon.Controller	177
9.7.9	TCustomDaemon.Status	177
9.7.10	TCustomDaemon.Logger	178
9.8	TCustomDaemonApplication	178
9.8.1	Description	178
9.8.2	Method overview	178
9.8.3	Property overview	178
9.8.4	TCustomDaemonApplication.ShowException	178
9.8.5	TCustomDaemonApplication.CreateDaemon	179
9.8.6	TCustomDaemonApplication.StopDaemons	179
9.8.7	TCustomDaemonApplication.InstallDaemons	179
9.8.8	TCustomDaemonApplication.RunDaemons	179
9.8.9	TCustomDaemonApplication.UnInstallDaemons	180
9.8.10	TCustomDaemonApplication.CreateForm	180
9.8.11	TCustomDaemonApplication.OnRun	180
9.8.12	TCustomDaemonApplication.Logger	180
9.8.13	TCustomDaemonApplication.GUIMainLoop	181
9.8.14	TCustomDaemonApplication.GuiHandle	181
9.8.15	TCustomDaemonApplication.RunMode	181

---

9.9	TCustomDaemonMapper	182
9.9.1	Description	182
9.9.2	Method overview	182
9.9.3	Property overview	182
9.9.4	TCustomDaemonMapper.Create	182
9.9.5	TCustomDaemonMapper.Destroy	182
9.9.6	TCustomDaemonMapper.DaemonDefs	183
9.9.7	TCustomDaemonMapper.OnCreate	183
9.9.8	TCustomDaemonMapper.OnDestroy	183
9.9.9	TCustomDaemonMapper.OnRun	183
9.9.10	TCustomDaemonMapper.OnInstall	184
9.9.11	TCustomDaemonMapper.OnUnInstall	184
9.10	TDaemon	184
9.10.1	Description	184
9.10.2	Property overview	185
9.10.3	TDaemon.Definition	185
9.10.4	TDaemon.Status	185
9.10.5	TDaemon.OnStart	185
9.10.6	TDaemon.OnStop	186
9.10.7	TDaemon.OnPause	186
9.10.8	TDaemon.OnContinue	186
9.10.9	TDaemon.OnShutDown	187
9.10.10	TDaemon.OnExecute	187
9.10.11	TDaemon.BeforeInstall	187
9.10.12	TDaemon.AfterInstall	188
9.10.13	TDaemon.BeforeUnInstall	188
9.10.14	TDaemon.AfterUnInstall	188
9.10.15	TDaemon.OnControlCode	188
9.11	TDaemonApplication	189
9.11.1	Description	189
9.12	TDaemonController	189
9.12.1	Description	189
9.12.2	Method overview	189
9.12.3	Property overview	189
9.12.4	TDaemonController.Create	189
9.12.5	TDaemonController.Destroy	190
9.12.6	TDaemonController.StartService	190
9.12.7	TDaemonController.Main	190
9.12.8	TDaemonController.Controller	190
9.12.9	TDaemonController.ReportStatus	191



9.12.10	TDaemonController.Daemon	191
9.12.11	TDaemonController.Params	191
9.12.12	TDaemonController.LastStatus	191
9.12.13	TDaemonController.CheckPoint	192
9.13	TDaemonDef	192
9.13.1	Description	192
9.13.2	Method overview	192
9.13.3	Property overview	192
9.13.4	TDaemonDef.Create	192
9.13.5	TDaemonDef.Destroy	193
9.13.6	TDaemonDef.DaemonClass	193
9.13.7	TDaemonDef.Instance	193
9.13.8	TDaemonDef.DaemonClassName	193
9.13.9	TDaemonDef.Name	194
9.13.10	TDaemonDef.Description	194
9.13.11	TDaemonDef.DisplayName	194
9.13.12	TDaemonDef.RunArguments	194
9.13.13	TDaemonDef.Options	195
9.13.14	TDaemonDef.Enabled	195
9.13.15	TDaemonDef.WinBindings	195
9.13.16	TDaemonDef.OnCreateInstance	195
9.13.17	TDaemonDef.LogStatusReport	196
9.14	TDaemonDefs	196
9.14.1	Description	196
9.14.2	Method overview	196
9.14.3	Property overview	196
9.14.4	TDaemonDefs.Create	196
9.14.5	TDaemonDefs.IndexOfDaemonDef	197
9.14.6	TDaemonDefs.FindDaemonDef	197
9.14.7	TDaemonDefs.DaemonDefByName	197
9.14.8	TDaemonDefs.Daemons	197
9.15	TDaemonMapper	198
9.15.1	Description	198
9.15.2	Method overview	198
9.15.3	TDaemonMapper.Create	198
9.15.4	TDaemonMapper.CreateNew	198
9.16	TDaemonThread	198
9.16.1	Description	198
9.16.2	Method overview	199
9.16.3	Property overview	199

9.16.4	<a href="#">TDaemonThread.Create</a>	199
9.16.5	<a href="#">TDaemonThread.Execute</a>	199
9.16.6	<a href="#">TDaemonThread.CheckControlMessage</a>	199
9.16.7	<a href="#">TDaemonThread.StopDaemon</a>	200
9.16.8	<a href="#">TDaemonThread.PauseDaemon</a>	200
9.16.9	<a href="#">TDaemonThread.ContinueDaemon</a>	200
9.16.10	<a href="#">TDaemonThread.ShutDownDaemon</a>	200
9.16.11	<a href="#">TDaemonThread.InterrogateDaemon</a>	201
9.16.12	<a href="#">TDaemonThread.Daemon</a>	201
9.17	<a href="#">TDependencies</a>	201
9.17.1	<a href="#">Description</a>	201
9.17.2	<a href="#">Method overview</a>	201
9.17.3	<a href="#">Property overview</a>	201
9.17.4	<a href="#">TDependencies.Create</a>	201
9.17.5	<a href="#">TDependencies.Items</a>	202
9.18	<a href="#">TDependency</a>	202
9.18.1	<a href="#">Description</a>	202
9.18.2	<a href="#">Method overview</a>	202
9.18.3	<a href="#">Property overview</a>	202
9.18.4	<a href="#">TDependency.Assign</a>	202
9.18.5	<a href="#">TDependency.Name</a>	202
9.18.6	<a href="#">TDependency.IsGroup</a>	203
9.19	<a href="#">TWinBindings</a>	203
9.19.1	<a href="#">Description</a>	203
9.19.2	<a href="#">Method overview</a>	203
9.19.3	<a href="#">Property overview</a>	203
9.19.4	<a href="#">TWinBindings.Create</a>	203
9.19.5	<a href="#">TWinBindings.Destroy</a>	204
9.19.6	<a href="#">TWinBindings.Assign</a>	204
9.19.7	<a href="#">TWinBindings.ErrCode</a>	204
9.19.8	<a href="#">TWinBindings.Win32ErrCode</a>	204
9.19.9	<a href="#">TWinBindings.Dependencies</a>	205
9.19.10	<a href="#">TWinBindings.GroupName</a>	205
9.19.11	<a href="#">TWinBindings.Password</a>	205
9.19.12	<a href="#">TWinBindings.UserName</a>	205
9.19.13	<a href="#">TWinBindings.StartType</a>	206
9.19.14	<a href="#">TWinBindings.WaitHint</a>	206
9.19.15	<a href="#">TWinBindings.IDTag</a>	206
9.19.16	<a href="#">TWinBindings.ServiceType</a>	207
9.19.17	<a href="#">TWinBindings.ErrorSeverity</a>	207

<b>10 Reference for unit 'db'</b>	<b>208</b>
10.1 Used units	208
10.2 Overview	208
10.3 Constants, types and variables	208
10.3.1 Constants	208
10.3.2 Types	209
10.4 Procedures and functions	218
10.4.1 BuffersEqual	218
10.4.2 DatabaseError	218
10.4.3 DatabaseErrorFmt	219
10.4.4 DateTimeRecToDateTime	219
10.4.5 DateTimeToDateTimeRec	219
10.4.6 DisposeMem	219
10.4.7 ExtractFieldName	220
10.4.8 SkipComments	220
10.5 EDatabaseError	220
10.5.1 Description	220
10.6 EUpdateError	220
10.6.1 Description	220
10.6.2 Method overview	221
10.6.3 Property overview	221
10.6.4 EUpdateError.Create	221
10.6.5 EUpdateError.Destroy	221
10.6.6 EUpdateError.Context	221
10.6.7 EUpdateError.ErrorCode	222
10.6.8 EUpdateError.OriginalExcaption	222
10.6.9 EUpdateError.PreviousError	222
10.7 TAutoIncField	222
10.7.1 Description	222
10.7.2 Method overview	223
10.7.3 TAutoIncField.Create	223
10.8 TBCDField	223
10.8.1 Description	223
10.8.2 Method overview	223
10.8.3 Property overview	223
10.8.4 TBCDField.Create	223
10.8.5 TBCDField.CheckRange	224
10.8.6 TBCDField.Value	224
10.8.7 TBCDField.Precision	224
10.8.8 TBCDField.Currency	225

10.8.9	TBCDField.MaxValue	225
10.8.10	TBCDField.MinValue	225
10.8.11	TBCDField.Size	226
10.9	TBinaryField	226
10.9.1	Description	226
10.9.2	Method overview	226
10.9.3	Property overview	226
10.9.4	TBinaryField.Create	226
10.9.5	TBinaryField.Size	226
10.10	TBlobField	227
10.10.1	Description	227
10.10.2	Method overview	227
10.10.3	Property overview	227
10.10.4	TBlobField.Create	227
10.10.5	TBlobField.Clear	228
10.10.6	TBlobField.IsBlob	228
10.10.7	TBlobField.LoadFromFile	228
10.10.8	TBlobField.LoadFromStream	228
10.10.9	TBlobField.SaveToFile	229
10.10.10	TBlobField.SaveToStream	229
10.10.11	TBlobField.SetFieldType	229
10.10.12	TBlobField.BlobSize	229
10.10.13	TBlobField.Modified	230
10.10.14	TBlobField.Value	230
10.10.15	TBlobField.Transliterate	230
10.10.16	TBlobField.BlobType	230
10.10.17	TBlobField.Size	231
10.11	TBooleanField	231
10.11.1	Description	231
10.11.2	Method overview	231
10.11.3	Property overview	231
10.11.4	TBooleanField.Create	231
10.11.5	TBooleanField.Value	232
10.11.6	TBooleanField.DisplayValues	232
10.12	TBytesField	232
10.12.1	Description	232
10.12.2	Method overview	232
10.12.3	TBytesField.Create	233
10.13	TCheckConstraint	233
10.13.1	Description	233

10.13.2 Method overview . . . . .	233
10.13.3 Property overview . . . . .	233
10.13.4 TCheckConstraint.Assign . . . . .	233
10.13.5 TCheckConstraint.CustomConstraint . . . . .	234
10.13.6 TCheckConstraint.ErrorMessage . . . . .	234
10.13.7 TCheckConstraint.FromDictionary . . . . .	234
10.13.8 TCheckConstraint.ImportedConstraint . . . . .	234
10.14 TCheckConstraints . . . . .	235
10.14.1 Description . . . . .	235
10.14.2 Method overview . . . . .	235
10.14.3 Property overview . . . . .	235
10.14.4 TCheckConstraints.Create . . . . .	235
10.14.5 TCheckConstraints.Add . . . . .	235
10.14.6 TCheckConstraints.Items . . . . .	235
10.15 TCurrencyField . . . . .	236
10.15.1 Description . . . . .	236
10.15.2 Method overview . . . . .	236
10.15.3 Property overview . . . . .	236
10.15.4 TCurrencyField.Create . . . . .	236
10.15.5 TCurrencyField.Currency . . . . .	236
10.16 TCustomConnection . . . . .	237
10.16.1 Description . . . . .	237
10.16.2 Method overview . . . . .	237
10.16.3 Property overview . . . . .	237
10.16.4 TCustomConnection.Close . . . . .	237
10.16.5 TCustomConnection.Destroy . . . . .	237
10.16.6 TCustomConnection.Open . . . . .	238
10.16.7 TCustomConnection.DataSetCount . . . . .	238
10.16.8 TCustomConnection.DataSets . . . . .	238
10.16.9 TCustomConnection.Connected . . . . .	239
10.16.10 TCustomConnection.LoginPrompt . . . . .	239
10.16.11 TCustomConnection.AfterConnect . . . . .	239
10.16.12 TCustomConnection.AfterDisconnect . . . . .	239
10.16.13 TCustomConnection.BeforeConnect . . . . .	240
10.16.14 TCustomConnection.BeforeDisconnect . . . . .	240
10.16.15 TCustomConnection.OnLogin . . . . .	240
10.17 TDatabase . . . . .	241
10.17.1 Description . . . . .	241
10.17.2 Method overview . . . . .	241
10.17.3 Property overview . . . . .	241

10.17.4 TDatabase.Create . . . . .	241
10.17.5 TDatabase.Destroy . . . . .	242
10.17.6 TDatabase.CloseDataSets . . . . .	242
10.17.7 TDatabase.CloseTransactions . . . . .	242
10.17.8 TDatabase.StartTransaction . . . . .	242
10.17.9 TDatabase.EndTransaction . . . . .	243
10.17.10 TDatabase.TransactionCount . . . . .	243
10.17.11 TDatabase.Transactions . . . . .	243
10.17.12 TDatabase.Directory . . . . .	243
10.17.13 TDatabase.IsSQLBased . . . . .	244
10.17.14 TDatabase.Connected . . . . .	244
10.17.15 TDatabase.DatabaseName . . . . .	244
10.17.16 TDatabase.KeepConnection . . . . .	244
10.17.17 TDatabase.Params . . . . .	245
10.18 TDataLink . . . . .	245
10.18.1 Description . . . . .	245
10.18.2 Method overview . . . . .	245
10.18.3 Property overview . . . . .	246
10.18.4 TDataLink.Create . . . . .	246
10.18.5 TDataLink.Destroy . . . . .	246
10.18.6 TDataLink.Edit . . . . .	246
10.18.7 TDataLink.UpdateRecord . . . . .	247
10.18.8 TDataLink.ExecuteAction . . . . .	247
10.18.9 TDataLink.UpdateAction . . . . .	247
10.18.10 TDataLink.Active . . . . .	247
10.18.11 TDataLink.ActiveRecord . . . . .	248
10.18.12 TDataLink.BOF . . . . .	248
10.18.13 TDataLink.BufferCount . . . . .	248
10.18.14 TDataLink.DataSet . . . . .	249
10.18.15 TDataLink.DataSource . . . . .	249
10.18.16 TDataLink.DataSourceFixed . . . . .	249
10.18.17 TDataLink.Editing . . . . .	249
10.18.18 TDataLink.Eof . . . . .	250
10.18.19 TDataLink.ReadOnly . . . . .	250
10.18.20 TDataLink.RecordCount . . . . .	250
10.19 TDataSet . . . . .	250
10.19.1 Description . . . . .	250
10.19.2 Method overview . . . . .	253
10.19.3 Property overview . . . . .	254
10.19.4 TDataSet.Create . . . . .	255

10.19.5 TDataSet.Destroy . . . . .	255
10.19.6 TDataSet.ActiveBuffer . . . . .	255
10.19.7 TDataSet.GetFieldData . . . . .	255
10.19.8 TDataSet.SetFieldData . . . . .	256
10.19.9 TDataSet.Append . . . . .	256
10.19.10 TDataSet.AppendRecord . . . . .	256
10.19.11 TDataSet.BookmarkValid . . . . .	257
10.19.12 TDataSet.Cancel . . . . .	257
10.19.13 TDataSet.CheckBrowseMode . . . . .	257
10.19.14 TDataSet.ClearFields . . . . .	257
10.19.15 TDataSet.Close . . . . .	258
10.19.16 TDataSet.ControlsDisabled . . . . .	258
10.19.17 TDataSet.CompareBookmarks . . . . .	258
10.19.18 TDataSet.CreateBlobStream . . . . .	259
10.19.19 TDataSet.CursorPosChanged . . . . .	259
10.19.20 TDataSet.DataConvert . . . . .	259
10.19.21 TDataSet.Delete . . . . .	259
10.19.22 TDataSet.DisableControls . . . . .	260
10.19.23 TDataSet.Edit . . . . .	260
10.19.24 TDataSet.EnableControls . . . . .	261
10.19.25 TDataSet.FieldByName . . . . .	261
10.19.26 TDataSet.FindField . . . . .	261
10.19.27 TDataSet.FindFirst . . . . .	262
10.19.28 TDataSet.FindLast . . . . .	262
10.19.29 TDataSet.FindNext . . . . .	262
10.19.30 TDataSet.FindPrior . . . . .	262
10.19.31 TDataSet.First . . . . .	263
10.19.32 TDataSet.FreeBookmark . . . . .	263
10.19.33 TDataSet.GetBookmark . . . . .	263
10.19.34 TDataSet.GetCurrentRecord . . . . .	264
10.19.35 TDataSet.GetFieldList . . . . .	264
10.19.36 TDataSet.GetFieldNames . . . . .	264
10.19.37 TDataSet.GotoBookmark . . . . .	264
10.19.38 TDataSet.Insert . . . . .	265
10.19.39 TDataSet.InsertRecord . . . . .	265
10.19.40 TDataSet.IsEmpty . . . . .	265
10.19.41 TDataSet.IsLinkedTo . . . . .	265
10.19.42 TDataSet.IsSequenced . . . . .	266
10.19.43 TDataSet.Last . . . . .	266
10.19.44 TDataSet.Locate . . . . .	266

10.19.45	DataSet.Lookup	267
10.19.46	DataSet.MoveBy	267
10.19.47	DataSet.Next	267
10.19.48	DataSet.Open	268
10.19.49	DataSet.Post	268
10.19.50	DataSet.Prior	269
10.19.51	DataSet.Refresh	269
10.19.52	DataSet.Resync	269
10.19.53	DataSet.SetFields	270
10.19.54	DataSet.Translate	270
10.19.55	DataSet.UpdateCursorPos	270
10.19.56	DataSet.UpdateRecord	270
10.19.57	DataSet.UpdateStatus	271
10.19.58	DataSet.BOF	271
10.19.59	DataSet.Bookmark	271
10.19.60	DataSet.CanModify	272
10.19.61	DataSet.DataSource	272
10.19.62	DataSet.DefaultFields	273
10.19.63	DataSet.EOF	273
10.19.64	DataSet.FieldCount	274
10.19.65	DataSet.FieldDefs	274
10.19.66	DataSet.Found	274
10.19.67	DataSet.Modified	275
10.19.68	DataSet.IsUniDirectional	275
10.19.69	DataSet.RecordCount	275
10.19.70	DataSet.RecNo	276
10.19.71	DataSet.RecordSize	276
10.19.72	DataSet.State	276
10.19.73	DataSet.Fields	277
10.19.74	DataSet.FieldValues	277
10.19.75	DataSet.Filter	277
10.19.76	DataSet.Filtered	278
10.19.77	DataSet.FilterOptions	278
10.19.78	DataSet.Active	278
10.19.79	DataSet.AutoCalcFields	279
10.19.80	DataSet.BeforeOpen	279
10.19.81	DataSet.AfterOpen	280
10.19.82	DataSet.BeforeClose	280
10.19.83	DataSet.AfterClose	280
10.19.84	DataSet.BeforeInsert	280



10.19.85	TDataSet.AfterInsert	281
10.19.86	TDataSet.BeforeEdit	281
10.19.87	TDataSet.AfterEdit	281
10.19.88	TDataSet.BeforePost	282
10.19.89	TDataSet.AfterPost	282
10.19.90	TDataSet.BeforeCancel	282
10.19.91	TDataSet.AfterCancel	283
10.19.92	TDataSet.BeforeDelete	283
10.19.93	TDataSet.AfterDelete	283
10.19.94	TDataSet.BeforeScroll	283
10.19.95	TDataSet.AfterScroll	284
10.19.96	TDataSet.BeforeRefresh	284
10.19.97	TDataSet.AfterRefresh	284
10.19.98	TDataSet.OnCalcFields	285
10.19.99	TDataSet.OnDeleteError	285
10.19.100	TDataSet.OnEditError	286
10.19.101	TDataSet.OnFilterRecord	286
10.19.102	TDataSet.OnNewRecord	286
10.19.103	TDataSet.OnPostError	287
10.20	TDataSource	287
10.20.1	Description	287
10.20.2	Method overview	287
10.20.3	Property overview	288
10.20.4	TDataSource.Create	288
10.20.5	TDataSource.Destroy	288
10.20.6	TDataSource.Edit	288
10.20.7	TDataSource.IsLinkedTo	289
10.20.8	TDataSource.State	289
10.20.9	TDataSource.AutoEdit	289
10.20.10	TDataSource.DataSet	289
10.20.11	TDataSource.Enabled	290
10.20.12	TDataSource.OnStateChange	290
10.20.13	TDataSource.OnDataChange	290
10.20.14	TDataSource.OnUpdateData	291
10.21	TDateField	291
10.21.1	Description	291
10.21.2	Method overview	291
10.21.3	TDateField.Create	291
10.22	TDateTimeField	291
10.22.1	Description	291

10.22.2 Method overview . . . . .	292
10.22.3 Property overview . . . . .	292
10.22.4 TDateTimeField.Create . . . . .	292
10.22.5 TDateTimeField.Value . . . . .	292
10.22.6 TDateTimeField.DisplayFormat . . . . .	292
10.23 TDBDataset . . . . .	293
10.23.1 Description . . . . .	293
10.23.2 Method overview . . . . .	293
10.23.3 Property overview . . . . .	293
10.23.4 TDBDataset.destroy . . . . .	293
10.23.5 TDBDataset.DataBase . . . . .	293
10.23.6 TDBDataset.Transaction . . . . .	294
10.24 TDBTransaction . . . . .	294
10.24.1 Description . . . . .	294
10.24.2 Method overview . . . . .	294
10.24.3 Property overview . . . . .	294
10.24.4 TDBTransaction.Create . . . . .	294
10.24.5 TDBTransaction.destroy . . . . .	295
10.24.6 TDBTransaction.CloseDataSets . . . . .	295
10.24.7 TDBTransaction.DataBase . . . . .	295
10.24.8 TDBTransaction.Active . . . . .	295
10.25 TDefCollection . . . . .	296
10.25.1 Description . . . . .	296
10.25.2 Method overview . . . . .	296
10.25.3 Property overview . . . . .	296
10.25.4 TDefCollection.create . . . . .	296
10.25.5 TDefCollection.Find . . . . .	296
10.25.6 TDefCollection.GetItemNames . . . . .	297
10.25.7 TDefCollection.IndexOf . . . . .	297
10.25.8 TDefCollection.Dataset . . . . .	297
10.25.9 TDefCollection.Updated . . . . .	297
10.26 TDetailDataLink . . . . .	298
10.26.1 Description . . . . .	298
10.26.2 Property overview . . . . .	298
10.26.3 TDetailDataLink.DetailDataSet . . . . .	298
10.27 TField . . . . .	298
10.27.1 Description . . . . .	298
10.27.2 Method overview . . . . .	299
10.27.3 Property overview . . . . .	301
10.27.4 TField.Create . . . . .	302

10.27.5 TField.Destroy	302
10.27.6 TField.Assign	302
10.27.7 TField.AssignValue	302
10.27.8 TField.Clear	303
10.27.9 TField.FocusControl	303
10.27.10 TField.GetData	303
10.27.11 TField.IsBlob	304
10.27.12 TField.IsValidChar	304
10.27.13 TField.RefreshLookupList	304
10.27.14 TField.SetData	304
10.27.15 TField.SetFieldType	305
10.27.16 TField.Validate	305
10.27.17 TField.AsBCD	305
10.27.18 TField.AsBoolean	306
10.27.19 TField.AsCurrency	306
10.27.20 TField.AsDateTime	306
10.27.21 TField.AsFloat	307
10.27.22 TField.AsLongint	307
10.27.23 TField.AsLargeInt	307
10.27.24 TField.AsInteger	308
10.27.25 TField.AsString	308
10.27.26 TField.AsWideString	308
10.27.27 TField.AsVariant	309
10.27.28 TField.AttributeSet	309
10.27.29 TField.Calculated	309
10.27.30 TField.CanModify	309
10.27.31 TField.CurValue	310
10.27.32 TField.DataSet	310
10.27.33 TField.DataSize	310
10.27.34 TField.DataType	310
10.27.35 TField.DisplayName	311
10.27.36 TField.DisplayText	311
10.27.37 TField.FieldNo	311
10.27.38 TField.IsIndexField	312
10.27.39 TField.IsNull	312
10.27.40 TField.Lookup	312
10.27.41 TField.NewValue	312
10.27.42 TField.Offset	313
10.27.43 TField.Size	313
10.27.44 TField.Text	313

10.27.45	Field.ValidChars	313
10.27.46	Field.Value	314
10.27.47	Field.OldValue	314
10.27.48	Field.LookupList	314
10.27.49	Field.Alignment	315
10.27.50	Field.CustomConstraint	315
10.27.51	Field.ConstraintErrorMessage	315
10.27.52	Field.DefaultExpression	316
10.27.53	Field.DisplayLabel	316
10.27.54	Field.DisplayWidth	316
10.27.55	Field.FieldKind	316
10.27.56	Field.FieldName	317
10.27.57	Field.HasConstraints	317
10.27.58	Field.Index	317
10.27.59	Field.ImportedConstraint	317
10.27.60	Field.KeyFields	318
10.27.61	Field.LookupCache	318
10.27.62	Field.LookupDataSet	318
10.27.63	Field.LookupKeyFields	319
10.27.64	Field.LookupResultField	319
10.27.65	Field.Origin	319
10.27.66	Field.ProviderFlags	319
10.27.67	Field.ReadOnly	320
10.27.68	Field.Required	320
10.27.69	Field.Visible	320
10.27.70	Field.OnChange	321
10.27.71	Field.OnGetText	321
10.27.72	Field.OnSetText	321
10.27.73	Field.OnValidate	322
10.28	TFieldDef	322
10.28.1	Description	322
10.28.2	Method overview	322
10.28.3	Property overview	322
10.28.4	TFieldDef.Create	322
10.28.5	TFieldDef.Destroy	323
10.28.6	TFieldDef.Assign	323
10.28.7	TFieldDef.CreateField	323
10.28.8	TFieldDef.FieldClass	324
10.28.9	TFieldDef.FieldNo	324
10.28.10	TFieldDef.InternalCalcField	324

10.28.1	IFieldDef.Required	324
10.28.12	TFFieldDef.Attributes	325
10.28.13	TFFieldDef.DataType	325
10.28.14	TFFieldDef.Precision	325
10.28.15	TFFieldDef.Size	326
10.29	TFFieldDefs	326
10.29.1	Description	326
10.29.2	Method overview	326
10.29.3	Property overview	326
10.29.4	TFFieldDefs.Create	326
10.29.5	TFFieldDefs.Add	327
10.29.6	TFFieldDefs.AddFieldDef	327
10.29.7	TFFieldDefs.Assign	327
10.29.8	TFFieldDefs.Find	328
10.29.9	TFFieldDefs.Update	328
10.29.10	TFFieldDefs.MakeNameUnique	328
10.29.11	IFFieldDefs.HiddenFields	328
10.29.12	TFFieldDefs.Items	329
10.30	TFields	329
10.30.1	Description	329
10.30.2	Method overview	329
10.30.3	Property overview	329
10.30.4	TFields.Create	329
10.30.5	TFields.Destroy	330
10.30.6	TFields.Add	330
10.30.7	TFields.CheckFieldName	330
10.30.8	TFields.CheckFieldNames	330
10.30.9	TFields.Clear	331
10.30.10	TFields.FindField	331
10.30.11	IFFields.FieldByName	331
10.30.12	TFields.FieldByNumber	331
10.30.13	TFields.GetEnumerator	332
10.30.14	TFields.GetFieldNames	332
10.30.15	TFields.IndexOf	332
10.30.16	TFields.Remove	332
10.30.17	TFields.Count	333
10.30.18	TFields.Dataset	333
10.30.19	TFields.Fields	333
10.31	TFieldsEnumerator	333
10.31.1	Method overview	333

10.31.2 Property overview . . . . .	334
10.31.3 TFieldsEnumerator.Create . . . . .	334
10.31.4 TFieldsEnumerator.MoveNext . . . . .	334
10.31.5 TFieldsEnumerator.Current . . . . .	334
10.32 TFloatField . . . . .	334
10.32.1 Description . . . . .	334
10.32.2 Method overview . . . . .	334
10.32.3 Property overview . . . . .	334
10.32.4 TFloatField.Create . . . . .	335
10.32.5 TFloatField.CheckRange . . . . .	335
10.32.6 TFloatField.Value . . . . .	335
10.32.7 TFloatField.Currency . . . . .	335
10.32.8 TFloatField.MaxValue . . . . .	336
10.32.9 TFloatField.MinValue . . . . .	336
10.32.10 TFloatField.Precision . . . . .	336
10.33 TGraphicField . . . . .	337
10.33.1 Description . . . . .	337
10.33.2 Method overview . . . . .	337
10.33.3 TGraphicField.Create . . . . .	337
10.34 TGuidField . . . . .	337
10.34.1 Description . . . . .	337
10.34.2 Method overview . . . . .	337
10.34.3 Property overview . . . . .	337
10.34.4 TGuidField.Create . . . . .	338
10.34.5 TGuidField.AsGuid . . . . .	338
10.35 TIndexDef . . . . .	338
10.35.1 Description . . . . .	338
10.35.2 Method overview . . . . .	338
10.35.3 Property overview . . . . .	338
10.35.4 TIndexDef.Create . . . . .	339
10.35.5 TIndexDef.Destroy . . . . .	339
10.35.6 TIndexDef.Expression . . . . .	339
10.35.7 TIndexDef.Fields . . . . .	339
10.35.8 TIndexDef.CaseInsFields . . . . .	340
10.35.9 TIndexDef.DescFields . . . . .	340
10.35.10 TIndexDef.Options . . . . .	340
10.35.11 TIndexDef.Source . . . . .	341
10.36 TIndexDefs . . . . .	341
10.36.1 Description . . . . .	341
10.36.2 Method overview . . . . .	341

10.36.3 Property overview	341
10.36.4 TIndexDefs.Create	341
10.36.5 TIndexDefs.Destroy	342
10.36.6 TIndexDefs.Add	342
10.36.7 TIndexDefs.AddIndexDef	342
10.36.8 TIndexDefs.Find	342
10.36.9 TIndexDefs.FindIndexForFields	343
10.36.10 TIndexDefs.GetIndexForFields	343
10.36.11 TIndexDefs.Update	343
10.36.12 TIndexDefs.Items	343
10.37 TLargeintField	344
10.37.1 Description	344
10.37.2 Method overview	344
10.37.3 Property overview	344
10.37.4 TLargeintField.Create	344
10.37.5 TLargeintField.CheckRange	344
10.37.6 TLargeintField.Value	345
10.37.7 TLargeintField.MaxValue	345
10.37.8 TLargeintField.MinValue	345
10.38 TLongintField	346
10.38.1 Description	346
10.38.2 Method overview	346
10.38.3 Property overview	346
10.38.4 TLongintField.Create	346
10.38.5 TLongintField.CheckRange	346
10.38.6 TLongintField.Value	347
10.38.7 TLongintField.MaxValue	347
10.38.8 TLongintField.MinValue	347
10.39 TLookupList	347
10.39.1 Description	347
10.39.2 Method overview	348
10.39.3 TLookupList.Create	348
10.39.4 TLookupList.Destroy	348
10.39.5 TLookupList.Add	348
10.39.6 TLookupList.Clear	348
10.39.7 TLookupList.FirstKeyByValue	349
10.39.8 TLookupList.ValueOfKey	349
10.39.9 TLookupList.ValuesToStrings	349
10.40 TMasterDataLink	349
10.40.1 Description	349

10.40.2 Method overview	350
10.40.3 Property overview	350
10.40.4 TMasterDataLink.Create	350
10.40.5 TMasterDataLink.Destroy	350
10.40.6 TMasterDataLink.FieldNames	350
10.40.7 TMasterDataLink.Fields	351
10.40.8 TMasterDataLink.OnMasterChange	351
10.40.9 TMasterDataLink.OnMasterDisable	351
10.41 TMasterParamsDataLink	351
10.41.1 Description	351
10.41.2 Method overview	352
10.41.3 Property overview	352
10.41.4 TMasterParamsDataLink.Create	352
10.41.5 TMasterParamsDataLink.RefreshParamNames	352
10.41.6 TMasterParamsDataLink.CopyParamsFromMaster	352
10.41.7 TMasterParamsDataLink.Params	353
10.42 TMemoField	353
10.42.1 Description	353
10.42.2 Method overview	353
10.42.3 Property overview	353
10.42.4 TMemoField.Create	353
10.42.5 TMemoField.Transliterate	354
10.43 TNamedItem	354
10.43.1 Description	354
10.43.2 Property overview	354
10.43.3 TNamedItem.DisplayName	354
10.43.4 TNamedItem.Name	354
10.44 TNumericField	355
10.44.1 Description	355
10.44.2 Method overview	355
10.44.3 Property overview	355
10.44.4 TNumericField.Create	355
10.44.5 TNumericField.Alignment	355
10.44.6 TNumericField.DisplayFormat	356
10.44.7 TNumericField.EditFormat	356
10.45 TParam	356
10.45.1 Description	356
10.45.2 Method overview	357
10.45.3 Property overview	357
10.45.4 TParam.Create	357



10.45.5 TParam.Assign	358
10.45.6 TParam.AssignField	358
10.45.7 TParam.AssignToField	358
10.45.8 TParam.AssignFieldValue	359
10.45.9 TParam.AssignFromField	359
10.45.10 TParam.Clear	359
10.45.11 TParam.GetData	359
10.45.12 TParam.GetDataSize	360
10.45.13 TParam.LoadFromFile	360
10.45.14 TParam.LoadFromStream	360
10.45.15 TParam.SetBlobData	360
10.45.16 TParam.SetData	361
10.45.17 TParam.AsBlob	361
10.45.18 TParam.AsBoolean	361
10.45.19 TParam.AsCurrency	361
10.45.20 TParam.AsDate	362
10.45.21 TParam.AsDateTime	362
10.45.22 TParam.AsFloat	362
10.45.23 TParam.AsInteger	362
10.45.24 TParam.AsLargeInt	363
10.45.25 TParam.AsMemo	363
10.45.26 TParam.AsSmallInt	363
10.45.27 TParam.AsString	363
10.45.28 TParam.AsTime	364
10.45.29 TParam.AsWord	364
10.45.30 TParam.Bound	364
10.45.31 TParam.Dataset	364
10.45.32 TParam.IsNull	365
10.45.33 TParam.NativeStr	365
10.45.34 TParam.Text	365
10.45.35 TParam.Value	365
10.45.36 TParam.AsWideString	366
10.45.37 TParam.DataType	366
10.45.38 TParam.Name	366
10.45.39 TParam.NumericScale	366
10.45.40 TParam.ParamType	367
10.45.41 TParam.Precision	367
10.45.42 TParam.Size	367
10.46 TParams	368
10.46.1 Description	368

10.46.2 Method overview . . . . .	368
10.46.3 Property overview . . . . .	368
10.46.4 TParams.Create . . . . .	368
10.46.5 TParams.AddParam . . . . .	369
10.46.6 TParams.AssignValues . . . . .	369
10.46.7 TParams.CreateParam . . . . .	369
10.46.8 TParams.FindParam . . . . .	369
10.46.9 TParams.GetParamList . . . . .	370
10.46.10 TParams.IsEqual . . . . .	370
10.46.11 TParams.ParamByName . . . . .	370
10.46.12 TParams.ParseSQL . . . . .	370
10.46.13 TParams.RemoveParam . . . . .	371
10.46.14 TParams.CopyParamValuesFromDataset . . . . .	371
10.46.15 TParams.Dataset . . . . .	372
10.46.16 TParams.Items . . . . .	372
10.46.17 TParams.ParamValues . . . . .	372
10.47 TSmallintField . . . . .	373
10.47.1 Description . . . . .	373
10.47.2 Method overview . . . . .	373
10.47.3 TSmallintField.Create . . . . .	373
10.48 TStringField . . . . .	373
10.48.1 Description . . . . .	373
10.48.2 Method overview . . . . .	373
10.48.3 Property overview . . . . .	373
10.48.4 TStringField.Create . . . . .	374
10.48.5 TStringField.SetFieldType . . . . .	374
10.48.6 TStringField.FixedChar . . . . .	374
10.48.7 TStringField.Transliterate . . . . .	374
10.48.8 TStringField.Value . . . . .	374
10.48.9 TStringField.Size . . . . .	375
10.49 TTimeField . . . . .	375
10.49.1 Description . . . . .	375
10.49.2 Method overview . . . . .	375
10.49.3 TTimeField.Create . . . . .	375
10.50 TVarBytesField . . . . .	375
10.50.1 Description . . . . .	375
10.50.2 Method overview . . . . .	376
10.50.3 TVarBytesField.Create . . . . .	376
10.51 TVariantField . . . . .	376
10.51.1 Description . . . . .	376

10.51.2 Method overview . . . . .	376
10.51.3 TVariantField.Create . . . . .	376
10.52 TWideMemoField . . . . .	377
10.52.1 Description . . . . .	377
10.52.2 Method overview . . . . .	377
10.52.3 Property overview . . . . .	377
10.52.4 TWideMemoField.Create . . . . .	377
10.52.5 TWideMemoField.Value . . . . .	377
10.53 TWideStringField . . . . .	378
10.53.1 Description . . . . .	378
10.53.2 Method overview . . . . .	378
10.53.3 Property overview . . . . .	378
10.53.4 TWideStringField.Create . . . . .	378
10.53.5 TWideStringField.Value . . . . .	378
10.54 TWordField . . . . .	378
10.54.1 Description . . . . .	378
10.54.2 Method overview . . . . .	379
10.54.3 TWordField.Create . . . . .	379
<b>11 Reference for unit 'dbugintf'</b>	<b>384</b>
11.1 Overview . . . . .	384
11.2 Writing a debug server . . . . .	384
11.3 Constants, types and variables . . . . .	384
11.3.1 Resource strings . . . . .	384
11.3.2 Constants . . . . .	385
11.3.3 Types . . . . .	385
11.4 Procedures and functions . . . . .	385
11.4.1 GetDebuggingEnabled . . . . .	385
11.4.2 InitDebugClient . . . . .	386
11.4.3 SendBoolean . . . . .	386
11.4.4 SendDateTime . . . . .	386
11.4.5 SendDebug . . . . .	386
11.4.6 SendDebugEx . . . . .	387
11.4.7 SendDebugFmt . . . . .	387
11.4.8 SendDebugFmtEx . . . . .	387
11.4.9 SendInteger . . . . .	388
11.4.10 SendMethodEnter . . . . .	388
11.4.11 SendMethodExit . . . . .	388
11.4.12 SendPointer . . . . .	389
11.4.13 SendSeparator . . . . .	389

11.4.14 SetDebuggingEnabled . . . . .	389
11.4.15 StartDebugServer . . . . .	389
<b>12 Reference for unit 'dbugmsg' . . . . .</b>	<b>391</b>
12.1 Used units . . . . .	391
12.2 Overview . . . . .	391
12.3 Constants, types and variables . . . . .	391
12.3.1 Constants . . . . .	391
12.3.2 Types . . . . .	392
12.4 Procedures and functions . . . . .	392
12.4.1 DebugMessageName . . . . .	392
12.4.2 ReadDebugMessageFromStream . . . . .	392
12.4.3 WriteDebugMessageToStream . . . . .	393
<b>13 Reference for unit 'eventlog' . . . . .</b>	<b>394</b>
13.1 Used units . . . . .	394
13.2 Overview . . . . .	394
13.3 Constants, types and variables . . . . .	394
13.3.1 Resource strings . . . . .	394
13.3.2 Types . . . . .	395
13.4 ELogError . . . . .	395
13.4.1 Description . . . . .	395
13.5 TEventLog . . . . .	395
13.5.1 Description . . . . .	395
13.5.2 Method overview . . . . .	396
13.5.3 Property overview . . . . .	396
13.5.4 TEventLog.Destroy . . . . .	396
13.5.5 TEventLog.EventTypeToString . . . . .	396
13.5.6 TEventLog.RegisterMessageFile . . . . .	397
13.5.7 TEventLog.Log . . . . .	398
13.5.8 TEventLog.Warning . . . . .	398
13.5.9 TEventLog.Error . . . . .	398
13.5.10 TEventLog.Debug . . . . .	399
13.5.11 TEventLog.Info . . . . .	399
13.5.12 TEventLog.Identification . . . . .	399
13.5.13 TEventLog.LogType . . . . .	399
13.5.14 TEventLog.Active . . . . .	400
13.5.15 TEventLog.RaiseExceptionOnError . . . . .	400
13.5.16 TEventLog.DefaultEventType . . . . .	400
13.5.17 TEventLog.FileName . . . . .	400
13.5.18 TEventLog.TimeStampFormat . . . . .	401

13.5.19 TEventLog.CustomLogType . . . . .	401
13.5.20 TEventLog.EventIDOffset . . . . .	401
13.5.21 TEventLog.OnGetCustomCategory . . . . .	402
13.5.22 TEventLog.OnGetCustomEventID . . . . .	402
13.5.23 TEventLog.OnGetCustomEvent . . . . .	402
<b>14 Reference for unit 'ezcgi' . . . . .</b>	<b>403</b>
14.1 Used units . . . . .	403
14.2 Overview . . . . .	403
14.3 Constants, types and variables . . . . .	403
14.3.1 Constants . . . . .	403
14.4 ECGIException . . . . .	403
14.4.1 Description . . . . .	403
14.5 TEZcgi . . . . .	404
14.5.1 Description . . . . .	404
14.5.2 Method overview . . . . .	404
14.5.3 Property overview . . . . .	404
14.5.4 TEZcgi.Create . . . . .	404
14.5.5 TEZcgi.Destroy . . . . .	404
14.5.6 TEZcgi.Run . . . . .	405
14.5.7 TEZcgi.WriteContent . . . . .	405
14.5.8 TEZcgi.PutLine . . . . .	405
14.5.9 TEZcgi.GetValue . . . . .	406
14.5.10 TEZcgi.DoPost . . . . .	406
14.5.11 TEZcgi.DoGet . . . . .	406
14.5.12 TEZcgi.Values . . . . .	406
14.5.13 TEZcgi.Names . . . . .	407
14.5.14 TEZcgi.Variables . . . . .	407
14.5.15 TEZcgi.VariableCount . . . . .	408
14.5.16 TEZcgi.Name . . . . .	408
14.5.17 TEZcgi.Email . . . . .	408
<b>15 Reference for unit 'fpTimer' . . . . .</b>	<b>409</b>
15.1 Used units . . . . .	409
15.2 Overview . . . . .	409
15.3 Constants, types and variables . . . . .	409
15.3.1 Types . . . . .	409
15.3.2 Variables . . . . .	409
15.4 TFPCustomTimer . . . . .	410
15.4.1 Description . . . . .	410
15.4.2 Method overview . . . . .	410

15.4.3	TFPCustomTimer.Create	410
15.4.4	TFPCustomTimer.Destroy	410
15.4.5	TFPCustomTimer.StartTimer	411
15.4.6	TFPCustomTimer.StopTimer	411
15.5	TFPTimer	411
15.5.1	Description	411
15.5.2	Property overview	411
15.5.3	TFPTimer.Enabled	411
15.5.4	TFPTimer.Interval	412
15.5.5	TFPTimer.OnTimer	412
15.6	TFPTimerDriver	412
15.6.1	Description	412
15.6.2	Method overview	412
15.6.3	Property overview	412
15.6.4	TFPTimerDriver.Create	413
15.6.5	TFPTimerDriver.StartTimer	413
15.6.6	TFPTimerDriver.StopTimer	413
15.6.7	TFPTimerDriver.Timer	413
<b>16</b>	<b>Reference for unit 'gettext'</b>	<b>414</b>
16.1	Used units	414
16.2	Overview	414
16.3	Constants, types and variables	414
16.3.1	Constants	414
16.3.2	Types	414
16.4	Procedures and functions	415
16.4.1	GetLanguageIDs	415
16.4.2	TranslateResourceStrings	416
16.4.3	TranslateUnitResourceStrings	416
16.5	EMOFileError	416
16.5.1	Description	416
16.6	TMOFile	416
16.6.1	Description	416
16.6.2	Method overview	417
16.6.3	TMOFile.Create	417
16.6.4	TMOFile.Destroy	417
16.6.5	TMOFile.Translate	417
<b>17</b>	<b>Reference for unit 'idea'</b>	<b>418</b>
17.1	Used units	418
17.2	Overview	418

17.3	Constants, types and variables	418
17.3.1	Constants	418
17.3.2	Types	419
17.4	Procedures and functions	419
17.4.1	CipherIdea	419
17.4.2	DeKeyIdea	419
17.4.3	EnKeyIdea	420
17.5	EIDEAError	420
17.5.1	Description	420
17.6	TIDEADeCryptStream	420
17.6.1	Description	420
17.6.2	Method overview	420
17.6.3	TIDEADeCryptStream.Create	420
17.6.4	TIDEADeCryptStream.Read	421
17.6.5	TIDEADeCryptStream.Seek	421
17.7	TIDEAEncryptStream	421
17.7.1	Description	421
17.7.2	Method overview	422
17.7.3	TIDEAEncryptStream.Create	422
17.7.4	TIDEAEncryptStream.Destroy	422
17.7.5	TIDEAEncryptStream.Write	422
17.7.6	TIDEAEncryptStream.Seek	423
17.7.7	TIDEAEncryptStream.Flush	423
17.8	TIDEAStream	423
17.8.1	Description	423
17.8.2	Method overview	423
17.8.3	Property overview	423
17.8.4	TIDEAStream.Create	424
17.8.5	TIDEAStream.Key	424
<b>18</b>	<b>Reference for unit 'inicol'</b>	<b>425</b>
18.1	Used units	425
18.2	Overview	425
18.3	Constants, types and variables	425
18.3.1	Constants	425
18.4	EIniCol	426
18.4.1	Description	426
18.5	TIniCollection	426
18.5.1	Description	426
18.5.2	Method overview	426

18.5.3	Property overview	426
18.5.4	TIniCollection.Load	426
18.5.5	TIniCollection.Save	427
18.5.6	TIniCollection.SaveToIni	427
18.5.7	TIniCollection.SaveToFile	427
18.5.8	TIniCollection.LoadFromIni	428
18.5.9	TIniCollection.LoadFromFile	428
18.5.10	TIniCollection.Prefix	428
18.5.11	TIniCollection.SectionPrefix	429
18.5.12	TIniCollection.FileName	429
18.5.13	TIniCollection.GlobalSection	429
18.6	TIniCollectionItem	429
18.6.1	Description	429
18.6.2	Method overview	430
18.6.3	Property overview	430
18.6.4	TIniCollectionItem.SaveToIni	430
18.6.5	TIniCollectionItem.LoadFromIni	430
18.6.6	TIniCollectionItem.SaveToFile	430
18.6.7	TIniCollectionItem.LoadFromFile	431
18.6.8	TIniCollectionItem.SectionName	431
18.7	TNamedIniCollection	431
18.7.1	Description	431
18.7.2	Method overview	431
18.7.3	Property overview	432
18.7.4	TNamedIniCollection.IndexOfUserData	432
18.7.5	TNamedIniCollection.IndexOfName	432
18.7.6	TNamedIniCollection.FindByName	432
18.7.7	TNamedIniCollection.FindByUserData	433
18.7.8	TNamedIniCollection.NamedItems	433
18.8	TNamedIniCollectionItem	433
18.8.1	Description	433
18.8.2	Property overview	433
18.8.3	TNamedIniCollectionItem.UserData	433
18.8.4	TNamedIniCollectionItem.Name	434
<b>19</b>	<b>Reference for unit 'IniFiles'</b>	<b>435</b>
19.1	Used units	435
19.2	Overview	435
19.3	TCustomIniFile	435
19.3.1	Description	435



---

19.3.2	Method overview	436
19.3.3	Property overview	436
19.3.4	TCustomIniFile.Create	436
19.3.5	TCustomIniFile.Destroy	437
19.3.6	TCustomIniFile.SectionExists	437
19.3.7	TCustomIniFile.ReadString	437
19.3.8	TCustomIniFile.WriteString	438
19.3.9	TCustomIniFile.ReadInteger	438
19.3.10	TCustomIniFile.WriteInteger	438
19.3.11	TCustomIniFile.ReadBool	438
19.3.12	TCustomIniFile.WriteBool	439
19.3.13	TCustomIniFile.ReadDate	439
19.3.14	TCustomIniFile.ReadDateTime	439
19.3.15	TCustomIniFile.ReadFloat	440
19.3.16	TCustomIniFile.ReadTime	440
19.3.17	TCustomIniFile.ReadBinaryStream	440
19.3.18	TCustomIniFile.WriteDate	441
19.3.19	TCustomIniFile.WriteDateTime	441
19.3.20	TCustomIniFile.WriteFloat	441
19.3.21	TCustomIniFile.WriteTime	442
19.3.22	TCustomIniFile.WriteBinaryStream	442
19.3.23	TCustomIniFile.ReadSection	442
19.3.24	TCustomIniFile.ReadSections	443
19.3.25	TCustomIniFile.ReadSectionValues	443
19.3.26	TCustomIniFile.EraseSection	443
19.3.27	TCustomIniFile.DeleteKey	443
19.3.28	TCustomIniFile.UpdateFile	444
19.3.29	TCustomIniFile.ValueExists	444
19.3.30	TCustomIniFile.FileName	444
19.3.31	TCustomIniFile.EscapeLineFeeds	445
19.3.32	TCustomIniFile.CaseSensitive	445
19.3.33	TCustomIniFile.StripQuotes	445
19.4	THashedStringList	445
19.4.1	Description	445
19.4.2	Method overview	446
19.4.3	THashedStringList.Create	446
19.4.4	THashedStringList.Destroy	446
19.4.5	THashedStringList.IndexOf	446
19.4.6	THashedStringList.IndexOfName	446
19.5	TIniFile	447

19.5.1	Description	447
19.5.2	Method overview	447
19.5.3	Property overview	447
19.5.4	TIniFile.Create	447
19.5.5	TIniFile.Destroy	447
19.5.6	TIniFile.ReadString	448
19.5.7	TIniFile.WriteString	448
19.5.8	TIniFile.ReadSection	448
19.5.9	TIniFile.ReadSectionRaw	448
19.5.10	TIniFile.ReadSections	449
19.5.11	TIniFile.ReadSectionValues	449
19.5.12	TIniFile.EraseSection	449
19.5.13	TIniFile.DeleteKey	449
19.5.14	TIniFile.UpdateFile	450
19.5.15	TIniFile.Stream	450
19.5.16	TIniFile.CacheUpdates	450
19.6	TIniFileKey	451
19.6.1	Description	451
19.6.2	Method overview	451
19.6.3	Property overview	451
19.6.4	TIniFileKey.Create	451
19.6.5	TIniFileKey.Ident	451
19.6.6	TIniFileKey.Value	451
19.7	TIniFileKeyList	452
19.7.1	Description	452
19.7.2	Method overview	452
19.7.3	Property overview	452
19.7.4	TIniFileKeyList.Destroy	452
19.7.5	TIniFileKeyList.Clear	452
19.7.6	TIniFileKeyList.Items	452
19.8	TIniFileSection	453
19.8.1	Description	453
19.8.2	Method overview	453
19.8.3	Property overview	453
19.8.4	TIniFileSection.Empty	453
19.8.5	TIniFileSection.Create	453
19.8.6	TIniFileSection.Destroy	453
19.8.7	TIniFileSection.Name	454
19.8.8	TIniFileSection.KeyList	454
19.9	TIniFileSectionList	454

19.9.1 Description . . . . .	454
19.9.2 Method overview . . . . .	454
19.9.3 Property overview . . . . .	454
19.9.4 TIniFileSectionList.Destroy . . . . .	455
19.9.5 TIniFileSectionList.Clear . . . . .	455
19.9.6 TIniFileSectionList.Items . . . . .	455
19.10 TMemIniFile . . . . .	455
19.10.1 Description . . . . .	455
19.10.2 Method overview . . . . .	455
19.10.3 TMemIniFile.Create . . . . .	456
19.10.4 TMemIniFile.Clear . . . . .	456
19.10.5 TMemIniFile.GetStrings . . . . .	456
19.10.6 TMemIniFile.Rename . . . . .	456
19.10.7 TMemIniFile.SetStrings . . . . .	457
<b>20 Reference for unit 'iostream'</b>	<b>458</b>
20.1 Used units . . . . .	458
20.2 Overview . . . . .	458
20.3 Constants, types and variables . . . . .	458
20.3.1 Types . . . . .	458
20.4 EIOStreamError . . . . .	459
20.4.1 Description . . . . .	459
20.5 TIOStream . . . . .	459
20.5.1 Description . . . . .	459
20.5.2 Method overview . . . . .	459
20.5.3 TIOStream.Create . . . . .	459
20.5.4 TIOStream.Read . . . . .	459
20.5.5 TIOStream.Write . . . . .	460
20.5.6 TIOStream.SetSize . . . . .	460
20.5.7 TIOStream.Seek . . . . .	460
<b>21 Reference for unit 'libtar'</b>	<b>461</b>
21.1 Used units . . . . .	461
21.2 Overview . . . . .	461
21.3 Constants, types and variables . . . . .	461
21.3.1 Constants . . . . .	461
21.3.2 Types . . . . .	462
21.4 Procedures and functions . . . . .	464
21.4.1 ClearDirRec . . . . .	464
21.4.2 ConvertFilename . . . . .	464
21.4.3 FileTimeGMT . . . . .	464

21.4.4	PermissionString	464
21.5	TTarArchive	465
21.5.1	Description	465
21.5.2	Method overview	465
21.5.3	TTarArchive.Create	465
21.5.4	TTarArchive.Destroy	465
21.5.5	TTarArchive.Reset	465
21.5.6	TTarArchive.FindNext	466
21.5.7	TTarArchive.ReadFile	466
21.5.8	TTarArchive.GetFilePos	466
21.5.9	TTarArchive.SetFilePos	467
21.6	TTarWriter	467
21.6.1	Description	467
21.6.2	Method overview	467
21.6.3	Property overview	467
21.6.4	TTarWriter.Create	467
21.6.5	TTarWriter.Destroy	468
21.6.6	TTarWriter.AddFile	468
21.6.7	TTarWriter.AddStream	468
21.6.8	TTarWriter.AddString	469
21.6.9	TTarWriter.AddDir	469
21.6.10	TTarWriter.AddSymbolicLink	469
21.6.11	TTarWriter.AddLink	470
21.6.12	TTarWriter.AddVolumeHeader	470
21.6.13	TTarWriter.Finalize	470
21.6.14	TTarWriter.Permissions	470
21.6.15	TTarWriter.UID	471
21.6.16	TTarWriter.GID	471
21.6.17	TTarWriter.UserName	471
21.6.18	TTarWriter.GroupName	471
21.6.19	TTarWriter.Mode	472
21.6.20	TTarWriter.Magic	472
<b>22</b>	<b>Reference for unit 'Pipes'</b>	<b>473</b>
22.1	Used units	473
22.2	Overview	473
22.3	Constants, types and variables	473
22.3.1	Constants	473
22.4	Procedures and functions	473
22.4.1	CreatePipeHandles	473

22.4.2	CreatePipeStreams	474
22.5	EPipeCreation	474
22.5.1	Description	474
22.6	EPipeError	474
22.6.1	Description	474
22.7	EPipeSeek	474
22.7.1	Description	474
22.8	TInputPipeStream	474
22.8.1	Description	474
22.8.2	Method overview	475
22.8.3	Property overview	475
22.8.4	TInputPipeStream.Write	475
22.8.5	TInputPipeStream.Seek	475
22.8.6	TInputPipeStream.Read	476
22.8.7	TInputPipeStream.NumBytesAvailable	476
22.9	TOutputPipeStream	476
22.9.1	Description	476
22.9.2	Method overview	476
22.9.3	TOutputPipeStream.Seek	476
22.9.4	TOutputPipeStream.Read	477
<b>23</b>	<b>Reference for unit 'pooledmm'</b>	<b>478</b>
23.1	Used units	478
23.2	Overview	478
23.3	Constants, types and variables	478
23.3.1	Types	478
23.4	TNonFreePooledMemManager	479
23.4.1	Description	479
23.4.2	Method overview	479
23.4.3	Property overview	479
23.4.4	TNonFreePooledMemManager.Clear	479
23.4.5	TNonFreePooledMemManager.Create	479
23.4.6	TNonFreePooledMemManager.Destroy	480
23.4.7	TNonFreePooledMemManager.NewItem	480
23.4.8	TNonFreePooledMemManager.EnumerateItems	480
23.4.9	TNonFreePooledMemManager.ItemSize	480
23.5	TPooledMemManager	481
23.5.1	Description	481
23.5.2	Method overview	481
23.5.3	Property overview	481

23.5.4	<a href="#">TPooledMemManager.Clear</a>	481
23.5.5	<a href="#">TPooledMemManager.Create</a>	481
23.5.6	<a href="#">TPooledMemManager.Destroy</a>	481
23.5.7	<a href="#">TPooledMemManager.MinimumFreeCount</a>	482
23.5.8	<a href="#">TPooledMemManager.MaximumFreeCountRatio</a>	482
23.5.9	<a href="#">TPooledMemManager.Count</a>	482
23.5.10	<a href="#">TPooledMemManager.FreeCount</a>	483
23.5.11	<a href="#">TPooledMemManager.AllocatedCount</a>	483
23.5.12	<a href="#">TPooledMemManager.FreedCount</a>	483
<b>24</b>	<b>Reference for unit 'process'</b>	<b>484</b>
24.1	<a href="#">Used units</a>	484
24.2	<a href="#">Overview</a>	484
24.3	<a href="#">Constants, types and variables</a>	484
24.3.1	<a href="#">Types</a>	484
24.4	<a href="#">EProcess</a>	486
24.4.1	<a href="#">Description</a>	486
24.5	<a href="#">TProcess</a>	486
24.5.1	<a href="#">Description</a>	486
24.5.2	<a href="#">Method overview</a>	487
24.5.3	<a href="#">Property overview</a>	487
24.5.4	<a href="#">TProcess.Create</a>	488
24.5.5	<a href="#">TProcess.Destroy</a>	488
24.5.6	<a href="#">TProcess.Execute</a>	488
24.5.7	<a href="#">TProcess.CloseInput</a>	489
24.5.8	<a href="#">TProcess.CloseOutput</a>	489
24.5.9	<a href="#">TProcess.CloseStderr</a>	489
24.5.10	<a href="#">TProcess.Resume</a>	489
24.5.11	<a href="#">TProcess.Suspend</a>	490
24.5.12	<a href="#">TProcess.Terminate</a>	490
24.5.13	<a href="#">TProcess.WaitOnExit</a>	490
24.5.14	<a href="#">TProcess.WindowRect</a>	491
24.5.15	<a href="#">TProcess.Handle</a>	491
24.5.16	<a href="#">TProcess.ProcessHandle</a>	491
24.5.17	<a href="#">TProcess.ThreadHandle</a>	491
24.5.18	<a href="#">TProcess.ProcessID</a>	492
24.5.19	<a href="#">TProcess.ThreadID</a>	492
24.5.20	<a href="#">TProcess.Input</a>	492
24.5.21	<a href="#">TProcess.Output</a>	493
24.5.22	<a href="#">TProcess.Stderr</a>	493

24.5.23 TProcess.ExitStatus . . . . .	493
24.5.24 TProcess.InheritHandles . . . . .	494
24.5.25 TProcess.Active . . . . .	494
24.5.26 TProcess.ApplicationName . . . . .	494
24.5.27 TProcess.CommandLine . . . . .	494
24.5.28 TProcess.ConsoleTitle . . . . .	495
24.5.29 TProcess.CurrentDirectory . . . . .	495
24.5.30 TProcess.Desktop . . . . .	495
24.5.31 TProcess.Environment . . . . .	496
24.5.32 TProcess.Options . . . . .	496
24.5.33 TProcess.Priority . . . . .	497
24.5.34 TProcess.StartupOptions . . . . .	497
24.5.35 TProcess.Running . . . . .	498
24.5.36 TProcess.ShowWindow . . . . .	498
24.5.37 TProcess.WindowColumns . . . . .	499
24.5.38 TProcess.WindowHeight . . . . .	499
24.5.39 TProcess.WindowLeft . . . . .	499
24.5.40 TProcess.WindowRows . . . . .	500
24.5.41 TProcess.WindowTop . . . . .	500
24.5.42 TProcess.WindowWidth . . . . .	500
24.5.43 TProcess.FillAttribute . . . . .	501
<b>25 Reference for unit 'rttiutils'</b>	<b>502</b>
25.1 Used units . . . . .	502
25.2 Overview . . . . .	502
25.3 Constants, types and variables . . . . .	502
25.3.1 Constants . . . . .	502
25.3.2 Types . . . . .	502
25.3.3 Variables . . . . .	503
25.4 Procedures and functions . . . . .	503
25.4.1 CreateStoredItem . . . . .	503
25.4.2 ParseStoredItem . . . . .	504
25.4.3 UpdateStoredList . . . . .	504
25.5 TPropInfoList . . . . .	504
25.5.1 Description . . . . .	504
25.5.2 Method overview . . . . .	504
25.5.3 Property overview . . . . .	505
25.5.4 TPropInfoList.Create . . . . .	505
25.5.5 TPropInfoList.Destroy . . . . .	505
25.5.6 TPropInfoList.Contains . . . . .	505

25.5.7	TPropInfoList.Find	505
25.5.8	TPropInfoList.Delete	506
25.5.9	TPropInfoList.Intersect	506
25.5.10	TPropInfoList.Count	506
25.5.11	TPropInfoList.Items	506
25.6	TPropsStorage	507
25.6.1	Description	507
25.6.2	Method overview	507
25.6.3	Property overview	507
25.6.4	TPropsStorage.StoreAnyProperty	507
25.6.5	TPropsStorage.LoadAnyProperty	507
25.6.6	TPropsStorage.StoreProperties	508
25.6.7	TPropsStorage.LoadProperties	508
25.6.8	TPropsStorage.LoadObjectsProps	508
25.6.9	TPropsStorage.StoreObjectsProps	509
25.6.10	TPropsStorage.AObject	510
25.6.11	TPropsStorage.Prefix	510
25.6.12	TPropsStorage.Section	510
25.6.13	TPropsStorage.OnReadString	510
25.6.14	TPropsStorage.OnWriteString	511
25.6.15	TPropsStorage.OnEraseSection	511
<b>26</b>	<b>Reference for unit 'simpleipc'</b>	<b>512</b>
26.1	Used units	512
26.2	Overview	512
26.3	Constants, types and variables	512
26.3.1	Resource strings	512
26.3.2	Constants	513
26.3.3	Types	513
26.3.4	Variables	513
26.4	EIPCErrors	514
26.4.1	Description	514
26.5	TIPCClientComm	514
26.5.1	Description	514
26.5.2	Method overview	514
26.5.3	Property overview	514
26.5.4	TIPCClientComm.Create	514
26.5.5	TIPCClientComm.Connect	514
26.5.6	TIPCClientComm.Disconnect	515
26.5.7	TIPCClientComm.ServerRunning	515



26.5.8	TIPCClientComm.SendMessage	515
26.5.9	TIPCClientComm.Owner	516
26.6	TIPCServerComm	516
26.6.1	Description	516
26.6.2	Method overview	516
26.6.3	Property overview	516
26.6.4	TIPCServerComm.Create	516
26.6.5	TIPCServerComm.StartServer	517
26.6.6	TIPCServerComm.StopServer	517
26.6.7	TIPCServerComm.PeekMessage	517
26.6.8	TIPCServerComm.ReadMessage	518
26.6.9	TIPCServerComm.Owner	518
26.6.10	TIPCServerComm.InstanceID	518
26.7	TSimpleIPC	518
26.7.1	Description	518
26.7.2	Property overview	518
26.7.3	TSimpleIPC.Active	519
26.7.4	TSimpleIPC.ServerID	519
26.8	TSimpleIPCClient	519
26.8.1	Description	519
26.8.2	Method overview	519
26.8.3	Property overview	520
26.8.4	TSimpleIPCClient.Create	520
26.8.5	TSimpleIPCClient.Destroy	520
26.8.6	TSimpleIPCClient.Connect	520
26.8.7	TSimpleIPCClient.Disconnect	521
26.8.8	TSimpleIPCClient.ServerRunning	521
26.8.9	TSimpleIPCClient.SendMessage	521
26.8.10	TSimpleIPCClient.SendStringMessage	521
26.8.11	TSimpleIPCClient.SendStringMessageFmt	522
26.8.12	TSimpleIPCClient.ServerInstance	522
26.9	TSimpleIPCServer	522
26.9.1	Description	522
26.9.2	Method overview	523
26.9.3	Property overview	523
26.9.4	TSimpleIPCServer.Create	523
26.9.5	TSimpleIPCServer.Destroy	523
26.9.6	TSimpleIPCServer.StartServer	523
26.9.7	TSimpleIPCServer.StopServer	524
26.9.8	TSimpleIPCServer.PeekMessage	524

26.9.9	TSimpleIPCServer.GetMessageData	524
26.9.10	TSimpleIPCServer.StringMessage	525
26.9.11	TSimpleIPCServer.MsgType	525
26.9.12	TSimpleIPCServer.MsgData	525
26.9.13	TSimpleIPCServer.InstanceID	525
26.9.14	TSimpleIPCServer.Global	526
26.9.15	TSimpleIPCServer.OnMessage	526
<b>27</b>	<b>Reference for unit 'streamcoll'</b>	<b>527</b>
27.1	Used units	527
27.2	Overview	527
27.3	Procedures and functions	527
27.3.1	ColReadBoolean	527
27.3.2	ColReadCurrency	528
27.3.3	ColReadDateTime	528
27.3.4	ColReadFloat	528
27.3.5	ColReadInteger	528
27.3.6	ColReadString	529
27.3.7	ColWriteBoolean	529
27.3.8	ColWriteCurrency	529
27.3.9	ColWriteDateTime	529
27.3.10	ColWriteFloat	530
27.3.11	ColWriteInteger	530
27.3.12	ColWriteString	530
27.4	EStreamColl	530
27.4.1	Description	530
27.5	TStreamCollection	530
27.5.1	Description	530
27.5.2	Method overview	531
27.5.3	Property overview	531
27.5.4	TStreamCollection.LoadFromStream	531
27.5.5	TStreamCollection.SaveToStream	531
27.5.6	TStreamCollection.Streaming	531
27.6	TStreamCollectionItem	532
27.6.1	Description	532
<b>28</b>	<b>Reference for unit 'streamex'</b>	<b>533</b>
28.1	Used units	533
28.2	Overview	533
28.3	TBidirBinaryObjectReader	533
28.3.1	Description	533

28.3.2	Property overview	533
28.3.3	TBidirBinaryObjectReader.Position	533
28.4	TBidirBinaryObjectWriter	534
28.4.1	Description	534
28.4.2	Property overview	534
28.4.3	TBidirBinaryObjectWriter.Position	534
28.5	TDelphiReader	534
28.5.1	Description	534
28.5.2	Method overview	534
28.5.3	Property overview	534
28.5.4	TDelphiReader.GetDriver	535
28.5.5	TDelphiReader.ReadStr	535
28.5.6	TDelphiReader.Read	535
28.5.7	TDelphiReader.Position	535
28.6	TDelphiWriter	535
28.6.1	Description	535
28.6.2	Method overview	536
28.6.3	Property overview	536
28.6.4	TDelphiWriter.GetDriver	536
28.6.5	TDelphiWriter.FlushBuffer	536
28.6.6	TDelphiWriter.Write	536
28.6.7	TDelphiWriter.WriteStr	536
28.6.8	TDelphiWriter.WriteValue	537
28.6.9	TDelphiWriter.Position	537
<b>29</b>	<b>Reference for unit 'StreamIO'</b>	<b>538</b>
29.1	Used units	538
29.2	Overview	538
29.3	Procedures and functions	538
29.3.1	AssignStream	538
29.3.2	GetStream	539
<b>30</b>	<b>Reference for unit 'syncobjs'</b>	<b>540</b>
30.1	Used units	540
30.2	Overview	540
30.3	Constants, types and variables	540
30.3.1	Constants	540
30.3.2	Types	540
30.4	TCriticalSection	541
30.4.1	Description	541
30.4.2	Method overview	541

30.4.3	TCriticalSection.Acquire . . . . .	542
30.4.4	TCriticalSection.Release . . . . .	542
30.4.5	TCriticalSection.Enter . . . . .	542
30.4.6	TCriticalSection.TryEnter . . . . .	542
30.4.7	TCriticalSection.Leave . . . . .	543
30.4.8	TCriticalSection.Create . . . . .	543
30.4.9	TCriticalSection.Destroy . . . . .	543
30.5	TEventObject . . . . .	543
30.5.1	Description . . . . .	543
30.5.2	Method overview . . . . .	544
30.5.3	Property overview . . . . .	544
30.5.4	TEventObject.Create . . . . .	544
30.5.5	TEventObject.destroy . . . . .	544
30.5.6	TEventObject.ResetEvent . . . . .	544
30.5.7	TEventObject.SetEvent . . . . .	545
30.5.8	TEventObject.WaitFor . . . . .	545
30.5.9	TEventObject.ManualReset . . . . .	545
30.6	THandleObject . . . . .	545
30.6.1	Description . . . . .	545
30.6.2	Method overview . . . . .	545
30.6.3	Property overview . . . . .	546
30.6.4	THandleObject.destroy . . . . .	546
30.6.5	THandleObject.Handle . . . . .	546
30.6.6	THandleObject.LastError . . . . .	546
30.7	TSimpleEvent . . . . .	546
30.7.1	Description . . . . .	546
30.7.2	Method overview . . . . .	546
30.7.3	TSimpleEvent.Create . . . . .	547
30.8	TSynchroObject . . . . .	547
30.8.1	Description . . . . .	547
30.8.2	Method overview . . . . .	547
30.8.3	TSynchroObject.Acquire . . . . .	547
30.8.4	TSynchroObject.Release . . . . .	547
<b>31</b>	<b>Reference for unit 'URIParser'</b>	<b>548</b>
31.1	Overview . . . . .	548
31.2	Constants, types and variables . . . . .	548
31.2.1	Types . . . . .	548
31.3	Procedures and functions . . . . .	548
31.3.1	EncodeURI . . . . .	548

31.3.2	FilenameToURI . . . . .	549
31.3.3	IsAbsoluteURI . . . . .	549
31.3.4	ParseURI . . . . .	549
31.3.5	ResolveRelativeURI . . . . .	550
31.3.6	URIToFilename . . . . .	550
<b>32</b>	<b>Reference for unit 'zstream'</b>	<b>551</b>
32.1	Used units . . . . .	551
32.2	Overview . . . . .	551
32.3	Constants, types and variables . . . . .	551
32.3.1	Types . . . . .	551
32.4	Ecompressionerror . . . . .	552
32.4.1	Description . . . . .	552
32.5	Edecompressionerror . . . . .	552
32.5.1	Description . . . . .	552
32.6	Egzfileerror . . . . .	552
32.6.1	Description . . . . .	552
32.7	Ezliberror . . . . .	552
32.7.1	Description . . . . .	552
32.8	Tcompressionstream . . . . .	552
32.8.1	Description . . . . .	552
32.8.2	Method overview . . . . .	553
32.8.3	Tcompressionstream.create . . . . .	553
32.8.4	Tcompressionstream.destroy . . . . .	553
32.8.5	Tcompressionstream.write . . . . .	553
32.8.6	Tcompressionstream.flush . . . . .	554
32.8.7	Tcompressionstream.get_compressionrate . . . . .	554
32.9	Tcustomzlibstream . . . . .	554
32.9.1	Description . . . . .	554
32.9.2	Method overview . . . . .	554
32.9.3	Tcustomzlibstream.create . . . . .	554
32.9.4	Tcustomzlibstream.destroy . . . . .	555
32.10	Tdecompressionstream . . . . .	555
32.10.1	Description . . . . .	555
32.10.2	Method overview . . . . .	555
32.10.3	Tdecompressionstream.create . . . . .	555
32.10.4	Tdecompressionstream.destroy . . . . .	555
32.10.5	Tdecompressionstream.read . . . . .	556
32.10.6	Tdecompressionstream.seek . . . . .	556
32.10.7	Tdecompressionstream.get_compressionrate . . . . .	557

32.11 TGZFileStream . . . . .	557
32.11.1 Description . . . . .	557
32.11.2 Method overview . . . . .	557
32.11.3 TGZFileStream.create . . . . .	557
32.11.4 TGZFileStream.read . . . . .	557
32.11.5 TGZFileStream.write . . . . .	558
32.11.6 TGZFileStream.seek . . . . .	558
32.11.7 TGZFileStream.destroy . . . . .	558

## About this guide

This document describes all constants, types, variables, functions and procedures as they are declared in the units that come standard with the FCL (Free Component Library).

Throughout this document, we will refer to functions, types and variables with `typewriter` font. Functions and procedures have their own subsections, and for each function or procedure we have the following topics:

**Declaration** The exact declaration of the function.

**Description** What does the procedure exactly do ?

**Errors** What errors can occur.

**See Also** Cross references to other related functions/commands.

## 0.1 Overview

The Free Component Library is a series of units that implement various classes and non-visual components for use with Free Pascal. They are building blocks for non-visual and visual programs, such as designed in Lazarus.

The `TDataset` descendents have been implemented in a way that makes them compatible to the Delphi implementation of these units. There are other units that have counterparts in Delphi, but most of them are unique to Free Pascal.

# Chapter 1

## Reference for unit 'ascii85'

### 1.1 Used units

Table 1.1: Used units by unit 'ascii85'

Name	Page
Classes	??
sysutils	??

### 1.2 Overview

The `ascii85` provides an ASCII 85 or base 85 decoding algorithm. It is class and stream based: the `TASCII85DecoderStream` (55) stream can be used to decode any stream with ASCII85 encoded data.

Currently, no ASCII85 encoder stream is available.

It's usage and purpose is similar to the IDEA (418) or base64 (74) units.

### 1.3 Constants, types and variables

#### 1.3.1 Types

```
TASCII85State = (ascInitial, ascOneEncodedChar, ascTwoEncodedChars,  
                 ascThreeEncodedChars, ascFourEncodedChars,  
                 ascNoEncodedChar, ascPrefix)
```

`TASCII85State` is for internal use, it contains the current state of the decoder.

### 1.4 TASCII85DecoderStream

#### 1.4.1 Description

`TASCII85DecoderStream` is a read-only stream: it takes an input stream with ASCII 85 encoded data, and decodes the data as it is read. To this end, it overrides the `TStream.Read` (??) method.



Table 1.2: Enumeration values for type TASCII85State

Value	Explanation
ascFourEncodedChars	Four encoded characters in buffer.
ascInitial	Initial state
ascNoEncodedChar	No encoded characters in buffer.
ascOneEncodedChar	One encoded character in buffer.
ascPrefix	Prefix processing
ascThreeEncodedChars	Three encoded characters in buffer.
ascTwoEncodedChars	Two encoded characters in buffer.

The stream cannot be written to, trying to write to the stream will result in an exception.

### 1.4.2 Method overview

Page	Property	Description
<a href="#">57</a>	Close	Close decoder
<a href="#">57</a>	ClosedP	Check if the state is correct
<a href="#">56</a>	Create	Create new ASCII 85 decoder stream
<a href="#">56</a>	Decode	Decode source byte
<a href="#">57</a>	Destroy	Clean up instance
<a href="#">57</a>	Read	Read data from stream
<a href="#">58</a>	Seek	Set stream position

### 1.4.3 Property overview

Page	Property	Access	Description
<a href="#">58</a>	BExpectBoundary	rw	Expect character

### 1.4.4 TASCII85DecoderStream.Create

Synopsis: Create new ASCII 85 decoder stream

Declaration: `constructor Create(aStream: TStream)`

Visibility: published

Description: `Create` instantiates a new `TASCII85DecoderStream` instance, and sets `aStream` as the source stream.

See also: `TASCII85DecoderStream.Destroy` ([57](#))

### 1.4.5 TASCII85DecoderStream.Decode

Synopsis: Decode source byte

Declaration: `procedure Decode(aInput: Byte)`

Visibility: published

Description: `Decode` decodes a source byte, and transfers it to the buffer. It is an internal routine and should not be used directly.

See also: `TASCII85DecoderStream.Close` ([57](#))

### 1.4.6 TASCII85DecoderStream.Close

Synopsis: Close decoder

Declaration: `procedure Close`

Visibility: `published`

Description: `Close` closes the decoder mechanism: it checks if all data was read and performs a check to see whether all input data was consumed.

Errors: If the input stream was invalid, an `EConvertError` exception is raised.

See also: `TASCII85DecoderStream.ClosedP` (57), `TASCII85DecoderStream.Read` (57), `TASCII85DecoderStream.Destroy` (57)

### 1.4.7 TASCII85DecoderStream.ClosedP

Synopsis: Check if the state is correct

Declaration: `function ClosedP : Boolean`

Visibility: `published`

Description: `ClosedP` checks if the decoder state is one of `ascInitial`, `ascNoEncodedChar`, `ascPrefix`, and returns `True` if it is.

See also: `TASCII85DecoderStream.Close` (57), `TASCII85DecoderStream.BExpectBoundary` (58)

### 1.4.8 TASCII85DecoderStream.Destroy

Synopsis: Clean up instance

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` closes the input stream using `Close` (57) and cleans up the `TASCII85DecoderStream` instance from memory.

Errors: In case the input stream was invalid, an exception may occur.

See also: `TASCII85DecoderStream.Close` (57)

### 1.4.9 TASCII85DecoderStream.Read

Synopsis: Read data from stream

Declaration: `function Read(var aBuffer;aCount: LongInt) : LongInt; Override`

Visibility: `public`

Description: `Read` attempts to read `aCount` bytes from the stream and places them in `aBuffer`. It reads only as much data as is available. The actual number of read bytes is returned.

The `read` method reads as much data from the input stream as needed to get to `aCount` bytes, in general this will be `aCount*5/4` bytes.

### 1.4.10 TASCII85DecoderStream.Seek

Synopsis: Set stream position

Declaration: `function Seek(aOffset: LongInt;aOrigin: Word) : LongInt; Override`  
`function Seek(const aOffset: Int64;aOrigin: TSeekOrigin) : Int64`  
`; Override; Overload`

Visibility: public

Description: `Seek` sets the stream position. It only allows to set the position to the current position of this file, and returns then the current position. All other arguments will result in an `EReadError` exception.

Errors: In case the arguments are different from `soCurrent` and 0, an `EReadError` exception will be raised.

See also: `TASCII85DecoderStream.Read` ([57](#))

### 1.4.11 TASCII85DecoderStream.BExpectBoundary

Synopsis: Expect character

Declaration: `Property BExpectBoundary : Boolean`

Visibility: published

Access: Read,Write

Description: `BExpectBoundary` is `True` if a encoded data boundary is to be expected ("`>`").

See also: `TASCII85DecoderStream.ClosedP` ([57](#))

## 1.5 TASCII85EncoderStream

### 1.5.1 Method overview

Page	Property	Description
<a href="#">58</a>	Create	
<a href="#">59</a>	Destroy	
<a href="#">59</a>	Write	

### 1.5.2 Property overview

Page	Property	Access	Description
<a href="#">59</a>	Boundary	r	
<a href="#">59</a>	Width	r	

### 1.5.3 TASCII85EncoderStream.Create

Declaration: `constructor Create(ADest: TStream;AWidth: Integer;ABoundary: Boolean)`

Visibility: public

### 1.5.4 TASCII85EncoderStream.Destroy

Declaration: destructor Destroy; Override

Visibility: public

### 1.5.5 TASCII85EncoderStream.Write

Declaration: function Write(const aBuffer;aCount: LongInt) : LongInt; Override

Visibility: public

### 1.5.6 TASCII85EncoderStream.Width

Declaration: Property Width : Integer

Visibility: public

Access: Read

### 1.5.7 TASCII85EncoderStream.Boundary

Declaration: Property Boundary : Boolean

Visibility: public

Access: Read

## 1.6 TASCII85RingBuffer

### 1.6.1 Description

TASCII85RingBuffer is an internal buffer class: it maintains a memory buffer of 1Kb, for faster reading of the stream. It should not be necessary to instantiate an instance of this class, the TASCII85DecoderStream ([55](#)) decoder stream will create an instance of this class automatically.

### 1.6.2 Method overview

Page	Property	Description
<a href="#">60</a>	Read	Read data from the internal buffer
<a href="#">59</a>	Write	Write data to the internal buffer

### 1.6.3 Property overview

Page	Property	Access	Description
<a href="#">60</a>	FillCount	r	Number of bytes in buffer
<a href="#">60</a>	Size	r	Size of buffer

### 1.6.4 TASCII85RingBuffer.Write

Synopsis: Write data to the internal buffer

Declaration: procedure Write(const aBuffer;aSize: Cardinal)

Visibility: published

Description: `Write` writes `aSize` bytes from `aBuffer` to the internal memory buffer. Only as much bytes are written as will fit in the buffer.

See also: `TASCII85RingBuffer.FillCount` (60), `TASCII85RingBuffer.Read` (60), `TASCII85RingBuffer.Size` (60)

### 1.6.5 TASCII85RingBuffer.Read

Synopsis: Read data from the internal buffer

Declaration: `function Read(var aBuffer; aSize: Cardinal) : Cardinal`

Visibility: published

Description: `Read` will read `aSize` bytes from the internal buffer and writes them to `aBuffer`. If not enough bytes are available, only as much bytes as available will be written. The function returns the number of bytes transferred.

See also: `TASCII85RingBuffer.FillCount` (60), `TASCII85RingBuffer.Write` (59), `TASCII85RingBuffer.Size` (60)

### 1.6.6 TASCII85RingBuffer.FillCount

Synopsis: Number of bytes in buffer

Declaration: `Property FillCount : Cardinal`

Visibility: published

Access: Read

Description: `FillCount` is the available amount of bytes in the buffer.

See also: `TASCII85RingBuffer.Write` (59), `TASCII85RingBuffer.Read` (60), `TASCII85RingBuffer.Size` (60)

### 1.6.7 TASCII85RingBuffer.Size

Synopsis: Size of buffer

Declaration: `Property Size : Cardinal`

Visibility: published

Access: Read

Description: `Size` is the total size of the memory buffer. This is currently hardcoded to 1024Kb.

See also: `TASCII85RingBuffer.FillCount` (60)

## Chapter 2

# Reference for unit 'AVL\_Tree'

### 2.1 Used units

Table 2.1: Used units by unit 'AVL\_Tree'

Name	Page
Classes	??
sysutils	??

### 2.2 Overview

The `avl_tree` unit implements a general-purpose AVL (balanced) tree class: the `TAVLTree` ([61](#)) class and it's associated data node class `TAVLTreeNode` ([70](#)).

### 2.3 TAVLTree

#### 2.3.1 Description

`TAVLTree` maintains a balanced AVL tree. The tree consists of `TAVLTreeNode` ([70](#)) nodes, each of which has a `Data` pointer associated with it. The `TAVLTree` component offers methods to balance and search the tree.

By default, the list is searched with a simple pointer comparison algorithm, but a custom search mechanism can be specified in the `OnCompare` ([69](#)) property.

### 2.3.2 Method overview

Page	Property	Description
<a href="#">66</a>	Add	Add a new node to the tree
<a href="#">67</a>	Clear	Clears the tree
<a href="#">68</a>	ConsistencyCheck	Check the consistency of the tree
<a href="#">69</a>	Create	Create a new instance of <code>TAVLTree</code>
<a href="#">66</a>	Delete	Delete a node from the tree
<a href="#">69</a>	Destroy	Destroy the <code>TAVLTree</code> instance
<a href="#">62</a>	Find	Find a data item in the tree.
<a href="#">64</a>	FindHighest	Find the highest (rightmost) node in the tree.
<a href="#">63</a>	FindKey	Find a data item in the tree using alternate compare mechanism
<a href="#">64</a>	FindLeftMost	Find the node most left to a specified data node
<a href="#">65</a>	FindLeftMostKey	Find the node most left to a specified key node
<a href="#">65</a>	FindLeftMostSameKey	Find the node most left to a specified node with the same data
<a href="#">63</a>	FindLowest	Find the lowest (leftmost) node in the tree.
<a href="#">64</a>	FindNearest	Find the node closest to the data in the tree
<a href="#">64</a>	FindPointer	Search for a data pointer
<a href="#">63</a>	FindPrecessor	
<a href="#">65</a>	FindRightMost	Find the node most right to a specified node
<a href="#">65</a>	FindRightMostKey	Find the node most right to a specified key node
<a href="#">66</a>	FindRightMostSameKey	Find the node most right of a specified node with the same data
<a href="#">63</a>	FindSuccessor	Find successor to node
<a href="#">68</a>	FreeAndClear	Clears the tree and frees nodes
<a href="#">68</a>	FreeAndDelete	Delete a node from the tree and destroy it
<a href="#">67</a>	MoveDataLeftMost	Move data to the nearest left element
<a href="#">67</a>	MoveDataRightMost	Move data to the nearest right element
<a href="#">66</a>	Remove	Remove a data item from the list.
<a href="#">67</a>	RemovePointer	Remove a pointer item from the list.
<a href="#">69</a>	ReportAsString	Return the tree report as a string
<a href="#">69</a>	SetNodeManager	
<a href="#">68</a>	WriteReportToStream	Write the contents of the tree consistency check to the stream

### 2.3.3 Property overview

Page	Property	Access	Description
<a href="#">70</a>	Count	r	Number of nodes in the tree.
<a href="#">69</a>	OnCompare	rw	Compare function used when comparing nodes

### 2.3.4 TAVLTree.Find

Synopsis: Find a data item in the tree.

Declaration: `function Find(Data: Pointer) : TAVLTreeNode`

Visibility: `public`

Description: `Find` uses the default `OnCompare` ([69](#)) comparing function to find the `Data` pointer in the tree. It returns the `TAVLTreeNode` instance that results in a successful compare with the `Data` pointer, or `Nil` if none is found.

The default `OnCompare` function compares the actual pointers, which means that by default `Find` will give the same result as `FindPointer` ([64](#)).

See also: `TAVLTree.OnCompare` (69), `TAVLTree.FindKey` (63)

### 2.3.5 `TAVLTree.FindKey`

Synopsis: Find a data item in the tree using alternate compare mechanism

Declaration: `function FindKey(Key: Pointer; OnCompareKeyWithData: TListSortCompare)  
: TAVLTreeNode`

Visibility: public

Description: `FindKey` uses the specified `OnCompareKeyWithData` comparing function to find the `Key` pointer in the tree. It returns the `TAVLTreeNode` instance that matches the `Data` pointer, or `Nil` if none is found.

See also: `TAVLTree.OnCompare` (69), `TAVLTree.Find` (62)

### 2.3.6 `TAVLTree.FindSuccessor`

Synopsis: Find successor to node

Declaration: `function FindSuccessor(ANode: TAVLTreeNode) : TAVLTreeNode`

Visibility: public

Description: `FindSuccessor` returns the successor to `ANode`: this is the leftmost node in the right subtree, or the leftmost node above the node `ANode`. This can of course be `Nil`.

This method is used when a node must be inserted at the rightmost position.

See also: `TAVLTree.FindPrecessor` (63), `TAVLTree.MoveDataRightMost` (67)

### 2.3.7 `TAVLTree.FindPrecessor`

Synopsis:

Declaration: `function FindPrecessor(ANode: TAVLTreeNode) : TAVLTreeNode`

Visibility: public

Description: `FindPrecessor` returns the successor to `ANode`: this is the rightmost node in the left subtree, or the rightmost node above the node `ANode`. This can of course be `Nil`.

This method is used when a node must be inserted at the leftmost position.

See also: `TAVLTree.FindSuccessor` (63), `TAVLTree.MoveDataLeftMost` (67)

### 2.3.8 `TAVLTree.FindLowest`

Synopsis: Find the lowest (leftmost) node in the tree.

Declaration: `function FindLowest : TAVLTreeNode`

Visibility: public

Description: `FindLowest` returns the leftmost node in the tree, i.e. the node which is reached when descending from the rootnode via the left (??) subtrees.

See also: `TAVLTree.FindHighest` (64)



### 2.3.9 TAVLTree.FindHighest

Synopsis: Find the highest (rightmost) node in the tree.

Declaration: `function FindHighest : TAVLTreeNode`

Visibility: public

Description: `FindHighest` returns the rightmost node in the tree, i.e. the node which is reached when descending from the rootnode via the Right (??) subtrees.

See also: `TAVLTree.FindLowest` (63)

### 2.3.10 TAVLTree.FindNearest

Synopsis: Find the node closest to the data in the tree

Declaration: `function FindNearest(Data: Pointer) : TAVLTreeNode`

Visibility: public

Description: `FindNearest` searches the node in the data tree that is closest to the specified `Data`. If `Data` appears in the tree, then its node is returned.

See also: `TAVLTree.FindHighest` (64), `TAVLTree.FindLowest` (63), `TAVLTree.Find` (62), `TAVLTree.FindKey` (63)

### 2.3.11 TAVLTree.FindPointer

Synopsis: Search for a data pointer

Declaration: `function FindPointer(Data: Pointer) : TAVLTreeNode`

Visibility: public

Description: `FindPointer` searches for a node where the actual data pointer equals `Data`. This is a more fine search than `find` (62), where a custom compare function can be used.

The default `OnCompare` (69) compares the data pointers, so the default `Find` will return the same node as `FindPointer`

See also: `TAVLTree.Find` (62), `TAVLTree.FindKey` (63)

### 2.3.12 TAVLTree.FindLeftMost

Synopsis: Find the node most left to a specified data node

Declaration: `function FindLeftMost(Data: Pointer) : TAVLTreeNode`

Visibility: public

Description: `FindLeftMost` finds the node most left from the `Data` node. It starts at the preceding node for `Data` and tries to move as far right in the tree as possible.

This operation corresponds to finding the previous item in a list.

See also: `TAVLTree.FindRightMost` (65), `TAVLTree.FindLeftMostKey` (65), `TAVLTree.FindRightMostKey` (65)

### 2.3.13 TAVLTree.FindRightMost

Synopsis: Find the node most right to a specified node

Declaration: `function FindRightMost (Data: Pointer) : TAVLTreeNode`

Visibility: public

Description: `FindRightMost` finds the node most right from the `Data` node. It starts at the succeeding node for `Data` and tries to move as far left in the tree as possible.

This operation corresponds to finding the next item in a list.

See also: `TAVLTree.FindLeftMost` (64), `TAVLTree.FindLeftMostKey` (65), `TAVLTree.FindRightMostKey` (65)

### 2.3.14 TAVLTree.FindLeftMostKey

Synopsis: Find the node most left to a specified key node

Declaration: `function FindLeftMostKey (Key: Pointer;  
OnCompareKeyWithData: TListSortCompare)  
: TAVLTreeNode`

Visibility: public

Description: `FindLeftMostKey` finds the node most left from the node associated with `Key`. It starts at the preceding node for `Key` and tries to move as far left in the tree as possible.

See also: `TAVLTree.FindLeftMost` (64), `TAVLTree.FindRightMost` (65), `TAVLTree.FindRightMostKey` (65)

### 2.3.15 TAVLTree.FindRightMostKey

Synopsis: Find the node most right to a specified key node

Declaration: `function FindRightMostKey (Key: Pointer;  
OnCompareKeyWithData: TListSortCompare)  
: TAVLTreeNode`

Visibility: public

Description: `FindRightMostKey` finds the node most left from the node associated with `Key`. It starts at the succeeding node for `Key` and tries to move as far right in the tree as possible.

See also: `TAVLTree.FindLeftMost` (64), `TAVLTree.FindRightMost` (65), `TAVLTree.FindLeftMostKey` (65)

### 2.3.16 TAVLTree.FindLeftMostSameKey

Synopsis: Find the node most left to a specified node with the same data

Declaration: `function FindLeftMostSameKey (ANode: TAVLTreeNode) : TAVLTreeNode`

Visibility: public

Description: `FindLeftMostSameKey` finds the node most left from and with the same data as the specified node `ANode`.

See also: `TAVLTree.FindLeftMost` (64), `TAVLTree.FindLeftMostKey` (65), `TAVLTree.FindRightMostSameKey` (66)

### 2.3.17 TAVLTree.FindRightMostSameKey

Synopsis: Find the node most right of a specified node with the same data

Declaration: `function FindRightMostSameKey (ANode: TAVLTreeNode) : TAVLTreeNode`

Visibility: public

Description: `FindRightMostSameKey` finds the node most right from and with the same data as the specified node `ANode`.

See also: `TAVLTree.FindRightMost` (65), `TAVLTree.FindRightMostKey` (65), `TAVLTree.FindLeftMostSameKey` (65)

### 2.3.18 TAVLTree.Add

Synopsis: Add a new node to the tree

Declaration: `procedure Add (ANode: TAVLTreeNode)`  
`function Add (Data: Pointer) : TAVLTreeNode`

Visibility: public

Description: `Add` adds a new `Data` or `Node` to the tree. It inserts the node so that the tree is maximally balanced by rebalancing the tree after the insert. In case a data pointer is added to the tree, then the node that was created is returned.

See also: `TAVLTree.Delete` (66), `TAVLTree.Remove` (66)

### 2.3.19 TAVLTree.Delete

Synopsis: Delete a node from the tree

Declaration: `procedure Delete (ANode: TAVLTreeNode)`

Visibility: public

Description: `Delete` removes the node from the tree. The node is not freed, but is passed to a `TAVLTreeNode-MemManager` (70) instance for future reuse. The data that the node represents is also not freed. The tree is rebalanced after the node was deleted.

See also: `TAVLTree.Remove` (66), `TAVLTree.RemovePointer` (67), `TAVLTree.Clear` (67)

### 2.3.20 TAVLTree.Remove

Synopsis: Remove a data item from the list.

Declaration: `procedure Remove (Data: Pointer)`

Visibility: public

Description: `Remove` finds the node associated with `Data` using `find` (62) and, if found, deletes it from the tree. Only the first occurrence of `Data` will be removed.

See also: `TAVLTree.Delete` (66), `TAVLTree.RemovePointer` (67), `TAVLTree.Clear` (67), `TAVLTree.Find` (62)

### 2.3.21 TAVLTree.RemovePointer

Synopsis: Remove a pointer item from the list.

Declaration: `procedure RemovePointer(Data: Pointer)`

Visibility: `public`

Description: `Remove` uses `FindPointer` (64) to find the node associated with the pointer `Data` and, if found, deletes it from the tree. Only the first occurrence of `Data` will be removed.

See also: `TAVLTree.Remove` (66), `TAVLTree.Delete` (66), `TAVLTree.Clear` (67)

### 2.3.22 TAVLTree.MoveDataLeftMost

Synopsis: Move data to the nearest left element

Declaration: `procedure MoveDataLeftMost(var ANode: TAVLTreeNode)`

Visibility: `public`

Description: `MoveDataLeftMost` moves the data from the node `ANode` to the nearest left location relative to `ANode`. It returns the new node where the data is positioned. The data from the former left node will be switched to `ANode`.

This operation corresponds to switching the current with the previous element in a list.

See also: `TAVLTree.MoveDataRightMost` (67)

### 2.3.23 TAVLTree.MoveDataRightMost

Synopsis: Move data to the nearest right element

Declaration: `procedure MoveDataRightMost(var ANode: TAVLTreeNode)`

Visibility: `public`

Description: `MoveDataRightMost` moves the data from the node `ANode` to the rightmost location relative to `ANode`. It returns the new node where the data is positioned. The data from the former rightmost node will be switched to `ANode`.

This operation corresponds to switching the current with the next element in a list.

See also: `TAVLTree.MoveDataLeftMost` (67)

### 2.3.24 TAVLTree.Clear

Synopsis: Clears the tree

Declaration: `procedure Clear`

Visibility: `public`

Description: `Clear` deletes all nodes from the tree. The nodes themselves are not freed, and the data pointer in the nodes is also not freed.

If the node's data must be freed as well, use `TAVLTree.FreeAndClear` (68) instead.

See also: `TAVLTree.FreeAndClear` (68), `TAVLTree.Delete` (66)

### 2.3.25 TAVLTree.FreeAndClear

Synopsis: Clears the tree and frees nodes

Declaration: `procedure FreeAndClear`

Visibility: public

Description: `FreeAndClear` deletes all nodes from the tree. The data pointer in the nodes is assumed to be an object, and is freed prior to deleting the node from the tree.

See also: `TAVLTree.Clear` (67), `TAVLTree.Delete` (66), `TAVLTree.FreeAndDelete` (68)

### 2.3.26 TAVLTree.FreeAndDelete

Synopsis: Delete a node from the tree and destroy it

Declaration: `procedure FreeAndDelete (ANode: TAVLTreeNode)`

Visibility: public

Description: `FreeAndDelete` deletes a node from the tree, and destroys the data pointer: The data pointer in the nodes is assumed to be an object, and is freed by calling its destructor.

See also: `TAVLTree.Clear` (67), `TAVLTree.Delete` (66), `TAVLTree.FreeAndClear` (68)

### 2.3.27 TAVLTree.ConsistencyCheck

Synopsis: Check the consistency of the tree

Declaration: `function ConsistencyCheck : Integer`

Visibility: public

Description: `ConsistencyCheck` checks the correctness of the tree. It returns 0 if the tree is internally consistent, and a negative number if the tree contains an error somewhere.

- 1The Count property doesn't match the actual node count
- 2A left node does not point to the correct parent
- 3A left node is larger than parent node
- 4A right node does not point to the correct parent
- 5A right node is less than parent node
- 6The balance of a node is not calculated correctly

See also: `TAVLTree.WriteReportToStream` (68)

### 2.3.28 TAVLTree.WriteReportToStream

Synopsis: Write the contents of the tree consistency check to the stream

Declaration: `procedure WriteReportToStream (s: TStream; var StreamSize: Int64)`

Visibility: public

Description: `WriteReportToStream` writes a visual representation of the tree to the stream S. The total number of written bytes is returned in `StreamSize`. This method is only useful for debugging purposes.

See also: `TAVLTree.ConsistencyCheck` (68)

### 2.3.29 TAVLTree.ReportAsString

Synopsis: Return the tree report as a string

Declaration: `function ReportAsString : String`

Visibility: public

Description: `ReportAsString` calls `WriteReportToStream` (68) and returns the stream data as a string.

See also: `TAVLTree.WriteReportToStream` (68)

### 2.3.30 TAVLTree.SetNodeManager

Declaration: `procedure SetNodeManager(newmgr: TBaseAVLTreeNodeManager)`

Visibility: public

### 2.3.31 TAVLTree.Create

Synopsis: Create a new instance of `TAVLTree`

Declaration: `constructor Create(OnCompareMethod: TListSortCompare)`  
`constructor Create`

Visibility: public

Description: `Create` initializes a new instance of `TAVLTree` (61). An alternate `OnCompare` (61) can be provided: the default `OnCompare` method compares the 2 data pointers of a node.

See also: `OnCompare` (61)

### 2.3.32 TAVLTree.Destroy

Synopsis: Destroy the `TAVLTree` instance

Declaration: `destructor Destroy; Override`

Visibility: public

Description: `Destroy` clears the nodes (the node data is not freed) and then destroys the `TAVLTree` instance.

See also: `TAVLTree.Create` (69), `TAVLTree.Clean` (61)

### 2.3.33 TAVLTree.OnCompare

Synopsis: Compare function used when comparing nodes

Declaration: `Property OnCompare : TListSortCompare`

Visibility: public

Access: Read,Write

Description: `OnCompare` is the comparing function used when the data of 2 nodes must be compared. By default, the function simply compares the 2 data pointers. A different function can be specified on creation.

See also: `TAVLTree.Create` (69)

### 2.3.34 TAVLTree.Count

Synopsis: Number of nodes in the tree.

Declaration: `Property Count : Integer`

Visibility: `public`

Access: `Read`

Description: `Count` is the number of nodes in the tree.

## 2.4 TAVLTreeNode

### 2.4.1 Description

`TAVLTreeNode` represents a single node in the AVL tree. It contains references to the other nodes in the tree, and provides a `Data (??)` pointer which can be used to store the data, associated with the node.

### 2.4.2 Method overview

Page	Property	Description
<a href="#">70</a>	<code>Clear</code>	Clears the node's data
<a href="#">70</a>	<code>TreeDepth</code>	Level of the node in the tree below

### 2.4.3 TAVLTreeNode.Clear

Synopsis: Clears the node's data

Declaration: `procedure Clear`

Visibility: `public`

Description: `Clear` clears all pointers and references in the node. It does not free the memory pointed to by these references.

### 2.4.4 TAVLTreeNode.TreeDepth

Synopsis: Level of the node in the tree below

Declaration: `function TreeDepth : Integer`

Visibility: `public`

Description: `TreeDepth` is the height of the node: this is the largest height of the left or right nodes, plus 1. If no nodes appear below this node (`left` and `Right` are `Nil`), the depth is 1.

See also: `TAVLTreeNode.Balance (??)`

## 2.5 TAVLTreeNodeMemManager

### 2.5.1 Description

`TAVLTreeNodeMemManager` is an internal object used by the `avl_tree` unit. Normally, no instance of this object should be created: An instance is created by the unit initialization code, and freed when the unit is finalized.

### 2.5.2 Method overview

Page	Property	Description
<a href="#">71</a>	Clear	Frees all unused nodes
<a href="#">72</a>	Create	Create a new instance of <code>TAVLTreeNodeMemManager</code>
<a href="#">72</a>	Destroy	
<a href="#">71</a>	DisposeNode	Return a node to the free list
<a href="#">71</a>	NewNode	Create a new <code>TAVLTreeNode</code> instance

### 2.5.3 Property overview

Page	Property	Access	Description
<a href="#">73</a>	Count	r	Number of nodes in the list.
<a href="#">72</a>	MaximumFreeNodeRatio	rw	Maximum amount of free nodes in the list
<a href="#">72</a>	MinimumFreeNode	rw	Minimum amount of free nodes to be kept.

### 2.5.4 TAVLTreeNodeMemManager.DisposeNode

Synopsis: Return a node to the free list

Declaration: `procedure DisposeNode (ANode: TAVLTreeNode); Override`

Visibility: public

Description: `DisposeNode` is used to put the node `ANode` in the list of free nodes, or optionally destroy it if the free list is full. After a call to `DisposeNode`, `ANode` must be considered invalid.

See also: `TAVLTreeNodeMemManager.NewNode` ([71](#))

### 2.5.5 TAVLTreeNodeMemManager.NewNode

Synopsis: Create a new `TAVLTreeNode` instance

Declaration: `function NewNode : TAVLTreeNode; Override`

Visibility: public

Description: `NewNode` returns a new `TAVLTreeNode` ([70](#)) instance. If there is a node in the free list, it are returned. If no more free nodes are present, a new node is created.

See also: `TAVLTreeNodeMemManager.DisposeNode` ([71](#))

### 2.5.6 TAVLTreeNodeMemManager.Clear

Synopsis: Frees all unused nodes

Declaration: `procedure Clear`

Visibility: public

Description: `Clear` removes all unused nodes from the list and frees them.

See also: `TAVLTreeNodeMemManager.MinimumFreeNode` ([72](#)), `TAVLTreeNodeMemManager.MaximumFreeNodeRatio` ([72](#))



### 2.5.7 TAVLTreeNodeMemManager.Create

Synopsis: Create a new instance of TAVLTreeNodeMemManager

Declaration: `constructor Create`

Visibility: `public`

Description: `Create` initializes a new instance of TAVLTreeNodeMemManager.

See also: TAVLTreeNodeMemManager.Destroy ([72](#))

### 2.5.8 TAVLTreeNodeMemManager.Destroy

Synopsis:

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` calls `clear` to clean up the free node list and then calls the inherited `destroy`.

See also: TAVLTreeNodeMemManager.Create ([72](#))

### 2.5.9 TAVLTreeNodeMemManager.MinimumFreeNode

Synopsis: Minimum amount of free nodes to be kept.

Declaration: `Property MinimumFreeNode : Integer`

Visibility: `public`

Access: `Read,Write`

Description: `MinimumFreeNode` is the minimum amount of nodes that must be kept in the free nodes list.

See also: TAVLTreeNodeMemManager.MaximumFreeNodeRatio ([72](#))

### 2.5.10 TAVLTreeNodeMemManager.MaximumFreeNodeRatio

Synopsis: Maximum amount of free nodes in the list

Declaration: `Property MaximumFreeNodeRatio : Integer`

Visibility: `public`

Access: `Read,Write`

Description: `MaximumFreeNodeRatio` is the maximum amount of free nodes that should be kept in the list: if a node is disposed of, then the ratio of the free nodes versus the total amount of nodes is checked, and if it is less than the `MaximumFreeNodeRatio` ratio but larger than the minimum amount of free nodes, then the node is disposed of instead of added to the free list.

See also: TAVLTreeNodeMemManager.Count ([73](#)), TAVLTreeNodeMemManager.MinimumFreeNode ([72](#))

### 2.5.11 TAVLTreeNodeMemManager.Count

Synopsis: Number of nodes in the list.

Declaration: `Property Count : Integer`

Visibility: `public`

Access: `Read`

Description: `Count` is the total number of nodes in the list, used or not.

See also: `TAVLTreeNodeMemManager.MinimumFreeNode` ([72](#)), `TAVLTreeNodeMemManager.MaximumFreeNodeRatio` ([72](#))

## 2.6 TBaseAVLTreeNodeManager

### 2.6.1 Method overview

Page	Property	Description
<a href="#">73</a>	<code>DisposeNode</code>	
<a href="#">73</a>	<code>NewNode</code>	

### 2.6.2 TBaseAVLTreeNodeManager.DisposeNode

Declaration: `procedure DisposeNode (ANode: TAVLTreeNode); Virtual; Abstract`

Visibility: `public`

### 2.6.3 TBaseAVLTreeNodeManager.NewNode

Declaration: `function NewNode : TAVLTreeNode; Virtual; Abstract`

Visibility: `public`

## Chapter 3

# Reference for unit 'base64'

### 3.1 Used units

Table 3.1: Used units by unit 'base64'

Name	Page
Classes	??
sysutils	??

### 3.2 Overview

`base64` implements base64 encoding (as used for instance in MIME encoding) based on streams. it implements 2 streams which encode or decode anything written or read from it. The source or the destination of the encoded data is another stream. 2 classes are implemented for this: `TBase64EncodingStream` (77) for encoding, and `TBase64DecodingStream` (75) for decoding.

The streams are designed as plug-in streams, which can be placed between other streams, to provide base64 encoding and decoding on-the-fly...

### 3.3 Constants, types and variables

#### 3.3.1 Types

```
TBase64DecodingMode = (bdmStrict, bdMIME)
```

Table 3.2: Enumeration values for type `TBase64DecodingMode`

Value	Explanation
<code>bdMIME</code>	MIME encoding
<code>bdmStrict</code>	Strict encoding

`TBase64DecodingMode` determines the decoding algorithm used by `TBase64DecodingStream` (75). There are 2 modes:

**bdmStrict** Strict mode, which follows RFC3548 and rejects any characters outside of base64 alphabet. In this mode only up to two '=' characters are accepted at the end. It requires the input to have a Size being a multiple of 4, otherwise an `EBase64DecodingException` (75) exception is raised.

**bdmMime** MIME mode, which follows RFC2045 and ignores any characters outside of base64 alphabet. In this mode any '=' is seen as the end of string, it handles apparently truncated input streams gracefully.

## 3.4 EBase64DecodingException

### 3.4.1 Description

`EBase64DecodeException` is raised when the stream contains errors against the encoding format. Whether or not this exception is raised depends on the mode in which the stream is decoded.

## 3.5 TBase64DecodingStream

### 3.5.1 Description

`TBase64DecodingStream` can be used to read data from a stream (the source stream) that contains Base64 encoded data. The data is read and decoded on-the-fly.

The decoding stream is read-only, and provides a limited forward-seeking capability.

### 3.5.2 Method overview

Page	Property	Description
<a href="#">75</a>	Create	Create a new instance of the <code>TBase64DecodingStream</code> class
<a href="#">76</a>	Read	Read and decrypt data from the source stream
<a href="#">76</a>	Reset	Reset the stream
<a href="#">76</a>	Seek	Set stream position.

### 3.5.3 Property overview

Page	Property	Access	Description
<a href="#">77</a>	EOF	r	
<a href="#">77</a>	Mode	rw	Decoding mode

### 3.5.4 TBase64DecodingStream.Create

**Synopsis:** Create a new instance of the `TBase64DecodingStream` class

**Declaration:** `constructor Create(ASource: TStream)`  
`constructor Create(ASource: TStream; AMode: TBase64DecodingMode)`

**Visibility:** public

**Description:** `Create` creates a new instance of the `TBase64DecodingStream` class. It stores the source stream `ASource` for reading the data from.

The optional `AMode` parameter determines the mode in which the decoding will be done. If omitted, `bdmMIME` is used.

See also: [TBase64EncodingStream.Create \(77\)](#), [TBase64DecodingMode \(74\)](#)

### 3.5.5 TBase64DecodingStream.Reset

Synopsis: Reset the stream

Declaration: `procedure Reset`

Visibility: `public`

Description: `Reset` resets the data as if it was again on the start of the decoding stream.

Errors: None.

See also: [TBase64DecodingStream.EOF \(77\)](#), [TBase64DecodingStream.Read \(76\)](#)

### 3.5.6 TBase64DecodingStream.Read

Synopsis: Read and decrypt data from the source stream

Declaration: `function Read(var Buffer; Count: LongInt) : LongInt; Override`

Visibility: `public`

Description: `Read` reads encrypted data from the source stream and stores this data in `Buffer`. At most `Count` bytes will be stored in the buffer, but more bytes will be read from the source stream: the encoding algorithm multiplies the number of bytes.

The function returns the number of bytes stored in the buffer.

Errors: If an error occurs during the read from the source stream, an exception may occur.

See also: [TBase64DecodingStream.Write \(75\)](#), [TBase64DecodingStream.Seek \(76\)](#), [#rtl.classes.TStream.Read \(??\)](#)

### 3.5.7 TBase64DecodingStream.Seek

Synopsis: Set stream position.

Declaration: `function Seek(Offset: LongInt; Origin: Word) : LongInt; Override`

Visibility: `public`

Description: `Seek` sets the position of the stream. In the `TBase64DecodingStream` class, the seek operation is forward only, it does not support backward seeks. The forward seek is emulated by reading and discarding data till the desired position is reached.

For an explanation of the parameters, see [TStream.Seek \(??\)](#)

Errors: In case of an unsupported operation, an `EStreamError` exception is raised.

See also: [TBase64DecodingStream.Read \(76\)](#), [TBase64DecodingStream.Write \(75\)](#), [TBase64EncodingStream.Seek \(78\)](#), [#rtl.classes.TStream.Seek \(??\)](#)

### 3.5.8 TBase64DecodingStream.EOF

Synopsis:

Declaration: Property EOF : Boolean

Visibility: public

Access: Read

Description:

### 3.5.9 TBase64DecodingStream.Mode

Synopsis: Decoding mode

Declaration: Property Mode : TBase64DecodingMode

Visibility: public

Access: Read,Write

Description: Mode is the mode in which the stream is read. It can be set when creating the stream or at any time afterwards.

See also: TBase64DecodingStream ([75](#))

## 3.6 TBase64EncodingStream

### 3.6.1 Description

TBase64EncodingStream can be used to encode data using the base64 algorithm. At creation time, a destination stream is specified. Any data written to the TBase64EncodingStream instance will be base64 encoded, and subsequently written to the destination stream.

The TBase64EncodingStream stream is a write-only stream. Obviously it is also not seekable. It is meant to be included in a chain of streams.

### 3.6.2 Method overview

Page	Property	Description
<a href="#">77</a>	Create	Create a new instance of the TBase64EncodingStream class.
<a href="#">78</a>	Destroy	Remove a TBase64EncodingStream instance from memory
<a href="#">78</a>	Seek	Position the stream
<a href="#">78</a>	Write	Write data to the stream.

### 3.6.3 TBase64EncodingStream.Create

Synopsis: Create a new instance of the TBase64EncodingStream class.

Declaration: constructor Create (ASource: TStream)

Visibility: public

Description: Create instantiates a new TBase64EncodingStream class. The ASource stream is stored and used to write the encoded data to.

See also: TBase64EncodingStream.Destroy ([78](#)), TBase64DecodingStream.Create ([75](#))

### 3.6.4 TBase64EncodingStream.Destroy

Synopsis: Remove a TBase64EncodingStream instance from memory

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` flushes any remaining output and then removes the TBase64EncodingStream instance from memory by calling the inherited destructor.

Errors: An exception may be raised if the destination stream no longer exists or is closed.

See also: TBase64EncodingStream.Create (77)

### 3.6.5 TBase64EncodingStream.Write

Synopsis: Write data to the stream.

Declaration: `function Write(const Buffer; Count: LongInt) : LongInt; Override`

Visibility: `public`

Description: `Write` encodes `Count` bytes from `Buffer` using the Base64 mechanism, and then writes the encoded data to the destination stream. It returns the number of bytes from `Buffer` that were actually written. Note that this is not the number of bytes written to the destination stream: the base64 mechanism writes more bytes to the destination stream.

Errors: If there is an error writing to the destination stream, an error may occur.

See also: TBase64EncodingStream.Seek (78), TBase64EncodingStream.Read (77), TBase64DecodingStream.Write (75), #rtl.classes.TStream.Write (??)

### 3.6.6 TBase64EncodingStream.Seek

Synopsis: Position the stream

Declaration: `function Seek(Offset: LongInt; Origin: Word) : LongInt; Override`

Visibility: `public`

Description: `Seek` always raises an `EStreamError` exception unless the arguments it received don't change the current file pointer position. The encryption stream is not seekable.

Errors: An `EStreamError` error is raised.

See also: TBase64EncodingStream.Read (77), TBase64EncodingStream.Write (78), #rtl.classes.TStream.Seek (??)

## Chapter 4

# Reference for unit 'BlowFish'

### 4.1 Used units

Table 4.1: Used units by unit 'BlowFish'

Name	Page
Classes	??
sysutils	??

### 4.2 Overview

The BlowFish implements a class TBlowFish (80) to handle blowfish encryption/decryption of memory buffers, and 2 TStream (??) descendents TBlowFishDeCryptStream (81) which descrypts any data that is read from it on the fly, as well as TBlowFishEnCryptStream (82) which encrypts the data that is written to it on the fly.

### 4.3 Constants, types and variables

#### 4.3.1 Constants

BFRounds = 16

Number of rounds in blowfish encryption.

#### 4.3.2 Types

PBlowFishKey = ^TBlowFishKey

PBlowFishKey is a simple pointer to a TBlowFishKey (80) array.

TBFBlock = Array[0..1] of LongInt



TBFBlock is the basic data structure used by the encrypting/decrypting routines in TBlowFish (80), TBlowFishDeCryptStream (81) and TBlowFishEnCryptStream (82). It is the basic encryption/decryption block for all encrypting/decrypting: all encrypting/decrypting happens on a TBFBlock structure.

TBlowFishKey = Array[0..55] of Byte

TBlowFishKey is a data structure which keeps the encryption or decryption key for the TBlowFish (80), TBlowFishDeCryptStream (81) and TBlowFishEnCryptStream (82) classes. It should be filled with the encryption key and passed to the constructor of one of these classes.

## 4.4 EBlowFishError

### 4.4.1 Description

EBlowFishError is used by the TBlowFishStream (83), TBlowFishEncryptStream (82) and TBlowFishDecryptStream (81) classes to report errors.

## 4.5 TBlowFish

### 4.5.1 Description

TBlowFish is a simple class that can be used to encrypt/decrypt a single TBFBlock (80) data block with the Encrypt (80) and Decrypt (81) calls. It is used internally by the TBlowFishEnCryptStream (82) and TBlowFishDeCryptStream (81) classes to encrypt or decrypt the actual data.

### 4.5.2 Method overview

Page	Property	Description
<a href="#">80</a>	Create	Create a new instance of the TBlowFish class
<a href="#">81</a>	Decrypt	Decrypt a block
<a href="#">80</a>	Encrypt	Encrypt a block

### 4.5.3 TBlowFish.Create

Synopsis: Create a new instance of the TBlowFish class

Declaration: constructor Create(Key: TBlowFishKey; KeySize: Integer)

Visibility: public

Description: Create initializes a new instance of the TBlowFish class: it stores the key Key in the internal data structures so it can be used in later calls to Encrypt (80) and Decrypt (81).

See also: TBlowFish.Encrypt (80), TBlowFish.Decrypt (81)

### 4.5.4 TBlowFish.Encrypt

Synopsis: Encrypt a block

Declaration: procedure Encrypt(var Block: TBFBlock)

Visibility: public

Description: `Encrypt` encrypts the data in `Block` (always 8 bytes) using the key (80) specified when the `TBlowFish` instance was created.

See also: `TBlowFishKey` (80), `TBlowFish.Decrypt` (81), `TBlowFish.Create` (80)

### 4.5.5 TBlowFish.Decrypt

Synopsis: Decrypt a block

Declaration: `procedure Decrypt (var Block: TBFBLOCK)`

Visibility: public

Description: `Decrypt` decrypts the data in `Block` (always 8 bytes) using the key (80) specified when the `TBlowFish` instance was created. The data must have been encrypted with the same key and the `Encrypt` (80) call.

See also: `TBlowFishKey` (80), `TBlowFish.Encrypt` (80), `TBlowFish.Create` (80)

## 4.6 TBlowFishDeCryptStream

### 4.6.1 Description

The `TBlowFishDeCryptStream` provides On-the-fly Blowfish decryption: all data that is read from the source stream is decrypted before it is placed in the output buffer. The source stream must be specified when the `TBlowFishDeCryptStream` instance is created. The Decryption key must also be created when the stream instance is created, and must be the same key as the one used when encrypting the data.

This is a read-only stream: it is seekable only in a forward direction, and data can only be read from it, writing is not possible. For writing data so it is encrypted, the `TBlowFishEncryptStream` (82) stream must be used.

### 4.6.2 Method overview

Page	Property	Description
<a href="#">81</a>	Read	Read data from the stream
<a href="#">82</a>	Seek	Set the stream position.

### 4.6.3 TBlowFishDeCryptStream.Read

Synopsis: Read data from the stream

Declaration: `function Read (var Buffer; Count: LongInt) : LongInt; Override`

Visibility: public

Description: `Read` reads `Count` bytes from the source stream, decrypts them using the key provided when the `TBlowFishDeCryptStream` instance was created, and writes the decrypted data to `Buffer`

See also: `TBlowFishStream.Create` (84), `TBlowFishEncryptStream` (82)

## 4.6.4 TBlowFishDeCryptStream.Seek

Synopsis: Set the stream position.

Declaration: `function Seek(Offset: LongInt; Origin: Word) : LongInt; Override`

Visibility: `public`

Description: `Seek` emulates a forward seek by reading and discarding data. The discarded data is lost. Since it is a forward seek, this means that only `soFromCurrent` can be specified for `Origin` with a positive (or zero) `Offset` value. All other values will result in an exception. The function returns the new position in the stream.

Errors: If any other combination of `Offset` and `Origin` than the allowed combination is specified, then an `EBlowFishError` (80) exception will be raised.

See also: `TBlowFishDeCryptStream.Read` (81), `EBlowFishError` (80)

## 4.7 TBlowFishEncryptStream

### 4.7.1 Description

The `TBlowFishEncryptStream` provides On-the-fly Blowfish encryption: all data that is written to it is encrypted and then written to a destination stream, which must be specified when the `TBlowFishEncryptStream` instance is created. The encryption key must also be created when the stream instance is created.

This is a write-only stream: it is not seekable, and data can only be written to it, reading is not possible. For reading encrypted data, the `TBlowFishDeCryptStream` (81) stream must be used.

### 4.7.2 Method overview

Page	Property	Description
<a href="#">82</a>	<code>Destroy</code>	Free the <code>TBlowFishEncryptStream</code>
<a href="#">83</a>	<code>Flush</code>	Flush the encryption buffer
<a href="#">83</a>	<code>Seek</code>	Set the position in the stream
<a href="#">82</a>	<code>Write</code>	Write data to the stream

### 4.7.3 TBlowFishEncryptStream.Destroy

Synopsis: Free the `TBlowFishEncryptStream`

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` flushes the encryption buffer, and writes it to the destination stream. After that the inherited destructor is called to clean up the `TBlowFishEncryptStream` instance.

See also: `TBlowFishEncryptStream.Flush` (83), `TBlowFishStream.Create` (84)

### 4.7.4 TBlowFishEncryptStream.Write

Synopsis: Write data to the stream

Declaration: `function Write(const Buffer; Count: LongInt) : LongInt; Override`

Visibility: public

**Description:** `Write` will encrypt and write `Count` bytes from `Buffer` to the destination stream. The function returns the actual number of bytes written. The data is not encrypted in-place, but placed in a special buffer for encryption.

Data is always written 4 bytes at a time, since this is the amount of bytes required by the Blowfish algorithm. If no multiple of 4 was written to the destination stream, the `Flush` (83) mechanism can be used to write the remaining bytes.

See also: `TBlowFishEncryptStream.Read` (82)

### 4.7.5 TBlowFishEncryptStream.Seek

Synopsis: Set the position in the stream

**Declaration:** `function Seek(Offset: LongInt; Origin: Word) : LongInt; Override`

Visibility: public

**Description:** `Read` will raise an `EBlowFishError` exception: `TBlowFishEncryptStream` is a write-only stream, and cannot be positioned.

**Errors:** Calling this function always results in an `EBlowFishError` (80) exception.

See also: `TBlowFishEncryptStream.Write` (82)

### 4.7.6 TBlowFishEncryptStream.Flush

Synopsis: Flush the encryption buffer

**Declaration:** `procedure Flush`

Visibility: public

**Description:** `Flush` writes the remaining data in the encryption buffer to the destination stream.

For efficiency, data is always written 4 bytes at a time, since this is the amount of bytes required by the Blowfish algorithm. If no multiple of 4 was written to the destination stream, the `Flush` mechanism can be used to write the remaining bytes.

`Flush` is called automatically when the stream is destroyed, so there is no need to call it after all data was written and the stream is no longer needed.

See also: `TBlowFishEncryptStream.Write` (82), `TBFBlock` (80)

## 4.8 TBlowFishStream

### 4.8.1 Description

`TBlowFishStream` is an abstract class which is used as a parent class for `TBlowFishEncryptStream` (82) and `TBlowFishDecryptStream` (81). It simply provides a constructor and storage for a `TBlowFish` (80) instance and for the source or destination stream.

Do not create an instance of `TBlowFishStream` directly. Instead create one of the descendent classes `TBlowFishEncryptStream` or `TBlowFishDecryptStream`.

### 4.8.2 Method overview

Page	Property	Description
<a href="#">84</a>	Create	Create a new instance of the <code>TBlowFishStream</code> class
<a href="#">84</a>	Destroy	Destroy the <code>TBlowFishStream</code> instance.

### 4.8.3 Property overview

Page	Property	Access	Description
<a href="#">84</a>	BlowFish	r	Blowfish instance used when encrypting/decrypting

### 4.8.4 TBlowFishStream.Create

Synopsis: Create a new instance of the `TBlowFishStream` class

Declaration: constructor `Create(AKey: TBlowFishKey; AKeySize: Byte; Dest: TStream)`  
 constructor `Create(const KeyPhrase: String; Dest: TStream)`

Visibility: public

Description: `Create` initializes a new instance of `TBlowFishStream`, and creates an internal instance of `TBlowFish` ([80](#)) using `AKey` and `AKeySize`. The `Dest` stream is stored so the descendent classes can refer to it.

Do not create an instance of `TBlowFishStream` directly. Instead create one of the descendent classes `TBlowFishEncryptStream` or `TBlowFishDecryptStream`.

The overloaded version with the `KeyPhrase` string argument is used for easy access: it computes the blowfish key from the given string.

See also: `TBlowFishEncryptStream` ([82](#)), `TBlowFishDecryptStream` ([81](#)), `TBlowFish` ([80](#))

### 4.8.5 TBlowFishStream.Destroy

Synopsis: Destroy the `TBlowFishStream` instance.

Declaration: destructor `Destroy`; Override

Visibility: public

Description: `Destroy` cleans up the internal `TBlowFish` ([80](#)) instance.

Errors:

See also: `TBlowFishStream.Create` ([84](#)), `TBlowFish` ([80](#))

### 4.8.6 TBlowFishStream.BlowFish

Synopsis: Blowfish instance used when encrypting/decrypting

Declaration: Property `BlowFish` : `TBlowFish`

Visibility: public

Access: Read

Description: `BlowFish` is the `TBlowFish` ([80](#)) instance which is created when the `TBlowFishStream` class is initialized. Normally it should not be used directly, it's intended for access by the descendent classes `TBlowFishEncryptStream` ([82](#)) and `TBlowFishDecryptStream` ([81](#)).

See also: `TBlowFishEncryptStream` ([82](#)), `TBlowFishDecryptStream` ([81](#)), `TBlowFish` ([80](#))

## Chapter 5

# Reference for unit 'bufstream'

### 5.1 Used units

Table 5.1: Used units by unit 'bufstream'

Name	Page
Classes	??
sysutils	??

### 5.2 Overview

BufStream implements two one-way buffered streams: the streams store all data from (or for) the source stream in a memory buffer, and only flush the buffer when it's full (or refill it when it's empty). The buffer size can be specified at creation time. 2 streams are implemented: TReadBufStream (89) which is for reading only, and TWriteBufStream (89) which is for writing only.

Buffered streams can help in speeding up read or write operations, especially when a lot of small read/write operations are done: it avoids doing a lot of operating system calls.

### 5.3 Constants, types and variables

#### 5.3.1 Constants

`DefaultBufferCapacity : Integer = 16`

If no buffer size is specified when the stream is created, then this size is used.

### 5.4 TBufStream

#### 5.4.1 Description

TBufStream is the common ancestor for the TReadBufStream (89) and TWriteBufStream (89) streams. It completely handles the buffer memory management and position management. An in-

stance of `TBufStream` should never be created directly. It also keeps the instance of the source stream.

### 5.4.2 Method overview

Page	Property	Description
<a href="#">87</a>	Create	Create a new <code>TBufStream</code> instance.
<a href="#">87</a>	Destroy	Destroys the <code>TBufStream</code> instance

### 5.4.3 Property overview

Page	Property	Access	Description
<a href="#">87</a>	Buffer	r	The current buffer
<a href="#">88</a>	BufferPos	r	Current buffer position.
<a href="#">88</a>	BufferSize	r	Amount of data in the buffer
<a href="#">88</a>	Capacity	rw	Current buffer capacity

### 5.4.4 TBufStream.Create

Synopsis: Create a new `TBufStream` instance.

Declaration: `constructor Create (ASource: TStream; ACapacity: Integer)`  
`constructor Create (ASource: TStream)`

Visibility: public

Description: `Create` creates a new `TBufStream` instance. A buffer of size `ACapacity` is allocated, and the `ASource` source (or destination) stream is stored. If no capacity is specified, then `DefaultBufferCapacity` ([86](#)) is used as the capacity.

An instance of `TBufStream` should never be instantiated directly. Instead, an instance of `TReadBufStream` ([89](#)) or `TWriteBufStream` ([89](#)) should be created.

Errors: If not enough memory is available for the buffer, then an exception may be raised.

See also: `TBufStream.Destroy` ([87](#)), `TReadBufStream` ([89](#)), `TWriteBufStream` ([89](#))

### 5.4.5 TBufStream.Destroy

Synopsis: Destroys the `TBufStream` instance

Declaration: `destructor Destroy;` `Override`

Visibility: public

Description: `Destroy` destroys the instance of `TBufStream`. It flushes the buffer, deallocates it, and then destroys the `TBufStream` instance.

See also: `TBufStream.Create` ([87](#)), `TReadBufStream` ([89](#)), `TWriteBufStream` ([89](#))

### 5.4.6 TBufStream.Buffer

Synopsis: The current buffer

Declaration: `Property Buffer : Pointer`



Visibility: public

Access: Read

Description: `Buffer` is a pointer to the actual buffer in use.

See also: `TBufStream.Create` (87), `TBufStream.Capacity` (88), `TBufStream.BufferSize` (88)

### 5.4.7 TBufStream.Capacity

Synopsis: Current buffer capacity

Declaration: `Property Capacity : Integer`

Visibility: public

Access: Read, Write

Description: `Capacity` is the amount of memory the buffer occupies. To change the buffer size, the capacity can be set. Note that the capacity cannot be set to a value that is less than the current buffer size, i.e. the current amount of data in the buffer.

See also: `TBufStream.Create` (87), `TBufStream.Buffer` (87), `TBufStream.BufferSize` (88), `TBufStream.BufferPos` (88)

### 5.4.8 TBufStream.BufferPos

Synopsis: Current buffer position.

Declaration: `Property BufferPos : Integer`

Visibility: public

Access: Read

Description: `BufferPos` is the current stream position in the buffer. Depending on whether the stream is used for reading or writing, data will be read from this position, or will be written at this position in the buffer.

See also: `TBufStream.Create` (87), `TBufStream.Buffer` (87), `TBufStream.BufferSize` (88), `TBufStream.Capacity` (88)

### 5.4.9 TBufStream.BufferSize

Synopsis: Amount of data in the buffer

Declaration: `Property BufferSize : Integer`

Visibility: public

Access: Read

Description: `BufferSize` is the actual amount of data in the buffer. This is always less than or equal to the `Capacity` (88).

See also: `TBufStream.Create` (87), `TBufStream.Buffer` (87), `TBufStream.BufferPos` (88), `TBufStream.Capacity` (88)

## 5.5 TReadBufStream

### 5.5.1 Description

`TReadBufStream` is a read-only buffered stream. It implements the needed methods to read data from the buffer and fill the buffer with additional data when needed.

The stream provides limited forward-seek possibilities.

### 5.5.2 Method overview

Page	Property	Description
<a href="#">89</a>	Read	Reads data from the stream
<a href="#">89</a>	Seek	Set location in the buffer

### 5.5.3 TReadBufStream.Seek

Synopsis: Set location in the buffer

Declaration: `function Seek(Offset: LongInt; Origin: Word) : LongInt; Override`

Visibility: public

Description: `Seek` sets the location in the buffer. Currently, only a forward seek is allowed. It is emulated by reading and discarding data. For an explanation of the parameters, see `TStream.Seek` "(?)"

The seek method needs enhancement to enable it to do a full-featured seek. This may be implemented in a future release of Free Pascal.

Errors: In case an illegal seek operation is attempted, an exception is raised.

See also: `TWriteBufStream.Seek` ([90](#)), `TReadBufStream.Read` ([89](#)), `TReadBufStream.Write` ([89](#))

### 5.5.4 TReadBufStream.Read

Synopsis: Reads data from the stream

Declaration: `function Read(var ABuffer; ACount: LongInt) : Integer; Override`

Visibility: public

Description: `Read` reads at most `ACount` bytes from the stream and places them in `Buffer`. The number of actually read bytes is returned.

`TReadBufStream` first reads whatever data is still available in the buffer, and then refills the buffer, after which it continues to read data from the buffer. This is repeated until `ACount` bytes are read, or no more data is available.

See also: `TReadBufStream.Seek` ([89](#)), `TReadBufStream.Read` ([89](#))

## 5.6 TWriteBufStream

### 5.6.1 Description

`TWriteBufStream` is a write-only buffered stream. It implements the needed methods to write data to the buffer and flush the buffer (i.e., write its contents to the source stream) when needed.

### 5.6.2 Method overview

Page	Property	Description
<a href="#">90</a>	Destroy	Remove the <code>TWriteBufStream</code> instance from memory
<a href="#">90</a>	Seek	Set stream position.
<a href="#">90</a>	Write	Write data to the stream

### 5.6.3 TWriteBufStream.Destroy

Synopsis: Remove the `TWriteBufStream` instance from memory

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` flushes the buffer and then calls the inherited `Destroy` ([87](#)).

Errors: If an error occurs during flushing of the buffer, an exception may be raised.

See also: `TBufStream.Create` ([87](#)), `TBufStream.Destroy` ([87](#))

### 5.6.4 TWriteBufStream.Seek

Synopsis: Set stream position.

Declaration: `function Seek(Offset: LongInt; Origin: Word) : LongInt; Override`

Visibility: `public`

Description: `Seek` always raises an `EStreamError` exception, except when the seek operation would not alter the current position.

A later implementation may perform a proper seek operation by flushing the buffer and doing a seek on the source stream.

Errors:

See also: `TWriteBufStream.Write` ([90](#)), `TWriteBufStream.Read` ([89](#)), `TReadBufStream.Seek` ([89](#))

### 5.6.5 TWriteBufStream.Write

Synopsis: Write data to the stream

Declaration: `function Write(const ABuffer; ACount: LongInt) : Integer; Override`

Visibility: `public`

Description: `Write` writes at most `ACount` bytes from `ABuffer` to the stream. The data is written to the internal buffer first. As soon as the internal buffer is full, it is flushed to the destination stream, and the internal buffer is filled again. This process continues till all data is written (or an error occurs).

Errors: An exception may occur if the destination stream has problems writing.

See also: `TWriteBufStream.Seek` ([90](#)), `TWriteBufStream.Read` ([89](#)), `TReadBufStream.Write` ([89](#))

## Chapter 6

# Reference for unit 'CacheCls'

### 6.1 Used units

Table 6.1: Used units by unit 'CacheCls'

Name	Page
sysutils	??

### 6.2 Overview

The `CacheCls` unit implements a caching class: similar to a hash class, it can be used to cache data, associated with string values (keys). The class is called `TCache`

### 6.3 Constants, types and variables

#### 6.3.1 Resource strings

```
SInvalidIndex = 'Invalid index %i'
```

Message shown when an invalid index is passed.

#### 6.3.2 Types

```
PCacheSlot = ^TCacheSlot
```

Pointer to `TCacheSlot` ([92](#)) record.

```
PCacheSlotArray = ^TCacheSlotArray
```

Pointer to `TCacheSlotArray` ([92](#)) array

```
TCacheSlot = record
```

```

Prev : PCacheSlot;
Next : PCacheSlot;
Data : Pointer;
Index : Integer;
end

```

TCacheSlot is internally used by the TCache (92) class. It represents 1 element in the linked list.

```
TCacheSlotArray = Array[0..MaxIntdivSizeOf(TCacheSlot)-1] of TCacheSlot
```

TCacheSlotArray is an array of TCacheSlot items. Do not use TCacheSlotArray directly, instead, use PCacheSlotArray (91) and allocate memory dynamically.

```
TOnFreeSlot = procedure(ACache: TCache; SlotIndex: Integer) of object
```

TOnFreeSlot is a callback prototype used when not enough slots are free, and a slot must be freed.

```

TOnIsDataEqual = function(ACache: TCache; AData1: Pointer;
                          AData2: Pointer) : Boolean of object

```

TOnIsDataEqual is a callback prototype; It is used by the TCache.Add (93) call to determine whether the item to be added is a new item or not. The function returns True if the 2 data pointers AData1 and AData2 should be considered equal, or False when they are not.

For most purposes, comparing the pointers will be enough, but if the pointers are ansistrings, then the contents should be compared.

## 6.4 ECacheError

### 6.4.1 Description

Exception class used in the cachecls unit.

## 6.5 TCache

### 6.5.1 Description

TCache implements a cache class: it is a list-like class, but which uses a counting mechanism, and keeps a Most-Recent-Used list; this list represents the 'cache'. The list is internally kept as a doubly-linked list.

The Data (95) property offers indexed access to the array of items. When accessing the array through this property, the MRUSlot (95) property is updated.

### 6.5.2 Method overview

Page	Property	Description
<a href="#">93</a>	Add	Add a data element to the list.
<a href="#">94</a>	AddNew	Add a new item to the list.
<a href="#">93</a>	Create	Create a new cache class.
<a href="#">93</a>	Destroy	Free the TCache class from memory
<a href="#">94</a>	FindSlot	Find data pointer in the list
<a href="#">94</a>	IndexOf	Return index of a data pointer in the list.
<a href="#">95</a>	Remove	Remove a data item from the list.

### 6.5.3 Property overview

Page	Property	Access	Description
<a href="#">95</a>	Data	rw	Indexed access to data items
<a href="#">96</a>	LRUSlot	r	Last used item
<a href="#">95</a>	MRUSlot	rw	Most recent item slot.
<a href="#">97</a>	OnFreeSlot	rw	Event called when a slot is freed
<a href="#">96</a>	OnIsDataEqual	rw	Event to compare 2 items.
<a href="#">96</a>	SlotCount	rw	Number of slots in the list
<a href="#">96</a>	Slots	r	Indexed array to the slots

### 6.5.4 TCache.Create

Synopsis: Create a new cache class.

Declaration: `constructor Create(ASlotCount: Integer)`

Visibility: `public`

Description: `Create` instantiates a new instance of `TCache`. It allocates room for `ASlotCount` entries in the list. The number of slots can be increased later.

See also: `TCache.SlotCount` ([96](#))

### 6.5.5 TCache.Destroy

Synopsis: Free the TCache class from memory

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` cleans up the array for the elements, and calls the inherited `Destroy`. The elements in the array are not freed by this action.

See also: `TCache.Create` ([93](#))

### 6.5.6 TCache.Add

Synopsis: Add a data element to the list.

Declaration: `function Add(AData: Pointer) : Integer`

Visibility: `public`

**Description:** Add checks whether `AData` is already in the list. If so, the item is added to the top of the MRU list. If the item is not yet in the list, then the item is added to the list and placed at the top of the MRU list using the `AddNew` (94) call.

The function returns the index at which the item was added.

If the maximum number of slots is reached, and a new item is being added, the least used item is dropped from the list.

See also: `TCache.AddNew` (94), `TCache.FindSlot` (94), `TCache.IndexOf` (94), `TCache.Data` (95), `TCache.MRUSlot` (95)

### 6.5.7 `TCache.AddNew`

**Synopsis:** Add a new item to the list.

**Declaration:** `function AddNew(AData: Pointer) : Integer`

**Visibility:** public

**Description:** `AddNew` adds a new item to the list: in difference with the `Add` (93) call, no checking is performed to see whether the item is already in the list.

The function returns the index at which the item was added.

If the maximum number of slots is reached, and a new item is being added, the least used item is dropped from the list.

See also: `TCache.Add` (93), `TCache.FindSlot` (94), `TCache.IndexOf` (94), `TCache.Data` (95), `TCache.MRUSlot` (95)

### 6.5.8 `TCache.FindSlot`

**Synopsis:** Find data pointer in the list

**Declaration:** `function FindSlot(AData: Pointer) : PCacheSlot`

**Visibility:** public

**Description:** `FindSlot` checks all items in the list, and returns the slot which contains a data pointer that matches the pointer `AData`.

If no item with data pointer that matches `AData` is found, `Nil` is returned.

For this function to work correctly, the `OnIsDataEqual` (96) event must be set.

**Errors:** If `OnIsDataEqual` is not set, an exception will be raised.

See also: `TCache.IndexOf` (94), `TCache.Add` (93), `TCache.OnIsDataEqual` (96)

### 6.5.9 `TCache.IndexOf`

**Synopsis:** Return index of a data pointer in the list.

**Declaration:** `function IndexOf(AData: Pointer) : Integer`

**Visibility:** public

**Description:** `IndexOF` searches in the list for a slot with data pointer that matches `AData` and returns the index of the slot.

If no item with data pointer that matches `AData` is found, `-1` is returned.

For this function to work correctly, the `OnIsDataEqual` (96) event must be set.

**Errors:** If `OnIsDataEqual` is not set, an exception will be raised.

See also: `TCache.FindSlot` (94), `TCache.Add` (93), `TCache.OnIsDataEqual` (96)

### 6.5.10 TCache.Remove

**Synopsis:** Remove a data item from the list.

**Declaration:** `procedure Remove(AData: Pointer)`

**Visibility:** `public`

**Description:** `Remove` searches the slot which matches `AData` and if it is found, sets the data pointer to `Nil`, thus effectively removing the pointer from the list.

**Errors:** None.

See also: `TCache.FindSlot` (94)

### 6.5.11 TCache.Data

**Synopsis:** Indexed access to data items

**Declaration:** `Property Data[SlotIndex: Integer]: Pointer`

**Visibility:** `public`

**Access:** Read,Write

**Description:** `Data` offers index-based access to the data pointers in the cache. By accessing an item in the list in this manner, the item is moved to the front of the MRU list, i.e. `MRUSlot` (95) will point to the accessed item. The access is both read and write.

The index is zero-based and can maximally be `SlotCount-1` (96). Providing an invalid index will result in an exception.

See also: `TCache.MRUSlot` (95)

### 6.5.12 TCache.MRUSlot

**Synopsis:** Most recent item slot.

**Declaration:** `Property MRUSlot : PCacheSlot`

**Visibility:** `public`

**Access:** Read,Write

**Description:** `MRUSlot` points to the most recent used slot. The most recent used slot is updated when the list is accessed through the `Data` (95) property, or when an item is added to the list with `Add` (93) or `AddNew` (94)

See also: `TCache.Add` (93), `TCache.AddNew` (94), `TCache.Data` (95), `TCache.LRUSlot` (96)



### 6.5.13 TCache.LRUSlot

Synopsis: Last used item

Declaration: `Property LRUSlot : PCacheSlot`

Visibility: public

Access: Read

Description: `LRUSlot` points to the least recent used slot. It is the last item in the chain of slots.

See also: `TCache.Add` (93), `TCache.AddNew` (94), `TCache.Data` (95), `TCache.MRUSlot` (95)

### 6.5.14 TCache.SlotCount

Synopsis: Number of slots in the list

Declaration: `Property SlotCount : Integer`

Visibility: public

Access: Read,Write

Description: `SlotCount` is the number of slots in the list. Its initial value is set when the `TCache` instance is created, but this can be changed at any time. If items are added to the list and the list is full, then the number of slots is not increased, but the least used item is dropped from the list. In that case `OnFreeSlot` (97) is called.

See also: `TCache.Create` (93), `TCache.Data` (95), `TCache.Slots` (96)

### 6.5.15 TCache.Slots

Synopsis: Indexed array to the slots

Declaration: `Property Slots[SlotIndex: Integer]: PCacheSlot`

Visibility: public

Access: Read

Description: `Slots` provides index-based access to the `TCacheSlot` records in the list. Accessing the records directly does not change their position in the MRU list.

The index is zero-based and can maximally be `SlotCount-1` (96). Providing an invalid index will result in an exception.

See also: `TCache.Data` (95), `TCache.SlotCount` (96)

### 6.5.16 TCache.OnIsDataEqual

Synopsis: Event to compare 2 items.

Declaration: `Property OnIsDataEqual : TOnIsDataEqual`

Visibility: public

Access: Read,Write

**Description:** `OnIsDataEqual` is used by `FindSlot` (94) and `IndexOf` (94) to compare items when looking for a particular item. These functions are called by the `Add` (93) method. Failing to set this event will result in an exception. The function should return `True` if the 2 data pointers should be considered equal.

See also: `TCache.FindSlot` (94), `TCache.IndexOf` (94), `TCache.Add` (93)

### 6.5.17 TCache.OnFreeSlot

**Synopsis:** Event called when a slot is freed

**Declaration:** `Property OnFreeSlot : TOnFreeSlot`

**Visibility:** `public`

**Access:** `Read,Write`

**Description:** `OnFreeSlot` is called when an item needs to be freed, i.e. when a new item is added to a full list, and the least recent used item needs to be dropped from the list.

The cache class instance and the index of the item to be removed are passed to the callback.

See also: `TCache.Add` (93), `TCache.AddNew` (94), `TCache.SlotCount` (96)

## Chapter 7

# Reference for unit 'contrns'

### 7.1 Used units

Table 7.1: Used units by unit 'contrns'

Name	Page
Classes	??
sysutils	??

### 7.2 Overview

The contrns unit implements various general-purpose classes:

**Object lists** lists that manage objects instead of pointers, and which automatically dispose of the objects.

**Component lists** lists that manage components instead of pointers, and which automatically dispose the components.

**Class lists** lists that manage class pointers instead of pointers.

**Stacks** Stack classes to push/pop pointers or objects

**Queues** Classes to manage a FIFO list of pointers or objects

**Hash lists** General-purpose Hash lists.

### 7.3 Constants, types and variables

#### 7.3.1 Constants

`MaxHashListSize = Maxint div 16`

`MaxHashListSize` is the maximum number of elements a hash list can contain.

```
MaxHashStrSize = Maxint
```

MaxHashStrSize is the maximum amount of data for the key string values. The key strings are kept in a continuous memory area. This constant determines the maximum size of this memory area.

```
MaxHashTableSize = Maxint div 4
```

MaxHashTableSize is the maximum number of elements in the hash.

```
MaxItemsPerHash = 3
```

MaxItemsPerHash is the threshold above which the hash is expanded. If the number of elements in a hash bucket becomes larger than this value, the hash size is increased.

### 7.3.2 Types

```
PBucket = ^TBucket
```

Pointer to TBucket (99)" type.

```
PHashItem = ^THashItem
```

PHashItem is a pointer type, pointing to the THashItem (101) record.

```
PHashItemList = ^THashItemList
```

PHashItemList is a pointer to the THashItemList (101). It's used in the TFPHashList (118) as a pointer to the memory area containing the hash item records.

```
PHashTable = ^THashTable
```

PHashTable is a pointer to the THashTable (101). It's used in the TFPHashList (118) as a pointer to the memory area containing the hash values.

```
TBucket = record
  Count : Integer;
  Items : TBucketItemArray;
end
```

TBucket describes 1 bucket in the TCustomBucketList (109) class. It is a container for TBucketItem (100) records. It should never be used directly.

```
TBucketArray = Array of TBucket
```

Array of TBucket (99) records.

```
TBucketItem = record
  Item : Pointer;
  Data : Pointer;
end
```

TBucketItem is a record used for internal use in TCustomBucketList (109). It should not be necessary to use it directly.

TBucketItemArray = Array of TBucketItem

Array of TBucketItem records

TBucketListSizes = (bl2,bl4,bl8,bl16,bl32,bl64,bl128,bl256)

Table 7.2: Enumeration values for type TBucketListSizes

Value	Explanation
bl128	List with 128 buckets
bl16	List with 16 buckets
bl2	List with 2 buckets
bl256	List with 256 buckets
bl32	List with 32 buckets
bl4	List with 4 buckets
bl64	List with 64 buckets
bl8	List with 8 buckets

TBucketListSizes is used to set the bucket list size: It specified the number of buckets created by TBucketList (102).

TBucketProc = procedure(AInfo: Pointer;AItem: Pointer;AData: Pointer;  
out AContinue: Boolean)

TBucketProc is the prototype for the #TCustomBucketList.Foreach (??) call. It is the plain procedural form. The Continue parameter can be set to False to indicate that the Foreach call should stop the iteration.

For a procedure of object (a method) callback, see the TBucketProcObject (100) prototype.

TBucketProcObject = procedure(AItem: Pointer;AData: Pointer;  
out AContinue: Boolean) of object

TBucketProcObject is the prototype for the #TCustomBucketList.Foreach (??) call. It is the method (procedure of object) form. The Continue parameter can be set to False to indicate that the Foreach call should stop the iteration.

For a plain procedural callback, see the TBucketProc (100) prototype.

TDataIteratorMethod = procedure(Item: Pointer;const Key: String;  
var Continue: Boolean) of object

TDataIteratorMethod is a callback prototype for the TDataHashTable.Iterate (98) method. It is called for each data pointer in the hash list, passing the key (key) and data pointer (item) for each item in the list. If Continue is set to false, the iteration stops.

THashFunction = function(const S: String;const TableSize: LongWord)  
: LongWord

THashFunction is the prototype for a hash calculation function. It should calculate a hash of string S, where the hash table size is TableSize. The return value should be the hash value.

```
THashItem = record
  HashValue : LongWord;
  StrIndex : Integer;
  NextIndex : Integer;
  Data : Pointer;
end
```

THashItem is used internally in the hash list. It should never be used directly.

```
THashItemList = Array[0..MaxHashListSize-1] of THashItem
```

THashItemList is an array type, primarily used to be able to define the PHashItemList (99) type. It's used in the TFPHashList (118) class.

```
THashTable = Array[0..MaxHashTableSize-1] of Integer
```

THashTable defines an array of integers, used to hold hash values. It's mainly used to define the PHashTable (99) class.

```
THTCustomNodeClass = Class of THTCustomNode
```

THTCustomNodeClass is used by THTCustomHashTable (98) to decide which class should be created for elements in the list.

```
THTNode = THTDataNode
```

THTNode is provided for backwards compatibility.

```
TIteratorMethod = TDataIteratorMethod
```

TIteratorMethod is used in an internal TFPHashTable (98) method.

```
TObjectIteratorMethod = procedure(Item: TObject;const Key: String;
                                   var Continue: Boolean) of object
```

TObjectIteratorMethod is the iterator callback prototype. It is used to iterate over all items in the hash table, and is called with each key value (Key) and associated object (Item). If Continue is set to false, the iteration stops.

```
TObjectListCallback = procedure(data: TObject;arg: pointer) of object
```

TObjectListCallback is used as the prototype for the TFPObjectList.ForEachCall (142) link call when a method should be called. The Data argument will contain each of the objects in the list in turn, and the Data argument will contain the data passed to the ForEachCall call.

```
TObjectListStaticCallback = procedure(data: TObject;arg: pointer)
```

`TObjectListCallback` is used as the prototype for the `TFPObjectList.ForEachCall` (142) link call when a plain procedure should be called. The `Data` argument will contain each of the objects in the list in turn, and the `Data` argument will contain the data passed to the `ForEachCall` call.

```
TStringIteratorMethod = procedure (Item: String; const Key: String;
                                   var Continue: Boolean) of object
```

`TStringIteratorMethod` is the callback prototype for the `Iterate` (111) method. It is called for each element in the hash table, with the string. If `Continue` is set to `false`, the iteration stops.

## 7.4 Procedures and functions

### 7.4.1 RSHash

Synopsis: Standard hash value calculating function.

Declaration: `function RSHash(const S: String; const TableSize: LongWord) : LongWord`

Visibility: default

Description: `RSHash` is the standard hash calculating function used in the `TFPCustomHashTable` (111) hash class. It's Robert Sedgwick's "Algorithms in C" hash function.

Errors: None.

See also: `TFPCustomHashTable` (111)

## 7.5 EDuplicate

### 7.5.1 Description

Exception raised when a key is stored twice in a hash table.

## 7.6 EKeyNotFound

### 7.6.1 Description

Exception raised when a key is not found.

## 7.7 TBucketList

### 7.7.1 Description

`TBucketList` is a descendent of `TCustomBucketList` which allows to specify a bucket count which is a multiple of 2, up to 256 buckets. The size is passed to the constructor and cannot be changed in the lifetime of the bucket list instance.

The buckets for an item is determined by looking at the last bits of the item pointer: For 2 buckets, the last bit is examined, for 4 buckets, the last 2 bits are taken and so on. The algorithm takes into account the average granularity (4) of heap pointers.

### 7.7.2 Method overview

Page	Property	Description
<a href="#">103</a>	Create	Create a new <code>TBucketList</code> instance.

### 7.7.3 TBucketList.Create

Synopsis: Create a new `TBucketList` instance.

Declaration: constructor `Create (ABuckets: TBucketListSizes)`

Visibility: public

Description: `Create` instantiates a new bucketlist instance with a number of buckets determined by `ABuckets`. After creation, the number of buckets can no longer be changed.

Errors: If not enough memory is available to create the instance, an exception may be raised.

See also: `TBucketListSizes` ([100](#))

## 7.8 TClassList

### 7.8.1 Description

`TClassList` is a `Tlist` (??) descendent which stores class references instead of pointers. It introduces no new behaviour other than ensuring all stored pointers are class pointers.

The `OwnsObjects` property as found in `TComponentList` and `TObjectList` is not implemented as there are no actual instances.

### 7.8.2 Method overview

Page	Property	Description
<a href="#">103</a>	Add	Add a new class pointer to the list.
<a href="#">104</a>	Extract	Extract a class pointer from the list.
<a href="#">105</a>	First	Return first non-nil class pointer
<a href="#">104</a>	IndexOf	Search for a class pointer in the list.
<a href="#">105</a>	Insert	Insert a new class pointer in the list.
<a href="#">105</a>	Last	Return last non- <code>Nil</code> class pointer
<a href="#">104</a>	Remove	Remove a class pointer from the list.

### 7.8.3 Property overview

Page	Property	Access	Description
<a href="#">105</a>	Items	rw	Index based access to class pointers.

### 7.8.4 TClassList.Add

Synopsis: Add a new class pointer to the list.

Declaration: function `Add (AClass: TClass) : Integer`

Visibility: public



**Description:** `Add` adds `AClass` to the list, and returns the position at which it was added. It simply overrides the `TList` (??) behaviour, and introduces no new functionality.

**Errors:** If not enough memory is available to expand the list, an exception may be raised.

**See also:** `TClassList.Extract` (104), `#rtl.classes.tlist.add` (??)

### 7.8.5 TClassList.Extract

**Synopsis:** Extract a class pointer from the list.

**Declaration:** `function Extract (Item: TClass) : TClass`

**Visibility:** public

**Description:** `Extract` extracts a class pointer `Item` from the list, if it is present in the list. It returns the extracted class pointer, or `Nil` if the class pointer was not present in the list. It simply overrides the implementation in `TList` so it accepts a class pointer instead of a simple pointer. No new behaviour is introduced.

**Errors:** None.

**See also:** `TClassList.Remove` (104), `#rtl.classes.Tlist.Extract` (??)

### 7.8.6 TClassList.Remove

**Synopsis:** Remove a class pointer from the list.

**Declaration:** `function Remove (AClass: TClass) : Integer`

**Visibility:** public

**Description:** `Remove` removes a class pointer `Item` from the list, if it is present in the list. It returns the index of the removed class pointer, or `-1` if the class pointer was not present in the list. It simply overrides the implementation in `TList` so it accepts a class pointer instead of a simple pointer. No new behaviour is introduced.

**Errors:** None.

**See also:** `TClassList.Extract` (104), `#rtl.classes.Tlist.Remove` (??)

### 7.8.7 TClassList.IndexOf

**Synopsis:** Search for a class pointer in the list.

**Declaration:** `function IndexOf (AClass: TClass) : Integer`

**Visibility:** public

**Description:** `IndexOf` searches for `AClass` in the list, and returns its position if it was found, or `-1` if it was not found in the list.

**Errors:** None.

**See also:** `#rtl.classes.tlist.indexof` (??)

### 7.8.8 TClassList.First

Synopsis: Return first non-nil class pointer

Declaration: `function First : TClass`

Visibility: public

Description: `First` returns a reference to the first non-`Nil` class pointer in the list. If no non-`Nil` element is found, `Nil` is returned.

Errors: None.

See also: `TClassList.Last` (105), `TClassList.Pack` (103)

### 7.8.9 TClassList.Last

Synopsis: Return last non-`Nil` class pointer

Declaration: `function Last : TClass`

Visibility: public

Description: `Last` returns a reference to the last non-`Nil` class pointer in the list. If no non-`Nil` element is found, `Nil` is returned.

Errors: None.

See also: `TClassList.First` (105), `TClassList.Pack` (103)

### 7.8.10 TClassList.Insert

Synopsis: Insert a new class pointer in the list.

Declaration: `procedure Insert (Index: Integer; AClass: TClass)`

Visibility: public

Description: `Insert` inserts a class pointer in the list at position `Index`. It simply overrides the parent implementation so it only accepts class pointers. It introduces no new behaviour.

Errors: None.

See also: `#rtl.classes.TList.Insert` (??), `TClassList.Add` (103), `TClassList.Remove` (104)

### 7.8.11 TClassList.Items

Synopsis: Index based access to class pointers.

Declaration: `Property Items[Index: Integer]: TClass; default`

Visibility: public

Access: Read, Write

Description: `Items` provides index-based access to the class pointers in the list. `TClassList` overrides the default `Items` implementation of `TList` so it returns class pointers instead of pointers.

See also: `#rtl.classes.TList.Items` (??), `#rtl.classes.TList.Count` (??)

## 7.9 TComponentList

### 7.9.1 Description

`TComponentList` is a `TObjectList` (149) descendent which has as the default array property `TComponents` (??) instead of objects. It overrides some methods so only components can be added.

In difference with `TObjectList` (149), `TComponentList` removes any `TComponent` from the list if the `TComponent` instance was freed externally. It uses the `FreeNotification` mechanism for this.

### 7.9.2 Method overview

Page	Property	Description
<a href="#">106</a>	Add	Add a component to the list.
<a href="#">106</a>	Destroy	Destroys the instance
<a href="#">107</a>	Extract	Remove a component from the list without destroying it.
<a href="#">108</a>	First	First non-nil instance in the list.
<a href="#">107</a>	IndexOf	Search for an instance in the list
<a href="#">108</a>	Insert	Insert a new component in the list
<a href="#">108</a>	Last	Last non-nil instance in the list.
<a href="#">107</a>	Remove	Remove a component from the list, possibly destroying it.

### 7.9.3 Property overview

Page	Property	Access	Description
<a href="#">108</a>	Items	rw	Index-based access to the elements in the list.

### 7.9.4 TComponentList.Destroy

Synopsis: Destroys the instance

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` unhooks the free notification handler and then calls the inherited `destroy` to clean up the `TComponentList` instance.

Errors: None.

See also: `TObjectList` (149), `#rtl.classes.TComponent` (??)

### 7.9.5 TComponentList.Add

Synopsis: Add a component to the list.

Declaration: `function Add(AComponent: TComponent) : Integer`

Visibility: `public`

Description: `Add` overrides the `Add` operation of it's ancestors, so it only accepts `TComponent` instances. It introduces no new behaviour.

The function returns the index at which the component was added.

Errors: If not enough memory is available to expand the list, an exception may be raised.

See also: `TObjectList.Add` ([98](#))

### 7.9.6 TComponentList.Extract

**Synopsis:** Remove a component from the list without destroying it.

**Declaration:** `function Extract (Item: TComponent) : TComponent`

**Visibility:** public

**Description:** `Extract` removes a component (`Item`) from the list, without destroying it. It overrides the implementation of `TObjectList` ([149](#)) so only `TComponent` descendents can be extracted. It introduces no new behaviour.

`Extract` returns the instance that was extracted, or `Nil` if no instance was found.

See also: `TComponentList.Remove` ([107](#)), `TObjectList.Extract` ([150](#))

### 7.9.7 TComponentList.Remove

**Synopsis:** Remove a component from the list, possibly destroying it.

**Declaration:** `function Remove (AComponent: TComponent) : Integer`

**Visibility:** public

**Description:** `Remove` removes `item` from the list, and if the list owns it's items, it also destroys it. It returns the index of the item that was removed, or -1 if no item was removed.

`Remove` simply overrides the implementation in `TObjectList` ([149](#)) so it only accepts `TComponent` descendents. It introduces no new behaviour.

**Errors:** None.

See also: `TComponentList.Extract` ([107](#)), `TObjectList.Remove` ([151](#))

### 7.9.8 TComponentList.IndexOf

**Synopsis:** Search for an instance in the list

**Declaration:** `function IndexOf (AComponent: TComponent) : Integer`

**Visibility:** public

**Description:** `IndexOf` searches for an instance in the list and returns it's position in the list. The position is zero-based. If no instance is found, -1 is returned.

`IndexOf` just overrides the implementation of the parent class so it accepts only `TComponent` instances. It introduces no new behaviour.

**Errors:** None.

See also: `TObjectList.IndexOf` ([151](#))

### 7.9.9 TComponentList.First

Synopsis: First non-nil instance in the list.

Declaration: `function First : TComponent`

Visibility: public

Description: `First` overrides the implementation of it's ancestors to return the first non-nil instance of `TComponent` in the list. If no non-nil instance is found, `Nil` is returned.

Errors: None.

See also: `TComponentList.Last` ([108](#)), `TObjectList.First` ([152](#))

### 7.9.10 TComponentList.Last

Synopsis: Last non-nil instance in the list.

Declaration: `function Last : TComponent`

Visibility: public

Description: `Last` overrides the implementation of it's ancestors to return the last non-nil instance of `TComponent` in the list. If no non-nil instance is found, `Nil` is returned.

Errors: None.

See also: `TComponentList.First` ([108](#)), `TObjectList.Last` ([152](#))

### 7.9.11 TComponentList.Insert

Synopsis: Insert a new component in the list

Declaration: `procedure Insert (Index: Integer; AComponent: TComponent)`

Visibility: public

Description: `Insert` inserts a `TComponent` instance (`AComponent`) in the list at position `Index`. It simply overrides the parent implementation so it only accepts `TComponent` instances. It introduces no new behaviour.

Errors: None.

See also: `TObjectList.Insert` ([152](#)), `TComponentList.Add` ([106](#)), `TComponentList.Remove` ([107](#))

### 7.9.12 TComponentList.Items

Synopsis: Index-based access to the elements in the list.

Declaration: `Property Items[Index: Integer]: TComponent; default`

Visibility: public

Access: Read,Write

Description: `Items` provides access to the components in the list using an index. It simply overrides the default property of the parent classes so it returns/accepts `TComponent` instances only. Note that the index is zero based.

See also: `TObjectList.Items` ([153](#))

## 7.10 TCustomBucketList

### 7.10.1 Description

TCustomBucketList is an associative list using buckets for storage. It scales better than a regular TList (??) list class, especially when an item must be searched in the list.

Since the list associates a data pointer with each item pointer, it follows that each item pointer must be unique, and can be added to the list only once.

The TCustomBucketList class does not determine the number of buckets or the bucket hash mechanism, this must be done by descendent classes such as TBucketList (102). TCustomBucketList only takes care of storage and retrieval of items in the various buckets.

Because TCustomBucketList is an abstract class - it does not determine the number of buckets - one should never instantiate an instance of TCustomBucketList, but always use a descendent class such as TCustomBucketList (109).

### 7.10.2 Method overview

Page	Property	Description
<a href="#">110</a>	Add	Add an item to the list
<a href="#">110</a>	Assign	Assign one bucket list to another
<a href="#">109</a>	Clear	Clear the list
<a href="#">109</a>	Destroy	Frees the bucketlist from memory
<a href="#">110</a>	Exists	Check if an item exists in the list.
<a href="#">110</a>	Find	Find an item in the list
<a href="#">111</a>	ForEach	Loop over all items.
<a href="#">111</a>	Remove	Remove an item from the list.

### 7.10.3 Property overview

Page	Property	Access	Description
<a href="#">111</a>	Data	rw	Associative array for data pointers

### 7.10.4 TCustomBucketList.Destroy

Synopsis: Frees the bucketlist from memory

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` frees all storage for the buckets from memory. The items themselves are not freed from memory.

### 7.10.5 TCustomBucketList.Clear

Synopsis: Clear the list

Declaration: `procedure Clear`

Visibility: `public`

Description: `Clear` clears the list. The items and their data themselves are not disposed of, this must be done separately. `Clear` only removes all references to the items from the list.

Errors: None.

See also: `TCustomBucketList.Add` ([110](#))

### 7.10.6 `TCustomBucketList.Add`

Synopsis: Add an item to the list

Declaration: `function Add(AItem: Pointer; AData: Pointer) : Pointer`

Visibility: `public`

Description: `Add` adds `AItem` with it's associated `AData` to the list and returns `AData`.

Errors: If `AItem` is already in the list, an `EListError` exception will be raised.

See also: `TCustomBucketList.Exists` ([110](#)), `TCustomBucketList.Clear` ([109](#))

### 7.10.7 `TCustomBucketList.Assign`

Synopsis: Assign one bucket list to another

Declaration: `procedure Assign(AList: TCustomBucketList)`

Visibility: `public`

Description: `Assign` is implemented by `TCustomBucketList` to copy the contents of another bucket list to the bucket list. It clears the contents prior to the copy operation.

See also: `TCustomBucketList.Add` ([110](#)), `TCustomBucketList.Clear` ([109](#))

### 7.10.8 `TCustomBucketList.Exists`

Synopsis: Check if an item exists in the list.

Declaration: `function Exists(AItem: Pointer) : Boolean`

Visibility: `public`

Description: `Exists` searches the list and returns `True` if the `AItem` is already present in the list. If the item is not yet in the list, `False` is returned.

If the data pointer associated with `AItem` is also needed, then it is better to use `Find` ([110](#)).

See also: `TCustomBucketList.Find` ([110](#))

### 7.10.9 `TCustomBucketList.Find`

Synopsis: Find an item in the list

Declaration: `function Find(AItem: Pointer; out AData: Pointer) : Boolean`

Visibility: `public`

Description: `Find` searches for `AItem` in the list and returns the data pointer associated with it in `AData` if the item was found. In that case the return value is `True`. If `AItem` is not found in the list, `False` is returned.

See also: `TCustomBucketList.Exists` ([110](#))

### 7.10.10 TCustomBucketList.ForEach

Synopsis: Loop over all items.

Declaration: `function ForEach(AProc: TBucketProc; AInfo: Pointer) : Boolean`  
`function ForEach(AProc: TBucketProcObject) : Boolean`

Visibility: public

Description: Foreach loops over all items in the list and calls AProc, passing it in turn each item in the list.

AProc exists in 2 variants: one which is a simple procedure, and one which is a method. In the case of the simple procedure, the AInfo argument is passed as well in each call to AProc.

The loop stops when all items have been processed, or when the AContinue argument of AProc contains False on return.

The result of the function is True if all items were processed, or False if the loop was interrupted with a AContinue return of False.

Errors: None.

See also: TCustomBucketList.Data ([111](#))

### 7.10.11 TCustomBucketList.Remove

Synopsis: Remove an item from the list.

Declaration: `function Remove(AItem: Pointer) : Pointer`

Visibility: public

Description: Remove removes AItem from the list, and returns the associated data pointer of the removed item. If the item was not in the list, then Nil is returned.

See also: TCustomBucketList.Find ([110](#))

### 7.10.12 TCustomBucketList.Data

Synopsis: Associative array for data pointers

Declaration: `Property Data[AItem: Pointer]: Pointer; default`

Visibility: public

Access: Read, Write

Description: Data provides direct access to the Data pointers associated with the AItem pointers. If AItem is not in the list of pointers, an EListError exception will be raised.

See also: TCustomBucketList.Find ([110](#)), TCustomBucketList.Exists ([110](#))

## 7.11 TFPCustomHashTable

### 7.11.1 Description

TFPCustomHashTable is a general-purpose hashing class. It can store string keys and pointers associated with these strings. The hash mechanism is configurable and can be optionally be specified



when a new instance of the class is created; A default hash mechanism is implemented in `RSHash` (102).

A `TFPHasList` should be used when fast lookup of data based on some key is required. The other container objects only offer linear search methods, while the hash list offers faster search mechanisms.

### 7.11.2 Method overview

Page	Property	Description
113	<code>ChangeTableSize</code>	Change the table size of the hash table.
113	<code>Clear</code>	Clear the hash table.
112	<code>Create</code>	Instantiate a new <code>TFPCustomHashTable</code> instance using the default hash mechanism
112	<code>CreateWith</code>	Instantiate a new <code>TFPCustomHashTable</code> instance with given algorithm and size
114	<code>Delete</code>	Delete a key from the hash list.
113	<code>Destroy</code>	Free the hash table.
114	<code>Find</code>	Search for an item with a certain key value.
114	<code>IsEmpty</code>	Check if the hash table is empty.

### 7.11.3 Property overview

Page	Property	Access	Description
116	<code>AVGChainLen</code>	r	Average chain length
115	<code>Count</code>	r	Number of items in the hash table.
117	<code>Density</code>	r	Number of filled slots
114	<code>HashFunction</code>	rw	Hash function currently in use
115	<code>HashTable</code>	r	Hash table instance
115	<code>HashTableSize</code>	rw	Size of the hash table
116	<code>LoadFactor</code>	r	Fraction of count versus size
116	<code>MaxChainLength</code>	r	Maximum chain length
117	<code>NumberOfCollisions</code>	r	Number of extra items
116	<code>VoidSlots</code>	r	Number of empty slots in the hash table.

### 7.11.4 TFPCustomHashTable.Create

**Synopsis:** Instantiate a new `TFPCustomHashTable` instance using the default hash mechanism

**Declaration:** `constructor Create`

**Visibility:** `public`

**Description:** `Create` creates a new instance of `TFPCustomHashTable` with hash size 196613 and hash algorithm `RSHash` (102)

**Errors:** If no memory is available, an exception may be raised.

**See also:** `TFPCustomHashTable.CreateWith` (112)

### 7.11.5 TFPCustomHashTable.CreateWith

**Synopsis:** Instantiate a new `TFPCustomHashTable` instance with given algorithm and size

**Declaration:** `constructor CreateWith(AHashTableSize: LongWord;  
aHashFunc: THashFunction)`

**Visibility:** `public`

**Description:** `CreateWith` creates a new instance of `TFPCustomHashTable` with hash size `AHashTableSize` and hash calculating algorithm `aHashFunc`.

**Errors:** If no memory is available, an exception may be raised.

**See also:** `TFPCustomHashTable.Create` ([112](#))

### 7.11.6 TFPCustomHashTable.Destroy

**Synopsis:** Free the hash table.

**Declaration:** `destructor Destroy; Override`

**Visibility:** `public`

**Description:** `Destroy` removes the hash table from memory. If any data was associated with the keys in the hash table, then this data is not freed. This must be done by the programmer.

**Errors:** None.

**See also:** `TFPCustomHashTable.Destroy` ([113](#)), `TFPCustomHashTable.Create` ([112](#)), `TFPCustomHashTable.CreateWith` ([112](#)), `THTCustomNode.Data` ([145](#))

### 7.11.7 TFPCustomHashTable.ChangeTableSize

**Synopsis:** Change the table size of the hash table.

**Declaration:** `procedure ChangeTableSize(const ANewSize: LongWord); Virtual`

**Visibility:** `public`

**Description:** `ChangeTableSize` changes the size of the hash table: it recomputes the hash value for all of the keys in the table, so this is an expensive operation.

**Errors:** If no memory is available, an exception may be raised.

**See also:** `TFPCustomHashTable.HashTableSize` ([115](#))

### 7.11.8 TFPCustomHashTable.Clear

**Synopsis:** Clear the hash table.

**Declaration:** `procedure Clear; Virtual`

**Visibility:** `public`

**Description:** `Clear` removes all keys and their associated data from the hash table. The data itself is not freed from memory, this should be done by the programmer.

**Errors:** None.

**See also:** `TFPCustomHashTable.Destroy` ([113](#))

### 7.11.9 TFPCustomHashTable.Delete

Synopsis: Delete a key from the hash list.

Declaration: `procedure Delete(const aKey: String); Virtual`

Visibility: `public`

Description: `Delete` deletes all keys with value `AKey` from the hash table. It does not free the data associated with key. If `AKey` is not in the list, nothing is removed.

Errors: None.

See also: `TFPCustomHashTable.Find` ([114](#)), `TFPCustomHashTable.Add` ([111](#))

### 7.11.10 TFPCustomHashTable.Find

Synopsis: Search for an item with a certain key value.

Declaration: `function Find(const aKey: String) : THTCustomNode`

Visibility: `public`

Description: `Find` searches for the `THTCustomNode` ([145](#)) instance with key value equal to `Akey` and if it finds it, it returns the instance. If no matching value is found, `Nil` is returned.

Note that the instance returned by this function cannot be freed; If it should be removed from the hash table, the `Delete` ([114](#)) method should be used instead.

Errors: None.

See also: `TFPCustomHashTable.Add` ([111](#)), `TFPCustomHashTable.Delete` ([114](#))

### 7.11.11 TFPCustomHashTable.IsEmpty

Synopsis: Check if the hash table is empty.

Declaration: `function IsEmpty : Boolean`

Visibility: `public`

Description: `IsEmpty` returns `True` if the hash table contains no elements, or `False` if there are still elements in the hash table.

Errors:

See also: `TFPCustomHashTable.Count` ([115](#)), `TFPCustomHashTable.HashTableSize` ([115](#)), `TFPCustomHashTable.AVGChainLen` ([116](#)), `TFPCustomHashTable.MaxChainLength` ([116](#))

### 7.11.12 TFPCustomHashTable.HashFunction

Synopsis: Hash function currently in use

Declaration: `Property HashFunction : THashFunction`

Visibility: `public`

Access: Read,Write

**Description:** `HashFunction` is the hash function currently in use to calculate hash values from keys. The property can be set, this simply calls `SetHashFunction` (111). Note that setting the hash function does NOT the hash value of all keys to be recomputed, so changing the value while there are still keys in the table is not a good idea.

See also: `TFPCustomHashTable.SetHashFunction` (111), `TFPCustomHashTable.HashTableSize` (115)

### 7.11.13 `TFPCustomHashTable.Count`

**Synopsis:** Number of items in the hash table.

**Declaration:** `Property Count : LongWord`

**Visibility:** public

**Access:** Read

**Description:** `Count` is the number of items in the hash table.

See also: `TFPCustomHashTable.IsEmpty` (114), `TFPCustomHashTable.HashTableSize` (115), `TFPCustomHashTable.AVGChainLen` (116), `TFPCustomHashTable.MaxChainLength` (116)

### 7.11.14 `TFPCustomHashTable.HashTableSize`

**Synopsis:** Size of the hash table

**Declaration:** `Property HashTableSize : LongWord`

**Visibility:** public

**Access:** Read,Write

**Description:** `HashTableSize` is the size of the hash table. It can be set, in which case it will be rounded to the nearest prime number suitable for RSHash.

See also: `TFPCustomHashTable.IsEmpty` (114), `TFPCustomHashTable.Count` (115), `TFPCustomHashTable.AVGChainLen` (116), `TFPCustomHashTable.MaxChainLength` (116), `TFPCustomHashTable.VoidSlots` (116), `TFPCustomHashTable.Density` (117)

### 7.11.15 `TFPCustomHashTable.HashTable`

**Synopsis:** Hash table instance

**Declaration:** `Property HashTable : TFPObjectList`

**Visibility:** public

**Access:** Read

**Description:** `TFPCustomHashTable` is the internal list object (`TFPObjectList` (137)) used for the hash table. Each element in this table is again a `TFPObjectList` (137) instance or `Nil`.

### 7.11.16 TFPCustomHashTable.VoidSlots

Synopsis: Number of empty slots in the hash table.

Declaration: `Property VoidSlots : LongWord`

Visibility: `public`

Access: `Read`

Description: `VoidSlots` is the number of empty slots in the hash table. Calculating this is an expensive operation.

See also: `TFPCustomHashTable.IsEmpty` (114), `TFPCustomHashTable.Count` (115), `TFPCustomHashTable.AVGChainLen` (116), `TFPCustomHashTable.MaxChainLength` (116), `TFPCustomHashTable.LoadFactor` (116), `TFPCustomHashTable.Density` (117), `TFPCustomHashTable.NumberOfCollisions` (117)

### 7.11.17 TFPCustomHashTable.LoadFactor

Synopsis: Fraction of count versus size

Declaration: `Property LoadFactor : double`

Visibility: `public`

Access: `Read`

Description: `LoadFactor` is the ratio of elements in the table versus table size. Ideally, this should be as small as possible.

See also: `TFPCustomHashTable.IsEmpty` (114), `TFPCustomHashTable.Count` (115), `TFPCustomHashTable.AVGChainLen` (116), `TFPCustomHashTable.MaxChainLength` (116), `TFPCustomHashTable.VoidSlots` (116), `TFPCustomHashTable.Density` (117), `TFPCustomHashTable.NumberOfCollisions` (117)

### 7.11.18 TFPCustomHashTable.AVGChainLen

Synopsis: Average chain length

Declaration: `Property AVGChainLen : double`

Visibility: `public`

Access: `Read`

Description: `AVGChainLen` is the average chain length, i.e. the ratio of elements in the table versus the number of filled slots. Calculating this is an expensive operation.

See also: `TFPCustomHashTable.IsEmpty` (114), `TFPCustomHashTable.Count` (115), `TFPCustomHashTable.LoadFactor` (116), `TFPCustomHashTable.MaxChainLength` (116), `TFPCustomHashTable.VoidSlots` (116), `TFPCustomHashTable.Density` (117), `TFPCustomHashTable.NumberOfCollisions` (117)

### 7.11.19 TFPCustomHashTable.MaxChainLength

Synopsis: Maximum chain length

Declaration: `Property MaxChainLength : LongWord`

Visibility: `public`

Access: Read

Description: `MaxChainLength` is the length of the longest chain in the hash table. Calculating this is an expensive operation.

See also: `TFPCustomHashTable.IsEmpty` (114), `TFPCustomHashTable.Count` (115), `TFPCustomHashTable.LoadFactor` (116), `TFPCustomHashTable.AvgChainLength` (111), `TFPCustomHashTable.VoidSlots` (116), `TFPCustomHashTable.Density` (117), `TFPCustomHashTable.NumberOfCollisions` (117)

### 7.11.20 `TFPCustomHashTable.NumberOfCollisions`

Synopsis: Number of extra items

Declaration: Property `NumberOfCollisions` : LongWord

Visibility: public

Access: Read

Description: `NumberOfCollisions` is the number of items which are not the first item in a chain. If this number is too big, the hash size may be too small.

See also: `TFPCustomHashTable.IsEmpty` (114), `TFPCustomHashTable.Count` (115), `TFPCustomHashTable.LoadFactor` (116), `TFPCustomHashTable.AvgChainLength` (111), `TFPCustomHashTable.VoidSlots` (116), `TFPCustomHashTable.Density` (117)

### 7.11.21 `TFPCustomHashTable.Density`

Synopsis: Number of filled slots

Declaration: Property `Density` : LongWord

Visibility: public

Access: Read

Description: `Density` is the number of filled slots in the hash table.

See also: `TFPCustomHashTable.IsEmpty` (114), `TFPCustomHashTable.Count` (115), `TFPCustomHashTable.LoadFactor` (116), `TFPCustomHashTable.AvgChainLength` (111), `TFPCustomHashTable.VoidSlots` (116), `TFPCustomHashTable.Density` (117)

## 7.12 `TFPDataHashTable`

### 7.12.1 Description

`TFPDataHashTable` is a `TFPCustomHashTable` (111) descendent which stores simple data pointers together with the keys. In case the data associated with the keys are objects, it's better to use `TFPObjectHashTable` (135), or for string data, `TFPStringHashTable` (144) is more suitable. The data pointers are exposed with their keys through the `Items` (118) property.

### 7.12.2 Method overview

Page	Property	Description
118	Add	Add a data pointer to the list.

### 7.12.3 Property overview

Page	Property	Access	Description
<a href="#">118</a>	Items	rw	Key-based access to the items in the table

### 7.12.4 TFPDataHashTable.Add

Synopsis: Add a data pointer to the list.

Declaration: `procedure Add(const aKey: String; AItem: pointer); Virtual`

Visibility: `public`

Description: Add adds a data pointer (AItem) to the list with key AKey.

Errors: If AKey already exists in the table, an exception is raised.

See also: TFPDataHashTable.Items ([118](#))

### 7.12.5 TFPDataHashTable.Items

Synopsis: Key-based access to the items in the table

Declaration: `Property Items[index: String]: Pointer; default`

Visibility: `public`

Access: Read, Write

Description: Items provides access to the items in the hash table using their key: the array index Index is the key. A key which is not present will result in an Nil pointer.

See also: TFPStringHashTable.Add ([144](#))

## 7.13 TFPHashList

### 7.13.1 Description

TFPHashList implements a fast hash class. The class is built for speed, therefore the key values can be shortstrings only, and the data can only be pointers.

if a base class for an own hash class is wanted, the TFPCustomHashTable ([111](#)) class can be used. If a hash class for objects is needed instead of pointers, the TFPHashObjectList ([128](#)) class can be used.

### 7.13.2 Method overview

Page	Property	Description
<a href="#">120</a>	Add	Add a new key/data pair to the list
<a href="#">120</a>	Clear	Clear the list
<a href="#">119</a>	Create	Create a new instance of the hashlist
<a href="#">121</a>	Delete	Delete an item from the list.
<a href="#">119</a>	Destroy	Removes an instance of the hashlist from the heap
<a href="#">121</a>	Error	Raise an error
<a href="#">121</a>	Expand	Expand the list
<a href="#">122</a>	Extract	Extract a pointer from the list
<a href="#">122</a>	Find	Find data associated with key
<a href="#">122</a>	FindIndexOf	Return index of named item.
<a href="#">123</a>	FindWithHash	Find first element with given name and hash value
<a href="#">124</a>	ForEachCall	Call a procedure for each element in the list
<a href="#">121</a>	GetNextCollision	Get next collision number
<a href="#">120</a>	HashOfIndex	Return the hash value of an item by index
<a href="#">122</a>	IndexOf	Return the index of the data pointer
<a href="#">120</a>	NameOfIndex	Returns the key name of an item by index
<a href="#">123</a>	Pack	Remove nil pointers from the list
<a href="#">123</a>	Remove	Remove first instance of a pointer
<a href="#">123</a>	Rename	Rename a key
<a href="#">124</a>	ShowStatistics	Return some statistics for the list.

### 7.13.3 Property overview

Page	Property	Access	Description
<a href="#">124</a>	Capacity	rw	Capacity of the list.
<a href="#">124</a>	Count	rw	Current number of elements in the list.
<a href="#">125</a>	Items	rw	Indexed array with pointers
<a href="#">125</a>	List	r	Low-level hash list
<a href="#">125</a>	Strs	r	Low-level memory area with strings.

### 7.13.4 TFPHashList.Create

Synopsis: Create a new instance of the hashlist

Declaration: `constructor Create`

Visibility: `public`

Description: `Create` creates a new instance of `TFPHashList` on the heap and sets the hash capacity to 1.

See also: `TFPHashList.Destroy` ([119](#))

### 7.13.5 TFPHashList.Destroy

Synopsis: Removes an instance of the hashlist from the heap

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` cleans up the memory structures maintained by the hashlist and removes the `TFPHashList` instance from the heap.

`Destroy` should not be called directly, it's better to use `Free` or `FreeAndNil` instead.



See also: `TFPHashList.Create` ([119](#)), `TFPHashList.Clear` ([120](#))

### 7.13.6 TFPHashList.Add

Synopsis: Add a new key/data pair to the list

Declaration: `function Add(const AName: shortstring; Item: Pointer) : Integer`

Visibility: public

Description: `Add` adds a new data pointer (`Item`) with key `AName` to the list. It returns the position of the item in the list.

Errors: If not enough memory is available to hold the key and data, an exception may be raised.

See also: `TFPHashList.Extract` ([122](#)), `TFPHashList.Remove` ([123](#)), `TFPHashList.Delete` ([121](#))

### 7.13.7 TFPHashList.Clear

Synopsis: Clear the list

Declaration: `procedure Clear`

Visibility: public

Description: `Clear` removes all items from the list. It does not free the data items themselves. It frees all memory needed to contain the items.

Errors: None.

See also: `TFPHashList.Extract` ([122](#)), `TFPHashList.Remove` ([123](#)), `TFPHashList.Delete` ([121](#)), `TFPHashList.Add` ([120](#))

### 7.13.8 TFPHashList.NameOfIndex

Synopsis: Returns the key name of an item by index

Declaration: `function NameOfIndex(Index: Integer) : ShortString`

Visibility: public

Description: `NameOfIndex` returns the key name of the item at position `Index`.

Errors: If `Index` is out of the valid range, an exception is raised.

See also: `TFPHashList.HashOfIndex` ([120](#)), `TFPHashList.Find` ([122](#)), `TFPHashList.FindIndexOf` ([122](#)), `TFPHashList.FindWithHash` ([123](#))

### 7.13.9 TFPHashList.HashOfIndex

Synopsis: Return the hash value of an item by index

Declaration: `function HashOfIndex(Index: Integer) : LongWord`

Visibility: public

Description: `HashOfIndex` returns the hash value of the item at position `Index`.

Errors: If `Index` is out of the valid range, an exception is raised.

See also: `TFPHashList.HashOfName` (118), `TFPHashList.Find` (122), `TFPHashList.FindIndexOf` (122), `TFPHashList.FindWithHash` (123)

### 7.13.10 TFPHashList.GetNextCollision

Synopsis: Get next collision number

Declaration: `function GetNextCollision(Index: Integer) : Integer`

Visibility: public

Description: `GetNextCollision` returns the next collision in hash item `Index`. This is the count of items with the same hash.means that the next it

Errors:

### 7.13.11 TFPHashList.Delete

Synopsis: Delete an item from the list.

Declaration: `procedure Delete(Index: Integer)`

Visibility: public

Description: `Delete` deletes the item at position `Index`. The data to which it points is not freed from memory.

Errors: `TFPHashList.Extract` (122)`TFPHashList.Remove` (123)`TFPHashList.Add` (120)

### 7.13.12 TFPHashList.Error

Synopsis: Raise an error

Declaration: `procedure Error(const Msg: String;Data: PtrInt)`

Visibility: public

Description: `Error` raises an `EListError` exception, with message `Msg`. The `Data` pointer is used to format the message.

### 7.13.13 TFPHashList.Expand

Synopsis: Expand the list

Declaration: `function Expand : TFPHashList`

Visibility: public

Description: `Expand` enlarges the capacity of the list if the maximum capacity was reached. It returns itself.

Errors: If not enough memory is available, an exception may be raised.

See also: `TFPHashList.Clear` (120)

### 7.13.14 TFPHashList.Extract

Synopsis: Extract a pointer from the list

Declaration: `function Extract(item: Pointer) : Pointer`

Visibility: public

Description: `Extract` removes the data item from the list, if it is in the list. It returns the pointer if it was removed from the list, `Nil` otherwise.

`Extract` does a linear search, and is not very efficient.

See also: `TFPHashList.Delete` (121), `TFPHashList.Remove` (123), `TFPHashList.Clear` (120)

### 7.13.15 TFPHashList.IndexOf

Synopsis: Return the index of the data pointer

Declaration: `function IndexOf(Item: Pointer) : Integer`

Visibility: public

Description: `IndexOf` returns the index of the first occurrence of pointer `Item`. If the item is not in the list, -1 is returned.

The performed search is linear, and not very efficient.

See also: `TFPHashList.HashOfIndex` (120), `TFPHashList.NameOfIndex` (120), `TFPHashList.Find` (122), `TFPHashList.FindIndexOf` (122), `TFPHashList.FindWithHash` (123)

### 7.13.16 TFPHashList.Find

Synopsis: Find data associated with key

Declaration: `function Find(const AName: shortstring) : Pointer`

Visibility: public

Description: `Find` searches (using the hash) for the data item associated with item `AName` and returns the data pointer associated with it. If the item is not found, `Nil` is returned. It uses the hash value of the key to perform the search.

See also: `TFPHashList.HashOfIndex` (120), `TFPHashList.NameOfIndex` (120), `TFPHashList.IndexOf` (122), `TFPHashList.FindIndexOf` (122), `TFPHashList.FindWithHash` (123)

### 7.13.17 TFPHashList.FindIndexOf

Synopsis: Return index of named item.

Declaration: `function FindIndexOf(const AName: shortstring) : Integer`

Visibility: public

Description: `FindIndexOf` returns the index of the key `AName`, or -1 if the key does not exist in the list. It uses the hash value to search for the key.

See also: `TFPHashList.HashOfIndex` (120), `TFPHashList.NameOfIndex` (120), `TFPHashList.IndexOf` (122), `TFPHashList.Find` (122), `TFPHashList.FindWithHash` (123)

### 7.13.18 TFPHashList.FindWithHash

Synopsis: Find first element with given name and hash value

Declaration: `function FindWithHash(const AName: shortstring; AHash: LongWord)  
: Pointer`

Visibility: public

Description: `FindWithHash` searches for the item with key `AName`. It uses the provided hash value `AHash` to perform the search. If the item exists, the data pointer is returned, if not, the result is `Nil`.

See also: `TFPHashList.HashOfIndex` ([120](#)), `TFPHashList.NameOfIndex` ([120](#)), `TFPHashList.IndexOf` ([122](#)), `TFPHashList.Find` ([122](#)), `TFPHashList.FindIndexOf` ([122](#))

### 7.13.19 TFPHashList.Rename

Synopsis: Rename a key

Declaration: `function Rename(const AOldName: shortstring; const ANewName: shortstring)  
: Integer`

Visibility: public

Description: `Rename` renames key `AOldname` to `ANewName`. The hash value is recomputed and the item is moved in the list to it's new position.

Errors: If an item with `ANewName` already exists, an exception will be raised.

### 7.13.20 TFPHashList.Remove

Synopsis: Remove first instance of a pointer

Declaration: `function Remove(Item: Pointer) : Integer`

Visibility: public

Description: `Remove` removes the first occurrence of the data pointer `Item` in the list, if it is present. The return value is the removed data pointer, or `Nil` if no data pointer was removed.

See also: `TFPHashList.Delete` ([121](#)), `TFPHashList.Clear` ([120](#)), `TFPHashList.Extract` ([122](#))

### 7.13.21 TFPHashList.Pack

Synopsis: Remove nil pointers from the list

Declaration: `procedure Pack`

Visibility: public

Description: `Pack` removes all `Nil` items from the list, and frees all unused memory.

See also: `TFPHashList.Clear` ([120](#))

### 7.13.22 TFPHashList.ShowStatistics

Synopsis: Return some statistics for the list.

Declaration: `procedure ShowStatistics`

Visibility: `public`

Description: `ShowStatistics` prints some information about the hash list to standard output. It prints the following values:

**HashSize**Size of the hash table

**HashMean**Mean hash value

**HashStdDev**Standard deviation of hash values

**ListSize**Size and capacity of the list

**StringSize**Size and capacity of key strings

### 7.13.23 TFPHashList.ForEachCall

Synopsis: Call a procedure for each element in the list

Declaration: `procedure ForEachCall(proc2call: TListCallback;arg: pointer)`  
`procedure ForEachCall(proc2call: TListStaticCallback;arg: pointer)`

Visibility: `public`

Description: `ForEachCall` loops over the items in the list and calls `proc2call`, passing it the item and `arg`.

### 7.13.24 TFPHashList.Capacity

Synopsis: Capacity of the list.

Declaration: `Property Capacity : Integer`

Visibility: `public`

Access: Read,Write

Description: `Capacity` returns the current capacity of the list. The capacity is expanded as more elements are added to the list. If a good estimate of the number of elements that will be added to the list, the property can be set to a sufficiently large value to avoid reallocation of memory each time the list needs to grow.

See also: `TFPHashList.Count` ([124](#)), `TFPHashList.Items` ([125](#))

### 7.13.25 TFPHashList.Count

Synopsis: Current number of elements in the list.

Declaration: `Property Count : Integer`

Visibility: `public`

Access: Read,Write

Description: `Count` is the current number of elements in the list.

See also: `TFPHashList.Capacity` ([124](#)), `TFPHashList.Items` ([125](#))

### 7.13.26 TFPHashList.Items

Synopsis: Indexed array with pointers

Declaration: `Property Items[Index: Integer]: Pointer; default`

Visibility: public

Access: Read, Write

Description: `Items` provides indexed access to the pointers, the index runs from 0 to `Count-1` ([124](#)).

Errors: Specifying an invalid index will result in an exception.

See also: `TFPHashList.Capacity` ([124](#)), `TFPHashList.Count` ([124](#))

### 7.13.27 TFPHashList.List

Synopsis: Low-level hash list

Declaration: `Property List : PHashItemList`

Visibility: public

Access: Read

Description: `List` exposes the low-level item list ([101](#)). It should not be used directly.

See also: `TFPHashList.Strs` ([125](#)), `THashItemList` ([101](#))

### 7.13.28 TFPHashList.Strs

Synopsis: Low-level memory area with strings.

Declaration: `Property Strs : PChar`

Visibility: public

Access: Read

Description: `Strs` exposes the raw memory area with the strings.

See also: `TFPHashList.List` ([125](#))

## 7.14 TFPHashObject

### 7.14.1 Description

`TFPHashObject` is a `TObject` descendent which is aware of the `TFPHashObjectList` ([128](#)) class. It has a `name` property and an owning list: if the name is changed, it will reposition itself in the list which owns it. It offers methods to change the owning list: the object will correctly remove itself from the list which currently owns it, and insert itself in the new list.

### 7.14.2 Method overview

Page	Property	Description
<a href="#">126</a>	<code>ChangeOwner</code>	Change the list owning the object.
<a href="#">127</a>	<code>ChangeOwnerAndName</code>	Simultaneously change the list owning the object and the name of the object.
<a href="#">126</a>	<code>Create</code>	Create a named instance, and insert in a hash list.
<a href="#">126</a>	<code>CreateNotOwned</code>	Create an instance not owned by any list.
<a href="#">127</a>	<code>Rename</code>	Rename the object

### 7.14.3 Property overview

Page	Property	Access	Description
<a href="#">127</a>	<code>Hash</code>	<code>r</code>	Hash value
<a href="#">127</a>	<code>Name</code>	<code>r</code>	Current name of the object

### 7.14.4 `TFPHashObject.CreateNotOwned`

Synopsis: Create an instance not owned by any list.

Declaration: `constructor CreateNotOwned`

Visibility: `public`

Description: `CreateNotOwned` creates an instance of `TFPHashObject` which is not owned by any `TFPHashObjectList` ([128](#)) hash list. It also has no name when created in this way.

See also: `TFPHashObject.Name` ([127](#)), `TFPHashObject.ChangeOwner` ([126](#)), `TFPHashObject.ChangeOwnerAndName` ([127](#))

### 7.14.5 `TFPHashObject.Create`

Synopsis: Create a named instance, and insert in a hash list.

Declaration: `constructor Create (HashObjectList: TFPHashObjectList;  
const s: shortstring)`

Visibility: `public`

Description: `Create` creates an instance of `TFPHashObject`, gives it the name `S` and inserts it in the hash list `HashObjectList` ([128](#)).

See also: `TFPHashObject.CreateNotOwned` ([126](#)), `TFPHashObject.ChangeOwner` ([126](#)), `TFPHashObject.Name` ([127](#))

### 7.14.6 `TFPHashObject.ChangeOwner`

Synopsis: Change the list owning the object.

Declaration: `procedure ChangeOwner (HashObjectList: TFPHashObjectList)`

Visibility: `public`

Description: `ChangeOwner` can be used to move the object between hash lists: The object will be removed correctly from the hash list that currently owns it, and will be inserted in the list `HashObjectList`.

Errors: If an object with the same name already is present in the new hash list, an exception will be raised.

See also: `TFPHashObject.ChangeOwnerAndName` ([127](#)), `TFPHashObject.Name` ([127](#))

### 7.14.7 TFPHashObject.ChangeOwnerAndName

Synopsis: Simultaneously change the list owning the object and the name of the object.

Declaration: `procedure ChangeOwnerAndName (HashObjectList: TFPHashObjectList;  
const s: shortstring)`

Visibility: public

Description: `ChangeOwnerAndName` can be used to move the object between hash lists: The object will be removed correctly from the hash list that currently owns it (using the current name), and will be inserted in the list `HashObjectList` with the new name `S`.

Errors: If the new name already is present in the new hash list, an exception will be raised.

See also: `TFPHashObject.ChangeOwner` ([126](#)), `TFPHashObject.Name` ([127](#))

### 7.14.8 TFPHashObject.Rename

Synopsis: Rename the object

Declaration: `procedure Rename (const ANewName: shortstring)`

Visibility: public

Description: `Rename` changes the name of the object, and notifies the hash list of this change.

Errors: If the new name already is present in the hash list, an exception will be raised.

See also: `TFPHashObject.ChangeOwner` ([126](#)), `TFPHashObject.ChangeOwnerAndName` ([127](#)), `TFPHashObject.Name` ([127](#))

### 7.14.9 TFPHashObject.Name

Synopsis: Current name of the object

Declaration: `Property Name : shortstring`

Visibility: public

Access: Read

Description: `Name` is the name of the object, it is stored in the hash list using this name as the key.

See also: `TFPHashObject.Rename` ([127](#)), `TFPHashObject.ChangeOwnerAndName` ([127](#))

### 7.14.10 TFPHashObject.Hash

Synopsis: Hash value

Declaration: `Property Hash : LongWord`

Visibility: public

Access: Read

Description: `Hash` is the hash value of the object in the hash list that owns it.

See also: `TFPHashObject.Name` ([127](#))



## 7.15 TFPHashObjectList

### 7.15.1 Method overview

Page	Property	Description
<a href="#">129</a>	Add	Add a new key/data pair to the list
<a href="#">129</a>	Clear	Clear the list
<a href="#">128</a>	Create	Create a new instance of the hashlist
<a href="#">130</a>	Delete	Delete an object from the list.
<a href="#">128</a>	Destroy	Removes an instance of the hashlist from the heap
<a href="#">130</a>	Expand	Expand the list
<a href="#">131</a>	Extract	Extract a object instance from the list
<a href="#">131</a>	Find	Find data associated with key
<a href="#">132</a>	FindIndexOf	Return index of named object.
<a href="#">132</a>	FindInstanceOf	Search an instance of a certain class
<a href="#">132</a>	FindWithHash	Find first element with given name and hash value
<a href="#">133</a>	ForEachCall	Call a procedure for each object in the list
<a href="#">130</a>	GetNextCollision	Get next collision number
<a href="#">130</a>	HashOfIndex	Return the hash valye of an object by index
<a href="#">131</a>	IndexOf	Return the index of the object instance
<a href="#">129</a>	NameOfIndex	Returns the key name of an object by index
<a href="#">133</a>	Pack	Remove nil object instances from the list
<a href="#">131</a>	Remove	Remove first occurrence of a object instance
<a href="#">132</a>	Rename	Rename a key
<a href="#">133</a>	ShowStatistics	Return some statistics for the list.

### 7.15.2 Property overview

Page	Property	Access	Description
<a href="#">133</a>	Capacity	rw	Capacity of the list.
<a href="#">134</a>	Count	rw	Current number of elements in the list.
<a href="#">134</a>	Items	rw	Indexed array with object instances
<a href="#">134</a>	List	r	Low-level hash list
<a href="#">134</a>	OwnsObjects	rw	Does the list own the objects it contains

### 7.15.3 TFPHashObjectList.Create

Synopsis: Create a new instance of the hashlist

Declaration: constructor `Create(FreeObjects: Boolean)`

Visibility: public

Description: `Create` creates a new instance of `TFPHashObjectList` on the heap and sets the hash capacity to 1.

If `FreeObjects` is `True` (the default), then the list owns the objects: when an object is removed from the list, it is destroyed (freed from memory). Clearing the list will free all objects in the list.

See also: `TFPHashObjectList.Destroy` ([128](#)), `TFPHashObjectList.OwnsObjects` ([134](#))

### 7.15.4 TFPHashObjectList.Destroy

Synopsis: Removes an instance of the hashlist from the heap

**Declaration:** `destructor Destroy; Override`

**Visibility:** `public`

**Description:** `Destroy` cleans up the memory structures maintained by the hashlist and removes the `TFPHashObjectList` instance from the heap. If the list owns its objects, they are freed from memory as well.

`Destroy` should not be called directly, it's better to use `Free` or `FreeAndNil` instead.

See also: `TFPHashObjectList.Create` (128), `TFPHashObjectList.Clear` (129)

### 7.15.5 TFPHashObjectList.Clear

**Synopsis:** Clear the list

**Declaration:** `procedure Clear`

**Visibility:** `public`

**Description:** `Clear` removes all objects from the list. It does not free the objects themselves, unless `OwnsObjects` (134) is `True`. It always frees all memory needed to contain the objects.

**Errors:** None.

See also: `TFPHashObjectList.Extract` (131), `TFPHashObjectList.Remove` (131), `TFPHashObjectList.Delete` (130), `TFPHashObjectList.Add` (129)

### 7.15.6 TFPHashObjectList.Add

**Synopsis:** Add a new key/data pair to the list

**Declaration:** `function Add(const AName: shortstring; AObject: TObject) : Integer`

**Visibility:** `public`

**Description:** `Add` adds a new object instance (`AObject`) with key `AName` to the list. It returns the position of the object in the list.

**Errors:** If not enough memory is available to hold the key and data, an exception may be raised. If an object with this name already exists in the list, an exception is raised.

See also: `TFPHashObjectList.Extract` (131), `TFPHashObjectList.Remove` (131), `TFPHashObjectList.Delete` (130)

### 7.15.7 TFPHashObjectList.NameOfIndex

**Synopsis:** Returns the key name of an object by index

**Declaration:** `function NameOfIndex(Index: Integer) : ShortString`

**Visibility:** `public`

**Description:** `NameOfIndex` returns the key name of the object at position `Index`.

**Errors:** If `Index` is out of the valid range, an exception is raised.

See also: `TFPHashObjectList.HashOfIndex` (130), `TFPHashObjectList.Find` (131), `TFPHashObjectList.FindIndexOf` (132), `TFPHashObjectList.FindWithHash` (132)

### 7.15.8 TFPHashObjectList.HashOfIndex

Synopsis: Return the hash valye of an object by index

Declaration: `function HashOfIndex(Index: Integer) : LongWord`

Visibility: public

Description: `HashOfIndex` returns the hash value of the object at position `Index`.

Errors: If `Index` is out of the valid range, an exception is raised.

See also: `TFPHashObjectList.HashOfName` ([128](#)), `TFPHashObjectList.Find` ([131](#)), `TFPHashObjectList.FindIndexOf` ([132](#)), `TFPHashObjectList.FindWithHash` ([132](#))

### 7.15.9 TFPHashObjectList.GetNextCollision

Synopsis: Get next collision number

Declaration: `function GetNextCollision(Index: Integer) : Integer`

Visibility: public

Description: Get next collision number

Errors:

### 7.15.10 TFPHashObjectList.Delete

Synopsis: Delete an object from the list.

Declaration: `procedure Delete(Index: Integer)`

Visibility: public

Description: `Delete` deletes the object at position `Index`. If `OwnsObjects` ([134](#)) is `True`, then the object itself is also freed from memory.

See also: `TFPHashObjectList.Extract` ([131](#)), `TFPHashObjectList.Remove` ([131](#)), `TFPHashObjectList.Add` ([129](#)), `TFPHashObjectList.OwnsObjects` ([134](#))

### 7.15.11 TFPHashObjectList.Expand

Synopsis: Expand the list

Declaration: `function Expand : TFPHashObjectList`

Visibility: public

Description: `Expand` enlarges the capacity of the list if the maximum capacity was reached. It returns itself.

Errors: If not enough memory is available, an exception may be raised.

See also: `TFPHashObjectList.Clear` ([129](#))

### 7.15.12 TFPHashObjectList.Extract

Synopsis: Extract a object instance from the list

Declaration: `function Extract (Item: TObject) : TObject`

Visibility: public

Description: `Extract` removes the data object from the list, if it is in the list. It returns the object instance if it was removed from the list, `Nil` otherwise. The object is *not* freed from memory, regardless of the value of `OwnsObjects` (134).

`Extract` does a linear search, and is not very efficient.

See also: `TFPHashObjectList.Delete` (130), `TFPHashObjectList.Remove` (131), `TFPHashObjectList.Clear` (129)

### 7.15.13 TFPHashObjectList.Remove

Synopsis: Remove first occurrence of a object instance

Declaration: `function Remove (AObject: TObject) : Integer`

Visibility: public

Description: `Remove` removes the first occurrence of the object instance `Item` in the list, if it is present. The return value is the location of the removed object instance, or `-1` if no object instance was removed.

If `OwnsObjects` (134) is `True`, then the object itself is also freed from memory.

See also: `TFPHashObjectList.Delete` (130), `TFPHashObjectList.Clear` (129), `TFPHashObjectList.Extract` (131)

### 7.15.14 TFPHashObjectList.IndexOf

Synopsis: Return the index of the object instance

Declaration: `function IndexOf (AObject: TObject) : Integer`

Visibility: public

Description: `IndexOf` returns the index of the first occurrence of object instance `AObject`. If the object is not in the list, `-1` is returned.

The performed search is linear, and not very efficient.

See also: `TFPHashObjectList.HashOfIndex` (130), `TFPHashObjectList.NameOfIndex` (129), `TFPHashObjectList.Find` (131), `TFPHashObjectList.FindIndexOf` (132), `TFPHashObjectList.FindWithHash` (132)

### 7.15.15 TFPHashObjectList.Find

Synopsis: Find data associated with key

Declaration: `function Find (const s: shortstring) : TObject`

Visibility: public

Description: `Find` searches (using the hash) for the data object associated with key `AName` and returns the data object instance associated with it. If the object is not found, `Nil` is returned. It uses the hash value of the key to perform the search.

See also: `TFPHashObjectList.HashOfIndex` (130), `TFPHashObjectList.NameOfIndex` (129), `TFPHashObjectList.IndexOf` (131), `TFPHashObjectList.FindIndexOf` (132), `TFPHashObjectList.FindWithHash` (132)

### 7.15.16 TFPHashObjectList.FindIndexOf

Synopsis: Return index of named object.

Declaration: `function FindIndexOf(const s: shortstring) : Integer`

Visibility: public

Description: `FindIndexOf` returns the index of the key `AName`, or -1 if the key does not exist in the list. It uses the hash value to search for the key.

See also: `TFPHashObjectList.HashOfIndex` (130), `TFPHashObjectList.NameOfIndex` (129), `TFPHashObjectList.IndexOf` (131), `TFPHashObjectList.Find` (131), `TFPHashObjectList.FindWithHash` (132)

### 7.15.17 TFPHashObjectList.FindWithHash

Synopsis: Find first element with given name and hash value

Declaration: `function FindWithHash(const AName: shortstring; AHash: LongWord)  
: Pointer`

Visibility: public

Description: `FindWithHash` searches for the object with key `AName`. It uses the provided hash value `AHash` to perform the search. If the object exists, the data object instance is returned, if not, the result is `Nil`.

See also: `TFPHashObjectList.HashOfIndex` (130), `TFPHashObjectList.NameOfIndex` (129), `TFPHashObjectList.IndexOf` (131), `TFPHashObjectList.Find` (131), `TFPHashObjectList.FindIndexOf` (132)

### 7.15.18 TFPHashObjectList.Rename

Synopsis: Rename a key

Declaration: `function Rename(const AOldName: shortstring; const ANewName: shortstring)  
: Integer`

Visibility: public

Description: `Rename` renames key `AOldname` to `ANewName`. The hash value is recomputed and the object is moved in the list to it's new position.

Errors: If an object with `ANewName` already exists, an exception will be raised.

### 7.15.19 TFPHashObjectList.FindInstanceOf

Synopsis: Search an instance of a certain class

Declaration: `function FindInstanceOf(AClass: TClass; AExact: Boolean;  
AStartAt: Integer) : Integer`

Visibility: public

Description: `FindInstanceOf` searches the list for an instance of class `AClass`. It starts searching at position `AStartAt`. If `AExact` is `True`, only instances of class `AClass` are considered. If `AExact` is `False`, then descendent classes of `AClass` are also taken into account when searching. If no instance is found, `Nil` is returned.

### 7.15.20 TFPHashObjectList.Pack

Synopsis: Remove nil object instances from the list

Declaration: `procedure Pack`

Visibility: `public`

Description: `Pack` removes all `Nil` objects from the list, and frees all unused memory.

See also: `TFPHashObjectList.Clear` ([129](#))

### 7.15.21 TFPHashObjectList.ShowStatistics

Synopsis: Return some statistics for the list.

Declaration: `procedure ShowStatistics`

Visibility: `public`

Description: `ShowStatistics` prints some information about the hash list to standard output. It prints the following values:

**HashSize**Size of the hash table

**HashMean**Mean hash value

**HashStdDev**Standard deviation of hash values

**ListSize**Size and capacity of the list

**StringSize**Size and capacity of key strings

### 7.15.22 TFPHashObjectList.ForEachCall

Synopsis: Call a procedure for each object in the list

Declaration: `procedure ForEachCall(proc2call: TObjectListCallback;arg: pointer)`  
`procedure ForEachCall(proc2call: TObjectListStaticCallback;arg: pointer)`

Visibility: `public`

Description: `ForEachCall` loops over the objects in the list and calls `proc2call`, passing it the object and `arg`.

### 7.15.23 TFPHashObjectList.Capacity

Synopsis: Capacity of the list.

Declaration: `Property Capacity : Integer`

Visibility: `public`

Access: `Read,Write`

Description: `Capacity` returns the current capacity of the list. The capacity is expanded as more elements are added to the list. If a good estimate of the number of elements that will be added to the list, the property can be set to a sufficiently large value to avoid reallocation of memory each time the list needs to grow.

See also: `TFPHashObjectList.Count` ([134](#)), `TFPHashObjectList.Items` ([134](#))

### 7.15.24 TFPHashObjectList.Count

Synopsis: Current number of elements in the list.

Declaration: `Property Count : Integer`

Visibility: `public`

Access: `Read,Write`

Description: `Count` is the current number of elements in the list.

See also: `TFPHashObjectList.Capacity` ([133](#)), `TFPHashObjectList.Items` ([134](#))

### 7.15.25 TFPHashObjectList.OwnsObjects

Synopsis: Does the list own the objects it contains

Declaration: `Property OwnsObjects : Boolean`

Visibility: `public`

Access: `Read,Write`

Description: `OwnsObjects` determines what to do when an object is removed from the list: if it is `True` (the default), then the list owns the objects: when an object is removed from the list, it is destroyed (freed from memory). Clearing the list will free all objects in the list.

The value of `OwnsObjects` is set when the hash list is created, and cannot be changed during the lifetime of the hash list.

See also: `TFPHashObjectList.Create` ([128](#))

### 7.15.26 TFPHashObjectList.Items

Synopsis: Indexed array with object instances

Declaration: `Property Items[Index: Integer]: TObject; default`

Visibility: `public`

Access: `Read,Write`

Description: `Items` provides indexed access to the object instances, the index runs from 0 to `Count-1` ([134](#)).

Errors: Specifying an invalid index will result in an exception.

See also: `TFPHashObjectList.Capacity` ([133](#)), `TFPHashObjectList.Count` ([134](#))

### 7.15.27 TFPHashObjectList.List

Synopsis: Low-level hash list

Declaration: `Property List : TFPHashList`

Visibility: `public`

Access: `Read`

Description: `List` exposes the low-level hash list ([118](#)). It should not be used directly.

See also: `TFPHashList` ([118](#))

## 7.16 TFPOjectHashTable

### 7.16.1 Description

TFPStringHashTable is a TFPCustomHashTable (111) descendent which stores object instances together with the keys. In case the data associated with the keys are strings themselves, it's better to use TFPStringHashTable (144), or for arbitrary pointer data, TFPDataHashTable (117) is more suitable. The objects are exposed with their keys through the Items (136) property.

### 7.16.2 Method overview

Page	Property	Description
<a href="#">136</a>	Add	Add a new object to the hash table
<a href="#">135</a>	Create	Create a new instance of TFPOjectHashTable
<a href="#">135</a>	CreateWith	Create a new hash table with given size and hash function

### 7.16.3 Property overview

Page	Property	Access	Description
<a href="#">136</a>	Items	rw	Key-based access to the objects
<a href="#">136</a>	OwnsObjects	rw	Does the hash table own the objects ?

### 7.16.4 TFPOjectHashTable.Create

Synopsis: Create a new instance of TFPOjectHashTable

Declaration: constructor Create(AOwnsObjects: Boolean)

Visibility: public

Description: Create creates a new instance of TFPOjectHashTable on the heap. It sets the OwnsObjects (136) property to AOwnsObjects, and then calls the inherited Create. If AOwnsObjects is set to True, then the hash table owns the objects: whenever an object is removed from the list, it is automatically freed.

Errors: If not enough memory is available on the heap, an exception may be raised.

See also: TFPOjectHashTable.OwnsObjects (136), TFPOjectHashTable.CreateWith (135), TFPOjectHashTable.Items (136)

### 7.16.5 TFPOjectHashTable.CreateWith

Synopsis: Create a new hash table with given size and hash function

Declaration: constructor CreateWith(AHashTableSize: LongWord;  
aHashFunc: THashFunction; AOwnsObjects: Boolean)

Visibility: public

Description: CreateWith sets the OwnsObjects (136) property to AOwnsObjects, and then calls the inherited CreateWith. If AOwnsObjects is set to True, then the hash table owns the objects: whenever an object is removed from the list, it is automatically freed.

This constructor should be used when a table size and hash algorithm should be specified that differ from the default table size and hash algorithm.



Errors: If not enough memory is available on the heap, an exception may be raised.

See also: `TFObjectHashTable.OwnsObjects` (136), `TFObjectHashTable.Create` (135), `TFObjectHashTable.Items` (136)

### 7.16.6 TFObjectHashTable.Add

Synopsis: Add a new object to the hash table

Declaration: `procedure Add(const aKey: String; AItem: TObject); Virtual`

Visibility: public

Description: `Add` adds the object `AItem` to the hash table, and associates it with key `aKey`.

Errors: If the key `aKey` is already in the hash table, an exception will be raised.

See also: `TFObjectHashTable.Items` (136)

### 7.16.7 TFObjectHashTable.Items

Synopsis: Key-based access to the objects

Declaration: `Property Items[index: String]: TObject; default`

Visibility: public

Access: Read, Write

Description: `Items` provides access to the objects in the hash table using their key: the array index `Index` is the key. A key which is not present will result in an `Nil` instance.

See also: `TFObjectHashTable.Add` (136)

### 7.16.8 TFObjectHashTable.OwnsObjects

Synopsis: Does the hash table own the objects ?

Declaration: `Property OwnsObjects : Boolean`

Visibility: public

Access: Read, Write

Description: `OwnsObjects` determines what happens with objects which are removed from the hash table: if `True`, then removing an object from the hash list will free the object. If `False`, the object is not freed. Note that way in which the object is removed is not relevant: be it `Delete`, `Remove` or `Clear`.

See also: `TFObjectHashTable.Create` (135), `TFObjectHashTable.Items` (136)

## 7.17 TFObjectList

### 7.17.1 Description

TFObjectList is a TFPList (??) based list which has as the default array property TObjects (??) instead of pointers. By default it also manages the objects: when an object is deleted or removed from the list, it is automatically freed. This behaviour can be disabled when the list is created.

In difference with TObjectList (149), TFObjectList offers no notification mechanism of list operations, allowing it to be faster than TObjectList. For the same reason, it is also not a descendent of TFPList (although it uses one internally).

### 7.17.2 Method overview

Page	Property	Description
138	Add	Add an object to the list.
142	Assign	Copy the contents of a list.
138	Clear	Clear all elements in the list.
137	Create	Create a new object list
138	Delete	Delete an element from the list.
138	Destroy	Clears the list and destroys the list instance
139	Exchange	Exchange the location of two objects
139	Expand	Expand the capacity of the list.
139	Extract	Extract an object from the list
140	FindInstanceOf	Search for an instance of a certain class
141	First	Return the first non-nil object in the list
142	ForEachCall	For each object in the list, call a method or procedure, passing it the object.
140	IndexOf	Search for an object in the list
140	Insert	Insert a new object in the list
141	Last	Return the last non-nil object in the list.
141	Move	Move an object to another location in the list.
142	Pack	Remove all Nil references from the list
140	Remove	Remove an item from the list.
142	Sort	Sort the list of objects

### 7.17.3 Property overview

Page	Property	Access	Description
143	Capacity	rw	Capacity of the list
143	Count	rw	Number of elements in the list.
144	Items	rw	Indexed access to the elements of the list.
144	List	r	Internal list used to keep the objects.
143	OwnsObjects	rw	Should the list free elements when they are removed.

### 7.17.4 TFObjectList.Create

Synopsis: Create a new object list

Declaration: `constructor Create`  
`constructor Create(FreeObjects: Boolean)`

Visibility: public

**Description:** `Create` instantiates a new object list. The `FreeObjects` parameter determines whether objects that are removed from the list should also be freed from memory. By default this is `True`. This behaviour can be changed after the list was instantiated.

**Errors:** None.

**See also:** `TFPObjectList.Destroy` (138), `TFPObjectList.OwnsObjects` (143), `TObjectList` (149)

### 7.17.5 TFPObjectList.Destroy

**Synopsis:** Clears the list and destroys the list instance

**Declaration:** `destructor Destroy; Override`

**Visibility:** `public`

**Description:** `Destroy` clears the list, freeing all objects in the list if `OwnsObjects` (143) is `True`.

**See also:** `TFPObjectList.OwnsObjects` (143), `TObjectList.Create` (150)

### 7.17.6 TFPObjectList.Clear

**Synopsis:** Clear all elements in the list.

**Declaration:** `procedure Clear`

**Visibility:** `public`

**Description:** Removes all objects from the list, freeing all objects in the list if `OwnsObjects` (143) is `True`.

**See also:** `TObjectList.Destroy` (149)

### 7.17.7 TFPObjectList.Add

**Synopsis:** Add an object to the list.

**Declaration:** `function Add(AObject: TObject) : Integer`

**Visibility:** `public`

**Description:** `Add` adds `AObject` to the list and returns the index of the object in the list.

Note that when `OwnsObjects` (143) is `True`, an object should not be added twice to the list: this will result in memory corruption when the object is freed (as it will be freed twice). The `Add` method does not check this, however.

**Errors:** None.

**See also:** `TFPObjectList.OwnsObjects` (143), `TFPObjectList.Delete` (138)

### 7.17.8 TFPObjectList.Delete

**Synopsis:** Delete an element from the list.

**Declaration:** `procedure Delete(Index: Integer)`

**Visibility:** `public`

**Description:** `Delete` removes the object at index `Index` from the list. When `OwnsObjects` (143) is `True`, the object is also freed.

**Errors:** An access violation may occur when `OwnsObjects` (143) is `True` and either the object was freed externally, or when the same object is in the same list twice.

**See also:** `TFPObjectList.Remove` (98), `TFPObjectList.Extract` (139), `TFPObjectList.OwnsObjects` (143), `TFPObjectList.Add` (98), `TFPObjectList.Clear` (98)

### 7.17.9 TFPObjectList.Exchange

**Synopsis:** Exchange the location of two objects

**Declaration:** `procedure Exchange(Index1: Integer; Index2: Integer)`

**Visibility:** `public`

**Description:** `Exchange` exchanges the objects at indexes `Index1` and `Index2` in a direct operation (i.e. no delete/add is performed).

**Errors:** If either `Index1` or `Index2` is invalid, an exception will be raised.

**See also:** `TFPObjectList.Add` (98), `TFPObjectList.Delete` (98)

### 7.17.10 TFPObjectList.Expand

**Synopsis:** Expand the capacity of the list.

**Declaration:** `function Expand : TFPObjectList`

**Visibility:** `public`

**Description:** `Expand` increases the capacity of the list. It calls `#rtl.classes.tfplist.expand` (??) and then returns a reference to itself.

**Errors:** If there is not enough memory to expand the list, an exception will be raised.

**See also:** `TFPObjectList.Pack` (142), `TFPObjectList.Clear` (138), `#rtl.classes.tfplist.expand` (??)

### 7.17.11 TFPObjectList.Extract

**Synopsis:** Extract an object from the list

**Declaration:** `function Extract(Item: TObject) : TObject`

**Visibility:** `public`

**Description:** `Extract` removes `Item` from the list, if it is present in the list. It returns `Item` if it was found, `Nil` if item was not present in the list.

Note that the object is not freed, and that only the first found object is removed from the list.

**Errors:** None.

**See also:** `TFPObjectList.Pack` (142), `TFPObjectList.Clear` (138), `TFPObjectList.Remove` (140), `TFPObjectList.Delete` (138)

### 7.17.12 TFObjectList.Remove

Synopsis: Remove an item from the list.

Declaration: `function Remove(AObject: TObject) : Integer`

Visibility: public

Description: `Remove` removes `Item` from the list, if it is present in the list. It frees `Item` if `OwnsObjects` (143) is `True`, and returns the index of the object that was found in the list, or -1 if the object was not found.

Note that only the first found object is removed from the list.

Errors: None.

See also: `TFObjectList.Pack` (142), `TFObjectList.Clear` (138), `TFObjectList.Delete` (138), `TFObjectList.Extract` (139)

### 7.17.13 TFObjectList.IndexOf

Synopsis: Search for an object in the list

Declaration: `function IndexOf(AObject: TObject) : Integer`

Visibility: public

Description: `IndexOf` searches for the presence of `AObject` in the list, and returns the location (index) in the list. The index is 0-based, and -1 is returned if `AObject` was not found in the list.

Errors: None.

See also: `TFObjectList.Items` (144), `TFObjectList.Remove` (140), `TFObjectList.Extract` (139)

### 7.17.14 TFObjectList.FindInstanceOf

Synopsis: Search for an instance of a certain class

Declaration: `function FindInstanceOf(AClass: TClass; AExact: Boolean;  
                                  AStartAt: Integer) : Integer`

Visibility: public

Description: `FindInstanceOf` will look through the instances in the list and will return the first instance which is a descendent of class `AClass` if `AExact` is `False`. If `AExact` is `true`, then the instance should be of class `AClass`.

If no instance of the requested class is found, `Nil` is returned.

Errors: None.

See also: `TFObjectList.IndexOf` (140)

### 7.17.15 TFObjectList.Insert

Synopsis: Insert a new object in the list

Declaration: `procedure Insert (Index: Integer; AObject: TObject)`

Visibility: public

Description: `Insert` inserts `AObject` at position `Index` in the list. All elements in the list after this position are shifted. The index is zero based, i.e. an insert at position 0 will insert an object at the first position of the list.

Errors: None.

See also: `TFObjectList.Add` ([138](#)), `TFObjectList.Delete` ([138](#))

### 7.17.16 TFObjectList.First

Synopsis: Return the first non-nil object in the list

Declaration: `function First : TObject`

Visibility: public

Description: `First` returns a reference to the first non-`Nil` element in the list. If no non-`Nil` element is found, `Nil` is returned.

Errors: None.

See also: `TFObjectList.Last` ([141](#)), `TFObjectList.Pack` ([142](#))

### 7.17.17 TFObjectList.Last

Synopsis: Return the last non-nil object in the list.

Declaration: `function Last : TObject`

Visibility: public

Description: `Last` returns a reference to the last non-`Nil` element in the list. If no non-`Nil` element is found, `Nil` is returned.

Errors: None.

See also: `TFObjectList.First` ([141](#)), `TFObjectList.Pack` ([142](#))

### 7.17.18 TFObjectList.Move

Synopsis: Move an object to another location in the list.

Declaration: `procedure Move (CurIndex: Integer; NewIndex: Integer)`

Visibility: public

Description: `Move` moves the object at current location `CurIndex` to location `NewIndex`. Note that the `NewIndex` is determined *after* the object was removed from location `CurIndex`, and can hence be shifted with 1 position if `CurIndex` is less than `NewIndex`.

Contrary to exchange ([139](#)), the move operation is done by extracting the object from it's current location and inserting it at the new location.

**Errors:** If either `CurIndex` or `NewIndex` is out of range, an exception may occur.

See also: `TFPObjectList.Exchange` ([139](#)), `TFPObjectList.Delete` ([138](#)), `TFPObjectList.Insert` ([140](#))

### 7.17.19 TFPObjectList.Assign

**Synopsis:** Copy the contents of a list.

**Declaration:** `procedure Assign(Obj: TFPObjectList)`

**Visibility:** public

**Description:** `Assign` copies the contents of `Obj` if `Obj` is of type `TFPObjectList`

**Errors:** None.

### 7.17.20 TFPObjectList.Pack

**Synopsis:** Remove all `Nil` references from the list

**Declaration:** `procedure Pack`

**Visibility:** public

**Description:** `Pack` removes all `Nil` elements from the list.

**Errors:** None.

See also: `TFPObjectList.First` ([141](#)), `TFPObjectList.Last` ([141](#))

### 7.17.21 TFPObjectList.Sort

**Synopsis:** Sort the list of objects

**Declaration:** `procedure Sort(Compare: TListSortCompare)`

**Visibility:** public

**Description:** `Sort` will perform a quick-sort on the list, using `Compare` as the compare algorithm. This function should accept 2 pointers and should return the following result:

**less than 0** If the first pointer comes before the second.

**equal to 0** If the pointers have the same value.

**larger than 0** If the first pointer comes after the second.

The function should be able to deal with `Nil` values.

**Errors:** None.

See also: `#rtl.classes.TList.Sort` (??)

### 7.17.22 TFObjectList.ForEachCall

Synopsis: For each object in the list, call a method or procedure, passing it the object.

Declaration: `procedure ForEachCall(proc2call: TObjectListCallback;arg: pointer)`  
`procedure ForEachCall(proc2call: TObjectListStaticCallback;arg: pointer)`

Visibility: public

Description: `ForEachCall` loops through all objects in the list, and calls `proc2call`, passing it the object in the list. Additionally, `arg` is also passed to the procedure. `Proc2call` can be a plain procedure or can be a method of a class.

Errors: None.

See also: `TObjectListStaticCallback` ([102](#)), `TObjectListCallback` ([101](#))

### 7.17.23 TFObjectList.Capacity

Synopsis: Capacity of the list

Declaration: `Property Capacity : Integer`

Visibility: public

Access: Read,Write

Description: `Capacity` is the number of elements that the list can contain before it needs to expand itself, i.e., reserve more memory for pointers. It is always equal or larger than `Count` ([143](#)).

See also: `TFObjectList.Count` ([143](#))

### 7.17.24 TFObjectList.Count

Synopsis: Number of elements in the list.

Declaration: `Property Count : Integer`

Visibility: public

Access: Read,Write

Description: `Count` is the number of elements in the list. Note that this includes `Nil` elements.

See also: `TFObjectList.Capacity` ([143](#))

### 7.17.25 TFObjectList.OwnsObjects

Synopsis: Should the list free elements when they are removed.

Declaration: `Property OwnsObjects : Boolean`

Visibility: public

Access: Read,Write



**Description:** `OwnsObjects` determines whether the objects in the list should be freed when they are removed (not extracted) from the list, or when the list is cleared. If the property is `True` then they are freed. If the property is `False` the elements are not freed.

The value is usually set in the constructor, and is seldom changed during the lifetime of the list. It defaults to `True`.

See also: `TFPObjectList.Create` (137), `TFPObjectList.Delete` (138), `TFPObjectList.Remove` (140), `TFPObjectList.Clear` (138)

### 7.17.26 TFPObjectList.Items

**Synopsis:** Indexed access to the elements of the list.

**Declaration:** `Property Items[Index: Integer]: TObject; default`

**Visibility:** `public`

**Access:** `Read, Write`

**Description:** `Items` is the default property of the list. It provides indexed access to the elements in the list. The index `Index` is zero based, i.e., runs from 0 (zero) to `Count-1`.

See also: `TFPObjectList.Count` (143)

### 7.17.27 TFPObjectList.List

**Synopsis:** Internal list used to keep the objects.

**Declaration:** `Property List : TFPList`

**Visibility:** `public`

**Access:** `Read`

**Description:** `List` is a reference to the `TFPList` (??) instance used to manage the elements in the list.

See also: `#rtl.classes.tfplist` (??)

## 7.18 TFPStringHashTable

### 7.18.1 Description

`TFPStringHashTable` is a `TFPCustomHashTable` (111) descendent which stores simple strings together with the keys. In case the data associated with the keys are objects, it's better to use `TFPObjectHashTable` (135), or for arbitrary pointer data, `TFPDataHashTable` (117) is more suitable. The strings are exposed with their keys through the `Items` (145) property.

### 7.18.2 Method overview

Page	Property	Description
144	<code>Add</code>	Add a new string to the hash list

### 7.18.3 Property overview

Page	Property	Access	Description
145	<code>Items</code>	<code>rw</code>	Key based access to the strings in the hash table

### 7.18.4 TFPStringHashTable.Add

Synopsis: Add a new string to the hash list

Declaration: `procedure Add(const aKey: String; const aItem: String); Virtual`

Visibility: public

Description: Add adds a new string `AItem` to the hash list with key `AKey`.

Errors: If a string with key `Akey` already exists in the hash table, an exception will be raised.

See also: `TFPStringHashTable.Items` ([145](#))

### 7.18.5 TFPStringHashTable.Items

Synopsis: Key based access to the strings in the hash table

Declaration: `Property Items[index: String]: String; default`

Visibility: public

Access: Read, Write

Description: `Items` provides access to the strings in the hash table using their key: the array index `Index` is the key. A key which is not present will result in an empty string.

See also: `TFPStringHashTable.Add` ([144](#))

## 7.19 THTCustomNode

### 7.19.1 Description

`THTCustomNode` is used by the `TFPCustomHashTable` ([111](#)) class to store the keys and associated values.

### 7.19.2 Method overview

Page	Property	Description
<a href="#">145</a>	<code>CreateWith</code>	Create a new instance of <code>THTCustomNode</code>
<a href="#">146</a>	<code>HasKey</code>	Check whether this node matches the given key.

### 7.19.3 Property overview

Page	Property	Access	Description
<a href="#">146</a>	<code>Key</code>	r	Key value associated with this hash item.

### 7.19.4 THTCustomNode.CreateWith

Synopsis: Create a new instance of `THTCustomNode`

Declaration: `constructor CreateWith(const AString: String)`

Visibility: public

**Description:** `CreateWith` creates a new instance of `THTCustomNode` and stores the string `AString` in it. It should never be necessary to call this method directly, it will be called by the `TFPHashTable` (98) class when needed.

**Errors:** If no more memory is available, an exception may be raised.

**See also:** `TFPHashTable` (98)

### 7.19.5 THTCustomNode.HasKey

**Synopsis:** Check whether this node matches the given key.

**Declaration:** `function HasKey(const AKey: String) : Boolean`

**Visibility:** `public`

**Description:** `HasKey` checks whether this node matches the given key `AKey`, by comparing it with the stored key. It returns `True` if it does, `False` if not.

**Errors:** None.

**See also:** `THTCustomNode.Key` (146)

### 7.19.6 THTCustomNode.Key

**Synopsis:** Key value associated with this hash item.

**Declaration:** `Property Key : String`

**Visibility:** `public`

**Access:** `Read`

**Description:** `Key` is the key value associated with this hash item. It is stored when the item is created, and is read-only.

**See also:** `THTCustomNode.CreateWith` (145)

## 7.20 THTDataNode

### 7.20.1 Description

`THTDataNode` is used by `TDataHashTable` (98) to store the hash items in. It simply holds the data pointer.

It should not be necessary to use `THTDataNode` directly, it's only for inner use by `TFPDataHashTable`

### 7.20.2 Property overview

Page	Property	Access	Description
146	Data	rw	Data pointer

### 7.20.3 THTDataNode.Data

Synopsis: Data pointer

Declaration: `Property Data : pointer`

Visibility: public

Access: Read,Write

Description: Pointer containing the user data associated with the hash value.

## 7.21 THTObjectNode

### 7.21.1 Description

`THTObjectNode` is a `THTCustomNode` (145) descendent which holds the data in the `TFPObjectHashTable` (135) hash table. It exposes a data string.

It should not be necessary to use `THTObjectNode` directly, it's only for inner use by `TFPObjectHashTable`

### 7.21.2 Property overview

Page	Property	Access	Description
147	Data	rw	Object instance

### 7.21.3 THTObjectNode.Data

Synopsis: Object instance

Declaration: `Property Data : TObject`

Visibility: public

Access: Read,Write

Description: `Data` is the object instance associated with the key value. It is exposed in `TFPObjectHashTable.Items` (136)

See also: `TFPObjectHashTable` (135), `TFPObjectHashTable.Items` (136), `THTOwnedObjectNode` (147)

## 7.22 THTOwnedObjectNode

### 7.22.1 Description

`THTOwnedObjectNode` is used instead of `THTObjectNode` (147) in case `TFPObjectHashTable` (135) owns it's objects. When this object is destroyed, the associated data object is also destroyed.

### 7.22.2 Method overview

Page	Property	Description
147	Destroy	Destroys the node and the object.

### 7.22.3 THTOwnedObjectNode.Destroy

Synopsis: Destroys the node and the object.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` first frees the data object, and then only frees itself.

See also: `THTOwnedObjectNode` ([147](#)), `TFPObjectHashTable.OwnsObjects` ([136](#))

## 7.23 THTStringNode

### 7.23.1 Description

`THTStringNode` is a `THTCustomNode` ([145](#)) descendent which holds the data in the `TFPStringHashTable` ([144](#)) hash table. It exposes a data string.

It should not be necessary to use `THTStringNode` directly, it's only for inner use by `TFPStringHashTable`

### 7.23.2 Property overview

Page	Property	Access	Description
<a href="#">148</a>	<code>Data</code>	<code>rw</code>	String data

### 7.23.3 THTStringNode.Data

Synopsis: String data

Declaration: `Property Data : String`

Visibility: `public`

Access: `Read,Write`

Description: `Data` is the data of this has node. The data is a string, associated with the key. It is also exposed in `TFPStringHashTable.Items` ([145](#))

See also: `TFPStringHashTable` ([144](#))

## 7.24 TObjectBucketList

### 7.24.1 Description

`TObjectBucketList` is a class that redefines the associative `Data` array using `TObject` instead of `Pointer`. It also adds some overloaded versions of the `Add` and `Remove` calls using `TObject` instead of `Pointer` for the argument and result types.

### 7.24.2 Method overview

Page	Property	Description
<a href="#">148</a>	<code>Add</code>	Add an object to the list
<a href="#">149</a>	<code>Remove</code>	Remove an object from the list

### 7.24.3 Property overview

Page	Property	Access	Description
<a href="#">149</a>	Data	rw	Associative array of data items

### 7.24.4 TObjectBucketList.Add

Synopsis: Add an object to the list

Declaration: `function Add(AItem: TObject; AData: TObject) : TObject`

Visibility: public

Description: Add adds AItem to the list and associated AData with it.

See also: TObjectBucketList.Data ([149](#)), TObjectBucketList.Remove ([149](#))

### 7.24.5 TObjectBucketList.Remove

Synopsis: Remove an object from the list

Declaration: `function Remove(AItem: TObject) : TObject`

Visibility: public

Description: Remove removes the object AItem from the list. It returns the Data object which was associated with the item. If AItem was not in the list, then Nil is returned.

See also: TObjectBucketList.Add ([148](#)), TObjectBucketList.Data ([149](#))

### 7.24.6 TObjectBucketList.Data

Synopsis: Associative array of data items

Declaration: `Property Data[AItem: TObject]: TObject; default`

Visibility: public

Access: Read, Write

Description: Data provides associative access to the data in the list: it returns the data object associated with the AItem object. If the AItem object is not in the list, an EListError exception is raised.

See also: TObjectBucketList.Add ([148](#))

## 7.25 TObjectList

### 7.25.1 Description

TObjectList is a TList (??) descendent which has as the default array property TObjects (??) instead of pointers. By default it also manages the objects: when an object is deleted or removed from the list, it is automatically freed. This behaviour can be disabled when the list is created.

In difference with TFPObjectList ([137](#)), TObjectList offers a notification mechanism of list change operations: insert, delete. This slows down bulk operations, so if the notifications are not needed, TFPObjectList may be more appropriate.

### 7.25.2 Method overview

Page	Property	Description
<a href="#">150</a>	Add	Add an object to the list.
<a href="#">150</a>	create	Create a new object list.
<a href="#">150</a>	Extract	Extract an object from the list.
<a href="#">151</a>	FindInstanceOf	Search for an instance of a certain class
<a href="#">152</a>	First	Return the first non-nil object in the list
<a href="#">151</a>	IndexOf	Search for an object in the list
<a href="#">152</a>	Insert	Insert an object in the list.
<a href="#">152</a>	Last	Return the last non-nil object in the list.
<a href="#">151</a>	Remove	Remove (and possibly free) an element from the list.

### 7.25.3 Property overview

Page	Property	Access	Description
<a href="#">153</a>	Items	rw	Indexed access to the elements of the list.
<a href="#">152</a>	OwnsObjects	rw	Should the list free elements when they are removed.

### 7.25.4 TObjectList.create

Synopsis: Create a new object list.

Declaration: `constructor create`  
`constructor create(freeobjects: Boolean)`

Visibility: `public`

Description: `Create` instantiates a new object list. The `FreeObjects` parameter determines whether objects that are removed from the list should also be freed from memory. By default this is `True`. This behaviour can be changed after the list was instantiated.

Errors: None.

See also: `TObjectList.Destroy` ([149](#)), `TObjectList.OwnsObjects` ([152](#)), `TFPObjectList` ([137](#))

### 7.25.5 TObjectList.Add

Synopsis: Add an object to the list.

Declaration: `function Add(AObject: TObject) : Integer`

Visibility: `public`

Description: `Add` overrides the `TList` ([??](#)) implementation to accept objects (`AObject`) instead of pointers. The function returns the index of the position where the object was added.

Errors: If the list must be expanded, and not enough memory is available, an exception may be raised.

See also: `TObjectList.Insert` ([152](#)), `#rtl.classes.TList.Delete` ([??](#)), `TObjectList.Extract` ([150](#)), `TObjectList.Remove` ([151](#))

### 7.25.6 TObjectList.Extract

Synopsis: Extract an object from the list.

Declaration: `function Extract (Item: TObject) : TObject`

Visibility: public

Description: `Extract` removes the object `Item` from the list if it is present in the list. Contrary to `Remove` (151), `Extract` does not free the extracted element if `OwnsObjects` (152) is `True`

The function returns a reference to the item which was removed from the list, or `Nil` if no element was removed.

Errors: None.

See also: `TObjectList.Remove` (151)

### 7.25.7 TObjectList.Remove

Synopsis: Remove (and possibly free) an element from the list.

Declaration: `function Remove (AObject: TObject) : Integer`

Visibility: public

Description: `Remove` removes `Item` from the list, if it is present in the list. It frees `Item` if `OwnsObjects` (152) is `True`, and returns the index of the object that was found in the list, or -1 if the object was not found.

Note that only the first found object is removed from the list.

Errors: None.

See also: `TObjectList.Extract` (150)

### 7.25.8 TObjectList.IndexOf

Synopsis: Search for an object in the list

Declaration: `function IndexOf (AObject: TObject) : Integer`

Visibility: public

Description: `IndexOf` overrides the `TList` (??) implementation to accept an object instance instead of a pointer.

The function returns the index of the first match for `AObject` in the list, or -1 if no match was found.

Errors: None.

See also: `TObjectList.FindInstanceOf` (151)

### 7.25.9 TObjectList.FindInstanceOf

Synopsis: Search for an instance of a certain class

Declaration: `function FindInstanceOf (AClass: TClass; AExact: Boolean;  
AStartAt: Integer) : Integer`

Visibility: public



**Description:** `FindInstanceOf` will look through the instances in the list and will return the first instance which is a descendent of class `AClass` if `AExact` is `False`. If `AExact` is `true`, then the instance should be of class `AClass`.

If no instance of the requested class is found, `Nil` is returned.

**Errors:** None.

**See also:** `TObjectList.IndexOf` ([151](#))

### 7.25.10 TObjectList.Insert

**Synopsis:** Insert an object in the list.

**Declaration:** `procedure Insert (Index: Integer; AObject: TObject)`

**Visibility:** public

**Description:** `Insert` inserts `AObject` in the list at position `Index`. The index is zero-based. This method overrides the implementation in `TList` (??) to accept objects instead of pointers.

**Errors:** If an invalid `Index` is specified, an exception is raised.

**See also:** `TObjectList.Add` ([150](#)), `TObjectList.Remove` ([151](#))

### 7.25.11 TObjectList.First

**Synopsis:** Return the first non-nil object in the list

**Declaration:** `function First : TObject`

**Visibility:** public

**Description:** `First` returns a reference to the first non-`Nil` element in the list. If no non-`Nil` element is found, `Nil` is returned.

**Errors:** None.

**See also:** `TObjectList.Last` ([152](#)), `TObjectList.Pack` ([149](#))

### 7.25.12 TObjectList.Last

**Synopsis:** Return the last non-nil object in the list.

**Declaration:** `function Last : TObject`

**Visibility:** public

**Description:** `Last` returns a reference to the last non-`Nil` element in the list. If no non-`Nil` element is found, `Nil` is returned.

**Errors:** None.

**See also:** `TObjectList.First` ([152](#)), `TObjectList.Pack` ([149](#))

### 7.25.13 TObjectList.OwnsObjects

Synopsis: Should the list free elements when they are removed.

Declaration: `Property OwnsObjects : Boolean`

Visibility: public

Access: Read,Write

Description: `OwnsObjects` determines whether the objects in the list should be freed when they are removed (not extracted) from the list, or when the list is cleared. If the property is `True` then they are freed. If the property is `False` the elements are not freed.

The value is usually set in the constructor, and is seldom changed during the lifetime of the list. It defaults to `True`.

See also: `TObjectList.Create` (150), `TObjectList.Delete` (149), `TObjectList.Remove` (151), `TObjectList.Clear` (149)

### 7.25.14 TObjectList.Items

Synopsis: Indexed access to the elements of the list.

Declaration: `Property Items[Index: Integer]: TObject; default`

Visibility: public

Access: Read,Write

Description: `Items` is the default property of the list. It provides indexed access to the elements in the list. The index `Index` is zero based, i.e., runs from 0 (zero) to `Count-1`.

See also: `#rtl.classes.TList.Count` (??)

## 7.26 TObjectQueue

### 7.26.1 Method overview

Page	Property	Description
<a href="#">154</a>	<code>Peek</code>	Look at the first object in the queue.
<a href="#">153</a>	<code>Pop</code>	Pop the first element off the queue
<a href="#">153</a>	<code>Push</code>	Push an object on the queue

### 7.26.2 TObjectQueue.Push

Synopsis: Push an object on the queue

Declaration: `function Push(AObject: TObject) : TObject`

Visibility: public

Description: `Push` pushes another object on the queue. It overrides the `Push` method as implemented in `TQueue` so it accepts only objects as arguments.

Errors: If not enough memory is available to expand the queue, an exception may be raised.

See also: `TObjectQueue.Pop` (153), `TObjectQueue.Peek` (154)

### 7.26.3 TObjectQueue.Pop

Synopsis: Pop the first element off the queue

Declaration: `function Pop : TObject`

Visibility: public

Description: `Pop` removes the first element in the queue, and returns a reference to the instance. If the queue is empty, `Nil` is returned.

Errors: None.

See also: `TObjectQueue.Push` ([153](#)), `TObjectQueue.Peek` ([154](#))

### 7.26.4 TObjectQueue.Peek

Synopsis: Look at the first object in the queue.

Declaration: `function Peek : TObject`

Visibility: public

Description: `Peek` returns the first object in the queue, without removing it from the queue. If there are no more objects in the queue, `Nil` is returned.

Errors: None

See also: `TObjectQueue.Push` ([153](#)), `TObjectQueue.Pop` ([153](#))

## 7.27 TObjectStack

### 7.27.1 Description

`TObjectStack` is a stack implementation which manages pointers only.

`TObjectStack` introduces no new behaviour, it simply overrides some methods to accept and/or return `TObject` instances instead of pointers.

### 7.27.2 Method overview

Page	Property	Description
<a href="#">155</a>	<code>Peek</code>	Look at the top object in the stack.
<a href="#">154</a>	<code>Pop</code>	Pop the top object of the stack.
<a href="#">154</a>	<code>Push</code>	Push an object on the stack.

### 7.27.3 TObjectStack.Push

Synopsis: Push an object on the stack.

Declaration: `function Push(AObject: TObject) : TObject`

Visibility: public

Description: `Push` pushes another object on the stack. It overrides the `Push` method as implemented in `TStack` so it accepts only objects as arguments.

Errors: If not enough memory is available to expand the stack, an exception may be raised.

See also: `TObjectStack.Pop` ([154](#)), `TObjectStack.Peek` ([155](#))

### 7.27.4 TObjectStack.Pop

Synopsis: Pop the top object of the stack.

Declaration: `function Pop : TObject`

Visibility: `public`

Description: `Pop` pops the top object of the stack, and returns the object instance. If there are no more objects on the stack, `Nil` is returned.

Errors: None

See also: `TObjectStack.Push` ([154](#)), `TObjectStack.Peek` ([155](#))

### 7.27.5 TObjectStack.Peek

Synopsis: Look at the top object in the stack.

Declaration: `function Peek : TObject`

Visibility: `public`

Description: `Peek` returns the top object of the stack, without removing it from the stack. If there are no more objects on the stack, `Nil` is returned.

Errors: None

See also: `TObjectStack.Push` ([154](#)), `TObjectStack.Pop` ([154](#))

## 7.28 TOrderedList

### 7.28.1 Description

`TOrderedList` provides the base class for `TQueue` ([157](#)) and `TStack` ([157](#)). It provides an interface for pushing and popping elements on or off the list, and manages the internal list of pointers.

Note that `TOrderedList` does not manage objects on the stack, i.e. objects are not freed when the ordered list is destroyed.

### 7.28.2 Method overview

Page	Property	Description
<a href="#">156</a>	<code>AtLeast</code>	Check whether the list contains a certain number of elements.
<a href="#">156</a>	<code>Count</code>	Number of elements on the list.
<a href="#">155</a>	<code>Create</code>	Create a new ordered list
<a href="#">155</a>	<code>Destroy</code>	Free an ordered list
<a href="#">157</a>	<code>Peek</code>	Return the next element to be popped from the list.
<a href="#">157</a>	<code>Pop</code>	Remove an element from the list.
<a href="#">156</a>	<code>Push</code>	Push another element on the list.

### 7.28.3 TOrderedList.Create

Synopsis: Create a new ordered list

Declaration: `constructor Create`

Visibility: public

Description: `Create` instantiates a new ordered list. It initializes the internal pointer list.

Errors: None.

See also: `TOrderedList.Destroy` ([155](#))

#### 7.28.4 `TOrderedList.Destroy`

Synopsis: Free an ordered list

Declaration: `destructor Destroy; Override`

Visibility: public

Description: `Destroy` cleans up the internal pointer list, and removes the `TOrderedList` instance from memory.

Errors: None.

See also: `TOrderedList.Create` ([155](#))

#### 7.28.5 `TOrderedList.Count`

Synopsis: Number of elements on the list.

Declaration: `function Count : Integer`

Visibility: public

Description: `Count` is the number of pointers in the list.

Errors: None.

See also: `TOrderedList.AtLeast` ([156](#))

#### 7.28.6 `TOrderedList.AtLeast`

Synopsis: Check whether the list contains a certain number of elements.

Declaration: `function AtLeast (ACount: Integer) : Boolean`

Visibility: public

Description: `AtLeast` returns `True` if the number of elements in the list is equal to or bigger than `ACount`. It returns `False` otherwise.

Errors: None.

See also: `TOrderedList.Count` ([156](#))

### 7.28.7 TOrderedList.Push

Synopsis: Push another element on the list.

Declaration: `function Push(AItem: Pointer) : Pointer`

Visibility: `public`

Description: `Push` adds `AItem` to the list, and returns `AItem`.

Errors: If not enough memory is available to expand the list, an exception may be raised.

See also: `TOrderedList.Pop` ([157](#)), `TOrderedList.Peek` ([157](#))

### 7.28.8 TOrderedList.Pop

Synopsis: Remove an element from the list.

Declaration: `function Pop : Pointer`

Visibility: `public`

Description: `Pop` removes an element from the list, and returns the element that was removed from the list. If no element is on the list, `Nil` is returned.

Errors: None.

See also: `TOrderedList.Peek` ([157](#)), `TOrderedList.Push` ([156](#))

### 7.28.9 TOrderedList.Peek

Synopsis: Return the next element to be popped from the list.

Declaration: `function Peek : Pointer`

Visibility: `public`

Description: `Peek` returns the element that will be popped from the list at the next call to `Pop` ([157](#)), without actually popping it from the list.

Errors: None.

See also: `TOrderedList.Pop` ([157](#)), `TOrderedList.Push` ([156](#))

## 7.29 TQueue

### 7.29.1 Description

`TQueue` is a descendent of `TOrderedList` ([155](#)) which implements `Push` ([156](#)) and `Pop` ([157](#)) behaviour as a queue: what is first pushed on the queue, is popped of first (FIFO: First in, first out).

`TQueue` offers no new methods, it merely implements some abstract methods introduced by `TOrderedList` ([155](#))

## 7.30 TStack

### 7.30.1 Description

TStack is a descendent of TOrderedList (155) which implements Push (156) and Pop (157) behaviour as a stack: what is last pushed on the stack, is popped of first (LIFO: Last in, first out).

TStack offers no new methods, it merely implements some abstract methods introduced by TOrderedList (155)

## Chapter 8

# Reference for unit 'CustApp'

### 8.1 Used units

Table 8.1: Used units by unit 'CustApp'

Name	Page
Classes	??
sysutils	??

### 8.2 Overview

The `CustApp` unit implements the `TCustomApplication` ([159](#)) class, which serves as the common ancestor to many kinds of `TApplication` classes: a GUI application in the LCL, a CGI application in FPCGI, a daemon application in `daemonapp`. It introduces some properties to describe the environment in which the application is running (environment variables, program command-line parameters) and introduces some methods to initialize and run a program, as well as functionality to handle exceptions.

Typical use of a descendent class is to introduce a global variable `Application` and use the following code:

```
Application.Initialize;  
Application.Run;
```

Since normally only a single instance of this class is created, and it is a `TComponent` descendent, it can be used as an owner for many components, doing so will ensure these components will be freed when the application terminates.

### 8.3 Constants, types and variables

#### 8.3.1 Types

`TExceptionEvent` = procedure(Sender: TObject;E: Exception) of object

`TExceptionEvent` is the prototype for the exception handling events in `TCustomApplication`.



### 8.3.2 Variables

```
CustomApplication : TCustomApplication = nil
```

`CustomApplication` contains the global application instance. All descendents of `TCustomApplication` (159) should, in addition to storing an instance pointer in some variable (most likely called "Application") store the instance pointer in this variable. This ensures that, whatever kind of application is being created, user code can access the application object.

## 8.4 TCustomApplication

### 8.4.1 Description

`TCustomApplication` is the ancestor class for classes that wish to implement a global application class instance. It introduces several application-wide functionalities.

- Exception handling in `HandleException` (160), `ShowException` (161), `OnException` (166) and `StopOnException` (168).
- Command-line parameter parsing in `FindOptionIndex` (162), `GetOptionValue` (162), `CheckOptions` (163) and `HasOption` (163)
- Environment variable handling in `GetEnvironmentList` (164) and `EnvironmentVariable` (167).

Descendent classes need to override the `DoRun` protected method to implement the functionality of the program.

### 8.4.2 Method overview

Page	Property	Description
163	<code>CheckOptions</code>	Check whether all given options on the command-line are valid.
160	<code>Create</code>	Create a new instance of the <code>TCustomApplication</code> class
160	<code>Destroy</code>	Destroys the <code>TCustomApplication</code> instance.
162	<code>FindOptionIndex</code>	Return the index of an option.
164	<code>GetEnvironmentList</code>	Return a list of environment variables.
162	<code>GetOptionValue</code>	Return the value of a command-line option.
160	<code>HandleException</code>	Handle an exception.
163	<code>HasOption</code>	Check whether an option was specified.
161	<code>Initialize</code>	Initialize the application
164	<code>Log</code>	Write a message to the event log
161	<code>Run</code>	Runs the application.
161	<code>ShowException</code>	Show an exception to the user
162	<code>Terminate</code>	Terminate the application.

### 8.4.3 Property overview

Page	Property	Access	Description
<a href="#">168</a>	CaseSensitiveOptions	rw	Are options interpreted case sensitive or not
<a href="#">166</a>	ConsoleApplication	r	Is the application a console application or not
<a href="#">167</a>	EnvironmentVariable	r	Environment variable access
<a href="#">164</a>	ExeName	r	Name of the executable.
<a href="#">165</a>	HelpFile	rw	Location of the application help file.
<a href="#">166</a>	Location	r	Application location
<a href="#">166</a>	OnException	rw	Exception handling event
<a href="#">167</a>	OptionChar	rw	Command-line switch character
<a href="#">167</a>	ParamCount	r	Number of command-line parameters
<a href="#">166</a>	Params	r	Command-line parameters
<a href="#">168</a>	StopOnException	rw	Should the program loop stop on an exception
<a href="#">165</a>	Terminated	r	Was <code>Terminate</code> called or not
<a href="#">165</a>	Title	rw	Application title

### 8.4.4 TCustomApplication.Create

Synopsis: Create a new instance of the `TCustomApplication` class

Declaration: `constructor Create(AOwner: TComponent); Override`

Visibility: `public`

Description: `Create` creates a new instance of the `TCustomApplication` class. It sets some defaults for the various properties, and then calls the inherited `Create`.

See also: `TCustomApplication.Destroy` ([160](#))

### 8.4.5 TCustomApplication.Destroy

Synopsis: Destroys the `TCustomApplication` instance.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` simply calls the inherited `Destroy`.

See also: `TCustomApplication.Create` ([160](#))

### 8.4.6 TCustomApplication.HandleException

Synopsis: Handle an exception.

Declaration: `procedure HandleException(Sender: TObject); Virtual`

Visibility: `public`

Description: `HandleException` is called (or can be called) to handle the exception `Sender`. If the exception is not of class `Exception` then the default handling of exceptions in the `SysUtils` unit is called.

If the exception is of class `Exception` and the `OnException` ([166](#)) handler is set, the handler is called with the exception object and `Sender` argument.

If the `OnException` handler is not set, then the exception is passed to the `ShowException` ([161](#)) routine, which can be overridden by descendent application classes to show the exception in a way

that is fit for the particular class of application. (a GUI application might show the exception in a message dialog.

When the exception is handled in the above manner, and the `StopOnException` (168) property is set to `True`, the `Terminated` (165) property is set to `True`, which will cause the `Run` (161) loop to stop, and the application will exit.

See also: `TCustomApplication.ShowException` (161), `TCustomApplication.StopOnException` (168), `TCustomApplication.Terminated` (165), `TCustomApplication.Run` (161)

### 8.4.7 TCustomApplication.Initialize

Synopsis: Initialize the application

Declaration: `procedure Initialize; Virtual`

Visibility: `public`

Description: `Initialize` can be overridden by descendent applications to perform any initialization after the class was created. It can be used to react to properties being set at program startup. End-user code should call `Initialize` prior to calling `Run`

In `TCustomApplication`, `Initialize` sets `Terminated` to `False`.

See also: `TCustomApplication.Run` (161), `TCustomApplication.Terminated` (165)

### 8.4.8 TCustomApplication.Run

Synopsis: Runs the application.

Declaration: `procedure Run`

Visibility: `public`

Description: `Run` is the start of the user code: when called, it starts a loop and repeatedly calls `DoRun` until `Terminated` is set to `True`. If an exception is raised during the execution of `DoRun`, it is caught and handled to `TCustomApplication.HandleException` (160). If `TCustomApplication.StopOnException` (168) is set to `True` (which is *not* the default), `Run` will exit, and the application will then terminate. The default is to call `DoRun` again, which is useful for applications running a message loop such as services and GUI applications.

See also: `TCustomApplication.HandleException` (160), `TCustomApplication.StopException` (159)

### 8.4.9 TCustomApplication.ShowException

Synopsis: Show an exception to the user

Declaration: `procedure ShowException(E: Exception); Virtual`

Visibility: `public`

Description: `ShowException` should be overridden by descendent classes to show an exception message to the user. The default behaviour is to call the `ShowException(??)` procedure in the `SysUtils` unit.

Descendent classes should do something appropriate for their context: GUI applications can show a message box, daemon applications can write the exception message to the system log, web applications can send a 500 error response code.

Errors: None.

See also: `#rtl.sysutils.ShowException` (??), `TCustomApplication.HandleException` (160), `TCustomApplication.StopException` (159)

#### 8.4.10 TCustomApplication.Terminate

Synopsis: Terminate the application.

Declaration: `procedure Terminate; Virtual`

Visibility: `public`

Description: `Terminate` sets the `Terminated` property to `True`. By itself, this does not terminate the application. Instead, descendent classes should in their `DoRun` method, check the value of the `Terminated` (165) property and properly shut down the application if it is set to `True`.

See also: `TCustomApplication.Terminated` (165), `TCustomApplication.Run` (161)

#### 8.4.11 TCustomApplication.FindOptionIndex

Synopsis: Return the index of an option.

Declaration: `function FindOptionIndex(const S: String; var Longopt: Boolean) : Integer`

Visibility: `public`

Description: `FindOptionIndex` will return the index of the option `S` or the long option `LongOpt`. Neither of them should include the switch character. If no such option was specified, -1 is returned. If either the long or short option was specified, then the position on the command-line is returned.

Depending on the value of the `CaseSensitiveOptions` (168) property, the search is performed case sensitive or case insensitive.

Options are identified as command-line parameters which start with `OptionChar` (167) (by default the dash ('-') character).

See also: `TCustomApplication.HasOption` (163), `TCustomApplication.GetOptionValue` (162), `TCustomApplication.CheckOptions` (163), `TCustomApplication.CaseSensitiveOptions` (168), `TCustomApplication.OptionChar` (167)

#### 8.4.12 TCustomApplication.GetOptionValue

Synopsis: Return the value of a command-line option.

Declaration: `function GetOptionValue(const S: String) : String`  
`function GetOptionValue(const C: Char; const S: String) : String`

Visibility: `public`

Description: `GetOptionValue` returns the value of an option. Values are specified in the usual GNU option format, either of

`--longopt=Value`

or

`-c Value`

is supported.

The function returns the specified value, or the empty string if none was specified.

Depending on the value of the `CaseSensitiveOptions` (168) property, the search is performed case sensitive or case insensitive.

Options are identified as command-line parameters which start with `OptionChar` (167) (by default the dash ('-') character).

See also: `TCustomApplication.FindOptionIndex` (162), `TCustomApplication.HasOption` (163), `TCustomApplication.CheckOptions` (163), `TCustomApplication.CaseSensitiveOptions` (168), `TCustomApplication.OptionChar` (167)

### 8.4.13 TCustomApplication.HasOption

Synopsis: Check whether an option was specified.

Declaration: `function HasOption(const S: String) : Boolean`  
`function HasOption(const C: Char;const S: String) : Boolean`

Visibility: public

Description: `HasOption` returns `True` if the specified option was given on the command line. Either the short option character `C` or the long option `S` may be used. Note that both options (requiring a value) and switches can be specified.

Depending on the value of the `CaseSensitiveOptions` (168) property, the search is performed case sensitive or case insensitive.

Options are identified as command-line parameters which start with `OptionChar` (167) (by default the dash ('-') character).

See also: `TCustomApplication.FindOptionIndex` (162), `TCustomApplication.GetOptionValue` (162), `TCustomApplication.CheckOptions` (163), `TCustomApplication.CaseSensitiveOptions` (168), `TCustomApplication.OptionChar` (167)

### 8.4.14 TCustomApplication.CheckOptions

Synopsis: Check whether all given options on the command-line are valid.

Declaration: `function CheckOptions(const ShortOptions: String;`  
`const Longopts: TStrings;Opts: TStrings;`  
`NonOpts: TStrings) : String`  
`function CheckOptions(const ShortOptions: String;`  
`const Longopts: TStrings) : String`  
`function CheckOptions(const ShortOptions: String;`  
`const LongOpts: Array of String) : String`  
`function CheckOptions(const ShortOptions: String;const LongOpts: String)`  
`: String`

Visibility: public

Description: `CheckOptions` scans the command-line and checks whether the options given are valid options. It also checks whether options that require a value are indeed specified with a value.

The `ShortOptions` contains a string with valid short option characters. Each character in the string is a valid option character. If a character is followed by a colon (:), then a value must be specified. If it is followed by 2 colon characters (::) then the value is optional.

`LongOpts` is a list of strings (which can be specified as an array, a `TStrings` instance or a string with whitespace-separated values) of valid long options.

When the function returns, if `Opts` is non-`Nil`, the `Opts` stringlist is filled with the passed valid options. If `NonOpts` is non-`nil`, it is filled with any non-option strings that were passed on the command-line.

The function returns an empty string if all specified options were valid options, and whether options requiring a value have a value. If an error was found during the check, the return value is a string describing the error.

Options are identified as command-line parameters which start with `OptionChar` (167) (by default the dash ('-') character).

**Errors:** if an error was found during the check, the return value is a string describing the error.

**See also:** `TCustomApplication.FindOptionIndex` (162), `TCustomApplication.GetOptionValue` (162), `TCustomApplication.HasOption` (163), `TCustomApplication.CaseSensitiveOptions` (168), `TCustomApplication.OptionChar` (167)

### 8.4.15 TCustomApplication.GetEnvironmentList

**Synopsis:** Return a list of environment variables.

**Declaration:** `procedure GetEnvironmentList(List: TStrings; NamesOnly: Boolean);`  
`procedure GetEnvironmentList(List: TStrings)`

**Visibility:** public

**Description:** `GetEnvironmentList` returns a list of environment variables in `List`. They are in the form `Name=Value`, one per item in list. If `NamesOnly` is `True`, then only the names are returned.

**See also:** `TCustomApplication.EnvironmentVariable` (167)

### 8.4.16 TCustomApplication.Log

**Synopsis:** Write a message to the event log

**Declaration:** `procedure Log(EventType: TEventType; Msg: String);` Virtual

**Visibility:** public

**Description:** `Log` is meant for all applications to have a default logging mechanism. By default it does not do anything, descendent classes should override this method to provide appropriate logging: they should write the message `Msg` with type `EventType` to some log mechanism such as `#fcl.eventlog.TEventLog` (395)

**Errors:** None.

**See also:** `#rtl.classes.TEventType` (??)

### 8.4.17 TCustomApplication.ExeName

**Synopsis:** Name of the executable.

**Declaration:** `Property ExeName : String`

**Visibility:** public

Access: Read

Description: `ExeName` returns the full name of the executable binary (path+filename). This is equivalent to `Paramstr(0)`

Note that some operating systems do not return the full pathname of the binary.

See also: `#rtl.system.paramstr(??)`

### 8.4.18 TCustomApplication.HelpFile

Synopsis: Location of the application help file.

Declaration: `Property HelpFile : String`

Visibility: public

Access: Read,Write

Description: `HelpFile` is the location of the application help file. It is a simple string property which can be set by an IDE such as Lazarus, and is mainly provided for compatibility with Delphi's `TApplication` implementation.

See also: `TCustomApplication.Title` ([165](#))

### 8.4.19 TCustomApplication.Terminated

Synopsis: Was `Terminate` called or not

Declaration: `Property Terminated : Boolean`

Visibility: public

Access: Read

Description: `Terminated` indicates whether `Terminate` ([162](#)) was called or not. Descendent classes should check `Terminated` at regular intervals in their implementation of `DoRun`, and if it is set to `True`, should exit gracefully the `DoRun` method.

See also: `TCustomApplication.Terminate` ([162](#))

### 8.4.20 TCustomApplication.Title

Synopsis: Application title

Declaration: `Property Title : String`

Visibility: public

Access: Read,Write

Description: `Title` is a simple string property which can be set to any string describing the application. It does nothing by itself, and is mainly introduced for compatibility with Delphi's `TApplication` implementation.

See also: `TCustomApplication.HelpFile` ([165](#))

### 8.4.21 TCustomApplication.OnException

Synopsis: Exception handling event

Declaration: `Property OnException : TExceptionEvent`

Visibility: `public`

Access: `Read, Write`

Description: `OnException` can be set to provide custom handling of events, instead of the default action, which is simply to show the event using `ShowEvent` (159).

If set, `OnException` is called by the `HandleEvent` (159) routine. Do not use the `OnException` event directly, instead call `HandleEvent`

See also: `TCustomApplication.ShowEvent` (159)

### 8.4.22 TCustomApplication.ConsoleApplication

Synopsis: Is the application a console application or not

Declaration: `Property ConsoleApplication : Boolean`

Visibility: `public`

Access: `Read`

Description: `ConsoleApplication` returns `True` if the application is compiled as a console application (the default) or `False` if not. The result of this property is determined at compile-time by the settings of the compiler: it returns the value of the `IsConsole` (??) constant.

See also: `#rtl.system.IsConsole` (??)

### 8.4.23 TCustomApplication.Location

Synopsis: Application location

Declaration: `Property Location : String`

Visibility: `public`

Access: `Read`

Description: `Location` returns the directory part of the application binary. This property works on most platforms, although some platforms do not allow to retrieve this information (Mac OS under certain circumstances). See the discussion of `Paramstr` (??) in the RTL documentation.

See also: `#rtl.system.paramstr` (??), `TCustomApplication.Params` (166)

### 8.4.24 TCustomApplication.Params

Synopsis: Command-line parameters

Declaration: `Property Params[Index: Integer]: String`

Visibility: `public`

Access: `Read`



**Description:** `Params` gives access to the command-line parameters. They contain the value of the `Index`-th parameter, where `Index` runs from 0 to `ParamCount` (167). It is equivalent to calling `ParamStr` (??).

See also: `TCustomApplication.ParamCount` (167), `#rtl.system.paramstr` (??)

### 8.4.25 TCustomApplication.ParamCount

**Synopsis:** Number of command-line parameters

**Declaration:** `Property ParamCount : Integer`

**Visibility:** public

**Access:** Read

**Description:** `ParamCount` returns the number of command-line parameters that were passed to the program. The actual parameters can be retrieved with the `Params` (166) property.

See also: `TCustomApplication.Params` (166), `#rtl.system.paramstr` (??), `#rtl.system.paramcount` (??)

### 8.4.26 TCustomApplication.EnvironmentVariable

**Synopsis:** Environment variable access

**Declaration:** `Property EnvironmentVariable[envName: String]: String`

**Visibility:** public

**Access:** Read

**Description:** `EnvironmentVariable` gives access to the environment variables of the application: It returns the value of the environment variable `EnvName`, or an empty string if no such value is available.

To use this property, the name of the environment variable must be known. To get a list of available names (and values), `GetEnvironmentList` (164) can be used.

See also: `TCustomApplication.GetEnvironmentList` (164), `TCustomApplication.Params` (166)

### 8.4.27 TCustomApplication.OptionChar

**Synopsis:** Command-line switch character

**Declaration:** `Property OptionChar : Char`

**Visibility:** public

**Access:** Read, Write

**Description:** `OptionChar` is the character used for command line switches. By default, this is the dash ('-') character, but it can be set to any other non-alphanumeric character (although no check is performed on this).

See also: `TCustomApplication.FindOptionIndex` (162), `TCustomApplication.GetOptionValue` (162), `TCustomApplication.HasOption` (163), `TCustomApplication.CaseSensitiveOptions` (168), `TCustomApplication.CheckOptions` (163)

### 8.4.28 TCustomApplication.CaseSensitiveOptions

Synopsis: Are options interpreted case sensitive or not

Declaration: Property CaseSensitiveOptions : Boolean

Visibility: public

Access: Read,Write

Description: CaseSensitiveOptions determines whether FindOptionIndex (162) and CheckOptions (163) perform searches in a case sensitive manner or not. By default, the search is case-sensitive. Setting this property to False makes the search case-insensitive.

See also: TCustomApplication.FindOptionIndex (162), TCustomApplication.GetOptionValue (162), TCustomApplication.HasOption (163), TCustomApplication.OptionChar (167), TCustomApplication.CheckOptions (163)

### 8.4.29 TCustomApplication.StopOnException

Synopsis: Should the program loop stop on an exception

Declaration: Property StopOnException : Boolean

Visibility: public

Access: Read,Write

Description: StopOnException controls the behaviour of the Run (161) and HandleException (160) procedures in case of an unhandled exception in the DoRun code. If StopOnException is True then Terminate (162) will be called after the exception was handled.

See also: TCustomApplication.Run (161), TCustomApplication.HandleException (160), TCustomApplication.Terminate (162)

## Chapter 9

# Reference for unit 'daemonapp'

### 9.1 Used units

Table 9.1: Used units by unit 'daemonapp'

Name	Page
Classes	??
CustApp	<a href="#">158</a>
eventlog	<a href="#">394</a>
rtlconsts	<a href="#">169</a>
sysutils	??

### 9.2 Overview

The `daemonapp` unit implements a `TApplication` class which encapsulates a daemon or service application. It handles installation where this is necessary, and does instantiation of the various daemons where necessary.

The unit consists of 3 separate classes which cooperate tightly:

**TDaemon** This is a class that implements the daemon's functionality. One or more descendents of this class can be implemented and instantiated in a single daemon application. For more information, see `TDaemon` ([184](#)).

**TDaemonApplication** This is the actual daemon application class. A global instance of this class is instantiated. It handles the command-line arguments, and instantiates the various daemons. For more information, see `TDaemonApplication` ([189](#)).

**TDaemonDef** This class defines the daemon in the operation system. The `TDaemonApplication` class has a collection of `TDaemonDef` instances, which it uses to start the various daemons. For more information, see `TDaemonDef` ([192](#)).

As can be seen, a single application can implement one or more daemons (services). Each daemon will be run in a separate thread which is controlled by the application class.

The classes take care of logging through the `TEventLog` ([395](#)) class.

Many options are needed only to make the application behave as a windows service application on windows. These options are ignored in unix-like environment. The documentation will mention this.

## 9.3 Daemon application architecture

[Still needs to be completed]

## 9.4 Constants, types and variables

### 9.4.1 Resource strings

`SControlFailed = 'Control code %s handling failed: %s'`

The control code was not handled correctly

`SCustomCode = '[Custom code %d]'`

A custom code was received

`SDaemonStatus = 'Daemon %s current status: %s'`

Daemon status report log message

`SErrApplicationAlreadyCreated = 'An application instance of class %s was already created'`

A second application instance is created

`SErrDaemonStartFailed = 'Failed to start daemon %s : %s'`

The application failed to start the daemon

`SErrDuplicateName = 'Duplicate daemon name: %s'`

Duplicate service name

`SErrNoDaemonDefForStatus = '%s: No daemon definition for status report'`

Internal error: no daemon definition to report status for

`SErrNoDaemonForStatus = '%s: No daemon for status report'`

Internal error: no daemon to report status for

`SErrNoServiceMapper = 'No daemon mapper class registered.'`

No service mapper was found.

`SErrNothingToDo = 'Options do not allow determining what needs to be done.'`

No operation can be performed

`SErrOnlyOneMapperAllowed = 'Not changing daemon mapper class %s with %s: Only 1 mapper allowed'`

An attempt was made to install a second service mapper

```
SErrServiceManagerStartFailed = 'Failed to start service manager: %s'
```

Unable to start or contact the service manager

```
SErrUnknownDaemonClass = 'Unknown daemon class name: %s'
```

Unknown daemon class requested

```
SErrWindowClass = 'Could not register window class'
```

Could not register window class

## 9.4.2 Types

```
TCurrentStatus = (csStopped, csStartPending, csStopPending, csRunning,
                  csContinuePending, csPausePending, csPaused)
```

Table 9.2: Enumeration values for type TCurrentStatus

Value	Explanation
csContinuePending	The daemon is continuing, but not yet running
csPaused	The daemon is paused: running but not active.
csPausePending	The daemon is about to be paused.
csRunning	The daemon is running (it is operational).
csStartPending	The daemon is starting, but not yet fully running.
csStopped	The daemon is stopped, i.e. inactive.
csStopPending	The daemon is stopping, but not yet fully stopped.

TCurrentStatus indicates the current state of the daemon. It changes from one state to the next during the time the instance is active. The daemon application changes the state of the daemon, depending on signals it gets from the operating system, by calling the appropriate methods.

```
TCustomControlCodeEvent = procedure(Sender: TCustomDaemon; ACode: DWord;
                                     var Handled: Boolean) of object
```

In case the system sends a non-standard control code to the daemon, an event handler is executed with this prototype.

```
TCustomDaemonApplicationClass = Class of TCustomDaemonApplication
```

Class pointer for TCustomDaemonApplication

```
TCustomDaemonClass = Class of TCustomDaemon
```

The class type is needed in the TDaemonDef (192) definition.

```
TCustomDaemonMapperClass = Class of TCustomDaemonMapper
```

`TCustomDaemonMapperClass` is the class of `TCustomDaemonMapper`. It is used in the `RegisterDaemonMapper` (175) call.

`TDaemonClass` = Class of `TDaemon`

Class type of `TDaemon`

`TDaemonEvent` = procedure(Sender: `TCustomDaemon`) of object

`TDaemonEvent` is used in event handling. The `Sender` is the `TCustomDaemon` (175) instance that has initiated the event.

`TDaemonOKEvent` = procedure(Sender: `TCustomDaemon`; var `OK`: Boolean) of object

`TDaemonOKEvent` is used in event handling, when a boolean result must be obtained, for instance, to see if an operation was performed successfully.

`TDaemonOption` = (doAllowStop, doAllowPause, doInteractive)

Table 9.3: Enumeration values for type `TDaemonOption`

Value	Explanation
doAllowPause	The daemon can be paused.
doAllowStop	The daemon can be stopped.
doInteractive	The daemon interacts with the desktop.

Enumerated that enumerates the various daemon operation options.

`TDaemonOptions`= Set of (doAllowPause, doAllowStop, doInteractive)

`TDaemonOption` enumerates the various options a daemon can have.

`TDaemonRunMode` = (drmUnknown, drmInstall, drmUninstall, drmRun)

Table 9.4: Enumeration values for type `TDaemonRunMode`

Value	Explanation
drmInstall	Daemon install mode (windows only)
drmRun	Daemon is running normally
drmUninstall	Daemon uninstall mode (windows only)
drmUnknown	Unknown mode

`TDaemonRunMode` indicates in what mode the daemon application (as a whole) is currently running.

`TErrorSeverity` = (esIgnore, esNormal, esSevere, esCritical)

Table 9.5: Enumeration values for type TErrorSeverity

Value	Explanation
esCritical	Error is logged, and startup is stopped if last known good configuration is active, or system is restarted using last known good configuration
esIgnore	Ignore startup errors
esNormal	Error is logged, but startup continues
esSevere	Error is logged, and startup is continued if last known good configuration is active, or system is restarted using last known good configuration

TErrorSeverity determines what action windows takes when the daemon fails to start. It is used on windows only, and is ignored on other platforms.

TGuiLoopEvent = procedure of object

TGuiLoopEvent is the main GUI loop event procedure prototype. It is called by the application instance in case the daemon has a visual part, which needs to handle visual events. It is run in the main application thread.

TServiceType = (stWin32, stDevice, stFileSystem)

Table 9.6: Enumeration values for type TServiceType

Value	Explanation
stDevice	Device driver
stFileSystem	File system driver
stWin32	Regular win32 service

The type of service. This type is used on windows only, to signal the operating system what kind of service is being installed or run.

TStartType = (stBoot, stSystem, stAuto, stManual, stDisabled)

Table 9.7: Enumeration values for type TStartType

Value	Explanation
stAuto	Started automatically by service manager during system startup
stBoot	During system boot
stDisabled	Service is not started, it is disabled
stManual	Started manually by the user or other processes.
stSystem	During load of device drivers

TStartType can be used to define when the service must be started on windows. This type is not used on other platforms.

### 9.4.3 Variables

AppClass : TCustomDaemonApplicationClass

`CurrentStatusNames : Array[TCurrentStatus] of String = ('Stopped', 'Start Pending', 'S`

Names for various service statuses

`DefaultDaemonOptions : TDaemonOptions = [doAllowStop, doAllowPause]`

`DefaultDaemonOptions` are the default options with which a daemon definition (`TDaemonDef` (192)) is created.

`SStatus : Array[1..5] of String = ('Stop', 'Pause', 'Continue', 'Interrogate', 'Shutdown`

Status message

## 9.5 Procedures and functions

### 9.5.1 Application

Synopsis: Application instance

Declaration: `function Application : TCustomDaemonApplication`

Visibility: default

Description: `Application` is the `TCustomDaemonApplication` (178) instance used by this application. The instance is created at the first invocation of this function, so it is possible to use `RegisterDaemonApplicationClass` (174) to register an alternative `TCustomDaemonApplication` class to run the application.

See also: `TCustomDaemonApplication` (178), `RegisterDaemonApplicationClass` (174)

### 9.5.2 DaemonError

Synopsis: Raise an `EDaemon` exception

Declaration: `procedure DaemonError(Msg: String)`  
`procedure DaemonError(Fmt: String; Args: Array of const)`

Visibility: default

Description: `DaemonError` raises an `EDaemon` (175) exception with message `Msg` or it formats the message using `Fmt` and `Args`.

See also: `EDaemon` (175)

### 9.5.3 RegisterDaemonApplicationClass

Synopsis: Register alternative `TCustomDaemonApplication` class.

Declaration: `procedure RegisterDaemonApplicationClass`  
`(AClass: TCustomDaemonApplicationClass)`

Visibility: default

Description: `RegisterDaemonApplicationClass` can be used to register an alternative `TCustomDaemonApplication` (178) descendent which will be used when creating the global `Application` (174) instance. Only the last registered class pointer will be used.

See also: `TCustomDaemonApplication` (178), `Application` (174)



### 9.5.4 RegisterDaemonClass

Synopsis: Register daemon

Declaration: `procedure RegisterDaemonClass (AClass: TCustomDaemonClass)`

Visibility: default

Description: `RegisterDaemonClass` must be called for each `TCustomDaemon` (175) descendent that is used in the class: the class pointer and class name are used by the `TCustomDaemonMapperClass` (172) class to create a `TCustomDaemon` instance when a daemon is required.

See also: `TCustomDaemonMapperClass` (172), `TCustomDaemon` (175)

### 9.5.5 RegisterDaemonMapper

Synopsis: Register a daemon mapper class

Declaration: `procedure RegisterDaemonMapper (AMapperClass: TCustomDaemonMapperClass)`

Visibility: default

Description: `RegisterDaemonMapper` can be used to register an alternative class for the global daemon-mapper. The daemonmapper will be used only when the application is being run, by the `TCustomDaemonApplication` (178) code, so registering an alternative mapping class should happen in the initialization section of the application units.

See also: `TCustomDaemonApplication` (178), `TCustomDaemonMapperClass` (172)

## 9.6 EDaemon

### 9.6.1 Description

`EDaemon` is the exception class used by all code in the `DaemonApp` unit.

## 9.7 TCustomDaemon

### 9.7.1 Description

`TCustomDaemon` implements all the basic calls that are needed for a daemon to function. Descendents of `TCustomDaemon` can override these calls to implement the daemon-specific behaviour.

`TCustomDaemon` is an abstract class, it should never be instantiated. Either a descendent of it must be created and instantiated, or a descendent of `TDaemon` (184) can be designed to implement the behaviour of the daemon.

### 9.7.2 Method overview

Page	Property	Description
176	<code>LogMessage</code>	Log a message to the system log
176	<code>ReportStatus</code>	Report the current status to the operating system

### 9.7.3 Property overview

Page	Property	Access	Description
<a href="#">177</a>	Controller	r	TDaemonController instance controlling this daemon instance
<a href="#">177</a>	DaemonThread	r	Thread in which daemon is running
<a href="#">176</a>	Definition	r	The definition used to instantiate this daemon instance
<a href="#">178</a>	Logger	r	TEventLog instance used to send messages to the system log
<a href="#">177</a>	Status	rw	Current status of the daemon

### 9.7.4 TCustomDaemon.LogMessage

Synopsis: Log a message to the system log

Declaration: `procedure LogMessage(Msg: String)`

Visibility: `public`

Description: `LogMessage` can be used to send a message `Msg` to the system log. A `TEventLog` ([395](#)) instance is used to actually send messages to the system log.

The message is sent with an 'error' flag (using `TEventLog.Error` ([398](#))).

Errors: None.

See also: `TCustomDaemon.ReportStatus` ([176](#))

### 9.7.5 TCustomDaemon.ReportStatus

Synopsis: Report the current status to the operating system

Declaration: `procedure ReportStatus`

Visibility: `public`

Description: `ReportStatus` can be used to report the current status to the operating system. The start and stop or pause and continue operations can be slow to start up. This call can (and should) be used to report the current status to the operating system during such lengthy operations, or else it may conclude that the daemon has died.

This call is mostly important on windows operating systems, to notify the service manager that the operation is still in progress.

The implementation of `ReportStatus` simply calls `ReportStatus` in the controller.

Errors: None.

See also: `TCustomDaemon.LogMessage` ([176](#))

### 9.7.6 TCustomDaemon.Definition

Synopsis: The definition used to instantiate this daemon instance

Declaration: `Property Definition : TDaemonDef`

Visibility: `public`

Access: Read

**Description:** `Definition` is the `TDaemonDef` ([192](#)) definition that was used to start the daemon instance. It can be used to retrieve additional information about the intended behaviour of the daemon.

See also: `TDaemonDef` ([192](#))

### 9.7.7 `TCustomDaemon.DaemonThread`

**Synopsis:** Thread in which daemon is running

**Declaration:** `Property DaemonThread : TThread`

**Visibility:** `public`

**Access:** `Read`

**Description:** `DaemonThread` is the thread in which the daemon instance is running. Each daemon instance in the application runs in it's own thread, none of which are the main thread of the application. The application main thread is used to handle control messages coming from the operating system.

See also: `TCustomDaemon.Controller` ([177](#))

### 9.7.8 `TCustomDaemon.Controller`

**Synopsis:** `TDaemonController` instance controlling this daemon instance

**Declaration:** `Property Controller : TDaemonController`

**Visibility:** `public`

**Access:** `Read`

**Description:** `Controller` points to the `TDaemonController` instance that was created by the application instance to control this daemon.

See also: `TCustomDaemon.DaemonThread` ([177](#))

### 9.7.9 `TCustomDaemon.Status`

**Synopsis:** Current status of the daemon

**Declaration:** `Property Status : TCurrentStatus`

**Visibility:** `public`

**Access:** `Read,Write`

**Description:** `Status` indicates the current status of the daemon. It is set by the various operations that the controller operates on the daemon, and should not be set manually.

`Status` is the value which `ReportStatus` will send to the operating system.

See also: `TCustomDaemon.ReportStatus` ([176](#))

### 9.7.10 TCustomDaemon.Logger

Synopsis: TEventLog instance used to send messages to the system log

Declaration: `Property Logger : TEventLog`

Visibility: `public`

Access: `Read`

Description: `Logger` is the TEventLog (395) instance used to send messages to the system log. It is used by the `LogMessage` (176) call, but is accessible through the `Logger` property in case more configurable logging is needed than offered by `LogMessage`.

See also: `TCustomDaemon.LogMessage` (176), `#fcl.eventlog.TEventLog` (395)

## 9.8 TCustomDaemonApplication

### 9.8.1 Description

TCustomDaemonApplication is a TCustomApplication (159) descendent which is the main application instance for a daemon. It handles the command-line and decides what to do when the application is started, depending on the command-line options given to the application, by calling the various methods.

It creates the necessary TDaemon (184) instances by checking the TCustomDaemonMapperClass (172) instance that contains the daemon maps.

### 9.8.2 Method overview

Page	Property	Description
<a href="#">179</a>	CreateDaemon	Create daemon instance
<a href="#">180</a>	CreateForm	Create a component
<a href="#">179</a>	InstallDaemons	Install all daemons.
<a href="#">179</a>	RunDaemons	Run all daemons.
<a href="#">178</a>	ShowException	Show an exception
<a href="#">179</a>	StopDaemons	Stop all daemons
<a href="#">180</a>	UnInstallDaemons	Uninstall all daemons

### 9.8.3 Property overview

Page	Property	Access	Description
<a href="#">181</a>	GuiHandle	rw	Handle of GUI loop main application window handle
<a href="#">181</a>	GUIMainLoop	rw	GUI main loop callback
<a href="#">180</a>	Logger	r	Event logging instance used for logging messages
<a href="#">180</a>	OnRun	rw	
<a href="#">181</a>	RunMode	r	Application mode

### 9.8.4 TCustomDaemonApplication.ShowException

Synopsis: Show an exception

Declaration: `procedure ShowException(E: Exception); Override`

Visibility: `public`

**Description:** `ShowException` is overridden by `TCustomDaemonApplication`, it sends the exception message to the system log.

### 9.8.5 TCustomDaemonApplication.CreateDaemon

**Synopsis:** Create daemon instance

**Declaration:** `function CreateDaemon(DaemonDef: TDaemonDef) : TCustomDaemon`

**Visibility:** public

**Description:** `CreateDaemon` is called whenever a `TCustomDaemon` (175) instance must be created from a `TDaemonDef` (192) daemon definition, passed in `DaemonDef`. It initializes the `TCustomDaemon` instance, and creates a controller instance of type `TDaemonController` (189) to control the daemon. Finally, it assigns the created daemon to the `TDaemonDef.Instance` (193) property.

**Errors:** In case of an error, an exception may be raised.

**See also:** `TDaemonController` (189), `TCustomDaemon` (175), `TDaemonDef` (192), `TDaemonDef.Instance` (193)

### 9.8.6 TCustomDaemonApplication.StopDaemons

**Synopsis:** Stop all daemons

**Declaration:** `procedure StopDaemons(Force: Boolean)`

**Visibility:** public

**Description:** `StopDaemons` sends the `STOP` control code to all daemons, or the `SHUTDOWN` control code in case `Force` is `True`.

**See also:** `TDaemonController.Controller` (190), `TCustomDaemonApplication.UnInstallDaemons` (180), `TCustomDaemonApplication.RunDaemons` (179)

### 9.8.7 TCustomDaemonApplication.InstallDaemons

**Synopsis:** Install all daemons.

**Declaration:** `procedure InstallDaemons`

**Visibility:** public

**Description:** `InstallDaemons` installs all known daemons, i.e. registers them with the service manager on Windows. This method is called if the application is run with the `-i` or `-install` or `/install` command-line option.

**See also:** `TCustomDaemonApplication.UnInstallDaemons` (180), `TCustomDaemonApplication.RunDaemons` (179), `TCustomDaemonApplication.StopDaemons` (179)

### 9.8.8 TCustomDaemonApplication.RunDaemons

**Synopsis:** Run all daemons.

**Declaration:** `procedure RunDaemons`

**Visibility:** public

**Description:** `RunDaemons` runs (starts) all known daemons. This method is called if the application is run with the `-r` or `-run` methods.

**Errors:**

**See also:** `TCustomDaemonApplication.UnInstallDaemons` ([180](#)), `TCustomDaemonApplication.InstallDaemons` ([179](#)), `TCustomDaemonApplication.StopDaemons` ([179](#))

### 9.8.9 TCustomDaemonApplication.UnInstallDaemons

**Synopsis:** Uninstall all daemons

**Declaration:** `procedure UnInstallDaemons`

**Visibility:** `public`

**Description:** `UnInstallDaemons` uninstalls all known daemons, i.e. deregisters them with the service manager on Windows. This method is called if the application is run with the `-u` or `-uninstall` or `/uninstall` command-line option.

**See also:** `TCustomDaemonApplication.RunDaemons` ([179](#)), `TCustomDaemonApplication.InstallDaemons` ([179](#)), `TCustomDaemonApplication.StopDaemons` ([179](#))

### 9.8.10 TCustomDaemonApplication.CreateForm

**Synopsis:** Create a component

**Declaration:** `procedure CreateForm(InstanceClass: TComponentClass; var Reference)  
; Virtual`

**Visibility:** `public`

**Description:** `CreateForm` creates an instance of `InstanceClass` and fills `Reference` with the class instance pointer. It's main purpose is to give an IDE a means of assuring that forms or datamodules are created on application startup: the IDE will generate calls for all modules that are auto-created.

**Errors:** An exception may arise if the instance wants to stream itself from resources, but no resources are found.

**See also:** `TCustomDaemonApplication.CreateDaemon` ([179](#))

### 9.8.11 TCustomDaemonApplication.OnRun

**Declaration:** `Property OnRun : TNotifyEvent`

**Visibility:** `public`

**Access:** `Read,Write`

### 9.8.12 TCustomDaemonApplication.Logger

**Synopsis:** Event logging instance used for logging messages

**Declaration:** `Property Logger : TEventLog`

**Visibility:** `public`

Access: Read

Description: `Logger` contains a reference to the `TEventLog` (395) instance that can be used to send messages to the system log.

See also: `TCustomDaemon.LogMessage` (176)

### 9.8.13 `TCustomDaemonApplication.GUIMainLoop`

Synopsis: GUI main loop callback

Declaration: `Property GUIMainLoop : TGuiLoopEvent`

Visibility: public

Access: Read,Write

Description: `GUIMainLoop` contains a reference to a method that can be called to process a main GUI loop. The procedure should return only when the main GUI has finished and the application should exit. It is called when the daemons are running.

See also: `TCustomDaemonApplication.GuiHandle` (181)

### 9.8.14 `TCustomDaemonApplication.GuiHandle`

Synopsis: Handle of GUI loop main application window handle

Declaration: `Property GuiHandle : THandle`

Visibility: public

Access: Read,Write

Description: `GuiHandle` is the handle of a GUI window which can be used to run a message handling loop on. It is created when no `GUIMainLoop` (181) procedure exists, and the application creates and runs a message loop by itself.

See also: `TCustomDaemonApplication.GUIMainLoop` (181)

### 9.8.15 `TCustomDaemonApplication.RunMode`

Synopsis: Application mode

Declaration: `Property RunMode : TDaemonRunMode`

Visibility: public

Access: Read

Description: `RunMode` indicates in which mode the application is running currently. It is set automatically by examining the command-line, and when set, one of `InstallDaemons` (179), `RunDaemons` (179) or `UnInstallDaemons` (180) is called.

See also: `TCustomDaemonApplication.InstallDaemons` (179), `TCustomDaemonApplication.RunDaemons` (179), `TCustomDaemonApplication.UnInstallDaemons` (180)

## 9.9 TCustomDaemonMapper

### 9.9.1 Description

The `TCustomDaemonMapper` class is responsible for mapping a daemon definition to an actual `TDaemon` instance. It maintains a `TDaemonDefs` (196) collection with daemon definitions, which can be used to map the definition of a daemon to a `TDaemon` descendent class.

An IDE such as Lazarus can design a `TCustomDaemonMapper` instance visually, to help establish the relationship between various `TDaemonDef` (192) definitions and the actual `TDaemon` (184) instances that will be used to run the daemons.

The `TCustomDaemonMapper` class has no support for streaming. The `TDaemonMapper` (198) class has support for streaming (and hence visual designing).

### 9.9.2 Method overview

Page	Property	Description
<a href="#">182</a>	Create	Create a new instance of <code>TCustomDaemonMapper</code>
<a href="#">182</a>	Destroy	Clean up and destroy a <code>TCustomDaemonMapper</code> instance.

### 9.9.3 Property overview

Page	Property	Access	Description
<a href="#">183</a>	<code>DaemonDefs</code>	rw	Collection of daemons
<a href="#">183</a>	<code>OnCreate</code>	rw	Event called when the daemon mapper is created
<a href="#">183</a>	<code>OnDestroy</code>	rw	Event called when the daemon mapper is freed.
<a href="#">184</a>	<code>OnInstall</code>	rw	Event called when the daemons are installed
<a href="#">183</a>	<code>OnRun</code>	rw	Event called when the daemons are executed.
<a href="#">184</a>	<code>OnUnInstall</code>	rw	Event called when the daemons are uninstalled

### 9.9.4 TCustomDaemonMapper.Create

**Synopsis:** Create a new instance of `TCustomDaemonMapper`

**Declaration:** `constructor Create(AOwner: TComponent); Override`

**Visibility:** `public`

**Description:** `Create` creates a new instance of a `TCustomDaemonMapper`. It creates the `TDaemonDefs` (196) collection and then calls the inherited constructor. It should never be necessary to create a daemon mapper manually, the application will create a global `TCustomDaemonMapper` instance.

**See also:** `TDaemonDefs` (196), `TCustomDaemonApplication` (178), `TCustomDaemonMapper.Destroy` (182)

### 9.9.5 TCustomDaemonMapper.Destroy

**Synopsis:** Clean up and destroy a `TCustomDaemonMapper` instance.

**Declaration:** `destructor Destroy; Override`

**Visibility:** `public`

**Description:** `Destroy` frees the `DaemonDefs` (183) collection and calls the inherited destructor.

**See also:** `TDaemonDefs` (196), `TCustomDaemonMapper.Create` (182)



### 9.9.6 TCustomDaemonMapper.DaemonDefs

Synopsis: Collection of daemons

Declaration: `Property DaemonDefs : TDaemonDefs`

Visibility: published

Access: Read,Write

Description: `DaemonDefs` is the application's global collection of daemon definitions. This collection will be used to decide at runtime which `TDaemon` class must be created to run or install a daemon.

See also: `TCustomDaemonApplication` ([178](#))

### 9.9.7 TCustomDaemonMapper.OnCreate

Synopsis: Event called when the daemon mapper is created

Declaration: `Property OnCreate : TNotifyEvent`

Visibility: published

Access: Read,Write

Description: `OnCreate` is an event that is called when the `TCustomDaemonMapper` instance is created. It can for instance be used to dynamically create daemon definitions at runtime.

See also: `TCustomDaemonMapper.OnDestroy` ([183](#)), `TCustomDaemonMapper.OnUnInstall` ([184](#)), `TCustomDaemonMapper.OnCreate` ([183](#)), `TCustomDaemonMapper.OnDestroy` ([183](#))

### 9.9.8 TCustomDaemonMapper.OnDestroy

Synopsis: Event called when the daemon mapper is freed.

Declaration: `Property OnDestroy : TNotifyEvent`

Visibility: published

Access: Read,Write

Description: `OnDestroy` is called when the global daemon mapper instance is destroyed. it can be used to release up any resources that were allocated when the instance was created, in the `OnCreate` ([183](#)) event.

See also: `TCustomDaemonMapper.OnCreate` ([183](#)), `TCustomDaemonMapper.OnInstall` ([184](#)), `TCustomDaemonMapper.OnUnInstall` ([184](#)), `TCustomDaemonMapper.OnCreate` ([183](#))

### 9.9.9 TCustomDaemonMapper.OnRun

Synopsis: Event called when the daemons are executed.

Declaration: `Property OnRun : TNotifyEvent`

Visibility: published

Access: Read,Write

Description: `OnRun` is the event called when the daemon application is executed to run the daemons (with command-line parameter '-r'). it is called exactly once.

See also: [TCustomDaemonMapper.OnInstall \(184\)](#), [TCustomDaemonMapper.OnUnInstall \(184\)](#), [TCustomDaemonMapper.OnCreate \(183\)](#), [TCustomDaemonMapper.OnDestroy \(183\)](#)

### 9.9.10 TCustomDaemonMapper.OnInstall

Synopsis: Event called when the daemons are installed

Declaration: `Property OnInstall : TNotifyEvent`

Visibility: published

Access: Read,Write

Description: `OnInstall` is the event called when the daemon application is executed to install the daemons (with command-line parameter `'-i'` or `'/install'`). it is called exactly once.

See also: [TCustomDaemonMapper.OnRun \(183\)](#), [TCustomDaemonMapper.OnUnInstall \(184\)](#), [TCustomDaemonMapper.OnCreate \(183\)](#), [TCustomDaemonMapper.OnDestroy \(183\)](#)

### 9.9.11 TCustomDaemonMapper.OnUnInstall

Synopsis: Event called when the daemons are uninstalled

Declaration: `Property OnUnInstall : TNotifyEvent`

Visibility: published

Access: Read,Write

Description: `OnUnInstall` is the event called when the daemon application is executed to uninstall the daemons (with command-line parameter `'-u'` or `'/uninstall'`). it is called exactly once.

See also: [TCustomDaemonMapper.OnRun \(183\)](#), [TCustomDaemonMapper.OnInstall \(184\)](#), [TCustomDaemonMapper.OnCreate \(183\)](#), [TCustomDaemonMapper.OnDestroy \(183\)](#)

## 9.10 TDaemon

### 9.10.1 Description

`TDaemon` is a [TCustomDaemon \(175\)](#) descendent which is meant for development in a visual environment: it contains event handlers for all major operations. Whenever a `TCustomDaemon` method is executed, it's execution is shunted to the event handler, which can be filled with code in the IDE.

All the events of the daemon are executed in the thread in which the daemon's controller is running (as given by [DaemonThread \(177\)](#)), which is not the main program thread.

### 9.10.2 Property overview

Page	Property	Access	Description
<a href="#">188</a>	AfterInstall	rw	Called after the daemon was installed
<a href="#">188</a>	AfterUnInstall	rw	Called after the daemon is uninstalled
<a href="#">187</a>	BeforeInstall	rw	Called before the daemon will be installed
<a href="#">188</a>	BeforeUnInstall	rw	Called before the daemon is uninstalled
<a href="#">185</a>	Definition		
<a href="#">186</a>	OnContinue	rw	Daemon continue
<a href="#">188</a>	OnControlCode	rw	Called when a control code is received for the daemon
<a href="#">187</a>	OnExecute	rw	Daemon execute event
<a href="#">186</a>	OnPause	rw	Daemon pause event
<a href="#">187</a>	OnShutDown	rw	Daemon shutdown
<a href="#">185</a>	OnStart	rw	Daemon start event
<a href="#">186</a>	OnStop	rw	Daemon stop event
<a href="#">185</a>	Status		

### 9.10.3 TDaemon.Definition

Declaration: `Property Definition :`

Visibility: public

Access:

### 9.10.4 TDaemon.Status

Declaration: `Property Status :`

Visibility: public

Access:

### 9.10.5 TDaemon.OnStart

Synopsis: Daemon start event

Declaration: `Property OnStart : TDaemonOKEvent`

Visibility: published

Access: Read,Write

Description: `OnStart` is the event called when the daemon must be started. This event handler should return as quickly as possible. If it must perform lengthy operations, it is best to report the status to the operating system at regular intervals using the `ReportStatus` ([176](#)) method.

If the start of the daemon should do some continuous action, then this action should be performed in a new thread: this thread should then be created and started in the `OnExecute` ([187](#)) event handler, so the event handler can return at once.

See also: `TDaemon.OnStop` ([186](#)), `TDaemon.OnExecute` ([187](#)), `TDaemon.OnContinue` ([186](#)), `TCustomDaemon.ReportStatus` ([176](#))

### 9.10.6 TDaemon.OnStop

Synopsis: Daemon stop event

Declaration: `Property OnStop : TDaemonOKEvent`

Visibility: published

Access: Read,Write

Description: `OnStart` is the event called when the daemon must be stopped. This event handler should return as quickly as possible. If it must perform lengthy operations, it is best to report the status to the operating system at regular intervals using the `ReportStatus` (176) method.

If a thread was started in the `OnExecute` (187) event, this is the place where the thread should be stopped.

See also: `TDaemon.OnStart` (185), `TDaemon.OnPause` (186), `TCustomDaemon.ReportStatus` (176)

### 9.10.7 TDaemon.OnPause

Synopsis: Daemon pause event

Declaration: `Property OnPause : TDaemonOKEvent`

Visibility: published

Access: Read,Write

Description: `OnPause` is the event called when the daemon must be stopped. This event handler should return as quickly as possible. If it must perform lengthy operations, it is best to report the status to the operating system at regular intervals using the `ReportStatus` (176) method.

If a thread was started in the `OnExecute` (187) event, this is the place where the thread's execution should be suspended.

See also: `TDaemon.OnStop` (186), `TDaemon.OnContinue` (186), `TCustomDaemon.ReportStatus` (176)

### 9.10.8 TDaemon.OnContinue

Synopsis: Daemon continue

Declaration: `Property OnContinue : TDaemonOKEvent`

Visibility: published

Access: Read,Write

Description: `OnPause` is the event called when the daemon must be stopped. This event handler should return as quickly as possible. If it must perform lengthy operations, it is best to report the status to the operating system at regular intervals using the `ReportStatus` (176) method.

If a thread was started in the `OnExecute` (187) event and it was suspended in a `OnPause` (185) event, this is the place where the thread's executed should be resumed.

See also: `TDaemon.OnStart` (185), `TDaemon.OnPause` (186), `TCustomDaemon.ReportStatus` (176)

### 9.10.9 TDaemon.OnShutDown

Synopsis: Daemon shutdown

Declaration: `Property OnShutDown : TDaemonEvent`

Visibility: published

Access: Read,Write

Description: `OnShutDown` is the event called when the daemon must be shut down. When the system is being shut down and the daemon does not respond to stop signals, then a shutdown message is sent to the daemon. This event can be used to respond to such a message. The daemon process will simply be stopped after this event.

If a thread was started in the `OnExecute` (187), this is the place where the thread's executed should be stopped or the thread freed from memory.

See also: `TDaemon.OnStart` (185), `TDaemon.OnPause` (186), `TCustomDaemon.ReportStatus` (176)

### 9.10.10 TDaemon.OnExecute

Synopsis: Daemon execute event

Declaration: `Property OnExecute : TDaemonEvent`

Visibility: published

Access: Read,Write

Description: `OnExecute` is executed once after the daemon was started. If assigned, it should perform whatever operation the daemon is designed.

If the daemon's action is event based, then no `OnExecute` handler is needed, and the events will control the daemon's execution: the daemon thread will then go in a loop, passing control messages to the daemon.

If an `OnExecute` event handler is present, the checking for control messages must be done by the implementation of the `OnExecute` handler.

See also: `TDaemon.OnStart` (185), `TDaemon.OnStop` (186)

### 9.10.11 TDaemon.BeforeInstall

Synopsis: Called before the daemon will be installed

Declaration: `Property BeforeInstall : TDaemonEvent`

Visibility: published

Access: Read,Write

Description: `BeforeInstall` is called before the daemon is installed. It can be done to specify extra dependencies, or change the daemon description etc.

See also: `TDaemon.AfterInstall` (188), `TDaemon.BeforeUnInstall` (188), `TDaemon.AfterUnInstall` (188)

### 9.10.12 TDaemon.AfterInstall

Synopsis: Called after the daemon was installed

Declaration: `Property AfterInstall : TDaemonEvent`

Visibility: published

Access: Read,Write

Description: `AfterInstall` is called after the daemon was successfully installed.

See also: `TDaemon.BeforeInstall` ([187](#)), `TDaemon.BeforeUnInstall` ([188](#)), `TDaemon.AfterUnInstall` ([188](#))

### 9.10.13 TDaemon.BeforeUnInstall

Synopsis: Called before the daemon is uninstalled

Declaration: `Property BeforeUnInstall : TDaemonEvent`

Visibility: published

Access: Read,Write

Description: `BeforeUnInstall` is called before the daemon is uninstalled.

See also: `TDaemon.BeforeInstall` ([187](#)), `TDaemon.AfterInstall` ([188](#)), `TDaemon.AfterUnInstall` ([188](#))

### 9.10.14 TDaemon.AfterUnInstall

Synopsis: Called after the daemon is uninstalled

Declaration: `Property AfterUnInstall : TDaemonEvent`

Visibility: published

Access: Read,Write

Description: `AfterUnInstall` is called after the daemon is successfully uninstalled.

See also: `TDaemon.BeforeInstall` ([187](#)), `TDaemon.AfterInstall` ([188](#)), `TDaemon.BeforeUnInstall` ([188](#))

### 9.10.15 TDaemon.OnControlCode

Synopsis: Called when a control code is received for the daemon

Declaration: `Property OnControlCode : TCustomControlCodeEvent`

Visibility: published

Access: Read,Write

Description: `OnControlCode` is called when the daemon receives a control code. If the daemon has not handled the control code, it should set the `Handled` parameter to `False`. By default it is set to `True`.

See also: `daemonapp.architecture` ([169](#))

## 9.11 TDaemonApplication

### 9.11.1 Description

`TDaemonApplication` is the default `TCustomDaemonApplication` (178) descendent that is used to run the daemon application. It is possible to register an alternative `TCustomDaemonApplication` class (using `RegisterDaemonApplicationClass` (174)) to run the application in a different manner.

## 9.12 TDaemonController

### 9.12.1 Description

`TDaemonController` is a class that is used by the `TDaemonApplication` (189) class to control the daemon during runtime. The `TDaemonApplication` class instantiates an instance of `TDaemonController` for each daemon in the application and communicates with the daemon through the `TDaemonController` instance. It should rarely be necessary to access or use this class.

### 9.12.2 Method overview

Page	Property	Description
<a href="#">190</a>	Controller	Controller
<a href="#">189</a>	Create	Create a new instance of the <code>TDaemonController</code> class
<a href="#">190</a>	Destroy	Free a <code>TDaemonController</code> instance.
<a href="#">190</a>	Main	Daemon main entry point
<a href="#">191</a>	ReportStatus	Report the status to the operating system.
<a href="#">190</a>	StartService	Start the service

### 9.12.3 Property overview

Page	Property	Access	Description
<a href="#">192</a>	CheckPoint		Send checkpoint signal to the operating system
<a href="#">191</a>	Daemon	r	Daemon instance this controller controls.
<a href="#">191</a>	LastStatus	r	Last reported status
<a href="#">191</a>	Params	r	Parameters passed to the daemon

### 9.12.4 TDaemonController.Create

**Synopsis:** Create a new instance of the `TDaemonController` class

**Declaration:** `constructor Create(AOwner: TComponent); Override`

**Visibility:** `public`

**Description:** `Create` creates a new instance of the `TDaemonController` class. It should never be necessary to create a new instance manually, because the controllers are created by the global `TDaemonApplication` (189) instance, and `AOwner` will be set to the global `TDaemonApplication` (189) instance.

**See also:** `TDaemonApplication` (189), `TDaemonController.Destroy` (190)

### 9.12.5 TDaemonController.Destroy

Synopsis: Free a `TDaemonController` instance.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` deallocates some resources allocated when the instance was created.

See also: `TDaemonController.Create` ([189](#))

### 9.12.6 TDaemonController.StartService

Synopsis: Start the service

Declaration: `procedure StartService; Virtual`

Visibility: `public`

Description: `StartService` starts the service controlled by this instance.

Errors: None.

See also: `TDaemonController.Main` ([190](#))

### 9.12.7 TDaemonController.Main

Synopsis: Daemon main entry point

Declaration: `procedure Main(Argc: DWord; Args: PPChar); Virtual`

Visibility: `public`

Description: `Main` is the service's main entry point, called when the system wants to start the service. The global application will call this function whenever required, with the appropriate arguments.

The standard implementation starts the daemon thread, and waits for it to stop. All other daemon action - such as responding to control code events - is handled by the thread.

Errors: If the daemon thread cannot be created, an exception is raised.

See also: `TDaemonThread` ([198](#))

### 9.12.8 TDaemonController.Controller

Synopsis: Controller

Declaration: `procedure Controller(ControlCode: DWord; EventType: DWord;  
EventData: Pointer); Virtual`

Visibility: `public`

Description: `Controller` is responsible for sending the control code to the daemon thread so it can be processed.

This routine is currently only used on windows, as there is no service manager on linux. Later on this may be changed to respond to signals on linux as well.

See also: `TDaemon.OnControlCode` ([188](#))



### 9.12.9 TDaemonController.ReportStatus

Synopsis: Report the status to the operating system.

Declaration: `function ReportStatus : Boolean; Virtual`

Visibility: `public`

Description: `ReportStatus` reports the status of the daemon to the operating system. On windows, this sends the current service status to the service manager. On other operating systems, this sends a message to the system log.

Errors: If an error occurs, an error message is sent to the system log.

See also: `TDaemon.ReportStatus` ([184](#)), `TDaemonController.LastStatus` ([191](#))

### 9.12.10 TDaemonController.Daemon

Synopsis: Daemon instance this controller controls.

Declaration: `Property Daemon : TCustomDaemon`

Visibility: `public`

Access: `Read`

Description: `Daemon` is the daemon instance that is controller by this instance of the `TDaemonController` class.

### 9.12.11 TDaemonController.Params

Synopsis: Parameters passed to the daemon

Declaration: `Property Params : TStrings`

Visibility: `public`

Access: `Read`

Description: `Params` contains the parameters passed to the daemon application by the operating system, comparable to the application's command-line parameters. The property is set by the `Main` ([190](#)) method.

### 9.12.12 TDaemonController.LastStatus

Synopsis: Last reported status

Declaration: `Property LastStatus : TCurrentStatus`

Visibility: `public`

Access: `Read`

Description: `LastStatus` is the last status reported to the operating system.

See also: `TDaemonController.ReportStatus` ([191](#))

### 9.12.13 TDaemonController.CheckPoint

Synopsis: Send checkpoint signal to the operating system

Declaration: `Property CheckPoint : DWord`

Visibility: public

Access:

Description: `CheckPoint` can be used to send a checkpoint signal during lengthy operations, to signal that a lengthy operation is in progress. This should be used mainly on windows, to signal the service manager that the service is alive.

See also: `TDaemonController.ReportStatus` ([191](#))

## 9.13 TDaemonDef

### 9.13.1 Description

`TDaemonDef` contains the definition of a daemon in the application: The name of the daemon, which `TCustomDaemon` ([175](#)) descendent should be started to run the daemon, a description, and various other options should be set in this class. The global `TDaemonApplication` instance maintains a collection of `TDaemonDef` instances and will use these definitions to install or start the various daemons.

### 9.13.2 Method overview

Page	Property	Description
<a href="#">192</a>	Create	Create a new <code>TDaemonDef</code> instance
<a href="#">193</a>	Destroy	Free a <code>TDaemonDef</code> from memory

### 9.13.3 Property overview

Page	Property	Access	Description
<a href="#">193</a>	<code>DaemonClass</code>	r	<code>TDaemon</code> class to use for this daemon
<a href="#">193</a>	<code>DaemonClassName</code>	rw	Name of the <code>TDaemon</code> class to use for this daemon
<a href="#">194</a>	<code>Description</code>	rw	Description of the daemon
<a href="#">194</a>	<code>DisplayName</code>	rw	Displayed name of the daemon (service)
<a href="#">195</a>	<code>Enabled</code>	rw	Is the daemon enabled or not
<a href="#">193</a>	<code>Instance</code>	rw	Instance of the daemon class
<a href="#">196</a>	<code>LogStatusReport</code>	rw	Log the status report to the system log
<a href="#">194</a>	<code>Name</code>	rw	Name of the daemon (service)
<a href="#">195</a>	<code>OnCreateInstance</code>	rw	Event called when a daemon is instantiated
<a href="#">195</a>	<code>Options</code>	rw	Service options
<a href="#">194</a>	<code>RunArguments</code>	rw	Additional command-line arguments when running daemon.
<a href="#">195</a>	<code>WinBindings</code>	rw	Windows-specific bindings (windows only)

### 9.13.4 TDaemonDef.Create

Synopsis: Create a new `TDaemonDef` instance

Declaration: `constructor Create(ACollection: TCollection); Override`

Visibility: public

Description: `Create` initializes a new `TDaemonDef` instance. It should not be necessary to instantiate a definition manually, it is handled by the collection.

See also: `TDaemonDefs` ([196](#))

### 9.13.5 `TDaemonDef.Destroy`

Synopsis: Free a `TDaemonDef` from memory

Declaration: `destructor Destroy; Override`

Visibility: public

Description: `Destroy` removes the `TDaemonDef` from memory.

### 9.13.6 `TDaemonDef.DaemonClass`

Synopsis: `TDaemon` class to use for this daemon

Declaration: `Property DaemonClass : TCustomDaemonClass`

Visibility: public

Access: Read

Description: `DaemonClass` is the `TDaemon` class that is used when this service is requested. It is looked up in the application's global daemon mapper by its name in `DaemonClassName` ([193](#)).

See also: `TDaemonDef.DaemonClassName` ([193](#)), `TDaemonMapper` ([198](#))

### 9.13.7 `TDaemonDef.Instance`

Synopsis: Instance of the daemon class

Declaration: `Property Instance : TCustomDaemon`

Visibility: public

Access: Read,Write

Description: `Instance` points to the `TDaemon` ([184](#)) instance that is used when the service is in operation at runtime.

See also: `TDaemonDef.DaemonClass` ([193](#))

### 9.13.8 `TDaemonDef.DaemonClassName`

Synopsis: Name of the `TDaemon` class to use for this daemon

Declaration: `Property DaemonClassName : String`

Visibility: published

Access: Read,Write

**Description:** `DaemonClassName` is the name of the `TDaemon` class that will be used whenever the service is needed. The name is used to look up the class pointer registered in the daemon mapper, when `TCustomDaemonApplication.CreateDaemonInstance` (178) creates an instance of the daemon.

See also: `TDaemonDef.Instance` (193), `TDaemonDef.DaemonClass` (193), `RegisterDaemonClass` (175)

### 9.13.9 TDaemonDef.Name

**Synopsis:** Name of the daemon (service)

**Declaration:** `Property Name : String`

**Visibility:** published

**Access:** Read,Write

**Description:** `Name` is the internal name of the daemon as it is known to the operating system.

See also: `TDaemonDef.DisplayName` (194)

### 9.13.10 TDaemonDef.Description

**Synopsis:** Description of the daemon

**Declaration:** `Property Description : String`

**Visibility:** published

**Access:** Read,Write

**Description:** `Description` is the description shown in the Windows service manager when managing this service. It is supplied to the windows service manager when the daemon is installed.

### 9.13.11 TDaemonDef.DisplayName

**Synopsis:** Displayed name of the daemon (service)

**Declaration:** `Property DisplayName : String`

**Visibility:** published

**Access:** Read,Write

**Description:** `DisplayName` is the displayed name of the daemon as it is known to the operating system.

See also: `TDaemonDef.Name` (194)

### 9.13.12 TDaemonDef.RunArguments

**Synopsis:** Additional command-line arguments when running daemon.

**Declaration:** `Property RunArguments : String`

**Visibility:** published

**Access:** Read,Write

**Description:** `RunArguments` specifies any additional command-line arguments that should be specified when running the daemon: these arguments will be passed to the service manager when registering the service on windows.

### 9.13.13 TDaemonDef.Options

Synopsis: Service options

Declaration: `Property Options : TDaemonOptions`

Visibility: published

Access: Read,Write

Description: `Options` tells the operating system which operations can be performed on the daemon while it is running.

This option is only used during the installation of the daemon.

### 9.13.14 TDaemonDef.Enabled

Synopsis: Is the daemon enabled or not

Declaration: `Property Enabled : Boolean`

Visibility: published

Access: Read,Write

Description: `Enabled` specifies whether a daemon should be installed, run or uninstalled. Disabled daemons are not installed, run or uninstalled.

### 9.13.15 TDaemonDef.WinBindings

Synopsis: Windows-specific bindings (windows only)

Declaration: `Property WinBindings : TWinBindings`

Visibility: published

Access: Read,Write

Description: `WinBindings` is used to group together the windows-specific properties of the daemon. This property is totally ignored on other platforms.

See also: `TWinBindings` ([203](#))

### 9.13.16 TDaemonDef.OnCreateInstance

Synopsis: Event called when a daemon is instantiated

Declaration: `Property OnCreateInstance : TNotifyEvent`

Visibility: published

Access: Read,Write

Description: `OnCreateInstance` is called whenever an instance of the daemon is created. This can be used for instance when a single `TDaemon` class is used to run several services, to correctly initialize the `TDaemon`.

### 9.13.17 TDaemonDef.LogStatusReport

Synopsis: Log the status report to the system log

Declaration: `Property LogStatusReport : Boolean`

Visibility: published

Access: Read,Write

Description: `LogStatusReport` can be set to `True` to send the status reports also to the system log. This can be used to track the progress of the daemon.

See also: `TDaemon.ReportStatus` ([184](#))

## 9.14 TDaemonDefs

### 9.14.1 Description

`TDaemonDefs` is the class of the global list of daemon definitions. It contains an item for each daemon in the application.

Normally it is not necessary to create an instance of `TDaemonDefs` manually. The global `TCustomDaemonMapper` ([182](#)) instance will create a collection and maintain it.

### 9.14.2 Method overview

Page	Property	Description
<a href="#">196</a>	<code>Create</code>	Create a new instance of a <code>TDaemonDefs</code> collection.
<a href="#">197</a>	<code>DaemonDefByName</code>	Find and return instance of daemon definition with given name.
<a href="#">197</a>	<code>FindDaemonDef</code>	Find and return instance of daemon definition with given name.
<a href="#">197</a>	<code>IndexOfDaemonDef</code>	Return index of daemon definition

### 9.14.3 Property overview

Page	Property	Access	Description
<a href="#">197</a>	<code>Daemons</code>	rw	Indexed access to <code>TDaemonDef</code> instances

### 9.14.4 TDaemonDefs.Create

Synopsis: Create a new instance of a `TDaemonDefs` collection.

Declaration: `constructor Create(AOwner: TPersistent; AClass: TCollectionItemClass)`

Visibility: public

Description: `Create` creates a new instance of the `TDaemonDefs` collection. It keeps the `AOwner` parameter for future reference and calls the inherited constructor.

Normally it is not necessary to create an instance of `TDaemonDefs` manually. The global `TCustomDaemonMapper` ([182](#)) instance will create a collection and maintain it.

See also: `TDaemonDef` ([192](#))

### 9.14.5 TDaemonDefs.IndexOfDaemonDef

Synopsis: Return index of daemon definition

Declaration: `function IndexOfDaemonDef(const DaemonName: String) : Integer`

Visibility: public

Description: `IndexOfDaemonDef` searches the collection for a `TDaemonDef` (192) instance with a name equal to `DaemonName`, and returns it's index. It returns -1 if no definition was found with this name. The search is case insensitive.

See also: `TDaemonDefs.FindDaemonDef` (197), `TDaemonDefs.DaemonDefByName` (197)

### 9.14.6 TDaemonDefs.FindDaemonDef

Synopsis: Find and return instance of daemon definition with given name.

Declaration: `function FindDaemonDef(const DaemonName: String) : TDaemonDef`

Visibility: public

Description: `FindDaemonDef` searches the list of daemon definitions and returns the `TDaemonDef` (192) instance whose name matches `DaemonName`. If no definition is found, `Nil` is returned.

See also: `TDaemonDefs.IndexOfDaemonDef` (197), `TDaemonDefs.DaemonDefByName` (197)

### 9.14.7 TDaemonDefs.DaemonDefByName

Synopsis: Find and return instance of daemon definition with given name.

Declaration: `function DaemonDefByName(const DaemonName: String) : TDaemonDef`

Visibility: public

Description: `FindDaemonDef` searches the list of daemon definitions and returns the `TDaemonDef` (192) instance whose name matches `DaemonName`. If no definition is found, an `EDaemon` (175) exception is raised.

The `FindDaemonDef` (197) call does not raise an error, but returns `Nil` instead.

Errors: If no definition is found, an `EDaemon` (175) exception is raised.

See also: `TDaemonDefs.IndexOfDaemonDef` (197), `TDaemonDefs.FindDaemonDef` (197)

### 9.14.8 TDaemonDefs.Daemons

Synopsis: Indexed access to `TDaemonDef` instances

Declaration: `Property Daemons[Index: Integer]: TDaemonDef; default`

Visibility: public

Access: Read,Write

Description: `Daemons` is the default property of `TDaemonDefs`, it gives access to the `TDaemonDef` instances in the collection.

See also: `TDaemonDef` (192)

## 9.15 TDaemonMapper

### 9.15.1 Description

`TDaemonMapper` is a direct descendent of `TCustomDaemonMapper` (182), but introduces no new functionality. It's sole purpose is to make it possible for an IDE to stream the `TDaemonMapper` instance.

For this purpose, it overrides the `Create` constructor and tries to find a resource with the same name as the class name, and tries to stream the instance from this resource.

If the instance should not be streamed, the `CreateNew` (198) constructor can be used instead.

### 9.15.2 Method overview

Page	Property	Description
<a href="#">198</a>	<code>Create</code>	Create a new <code>TDaemonMapper</code> instance and initializes it from streamed resources.
<a href="#">198</a>	<code>CreateNew</code>	Create a new <code>TDaemonMapper</code> instance without initialization

### 9.15.3 TDaemonMapper.Create

**Synopsis:** Create a new `TDaemonMapper` instance and initializes it from streamed resources.

**Declaration:** `constructor Create(AOwner: TComponent); Override`

**Visibility:** default

**Description:** `Create` initializes a new instance of `TDaemonMapper` and attempts to read the component from resources compiled in the application.

If the instance should not be streamed, the `CreateNew` (198) constructor can be used instead.

**Errors:** If no streaming system is found, or no resource exists for the class, an exception is raised.

**See also:** `TDaemonMapper.CreateNew` (198)

### 9.15.4 TDaemonMapper.CreateNew

**Synopsis:** Create a new `TDaemonMapper` instance without initialization

**Declaration:** `constructor CreateNew(AOwner: TComponent; Dummy: Integer)`

**Visibility:** default

**Description:** `CreateNew` initializes a new instance of `TDaemonMapper`. In difference with the `Create` constructor, it does not attempt to read the component from a stream.

**See also:** `TDaemonMapper.Create` (198)

## 9.16 TDaemonThread

### 9.16.1 Description

`TDaemonThread` is the thread in which the daemons in the application are run. Each daemon is run in it's own thread.

It should not be necessary to create these threads manually, the `TDaemonController` (189) class will take care of this.



### 9.16.2 Method overview

Page	Property	Description
<a href="#">199</a>	CheckControlMessage	Check if a control message has arrived
<a href="#">200</a>	ContinueDaemon	Continue the daemon
<a href="#">199</a>	Create	Create a new thread
<a href="#">199</a>	Execute	Run the daemon
<a href="#">201</a>	InterrogateDaemon	Report the daemon status
<a href="#">200</a>	PauseDaemon	Pause the daemon
<a href="#">200</a>	ShutDownDaemon	Shut down daemon
<a href="#">200</a>	StopDaemon	Stops the daemon

### 9.16.3 Property overview

Page	Property	Access	Description
<a href="#">201</a>	Daemon	r	Daemon instance

### 9.16.4 TDaemonThread.Create

Synopsis: Create a new thread

Declaration: `constructor Create (ADaemon: TCustomDaemon)`

Visibility: `public`

Description: `Create` creates a new thread instance. It initializes the `Daemon` property with the passed `ADaemon`. The thread is created suspended.

See also: `TDaemonThread.Daemon` ([201](#))

### 9.16.5 TDaemonThread.Execute

Synopsis: Run the daemon

Declaration: `procedure Execute; Override`

Visibility: `public`

Description: `Execute` starts executing the daemon and waits till the daemon stops. It also listens for control codes for the daemon.

See also: `TDaemon.Execute` ([184](#))

### 9.16.6 TDaemonThread.CheckControlMessage

Synopsis: Check if a control message has arrived

Declaration: `procedure CheckControlMessage (WaitForMessage: Boolean)`

Visibility: `public`

Description: `CheckControlMessage` checks if a control message has arrived for the daemon and executes the appropriate daemon message. If the parameter `WaitForMessage` is `True`, then the routine waits for the message to arrive. If it is `False` and no message is present, it returns at once.

### 9.16.7 TDaemonThread.StopDaemon

Synopsis: Stops the daemon

Declaration: `function StopDaemon : Boolean; Virtual`

Visibility: `public`

Description: `StopDaemon` attempts to stop the daemon using its `TDaemon.Stop` (184) method, and terminates the thread.

See also: `TDaemon.Stop` (184), `TDaemonThread.PauseDaemon` (200), `TDaemonThread.ShutDownDaemon` (200)

### 9.16.8 TDaemonThread.PauseDaemon

Synopsis: Pause the daemon

Declaration: `function PauseDaemon : Boolean; Virtual`

Visibility: `public`

Description: `PauseDaemon` attempts to stop the daemon using its `TDaemon.Pause` (184) method, and suspends the thread. It returns `True` if the attempt was successful.

See also: `TDaemon.Pause` (184), `TDaemonThread.StopDaemon` (200), `TDaemonThread.ContinueDaemon` (200), `TDaemonThread.ShutDownDaemon` (200)

### 9.16.9 TDaemonThread.ContinueDaemon

Synopsis: Continue the daemon

Declaration: `function ContinueDaemon : Boolean; Virtual`

Visibility: `public`

Description: `ContinueDaemon` attempts to stop the daemon using its `TDaemon.Continue` (184) method. It returns `True` if the attempt was successful.

See also: `TDaemon.Continue` (184), `TDaemonThread.StopDaemon` (200), `TDaemonThread.PauseDaemon` (200), `TDaemonThread.ShutDownDaemon` (200)

### 9.16.10 TDaemonThread.ShutDownDaemon

Synopsis: Shut down daemon

Declaration: `function ShutDownDaemon : Boolean; Virtual`

Visibility: `public`

Description: `ShutDownDaemon` shuts down the daemon. This happens normally only when the system is shut down and the daemon didn't respond to the stop request. The return result is the result of the `TDaemon.Shutdown` (184) function. The thread is terminated by this method.

See also: `TDaemon.Shutdown` (184), `TDaemonThread.StopDaemon` (200), `TDaemonThread.PauseDaemon` (200), `TDaemonThread.ContinueDaemon` (200)

### 9.16.11 TDaemonThread.InterrogateDaemon

Synopsis: Report the daemon status

Declaration: `function InterrogateDaemon : Boolean; Virtual`

Visibility: `public`

Description: `InterrogateDaemon` simply calls `TDaemon.ReportStatus` (184) for the daemon that is running in this thread. It always returns `True`.

See also: `TDaemon.ReportStatus` (184)

### 9.16.12 TDaemonThread.Daemon

Synopsis: Daemon instance

Declaration: `Property Daemon : TCustomDaemon`

Visibility: `public`

Access: `Read`

Description: `Daemon` is the daemon instance which is running in this thread.

See also: `TDaemon` (184)

## 9.17 TDependencies

### 9.17.1 Description

`TDependencies` is just a descendent of `TCollection` which contains a series of dependencies on other services. It overrides the default property of `TCollection` to return `TDependency` (202) instances.

### 9.17.2 Method overview

Page	Property	Description
<a href="#">201</a>	<code>Create</code>	Create a new instance of a <code>TDependencies</code> collection.

### 9.17.3 Property overview

Page	Property	Access	Description
<a href="#">202</a>	<code>Items</code>	<code>rw</code>	Default property override

### 9.17.4 TDependencies.Create

Synopsis: Create a new instance of a `TDependencies` collection.

Declaration: `constructor Create(AOwner: TPersistent)`

Visibility: `public`

Description: `Create` Create a new instance of a `TDependencies` collection.

### 9.17.5 TDependencies.Items

Synopsis: Default property override

Declaration: `Property Items[Index: Integer]: TDependency; default`

Visibility: public

Access: Read,Write

Description: `Items` overrides the default property of `TCollection` so the items are of type `TDependency` (202).

See also: `TDependency` (202)

## 9.18 TDependency

### 9.18.1 Description

`TDependency` is a collection item used to specify dependencies on other daemons (services) in windows. It is used only on windows and when installing the daemon: changing the dependencies of a running daemon has no effect.

### 9.18.2 Method overview

Page	Property	Description
<a href="#">202</a>	Assign	Assign <code>TDependency</code> instance to another

### 9.18.3 Property overview

Page	Property	Access	Description
<a href="#">203</a>	IsGroup	rw	Name refers to a service group
<a href="#">202</a>	Name	rw	Name of the service

### 9.18.4 TDependency.Assign

Synopsis: Assign `TDependency` instance to another

Declaration: `procedure Assign(Source: TPersistent); Override`

Visibility: public

Description: `Assign` is overridden by `TDependency` to copy all properties from one instance to another.

### 9.18.5 TDependency.Name

Synopsis: Name of the service

Declaration: `Property Name : String`

Visibility: published

Access: Read,Write

Description: `Name` is the name of a service or service group that the current daemon depends on.

See also: `TDependency.IsGroup` (203)

### 9.18.6 TDependency.IsGroup

Synopsis: Name refers to a service group

Declaration: `Property IsGroup : Boolean`

Visibility: `published`

Access: `Read,Write`

Description: `IsGroup` can be set to `True` to indicate that `Name` refers to the name of a service group.

See also: `TDependency.Name` ([202](#))

## 9.19 TWinBindings

### 9.19.1 Description

`TWinBindings` contains windows-specific properties for the daemon definition (in `TDaemonDef.WinBindings` ([195](#))). If the daemon should not run on Windows, then the properties can be ignored.

### 9.19.2 Method overview

Page	Property	Description
<a href="#">204</a>	<code>Assign</code>	Copies all properties
<a href="#">203</a>	<code>Create</code>	Create a new <code>TWinBindings</code> instance
<a href="#">204</a>	<code>Destroy</code>	Remove a <code>TWinBindings</code> instance from memory

### 9.19.3 Property overview

Page	Property	Access	Description
<a href="#">205</a>	<code>Dependencies</code>	<code>rw</code>	Service dependencies
<a href="#">204</a>	<code>ErrCode</code>	<code>rw</code>	Service specific error code
<a href="#">207</a>	<code>ErrorSeverity</code>	<code>rw</code>	Error severity in case of startup failure
<a href="#">205</a>	<code>GroupName</code>	<code>rw</code>	Service group name
<a href="#">206</a>	<code>IDTag</code>	<code>rw</code>	Location in the service group
<a href="#">205</a>	<code>Password</code>	<code>rw</code>	Password for service startup
<a href="#">207</a>	<code>ServiceType</code>	<code>rw</code>	Type of service
<a href="#">206</a>	<code>StartType</code>	<code>rw</code>	Service startup type.
<a href="#">205</a>	<code>UserName</code>	<code>rw</code>	Username to run service as
<a href="#">206</a>	<code>WaitHint</code>	<code>rw</code>	Timeout wait hint
<a href="#">204</a>	<code>Win32ErrCode</code>	<code>rw</code>	General windows error code

### 9.19.4 TWinBindings.Create

Synopsis: Create a new `TWinBindings` instance

Declaration: `constructor Create`

Visibility: `public`

Description: `Create` initializes various properties such as the dependencies.

See also: `TDaemonDef` ([192](#)), `TDaemonDef.WinBindings` ([195](#)), `TWinBindings.Dependencies` ([205](#))

### 9.19.5 TWinBindings.Destroy

Synopsis: Remove a TWinBindings instance from memory

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: Destroy cleans up the TWinBindings instance.

See also: TWinBindings.Dependencies ([205](#)), TWinBindings.Create ([203](#))

### 9.19.6 TWinBindings.Assign

Synopsis: Copies all properties

Declaration: `procedure Assign(Source: TPersistent); Override`

Visibility: `public`

Description: Assign is overridden by TWinBindings so all properties are copied from Source to the TWinBindings instance.

### 9.19.7 TWinBindings.ErrCode

Synopsis: Service specific error code

Declaration: `Property ErrCode : DWord`

Visibility: `public`

Access: Read,Write

Description: ErrCode contains a service specific error code that is reported with TDaemon.ReportStatus ([184](#)) to the windows service manager. If it is zero, then the contents of Win32ErrCode ([204](#)) are reported. If it is nonzero, then the windows-errorcode is set to ERROR\_SERVICE\_SPECIFIC\_ERROR.

See also: TWinBindings.Win32ErrCode ([204](#))

### 9.19.8 TWinBindings.Win32ErrCode

Synopsis: General windows error code

Declaration: `Property Win32ErrCode : DWord`

Visibility: `public`

Access: Read,Write

Description: Win32ErrCode is a general windows service error code that can be reported with TDaemon.ReportStatus ([184](#)) to the windows service manager. It is sent if ErrCode ([204](#)) is zero.

See also: TWinBindings.ErrCode ([204](#))

### 9.19.9 TWinBindings.Dependencies

Synopsis: Service dependencies

Declaration: `Property Dependencies : TDependencies`

Visibility: published

Access: Read,Write

Description: `Dependencies` contains the list of other services (or service groups) that this service depends on. Windows will first attempt to start these services prior to starting this service. If they cannot be started, then the service will not be started either.

This property is only used during installation of the service.

### 9.19.10 TWinBindings.GroupName

Synopsis: Service group name

Declaration: `Property GroupName : String`

Visibility: published

Access: Read,Write

Description: `GroupName` specifies the name of a service group that the service belongs to. If it is empty, then the service does not belong to any group.

This property is only used during installation of the service.

See also: `TDependency.IsGroup` ([203](#))

### 9.19.11 TWinBindings.Password

Synopsis: Password for service startup

Declaration: `Property Password : String`

Visibility: published

Access: Read,Write

Description: `Password` contains the service password: if the service is started with credentials other than one of the system users, then the password for the user must be entered here.

This property is only used during installation of the service.

See also: `TWinBindings.UserName` ([205](#))

### 9.19.12 TWinBindings.UserName

Synopsis: Username to run service as

Declaration: `Property UserName : String`

Visibility: published

Access: Read,Write

**Description:** Username specifies the name of a user whose credentials should be used to run the service. If it is left empty, the service is run as the system user. The password can be set in the Password (205) property.

This property is only used during installation of the service.

See also: TWinBindings.Password (205)

### 9.19.13 TWinBindings.StartType

**Synopsis:** Service startup type.

**Declaration:** Property StartType : TStartType

**Visibility:** published

**Access:** Read,Write

**Description:** StartType specifies when the service should be started during system startup.

This property is only used during installation of the service.

### 9.19.14 TWinBindings.WaitHint

**Synopsis:** Timeout wait hint

**Declaration:** Property WaitHint : Integer

**Visibility:** published

**Access:** Read,Write

**Description:** WaitHint specifies the estimated time for a start/stop/pause or continue operation (in milliseconds). ReportStatus should be called prior to this time to report the next status.

See also: TDaemon.ReportStatus (184)

### 9.19.15 TWinBindings.IDTag

**Synopsis:** Location in the service group

**Declaration:** Property IDTag : DWord

**Visibility:** published

**Access:** Read,Write

**Description:** IDTag contains the location of the service in the service group after installation of the service. It should not be set, it is reported by the service manager.

This property is only used during installation of the service.



### 9.19.16 **TwInBindings.ServiceType**

Synopsis: Type of service

Declaration: `Property ServiceType : TServiceType`

Visibility: published

Access: Read,Write

Description: `ServiceType` specifies what kind of service is being installed.

This property is only used during installation of the service.

### 9.19.17 **TwInBindings.ErrorSeverity**

Synopsis: Error severity in case of startup failure

Declaration: `Property ErrorSeverity : TErrorSeverity`

Visibility: published

Access: Read,Write

Description: `ErrorSeverity` can be used at installation time to tell the windows service manager how to behave when the service fails to start during system startup.

This property is only used during installation of the service.

## Chapter 10

# Reference for unit 'db'

### 10.1 Used units

Table 10.1: Used units by unit 'db'

Name	Page
Classes	??
FmtBCD	<a href="#">208</a>
sysutils	??
Variants	<a href="#">208</a>

### 10.2 Overview

The `db` unit provides the basis for all database access mechanisms. It introduces abstract classes, on which all database access mechanisms are based: `TDataset` ([250](#)) representing a set of records from a database, `TField` ([298](#)) which represents the contents of a field in a record, `TDataSource` ([287](#)) which acts as an event distributor on behalf of a dataset and `TParams` ([368](#)) which can be used to parametrize queries. The databases connections themselves are abstracted in the `TDatabase` ([241](#)) class.

### 10.3 Constants, types and variables

#### 10.3.1 Constants

```
DefaultFieldClasses : Array[TFieldType] of TFieldClass = (Tfield, TStringField, TSmall
```

`DefaultFieldClasses` contains the `TField` ([298](#)) descendent class to use when a `TDataset` instance needs to create fields based on the `TFieldDefs` ([326](#)) field definitions when opening the dataset. The entries can be set to create customized `TField` descendents for certain field datatypes in all datasets.

```
dsEditModes = [dsEdit, dsInsert, dsSetKey]
```

`dsEditModes` contains the various values of `TDataset.State` (276) for which the dataset is in edit mode, i.e. states in which it is possible to set field values for that dataset.

```
dsMaxBufferCount = MAXINT div 8
```

Maximum data buffers count for dataset

```
dsMaxStringSize = 8192
```

Maximum size of string fields

```
dsWriteModes = [dsEdit, dsInsert, dsSetKey, dsCalcFields, dsFilter, dsNewValue, dsInternal
```

`dsWriteModes` contains the various values of `TDataset.State` (276) for which data can be written to the dataset buffer.

```
FieldtypeNameames : Array[TFieldType] of String = ('Unknown', 'String', 'Smallint', 'Integ
```

`FieldTypeNames` contains the names (in english) for the various field data types.

```
FieldTypetoVariantMap : Array[TFieldType] of Integer = (varError, varOleStr, varSmalli
```

`FieldTypetoVariantMap` contains for each field datatype the variant value type that corresponds to it. If a field type cannot be expressed by a variant type, then `varError` is stored in the variant value.

```
SQLDelimiterCharacters = [';', ',', ' ', '(', ')', #13, #10, #9]
```

SQL statement delimiter token characters

```
YesNoChars : Array[Boolean] of Char = ('N', 'Y')
```

Array of characters mapping a boolean to Y/N

### 10.3.2 Types

```
LargeInt = Int64
```

Large (64-bit) integer

```
PBookmarkFlag = ^TBookmarkFlag
```

`PBookmarkFlag` is a convenience type, defined for internal use in `TDataset` (250) or one of its descendents.

```
PBufferList = ^TBufferList
```

`PBufferList` is a pointer to a structure of type `TBufferList` (211). It is an internal type, and should not be used in end-user code.

```
PDateTimeRec = ^TdateTimeRec
```

Pointer to TDateTimeRec record

PLargeInt = ^LargeInt

Pointer to Large (64-bit) integer

PLookupListRec = ^TLookupListRec

Pointer to TLookupListRec record

TBlobData = String

TBlobData should never be used directly in application code.

TBlobStreamMode = (bmRead, bmWrite, bmReadWrite)

Table 10.2: Enumeration values for type TBlobStreamMode

Value	Explanation
bmRead	Read blob data
bmReadWrite	Read and write blob data
bmWrite	Write blob data

TBlobStramMode is used when creating a stream for redaing BLOB data. It indicates what the data will be used for: reading, writing or both.

TBlobType = ftBlob..ftWideMemo

TBlobType is a subrange type, indicating the various datatypes of BLOB fields.

TBookmark = Pointer

TBookMark is the type used by the TDataset.SetBookMark (250) method. It is an opaque type, and should not be used any more, it is superseded by the TBookmarkStr (211) type.

TBookmarkFlag = (bfCurrent, bfBOF, bfEOF, bfInserted)

Table 10.3: Enumeration values for type TBookmarkFlag

Value	Explanation
bfBOF	First record in the dataset.
bfCurrent	Buffer used for the current record
bfEOF	Last record in the dataset
bfInserted	Buffer used for insert

TBookmarkFlag is used internally by TDataset (250) and it's descendent types to mark the internal memory buffers. It should not be used in end-user applications.

`TBookmarkStr = String`

`TBookmarkStr` is the type used by the `TDataset.Bookmark` (271) property. It can be used as a string, but should in fact be considered an opaque type.

`TBufferArray = ^pchar`

`TBufferArray` is an internally used type. It can change in future implementations, and should not be used in application code.

`TBufferList = Array[0..dsMaxBufferCount-1] of PChar`

`TBufferList` is used internally by the `TDataset` (250) class to manage the memory buffers for the data. It should not be necessary to use this type in end-user applications.

`TDataAction = (daFail, daAbort, daRetry)`

Table 10.4: Enumeration values for type `TDataAction`

Value	Explanation
<code>daAbort</code>	The operation should be aborted (edits are undone, and an <code>EAbort</code> exception is raised)
<code>daFail</code>	The operation should fail (an exception will be raised)
<code>daRetry</code>	Retry the operation.

`TDataAction` is used by the `TDataSetErrorEvent` (212) event handler prototype. The parameter `Action` of this event handler is of `TDataAction` type, and should indicate what action must be taken by the dataset.

`TDatabaseClass = Class of TDataBase`

`TDatabaseClass` is the class pointer for the `TDatabase` (241) class.

`TDataChangeEvent = procedure(Sender: TObject; Field: TField) of object`

`TDataChangeEvent` is the event handler prototype for the `TDatasource.OnDataChange` (290) event. The sender parameter is the `TDatasource` instance that triggered the event, and the `Field` parameter is the field whose data has changed. If the dataset has scrolled, then the `Field` parameter is `Nil`.

`TDataEvent = (deFieldChange, deRecordChange, deDataSetChange, deDataSetScroll, deLayoutChange, deUpdateRecord, deUpdateState, deCheckBrowseMode, dePropertyChange, deFieldListChange, deFocusControl, deParentScroll, deConnectChange, deReconcileError, deDisabledStateChange)`

`TDataEvent` describes the various events that can be sent to `TDatasource` (287) instances connected to a `TDataset` (250) instance.

`TDataOperation = procedure of object`

Table 10.5: Enumeration values for type TDataEvent

Value	Explanation
deCheckBrowseMode	The browse mode is being checked
deConnectChange	Unused
deDataSetChange	The dataset property changed
deDataSetScroll	The dataset scrolled to another record
deDisabledStateChange	Unused
deFieldChange	A field value changed
deFieldListChange	Event sent when the list of fields of a dataset changes
deFocusControl	Event sent whenever a control connected to a field should be focused
deLayoutChange	The layout properties of one of the fields changed
deParentScroll	Unused
dePropertyChange	Unused
deReconcileError	Unused
deRecordChange	The current record changed
deUpdateRecord	The record is being updated
deUpdateState	The dataset state is updated

TDataOperation is a prototype handler used internally in TDataSet. It can be changed at any time, so it should not be used in end-user code.

```
TDataSetClass = Class of TDataSet
```

TDataSetClass is the class type for the TDataSet (250) class. It is currently unused in the DB unit and is defined for the benefit of other units.

```
TDataSetErrorEvent = procedure (DataSet: TDataSet; E: EDatabaseError;
                                var DataAction: TDataAction) of object
```

TDataSetErrorEvent is used by the TDataSet.OnEditError (286), TDataSet.OnPostError (287) and TDataSet.OnDeleteError (285) event handlers to allow the programmer to specify what should be done if an update operation fails with an exception: The DataSet parameter indicates what dataset triggered the event, the E parameter contains the exception object. The DataAction must be set by the event handler, and based on its return value, the dataset instance will take appropriate action. The default value is daFail, i.e. the exception will be raised again. For a list of available return values, see TDataAction (211).

```
TDataSetNotifyEvent = procedure (DataSet: TDataSet) of object
```

TDataSetNotifyEvent is used in most of the TDataSet (250) event handlers. It differs from the more general TNotifyEvent (defined in the Classes unit) in that the Sender parameter of the latter is replaced with the DataSet parameter. This avoids typecasts, the available TDataSet methods can be used directly.

```
TDataSetState = (dsInactive, dsBrowse, dsEdit, dsInsert, dsSetKey,
                 dsCalcFields, dsFilter, dsNewValue, dsOldValue, dsCurValue,
                 dsBlockRead, dsInternalCalc, dsOpening)
```

TDataSetState describes the current state of the dataset. During its lifetime, the dataset's state is described by these enumerated values.

Table 10.6: Enumeration values for type TDataSetState

Value	Explanation
dsBlockRead	The dataset is open, but no events are transferred to datasources.
dsBrowse	The dataset is active, and the cursor can be used to navigate the data.
dsCalcFields	The dataset is calculating it's calculated fields.
dsCurValue	The dataset is showing the current values of a record.
dsEdit	The dataset is in editing mode: the current record can be modified.
dsFilter	The dataset is filtering records.
dsInactive	The dataset is not active. No data is available.
dsInsert	The dataset is in insert mode: the current record is a new record which can be edited.
dsInternalCalc	The dataset is calculating it's internally calculated fields.
dsNewValue	The dataset is showing the new values of a record.
dsOldValue	The dataset is showing the old values of a record.
dsOpening	The dataset is currently opening, but is not yet completely open.
dsSetKey	The dataset is calculating the primary key.

Some state are not used in the default TDataset implementation, and are only used by certain descendants.

```
TDateTimeAlias = TDateTime
```

TDateTimeAlias is no longer used.

```
TDateTimeRec = record
end
```

TDateTimeRec was used by older TDataset (250) implementations to store date/time values. Newer implementations use the TDateTime. This type should no longer be used.

```
TDBDatasetClass = Class of TDBDataset
```

TDBDatasetClass is the class pointer for TDBDataset (293)

```
TDBTransactionClass = Class of TDBTransaction
```

TDBTransactionClass is the class pointer for the TDBTransaction (294) class.

```
TFieldAttribute = (faHiddenCol, faReadonly, faRequired, faLink, faUnNamed,
                  faFixed)
```

TFieldAttribute is used to denote some attributes of a field in a database. It is used in the Attributes (325) property of TFieldDef (322).

```
TFieldAttributes= Set of (faFixed, faHiddenCol, faLink, faReadonly,
                        faRequired, faUnNamed)
```

TFieldAttributes is used in the TFieldDef.Attributes (325) property to denote additional attributes of the underlying field.

Table 10.7: Enumeration values for type TFieldAttribute

Value	Explanation
faFixed	Fixed length field
faHiddenCol	Field is a hidden column (used to construct a unique key)
faLink	Field is a link field for other datasets
faReadonly	Field is read-only
faRequired	Field is required
faUnNamed	Field has no original name

TFieldChars = Set of Char

TFieldChars is a type used in the TField.ValidChars (313) property. It's a simple set of characters.

TFieldClass = Class of TField

TFieldGetTextEvent = procedure(Sender: TField; var aText: String;  
DisplayText: Boolean) of object

TFieldGetTextEvent is the prototype for the TField.OnGetText (321) event handler. It should be used when the text of a field requires special formatting. The event handler should return the contents of the field in formatted form in the AText parameter. The DisplayText is True if the text is used for displaying purposes or is False if it will be used for editing purposes.

TFieldKind = (fkData, fkCalculated, fkLookup, fkInternalCalc)

Table 10.8: Enumeration values for type TFieldKind

Value	Explanation
fkCalculated	The field is calculated on the fly.
fkData	Field represents actual data in the underlying data structure.
fkInternalCalc	Field is calculated but stored in an underlying buffer.
fkLookup	The field is a lookup field.

TFieldKind indicates the type of a TField instance. Besides TField instances that represent fields present in the underlying data records, there can also be calculated or lookup fields. To distinguish between these kind of fields, TFieldKind is introduced.

TFieldKinds= Set of (fkCalculated, fkData, fkInternalCalc, fkLookup)

TFieldKinds is a set of TFieldKind (214) values. It is used internally by the classes of the DB unit.

TFieldMap = Array[TFieldType] of Byte

TFieldMap is no longer used.

TFieldNotifyEvent = procedure(Sender: TField) of object



`TFieldNotifyEvent` is a prototype for the event handlers in the `TField` (298) class. Its `Sender` parameter is the field instance that triggered the event.

```
TFieldRef = ^TField
```

Pointer to a `TField` instance

```
TFieldSetTextEvent = procedure(Sender: TField; const aText: String)
                      of object
```

`TFieldSetTextEvent` is the prototype for an event handler used to set the contents of a field based on a user-edited text. It should be used when the text of a field is entered with special formatting. The event handler should set the contents of the field based on the formatted text in the `AText` parameter.

```
TFieldType = (ftUnknown, ftString, ftSmallint, ftInteger, ftWord, ftBoolean,
              ftFloat, ftCurrency, ftBCD, ftDate, ftTime, ftDateTime, ftBytes,
              ftVarBytes, ftAutoInc, ftBlob, ftMemo, ftGraphic, ftFmtMemo,
              ftParadoxOle, ftDBaseOle, ftTypedBinary, ftCursor,
              ftFixedChar, ftWideString, ftLargeint, ftADT, ftArray,
              ftReference, ftDataSet, ftOraBlob, ftOraClob, ftVariant,
              ftInterface, ftIDispatch, ftGuid, ftTimeStamp, ftFMTBcd,
              ftFixedWideChar, ftWideMemo)
```

`TFieldType` indicates the type of a `TField` (298) underlying data, in the `DataType` (310) property.

```
TFilterOption = (foCaseInsensitive, foNoPartialCompare)
```

`TFilterOption` enumerates the various options available when filtering a dataset. The `TFilterOptions` (215) set is used in the `TDataset.FilterOptions` (278) property to indicate which of the options should be used when filtering the data.

```
TFilterOptions= Set of (foCaseInsensitive, foNoPartialCompare)
```

`TFilterOption` is the set of filter options to use when filtering a dataset. This set type is used in the `TDataset.FilterOptions` (278) property. The available values are described in the `TFilterOption` (215) type.

```
TFilterRecordEvent = procedure(DataSet: TDataset; var Accept: Boolean)
                      of object
```

`TFilterRecordEvent` is the prototype for the `TDataset.OnFilterRecord` (286) event handler. The `DataSet` parameter indicates which dataset triggered the event, and the `Accept` parameter must be set to `true` if the current record should be shown, `False` should be used when the record should be hidden.

```
TGetMode = (gmCurrent, gmNext, gmPrior)
```

`TGetMode` is used internally by `TDataset` (250) when it needs to fetch more data for its buffers (using `GetRecord`). It tells the descendent dataset what operation must be performed.

```
TGetResult = (grOK, grBOF, grEOF, grError)
```

TGetResult is used by descendents of TDataset (250) when they have to communicate the result of the GetRecord operation back to the TDataset record.

```
TIndexOption = (ixPrimary, ixUnique, ixDescending, ixCaseInsensitive,
                ixExpression, ixNonMaintained)
```

TIndexOption describes the various properties that an index can have. It is used in the TIndexOptions (216) set type to describe all properties of an index definition as in TIndexDef (338).

```
TIndexOptions= Set of (ixCaseInsensitive, ixDescending, ixExpression,
                       ixNonMaintained, ixPrimary, ixUnique)
```

TIndexOptions contains the set of properties that an index can have. It is used in the TIndexDef.Options (340) property to describe all properties of an index definition as in TIndexDef (338).

```
TIntegerField = TLongintField
```

TIntegerField is an alias for TLongintField (346).

```
TLocateOption = (loCaseInsensitive, loPartialKey)
```

TLocateOption is used in the TDataset.Locate (266) call to enumerate the possible options available when locating a record in the dataset.

```
TLocateOptions= Set of (loCaseInsensitive, loPartialKey)
```

TLocateOptions is used in the TDataset.Locate (266) call: It should contain the actual options to use when locating a record in the dataset.

```
TLoginEvent = procedure(Sender: TObject; Username: String;
                        Password: String) of object
```

TLoginEvent is the prototype for a the the TCustomConnection.OnLogin (240) event handler. It gets passed the TCustomConnection instance that is trying to login, and the initial username and password.

```
TLookupListRec = record
    Key : Variant;
    Value : Variant;
end
```

TLookupListRec is used by lookup fields to store lookup results, if the results should be cached. Its two fields keep the key value and associated lookup value.

```
TParamBinding = Array of Integer
```

TParamBinding is an auxiliary type used when parsing and binding parameters in SQL statements. It should never be used directly in application code.

```
TParamStyle = (psInterbase, psPostgreSQL, psSimulated)
```

`TParamStyle` denotes the style in which parameters are specified in a query. It is used in the `TParams.ParseSQL` (370) method, and can have the following values:

**psInterbase** Parameters are specified by a ? character

**psPostgreSQL** Parameters are specified by a \$N character.

**psSimulated** Parameters are specified by a \$N character.

`TParamType` = (ptUnknown,ptInput,ptOutput,ptInputOutput,ptResult)

`TParamType` indicates the kind of parameter represented by a `TParam` (356) instance. it has one of the following values:

**ptUnknown** Unknown type

**ptInput** Input parameter

**ptOutput** Output paramete, filled on result

**ptInputOutput** Input/output parameter

**ptResult** Result parameter

`TParamTypes`= Set of (ptInput,ptInputOutput,ptOutput,ptResult,ptUnknown)

`TParamTypes` is defined for completeness: a set of `TParamType` (217) values.

`TProviderFlag` = (pfInUpdate,pfInWhere,pfInKey,pfHidden)

`TProviderFlag` describes how the field should be used when applying updates from a dataset to the database. Each field of a `TDataset` (250) has one or more of these flags.

`TProviderFlags`= Set of (pfHidden,pfInKey,pfInUpdate,pfInWhere)

`TProviderFlags` is used for the `TField.ProviderFlags` (319) property to describe the role of the field when applying updates to a database.

`TResolverResponse` = (rrSkip,rrAbort,rrMerge,rrApply,rrIgnore)

`TResolverResponse` is used to indicate what should happen to a pending change that could not be resolved. It is used in callbacks.

`TResyncMode`= Set of (rmExact,rmCenter)

`TResyncMode` is used internally by various `TDataset` (250) navigation and data manipulation methods such as the `TDataset.Refresh` (269) method when they need to reset the cursor position in the dataset's buffer.

`TStringFieldBuffer` = Array[0..dsMaxStringSize] of Char

Type to access string field content buffers as an array of characters

`TUpdateAction` = (uaFail,uaAbort,uaSkip,uaRetry,uaApplied)

`TUpdateAction` indicates what action must be taken in case the applying of updates on the underlying database fails. This type is not used in the `TDataset` (250) class, but is defined on behalf of `TDataset` descendents that implement caching of updates: It indicates what should be done when the (delayed) applying of the updates fails. This event occurs long after the actual post or delete operation.

`TUpdateKind = (ukModify, ukInsert, ukDelete)`

`TUpdateKind` indicates what kind of update operation is in progress when applying updates.

`TUpdateMode = (upWhereAll, upWhereChanged, upWhereKeyOnly)`

`TUpdateMode` determines how the `WHERE` clause of update queries for SQL databases should be constructed.

`TUpdateStatus = (usUnmodified, usModified, usInserted, usDeleted)`

`TUpdateStatus` determines the current state of the record buffer, if updates have not yet been applied to the database.

`TUpdateStatusSet = Set of (usDeleted, usInserted, usModified, usUnmodified)`

`TUpdateStatusSet` is a set of `TUpdateStatus` (218) values.

## 10.4 Procedures and functions

### 10.4.1 BuffersEqual

Synopsis: Check whether 2 memory buffers are equal

Declaration: `function BuffersEqual (Buf1: Pointer; Buf2: Pointer; Size: Integer)  
: Boolean`

Visibility: default

Description: `BuffersEqual` compares the memory areas pointed to by the `Buf1` and `Buf2` pointers and returns `True` if the contents are equal. The memory areas are compared for the first `Size` bytes. If all bytes in the indicated areas are equal, then `True` is returned, otherwise `False` is returned.

Errors: If `Buf1` or `Buf2` do not point to a valid memory area or `Size` is too large, then an exception may occur

See also: `#rtl.system.Comparemem` (??)

### 10.4.2 DatabaseError

Synopsis: Raise an `EDatabaseError` exception.

Declaration: `procedure DatabaseError(const Msg: String); Overload  
procedure DatabaseError(const Msg: String; Comp: TComponent); Overload`

Visibility: default

Description: `DatabaseError` raises an `EDatabaseError` (220) exception, passing it `Msg`. If `Comp` is specified, the name of the component is prepended to the message.

See also: `DatabaseErrorFmt` (219), `EDatabaseError` (220)

### 10.4.3 DatabaseErrorFmt

**Synopsis:** Raise an `EDatabaseError` exception with a formatted message

**Declaration:** `procedure DatabaseErrorFmt(const Fmt: String; Args: Array of const)  
; Overload  
procedure DatabaseErrorFmt(const Fmt: String; Args: Array of const;  
Comp: TComponent); Overload`

**Visibility:** default

**Description:** `DatabaseErrorFmt` raises an `EDatabaseError` (220) exception, passing it a message made by calling `rtl.sysutils.format` (208) with the `fmt` and `Args` arguments. If `Comp` is specified, the name of the component is prepended to the message.

**See also:** `DatabaseError` (218), `EDatabaseError` (220)

### 10.4.4 DateTimeRecToDateTime

**Synopsis:** Convert `TDateTimeRec` record to a `TDateTime` value.

**Declaration:** `function DateTimeRecToDateTime(DT: TFieldType; Data: TDateTimeRec)  
: TDateTime`

**Visibility:** default

**Description:** `DateTimeRecToDateTime` examines `Data` and `Dt` and uses `dt` to convert the timestamp in `Data` to a `TDateTime` value.

**See also:** `TFieldType` (215), `TDateTimeRec` (213), `DateTimeToDateTimeRec` (219)

### 10.4.5 DateTimeToDateTimeRec

**Synopsis:** Convert `TDateTime` value to a `TDateTimeRec` record.

**Declaration:** `function DateTimeToDateTimeRec(DT: TFieldType; Data: TDateTime)  
: TDateTimeRec`

**Visibility:** default

**Description:** `DateTimeToDateTimeRec` examines `Data` and `Dt` and uses `dt` to convert the date/time value in `Data` to a `TDateTimeRec` record.

**Errors:**

**See also:** `TFieldType` (215), `TDateTimeRec` (213), `DateTimeRecToDateTime` (219)

### 10.4.6 DisposeMem

**Synopsis:** Dispose of a heap memory block and `Nil` the pointer (deprecated)

**Declaration:** `procedure DisposeMem(var Buffer; Size: Integer)`

**Visibility:** default

**Description:** `DisposeMem` disposes of the heap memory area pointed to by `Buffer` (`Buffer` must be of type `Pointer`). The `Size` parameter indicates the size of the memory area (it is, in fact, ignored by the heap manager). The pointer `Buffer` is set to `Nil`. If `Buffer` is `Nil`, then nothing happens. Do not use `DisposeMem` on objects, because their destructor will not be called.

**Errors:** If `Buffer` is not pointing to a valid heap memory block, then memory corruption may occur.

See also: `#rtl.system.FreeMem` (??), `#rtl.sysutils.freeandnil` (??)

### 10.4.7 ExtractFieldName

**Synopsis:** Extract the field name at position

**Declaration:** `function ExtractFieldName(const Fields: String; var Pos: Integer) : String`

**Visibility:** default

**Description:** `ExtractFieldName` returns the string starting at position `Pos` till the next semicolon (;) character or the end of the string. On return, `Pos` contains the position of the first character after the semicolon character (or one more than the length of the string).

See also: `TFields.GetFieldList` (329)

### 10.4.8 SkipComments

**Synopsis:** Skip SQL comments

**Declaration:** `function SkipComments(var p: PChar; EscapeSlash: Boolean; EscapeRepeat: Boolean) : Boolean`

**Visibility:** default

**Description:** `SkipComments` examines the null-terminated string in `P` and skips any SQL comment or string literal found at the start. It returns `P` the first non-comment or non-string literal position. The `EscapeSlash` parameter determines whether the backslash character (\) functions as an escape character (i.e. the following character is not considered a delimiter). `EscapeRepeat` must be set to `True` if the quote character is repeated to indicate itself.

The function returns `True` if a comment was found and skipped, `False` otherwise.

**Errors:** No checks are done on the validity of `P`.

See also: `TParams.ParseSQL` (370)

## 10.5 EDatabaseError

### 10.5.1 Description

`EDatabaseError` is the base class from which database-related exception classes should derive. It is raised by the `DatabaseError` (218) call.

## 10.6 EUpdateError

### 10.6.1 Description

`EupdateError` is an exception used by the `TProvider` database support. It should never be raised directly.

### 10.6.2 Method overview

Page	Property	Description
<a href="#">221</a>	Create	Create a new EUpdateError instance
<a href="#">221</a>	Destroy	Free the EupdateError instance

### 10.6.3 Property overview

Page	Property	Access	Description
<a href="#">221</a>	Context	r	Context in which exception occurred.
<a href="#">222</a>	ErrorCode	r	Numerical error code.
<a href="#">222</a>	OriginalException	r	Original exception object, if available.
<a href="#">222</a>	PreviousError	r	Previous error number

### 10.6.4 EUpdateError.Create

Synopsis: Create a new EUpdateError instance

Declaration: `constructor Create (NativeError: String; Context: String; ErrCode: Integer; PrevError: Integer; E: Exception)`

Visibility: public

Description: `Create` instantiates a new `EUpdateError` object and populates the various properties with the `NativeError`, `Context`, `ErrCode` and `PrevError` parameters. The `E` parameter is the actual exception that occurred while the update operation was attempted. The exception object `E` will be freed if the `EUpdateError` instance is freed.

See also: `EDatabaseError` ([220](#))

### 10.6.5 EUpdateError.Destroy

Synopsis: Free the EupdateError instance

Declaration: `destructor Destroy; Override`

Visibility: public

Description: `Destroy` frees the original exception object (if there was one) and then calls the inherited destructor.

Errors: If the original exception object was already freed, an error will occur.

See also: `EUpdateError.OriginalException` ([220](#))

### 10.6.6 EUpdateError.Context

Synopsis: Context in which exception occurred.

Declaration: `Property Context : String`

Visibility: public

Access: Read

Description: A description of the context in which the original exception was raised.

See also: `EUpdateError.OriginalException` ([220](#)), `EUpdateError.ErrorCode` ([222](#)), `EUpdateError.PreviousError` ([222](#))

### 10.6.7 EUpdateError.ErrorCode

Synopsis: Numerical error code.

Declaration: `Property ErrorCode : Integer`

Visibility: `public`

Access: `Read`

Description: `ErrorCode` is a numerical error code, provided by the native data access layer, to describe the error. It may or not be filled.

See also: [EUpdateError.OriginalException \(220\)](#), [EUpdateError.Context \(221\)](#), [EUpdateError.PreviousError \(222\)](#)

### 10.6.8 EUpdateError.OriginalException

Synopsis: Original exception object, if available.

Declaration: `Property OriginalException : Exception`

Visibility: `public`

Access: `Read`

Description: `OriginalException` is the original exception object as raised by the database access layer. It may or may not be available.

See also: [EUpdateError.ErrorCode \(222\)](#), [EUpdateError.Context \(221\)](#), [EUpdateError.PreviousError \(222\)](#)

### 10.6.9 EUpdateError.PreviousError

Synopsis: Previous error number

Declaration: `Property PreviousError : Integer`

Visibility: `public`

Access: `Read`

Description: `PreviousError` is used to order the errors which occurred during an update operation.

See also: [EUpdateError.ErrorCode \(222\)](#), [EUpdateError.Context \(221\)](#), [EUpdateError.OriginalException \(220\)](#)

## 10.7 TAutoIncField

### 10.7.1 Description

`TAutoIncField` is the class created when a dataset must manage 32-bit signed integer data, of datatype `ftAutoInc`: This field gets its data automatically by the database engine. It exposes no new properties, but simply overrides some methods to manage 32-bit signed integer data.

It should never be necessary to create an instance of `TAutoIncField` manually, a field of this class will be instantiated automatically for each auto-incremental field when a dataset is opened.



### 10.7.2 Method overview

Page	Property	Description
<a href="#">223</a>	Create	Create a new instance of the <code>TAutoIncField</code> class.

### 10.7.3 TAutoIncField.Create

**Synopsis:** Create a new instance of the `TAutoIncField` class.

**Declaration:** `constructor Create(AOwner: TComponent); Override`

**Visibility:** `public`

**Description:** `Create` initializes a new instance of the `TAutoIncField` class. It simply calls the inherited constructor and then sets up some of the `TField` ([298](#)) class' fields.

See also: `TField` ([298](#))

## 10.8 TBCDField

### 10.8.1 Description

`TBCDField` is the class used when a dataset must manage data of Binary Coded Decimal type. (`TField.DataType` ([310](#)) equals `ftBCD`). It initializes some of the properties of the `TField` ([298](#)) class, and overrides some of its methods to be able to work with BCD fields.

`TBCDField` assumes that the field's contents can be stored in a currency type, i.e. the maximum number of decimals after the decimal separator that can be stored in a `TBCDField` is 4. Fields that need to store a larger amount of decimals should be represented by a `TFMTBCDField` ([208](#)) instance.

It should never be necessary to create an instance of `TBCDField` manually, a field of this class will be instantiated automatically for each BCD field when a dataset is opened.

### 10.8.2 Method overview

Page	Property	Description
<a href="#">224</a>	CheckRange	Check whether a values falls within the allowed range
<a href="#">223</a>	Create	Create a new instance of a <code>TBCDField</code> class.

### 10.8.3 Property overview

Page	Property	Access	Description
<a href="#">225</a>	Currency	rw	Does the field represent a currency amount
<a href="#">225</a>	MaxValue	rw	Maximum value for the field
<a href="#">225</a>	MinValue	rw	Minimum value for the field
<a href="#">224</a>	Precision	rw	Precision of the BCD field
<a href="#">226</a>	Size		Number of decimals after the decimal separator
<a href="#">224</a>	Value	rw	Value of the field contents as a Currency type

### 10.8.4 TBCDField.Create

**Synopsis:** Create a new instance of a `TBCDField` class.

**Declaration:** `constructor Create(AOwner: TComponent); Override`

Visibility: public

Description: `Create` initializes a new instance of the `TBCDField` class. It calls the inherited destructor, and then sets some `TField` (298) properties to configure the instance for working with BCD data values.

See also: `TField` (298)

### 10.8.5 TBCDField.CheckRange

Synopsis: Check whether a values falls within the allowed range

Declaration: `function CheckRange(AValue: Currency) : Boolean`

Visibility: public

Description: `CheckRange` returns `True` if `AValue` lies within the range defined by the `MinValue` (225) and `MaxValue` (225) properties. If the value lies outside of the allowed range, then `False` is returned.

See also: `TBCDField.MaxValue` (225), `TBCDField.MinValue` (225)

### 10.8.6 TBCDField.Value

Synopsis: Value of the field contents as a `Currency` type

Declaration: `Property Value : Currency`

Visibility: public

Access: Read,Write

Description: `Value` is overridden from the `TField.Value` (314) property to a currency type field. It returns the same value as the `TField.AsCurrency` (306) field.

See also: `TField.Value` (314), `TField.AsCurrency` (306)

### 10.8.7 TBCDField.Precision

Synopsis: Precision of the BCD field

Declaration: `Property Precision : LongInt`

Visibility: published

Access: Read,Write

Description: `Precision` is the total number of decimals in the BCD value. It is not the same as `TBCDField.Size` (226), which is the number of decimals after the decimal point. The `Precision` property should be set by the descendent classes when they initialize the field, and should be considered read-only. Changing the value will influence the values returned by the various `AsXXX` properties.

See also: `TBCDField.Size` (226), `TBCDField.Value` (224)

### 10.8.8 TBCDField.Currency

Synopsis: Does the field represent a currency amount

Declaration: `Property Currency : Boolean`

Visibility: published

Access: Read,Write

Description: `Currency` can be set to `True` to indicate that the field contains data representing an amount of currency. This affects the way the `TField.DisplayText` (311) and `TField.Text` (313) properties format the value of the field: if the `Currency` property is `True`, then these properties will format the value as a currency value (generally appending the currency sign) and if the `Currency` property is `False`, then they will format it as a normal floating-point value.

See also: `TField.DisplayText` (311), `TField.Text` (313)

### 10.8.9 TBCDField.MaxValue

Synopsis: Maximum value for the field

Declaration: `Property MaxValue : Currency`

Visibility: published

Access: Read,Write

Description: `MaxValue` can be set to a value different from zero, it is then the maximum value for the field if set to any value different from zero. When setting the field's value, the value may not be larger than `MaxValue`. Any attempt to write a larger value as the field's content will result in an exception. By default `MaxValue` equals 0, i.e. any floating-point value is allowed.

If `MaxValue` is set, `MinField` (208) should also be set, because it will also be checked.

See also: `TBCDField.MinValue` (225), `TBCDField.CheckRange` (224)

### 10.8.10 TBCDField.MinValue

Synopsis: Minimum value for the field

Declaration: `Property MinValue : Currency`

Visibility: published

Access: Read,Write

Description: `MinValue` can be set to a value different from zero, then it is the minimum value for the field. When setting the field's value, the value may not be less than `MinValue`. Any attempt to write a smaller value as the field's content will result in an exception. By default `MinValue` equals 0, i.e. any floating-point value is allowed.

If `MinValue` is set, `MaxField` (208) should also be set, because it will also be checked.

See also: `TBCDField.MaxValue` (225), `TBCDField.CheckRange` (224)

### 10.8.11 TBCDField.Size

Synopsis: Number of decimals after the decimal separator

Declaration: `Property Size :`

Visibility: `published`

Access:

Description: `Size` is the number of decimals after the decimal separator. It is not the total number of decimals, which is stored in the `TBCDField.Precision` (224) field.

See also: `TBCDField.Precision` (224)

## 10.9 TBinaryField

### 10.9.1 Description

`TBinaryField` is an abstract class, designed to handle binary data of variable size. It overrides some of the properties and methods of the `TField` (298) class to be able to work with binary field data, such as retrieving the contents as a string or as a variant.

One must never create an instance of `TBinaryField` manually, it is an abstract class. Instead, a descendent class such as `TBytesField` (232) or `TVarBytesField` (375) should be created.

### 10.9.2 Method overview

Page	Property	Description
<a href="#">226</a>	<code>Create</code>	Create a new instance of a <code>TBinaryField</code> class.

### 10.9.3 Property overview

Page	Property	Access	Description
<a href="#">226</a>	<code>Size</code>		Size of the binary data

### 10.9.4 TBinaryField.Create

Synopsis: Create a new instance of a `TBinaryField` class.

Declaration: `constructor Create(AOwner: TComponent); Override`

Visibility: `public`

Description: `Create` initializes a new instance of the `TBinaryField` class. It simply calls the inherited destructor.

See also: `TField` (298)

### 10.9.5 TBinaryField.Size

Synopsis: Size of the binary data

Declaration: `Property Size :`

Visibility: `published`

Access:

Description: `Size` is simply redeclared published with a default value of 16.

See also: `TField.Size` (313)

## 10.10 TBlobField

### 10.10.1 Description

`TBlobField` is the class used when a dataset must manage BLOB data. (`TField.DataType` (310) equals `ftBLOB`). It initializes some of the properties of the `TField` (298) class, and overrides some of its methods to be able to work with BLOB fields. It also serves as parent class for some specialized blob-like field types such as `TMemoField` (353), `TWideMemoField` (377) or `TGraphicField` (337)

It should never be necessary to create an instance of `TBlobField` manually, a field of this class will be instantiated automatically for each BLOB field when a dataset is opened.

### 10.10.2 Method overview

Page	Property	Description
<a href="#">228</a>	<code>Clear</code>	Clear the BLOB field's contents
<a href="#">227</a>	<code>Create</code>	Create a new instance of a <code>TBlobField</code> class.
<a href="#">228</a>	<code>IsBlob</code>	Is the field a blob field
<a href="#">228</a>	<code>LoadFromFile</code>	Load the contents of the field from a file
<a href="#">228</a>	<code>LoadFromStream</code>	Load the field's contents from stream
<a href="#">229</a>	<code>SaveToFile</code>	Save field contents to a file
<a href="#">229</a>	<code>SaveToStream</code>	Save the field's contents to stream
<a href="#">229</a>	<code>SetFieldType</code>	Set field type

### 10.10.3 Property overview

Page	Property	Access	Description
<a href="#">229</a>	<code>BlobSize</code>	r	Size of the current blob
<a href="#">230</a>	<code>BlobType</code>	rw	Type of blob
<a href="#">230</a>	<code>Modified</code>	rw	Has the field's contents been modified.
<a href="#">231</a>	<code>Size</code>		Size of the blob field
<a href="#">230</a>	<code>Transliterate</code>	rw	Should the contents of the field be transliterated
<a href="#">230</a>	<code>Value</code>	rw	Return the field's contents as a string

### 10.10.4 TBlobField.Create

Synopsis: Create a new instance of a `TBlobField` class.

Declaration: `constructor Create(AOwner: TComponent); Override`

Visibility: `public`

Description: `Create` initializes a new instance of the `TBlobField` class. It calls the inherited destructor, and then sets some `TField` (298) properties to configure the instance for working with BLOB data.

See also: `TField` (298)

### 10.10.5 TBlobField.Clear

Synopsis: Clear the BLOB field's contents

Declaration: `procedure Clear; Override`

Visibility: `public`

Description: `Clear` overrides the `TField` implementation of `TField.Clear` (303). It creates and immediately releases an empty blob stream in write mode, effectively clearing the contents of the BLOB field.

See also: `TField.Clear` (303), `TField.IsNull` (312)

### 10.10.6 TBlobField.IsBlob

Synopsis: Is the field a blob field

Declaration: `function IsBlob : Boolean; Override`

Visibility: `public`

Description: `IsBlob` is overridden by `TBlobField` to return `True`

See also: `TField.IsBlob` (304)

### 10.10.7 TBlobField.LoadFromFile

Synopsis: Load the contents of the field from a file

Declaration: `procedure LoadFromFile(const FileName: String)`

Visibility: `public`

Description: `LoadFromFile` creates a file stream with `FileName` as the name of the file to open, then calls `LoadFromStream` (228) to read the contents of the blob field from the file. The file is opened in read-only mode.

Errors: If the file does not exist or is not available for reading, an exception will be raised.

See also: `TBlobField.LoadFromStream` (228), `TBlobField.SaveToFile` (229)

### 10.10.8 TBlobField.LoadFromStream

Synopsis: Load the field's contents from stream

Declaration: `procedure LoadFromStream(Stream: TStream)`

Visibility: `public`

Description: `LoadFromStream` can be used to load the contents of the field from a `TStream` (??) descendant. The entire data of the stream will be copied, and the stream will be positioned on the first byte of data, so it must be seekable.

Errors: If the stream is not seekable, an exception will be raised.

See also: `TBlobField.SaveToStream` (229), `TField.LoadFromFile` (228)

### 10.10.9 TBlobField.SaveToFile

Synopsis: Save field contents to a file

Declaration: `procedure SaveToFile(const FileName: String)`

Visibility: public

Description: `SaveToFile` creates a file stream with `FileName` as the name of the file to open, en then calls `SaveToStream` (229) to write the contents of the blob field to the file. The file is opened in write mode and is created if it does not yet exist.

Errors: If the file cannot be created or is not available for writing, an exception will be raised.

See also: `TBlobField.LoadFromFile` (228), `TBlobField.SaveToStream` (229)

### 10.10.10 TBlobField.SaveToStream

Synopsis: Save the field's contents to stream

Declaration: `procedure SaveToStream(Stream: TStream)`

Visibility: public

Description: `SaveToStream` can be used to save the contents of the field to a `TStream` (??) descendent. The entire data of the field will be copied. The stream must of course support writing.

Errors: If the stream is not writable, an exception will be raised.

See also: `TBlobField.SaveToFile` (229), `TBlobField.LoadFromStream` (228)

### 10.10.11 TBlobField.SetFieldType

Synopsis: Set field type

Declaration: `procedure SetFieldType(AValue: TFieldType); Override`

Visibility: public

Description: `SetFieldType` is overridden by `TBlobField` to check whether a valid Blob field type is set. If so, it calls the inherited method.

See also: `TField.DataType` (310)

### 10.10.12 TBlobField.BlobSize

Synopsis: Size of the current blob

Declaration: `Property BlobSize : LongInt`

Visibility: public

Access: Read

Description: `BlobSize` is the size (in bytes) of the current contents of the field. It will vary as the dataset's current record moves from record to record.

See also: `TField.Size` (313), `TField.DataSize` (310)

### 10.10.13 TBlobField.Modified

Synopsis: Has the field's contents been modified.

Declaration: `Property Modified : Boolean`

Visibility: `public`

Access: `Read,Write`

Description: `Modified` indicates whether the field's contents have been modified for the current record.

See also: `TBlobField.LoadFromStream` ([228](#))

### 10.10.14 TBlobField.Value

Synopsis: Return the field's contents as a string

Declaration: `Property Value : String`

Visibility: `public`

Access: `Read,Write`

Description: `Value` is redefined by `TBlobField` as a string value: getting or setting this value will convert the BLOB data to a string, it will return the same value as the `TField.AsString` ([308](#)) property.

See also: `TField.Value` ([314](#)), `TField.AsString` ([308](#))

### 10.10.15 TBlobField.Transliterate

Synopsis: Should the contents of the field be transliterated

Declaration: `Property Transliterate : Boolean`

Visibility: `public`

Access: `Read,Write`

Description: `Transliterate` indicates whether the contents of the field should be transliterated (i.e. changed from OEM to non OEM codepage and vice versa) when reading or writing the value. The actual transliteration must be done in the `TDataset.Translate` ([270](#)) method of the dataset to which the field belongs. By default this property is `False`, but it can be set to `True` for BLOB data which contains text in another codepage.

See also: `TStringField.Transliterate` ([374](#)), `TDataset.Translate` ([270](#))

### 10.10.16 TBlobField.BlobType

Synopsis: Type of blob

Declaration: `Property BlobType : TBlobType`

Visibility: `published`

Access: `Read,Write`

Description: `BlobType` is an alias for `TField.DataType` ([310](#)), but with a restricted set of values. Setting `BlobType` is equivalent to setting the `TField.DataType` ([310](#)) property.

See also: `TField.DataType` ([310](#))



### 10.10.17 TBlobField.Size

Synopsis: Size of the blob field

Declaration: `Property Size :`

Visibility: `published`

Access:

Description: `Size` is the size of the blob in the internal memory buffer. It defaults to 0, as the BLOB data is not stored in the internal memory buffer. To get the size of the data in the current record, use the `BlobSize` (229) property instead.

See also: `TBlobField.BlobSize` (229)

## 10.11 TBooleanField

### 10.11.1 Description

`TBooleanField` is the field class used by `TDataset` (250) whenever it needs to manage boolean data (`TField.DataType` (310) equals `ftBoolean`). It overrides some properties and methods of `TField` (298) to be able to work with boolean data.

It should never be necessary to create an instance of `TBooleanField` manually, a field of this class will be instantiated automatically for each boolean field when a dataset is opened.

### 10.11.2 Method overview

Page	Property	Description
<a href="#">231</a>	<code>Create</code>	Create a new instance of the <code>TBooleanField</code> class.

### 10.11.3 Property overview

Page	Property	Access	Description
<a href="#">232</a>	<code>DisplayValues</code>	<code>rw</code>	Textual representation of the true and false values
<a href="#">232</a>	<code>Value</code>	<code>rw</code>	Value of the field as a boolean value

### 10.11.4 TBooleanField.Create

Synopsis: Create a new instance of the `TBooleanField` class.

Declaration: `constructor Create(AOwner: TComponent); Override`

Visibility: `public`

Description: `Create` initializes a new instance of the `TBooleanField` class. It calls the inherited constructor and then sets some `TField` (298) properties to configure it for working with boolean values.

See also: `TField` (298)

### 10.11.5 TBooleanField.Value

Synopsis: Value of the field as a boolean value

Declaration: `Property Value : Boolean`

Visibility: `public`

Access: `Read,Write`

Description: `Value` is redefined from `TField.Value` (314) by `TBooleanField` as a boolean value. It returns the same value as the `TField.AsBoolean` (306) property.

See also: `TField.AsBoolean` (306), `TField.Value` (314)

### 10.11.6 TBooleanField.DisplayValues

Synopsis: Textual representation of the true and false values

Declaration: `Property DisplayValues : String`

Visibility: `published`

Access: `Read,Write`

Description: `DisplayValues` contains 2 strings, separated by a semicolon (;) which are used to display the `True` and `False` values of the fields. The first string is used for `True` values, the second value is used for `False` values. If only one value is given, it will serve as the representation of the `True` value, the `False` value will be represented as an empty string.

A value of `Yes;No` will result in `True` values being displayed as 'Yes', and `False` values as 'No'. When writing the value of the field as a string, the string will be compared (case insensitively) with the value for `True`, and if it matches, the field's value will be set to `True`. After this it will be compared to the value for `False`, and if it matches, the field's value will be set to `False`. If the text matches neither of the two values, an exception will be raised.

See also: `TField.AsString` (308), `TField.Text` (313)

## 10.12 TBytesField

### 10.12.1 Description

`TBytesField` is the class used when a dataset must manage data of fixed-size binary type. (`TField.DataType` (310) equals `ftBytes`). It initializes some of the properties of the `TField` (298) class to be able to work with fixed-size byte fields.

It should never be necessary to create an instance of `TBytesField` manually, a field of this class will be instantiated automatically for each binary data field when a dataset is opened.

### 10.12.2 Method overview

Page	Property	Description
<a href="#">233</a>	<code>Create</code>	Create a new instance of a <code>TBytesField</code> class.

### 10.12.3 TBytesField.Create

**Synopsis:** Create a new instance of a `TBytesField` class.

**Declaration:** `constructor Create(AOwner: TComponent); Override`

**Visibility:** public

**Description:** `Create` initializes a new instance of the `TBytesField` class. It calls the inherited destructor, and then sets some `TField` (298) properties to configure the instance for working with binary data values.

See also: `TField` (298)

## 10.13 TCheckConstraint

### 10.13.1 Description

`TCheckConstraint` can be used to store the definition of a record-level constraint. It does not enforce the constraint, it only stores the constraint's definition. The constraint can come from several sources: an imported constraints from the database, usually stored in the `TCheckConstraint.ImportedConstraint` (234) property, or a constraint enforced by the user on a particular dataset instance stored in `TCheckConstraint.CustomConstraint` (234)

### 10.13.2 Method overview

Page	Property	Description
233	<code>Assign</code>	Assign one constraint to another

### 10.13.3 Property overview

Page	Property	Access	Description
234	<code>CustomConstraint</code>	rw	User-defined constraint
234	<code>ErrorMessage</code>	rw	Message to display when the constraint is violated
234	<code>FromDictionary</code>	rw	True if the constraint is imported from a datadictionary
234	<code>ImportedConstraint</code>	rw	Constraint imported from the database engine

### 10.13.4 TCheckConstraint.Assign

**Synopsis:** Assign one constraint to another

**Declaration:** `procedure Assign(Source: TPersistent); Override`

**Visibility:** public

**Description:** `Assign` is overridden by `TCheckConstraint` to copy all published properties if `Source` is also a `TCheckConstraint` instance.

**Errors:** If `Source` is not an instance of `TCheckConstraint`, an exception may be thrown.

See also: `TCheckConstraint.ImportedConstraint` (234), `TCheckConstraint.CustomConstraint` (234)

### 10.13.5 TCheckConstraint.CustomConstraint

Synopsis: User-defined constraint

Declaration: `Property CustomConstraint : String`

Visibility: published

Access: Read,Write

Description: `CustomConstraint` is an SQL expression with an additional user-defined constraint. The expression should be enforced by a `TDataset` (250) descendent when data is posted to the dataset. If the constraint is violated, then the dataset should raise an exception, with message as specified in `TCustomConstraint.ErrorMessage` (208)

See also: `TCustomConstraint.ErrorMessage` (208)

### 10.13.6 TCheckConstraint.ErrorMessage

Synopsis: Message to display when the constraint is violated

Declaration: `Property ErrorMessage : String`

Visibility: published

Access: Read,Write

Description: `ErrorMessage` is used as the message when the dataset instance raises an exception if the constraint is violated.

See also: `TCheckConstraint.CustomConstraint` (234)

### 10.13.7 TCheckConstraint.FromDictionary

Synopsis: True if the constraint is imported from a datadictionary

Declaration: `Property FromDictionary : Boolean`

Visibility: published

Access: Read,Write

Description: `FromDictionary` indicates whether a constraint is imported from a data dictionary. This can be set by `TDataset` (250) descendents to indicate the source of the constraint, but is otherwise ignored.

See also: `TCheckConstraint.ImportedConstraint` (234)

### 10.13.8 TCheckConstraint.ImportedConstraint

Synopsis: Constraint imported from the database engine

Declaration: `Property ImportedConstraint : String`

Visibility: published

Access: Read,Write

Description: `ImportedConstraint` is a constraint imported from the database engine: it will not be enforced locally by the `TDataset` (250) descendent.

See also: `TCheckConstraint.CustomConstraint` (234)

## 10.14 TCheckConstraints

### 10.14.1 Description

TCheckConstraints is a TCollection descendent which keeps a collection of TCheckConstraint (233) items. It overrides the Add (235) method to return a TCheckConstraint instance.

### 10.14.2 Method overview

Page	Property	Description
<a href="#">235</a>	Add	Add new TCheckConstraint item to the collection
<a href="#">235</a>	Create	Create a new instance of the TCheckConstraints class.

### 10.14.3 Property overview

Page	Property	Access	Description
<a href="#">235</a>	Items	rw	Indexed access to the items in the collection

### 10.14.4 TCheckConstraints.Create

Synopsis: Create a new instance of the TCheckConstraints class.

Declaration: constructor Create(AOwner: TPersistent)

Visibility: public

Description: Create initializes a new instance of the TCheckConstraints class. The AOwner argument is usually the TDataSet (250) instance for which the data is managed. It is kept for future reference. After storing the owner, the inherited constructor is called with the TCheckConstraint (233) class pointer.

See also: TCheckConstraint (233), TDataSet (250)

### 10.14.5 TCheckConstraints.Add

Synopsis: Add new TCheckConstraint item to the collection

Declaration: function Add : TCheckConstraint

Visibility: public

Description: Add is overridden by TCheckConstraint to add a new TCheckConstraint (233) instance to the collection. it returns the newly added instance.

See also: TCheckConstraint (233), #rtl.classes.TCollection.Add (??)

### 10.14.6 TCheckConstraints.Items

Synopsis: Indexed access to the items in the collection

Declaration: Property Items[Index: LongInt]: TCheckConstraint; default

Visibility: public

Access: Read,Write

**Description:** `Items` is overridden by `TCheckConstraints` to provide type-safe access to the items in the collection. The `index` is zero-based, so it runs from 0 to `Count-1`.

See also: `#rtl.classes.TCollection.Items` (??)

## 10.15 TCurrencyField

### 10.15.1 Description

`TCurrencyField` is the field class used by `TDataset` (250) when it needs to manage currency-valued data. (`TField.Datatype` (310) equals `ftCurrency`). It simply sets some `Tfield` (298) properties to be able to work with currency data.

It should never be necessary to create an instance of `TCurrencyField` manually, a field of this class will be instantiated automatically for each currency field when a dataset is opened.

### 10.15.2 Method overview

Page	Property	Description
<a href="#">236</a>	<code>Create</code>	Create a new instance of a <code>TCurrencyField</code> .

### 10.15.3 Property overview

Page	Property	Access	Description
<a href="#">236</a>	<code>Currency</code>		Is the field a currency field

### 10.15.4 TCurrencyField.Create

**Synopsis:** Create a new instance of a `TCurrencyField`.

**Declaration:** `constructor Create(AOwner: TComponent); Override`

**Visibility:** `public`

**Description:** `Create` initializes a new instance of `TCurrencyField`. It calls the inherited constructor and then sets some properties (`TCurrencyField.Currency` (236)) to be able to work with currency data.

See also: `TField` (298), `TCurrencyField.Currency` (236)

### 10.15.5 TCurrencyField.Currency

**Synopsis:** Is the field a currency field

**Declaration:** `Property Currency :`

**Visibility:** `published`

**Access:**

**Description:** `Currency` is inherited from `TFloatField.Currency` (335) but is initialized to `True` by the `TCurrencyField` constructor. It can be set to `False` if the contents of the field is of type currency, but does not represent an amount of currency.

See also: `TFloatField.Currency` (335)

## 10.16 TCustomConnection

### 10.16.1 Description

`TCustomConnection` must be used for all database classes that need a connection to a server. The class introduces some methods and classes to activate the connection (`Open` (238)) and to deactivate the connection (`TCustomConnection.Close` (237)), plus a property to inspect the state (`Connected` (239)) of the connected.

### 10.16.2 Method overview

Page	Property	Description
<a href="#">237</a>	<code>Close</code>	Close the connection
<a href="#">237</a>	<code>Destroy</code>	Remove the <code>TCustomconnection</code> instance from memory
<a href="#">238</a>	<code>Open</code>	Makes the connection to the server

### 10.16.3 Property overview

Page	Property	Access	Description
<a href="#">239</a>	<code>AfterConnect</code>	rw	Event triggered after a connection is made.
<a href="#">239</a>	<code>AfterDisconnect</code>	rw	Event triggered after a connection is closed
<a href="#">240</a>	<code>BeforeConnect</code>	rw	Event triggered before a connection is made.
<a href="#">240</a>	<code>BeforeDisconnect</code>	rw	Event triggered before a connection is closed
<a href="#">239</a>	<code>Connected</code>	rw	Is the connection established or not
<a href="#">238</a>	<code>DataSetCount</code>	r	Number of datasets connected to this connection
<a href="#">238</a>	<code>DataSets</code>	r	Datasets linked to this connection
<a href="#">239</a>	<code>LoginPrompt</code>	rw	Should the <code>OnLogin</code> be triggered
<a href="#">240</a>	<code>OnLogin</code>	rw	Event triggered when a login prompt is shown.

### 10.16.4 TCustomConnection.Close

**Synopsis:** Close the connection

**Declaration:** `procedure Close`

**Visibility:** `public`

**Description:** `Close` closes the connection with the server if it was connected. Calling this method first triggers the `BeforeDisconnect` (240) event. If an exception is raised during the execution of that event handler, the disconnect process is aborted. After calling this event, the connection is actually closed. After the connection was closed, the `AfterDisconnect` (239) event is triggered.

Calling the `Close` method is equivalent to setting the `Connected` (239) property to `False`.

**Errors:** If the connection cannot be broken for some reason, an `EDatabaseError` (220) exception will be raised.

**See also:** `TCustomConnection.BeforeDisconnect` (240), `TCustomConnection.AfterDisconnect` (239), `TCustomConnection.Open` (238), `TCustomConnection.Connected` (239)

### 10.16.5 TCustomConnection.Destroy

**Synopsis:** Remove the `TCustomconnection` instance from memory

**Declaration:** `destructor Destroy; Override`

Visibility: public

Description: `Destroy` closes the connection, and then calls the inherited destructor.

Errors: If an exception is raised during the disconnect process, an exception will be raised, and the instance is not removed from memory.

See also: `TCustomConnection.Close` (237)

### 10.16.6 TCustomConnection.Open

Synopsis: Makes the connection to the server

Declaration: `procedure Open`

Visibility: public

Description: `Open` establishes the connection with the server if it was not yet connected. Calling this method first triggers the `BeforeConnect` (240) event. If an exception is raised during the execution of that event handler, the connect process is aborted. If `LoginPrompt` (239) is `True`, the `OnLogin` (240) event handler is called. Only after this event, the connection is actually established. After the connection was established, the `AfterConnect` (239) event is triggered.

Calling the `Open` method is equivalent to setting the `Connected` (239) property to `True`.

Errors: If an exception is raised during the `BeforeConnect` or `OnLogin` handlers, the connection is not actually established.

See also: `TCustomConnection.BeforeConnect` (240), `TCustomConnection.LoginPrompt` (239), `TCustomConnection.OnLogin` (240), `TCustomConnection.AfterConnect` (239), `TCustomConnection.Connected` (239)

### 10.16.7 TCustomConnection.DataSetCount

Synopsis: Number of datasets connected to this connection

Declaration: `Property DataSetCount : LongInt`

Visibility: public

Access: Read

Description: `DataSetCount` is the number of datasets connected to this connection component. The actual datasets are available through the `Datasets` (238) array property. As implemented in `TCustomConnection`, this property is always zero. Descendent classes implement the actual count.

See also: `TDataset` (250), `TCustomConnection.Datasets` (238)

### 10.16.8 TCustomConnection.DataSets

Synopsis: Datasets linked to this connection

Declaration: `Property DataSets[Index: LongInt]: TDataset`

Visibility: public

Access: Read

Description: `Datasets` allows indexed access to the datasets connected to this connection. `Index` is a zero-based indexed, its maximum value is `DataSetCount-1` (238).

See also: `TCustomConnection.DataSetCount` (238)



### 10.16.9 TCustomConnection.Connected

Synopsis: Is the connection established or not

Declaration: Property Connected : Boolean

Visibility: published

Access: Read,Write

Description: Connected is True if the connection to the server is established, False if it is disconnected. The property can be set to True to establish a connection (equivalent to calling TCustomConnection.Open (238), or to False to break it (equivalent to calling TCustomConnection.Close (237)).

See also: TCustomConnection.Open (238), TCustomConnection.Close (237)

### 10.16.10 TCustomConnection.LoginPrompt

Synopsis: Should the OnLogin be triggered

Declaration: Property LoginPrompt : Boolean

Visibility: published

Access: Read,Write

Description: LoginPrompt can be set to True if the OnLogin handler should be called when the Open method is called. If it is not True, then the event handler is not called.

See also: TCustomConnection.OnLogin (240)

### 10.16.11 TCustomConnection.AfterConnect

Synopsis: Event triggered after a connection is made.

Declaration: Property AfterConnect : TNotifyEvent

Visibility: published

Access: Read,Write

Description: AfterConnect is called after a connection is successfully established in TCustomConnection.Open (238). It can be used to open datasets, or indicate a connection status change.

See also: TCustomConnection.Open (238), TCustomConnection.BeforeConnect (240), TCustomConnection.OnLogin (240)

### 10.16.12 TCustomConnection.AfterDisconnect

Synopsis: Event triggered after a connection is closed

Declaration: Property AfterDisconnect : TNotifyEvent

Visibility: published

Access: Read,Write

Description: AfterDisconnect is called after a connection is successfully closed in TCustomConnection.Close (237). It can be used for instance to indicate a connection status change.

See also: TCustomConnection.Close (237), TCustomConnection.BeforeDisconnect (240)

### 10.16.13 TCustomConnection.BeforeConnect

Synopsis: Event triggered before a connection is made.

Declaration: `Property BeforeConnect : TNotifyEvent`

Visibility: published

Access: Read,Write

Description: `BeforeConnect` is called before a connection is attempted in `TCustomConnection.Open` (238).

It can be used to set connection parameters, or to abort the establishing of the connection: if an exception is raised during this event, the connection attempt is aborted.

See also: `TCustomConnection.Open` (238), `TCustomConnection.AfterConnect` (239), `TCustomConnection.OnLogin` (240)

### 10.16.14 TCustomConnection.BeforeDisconnect

Synopsis: Event triggered before a connection is closed

Declaration: `Property BeforeDisconnect : TNotifyEvent`

Visibility: published

Access: Read,Write

Description: `BeforeDisConnect` is called before a connection is closed in `TCustomConnection.Close` (237).

It can be used for instance to check for unsaved changes, to save these changes, or to abort the disconnect operation: if an exception is raised during the event handler, the disconnect operation is aborted entirely.

See also: `TCustomConnection.Close` (237), `TCustomConnection.AfterDisconnect` (239)

### 10.16.15 TCustomConnection.OnLogin

Synopsis: Event triggered when a login prompt is shown.

Declaration: `Property OnLogin : TLoginEvent`

Visibility: published

Access: Read,Write

Description: `OnLogin` is triggered when the connection needs a login prompt during the call: it is triggered when the `LoginPrompt` (239) property is `True`, after the `TCustomConnection.BeforeConnect` (240) event, but before the connection is actually established.

See also: `TCustomConnection.BeforeConnect` (240), `TCustomConnection.LoginPrompt` (239), `TCustomConnection.Open` (238)

## 10.17 TDatabase

### 10.17.1 Description

TDatabase is a component whose purpose is to provide a connection to an external database engine, not to provide the database itself. This class provides generic methods for attachment to databases and querying their contents; the details of the actual connection are handled by database-specific components (such as SQLDb for SQL-based databases, or DBA for DBASE/FoxPro style databases).

Like TDataset (250), TDatabase is an abstract class. It provides methods to keep track of datasets connected to the database, and to close these datasets when the connection to the database is closed. To this end, it introduces a Connected (244) boolean property, which indicates whether a connection to the database is established or not. The actual logic to establish a connection to a database must be implemented by descendent classes.

### 10.17.2 Method overview

Page	Property	Description
<a href="#">242</a>	CloseDataSets	Close all connected datasets
<a href="#">242</a>	CloseTransactions	End all transactions
<a href="#">241</a>	Create	Initialize a new TDatabase class instance.
<a href="#">242</a>	Destroy	Remove a TDatabase instance from memory.
<a href="#">243</a>	EndTransaction	End an active transaction.
<a href="#">242</a>	StartTransaction	Start a new transaction.

### 10.17.3 Property overview

Page	Property	Access	Description
<a href="#">244</a>	Connected	rw	Is the database connected
<a href="#">244</a>	DatabaseName	rw	Database name or path
<a href="#">243</a>	Directory	rw	Directory for the database
<a href="#">244</a>	IsSQLBased	r	Is the database SQL based.
<a href="#">244</a>	KeepConnection	rw	Should the connection be kept active
<a href="#">245</a>	Params	rw	Connection parameters
<a href="#">243</a>	TransactionCount	r	Number of transaction components connected to this database.
<a href="#">243</a>	Transactions	r	Indexed access to all transaction components connected to this database.

### 10.17.4 TDatabase.Create

Synopsis: Initialize a new TDatabase class instance.

Declaration: `constructor Create(AOwner: TComponent); Override`

Visibility: `public`

Description: `Create` initializes a new instance of the TDatabase class. It allocates some resources and then calls the inherited constructor.

See also: TDBDataset (293), TTransaction (208), TDatabase.Destroy (242)

### 10.17.5 TDatabase.Destroy

Synopsis: Remove a TDatabase instance from memory.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` starts by disconnecting the database (thus closing all datasets and ending all transactions), then notifies all connected datasets and transactions that it is about to be released. After this, it releases all resources used by the TDatabase instance

See also: `TDatabase.CloseDatasets` ([242](#))

### 10.17.6 TDatabase.CloseDataSets

Synopsis: Close all connected datasets

Declaration: `procedure CloseDataSets`

Visibility: `public`

Description: `CloseDatasets` closes all connected datasets. It is called automatically when the connection is closed.

See also: `TCustomConnection.Close` ([237](#)), `TDatabase.CloseTransactions` ([242](#))

### 10.17.7 TDatabase.CloseTransactions

Synopsis: End all transactions

Declaration: `procedure CloseTransactions`

Visibility: `public`

Description: `CloseTransaction` calls `TTransaction.EndTransaction` ([208](#)) on all connected transactions. It is called automatically when the connection is closed, after all datasets are closed.

See also: `TCustomConnection.Close` ([237](#)), `TDatabase.CloseDatasets` ([242](#))

### 10.17.8 TDatabase.StartTransaction

Synopsis: Start a new transaction.

Declaration: `procedure StartTransaction; Virtual; Abstract`

Visibility: `public`

Description: `StartTransaction` must be implemented by descendent classes to start a new transaction. This method is provided for Delphi compatibility: new applications should use a `TDBTransaction` ([294](#)) component instead and invoke the `TDBTransaction.StartTransaction` ([294](#)) method.

See also: `TDBTransaction` ([294](#)), `TDBTransaction.StartTransaction` ([294](#))

### 10.17.9 TDatabase.EndTransaction

Synopsis: End an active transaction.

Declaration: `procedure EndTransaction; Virtual; Abstract`

Visibility: `public`

Description: `EndTransaction` must be implemented by descendent classes to end an active transaction. This method is provided for Delphi compatibility: new applications should use a `TDBTransaction` (294) component instead and invoke the `TDBTransaction.EndTransaction` (294) method.

See also: `TDBTransaction` (294), `TDBTransaction.EndTransaction` (294)

### 10.17.10 TDatabase.TransactionCount

Synopsis: Number of transaction components connected to this database.

Declaration: `Property TransactionCount : LongInt`

Visibility: `public`

Access: `Read`

Description: `TransactionCount` is the number of transaction components which are connected to this database instance. It is the upper bound for the `TDatabase.Transactions` (243) array property.

See also: `TDatabase.Transactions` (243)

### 10.17.11 TDatabase.Transactions

Synopsis: Indexed access to all transaction components connected to this database.

Declaration: `Property Transactions[Index: LongInt]: TDBTransaction`

Visibility: `public`

Access: `Read`

Description: `Transactions` provides indexed access to the transaction components connected to this database. The `Index` is zero based: it runs from 0 to `TransactionCount-1`.

See also: `TDatabase.TransactionCount` (243)

### 10.17.12 TDatabase.Directory

Synopsis: Directory for the database

Declaration: `Property Directory : String`

Visibility: `public`

Access: `Read,Write`

Description: `Directory` is provided for Delphi compatibility: it indicates (for Paradox and dBase based databases) the directory where the database files are located. It is not used in the Free Pascal implementation of `TDatabase` (241).

See also: `TDatabase.Params` (245), `TDatabase.IsSQLBased` (244)

### 10.17.13 TDatabase.IsSQLBased

Synopsis: Is the database SQL based.

Declaration: `Property IsSQLBased : Boolean`

Visibility: `public`

Access: `Read`

Description: `IsSQLbased` is a read-only property which indicates whether a property is SQL-Based, i.e. whether the database engine accepts SQL commands.

See also: `TDatabase.Params` ([245](#)), `TDatabase.Directory` ([243](#))

### 10.17.14 TDatabase.Connected

Synopsis: Is the database connected

Declaration: `Property Connected : Boolean`

Visibility: `published`

Access: `Read,Write`

Description: `Connected` is simply promoted to published property from `TCustomConnection.Connected` ([239](#)).

See also: `TCustomConnection.Connected` ([239](#))

### 10.17.15 TDatabase.DatabaseName

Synopsis: Database name or path

Declaration: `Property DatabaseName : String`

Visibility: `published`

Access: `Read,Write`

Description: `DatabaseName` specifies the path of the database. For directory-based databases this will be the same as the `Directory` ([243](#)) property. For other databases this will be the name of a known pre-configured connection, or the location of the database file.

See also: `TDatabase.Directory` ([243](#)), `TDatabase.Params` ([245](#))

### 10.17.16 TDatabase.KeepConnection

Synopsis: Should the connection be kept active

Declaration: `Property KeepConnection : Boolean`

Visibility: `published`

Access: `Read,Write`

Description: `KeepConnection` is provided for Delphi compatibility, and is not used in the Free Pascal implementation of `TDatabase`.

See also: `TDatabase.Params` ([245](#))

### 10.17.17 TDatabase.Params

Synopsis: Connection parameters

Declaration: `Property Params : TStrings`

Visibility: published

Access: Read,Write

Description: `Params` is a catch-all storage mechanism for database connection parameters. It is a list of strings in the form of `Name=Value` pairs. Which name/value pairs are supported depends on the `TDatabase` descendent, but the `user_name` and `password` parameters are commonly used to store the login credentials for the database.

See also: `TDatabase.Directory` (243), `TDatabase.DatabaseName` (244)

## 10.18 TDataLink

### 10.18.1 Description

`TDataLink` is used by GUI controls or datasets in a master-detail relationship to handle data events coming from a `TDataSource` (287) instance. It is a class that exists for component programmers, application coders should never need to use `TDataLink` or one of its descendents.

DB-Aware Component coders must use a `TDataLink` instance to handle all communication with a `TDataSet` (250) instance, rather than communicating directly with the dataset. `TDataLink` contains methods which are called by the various events triggered by the dataset. Inversely, it has some methods to trigger actions in the dataset.

`TDataLink` is an abstract class; it is never used directly. Instead, a descendent class is used which overrides the various methods that are called in response to the events triggered by the dataset. Examples are .

### 10.18.2 Method overview

Page	Property	Description
<a href="#">246</a>	Create	Initialize a new instance of <code>TDataLink</code>
<a href="#">246</a>	Destroy	Remove an instance of <code>TDataLink</code> from memory
<a href="#">246</a>	Edit	Set the dataset in edit mode, if possible
<a href="#">247</a>	ExecuteAction	Execute action
<a href="#">247</a>	UpdateAction	Update handler for actions
<a href="#">247</a>	UpdateRecord	Called when the data in the dataset must be updated

### 10.18.3 Property overview

Page	Property	Access	Description
<a href="#">247</a>	Active	r	Is the link active
<a href="#">248</a>	ActiveRecord	rw	Currently active record
<a href="#">248</a>	BOF	r	Is the dataset at the first record
<a href="#">248</a>	BufferCount	rw	Set to the number of record buffers this datalink needs.
<a href="#">249</a>	DataSet	r	Dataset this datalink is connected to
<a href="#">249</a>	DataSource	rw	Datasource this datalink is connected to
<a href="#">249</a>	DataSourceFixed	rw	Can the datasource be changed
<a href="#">249</a>	Editing	r	Is the dataset in edit mode
<a href="#">250</a>	Eof	r	
<a href="#">250</a>	ReadOnly	rw	Is the link readonly
<a href="#">250</a>	RecordCount	r	Number of records in the buffer of the dataset

### 10.18.4 TDataLink.Create

Synopsis: Initialize a new instance of `TDataLink`

Declaration: `constructor Create`

Visibility: `public`

Description: `Create` calls the inherited constructor and then initializes some fields. In particular, it sets the `buffercount` to 1.

See also: `TDataLink.Destroy` ([246](#))

### 10.18.5 TDataLink.Destroy

Synopsis: Remove an instance of `TDataLink` from memory

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` cleans up the `TDataLink` instance (in particular, it removes itself from the `datasource` it is coupled to), and then calls the inherited destructor.

See also: `TDataLink.Destroy` ([246](#))

### 10.18.6 TDataLink.Edit

Synopsis: Set the dataset in edit mode, if possible

Declaration: `function Edit : Boolean`

Visibility: `public`

Description: `Edit` attempts to put the dataset in edit mode. It returns `True` if this operation succeeded, `False` if not. To this end, it calls the `Edit` ([288](#)) method of the `DataSource` ([249](#)) to which the datalink instance is coupled. If the `TDataSource.AutoEdit` ([289](#)) property is `False` then this operation will not succeed, unless the dataset is already in edit mode. GUI controls should always respect the result of this function, and not allow the user to edit data if this function returned `false`.

See also: `TDataSource` ([287](#)), `TDataLink.DataSource` ([249](#)), `TDataSource.Edit` ([288](#)), `TDataSource.AutoEdit` ([289](#))



### 10.18.7 TDataLink.UpdateRecord

Synopsis: Called when the data in the dataset must be updated

Declaration: `procedure UpdateRecord`

Visibility: `public`

Description: `Updaterecord` is called when the dataset expects the GUI controls to post any pending changes to the dataset. This method guards against recursive behaviour: while an `UpdateRecord` is in progress, the `TDatalink.RecordChange` (245) notification (which could result from writing data to the dataset) will be blocked.

See also: `TDatalink.RecordChange` (245)

### 10.18.8 TDataLink.ExecuteAction

Synopsis: Execute action

Declaration: `function ExecuteAction(Action: TBasicAction) : Boolean; Virtual`

Visibility: `public`

Description: `ExecuteAction` implements action support. It should never be necessary to call `ExecuteAction` from program code, as it is called automatically whenever a target control needs to handle an action. This method must be overridden in case any additional action must be taken when the action must be executed. The implementation in `TDatalink` checks if the action handles the datasource, and then calls `Action.ExecuteTarget`, passing it the datasource. If so, it returns `True`.

See also: `TDatalink.UpdateAction` (247)

### 10.18.9 TDataLink.UpdateAction

Synopsis: Update handler for actions

Declaration: `function UpdateAction(Action: TBasicAction) : Boolean; Virtual`

Visibility: `public`

Description: `UpdateAction` implements action update support. It should never be necessary to call `UpdateAction` from program code, as it is called automatically whenever a target control needs to update an action. This method must be overridden in case any specific action must be taken when the action must be updated. The implementation in `TDatalink` checks if the action handles the datasource, and then calls `Action.UpdateTarget`, passing it the datasource. If so, it returns `True`.

See also: `TDataLink.ExecuteAction` (247)

### 10.18.10 TDataLink.Active

Synopsis: Is the link active

Declaration: `Property Active : Boolean`

Visibility: `public`

Access: `Read`

**Description:** `Active` determines whether the events of the dataset are passed on to the control connected to the `actionlink`. If it is set to `False`, then no events are passed between control and dataset. It is set to `TDataset.Active` (278) whenever the `DataSource` (249) property is set.

See also: `TDatalink.DataSource` (249), `TDatalink.ReadOnly` (250), `TDataset.Active` (278)

### 10.18.11 `TDDataLink.ActiveRecord`

**Synopsis:** Currently active record

**Declaration:** `Property ActiveRecord : Integer`

**Visibility:** `public`

**Access:** `Read,Write`

**Description:** `ActiveRecord` returns the index of the active record in the dataset's record buffer for this datalink.

See also: `TDatalink.BOF` (248), `TDatalink.EOF` (250)

### 10.18.12 `TDDataLink.BOF`

**Synopsis:** Is the dataset at the first record

**Declaration:** `Property BOF : Boolean`

**Visibility:** `public`

**Access:** `Read`

**Description:** `BOF` returns `TDataset.BOF` (271) if the dataset is available, `True` otherwise.

See also: `TDatalink.EOF` (250), `TDataset.BOF` (271)

### 10.18.13 `TDDataLink.BufferCount`

**Synopsis:** Set to the number of record buffers this datalink needs.

**Declaration:** `Property BufferCount : Integer`

**Visibility:** `public`

**Access:** `Read,Write`

**Description:** `BufferCount` can be set to the number of buffers that the dataset should manage on behalf of the control connected to this datalink. By default, this is 1. Controls that must display more than 1 buffer (such as grids) can set this to a higher value.

See also: `TDataset.ActiveBuffer` (255), `TDatalink.ActiveRecord` (248)

**10.18.14 TDataLink.DataSet**

Synopsis: Dataset this datalink is connected to

Declaration: `Property DataSet : TDataSet`

Visibility: public

Access: Read

Description: `DataSet` equals `Datasource.Dataset` if the `datasource` is set, or `Nil` otherwise.

See also: `TDatalink.DataSource` (249), `TDataSet` (250)

**10.18.15 TDataLink.DataSource**

Synopsis: Datasource this datalink is connected to

Declaration: `Property DataSource : TDataSource`

Visibility: public

Access: Read,Write

Description: `DataSource` should be set to a `TDataSource` (287) instance to get access to the dataset it is connected to. A datalink never points directly to a `TDataSet` (250) instance, always to a `datasource`. When the `datasource` is enabled or disabled, all `TDatalink` instances connected to it are enabled or disabled at once.

See also: `TDataSet` (250), `TDataSource` (287)

**10.18.16 TDataLink.DataSourceFixed**

Synopsis: Can the datasource be changed

Declaration: `Property DataSourceFixed : Boolean`

Visibility: public

Access: Read,Write

Description: `DataSourceFixed` can be set to `True` to prevent changing of the `DataSource` (249) property. When lengthy operations are in progress, this can be done to prevent user code (e.g. event handlers) from changing the `datasource` property which might interfere with the operation in progress.

See also: `TDataLink.DataSource` (249)

**10.18.17 TDataLink.Editing**

Synopsis: Is the dataset in edit mode

Declaration: `Property Editing : Boolean`

Visibility: public

Access: Read

Description: `Editing` determines whether the dataset is in one of the edit states (`dsEdit`, `dsInsert`). It can be set into this mode by calling the `TDatalink.Edit` (246) method. Never attempt to set the dataset in editing mode directly. The `Edit` method will perform the needed checks prior to setting the dataset in edit mode and will return `True` if the dataset was successfully set in the editing state.

See also: `TDatalink.Edit` (246), `TDataSet.Edit` (260)

**10.18.18 TDataLink.Eof**

Synopsis:

Declaration: `Property Eof : Boolean`

Visibility: `public`

Access: `Read`

Description: `EOF` returns `TDataset.EOF` (273) if the dataset is available, `True` otherwise.

See also: `TDatalink.BOF` (248), `TDataset.EOF` (273)

**10.18.19 TDataLink.ReadOnly**

Synopsis: Is the link readonly

Declaration: `Property ReadOnly : Boolean`

Visibility: `public`

Access: `Read,Write`

Description: `ReadOnly` can be set to `True` to indicate that the link is read-only, i.e. the connected control will not modify the dataset. Methods as `TDatalink.Edit` (246) will check this property and fail if the link is read-only. This setting has no effect on the communication of dataset events to the datalink: the `TDatalink.Active` (247) property can be used to disable delivery of events to the datalink.

See also: `TDatalink.Active` (247), `TDatalink.edit` (246)

**10.18.20 TDataLink.RecordCount**

Synopsis: Number of records in the buffer of the dataset

Declaration: `Property RecordCount : Integer`

Visibility: `public`

Access: `Read`

Description: `RecordCount` returns the number of records in the dataset's buffer. It is limited by the `TDatalink.BufferCount` (248) property: `RecordCount` is always less than `Buffercount`.

See also: `TDatalink.BufferCount` (248)

**10.19 TDataSet****10.19.1 Description**

`TDataset` is the main class of the `db` unit. This abstract class provides all basic functionality to access data stored in tabular format: The data consists of records, and the data in each record is organised in several fields.

`TDataset` has a buffer to cache a few records in memory, this buffer is used by `TDatasource` to create the ability to use data-aware components.

`TDataset` is an abstract class, which provides the basic functionality to access, navigate through the data and - in case read-write access is available, edit existing or add new records.

`TDataset` is an abstract class: it does not have the knowledge to store or load the records from whatever medium the records are stored on. Descendants add the functionality to load and save the data. Therefore `TDataset` is never used directly, one always instantiates a descendent class.

Initially, no data is available: the dataset is inactive. The `Open` (268) method must be used to fetch data into memory. After this command, the data is available in memory for browsing or editing purposes: The dataset is active (indicated by the `TDataset.Active` (278) property). Likewise, the `Close` (258) method can be used to remove the data from memory. Any changes not yet saved to the underlying medium will be lost.

Data is expected to be in tabular format, where each row represents a record. The dataset has an idea of a cursor: this is the current position of the data cursor in the set of rows. Only the data of the current record is available for display or editing purposes. Through the `Next` (267), `Prev` (250), `First` (263) and `Last` (266) methods, it is possible to navigate through the records. The `EOF` (273) property will be `True` if the last row has been reached. Likewise, the `BOF` (271) property will return `True` if the first record in the dataset has been reached when navigating backwards. If both properties are empty, then there is no data available. For dataset descendants that support counting the number of records, the `RecordCount` (275) will be zero.

The `Append` (256) and `Insert` (265) methods can be used to insert new records to the set of records. The `TDataset.Delete` (259) statement is used to delete the current record, and the `Edit` (260) command must be used to set the dataset in editing mode: the contents of the current record can then be changed. Any changes made to the current record (be it a new or existing record) must be saved by the `Post` (268) method, or can be undone using the `Cancel` (257) method.

The data in the various fields properties is available through the `Fields` (277) array property, giving indexed access to all the fields in a record. The contents of a field is always readable. If the dataset is in one of the editing modes, then the fields can also be written to.



### 10.19.2 Method overview

Page	Property	Description
255	ActiveBuffer	Currently active memory buffer
256	Append	Append a new record to the data
256	AppendRecord	Append a new record to the dataset and fill with data
257	BookmarkValid	Test whether ABookMark is a valid bookmark.
257	Cancel	Cancel the current editing operation
257	CheckBrowseMode	Check whether the dataset is in browse mode.
257	ClearFields	Clear the values of all fields
258	Close	Close the dataset
258	CompareBookmarks	Compare two bookmarks
258	ControlsDisabled	Check whether the controls are disabled
255	Create	Create a new TDataset instance
259	CreateBlobStream	Create blob stream
259	CursorPosChanged	Indicate a change in cursor position
259	DataConvert	Convert data from/to native format
259	Delete	Delete the current record.
255	Destroy	Free a TDataset instance
260	DisableControls	Disable event propagation of controls
260	Edit	Set the dataset in editing mode.
261	EnableControls	Enable event propagation of controls
261	FieldByName	Search a field by name
261	FindField	Find a field by name
262	FindFirst	Find the first active record (deprecated)
262	FindLast	Find the last active record (deprecated)
262	FindNext	Find the next active record (deprecated)
262	FindPrior	Find the previous active record (deprecated)
263	First	Position the dataset on the first record.
263	FreeBookmark	Free a bookmark obtained with GetBookmark (deprecated)
263	GetBookmark	Get a bookmark pointer (deprecated)
264	GetCurrentRecord	Copy the data for the current record in a memory buffer
255	GetFieldData	Get the data for a field
264	GetFieldList	Return field instances in a list
264	GetFieldNames	Return a list of all available field names
264	GotoBookmark	Jump to bookmark
265	Insert	Insert a new record at the current position.
265	InsertRecord	Insert a new record with given values.
265	IsEmpty	Check if the dataset contains no data
265	IsLinkedTo	Check whether a datasource is linked to the dataset
266	IsSequenced	Is the data sequenced
266	Last	Navigate forward to the last record
266	Locate	Locate a record based on some key values
267	Lookup	Search for a record and return matching values.
267	MoveBy	Move the cursor position
267	Next	Go to the next record in the dataset.
268	Open	Activate the dataset: Fetch data into memory.
268	Post	Post pending edits to the database.
269	Prior	Go to the previous record
269	Refresh	Refresh the records in the dataset
269	Resync	Resynchronize the data buffer
256	SetFieldData	Store the data for a field
270	SetFields	Set a number of field values at once
270	Translate	Transliterate a buffer
270	UpdateCursorPos	Update cursor position
270	UpdateRecord	Indicate that the record contents have changed
271	UpdateStatus	Get the update status for the current record

### 10.19.3 Property overview

Page	Property	Access	Description
278	Active	rw	Is the dataset open or closed.
283	AfterCancel	rw	Event triggered after a Cancel operation.
280	AfterClose	rw	Event triggered after the dataset is closed
283	AfterDelete	rw	
281	AfterEdit	rw	Event triggered after the dataset is put in edit mode.
281	AfterInsert	rw	Event triggered after the dataset is put in insert mode.
280	AfterOpen	rw	Event triggered after the dataset is opened.
282	AfterPost	rw	Event called after changes have been posted to the underlying database
284	AfterRefresh	rw	Event triggered after the data has been refreshed.
284	AfterScroll	rw	Event triggered after the cursor has changed position.
279	AutoCalcFields	rw	How often should the value of calculated fields be calculated
282	BeforeCancel	rw	Event triggered before a Cancel operation.
280	BeforeClose	rw	Event triggered before the dataset is closed.
283	BeforeDelete	rw	Event triggered before a Delete operation.
281	BeforeEdit	rw	Event triggered before the dataset is put in edit mode.
280	BeforeInsert	rw	Event triggered before the dataset is put in insert mode.
279	BeforeOpen	rw	Event triggered before the dataset is opened.
282	BeforePost	rw	Event called before changes are posted to the underlying database
284	BeforeRefresh	rw	Event triggered before the data is refreshed.
283	BeforeScroll	rw	Event triggered before the cursor changes position.
271	BOF	r	Is the cursor at the beginning of the data (on the first record)
271	Bookmark	rw	Get or set the current cursor position
272	CanModify	r	Can the data in the dataset be modified
272	DataSource	r	Datasource this dataset is connected to.
273	DefaultFields	r	Is the dataset using persistent fields or not.
273	EOF	r	Indicates whether the last record has been reached.
274	FieldCount	r	Number of fields
274	FieldDefs	rw	Definitions of available fields in the underlying database
277	Fields	r	Indexed access to the fields of the dataset.
277	FieldValues	rw	Access to field values based on the field names.
277	Filter	rw	Filter to apply to the data in memory.
278	Filtered	rw	Is the filter active or not.
278	FilterOptions	rw	Options to apply when filtering
274	Found	r	Check success of one of the Find methods
275	IsUniDirectional	r	Is the dataset unidirectional (i.e. forward scrolling only)
275	Modified	rw	Was the current record modified ?
285	OnCalcFields	rw	Event triggered when values for calculated fields must be computed.
285	OnDeleteError	rw	Event triggered when a delete operation fails.
286	OnEditError	rw	Event triggered when an edit operation fails.
286	OnFilterRecord	rw	Event triggered to filter records.
286	OnNewRecord	rw	Event triggered when a new record is created.
287	OnPostError	rw	Event triggered when a post operation fails.
276	RecNo	rw	Current record number
275	RecordCount	r	Number of records in the dataset
276	RecordSize	r	Size of the record in memory
276	State	r	Current operational state of the dataset



#### 10.19.4 TDataSet.Create

Synopsis: Create a new TDataSet instance

Declaration: constructor Create(AOwner: TComponent); Override

Visibility: public

Description: Create initializes a new TDataSet (250) instance. It calls the inherited constructor, and then initializes the internal structures needed to manage the dataset (fielddefs, fieldlist, constraints etc.).

See also: TDataSet.Destroy (255)

#### 10.19.5 TDataSet.Destroy

Synopsis: Free a TDataSet instance

Declaration: destructor Destroy; Override

Visibility: public

Description: Destroy removes a TDataSet instance from memory. It closes the dataset if it was open, clears all internal structures and then calls the inherited destructor.

Errors: An exception may occur during the close operation, in that case, the dataset will not be removed from memory.

See also: TDataSet.Close (258), TDataSet.Create (255)

#### 10.19.6 TDataSet.ActiveBuffer

Synopsis: Currently active memory buffer

Declaration: function ActiveBuffer : PChar

Visibility: public

Description: ActiveBuffer points to the currently active memory buffer. It should not be used in application code.

#### 10.19.7 TDataSet.GetFieldData

Synopsis: Get the data for a field

```
Declaration: function GetFieldData(Field: TField; Buffer: Pointer) : Boolean; Virtual
                ; Overload
function GetFieldData(Field: TField; Buffer: Pointer;
                NativeFormat: Boolean) : Boolean; Virtual
                ; Overload
```

Visibility: public

Description: GetFieldData should copy the data for field Field from the internal dataset memory buffer into the memory pointed to by Buffer. This function is not intended for use by end-user applications, and should be used only in descendent classes, where it can be overridden. The function should return True if data was available and has been copied, or False if no data was available (in which case the field has value Null). The NativeFormat determines whether the data should be in native format (e.g. whether the date/time values should be in TDateTime format).

Errors: No checks are performed on the validity of the memory buffer

See also: `TField.DisplayText` ([311](#))

### 10.19.8 TDataSet.SetFieldData

Synopsis: Store the data for a field

Declaration: `procedure SetFieldData(Field: TField; Buffer: Pointer); Virtual  
; Overload  
procedure SetFieldData(Field: TField; Buffer: Pointer;  
NativeFormat: Boolean); Virtual; Overload`

Visibility: public

Description: `SetFieldData` should copy the data from field `Field`, stored in the memory pointed to by `Buffer` to the dataset memory buffer for the current record. This function is not intended for use by end-user applications, and should be used only in descendent classes, where it can be overridden. The `NativeFormat` determines whether the data is in native format (e.g. whether the date/time values are in `TDatetime` format).

See also: `TField.DisplayText` ([311](#))

### 10.19.9 TDataSet.Append

Synopsis: Append a new record to the data

Declaration: `procedure Append`

Visibility: public

Description: `Append` appends a new record at the end of the dataset. It is functionally equal to the `TDataSet.Insert` ([265](#)) call, but the cursor is positioned at the end of the dataset prior to performing the insert operation. The same events occur as when the `Insert` call is made.

See also: `TDataSet.Insert` ([265](#)), `TDataSet.Edit` ([260](#))

### 10.19.10 TDataSet.AppendRecord

Synopsis: Append a new record to the dataset and fill with data

Declaration: `procedure AppendRecord(const Values: Array of const)`

Visibility: public

Description: `AppendRecord` first calls `Append` to add a new record to the dataset. It then copies the values in `Values` to the various fields (using `TDataSet.SetFields` ([270](#))) and attempts to post the record using `TDataSet.Post` ([268](#)). If all went well, the result is that the values in `Values` have been added as a new record to the dataset.

Errors: Various errors may occur (not supplying a value for all required fields, invalid values) and may cause an exception. This may leave the dataset in editing mode.

See also: `TDataSet.Append` ([256](#)), `TDataSet.SetFields` ([270](#)), `TDataSet.Post` ([268](#))

### 10.19.11 TDataSet.BookmarkValid

Synopsis: Test whether ABookmark is a valid bookmark.

Declaration: `function BookmarkValid(ABookmark: TBookmark) : Boolean; Virtual`

Visibility: `public`

Description: `BookmarkValid` returns `True` if `ABookmark` is a valid bookmark for the dataset. Various operations can render a bookmark invalid: changing the sort order, closing and re-opening the dataset. `BookmarkValid` always returns `False` in `TDataSet`. Descendent classes must override this method to do an actual test.

Errors: If the bookmark is a completely arbitrary pointer, an exception may be raised.

See also: `TDataSet.GetBookmark` (263), `TDataSet.SetBookmark` (250), `TDataSet.FreeBookmark` (263), `TDataSet.BookmarkAvailable` (250)

### 10.19.12 TDataSet.Cancel

Synopsis: Cancel the current editing operation

Declaration: `procedure Cancel; Virtual`

Visibility: `public`

Description: `Cancel` cancels the current editing operation and sets the dataset again in browse mode. This operation triggers the `TDataSet.OnBeforeCancel` (250) and `TDataSet.OnAfterCancel` (250) events. If the dataset was in insert mode, then the `TDataSet.OnBeforeScroll` (250) and `TDataSet.OnAfterScroll` (250) events are triggered after and respectively before the `OnBeforeCancel` and `OnAfterCancel` events.

If the dataset was not in one of the editing modes when `Cancel` is called, then nothing will happen.

Errors:

See also: `TDataSet.State` (276), `TDataSet.Append` (256), `TDataSet.Insert` (265), `TDataSet.Edit` (260)

### 10.19.13 TDataSet.CheckBrowseMode

Synopsis: Check whether the dataset is in browse mode.

Declaration: `procedure CheckBrowseMode`

Visibility: `public`

Description: `CheckBrowseMode` checks whether the dataset is in browse mode (`State=dsBrowse`). If it is not, an `EDatabaseError` (220) exception is raised.

See also: `TDataSet.State` (276)

### 10.19.14 TDataSet.ClearFields

Synopsis: Clear the values of all fields

Declaration: `procedure ClearFields`

Visibility: `public`

**Description:** `ClearFields` clears the values of all fields.

**Errors:** If the dataset is not in editing mode (`State` in `dsEditmodes`), then an `EDatabaseError` (220) exception will be raised.

See also: `TDataset.State` (276), `TField.Clear` (303)

### 10.19.15 `TDataset.Close`

**Synopsis:** Close the dataset

**Declaration:** `procedure Close`

**Visibility:** `public`

**Description:** `Close` closes the dataset if it is open (`Active=True`). This action triggers the `TDataset.OnBeforeClose` (250) and `TDataset.OnAfterClose` (250) events. If the dataset is not active, nothing happens.

**Errors:** If an exception occurs during the closing of the dataset, the `OnAfterClose` event will not be triggered.

See also: `TDataset.Active` (278), `TDataset.Open` (268)

### 10.19.16 `TDataset.ControlsDisabled`

**Synopsis:** Check whether the controls are disabled

**Declaration:** `function ControlsDisabled : Boolean`

**Visibility:** `public`

**Description:** `ControlsDisabled` returns `True` if the controls are disabled, i.e. no events are propagated to the controls connected to this dataset. The `TDataset.DisableControls` (260) call can be used to disable sending of data events to the controls. The sending can be re-enabled with `TDataset.EnableControls` (261). This mechanism has a counting mechanism: in order to enable sending of events to the controls, `EnableControls` must be called as much as `DisableControls` was called. The `ControlsDisabled` function will return `true` as long as the internal counter is not zero.

See also: `TDataset.DisableControls` (260), `TDataset.EnableControls` (261)

### 10.19.17 `TDataset.CompareBookmarks`

**Synopsis:** Compare two bookmarks

**Declaration:** `function CompareBookmarks (Bookmark1: TBookmark; Bookmark2: TBookmark)  
: LongInt; Virtual`

**Visibility:** `public`

**Description:** `CompareBookmarks` can be used to compare the relative positions of 2 bookmarks. It returns a negative value if `Bookmark1` is located before `Bookmark2`, zero if they refer to the same record, and a positive value if the second bookmark appears before the first bookmark. This function must be overridden by descendent classes of `TDataset`. The implementation in `TDataset` always returns zero.

**Errors:** No checks are performed on the validity of the bookmarks.

See also: `TDataset.BookmarkValid` (257), `TDataset.GetBookmark` (263), `TDataset.SetBookmark` (250)

**10.19.18 TDataSet.CreateBlobStream**

Synopsis: Create blob stream

Declaration: `function CreateBlobStream(Field: TField; Mode: TBlobStreamMode) : TStream  
; Virtual`

Visibility: public

Description: `CreateBlobStream` is not intended for use by application programmers. It creates a stream object which can be used to read or write data from a blob field. Instead, application programmers should use the `TBlobField.LoadFromStream` (228) and `TBlobField.SaveToStream` (229) methods when reading and writing data from/to BLOB fields. Which operation must be performed on the stream is indicated in the `Mode` parameter, and the `Field` parameter contains the field whose data should be read. The caller is responsible for freeing the stream created by this function.

See also: `TBlobField.LoadFromStream` (228), `TBlobField.SaveToStream` (229)

**10.19.19 TDataSet.CursorPosChanged**

Synopsis: Indicate a change in cursor position

Declaration: `procedure CursorPosChanged`

Visibility: public

Description: `CursorPosChanged` is not intended for internal use only, and serves to indicate that the current cursor position has changed. (it clears the internal cursor position).

**10.19.20 TDataSet.DataConvert**

Synopsis: Convert data from/to native format

Declaration: `procedure DataConvert(aField: TField; aSource: Pointer; aDest: Pointer;  
aToNative: Boolean); Virtual`

Visibility: public

Description: `DataConvert` converts the data from field `AField` in buffer `ASource` to native format and puts the result in `ADest`. If the `aToNative` parameter equals `False`, then the data is converted from native format to non-native format. Currently, only date/time/datetime and BCD fields are converted from/to native data. This means the routine handles conversion between `TDateTime` (the native format) and `TDateTimeRec`, and between `TBCD` and currency (the native format) for BCD fields. `DataConvert` is used internally by `TDataset` and descendent classes. There should be no need to use this routine in application code.

Errors: No checking on the validity of the buffer pointers is performed. If an invalid pointer is passed, an exception may be raised.

See also: `TDataset.GetFieldData` (255), `TDataset.SetFieldData` (256)

**10.19.21 TDataSet.Delete**

Synopsis: Delete the current record.

Declaration: `procedure Delete`

Visibility: public

**Description:** `Delete` will delete the current record. This action will trigger the `TDataset.BeforeDelete` (283), `TDataset.BeforeScroll` (283), `TDataset.AfterDelete` (283) and `TDataset.AfterScroll` (284) events. If the dataset was in edit mode, the edits will be canceled before the delete operation starts.

**Errors:** If the dataset is empty or read-only, then an `EDatabaseError` (220) exception will be raised.

**See also:** `TDataset.Cancel` (257), `TDataset.BeforeDelete` (283), `TDataset.BeforeScroll` (283), `TDataset.AfterDelete` (283), `TDataset.AfterScroll` (284)

### 10.19.22 TDataSet.DisableControls

**Synopsis:** Disable event propagation of controls

**Declaration:** `procedure DisableControls`

Visibility: public

**Description:** `DisableControls` tells the dataset to stop sending data-related events to the controls. This can be used before starting operations that will cause the current record to change a lot, or before any other lengthy operation that may cause a lot of events to be sent to the controls that show data from the dataset: each event will cause the control to update itself, which is a time-consuming operation that may also cause a lot of flicker on the screen.

The sending of events to the controls can be re-enabled with `Tdataset.EnableControls` (261). Note that for each call to `DisableControls`, a matching call to `EnableControls` must be made: an internal count is kept and only when the count reaches zero, the controls are again notified of changes to the dataset. It is therefore essential that the call to `EnableControls` is put in a `Finally` block:

```
MyDataset.DisableControls;
Try
    // Do some intensive stuff
Finally
    MyDataset.EnableControls
end;
```

**Errors:** Failure to call `enablecontrols` will prevent the controls from receiving updates. The state can be checked with `TDataset.ControlsDisabled` (258).

**See also:** `TDataset.EnableControls` (261), `TDataset.ControlsDisabled` (258)

### 10.19.23 TDataSet.Edit

**Synopsis:** Set the dataset in editing mode.

**Declaration:** `procedure Edit`

Visibility: public

**Description:** `Edit` will set the dataset in edit mode: the contents of the current record can then be changed. This action will call the `TDataset.BeforeEdit` (281) and `TDataset.AfterEdit` (281) events. If the dataset was already in insert or edit mode, nothing will happen (the events will also not be triggered). If the dataset is empty, this action will execute `TDataset.Append` (256) instead.

**Errors:** If the dataset is read-only or not opened, then an `EDatabaseError` (220) exception will be raised.

**See also:** `TDataset.State` (276), `TDataset.EOF` (273), `TDataset.BOF` (271), `TDataset.Append` (256), `TDataset.BeforeEdit` (281), `TDataset.AfterEdit` (281)

### 10.19.24 TDataSet.EnableControls

Synopsis: Enable event propagation of controls

Declaration: `procedure EnableControls`

Visibility: `public`

Description: `EnableControls` tells the dataset to resume sending data-related events to the controls. This must be used after a call to `TDataSet.DisableControls` (260) to re-enable updating of controls.

Note that for each call to `DisableControls`, a matching call to `EnableControls` must be made: an internal count is kept and only when the count reaches zero, the controls are again notified of changes to the dataset. It is therefore essential that the call to `EnableControls` is put in a `Finally` block:

```
MyDataset.DisableControls;
Try
  // Do some intensive stuff
Finally
  MyDataset.EnableControls
end;
```

Errors: Failure to call `enablecontrols` will prevent the controls from receiving updates. The state can be checked with `TDataSet.ControlsDisabled` (258).

See also: `TDataSet.DisableControls` (260), `TDataSet.ControlsDisabled` (258)

### 10.19.25 TDataSet.FieldByName

Synopsis: Search a field by name

Declaration: `function FieldByName(const FieldName: String) : TField`

Visibility: `public`

Description: `FieldByName` is a shortcut for `Fields.FieldByName` (331): it searches for the field with `fieldname` equalling `FieldName`. The case is performed case-insensitive. The matching field instance is returned.

Errors: If the field is not found, an `EDatabaseError` (220) exception will be raised.

See also: `TFields.FieldByName` (331), `TDataSet.FindField` (261)

### 10.19.26 TDataSet.FindField

Synopsis: Find a field by name

Declaration: `function FindField(const FieldName: String) : TField`

Visibility: `public`

Description: `FindField` is a shortcut for `Fields.FindField` (331): it searches for the field with `fieldname` equalling `FieldName`. The case is performed case-insensitive. The matching field instance is returned, and if no match is found, `Nil` is returned.

See also: `TDataSet.FieldByName` (261), `TFields.FindField` (331)

### 10.19.27 TDataSet.FindFirst

Synopsis: Find the first active record (deprecated)

Declaration: `function FindFirst : Boolean`

Visibility: `public`

Description: `FindFirst` positions the cursor on the first record (taking into account filtering), and returns `True` if the cursor position was changed. This method must be implemented by descendents of `TDataSet`: The implementation in `TDataSet` always returns `False`, indicating that the position was not changed.

This method is deprecated, use `TDataSet.First` (263) instead.

See also: `TDataSet.First` (263), `TDataSet.FindLast` (262), `TDataSet.FindNext` (262), `TDataSet.FindPrior` (262)

### 10.19.28 TDataSet.FindLast

Synopsis: Find the last active record (deprecated)

Declaration: `function FindLast : Boolean`

Visibility: `public`

Description: `FindLast` positions the cursor on the last record (taking into account filtering), and returns `True` if the cursor position was changed. This method must be implemented by descendents of `TDataSet`: The implementation in `TDataSet` always returns `False`, indicating that the position was not changed.

This method is deprecated, use `TDataSet.Last` (266) instead.

See also: `TDataSet.Last` (266), `TDataSet.FindFirst` (262), `TDataSet.FindNext` (262), `TDataSet.FindPrior` (262)

### 10.19.29 TDataSet.FindNext

Synopsis: Find the next active record (deprecated)

Declaration: `function FindNext : Boolean`

Visibility: `public`

Description: `FindNext` positions the cursor on the next record (taking into account filtering), and returns `True` if the cursor position was changed. This method must be implemented by descendents of `TDataSet`: The implementation in `TDataSet` always returns `False`, indicating that the position was not changed.

This method is deprecated, use `TDataSet.Next` (267) instead.

See also: `TDataSet.Next` (267), `TDataSet.FindFirst` (262), `TDataSet.FindLast` (262), `TDataSet.FindPrior` (262)

### 10.19.30 TDataSet.FindPrior

Synopsis: Find the previous active record (deprecated)

Declaration: `function FindPrior : Boolean`

Visibility: `public`



**Description:** `FindPrior` positions the cursor on the previous record (taking into account filtering), and returns `True` if the cursor position was changed. This method must be implemented by descendents of `TDataset`: The implementation in `TDataset` always returns `False`, indicating that the position was not changed.

This method is deprecated, use `TDataset.Prior` (269) instead.

See also: `TDataset.Prior` (269), `TDataset.FindFirst` (262), `TDataset.FindLast` (262), `TDataset.FindPrior` (262)

### 10.19.31 `TDataset.First`

**Synopsis:** Position the dataset on the first record.

**Declaration:** `procedure First`

**Visibility:** `public`

**Description:** `First` positions the dataset on the first record. This action will trigger the `TDataset.BeforeScroll` (283) and `TDataset.AfterScroll` (284) events. After the action is completed, the `TDataset.BOF` (271) property will be `True`.

**Errors:** If the dataset is unidirectional or is closed, an `EDatabaseError` (220) exception will be raised.

See also: `TDataset.Prior` (269), `TDataset.Last` (266), `TDataset.Next` (267), `TDataset.BOF` (271), `TDataset.BeforeScroll` (283), `TDataset.AfterScroll` (284)

### 10.19.32 `TDataset.FreeBookmark`

**Synopsis:** Free a bookmark obtained with `GetBookmark` (deprecated)

**Declaration:** `procedure FreeBookmark(ABookmark: TBookmark); Virtual`

**Visibility:** `public`

**Description:** `FreeBookmark` must be used to free a bookmark obtained by `TDataset.GetBookmark` (263). It should not be used on bookmarks obtained with the `TDataset.Bookmark` (271) property. Both `GetBookmark` and `FreeBookmark` are deprecated. Use the `Bookmark` property instead: it uses a string type, which is automatically disposed of when the string variable goes out of scope.

See also: `TDataset.GetBookmark` (263), `TDataset.Bookmark` (271)

### 10.19.33 `TDataset.GetBookmark`

**Synopsis:** Get a bookmark pointer (deprecated)

**Declaration:** `function GetBookmark : TBookmark; Virtual`

**Visibility:** `public`

**Description:** `GetBookmark` gets a bookmark pointer to the current cursor location. The `TDataset.SetBookmark` (250) call can be used to return to the current record in the dataset. After use, the bookmark must be disposed of with the `TDataset.FreeBookmark` (263) call. The bookmark will be `Nil` if the dataset is empty or not active.

This call is deprecated. Use the `TDataset.Bookmark` (271) property instead to get a bookmark.

See also: `TDataset.SetBookmark` (250), `TDataset.FreeBookmark` (263), `TDataset.Bookmark` (271)

### 10.19.34 TDataSet.GetCurrentRecord

Synopsis: Copy the data for the current record in a memory buffer

Declaration: `function GetCurrentRecord(Buffer: PChar) : Boolean; Virtual`

Visibility: public

Description: `GetCurrentRecord` can be overridden by `TDataSet` descendents to copy the data for the current record to `Buffer`. `Buffer` must point to a memory area, large enough to contain the data for the record. If the data is copied successfully to the buffer, the function returns `True`. The `TDataSet` implementation is empty, and returns `False`.

See also: `TDataSet.ActiveBuffer` (255)

### 10.19.35 TDataSet.GetFieldList

Synopsis: Return field instances in a list

Declaration: `procedure GetFieldList(List: TList; const FieldNames: String)`

Visibility: public

Description: `GetFieldList` parses `FieldNames` for names of fields, and returns the field instances that match the names in `list`. `FieldNames` must be a list of field names, separated by semicolons. The list is cleared prior to filling with the requested field instances.

Errors: If `FieldNames` contains a name of a field that does not exist in the dataset, then an `EDatabaseError` (220) exception will be raised.

See also: `TDataSet.GetFieldNames` (264), `TDataSet.FieldByName` (261), `TDataSet.FindField` (261)

### 10.19.36 TDataSet.GetFieldNames

Synopsis: Return a list of all available field names

Declaration: `procedure GetFieldNames(List: TStrings)`

Visibility: public

Description: `GetFieldNames` returns in `List` the names of all available fields, one field per item in the list. The dataset must be open for this function to work correctly.

See also: `TDataSet.GetFieldNameList` (250), `TDataSet.FieldByName` (261), `TDataSet.FindField` (261)

### 10.19.37 TDataSet.GotoBookmark

Synopsis: Jump to bookmark

Declaration: `procedure GotoBookmark(ABookmark: TBookmark)`

Visibility: public

Description: `GotoBookmark` positions the dataset to the bookmark position indicated by `ABookmark`. `ABookmark` is a bookmark obtained by the `TDataSet.GetBookmark` (263) function.

This function is deprecated, use the `TDataSet.Bookmark` (271) property instead.

Errors: if `ABookmark` does not contain a valid bookmark, then an exception may be raised.

See also: `TDataSet.Bookmark` (271), `TDataSet.GetBookmark` (263), `TDataSet.FreeBookmark` (263)

### 10.19.38 TDataSet.Insert

Synopsis: Insert a new record at the current position.

Declaration: `procedure Insert`

Visibility: `public`

Description: `Insert` will insert a new record at the current position. When this function is called, any pending modifications (when the dataset already is in insert or edit mode) will be posted. After that, the `BeforeInsert` (280), `BeforeScroll` (283), `OnNewRecord` (286), `AfterInsert` (281) and `AfterScroll` (284) events are triggered in the order indicated here. The dataset is in the `dsInsert` state after this method is called, and the contents of the various fields can be set. To write the new record to the underlying database `TDataSet.Post` (268) must be called.

Errors: If the dataset is read-only, calling `Insert` will result in an `EDatabaseError` (220).

See also: `TDataSet.BeforeInsert` (280), `TDataSet.BeforeScroll` (283), `TDataSet.OnNewrecord` (286), `TDataSet.AfterInsert` (281), `TDataSet.AfterScroll` (284), `TDataSet.Post` (268), `TDataSet.Append` (256)

### 10.19.39 TDataSet.InsertRecord

Synopsis: Insert a new record with given values.

Declaration: `procedure InsertRecord(const Values: Array of const)`

Visibility: `public`

Description: `InsertRecord` is not yet implemented in Free Pascal. It does nothing.

Errors:

See also: `TDataSet.Insert` (265), `TDataSet.SetFieldValues` (250)

### 10.19.40 TDataSet.IsEmpty

Synopsis: Check if the dataset contains no data

Declaration: `function IsEmpty : Boolean`

Visibility: `public`

Description: `IsEmpty` returns `True` if the dataset is empty, i.e. if `EOF` (273) and `TDataSet.BOF` (271) are both `True`, and the dataset is not in insert mode.

See also: `TDataSet.EOF` (273), `TDataSet.BOF` (271), `TDataSet.State` (276)

### 10.19.41 TDataSet.IsLinkedTo

Synopsis: Check whether a datasource is linked to the dataset

Declaration: `function IsLinkedTo(ADatasource: TDataSource) : Boolean`

Visibility: `public`

Description: `IsLinkedTo` returns `True` if `ADatasource` is linked to this dataset, either directly (the `ADatasource.Dataset`" (289) points to the current dataset instance, or indirectly.

See also: `TDataSource.Dataset` (289)

### 10.19.42 TDataSet.IsSequenced

Synopsis: Is the data sequenced

Declaration: `function IsSequenced : Boolean; Virtual`

Visibility: `public`

Description: `IsSequenced` indicates whether it is safe to use the `TDataSet.RecNo` (276) property to navigate in the records of the data. By default, this property is set to `True`, but `TDataSet` descendents may set this property to `False` (for instance, unidirectional datasets), in which case `RecNo` should not be used to navigate through the data.

See also: `TDataSet.RecNo` (276)

### 10.19.43 TDataSet.Last

Synopsis: Navigate forward to the last record

Declaration: `procedure Last`

Visibility: `public`

Description: `Last` puts the cursor at the last record in the dataset, fetching more records from the underlying database if needed. After a call to `Last`, the `TDataSet.EOF` (273) property will be `True`. Calling this method will trigger the `TDataSet.BeforeScroll` (283) and `TDataSet.AfterScroll` (284) events.

See also: `TDataSet.First` (263), `TDataSet.Next` (267), `TDataSet.EOF` (273), `TDataSet.BeforeScroll` (283), `TDataSet.AfterScroll` (284)

### 10.19.44 TDataSet.Locate

Synopsis: Locate a record based on some key values

Declaration: `function Locate(const keyfields: String;const keyvalues: Variant;  
options: TLocateOptions) : Boolean; Virtual`

Visibility: `public`

Description: `Locate` attempts to locate a record in the dataset. There are 2 possible cases when using `Locate`.

1. `Keyvalues` is a single value. In that case, `KeyFields` is the name of the field whose value must be matched to the value in `KeyValues`
2. `Keyvalues` is a variant array. In that case, `KeyFields` must contain a list of names of fields (separated by semicolons) whose values must be matched to the values in the `KeyValues` array

The matching always happens according to the `Options` parameter. For a description of the possible values, see `TLocateOption` (216).

If a record is found that matches the criteria, then the `locate` operation positions the cursor on this record, and returns `True`. If no record is found to match the criteria, `False` is returned, and the position of the cursor is unchanged.

The implementation in `TDataSet` always returns `False`. It is up to `TDataSet` descendents to implement this method and return an appropriate value.

See also: `TDataSet.Find` (250), `TDataSet.Lookup` (267), `TLocateOption` (216)

### 10.19.45 TDataSet.Lookup

Synopsis: Search for a record and return matching values.

Declaration: `function Lookup(const KeyFields: String; const KeyValues: Variant;  
const ResultFields: String) : Variant; Virtual`

Visibility: public

Description: `Lookup` always returns `False` in `TDataSet`. Descendents of `TDataSet` can override this method to call `TDataSet.Locate` (266) to locate the record with fields `KeyFields` matching `KeyValues` and then to return the values of the fields in `ResultFields`. If `ResultFields` contains more than one fieldname (separated by semicolons), then the function returns an array. If there is only 1 fieldname, the value is returned directly.

Errors: If the dataset is unidirectional, then a `EDatabaseError` (220) exception will be raised.

See also: `TDataSet.Locate` (266)

### 10.19.46 TDataSet.MoveBy

Synopsis: Move the cursor position

Declaration: `function MoveBy(Distance: LongInt) : LongInt`

Visibility: public

Description: `MoveBy` moves the current record pointer with `Distance` positions. `Distance` may be a positive number, in which case the cursor is moved forward, or a negative number, in which case the cursor is moved backward. The move operation will stop as soon as the beginning or end of the data is reached. The `TDataSet.BeforeScroll` (283) and `TDataSet.AfterScroll` (284) events are triggered (once) when this method is called. The function returns the distance which was actually moved by the cursor.

Errors: A negative distance will result in an `EDatabaseError` (220) exception on unidirectional datasets.

See also: `TDataSet.RecNo` (276), `TDataSet.BeforeScroll` (283), `TDataSet.AfterScroll` (284)

### 10.19.47 TDataSet.Next

Synopsis: Go to the next record in the dataset.

Declaration: `procedure Next`

Visibility: public

Description: `Next` positions the cursor on the next record in the dataset. It is equivalent to a `MoveBy(1)` operation. Calling this method triggers the `TDataSet.BeforeScroll` (283) and `TDataSet.AfterScroll` (284) events. If the dataset is located on the last known record (`EOF` (273) is true), then no action is performed, and the events are not triggered.

Errors: Calling this method on a closed dataset will result in an `EDatabaseError` (220) exception.

See also: `TDataSet.MoveBy` (267), `TDataSet.Prior` (269), `TDataSet.Last` (266), `TDataSet.BeforeScroll` (283), `TDataSet.AfterScroll` (284), `TDataSet.EOF` (273)

**10.19.48 TDataSet.Open**

Synopsis: Activate the dataset: Fetch data into memory.

Declaration: `procedure Open`

Visibility: `public`

Description: `Open` must be used to make the `TDataSet` Active. It does nothing if the dataset is already active. `Open` initialises the `TDataSet` and brings the dataset in a browsable state:

Effectively the following happens:

1. The `BeforeOpen` event is triggered.
2. The descendents `InternalOpen` method is called to actually fetch data and initialize field-defs and field instances.
3. `BOF` (271) is set to `True`
4. Internal buffers are allocated and filled with data
5. If the dataset is empty, `EOF` (273) is set to `true`
6. `State` (276) is set to `dsBrowse`
7. The `AfterOpen` (280) event is triggered

Errors: If the descendent class cannot fetch the data, or the data does not match the field definitions present in the dataset, then an exception will be raised.

See also: `TDataSet.Active` (278), `TDataSet.State` (276), `TDataSet.BOF` (271), `TDataSet.EOF` (273), `TDataSet.BeforeOpen` (279), `TDataSet.AfterOpen` (280)

**10.19.49 TDataSet.Post**

Synopsis: Post pending edits to the database.

Declaration: `procedure Post; Virtual`

Visibility: `public`

Description: `Post` attempts to save pending edits when the dataset is in one of the edit modes: that is, after a `Insert` (265), `Append` (256) or `TDataSet.Edit` (260) operation. The changes will be committed to memory - and usually immediatly to the underlying database as well. Prior to saving the data to memory, it will check some constraints: in `TDataSet`, the presence of a value for all required fields is checked. if for a required field no value is present, an exception will be raised. A call to `Post` results in the triggering of the `BeforePost` (282), `AfterPost` (282) events. After the call to `Post`, the `State` (276) of the dataset is again `dsBrowse`, i.e. the dataset is again in browse mode.

Errors: Invoking the `post` method when the dataset is not in one of the editing modes (`dsEditModes` (209)) will result in an `EdatabaseError` (220) exception. If an exception occurs during the save operation, the `OnPostError` (287) event is triggered to handle the error.

See also: `TDataSet.Insert` (265), `Tdataset.Append` (256), `TDataSet.Edit` (260), `Tdataset.OnPostError` (287), `TDataSet.BeforePost` (282), `TDataSet.AfterPost` (282), `TDataSet.State` (276)

**10.19.50 TDataSet.Prior**

Synopsis: Go to the previous record

Declaration: `procedure Prior`

Visibility: `public`

Description: `Prior` moves the cursor to the previous record. It is equivalent to a `MoveBy(-1)` operation. Calling this method triggers the `TDataSet.BeforeScroll` (283) and `TDataSet.AfterScroll` (284) events. If the dataset is located on the first record, (`BOF` (271) is true) then no action is performed, and the events are not triggered.

Errors: Calling this method on a closed dataset will result in an `EDatabaseError` (220) exception.

See also: `TDataSet.MoveBy` (267), `TDataSet.Next` (267), `TDataSet.First` (263), `TDataSet.BeforeScroll` (283), `TDataSet.AfterScroll` (284), `TDataSet.BOF` (271)

**10.19.51 TDataSet.Refresh**

Synopsis: Refresh the records in the dataset

Declaration: `procedure Refresh`

Visibility: `public`

Description: `Refresh` posts any pending edits, and refetches the data in the dataset from the underlying database, and attempts to reposition the cursor on the same record as it was. This operation is not supported by all datasets, and should be used with care. The repositioning may not always succeed, in which case the cursor will be positioned on the first record in the dataset. This is in particular true for unidirectional datasets. Calling `Refresh` results in the triggering of the `BeforeRefresh` (284) and `AfterRefresh` (284) events.

Errors: Refreshing may fail if the underlying dataset descendent does not support it.

See also: `TDataSet.Close` (258), `TDataSet.Open` (268), `TDataSet.BeforeRefresh` (284), `TDataSet.AfterRefresh` (284)

**10.19.52 TDataSet.Resync**

Synopsis: Resynchronize the data buffer

Declaration: `procedure Resync (Mode: TResyncMode); Virtual`

Visibility: `public`

Description: `Resync` refetches the records around the cursor position. It should not be used by application code, instead `TDataSet.Refresh` (269) should be used. The `Resync` parameter indicates how the buffers should be refreshed.

See also: `TDataSet.Refresh` (269)

### 10.19.53 TDataSet.SetFields

Synopsis: Set a number of field values at once

Declaration: `procedure SetFields(const Values: Array of const)`

Visibility: public

Description: `SetFields` sets the values of the fields with the corresponding values in the array. It starts with the first field in the `TDataSet.Fields` (277) property, and works its way down the array.

Errors: If the dataset is not in edit mode, then an `EDatabaseError` (220) exception will be raised. If there are more values than fields, an `EListError` exception will be raised.

See also: `TDataSet.Fields` (277)

### 10.19.54 TDataSet.Translate

Synopsis: Transliterate a buffer

Declaration: `function Translate(Src: PChar; Dest: PChar; ToOem: Boolean) : Integer  
; Virtual`

Visibility: public

Description: `Translate` is called for all string fields for which the `TStringField.Transliterate` (374) property is set to `True`. The `toOEM` parameter is set to `True` if the transliteration must happen from the used codepage to the codepage used for storage, and if it is set to `False` then the transliteration must happen from the native codepage to the storage codepage. This call must be overridden by descendants of `TDataSet` to provide the necessary transliteration: `TDataSet` just copies the contents of the `Src` buffer to the `Dest` buffer. The result must be the number of bytes copied to the destination buffer.

Errors: No checks are performed on the buffers.

See also: `TStringField.Transliterate` (374)

### 10.19.55 TDataSet.UpdateCursorPos

Synopsis: Update cursor position

Declaration: `procedure UpdateCursorPos`

Visibility: public

Description: `UpdateCursorPos` should not be used in application code. It is used to ensure that the logical cursor position is the correct (physical) position.

See also: `TDataSet.Refresh` (269)

### 10.19.56 TDataSet.UpdateRecord

Synopsis: Indicate that the record contents have changed

Declaration: `procedure UpdateRecord`

Visibility: public



**Description:** `UpdateRecord` notifies controls that the contents of the current record have changed. It triggers the event. This should never be called by application code, and is intended only for descendents of `TDataset`.

See also: `TDataset.OnUpdateRecord` ([250](#))

### 10.19.57 `TDataset.UpdateStatus`

**Synopsis:** Get the update status for the current record

**Declaration:** `function UpdateStatus : TUpdateStatus; Virtual`

**Visibility:** public

**Description:** `UpdateStatus` always returns `usUnModified` in the `TDataset` implementation. Descendent classes should override this method to indicate the status for the current record in case they support cached updates: the function should return the status of the current record: has the record been locally inserted, modified or deleted, or none of these. `UpdateStatus` is not used in `TDataset` itself, but is provided so applications have a unique API to work with datasets that have support for cached updates.

### 10.19.58 `TDataset.BOF`

**Synopsis:** Is the cursor at the beginning of the data (on the first record)

**Declaration:** `Property BOF : Boolean`

**Visibility:** public

**Access:** Read

**Description:** `BOF` returns `True` if the first record is the first record in the dataset, `False` otherwise. It will always be `True` if the dataset is just opened, or after a call to `TDataset.First` ([263](#)). As soon as `TDataset.Next` ([267](#)) is called, `BOF` will no longer be true.

See also: `TDataset.EOF` ([273](#)), `TDataset.Next` ([267](#)), `TDataset.First` ([263](#))

### 10.19.59 `TDataset.Bookmark`

**Synopsis:** Get or set the current cursor position

**Declaration:** `Property Bookmark : TBookmarkStr`

**Visibility:** public

**Access:** Read, Write

**Description:** `Bookmark` can be read to obtain a bookmark to the current position in the dataset. The obtained value can be used to return to current position at a later stage. Writing the `Bookmark` property with a value previously obtained like this, will reposition the dataset on the same position as it was when the property was read.

This is often used when scanning all records, like this:

```

Var
  B : TBookmarkStr;

begin
  With MyDataset do
    begin
      B:=Bookmark;
      DisableControls;
    try
      First;
      While Not EOF do
        begin
          DoSomething;
        Next;
      end;
    finally
      EnableControls;
      Bookmark:=B;
    end;
  end;
end;

```

At the end of this code, the dataset will be positioned on the same record as when the code was started. The `TDataset.DisableControls` (260) and `TDataset.EnableControls` (261) calls prevent the controls from receiving update notifications as the dataset scrolls through the records, thus reducing flicker on the screen.

Note that bookmarks become invalid as soon as the dataset closes. A call to refresh may also destroy the bookmarks.

See also: `TDataset.DisableControls` (260), `TDataset.EnableControls` (261)

### 10.19.60 `TDataset.CanModify`

Synopsis: Can the data in the dataset be modified

Declaration: Property `CanModify` : Boolean

Visibility: public

Access: Read

Description: `CanModify` indicates whether the dataset allows editing. Unidirectional datasets do not allow editing. Descendent datasets can impose additional conditions under which the data can not be modified (read-only datasets, for instance). If the `CanModify` property is `False`, then the edit, append or insert methods will fail.

See also: `TDataset.Insert` (265), `TDataset.Append` (256), `TDataset.Delete` (259), `TDataset.Edit` (260)

### 10.19.61 `TDataset.DataSource`

Synopsis: Datasource this dataset is connected to.

Declaration: Property `DataSource` : `TDatasource`

Visibility: public

Access: Read

**Description:** `Datasource` is the datasource this dataset is connected to, and from which it can get values for parameters. In `TDataSet`, the `Datasource` property is not used, and is always `Nil`. It is up to descendent classes that actually support a datasource to implement getter and setter routines for the `Datasource` property.

See also: `TDatasource` (287)

### 10.19.62 TDataSet.DefaultFields

**Synopsis:** Is the dataset using persistent fields or not.

**Declaration:** Property `DefaultFields` : Boolean

**Visibility:** public

**Access:** Read

**Description:** `DefaultFields` is `True` if the fields were generated dynamically when the dataset was opened. If it is `False` then the field instances are persistent, i.e. they were created at design time with the fields editor. If `DefaultFields` is `True`, then for each item in the `TDataSet.FieldDefs` (274) property, a field instance is created. These field instances are freed again when the dataset is closed. If `DefaultFields` is `False`, then there may be less field instances than there are items in the `FieldDefs` property. This can be the case for instance when opening a DBF file at runtime which has more fields than the file used at design time.

See also: `TDataSet.FieldDefs` (274), `TDataSet.Fields` (277), `TField` (298)

### 10.19.63 TDataSet.EOF

**Synopsis:** Indicates whether the last record has been reached.

**Declaration:** Property `EOF` : Boolean

**Visibility:** public

**Access:** Read

**Description:** `EOF` is `True` if the cursor is on the last record in the dataset, and no more records are available. It is also `True` for an empty dataset. The `EOF` property will be set to `True` in the following cases:

1. The `TDataSet.Last` (266) method is called.
2. The record is on the last record, and the `TDataSet.Next` (267) method is called.
3. The dataset is empty when opened

In all other cases, `EOF` is `False`. Note that when the cursor is on the last-but-one record, and `Next` is called, `EOF` will not yet be `True`. It is only when the cursor is on the last record and `Next` is called, that `EOF` will become `True`. This means that the following loop will stop after the last record was visited:

```
With MyDataset do
  While not EOF do
    begin
      DoSomething;
      Next;
    end;
```

See also: `TDataSet.BOF` (271), `TDataSet.Next` (267), `TDataSet.Last` (266), `TDataSet.IsEmpty` (265)

#### 10.19.64 TDataSet.FieldCount

Synopsis: Number of fields

Declaration: `Property FieldCount : LongInt`

Visibility: `public`

Access: `Read`

Description: `FieldCount` is the same as `Fields.Count` (333), i.e. the number of fields. For a dataset with persistent fields (when `DefaultFields` (273) is `False`) then this number will be always the same every time the dataset is opened. For a dataset with dynamically created fields, the number of fields may be different each time the dataset is opened.

See also: `TFields` (329)

#### 10.19.65 TDataSet.FieldDefs

Synopsis: Definitions of available fields in the underlying database

Declaration: `Property FieldDefs : TFieldDefs`

Visibility: `public`

Access: `Read,Write`

Description: `FieldDefs` is filled by the `TDataset` descendent when the dataset is opened. It represents the fields as they are returned by the particular database when the data is initially fetched from the engine. If the dataset uses dynamically created fields (when `DefaultFields` (273) is `True`), then for each item in this list, a field instance will be created with default properties available in the field definition. If the dataset uses persistent fields, then the fields in the field list will be checked against the items in the `FieldDefs` property. If no matching item is found for a persistent field, then an exception will be raised. Items that exist in the `fielddefs` property but for which there is no matching field instance, are ignored.

See also: `TDataset.Open` (268), `TDataset.DefaultFields` (273), `TDataset.Fields` (277)

#### 10.19.66 TDataSet.Found

Synopsis: Check success of one of the `Find` methods

Declaration: `Property Found : Boolean`

Visibility: `public`

Access: `Read`

Description: `Found` is `True` if the last of one of the `TDataset.FindFirst` (262), `TDataset.FindLast` (262), `TDataset.FindNext` (262) or `TDataset.FindPrior` (262) operations was succesful.

See also: `TDataset.FindFirst` (262), `TDataset.FindLast` (262), `TDataset.FindNext` (262), `TDataset.FindPrior` (262)

**10.19.67 TDataSet.Modified**

Synopsis: Was the current record modified ?

Declaration: `Property Modified : Boolean`

Visibility: `public`

Access: `Read, Write`

Description: `Modified` is `True` if the current record was modified after a call to `Tdataset.Edit` (260) or `Tdataset.Insert` (265). It becomes `True` if a value was written to one of the fields of the dataset.

See also: `Tdataset.Edit` (260), `TDataset.Insert` (265), `TDataset.Append` (256), `TDataset.Cancel` (257), `TDataset.Post` (268)

**10.19.68 TDataSet.IsUniDirectional**

Synopsis: Is the dataset unidirectional (i.e. forward scrolling only)

Declaration: `Property IsUniDirectional : Boolean`

Visibility: `public`

Access: `Read`

Description: `IsUniDirectional` is `True` if the dataset is unidirectional. By default it is `False`, i.e. scrolling backwards is allowed. If the dataset is unidirectional, then any attempt to scroll backwards (using one of `TDataset.Prior` (269) or `TDataset.Next` (267)), random positioning of the cursor, editing or filtering will result in an `EDatabaseError` (220). Unidirectional datasets are also not suitable for display in a grid, as they have only 1 record in memory at any given time: they are only useful for performing an action on all records:

```
With MyDataset do
  While not EOF do
    begin
      DoSomething;
      Next;
    end;
```

See also: `TDataset.Prior` (269), `TDataset.Next` (267)

**10.19.69 TDataSet.RecordCount**

Synopsis: Number of records in the dataset

Declaration: `Property RecordCount : LongInt`

Visibility: `public`

Access: `Read`

Description: `RecordCount` is the number of records in the dataset. This number is not necessarily equal to the number of records returned by a query. For optimization purposes, a `TDataset` descendent may choose not to fetch all records from the database when the dataset is opened. If this is the case, then the `RecordCount` will only reflect the number of records that have actually been fetched at the current time, and therefor the value will change as more records are fetched from the database.

Only when `Last` has been called (and the dataset has been forced to fetch all records returned by the database), will the value of `RecordCount` be equal to the number of records returned by the query.

In general, datasets based on in-memory data or flat files, will return the correct number of records in `RecordCount`.

See also: `TDataset.RecNo` ([276](#))

### 10.19.70 `TDataset.RecNo`

Synopsis: Current record number

Declaration: Property `RecNo` : `LongInt`

Visibility: public

Access: Read,Write

Description: `RecNo` returns the current position in the dataset. It can be written to set the cursor to the indicated position. This property must be implemented by `TDataset` descendents, for `TDataset` the property always returns -1.

This property should not be used if exact positioning is required. it is inherently unreliable.

See also: `TDataset.RecordCount` ([275](#))

### 10.19.71 `TDataset.RecordSize`

Synopsis: Size of the record in memory

Declaration: Property `RecordSize` : `Word`

Visibility: public

Access: Read

Description: `RecordSize` is the total size of the memory buffer used for the records. This property returns always 0 in the `TDataset` implementation. Descendent classes should implement this property. Note that this property does not necessarily reflect the actual data size for the records. that may be more or less, depending on how the `TDataset` descendent manages it's data.

See also: `TField.Datasize` ([310](#)), `TDataset.RecordCount` ([275](#)), `TDataset.RecNo` ([276](#))

### 10.19.72 `TDataset.State`

Synopsis: Current operational state of the dataset

Declaration: Property `State` : `TDatasetState`

Visibility: public

Access: Read

Description: `State` determines the current operational state of the dataset. During it's lifetime, the dataset is in one of many states, depending on which operation is currently in progress:

- If a dataset is closed, the `State` is `dsInactive`.
- As soon as it is opened, it is in `dsBrowse` mode, and remains in this state while changing the cursor position.

- If the `Edit` or `Insert` or `Append` methods is called, the State changes to `dsEdit` or `dsInsert`, respectively.
- As soon as edits have been posted or cancelled, the state is again `dsBrowse`.
- Closing the dataset sets the state again to `dsInactive`.

There are some other states, mainly connected to internal operations, but which can become visible in some of the dataset's events.

See also: `TDataset.Active` (278), `TDataset.Edit` (260), `TDataset.Insert` (265), `TDataset.Append` (256), `TDataset.Post` (268), `TDataset.Cancel` (257)

### 10.19.73 TDataSet.Fields

Synopsis: Indexed access to the fields of the dataset.

Declaration: `Property Fields : Tfields`

Visibility: `public`

Access: `Read`

Description: `Fields` provides access to the fields of the dataset. It is of type `TFields` (329) and therefore gives indexed access to the fields, but also allows other operations such as searching for fields based on their names or getting a list of fieldnames.

See also: `TFieldDefs` (326), `TField` (298)

### 10.19.74 TDataSet.FieldValues

Synopsis: Acces to field values based on the field names.

Declaration: `Property FieldValues[fieldname: String]: Variant; default`

Visibility: `public`

Access: `Read,Write`

Description: `FieldValues` provides array-like access to the values of the fields, based on the names of the fields. The value is read or written as a variant type. It is equivalent to the following:

```
FieldByName(FieldName).AsVariant
```

It can be read as well as written.

See also: `FieldByname` (208)

### 10.19.75 TDataSet.Filter

Synopsis: Filter to apply to the data in memory.

Declaration: `Property Filter : String`

Visibility: `public`

Access: `Read,Write`

**Description:** `Filter` is not implemented by `TDataset`. It is up to descendent classes to implement actual filtering: the filtering happens on in-memory data, and is not applied on the database level. (in particular: setting the filter property will in no way influence the `WHERE` clause of an SQL-based dataset).

In general, the `filter` property accepts a SQL-like syntax usually encountered in the `WHERE` clause of an SQL `SELECT` statement.

The filter is only applied if the `Filtered` property is set to `True`. If the `Filtered` property is `False`, the `Filter` property is ignored.

See also: `TDataset.Filtered` (278), `TDataset.FilterOptions` (278)

### 10.19.76 `TDataset.Filtered`

**Synopsis:** Is the filter active or not.

**Declaration:** `Property Filtered : Boolean`

**Visibility:** `public`

**Access:** `Read,Write`

**Description:** `Filtered` determines whether the filter condition in `TDataset.Filter` (277) is applied or not. The filter is only applied if the `Filtered` property is set to `True`. If the `Filtered` property is `False`, the `Filter` property is ignored.

See also: `TDataset.Filter` (277), `TDataset.FilterOptions` (278)

### 10.19.77 `TDataset.FilterOptions`

**Synopsis:** Options to apply when filtering

**Declaration:** `Property FilterOptions : TFilterOptions`

**Visibility:** `public`

**Access:** `Read,Write`

**Description:** `FilterOptions` determines what options should be taken into account when applying the filter in `TDataset.Filter` (277), such as case-sensitivity or whether to treat an asterisk as a wildcard: By default, an asterisk (\*) at the end of a literal string in the filter expression is treated as a wildcard. When `FilterOptions` does not include `foNoPartialCompare`, strings that have an asterisk at the end, indicate a partial string match. In that case, the asterisk matches any number of characters. If `foNoPartialCompare` is included in the options, the asterisk is regarded as a regular character.

See also: `TDataset.Filter` (277), `TDataset.FilterOptions` (278)

### 10.19.78 `TDataset.Active`

**Synopsis:** Is the dataset open or closed.

**Declaration:** `Property Active : Boolean`

**Visibility:** `public`

**Access:** `Read,Write`



**Description:** `Active` is `True` if the dataset is open, and `False` if it is closed (`TDataset.State` (276) is then `dsInactive`). Setting the `Active` property to `True` is equivalent to calling `TDataset.Open` (268), setting it to `False` is equivalent to calling `TDataset.Close` (258)

See also: `TDataset.State` (276), `TDataset.Open` (268), `TDataset.Close` (258)

### 10.19.79 `TDataset.AutoCalcFields`

**Synopsis:** How often should the value of calculated fields be calculated

**Declaration:** `Property AutoCalcFields : Boolean`

**Visibility:** `public`

**Access:** `Read, Write`

**Description:** `AutoCalcFields` is by default `true`, meaning that the values of calculated fields will be computed in the following cases:

- When the dataset is opened
- When the dataset is put in edit mode
- When a data field changed

When `AutoCalcFields` is `False`, then the calculated fields are called whenever

- The dataset is opened
- The dataset is put in edit mode

Both proper calculated fields and lookup fields are computed. Calculated fields are computed through the `TDataset.OnCalcFields` (285) event.

See also: `TField.FieldKind` (316), `TDataset.OnCalcFields` (285)

### 10.19.80 `TDataset.BeforeOpen`

**Synopsis:** Event triggered before the dataset is opened.

**Declaration:** `Property BeforeOpen : TDataSetNotifyEvent`

**Visibility:** `public`

**Access:** `Read, Write`

**Description:** `BeforeOpen` is triggered before the dataset is opened. No actions have been performed yet when this event is called, and the dataset is still in `dsInactive` state. It can be used to set parameters and options that influence the opening process. If an exception is raised during the event handler, the dataset remains closed.

See also: `TDataset.AfterOpen` (280), `TDataset.State` (276)

### 10.19.81 TDataSet.AfterOpen

Synopsis: Event triggered after the dataset is opened.

Declaration: Property AfterOpen : TDataSetNotifyEvent

Visibility: public

Access: Read,Write

Description: AfterOpen is triggered after the dataset is opened. The dataset has fetched its data and is in dsBrowse state when this event is triggered. If the dataset is not empty, then a TDataSet.AfterScroll (284) event will be triggered immediately after the AfterOpen event. If an exception is raised during the event handler, the dataset remains open, but the AfterScroll event will not be triggered.

See also: TDataSet.AfterOpen (280), TDataSet.State (276), TDataSet.AfterScroll (284)

### 10.19.82 TDataSet.BeforeClose

Synopsis: Event triggered before the dataset is closed.

Declaration: Property BeforeClose : TDataSetNotifyEvent

Visibility: public

Access: Read,Write

Description: BeforeClose is triggered before the dataset is closed. No actions have been performed yet when this event is called, and the dataset is still in dsBrowse state or one of the editing states. It can be used to prevent closing of the dataset, for instance if there are pending changes not yet committed to the database. If an exception is raised during the event handler, the dataset remains opened.

See also: TDataSet.AfterClose (280), TDataSet.State (276)

### 10.19.83 TDataSet.AfterClose

Synopsis: Event triggered after the dataset is closed

Declaration: Property AfterClose : TDataSetNotifyEvent

Visibility: public

Access: Read,Write

Description: AfterOpen is triggered after the dataset is opened. The dataset has discarded its data and has cleaned up its internal memory structures. It is in dsInactive state when this event is triggered.

See also: TDataSet.BeforeClose (280), TDataSet.State (276)

### 10.19.84 TDataSet.BeforeInsert

Synopsis: Event triggered before the dataset is put in insert mode.

Declaration: Property BeforeInsert : TDataSetNotifyEvent

Visibility: public

Access: Read,Write

**Description:** `BeforeInsert` is triggered at the start of the `TDataset.Append` (256) or `TDataset.Insert` (265) methods. The dataset is still in `dsBrowse` state when this event is triggered. If an exception is raised in the `BeforeInsert` event handler, then the dataset will remain in `dsBrowse` state, and the append or insert operation is cancelled.

See also: `TDataset.AfterInsert` (281), `TDataset.Append` (256), `TDataset.Insert` (265)

### 10.19.85 `TDataset.AfterInsert`

**Synopsis:** Event triggered after the dataset is put in insert mode.

**Declaration:** `Property AfterInsert : TDatasetNotifyEvent`

**Visibility:** public

**Access:** Read,Write

**Description:** `AfterInsert` is triggered after the dataset has finished putting the dataset in `dsInsert` state and it has initialized the new record buffer. This event can be used e.g. to set initial field values. After the `AfterInsert` event, the `TDataset.AfterScroll` (284) event is still triggered. Raising an exception in the `AfterInsert` event, will prevent the `AfterScroll` event from being triggered, but does not undo the insert or append operation.

See also: `TDataset.BeforeInsert` (280), `TDataset.AfterScroll` (284), `TDataset.Append` (256), `TDataset.Insert` (265)

### 10.19.86 `TDataset.BeforeEdit`

**Synopsis:** Event triggered before the dataset is put in edit mode.

**Declaration:** `Property BeforeEdit : TDatasetNotifyEvent`

**Visibility:** public

**Access:** Read,Write

**Description:** `BeforeEdit` is triggered at the start of the `TDataset.Edit` (260) method. The dataset is still in `dsBrowse` state when this event is triggered. If an exception is raised in the `BeforeEdit` event handler, then the dataset will remain in `dsBrowse` state, and the edit operation is cancelled.

See also: `TDataset.AfterEdit` (281), `TDataset.Edit` (260), `TDataset.State` (276)

### 10.19.87 `TDataset.AfterEdit`

**Synopsis:** Event triggered after the dataset is put in edit mode.

**Declaration:** `Property AfterEdit : TDatasetNotifyEvent`

**Visibility:** public

**Access:** Read,Write

**Description:** `AfterEdit` is triggered after the dataset has finished putting the dataset in `dsEdit` state and it has initialized the edit buffer for the record. Raising an exception in the `AfterEdit` event does not undo the edit operation.

See also: `TDataset.BeforeEdit` (281), `TDataset.Edit` (260), `TDataset.State` (276)

### 10.19.88 TDataSet.BeforePost

Synopsis: Event called before changes are posted to the underlying database

Declaration: `Property BeforePost : TDataSetNotifyEvent`

Visibility: `public`

Access: `Read,Write`

Description: `BeforePost` is triggered at the start of the `TDataSet.Post` (268) method, when the dataset is still in one of the edit states (`dsEdit,dsInsert`). If the dataset was not in an edit state when `Post` is called, the `BeforePost` event is not triggered. This event can be used to supply values for required fields that have no value yet (the `Post` operation performs the check on required fields only after this event), or it can be used to abort the post operation: if an exception is raised during the `BeforePost` operation, the posting operation is cancelled, and the dataset remains in the editing state it was in before the post operation.

See also: `TDataSet.post` (268), `TDataSet.AfterPost` (282), `TDataSet.State` (276)

### 10.19.89 TDataSet.AfterPost

Synopsis: Event called after changes have been posted to the underlying database

Declaration: `Property AfterPost : TDataSetNotifyEvent`

Visibility: `public`

Access: `Read,Write`

Description: `AfterPost` is triggered when the `TDataSet.Post` (268) operation was successfully completed, and the dataset is again in `dsBrowse` state. If an error occurred during the post operation, then the `AfterPost` event is not called, but the `TDataSet.OnPostError` (287) event is triggered instead.

See also: `TDataSet.BeforePost` (282), `TDataSet.Post` (268), `TDataSet.State` (276), `TDataSet.OnPostError` (287)

### 10.19.90 TDataSet.BeforeCancel

Synopsis: Event triggered before a Cancel operation.

Declaration: `Property BeforeCancel : TDataSetNotifyEvent`

Visibility: `public`

Access: `Read,Write`

Description: `BeforeCancel` is triggered at the start of the `TDataSet.Cancel` (257) operation, when the state is still one of the editing states (`dsEdit,dsInsert`). The event handler can be used to abort the cancel operation: if an exception is raised during the event handler, then the cancel operation stops. If the dataset was not in one of the editing states when the `Cancel` method was called, then the event is not triggered.

See also: `TDataSet.AfterCancel` (283), `TDataSet.Cancel` (257), `TDataSet.State` (276)

### 10.19.91 TDataSet.AfterCancel

Synopsis: Event triggered after a Cancel operation.

Declaration: `Property AfterCancel : TDataSetNotifyEvent`

Visibility: public

Access: Read,Write

Description: `AfterCancel` is triggered when the `TDataSet.Cancel` (257) operation was successfully completed, and the dataset is again in `dsBrowse` state.

See also: `TDataSet.BeforeCancel` (282), `TDataSet.Cancel` (257), `TDataSet.State` (276)

### 10.19.92 TDataSet.BeforeDelete

Synopsis: Event triggered before a Delete operation.

Declaration: `Property BeforeDelete : TDataSetNotifyEvent`

Visibility: public

Access: Read,Write

Description: `BeforeDelete` is triggered at the start of the `TDataSet.Delete` (259) operation, when the dataset is still in `dsBrowse` state. The event handler can be used to abort the delete operation: if an exception is raised during the event handler, then the delete operation stops. The event is followed by a `TDataSet.BeforeScroll` (283) event. If the dataset was in insert mode when the `Delete` method was called, then the event will not be called, as `TDataSet.Cancel` (257) is called instead.

See also: `TDataSet.AfterDelete` (283), `TDataSet.Delete` (259), `TDataSet.BeforeScroll` (283), `TDataSet.Cancel` (257), `TDataSet.State` (276)

### 10.19.93 TDataSet.AfterDelete

Synopsis:

Declaration: `Property AfterDelete : TDataSetNotifyEvent`

Visibility: public

Access: Read,Write

Description: `AfterDelete` is triggered after the successful completion of the `TDataSet.Delete` (259) operation, when the dataset is again in `dsBrowse` state. The event is followed by a `TDataSet.AfterScroll` (284) event.

See also: `TDataSet.BeforeDelete` (283), `TDataSet.Delete` (259), `TDataSet.AfterScroll` (284), `TDataSet.State` (276)

### 10.19.94 TDataSet.BeforeScroll

Synopsis: Event triggered before the cursor changes position.

Declaration: `Property BeforeScroll : TDataSetNotifyEvent`

Visibility: public

Access: Read,Write

**Description:** `BeforeScroll` is triggered before the cursor changes position. This can happen with one of the navigation methods: `TDataset.Next` (267), `TDataset.Prior` (269), `TDataset.First` (263), `TDataset.Last` (266), but also with two of the editing operations: `TDataset.Insert` (265) and `TDataset.Delete` (259). Raising an exception in this event handler aborts the operation in progress.

See also: `TDataset.AfterScroll` (284), `TDataset.Next` (267), `TDataset.Prior` (269), `TDataset.First` (263), `TDataset.Last` (266), `TDataset.Insert` (265), `TDataset.Delete` (259)

### 10.19.95 TDataSet.AfterScroll

**Synopsis:** Event triggered after the cursor has changed position.

**Declaration:** `Property AfterScroll : TDataSetNotifyEvent`

Visibility: public

Access: Read,Write

**Description:** `AfterScroll` is triggered after the cursor has changed position. This can happen with one of the navigation methods: `TDataset.Next` (267), `TDataset.Prior` (269), `TDataset.First` (263), `TDataset.Last` (266), but also with two of the editing operations: `TDataset.Insert` (265) and `TDataset.Delete` (259) and after the dataset was opened. It is suitable for displaying status information or showing a value that needs to be calculated for each record.

See also: `TDataset.AfterScroll` (284), `TDataset.Next` (267), `TDataset.Prior` (269), `TDataset.First` (263), `TDataset.Last` (266), `TDataset.Insert` (265), `TDataset.Delete` (259), `TDataset.Open` (268)

### 10.19.96 TDataSet.BeforeRefresh

**Synopsis:** Event triggered before the data is refreshed.

**Declaration:** `Property BeforeRefresh : TDataSetNotifyEvent`

Visibility: public

Access: Read,Write

**Description:** `BeforeRefresh` is triggered at the start of the `TDataset.Refresh` (269) method, after the dataset has been put in browse mode. If the dataset cannot be put in browse mode, the `BeforeRefresh` method will not be triggered. If an exception is raised during the `BeforeRefresh` method, then the refresh method is cancelled and the dataset remains in the `dsBrowse` state.

See also: `TDataset.Refresh` (269), `TDataset.AfterRefresh` (284), `TDataset.State` (276)

### 10.19.97 TDataSet.AfterRefresh

**Synopsis:** Event triggered after the data has been refreshed.

**Declaration:** `Property AfterRefresh : TDataSetNotifyEvent`

Visibility: public

Access: Read,Write

**Description:** `AfterRefresh` is triggered at the end of the `TDataset.Refresh` (269) method, after the dataset has refreshed its data and is again in `dsBrowse` state. This event can be used to react on changes in data in the current record

See also: `TDataset.Refresh` (269), `TDataset.State` (276), `TDataset.BeforeRefresh` (284)

### 10.19.98 `TDataset.OnCalcFields`

**Synopsis:** Event triggered when values for calculated fields must be computed.

**Declaration:** `Property OnCalcFields : TDatasetNotifyEvent`

**Visibility:** `public`

**Access:** `Read,Write`

**Description:** `OnCalcFields` is triggered whenever the dataset needs to (re)compute the values of any calculated fields in the dataset. It is called very often, so this event should return as quickly as possible. Only the values of the calculated fields should be set, no methods of the dataset that change the data or cursor position may be called during the execution of this event handler. The frequency with which this event is called can be controlled through the `TDataset.AutoCalcFields` (279) property. Note that the value of lookup fields does not need to be calculated in this event, their value is computed automatically before this event is triggered.

See also: `TDataset.AutoCalcFields` (279), `TField.Kind` (298)

### 10.19.99 `TDataset.OnDeleteError`

**Synopsis:** Event triggered when a delete operation fails.

**Declaration:** `Property OnDeleteError : TDatasetErrorEvent`

**Visibility:** `public`

**Access:** `Read,Write`

**Description:** `OnDeleteError` is triggered when the `TDataset.Delete` (259) method fails to delete the record in the underlying database. The event handler can be used to indicate what the response to the failed delete should be. To this end, it gets the exception object passed to it (parameter `E`), and it can examine this object to return an appropriate action in the `DataAction` parameter. The following responses are supported:

**daFail**The operation should fail (an exception will be raised)

**daAbort**The operation should be aborted (edits are undone, and an `EAbort` exception is raised)

**daRetry**Retry the operation.

For more information, see also the description of the `TDatasetErrorEvent` (212) event handler type.

See also: `TDatasetErrorEvent` (212), `TDataset.Delete` (259), `TDataset.OnEditError` (286), `TDataset.OnPostError` (287)

**10.19.100 TDataSet.OnEditError**

Synopsis: Event triggered when an edit operation fails.

Declaration: Property OnEditError : TDataSetErrorEvent

Visibility: public

Access: Read,Write

Description: OnEditError is triggered when the TDataSet.Edit (260) method fails to put the dataset in edit mode because the underlying database engine reported an error. The event handler can be used to indicate what the response to the failed edit operation should be. To this end, it gets the exception object passed to it (parameter E), and it can examine this object to return an appropriate action in the DataAction parameter. The following responses are supported:

**daFail**The operation should fail (an exception will be raised)

**daAbort**The operation should be aborted (edits are undone, and an EAbort exception is raised)

**daRetry**Retry the operation.

For more information, see also the description of the TDataSetErrorEvent (212) event handler type.

See also: TDataSetErrorEvent (212), TDataSet.Edit (260), TDataSet.OnDeleteError (285), TDataSet.OnPostError (287)

**10.19.101 TDataSet.OnFilterRecord**

Synopsis: Event triggered to filter records.

Declaration: Property OnFilterRecord : TFilterRecordEvent

Visibility: public

Access: Read,Write

Description: OnFilterRecord can be used to provide event-based filtering for datasets that support it. This event is only triggered when the Tdataset.Filtered (278) property is set to True. The event handler should set the Accept parameter to True if the current record should be accepted, or to False if it should be rejected. No methods that change the state of the dataset may be used during this event, and calculated fields or lookup field values are not yet available.

See also: TDataSet.Filter (277), TDataSet.Filtered (278), TDataSet.state (276)

**10.19.102 TDataSet.OnNewRecord**

Synopsis: Event triggered when a new record is created.

Declaration: Property OnNewRecord : TDataSetNotifyEvent

Visibility: public

Access: Read,Write

Description: OnNewRecord is triggered by the TDataSet.Append (256) or TDataSet.Insert (265) methods when the buffer for the new record's data has been allocated. This event can be used to set default value for some of the fields in the dataset. If an exception is raised during this event handler, the operation is cancelled and the dataset is put again in browse mode (TDataSet.State (276) is again dsBrowse).

See also: TDataSet.Append (256), TDataSet.Insert (265), TDataSet.State (276)



### 10.19.103 TDataSet.OnPostError

Synopsis: Event triggered when a post operation fails.

Declaration: Property OnPostError : TDataSetErrorEvent

Visibility: public

Access: Read,Write

Description: OnPostError is triggered when the TDataSet.Post (268) method fails to post the changes in the dataset buffer to the underlying database, because the database engine reported an error. The event handler can be used to indicate what the response to the failed post operation should be. To this end, it gets the exception object passed to it (parameter E), and it can examine this object to return an appropriate action in the DataAction parameter. The following responses are supported:

**daFail**The operation should fail (an exception will be raised)

**daAbort**The operation should be aborted (edits are undone, and an EAbort exception is raised)

**daRetry**Retry the operation.

For more information, see also the description of the TDataSetErrorEvent (212) event handler type.

See also: TDataSetErrorEvent (212), TDataSet.Post (268), TDataSet.OnDeleteError (285), TDataSet.OnEditError (286)

## 10.20 TDataSource

### 10.20.1 Description

TDataSource is a mediating component: it handles communication between any DB-Aware component (often edit controls on a form) and a TDataSet (250) instance. Any database aware component should never communicate with a dataset directly. Instead, it should communicate with a TDataSource (287) instance. The TDataSet instance will communicate with the TDataSource instance, which will notify every component attached to it. Vice versa, any component that wishes to make changes to the dataset, will notify the TDataSource instance, which will then (if needed) notify the TDataSet instance. The datasource can be disabled, in which case all communication between the dataset and the DB-Aware components is suspended until the datasource is again enabled.

### 10.20.2 Method overview

Page	Property	Description
<a href="#">288</a>	Create	Create a new instance of TDataSource
<a href="#">288</a>	Destroy	Remove a TDataSource instance from memory
<a href="#">288</a>	Edit	Put the dataset in edit mode, if needed
<a href="#">289</a>	IsLinkedTo	Check if a dataset is linked to a certain dataset

### 10.20.3 Property overview

Page	Property	Access	Description
<a href="#">289</a>	AutoEdit	rw	Should the dataset be put in edit mode automatically
<a href="#">289</a>	DataSet	rw	Dataset this datasource is connected to
<a href="#">290</a>	Enabled	rw	Enable or disable sending of events
<a href="#">290</a>	OnDataChange	rw	Called whenever data changes in the current record
<a href="#">290</a>	OnStateChange	rw	Called whenever the state of the dataset changes
<a href="#">291</a>	OnUpdateData	rw	Called whenever the data in the dataset must be updated
<a href="#">289</a>	State	r	State of the dataset

### 10.20.4 TDataSource.Create

Synopsis: Create a new instance of TDataSource

Declaration: `constructor Create(AOwner: TComponent); Override`

Visibility: `public`

Description: `Create` initializes a new instance of `TDataSource`. It simply allocates some resources and then calls the inherited constructor.

See also: `TDataSource.Destroy` ([288](#))

### 10.20.5 TDataSource.Destroy

Synopsis: Remove a TDataSource instance from memory

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` notifies all `TDataLink` ([245](#)) instances connected to it that the dataset is no longer available, and then removes itself from the `TDataLink` instance. It then cleans up all resources and calls the inherited constructor.

See also: `TDataSource.Create` ([288](#)), `TDataLink` ([245](#))

### 10.20.6 TDataSource.Edit

Synopsis: Put the dataset in edit mode, if needed

Declaration: `procedure Edit`

Visibility: `public`

Description: `Edit` will check `AutoEdit` ([289](#)): if it is `True`, then it puts the `Dataset` ([289](#)) it is connected to in edit mode, if it was in browse mode. If `AutoEdit` is `False`, then nothing happens. Application or component code that deals with GUI development should always attempt to set a dataset in edit mode through this method instead of calling `TDataset.Edit` ([260](#)) directly.

Errors: An `EDatabaseError` ([220](#)) exception can occur if the dataset is read-only or fails to set itself in edit mode. (e.g. unidirectional datasets).

See also: `TDataSource.AutoEdit` ([289](#)), `TDataset.Edit` ([260](#)), `TDataset.State` ([276](#))

### 10.20.7 TDataSource.IsLinkedTo

Synopsis: Check if a dataset is linked to a certain dataset

Declaration: `function IsLinkedTo (ADataset: TDataSet) : Boolean`

Visibility: public

Description: `IsLinkedTo` checks if it is somehow linked to `ADataset`: it checks the `Dataset` (289) property, and returns `True` if it is the same. If not, it continues by checking any detail dataset fields that the dataset possesses (recursively). This function can be used to detect circular links in e.g. master-detail relationships.

See also: `TDataSource.Dataset` (289)

### 10.20.8 TDataSource.State

Synopsis: State of the dataset

Declaration: `Property State : TDataSetState`

Visibility: public

Access: Read

Description: `State` contains the `State` (276) of the dataset it is connected to, or `dsInactive` if the dataset property is not set or the `datasource` is not enabled. Components connected to a dataset through a `datasource` property should always check `TDataSource.State` instead of checking `TDataSet.State` (276) directly, to take into account the effect of the `Enabled` (290) property.

See also: `TDataSet.State` (276), `TDataSource.Enabled` (290)

### 10.20.9 TDataSource.AutoEdit

Synopsis: Should the dataset be put in edit mode automatically

Declaration: `Property AutoEdit : Boolean`

Visibility: published

Access: Read,Write

Description: `AutoEdit` can be set to `True` to prevent visual controls from putting the dataset in edit mode. Visual controls use the `TDataSource.Edit` (288) method to attempt to put the dataset in edit mode as soon as the user changes something. If `AutoEdit` is set to `False` then the `Edit` method does nothing. The effect is that the user must explicitly set the dataset in edit mode (by clicking some button or some other action) before the fields can be edited.

See also: `TDataSource.Edit` (288), `TDataSet.Edit` (260)

### 10.20.10 TDataSource.DataSet

Synopsis: Dataset this datasource is connected to

Declaration: `Property DataSet : TDataSet`

Visibility: published

Access: Read,Write

**Description:** `Dataset` must be set by the application programmer to the `TDataset` (250) instance for which this datasource is handling events. Setting it to `Nil` will disable all controls that are connected to this datasource instance. Once it is set and the datasource is enabled, the datasource will start sending data events to the controls or components connected to it.

See also: `TDataset` (250), `TDatasource.Enabled` (290)

### 10.20.11 `TDatasource.Enabled`

**Synopsis:** Enable or disable sending of events

**Declaration:** `Property Enabled : Boolean`

**Visibility:** published

**Access:** Read,Write

**Description:** `Enabled` is by default set to `True`: the datasource instance communicates events from the dataset to components connected to the datasource, and vice versa: components can interact with the dataset. If the `Enabled` property is set to `False` then no events are communicated to connected components: it is as if the dataset property was set to `Nil`. Reversely, the components cannot interact with the dataset if the `Enabled` property is set to `False`.

See also: `TDataset` (250), `TDatasource.Dataset` (289), `TDatasource.AutoEdit` (289)

### 10.20.12 `TDatasource.OnStateChange`

**Synopsis:** Called whenever the state of the dataset changes

**Declaration:** `Property OnStateChange : TNotifyEvent`

**Visibility:** published

**Access:** Read,Write

**Description:** `OnStateChange` is called whenever the `TDataset.State` (276) property changes, and the datasource is enabled. It can be used in application code to react to state changes: enabling or disabling non-DB-Aware controls, setting empty values etc.

See also: `TDatasource.OnUpdateData` (291), `TDatasource.OnStateChange` (290), `TDataset.State` (276), `TDatasource.Enabled` (290)

### 10.20.13 `TDatasource.OnDataChange`

**Synopsis:** Called whenever data changes in the current record

**Declaration:** `Property OnDataChange : TDataChangeEvent`

**Visibility:** published

**Access:** Read,Write

**Description:** `OnDataChange` is called whenever a field value changes: if the `Field` parameter is set, a single field value changed. If the `Field` parameter is `Nil`, then the whole record changed: when the dataset is opened, when the user scrolls to a new record. This event handler can be set to react to data changes: to update the contents of non-DB-aware controls for instance. The event is not called when the datasource is not enabled.

See also: `TDatasource.OnUpdateData` (291), `TDatasource.OnStateChange` (290), `TDataset.AfterScroll` (284), `TField.OnChange` (321), `TDatasource.Enabled` (290)

### 10.20.14 TDataSource.OnUpdateData

**Synopsis:** Called whenever the data in the dataset must be updated

**Declaration:** `Property OnUpdateData : TNotifyEvent`

**Visibility:** published

**Access:** Read, Write

**Description:** `OnUpdateData` is called whenever the dataset needs the latest data from the controls: usually just before a `TDataset.Post` (268) operation. It can be used to copy data from non-db-aware controls to the dataset just before the dataset is posting the changes to the underlying database.

See also: `TDatasource.OnDataChange` (290), `TDatasource.OnStateChange` (290), `TDataset.Post` (268)

## 10.21 TDateField

### 10.21.1 Description

`TDateField` is the class used when a dataset must manage data of type date. (`TField.DataType` (310) equals `ftDate`). It initializes some of the properties of the `TField` (298) class to be able to work with date fields.

It should never be necessary to create an instance of `TDateField` manually, a field of this class will be instantiated automatically for each date field when a dataset is opened.

### 10.21.2 Method overview

Page	Property	Description
291	Create	Create a new instance of a <code>TDateField</code> class.

### 10.21.3 TDateField.Create

**Synopsis:** Create a new instance of a `TDateField` class.

**Declaration:** `constructor Create(AOwner: TComponent); Override`

**Visibility:** public

**Description:** `Create` initializes a new instance of the `TDateField` class. It calls the inherited destructor, and then sets some `TField` (298) properties to configure the instance for working with date values.

See also: `TField` (298)

## 10.22 TDateTimeField

### 10.22.1 Description

`TDateTimeField` is the class used when a dataset must manage data of type datetime. (`TField.DataType` (310) equals `ftDateTime`). It also serves as base class for the `TDateField` (291) or `TTimeField` (375) classes. It overrides some of the properties and methods of the `TField` (298) class to be able to work with date/time fields.

It should never be necessary to create an instance of `TDateTimeField` manually, a field of this class will be instantiated automatically for each datetime field when a dataset is opened.

**10.22.2 Method overview**

Page	Property	Description
<a href="#">292</a>	Create	Create a new instance of a <code>TDateTimeField</code> class.

**10.22.3 Property overview**

Page	Property	Access	Description
<a href="#">292</a>	DisplayFormat	rw	Formatting string for textual representation of the field
<a href="#">292</a>	Value	rw	Contents of the field as a <code>TDateTime</code> value

**10.22.4 TDateTimeField.Create**

Synopsis: Create a new instance of a `TDateTimeField` class.

Declaration: `constructor Create(AOwner: TComponent); Override`

Visibility: `public`

Description: `Create` initializes a new instance of the `TDateTimeField` class. It calls the inherited destructor, and then sets some `TField` ([298](#)) properties to configure the instance for working with date/time values.

See also: `TField` ([298](#))

**10.22.5 TDateTimeField.Value**

Synopsis: Contents of the field as a `TDateTime` value

Declaration: `Property Value : TDateTime`

Visibility: `public`

Access: Read,Write

Description: `Value` is redefined from `TField.Value` ([314](#)) by `TDateTimeField` as a `TDateTime` value. It returns the same value as the `TField.AsDateTime` ([306](#)) property.

See also: `TField.AsDateTime` ([306](#)), `TField.Value` ([314](#))

**10.22.6 TDateTimeField.DisplayFormat**

Synopsis: Formatting string for textual representation of the field

Declaration: `Property DisplayFormat : String`

Visibility: `published`

Access: Read,Write

Description: `DisplayFormat` can be set to a formatting string that will then be used by the `TField.DisplayText` ([311](#)) property to format the value with the `DateTimeToString` ([??](#)) function.

See also: `#rtl.sysutils.datetimetostring` ([??](#)), `#rtl.sysutils.formatdatetime` ([??](#)), `TField.DisplayText` ([311](#))

## 10.23 TDBDataset

### 10.23.1 Description

TDBDataset is a TDataset descendent which introduces the concept of a database: a central component (TDatabase (241)) which represents a connection to a database. This central component is exposed in the TDBDataset.Database (293) property. When the database is no longer connected, or is no longer in memory, all TDBDataset instances connected to it are disabled.

TDBDataset also introduces the notion of a transaction, exposed in the Transaction (294) property.

TDBDataset is an abstract class, it should never be used directly.

Dataset component writers should descend their component from TDBDataset if they wish to introduce a central database connection component. The database connection logic will be handled automatically by TDBDataset.

### 10.23.2 Method overview

Page	Property	Description
<a href="#">293</a>	destroy	Remove the TDBDataset instance from memory.

### 10.23.3 Property overview

Page	Property	Access	Description
<a href="#">293</a>	DataBase	rw	Database this dataset is connected to
<a href="#">294</a>	Transaction	rw	Transaction in which this dataset is running.

### 10.23.4 TDBDataset.destroy

Synopsis: Remove the TDBDataset instance from memory.

Declaration: `destructor destroy; Override`

Visibility: `public`

Description: Destroy will disconnect the TDBDataset from its Database (293) and Transaction (294). After this it calls the inherited destructor.

See also: TDBDataset.Database (293), TDatabase (241)

### 10.23.5 TDBDataset.Database

Synopsis: Database this dataset is connected to

Declaration: `Property DataBase : TDataBase`

Visibility: `public`

Access: Read,Write

Description: Database should be set to the TDatabase (241) instance this dataset is connected to. It can only be set when the dataset is closed.

Descendent classes should check in the property setter whether the database instance is of the correct class.

Errors: If the property is set when the dataset is active, an EDatabaseError (220) exception will be raised.

See also: TDatabase (241), TDBDataset.Transaction (294)

### 10.23.6 TDBDataset.Transaction

Synopsis: Transaction in which this dataset is running.

Declaration: `Property Transaction : TDBTransaction`

Visibility: public

Access: Read,Write

Description: `Transaction` points to a `TDBTransaction` (294) component that represents the transaction this dataset is active in. This property should only be used for databases that support transactions.

The property can only be set when the dataset is disabled.

See also: `TDBTransaction` (294), `TDBDataset.Database` (293)

## 10.24 TDBTransaction

### 10.24.1 Description

`TDBTransaction` encapsulates a SQL transaction. It is an abstract class, and should be used by component creators that wish to encapsulate transactions in a class. The `TDBTransaction` class offers functionality to refer to a `TDatabase` (241) instance, and to keep track of `TDataset` instances which are connected to the transaction.

### 10.24.2 Method overview

Page	Property	Description
<a href="#">295</a>	<code>CloseDataSets</code>	Close all connected datasets
<a href="#">294</a>	<code>Create</code>	Transaction property
<a href="#">295</a>	<code>destroy</code>	Remove a <code>TDBTransaction</code> instance from memory.

### 10.24.3 Property overview

Page	Property	Access	Description
<a href="#">295</a>	<code>Active</code>	rw	Is the transaction active or not
<a href="#">295</a>	<code>DataBase</code>	rw	Database this transaction is connected to

### 10.24.4 TDBTransaction.Create

Synopsis: Transaction property

Declaration: `constructor Create(AOwner: TComponent); Override`

Visibility: public

Description: `Create` initializes a new `TDBTransaction` instance. It sets up the necessary resources, after having called the inherited constructor.

See also: `TDBTransaction.Destroy` (295)



### 10.24.5 TDBTransaction.destroy

Synopsis: Remove a `TDBTransaction` instance from memory.

Declaration: `destructor destroy; Override`

Visibility: `public`

Description: `Destroy` first disconnects all connected `TBDDataset` (293) instances and then cleans up the resources allocated in the `Create` (294) constructor. After that it calls the inherited destructor.

See also: `TDBTransaction.Create` (294)

### 10.24.6 TDBTransaction.CloseDataSets

Synopsis: Close all connected datasets

Declaration: `procedure CloseDataSets`

Visibility: `public`

Description: `CloseDataSets` closes all connected datasets (All `TBDDataset` (293) instances whose `Transaction` (294) property points to this `TDBTransaction` instance).

See also: `TBDDataset` (293), `TBDDataset.Transaction` (294)

### 10.24.7 TDBTransaction.Database

Synopsis: Database this transaction is connected to

Declaration: `Property DataBase : TDataBase`

Visibility: `public`

Access: `Read,Write`

Description: `Database` points to the database that this transaction is part of. This property can be set only when the transaction is not active.

Errors: Setting this property to a new value when the transaction is active will result in an `EDatabaseError` (220) exception.

See also: `TDBTransaction.Active` (295), `TDatabase` (241)

### 10.24.8 TDBTransaction.Active

Synopsis: Is the transaction active or not

Declaration: `Property Active : Boolean`

Visibility: `published`

Access: `Read,Write`

Description: `Active` is `True` if a transaction was started using `TDBTransaction.StartTransaction` (294). Reversely, setting `Active` to `True` will call `StartTransaction`, setting it to `False` will call `TDBTransaction.EndTransaction` (294).

See also: `TDBTransaction.StartTransaction` (294), `TDBTransaction.EndTransaction` (294)

## 10.25 TDefCollection

### 10.25.1 Description

`TDefCollection` is a parent class for the `TFieldDefs` (326) and `TIndexDefs` (341) collections: It holds a set of named definitions on behalf of a `TDataset` (250) component. To this end, it introduces a dataset (297) property, and a mechanism to notify the dataset of any updates in the collection. It is supposed to hold items of class `TNamedItem` (354), so the `TDefCollection.Find` (296) method can find items by named.

### 10.25.2 Method overview

Page	Property	Description
<a href="#">296</a>	<code>create</code>	Instantiate a new <code>TDefCollection</code> instance.
<a href="#">296</a>	<code>Find</code>	Find an item by name
<a href="#">297</a>	<code>GetItemNames</code>	Return a list of all names in the collection
<a href="#">297</a>	<code>IndexOf</code>	Find location of item by name

### 10.25.3 Property overview

Page	Property	Access	Description
<a href="#">297</a>	<code>Dataset</code>	r	Dataset this collection manages definitions for.
<a href="#">297</a>	<code>Updated</code>	rw	Has one of the items been changed

### 10.25.4 TDefCollection.create

Synopsis: Instantiate a new `TDefCollection` instance.

Declaration: `constructor create(ADataset: TDataset; AOwner: TPersistent;  
AClass: TCollectionItemClass)`

Visibility: public

Description: `Create` saves the `ADataset` and `AOwner` components in local variables for later reference, and then calls the inherited `Create` with `AClass` as a parameter. `AClass` should at least be of type `TNamedItem`. `ADataset` is the dataset on whose behalf the collection is managed. `AOwner` is the owner of the collection, normally this is the form or datamodule on which the dataset is dropped.

See also: `TDataset` (250), `TNamedItem` (354)

### 10.25.5 TDefCollection.Find

Synopsis: Find an item by name

Declaration: `function Find(const AName: String) : TNamedItem`

Visibility: public

Description: `Find` searches for an item in the collection with name `AName` and returns the item if it is found. If no item with the requested name is found, `Nil` is returned. The search is performed case-insensitive.

Errors: If no item with matching name is found, `Nil` is returned.

See also: `TNamedItem.Name` (354), `TDefCollection.IndexOf` (297)

### 10.25.6 TDefCollection.GetItemNames

Synopsis: Return a list of all names in the collection

Declaration: `procedure GetItemNames(List: TStrings)`

Visibility: public

Description: `GetItemNames` fills `List` with the names of all items in the collection. It clears the list first.

Errors: If `List` is not a valid `TStrings` instance, an exception will occur.

See also: `TNamedItem.Name` ([354](#))

### 10.25.7 TDefCollection.IndexOf

Synopsis: Find location of item by name

Declaration: `function IndexOf(const AName: String) : LongInt`

Visibility: public

Description: `IndexOf` searches in the collection for an item whose `Name` property matches `AName` and returns the index of the item if it finds one. If no item is found, -1 is returned. The search is performed case-insensitive.

See also: `TDefCollection.Find` ([296](#)), `TNamedItem.Name` ([354](#))

### 10.25.8 TDefCollection.Dataset

Synopsis: Dataset this collection manages definitions for.

Declaration: `Property Dataset : TDataSet`

Visibility: public

Access: Read

Description: `Dataset` is the dataset this collection manages definitions for. It must be supplied when the collection is created and cannot change during the lifetime of the collection.

### 10.25.9 TDefCollection.Updated

Synopsis: Has one of the items been changed

Declaration: `Property Updated : Boolean`

Visibility: public

Access: Read, Write

Description: `Changed` indicates whether the collection has changed: an item was added or removed, or one of the properties of the items was changed.

## 10.26 TDetailDataLink

### 10.26.1 Description

`TDetailDataLink` handles the communication between a detail dataset and the master datasource in a master-detail relationship between datasets. It should never be used in an application, and should only be used by component writers that wish to provide master-detail functionality for `TDataSet` descendents.

### 10.26.2 Property overview

Page	Property	Access	Description
<a href="#">298</a>	<code>DetailDataSet</code>	r	Detail dataset in Master-detail relation

### 10.26.3 TDetailDataLink.DetailDataSet

Synopsis: Detail dataset in Master-detail relation

Declaration: `Property DetailDataSet : TDataSet`

Visibility: public

Access: Read

Description: `DetailDataSet` is the detail dataset in a master-detail relationship between 2 datasets. `DetailDataSet` is always `Nil` in `TDetailDataLink` and is only filled in in descendent classes like `TMasterDataLink` ([349](#)). The master dataset is available through the regular `TDataLink.DataSource` ([249](#)) property.

See also: `TDataSet` ([250](#)), `TMasterDataLink` ([349](#)), `TDataLink.DataSource` ([249](#))

## 10.27 TField

### 10.27.1 Description

`TField` is an abstract class that defines access methods for a field in a record, controlled by a `TDataSet` ([250](#)) instance. It provides methods and properties to access the contents of the field in the current record. Reading one of the `AsXXX` properties of `TField` will access the field contents and return the contents as the desired type. Writing one of the `AsXXX` properties will write a value to the buffer represented by the `TField` instance.

`TField` is an abstract class, meaning that it should never be created directly. `TDataSet` instances always create one of the descendent classes of `TField`, depending on the type of the underlying data.

**10.27.2 Method overview**

Page	Property	Description
<a href="#">302</a>	Assign	Copy properties from one TField instance to another
<a href="#">302</a>	AssignValue	Assign value of a variant record to the field.
<a href="#">303</a>	Clear	Clear the field contents.
<a href="#">302</a>	Create	Create a new TField instance
<a href="#">302</a>	Destroy	Destroy the TField instance
<a href="#">303</a>	FocusControl	Set focus to the first control connected to this field.
<a href="#">303</a>	GetData	Get the data from this field
<a href="#">304</a>	IsBlob	Is the field a BLOB field (untyped data of indeterminate size).
<a href="#">304</a>	IsValidChar	Check whether a character is valid input for the field
<a href="#">304</a>	RefreshLookupList	Refresh the lookup list
<a href="#">304</a>	SetData	Save the field data
<a href="#">305</a>	SetFieldType	Set the field data type
<a href="#">305</a>	Validate	Validate the data buffer



**10.27.3 Property overview**

Page	Property	Access	Description
315	Alignment	rw	Alignment for this field
305	AsBCD	rw	Access the field's contents as a BCD (Binary coded Decimal)
306	AsBoolean	rw	Access the field's contents as a Boolean value.
306	AsCurrency	rw	Access the field's contents as a Currency value.
306	AsDateTime	rw	Access the field's contents as a TDateTime value.
307	AsFloat	rw	Access the field's contents as a floating-point (Double) value.
308	AsInteger	rw	Access the field's contents as a 32-bit signed integer (longint) value.
307	AsLargeInt	rw	Access the field's contents as a 64-bit signed integer (longint) value.
307	AsLongint	rw	Access the field's contents as a 32-bit signed integer (longint) value.
308	AsString	rw	Access the field's contents as an AnsiString value.
309	AsVariant	rw	Access the field's contents as a Variant value.
308	AsWideString	rw	Access the field's contents as a WideString value.
309	AttributeSet	rw	
309	Calculated	rw	Is the field a calculated field ?
309	CanModify	r	Can the field's contents be modified.
315	ConstraintErrorMessage	rw	Message to display if the CustomConstraint constraint is violated.
310	CurValue	r	Current value of the field
315	CustomConstraint	rw	Custom constraint for the field's value
310	DataSet	rw	Dataset this field belongs to
310	DataSetSize	r	Size of the field's data
310	DataType	r	The data type of the field.
316	DefaultExpression	rw	Default value for the field
316	DisplayLabel	rws	Name of the field for display purposes
311	DisplayName	r	User-readable fieldname
311	DisplayText	r	Formatted field value
316	DisplayWidth	rw	Width of the field in characters
316	FieldKind	rw	The kind of field.
317	FieldName	rw	Name of the field
311	FieldNo	r	Number of the field in the record
317	HasConstraints	r	Does the field have any constraints defined
317	ImportedConstraint	rw	Constraint for the field value on the level of the underlying database
317	Index	rw	Index of the field in the list of fields
312	IsIndexedField	r	Is the field an indexed field ?
312	IsNull	r	Is the field empty
318	KeyFields	rw	Key fields to use when looking up a field value.
312	Lookup	rw	Is the field a lookup field
318	LookupCache	rw	Should lookup values be cached
318	LookupDataSet	rw	Dataset with lookup values
319	LookupKeyFields	rw	Names of fields on which to perform a locate
314	LookupList	r	List of lookup values
319	LookupResultField	rw	Name of field to use as lookup value
312	NewValue	rw	The new value of the field
313	Offset	r	Offset of the field's value in the dataset buffer
314	OldValue	r	Old value of the field
321	OnChange	rw	Event triggered when the field's value has changed
321	OnGetText	rw	Event to format the field's content
321	OnSetText	rw	Event to set the field's content based on a user-formatted string
322	OnValidate	rw	Event to validate the value of a field before it is written to the data buffer
319	Origin	rw	Original fieldname of the field.
319	ProviderFlags	rw	Flags for provider or update support

### 10.27.4 TField.Create

Synopsis: Create a new TField instance

Declaration: constructor Create(AOwner: TComponent); Override

Visibility: public

Description: Create creates a new TField instance and sets up initial values for the fields. TField is a component, and AOwner will be used as the owner of the TField instance. This usually will be the form or datamodule on which the dataset was placed. There should normally be no need for a programmer to create a Tfield instance manually. The TDataSet.Open (268) method will create the necessary TField instances, if none had been created in the designer.

See also: TDataSet.Open (268)

### 10.27.5 TField.Destroy

Synopsis: Destroy the TField instance

Declaration: destructor Destroy; Override

Visibility: public

Description: Destroy cleans up any structures set up by the field instance, and then calls the inherited destructor. There should be no need to call this method under normal circumstances: the dataset instance will free any TField instances it has created when the dataset was opened.

See also: TDataSet.Close (258)

### 10.27.6 TField.Assign

Synopsis: Copy properties from one TField instance to another

Declaration: procedure Assign(Source: TPersistent); Override

Visibility: public

Description: Assign is overridden by TField to copy the field value (not the field properties) from Source if it exists. If Source is Nil then the value of the field is cleared.

Errors: If Source is not a TField instance, then an exception will be raised.

See also: TField.Value (314)

### 10.27.7 TField.AssignValue

Synopsis: Assign value of a variant record to the field.

Declaration: procedure AssignValue(const AValue: TVarRec)

Visibility: public

Description: AssignValue assigns the value of a "array of const" record AValue (of type TVarRec) to the field's value. If the record contains a TPersistent instance, it will be used as argument for the Assign to the field.

The dataset must be in edit mode to execute this method.



**Errors:** If the `AValue` contains an unsupported value (such as a non-nil pointer) then an exception will be raised. If the dataset is not in one of the edit modes, then executing this method will raise an `EDatabaseError` (220) exception.

See also: `TField.Assign` (302), `TField.Value` (314)

### 10.27.8 TField.Clear

**Synopsis:** Clear the field contents.

**Declaration:** `procedure Clear; Virtual`

**Visibility:** `public`

**Description:** `Clear` clears the contents of the field. After calling this method the value of the field is `Null` and `IsNull` (312) returns `True`.

The dataset must be in edit mode to execute this method.

**Errors:** If the dataset is not in one of the edit modes, then executing this method will raise an `EDatabaseError` (220) exception.

See also: `TField.IsNull` (312), `TField.Value` (314)

### 10.27.9 TField.FocusControl

**Synopsis:** Set focus to the first control connected to this field.

**Declaration:** `procedure FocusControl`

**Visibility:** `public`

**Description:** `FocusControl` will set focus to the first control that is connected to this field.

**Errors:** If the control cannot receive focus, then this method will raise an exception.

See also: `TDataset.EnableControls` (261), `TDataset.DisableControls` (260)

### 10.27.10 TField.GetData

**Synopsis:** Get the data from this field

**Declaration:** `function GetData(Buffer: Pointer) : Boolean; Overload`  
`function GetData(Buffer: Pointer; NativeFormat: Boolean) : Boolean`  
`; Overload`

**Visibility:** `public`

**Description:** `GetData` is used internally by `TField` to fetch the value of the data of this field into the data buffer pointed to by `Buffer`. If it returns `False` if the field has no value (i.e. is `Null`). If the `NativeFormat` parameter is true, then date/time formats should use the `TDateTime` format. It should not be necessary to use this method, instead use the various 'AsXXX' methods to access the data.

**Errors:** No validity checks are performed on `Buffer`: it should point to a valid memory area, and should be large enough to contain the value of the field. Failure to provide a buffer that matches these criteria will result in an exception.

See also: `TField.IsNull` (312), `TField.SetData` (304), `TField.Value` (314)

**10.27.11 TField.IsBlob**

Synopsis: Is the field a BLOB field (untyped data of indeterminate size).

Declaration: `function IsBlob : Boolean; Virtual`

Visibility: `public`

Description: `IsBlob` returns `True` if the field is one of the blob field types. The `TField` implementation returns `false`. Only one of the blob-type field classes override this function and let it return `True`.

Errors: None.

See also: `TBlobField.IsBlob` (228)

**10.27.12 TField.IsValidChar**

Synopsis: Check whether a character is valid input for the field

Declaration: `function IsValidChar(InputChar: Char) : Boolean; Virtual`

Visibility: `public`

Description: `IsValidChar` checks whether `InputChar` is a valid characters for the current field. It does this by checking whether `InputChar` is in the set of characters specified by the `TField.ValidChars` (313) property. The `ValidChars` property will be initialized to a correct set of characters by descendent classes. For instance, a numerical field will only accept numerical characters and the sign and decimal separator characters.

Descendent classes can override this method to provide custom checks. The `ValidChars` property can be set to restrict the list of valid characters to a subset of what would normally be available.

See also: `TField.ValidChars` (313)

**10.27.13 TField.RefreshLookupList**

Synopsis: Refresh the lookup list

Declaration: `procedure RefreshLookupList`

Visibility: `public`

Description: `RefreshLookupList` fills the lookup list for a lookup fields with all key, value pairs found in the lookup dataset. It will open the lookup dataset if needed. The lookup list is only used if the `TField.LookupCache` (318) property is set to `True`.

Errors: If the values of the various lookup properties is not correct or the lookup dataset cannot be opened, then an exception will be raised.

See also: `TField.LookupDataset` (318), `TField.LookupKeyFields` (319), `TField.LookupResultField` (319)

**10.27.14 TField.SetData**

Synopsis: Save the field data

Declaration: `procedure SetData(Buffer: Pointer); Overload`  
`procedure SetData(Buffer: Pointer; NativeFormat: Boolean); Overload`

Visibility: `public`

**Description:** `SetData` saves the value of the field data in `Buffer` to the dataset internal buffer. The `Buffer` pointer should point to a memory buffer containing the data for the field in the correct format. If the `NativeFormat` parameter is true, then date/time formats should use the `TDateTime` format.

There should normally not be any need to call `SetData` directly: it is called by the various setter methods of the `AsXXX` properties of `TField`.

**Errors:** No validity checks are performed on `Buffer`: it should point to a valid memory area, and should be large enough to contain the value of the field. Failure to provide a buffer that matches these criteria will result in an exception.

See also: `TField.GetData` (303), `TField.Value` (314)

### 10.27.15 TField.SetFieldType

**Synopsis:** Set the field data type

**Declaration:** `procedure SetFieldType(AValue: TFieldType); Virtual`

**Visibility:** public

**Description:** `SetFieldType` does nothing, but it can be overridden by descendent classes to provide special handling when the field type is set.

See also: `TField.DataType` (310)

### 10.27.16 TField.Validate

**Synopsis:** Validate the data buffer

**Declaration:** `procedure Validate(Buffer: Pointer)`

**Visibility:** public

**Description:** `Validate` is called by `SetData` prior to writing the data from `Buffer` to the dataset buffer. It will call the `TField.OnValidate` (322) event handler, if one is set, to allow the application programmer to program additional checks.

See also: `TField.SetData` (304), `TField.OnValidate` (322)

### 10.27.17 TField.AsBCD

**Synopsis:** Access the field's contents as a BCD (Binary coded Decimal)

**Declaration:** `Property AsBCD : TBCD`

**Visibility:** public

**Access:** Read, Write

**Description:** `AsBCD` can be used to read or write the contents of the field as a BCD value (Binary Coded Decimal). If the native type of the field is not BCD, then an attempt will be made to convert the field value from the native format to a BCD value when reading the field's content. Likewise, when writing the property, the value will be converted to the native type of the field (if the value allows it). Therefore, when reading or writing a field value for a field whose native data type is not a BCD value, an exception may be raised.

See also: `TField.AsCurrency` (306), `TField.Value` (314)

### 10.27.18 TField.AsBoolean

Synopsis: Access the field's contents as a Boolean value.

Declaration: `Property AsBoolean : Boolean`

Visibility: `public`

Access: Read,Write

Description: `AsBoolean` can be used to read or write the contents of the field as a boolean value. If the native type of the field is not Boolean, then an attempt will be made to convert the field value from the native format to a boolean value when reading the field's content. Likewise, when writing the property, the value will be converted to the native type of the field (if the value allows it). Therefor, when reading or writing a field value for a field whose native data type is not a Boolean value (for instance a string value), an exception may be raised.

See also: `TField.Value` (314), `TField.AsInteger` (308)

### 10.27.19 TField.AsCurrency

Synopsis: Access the field's contents as a Currency value.

Declaration: `Property AsCurrency : Currency`

Visibility: `public`

Access: Read,Write

Description: `AsBoolean` can be used to read or write the contents of the field as a currency value. If the native type of the field is not Boolean, then an attempt will be made to convert the field value from the native format to a currency value when reading the field's content. Likewise, when writing the property, the value will be converted to the native type of the field (if the value allows it). Therefor, when reading or writing a field value for a field whose native data type is not a currency-compatible value (dates or string values), an exception may be raised.

See also: `TField.Value` (314), `TField.AsFloat` (307)

### 10.27.20 TField.AsDateTime

Synopsis: Access the field's contents as a TDateTime value.

Declaration: `Property AsDateTime : TDateTime`

Visibility: `public`

Access: Read,Write

Description: `AsDateTime` can be used to read or write the contents of the field as a TDateTime value (for both date and time values). If the native type of the field is not a date or time value, then an attempt will be made to convert the field value from the native format to a TDateTime value when reading the field's content. Likewise, when writing the property, the value will be converted to the native type of the field (if the value allows it). Therefor, when reading or writing a field value for a field whose native data type is not a TDateTime-compatible value (dates or string values), an exception may be raised.

See also: `TField.Value` (314), `TField.AsString` (308)

**10.27.21 TField.AsFloat**

**Synopsis:** Access the field's contents as a floating-point (Double) value.

**Declaration:** `Property AsFloat : Double`

**Visibility:** public

**Access:** Read,Write

**Description:** `AsFloat` can be used to read or write the contents of the field as a floating-point value (of type double, i.e. with double precision). If the native type of the field is not a floating-point value, then an attempt will be made to convert the field value from the native format to a floating-point value when reading the field's content. Likewise, when writing the property, the value will be converted to the native type of the field (if the value allows it). Therefor, when reading or writing a field value for a field whose native data type is not a floating-point-compatible value (string values for instance), an exception may be raised.

See also: `TField.Value` (314), `TField.AsString` (308), `TField.AsCurrency` (306)

**10.27.22 TField.AsLongint**

**Synopsis:** Access the field's contents as a 32-bit signed integer (longint) value.

**Declaration:** `Property AsLongint : LongInt`

**Visibility:** public

**Access:** Read,Write

**Description:** `AsLongint` can be used to read or write the contents of the field as a 32-bit signed integer value (of type longint). If the native type of the field is not a longint value, then an attempt will be made to convert the field value from the native format to a longint value when reading the field's content. Likewise, when writing the property, the value will be converted to the native type of the field (if the value allows it). Therefor, when reading or writing a field value for a field whose native data type is not a 32-bit signed integer-compatible value (string values for instance), an exception may be raised.

This is an alias for the `TField.AsInteger` (308).

See also: `TField.Value` (314), `TField.AsString` (308), `TField.AsInteger` (308)

**10.27.23 TField.AsLargeInt**

**Synopsis:** Access the field's contents as a 64-bit signed integer (longint) value.

**Declaration:** `Property AsLargeInt : LargeInt`

**Visibility:** public

**Access:** Read,Write

**Description:** `AsLargeInt` can be used to read or write the contents of the field as a 64-bit signed integer value (of type Int64). If the native type of the field is not an Int64 value, then an attempt will be made to convert the field value from the native format to an Int64 value when reading the field's content. Likewise, when writing the property, the value will be converted to the native type of the field (if the value allows it). Therefor, when reading or writing a field value for a field whose native data type is not a 64-bit signed integer-compatible value (string values for instance), an exception may be raised.

See also: `TField.Value` (314), `TField.AsString` (308), `TField.AsInteger` (308)

#### 10.27.24 TField.AsInteger

Synopsis: Access the field's contents as a 32-bit signed integer (longint) value.

Declaration: `Property AsInteger : Integer`

Visibility: `public`

Access: Read,Write

Description: `AsInteger` can be used to read or write the contents of the field as a 32-bit signed integer value (of type `Integer`). If the native type of the field is not an integer value, then an attempt will be made to convert the field value from the native format to a integer value when reading the field's content. Likewise, when writing the property, the value will be converted to the native type of the field (if the value allows it). Therefor, when reading or writing a field value for a field whose native data type is not a 32-bit signed integer-compatible value (string values for instance), an exception may be raised.

See also: `TField.Value` (314), `TField.AsString` (308), `TField.AsLongint` (307), `TField.AsInt64` (298)

#### 10.27.25 TField.AsString

Synopsis: Access the field's contents as an `AnsiString` value.

Declaration: `Property AsString : String`

Visibility: `public`

Access: Read,Write

Description: `AsString` can be used to read or write the contents of the field as an `AnsiString` value. If the native type of the field is not an `ansistring` value, then an attempt will be made to convert the field value from the native format to a `ansistring` value when reading the field's content. Likewise, when writing the property, the value will be converted to the native type of the field (if the value allows it). Therefor, when reading or writing a field value for a field whose native data type is not an `ansistring`-compatible value, an exception may be raised.

See also: `TField.Value` (314), `TField.AsWideString` (308)

#### 10.27.26 TField.AsWideString

Synopsis: Access the field's contents as a `WideString` value.

Declaration: `Property AsWideString : WideString`

Visibility: `public`

Access: Read,Write

Description: `AsWideString` can be used to read or write the contents of the field as a `WideString` value. If the native type of the field is not a `widestring` value, then an attempt will be made to convert the field value from the native format to a `widestring` value when reading the field's content. Likewise, when writing the property, the value will be converted to the native type of the field (if the value allows it). Therefor, when reading or writing a field value for a field whose native data type is not a `widestring`-compatible value, an exception may be raised.

See also: `TField.Value` (314), `TField.Astring` (298)

**10.27.27 TField.AsVariant**

Synopsis: Access the field's contents as a Variant value.

Declaration: `Property AsVariant : variant`

Visibility: `public`

Access: Read,Write

Description: `AsVariant` can be used to read or write the contents of the field as a Variant value. If the native type of the field is not a Variant value, then an attempt will be made to convert the field value from the native format to a variant value when reading the field's content. Likewise, when writing the property, the value will be converted to the native type of the field (if the value allows it). Therefore, when reading or writing a field value for a field whose native data type is not a variant-compatible value, an exception may be raised.

See also: `TField.Value` (314), `TField.Astring` (298)

**10.27.28 TField.AttributeSet**

Synopsis:

Declaration: `Property AttributeSet : String`

Visibility: `public`

Access: Read,Write

Description:

**10.27.29 TField.Calculated**

Synopsis: Is the field a calculated field ?

Declaration: `Property Calculated : Boolean`

Visibility: `public`

Access: Read,Write

Description: `Calculated` is `True` if the `FieldKind` (316) is `fkCalculated`. Setting the property will result in `FieldKind` being set to `fkCalculated` (for a value of `True`) or `fkData`. This property should be considered read-only.

See also: `TField.FieldKind` (316)

**10.27.30 TField.CanModify**

Synopsis: Can the field's contents be modified.

Declaration: `Property CanModify : Boolean`

Visibility: `public`

Access: Read

Description: `CanModify` is `True` if the field is not read-only and the dataset allows modification.

See also: `TField.ReadOnly` (320), `TDataset.CanModify` (272)

### 10.27.31 TField.CurValue

Synopsis: Current value of the field

Declaration: `Property CurValue : Variant`

Visibility: `public`

Access: `Read`

Description: `CurValue` returns the current value of the field as a variant.

See also: `TField.Value` ([314](#))

### 10.27.32 TField.DataSet

Synopsis: Dataset this field belongs to

Declaration: `Property DataSet : TDataSet`

Visibility: `public`

Access: `Read, Write`

Description: `DataSet` contains the dataset this field belongs to. Writing this property will add the field to the list of fields of a dataset, after removing it from the list of fields of the dataset the field was previously assigned to. It should under normal circumstances never be necessary to set this property, the `TDataSet` code will take care of this.

See also: `TDataSet` ([250](#)), `TDataSet.Fields` ([277](#))

### 10.27.33 TField.DataSize

Synopsis: Size of the field's data

Declaration: `Property DataSize : Integer`

Visibility: `public`

Access: `Read`

Description: `DataSize` is the memory size needed to store the field's contents. This is different from the `Size` ([313](#)) property which declares a logical size for datatypes that have a variable size (such as string fields). For BLOB fields, use the `TBlobField.BlobSize` ([229](#)) property to get the size of the field's contents for the current record..

See also: `TField.Size` ([313](#)), `TBlobField.BlobSize` ([229](#))

### 10.27.34 TField.DataType

Synopsis: The data type of the field.

Declaration: `Property DataType : TFieldType`

Visibility: `public`

Access: `Read`



**Description:** `Datatype` indicates the type of data the field has. This property is initialized when the dataset is opened or when persistent fields are created for the dataset. Instead of checking the class type of the field, it is better to check the `Datatype`, since the actual class of the `TField` instance may differ depending on the dataset.

See also: `TField.FieldKind` (316)

### 10.27.35 TField.DisplayName

**Synopsis:** User-readable fieldname

**Declaration:** `Property DisplayName : String`

**Visibility:** public

**Access:** Read

**Description:** `DisplayName` is the name of the field as it will be displayed to the user e.g. in grid column headers. By default it equals the `FieldName` (317) property, unless assigned another value.

The use of this property is deprecated. Use `DisplayLabel` (316) instead.

See also: `TField.FieldName` (317)

### 10.27.36 TField.DisplayText

**Synopsis:** Formatted field value

**Declaration:** `Property DisplayText : String`

**Visibility:** public

**Access:** Read

**Description:** `DisplayText` returns the field's value as it should be displayed to the user, with all necessary formatting applied. Controls that should display the value of the field should use `DisplayText` instead of the `TField.AsString` (308) property, which does not take into account any formatting.

See also: `TField.AsString` (308)

### 10.27.37 TField.FieldNo

**Synopsis:** Number of the field in the record

**Declaration:** `Property FieldNo : LongInt`

**Visibility:** public

**Access:** Read

**Description:** `FieldNo` is the position of the field in the record. It is a 1-based index and is initialized when the dataset is opened or when persistent fields are created for the dataset.

See also: `TField.Index` (317)

### 10.27.38 TField.IsIndexField

Synopsis: Is the field an indexed field ?

Declaration: `Property IsIndexField : Boolean`

Visibility: `public`

Access: `Read`

Description: `IsIndexField` is `true` if the field is an indexed field. By default this property is `False`, descendants of `TDataset` (250) can change this to `True`.

See also: `TField.Calculated` (309)

### 10.27.39 TField.IsNull

Synopsis: Is the field empty

Declaration: `Property IsNull : Boolean`

Visibility: `public`

Access: `Read`

Description: `IsNull` is `True` if the field does not have a value. If the underlying data contained a value, or a value is written to it, `IsNull` will return `False`. After `TDataset.Insert` (265) is called or `Clear` (303) is called then `IsNull` will return `True`.

See also: `TField.Clear` (303), `TDataset.Insert` (265)

### 10.27.40 TField.Lookup

Synopsis: Is the field a lookup field

Declaration: `Property Lookup : Boolean`

Visibility: `public`

Access: `Read,Write`

Description: `Lookup` is `True` if the `FieldKind` (316) equals `fkLookup`, `False` otherwise. Setting the `Lookup` property will switch the `FieldKind` between the `fkLookup` and `fkData`.

See also: `TField.FieldKind` (316)

### 10.27.41 TField.NewValue

Synopsis: The new value of the field

Declaration: `Property NewValue : Variant`

Visibility: `public`

Access: `Read,Write`

Description: `NewValue` returns the new value of the field. The FPC implementation of `TDataset` (250) does not yet support this.

See also: `TField.Value` (314), `TField.CurValue` (310)

#### 10.27.42 TField.Offset

Synopsis: Offset of the field's value in the dataset buffer

Declaration: `Property Offset : Word`

Visibility: public

Access: Read

Description: `Offset` is the location of the field's contents in the dataset memory buffer. It is read-only and initialized by the dataset when it is opened.

See also: `TField.FieldNo` (311), `TField.Index` (317), `TField.Datasize` (310)

#### 10.27.43 TField.Size

Synopsis: Logical size of the field

Declaration: `Property Size : Integer`

Visibility: public

Access: Read,Write

Description: `Size` is the declared size of the field for datatypes that can have variable size, such as string types, BCD types or array types. To get the size of the storage needed to store the field's content, the `DataSource` (310) should be used. For blob fields, the current size of the

#### 10.27.44 TField.Text

Synopsis: Text representation of the field

Declaration: `Property Text : String`

Visibility: public

Access: Read,Write

Description: `Text` can be used to retrieve or set the value of the value as a string value for editing purposes. It will trigger the `TField.OnGetText` (321) event handler if a handler was specified. For display purposes, the `TField.DisplayText` (311) property should be used. Controls that should display the value in a textual format should use text whenever they must display the text for editing purposes. Inversely, when a control should save the value entered by the user, it should write the contents to the `Text` property, not the `AsString` (308) property, this will invoke the `TField.OnSetText` (321) event handler, if one is set.

See also: `TField.AsString` (308), `TField.DisplayText` (311), `TField.Value` (314)

#### 10.27.45 TField.ValidChars

Synopsis: Characters that are valid input for the field's content

Declaration: `Property ValidChars : TFieldChars`

Visibility: public

Access: Read

**Description:** `ValidChars` is a property that is initialized by descendent classes to contain the set of characters that can be entered in an edit control which is used to edit the field. Numerical fields will set this to a set of numerical characters, string fields will set this to all possible characters. It is possible to restrict the possible input by setting this property to a subset of all possible characters (for example, set it to all uppercase letters to allow the user to enter only uppercase characters). `TField` itself does not enforce the validity of the data when the content of the field is set, an edit control should check the validity of the user input by means of the `IsValidChar` (304) function.

See also: `TField.IsValidChar` (304)

### 10.27.46 TField.Value

**Synopsis:** Value of the field as a variant value

**Declaration:** `Property Value : variant`

**Visibility:** public

**Access:** Read, Write

**Description:** `Value` can be used to read or write the value of the field as a Variant value. When setting the value, the value will be converted to the actual type of the field as defined in the underlying data. Likewise, when reading the value property, the actual field value will be converted to a variant value. If the field does not contain a value (when `IsNull` (312) returns `True`), then `Value` will contain `Null`.

It is not recommended to use the `Value` property: it should only be used when the type of the field is unknown. If the type of the field is known, it is better to use one of the `AsXXX` properties, which will not only result in faster code, but will also avoid strange type conversions.

See also: `TField.IsNull` (312), `TField.Text` (313), `TField.DisplayText` (311)

### 10.27.47 TField.OldValue

**Synopsis:** Old value of the field

**Declaration:** `Property OldValue : variant`

**Visibility:** public

**Access:** Read

**Description:** `OldValue` returns the value of the field prior to an edit operation. This feature is currently not supported in FPC.

See also: `TField.Value` (314), `TField.CurValue` (310), `TField.NewValue` (312)

### 10.27.48 TField.LookupList

**Synopsis:** List of lookup values

**Declaration:** `Property LookupList : TLookupList`

**Visibility:** public

**Access:** Read

**Description:** `LookupList` contains the list of key, value pairs used when caching the possible lookup values for a lookup field. The list is only valid when the `LookupCache` (318) property is set to `True`. It can be refreshed using the `RefreshLookupList` (304) method.

See also: `TField.RefreshLookupList` (304), `TField.LookupCache` (318)

### 10.27.49 TField.Alignment

Synopsis: Alignment for this field

Declaration: `Property Alignment : TAlignment`

Visibility: published

Access: Read,Write

Description: `Alignment` contains the alignment that UI controls should observe when displaying the contents of the field. Setting the property at the field level will make sure that all DB-Aware controls will display the contents of the field with the same alignment.

See also: `TField.DisplayText` ([311](#))

### 10.27.50 TField.CustomConstraint

Synopsis: Custom constraint for the field's value

Declaration: `Property CustomConstraint : String`

Visibility: published

Access: Read,Write

Description: `CustomConstraint` may contain a constraint that will be enforced when the dataset posts it's data. It should be a SQL-like expression that results in a `True` or `False` value. Examples of valid constraints are:

```
Salary < 10000  
YearsEducation < Age
```

If the constraint is not satisfied when the record is posted, then an exception will be raised with the value of `ConstraintErrorMessage` ([315](#)) as a message.

This feature is not yet implemented in FPC.

See also: `TField.ConstraintErrorMessage` ([315](#)), `TField.ImportedConstraint` ([317](#))

### 10.27.51 TField.ConstraintErrorMessage

Synopsis: Message to display if the `CustomConstraint` constraint is violated.

Declaration: `Property ConstraintErrorMessage : String`

Visibility: published

Access: Read,Write

Description: `ConstraintErrorMessage` is the message that should be displayed when the dataset checks the constraints and the constraint in `TField.CustomConstraint` ([315](#)) is violated.

This feature is not yet implemented in FPC.

See also: `TField.CustomConstraint` ([315](#))

### 10.27.52 TField.DefaultExpression

Synopsis: Default value for the field

Declaration: `Property DefaultExpression : String`

Visibility: published

Access: Read,Write

Description: `DefaultValue` can be set to a value that should be entered in the field whenever the `TDataset.Append` (256) or `TDataset.Insert` (265) methods are executed. It should contain a valid SQL expression that results in the correct type for the field.

This feature is not yet implemented in FPC.

See also: `TDataset.Insert` (265), `TDataset.Append` (256), `TDataset.CustomConstraint` (250)

### 10.27.53 TField.DisplayLabel

Synopsis: Name of the field for display purposes

Declaration: `Property DisplayLabel : String`

Visibility: published

Access: Read,Write

Description: `DisplayLabel` is the name of the field as it will be displayed to the user e.g. in grid column headers. By default it equals the `FieldName` (317) property, unless assigned another value.

See also: `TField.FieldName` (317)

### 10.27.54 TField.DisplayWidth

Synopsis: Width of the field in characters

Declaration: `Property DisplayWidth : LongInt`

Visibility: published

Access: Read,Write

Description: `DisplayWidth` is the width (in characters) that should be used by controls that display the contents of the field (such as in grids or lookup lists). It is initialized to a default value for most fields (e.g. it equals `Size` (313) for string fields) but can be modified to obtain a more appropriate value for the field's expected content.

See also: `TField.Alignment` (315), `TField.DisplayText` (311)

### 10.27.55 TField.FieldKind

Synopsis: The kind of field.

Declaration: `Property FieldKind : TFieldKind`

Visibility: published

Access: Read,Write

Description: `FieldKind` indicates the type of the `TField` instance. Besides `TField` instances that represent fields present in the underlying data records, there can also be calculated or lookup fields. This property determines what kind of field the `TField` instance is.

### 10.27.56 TField.FieldName

Synopsis: Name of the field

Declaration: `Property FieldName : String`

Visibility: published

Access: Read,Write

Description: `FieldName` is the name of the field as it is defined in the underlying data structures (for instance the name of the field in a SQL table, DBase file, or the alias of the field if it was aliased in a SQL SELECT statement. It does not always equal the `Name` property, which is the name of the `TField` component instance. The `Name` property will generally equal the name of the dataset appended with the value of the `FieldName` property.

See also: `TFieldDef.Name` ([322](#)), `TField.Size` ([313](#)), `TField.DataType` ([310](#))

### 10.27.57 TField.HasConstraints

Synopsis: Does the field have any constraints defined

Declaration: `Property HasConstraints : Boolean`

Visibility: published

Access: Read

Description: `HasConstraints` will contain `True` if one of the `CustomConstraint` ([315](#)) or `ImportedConstraint` ([317](#)) properties is set to a non-empty value.

See also: `TField.CustomConstraint` ([315](#)), `TField.ImportedConstraint` ([317](#))

### 10.27.58 TField.Index

Synopsis: Index of the field in the list of fields

Declaration: `Property Index : LongInt`

Visibility: published

Access: Read,Write

Description: `Index` is the name of the field in the list of fields of a dataset. It is, in general, the (0-based) position of the field in the underlying data structures, but this need not always be so. The `TField.FieldNo` ([311](#)) property should be used for that.

See also: `TField.FieldNo` ([311](#))

### 10.27.59 TField.ImportedConstraint

Synopsis: Constraint for the field value on the level of the underlying database

Declaration: `Property ImportedConstraint : String`

Visibility: published

Access: Read,Write

**Description:** `ImportedConstraint` contains any constraints that the underlying data engine imposes on the values of a field (usually in an SQL CONSTRAINT) clause. Whether this field is filled with appropriate data depends on the implementation of the `TDataset` (250) descendent.

See also: `TField.CustomConstraint` (315), `TDataset` (250), `TField.ConstraintErrorMessage` (315)

### 10.27.60 TField.KeyFields

**Synopsis:** Key fields to use when looking up a field value.

**Declaration:** `Property KeyFields : String`

**Visibility:** published

**Access:** Read,Write

**Description:** `KeyFields` should contain a semi-colon separated list of field names from the lookupfield's dataset which will be matched to the fields enumerated in `LookupKeyFields` (319) in the dataset pointed to by the `LookupDataset` (318) property.

See also: `TField.LookupKeyFields` (319), `Tfield.LookupDataset` (318)

### 10.27.61 TField.LookupCache

**Synopsis:** Should lookup values be cached

**Declaration:** `Property LookupCache : Boolean`

**Visibility:** published

**Access:** Read,Write

**Description:** `LookupCache` is by default `False`. If it is set to `True` then a list of key, value pairs will be created from the `LookupKeyFields` (319) in the dataset pointed to by the `LookupDataset` (318) property. The list of key, value pairs is available through the `TField.LookupList` (314) property.

See also: `TField.LookupKeyFields` (319), `Tfield.LookupDataset` (318), `TField.LookupList` (314)

### 10.27.62 TField.LookupDataSet

**Synopsis:** Dataset with lookup values

**Declaration:** `Property LookupDataSet : TDataset`

**Visibility:** published

**Access:** Read,Write

**Description:** `LookupDataset` is used by lookup fields to fetch the field's value. The `LookupKeyFields` (319) property is used as a list of fields to locate a record in this dataset, and the value of the `LookupResultField` (319) field is then used as the value of the lookup field.

See also: `TField.KeyFields` (318), `TField.LookupKeyFields` (319), `TField.LookupResultField` (319), `TField.LookupCache` (318)



### 10.27.63 TField.LookupKeyFields

Synopsis: Names of fields on which to perform a locate

Declaration: `Property LookupKeyFields : String`

Visibility: published

Access: Read,Write

Description: `LookupKeyFields` should contain a semi-colon separated list of field names from the dataset pointed to by the `LookupDataset` (318) property. These fields will be used when locating a record corresponding to the values in the `TField.KeyFields` (318) property.

See also: `TField.KeyFields` (318), `TField.LookupDataset` (318), `TField.LookupResultField` (319), `TField.LookupCache` (318)

### 10.27.64 TField.LookupResultField

Synopsis: Name of field to use as lookup value

Declaration: `Property LookupResultField : String`

Visibility: published

Access: Read,Write

Description: `LookupResultField` contains the field name from a field in the dataset pointed to by the `LookupDataset` (318) property. The value of this field will be used as the lookup's field value when a record is found in the lookup dataset as result for the lookup field value.

See also: `TField.KeyFields` (318), `TField.LookupDataset` (318), `TField.LookupKeyFields` (319), `TField.LookupCache` (318)

### 10.27.65 TField.Origin

Synopsis: Original fieldname of the field.

Declaration: `Property Origin : String`

Visibility: published

Access: Read,Write

Description: `Origin` contains the origin of the field in the form `TableName.fieldName`. This property is filled only if the `TDataset` (250) descendent or the database engine support retrieval of this property. It can be used to automatically create update statements, together with the `TField.ProviderFlags` (319) property.

See also: `TDataset` (250), `TField.ProviderFlags` (319)

### 10.27.66 TField.ProviderFlags

Synopsis: Flags for provider or update support

Declaration: `Property ProviderFlags : TProviderFlags`

Visibility: published

Access: Read,Write

**Description:** `ProviderFlags` contains a set of flags that can be used by engines that automatically generate update SQL statements or update data packets. The various items in the set tell the engine whether the key is a key field, should be used in the where clause of an update statement or whether - in fact - it should be updated at all.

These properties should be set by the programmer so engines such as `SQLDB` can create correct update SQL statements whenever they need to post changes to the database. Note that to be able to set these properties in a designer, persistent fields must be created.

See also: `TField.Origin` ([319](#))

### 10.27.67 TField.ReadOnly

**Synopsis:** Is the field read-only

**Declaration:** `Property ReadOnly : Boolean`

**Visibility:** published

**Access:** Read,Write

**Description:** `ReadOnly` can be set to `True` to prevent controls of writing data to the field, effectively making it a read-only field. Setting this property to `True` does not prevent the field from getting a value through code: it is just an indication for GUI controls that the field's value is considered read-only.

See also: `TFieldDef.Attributes` ([325](#))

### 10.27.68 TField.Required

**Synopsis:** Does the field require a value

**Declaration:** `Property Required : Boolean`

**Visibility:** published

**Access:** Read,Write

**Description:** `Required` determines whether the field needs a value when posting the data: when a dataset posts the changed made to a record (new or existing), it will check whether all fields with the `Required` property have a value assigned to them. If not, an exception will be raised. Descendents of `TDataset` ([250](#)) will set the property to `True` when opening the dataset, depending on whether the field is required in the underlying data engine. For fields that are not required by the database engine, the programmer can still set the property to `True` if the business logic requires a field.

See also: `TDataset.Open` ([268](#)), `TField.ReadOnly` ([320](#)), `TField.Visible` ([320](#))

### 10.27.69 TField.Visible

**Synopsis:** Should the field be shown in grids

**Declaration:** `Property Visible : Boolean`

**Visibility:** published

**Access:** Read,Write

**Description:** `Visible` can be used to hide fields from a grid when displaying data to the user. Invisible fields will by default not be shown in the grid.

See also: `TField.ReadOnly` (320), `TField.Required` (320)

### 10.27.70 TField.OnChange

**Synopsis:** Event triggerd when the field's value has changed

**Declaration:** `Property OnChange : TFieldNotifyEvent`

**Visibility:** published

**Access:** Read,Write

**Description:** `OnChange` is triggered whenever the field's value has been changed. It is triggered only after the new contents have been written to the dataset buffer, so it can be used to react to changes in the field's content. To prevent the writing of changes to the buffer, use the `TField.OnValidate` (322) event. It is not allowed to change the state of the dataset or the contents of the field during the execution of this event handler: doing so may lead to infinite loops and other unexpected results.

See also: `TField.OnChange` (321)

### 10.27.71 TField.OnGetText

**Synopsis:** Event to format the field's content

**Declaration:** `Property OnGetText : TFieldGetTextEvent`

**Visibility:** published

**Access:** Read,Write

**Description:** `OnGetText` is triggered whenever the `TField.Text` (313) or `TField.DisplayText` (311) properties are read. It can be used to return a custom formatted string in the `AText` parameter which will then typically be used by a control to display the field's contents to the user. It is not allowed to change the state of the dataset or the contents of the field during the execution of this event handler.

See also: `TField.Text` (313), `TField.DisplayText` (311), `TField.OnSetText` (321), `TFieldGetTextEvent` (214)

### 10.27.72 TField.OnSetText

**Synopsis:** Event to set the field's content based on a user-formatted string

**Declaration:** `Property OnSetText : TFieldSetTextEvent`

**Visibility:** published

**Access:** Read,Write

**Description:** `OnSetText` is called whenever the `TField.Text` (313) property is written. It can be used to set the actual value of the field based on the passed `AText` parameter. Typically, this event handler will perform the inverse operation of the `TField.OnGetText` (321) handler, if it exists.

See also: `TField.Text` (313), `TField.OnGetText` (321), `TFieldGetTextEvent` (214)

### 10.27.73 TField.OnValidate

Synopsis: Event to validate the value of a field before it is written to the data buffer

Declaration: `Property OnValidate : TFieldNotifyEvent`

Visibility: published

Access: Read,Write

Description: `OnValidate` is called prior to writing a new field value to the dataset's data buffer. It can be used to prevent writing the new value to the buffer by raising an exception in the event handler. Note that this event handler is always called, irrespective of the way the value of the field is set.

See also: `TField.Text` (313), `TField.OnGetText` (321), `TField.OnSetText` (321), `TField.OnChange` (321)

## 10.28 TFieldDef

### 10.28.1 Description

`TFieldDef` is used to describe the fields that are present in the data underlying the dataset. For each field in the underlying field, an `TFieldDef` instance is created when the dataset is opened. This class offers almost no methods, it is mainly a storage class, to store all relevant properties of fields in a record (name, data type, size, required or not, etc.)

### 10.28.2 Method overview

Page	Property	Description
<a href="#">323</a>	Assign	Assign the contents of one <code>TFieldDef</code> instance to another.
<a href="#">322</a>	Create	Constructor for <code>TFieldDef</code> .
<a href="#">323</a>	CreateField	Create <code>TField</code> instance based on definitions in current <code>TFieldDef</code> instance.
<a href="#">323</a>	Destroy	Free the <code>TFieldDef</code> instance

### 10.28.3 Property overview

Page	Property	Access	Description
<a href="#">325</a>	Attributes	rw	Additional attributes of the field.
<a href="#">325</a>	DataType	rw	Data type for the field
<a href="#">324</a>	FieldClass	r	<code>TField</code> class used for this fielddef
<a href="#">324</a>	FieldNo	r	Field number
<a href="#">324</a>	InternalCalcField	rw	Is this a definition of an internally calculated field ?
<a href="#">325</a>	Precision	rw	Precision used in BCD (Binary Coded Decimal) fields
<a href="#">324</a>	Required	rw	Is the field required ?
<a href="#">326</a>	Size	rw	Size of the buffer needed to store the data of the field

### 10.28.4 TFieldDef.Create

Synopsis: Constructor for `TFieldDef`.

Declaration: `constructor create(ACollection: TCollection); Override`  
`constructor Create(AOwner: TFieldDefs;const AName: String;`  
`ADataType: TFieldType;ASize: Integer;`  
`ARequired: Boolean;AFieldNo: LongInt); Overload`

Visibility: public

Description: `Create` is the constructor for the `TFieldDef` class.

If a simple call is used, with a single argument `ACollection`, the inherited `Create` is called and the `Field` number is set to the incremented current index.

If the more complicated call is used, with multiple arguments, then after the inherited `Create` call, the `Name` (322), `datatype` (325), `size` (326), `precision` (325), `FieldNo` (324) and the `Required` (324) property are all set according to the passed arguments.

Errors: If a duplicate name is passed, then an exception will occur.

See also: `TFieldDef.name` (322), `TFieldDef.Datatype` (325), `TFieldDef.Size` (326), `TFieldDef.Precision` (325), `TFieldDef.FieldNo` (324), `TFieldDef.Required` (324)

### 10.28.5 TFieldDef.Destroy

Synopsis: Free the `TFieldDef` instance

Declaration: `destructor Destroy; Override`

Visibility: public

Description: `Destroy` destroys the `TFieldDef` instance. It simply calls the inherited destructor.

See also: `TFieldDef.Create` (322)

### 10.28.6 TFieldDef.Assign

Synopsis: Assign the contents of one `TFieldDef` instance to another.

Declaration: `procedure Assign(APersistent: TPersistent); Override`

Visibility: public

Description: `Assign` assigns all published properties of `APersistent` to the current instance, if `APersistent` is an instance of class `TFieldDef`.

Errors: If `APersistent` is not of class `TFieldDef` (322), then an exception will be raised.

### 10.28.7 TFieldDef.CreateField

Synopsis: Create `TField` instance based on definitions in current `TFieldDef` instance.

Declaration: `function CreateField(AOwner: TComponent) : TField`

Visibility: public

Description: `CreateField` determines, based on the `DataType` (325) what `TField` (298) descendent it should create, and then returns a newly created instance of this class. It sets the appropriate defaults for the `Size` (313), `FieldName` (317), `FieldNo` (311), `Precision` (298), `ReadOnly` (320) and `Required` (320) properties of the newly created instance. It should never be necessary to use this call in an end-user program, only `TDataset` descendent classes should use this call.

The newly created field is owned by the component instance passed in the `AOwner` parameter.

The `DefaultFieldClasses` (208) array is used to determine which `TField` Descendent class should be used when creating the `TField` instance, but descendents of `TDataset` may override the values in that array.

Errors:

See also: [DefaultFieldClasses \(208\)](#), [TField \(298\)](#)

### 10.28.8 TFieldDef.FieldClass

Synopsis: TField class used for this fielddef

Declaration: `Property FieldClass : TFieldClass`

Visibility: public

Access: Read

Description: `FieldClass` is the class of the `TField` instance that is created by the [CreateField \(323\)](#) class. The return value is retrieved from the `TDataset` instance the `TFieldDef` instance is associated with. If there is no `TDataset` instance available, the return value is `Nil`

See also: [TDataset \(250\)](#), [TFieldDef.CreateField \(323\)](#), [TField \(298\)](#)

### 10.28.9 TFieldDef.FieldNo

Synopsis: Field number

Declaration: `Property FieldNo : LongInt`

Visibility: public

Access: Read

Description: `FieldNo` is the number of the field in the data structure where the dataset contents comes from, for instance in a DBase file. If the underlying data layer does not support the concept of field number, a sequential number is assigned.

### 10.28.10 TFieldDef.InternalCalcField

Synopsis: Is this a definition of an internally calculated field ?

Declaration: `Property InternalCalcField : Boolean`

Visibility: public

Access: Read,Write

Description: `InternalCalc` is `True` if the `fielddef` instance represents an internally calculated field: for internally calculated fields, storage must be provided by the underlying data mechanism.

### 10.28.11 TFieldDef.Required

Synopsis: Is the field required ?

Declaration: `Property Required : Boolean`

Visibility: public

Access: Read,Write

**Description:** `Required` is set to `True` if the field requires a value when posting data to the dataset. If no value was entered, the dataset will raise an exception when the record is posted. The `Required` property is usually initialized based on the definition of the field in the underlying database. For SQL-based databases, a field declared as `NOT NULL` will result in a `Required` property of `True`.

#### 10.28.12 TFieldDef.Attributes

**Synopsis:** Additional attributes of the field.

**Declaration:** `Property Attributes : TFieldAttributes`

**Visibility:** published

**Access:** Read,Write

**Description:** `Attributes` contain additional attributes of the field. It shares the `faRequired` attribute with the `Required` property.

See also: `TFieldDef.Required` ([324](#))

#### 10.28.13 TFieldDef.DataType

**Synopsis:** Data type for the field

**Declaration:** `Property DataType : TFieldType`

**Visibility:** published

**Access:** Read,Write

**Description:** `DataType` contains the data type of the field's contents. Based on this property, the `FieldClass` property determines what kind of field class must be used to represent this field.

See also: `TFieldDef.FieldClass` ([324](#)), `TFieldDef.CreateField` ([323](#))

#### 10.28.14 TFieldDef.Precision

**Synopsis:** Precision used in BCD (Binary Coded Decimal) fields

**Declaration:** `Property Precision : LongInt`

**Visibility:** published

**Access:** Read,Write

**Description:** `Precision` is the number of digits used in a BCD (Binary Coded Decimal) field. It is not the number of digits after the decimal separator, but the total number of digits.

See also: `TFieldDef.Size` ([326](#))

### 10.28.15 TFieldDef.Size

Synopsis: Size of the buffer needed to store the data of the field

Declaration: `Property Size : Integer`

Visibility: published

Access: Read,Write

Description: `Size` indicates the size of the buffer needed to hold data for the field. For types with a fixed size (such as integer, word or data/time) the size can be zero: the buffer mechanism reserves automatically enough heap memory. For types which can have various sizes (blobs, string types, BCD types), the `Size` property tells the buffer mechanism how many bytes are needed to hold the data for the field.

See also: `TFieldDef.Precision` ([325](#)), `TFieldDef.DataType` ([325](#))

## 10.29 TFieldDefs

### 10.29.1 Description

`TFieldDefs` is used by each `TDataSet` instance to keep a description of the data that it manages; for each field in a record that makes up the underlying data, the `TFieldDefs` instance keeps an instance of `TFieldDef` that describes the field's contents. For any internally calculated fields of the dataset, a `TFieldDef` instance is kept as well. This collection is filled by descendent classes of `TDataSet` as soon as the dataset is opened; it is cleared when the dataset closes. After the collection was populated, the dataset creates `TField` instances based on all the definitions in the collections. If persistent fields were used, the contents of the fielddefs collection is compared to the field components that are present in the dataset. If the collection contains more field definitions than field components, these extra fields will not be available in the dataset.

### 10.29.2 Method overview

Page	Property	Description
<a href="#">327</a>	Add	Add a new field definition to the collection.
<a href="#">327</a>	AddFieldDef	Add new <code>TFieldDef</code>
<a href="#">327</a>	Assign	Copy all items from one dataset to another
<a href="#">326</a>	Create	Create a new instance of <code>TFieldDefs</code>
<a href="#">328</a>	Find	Find item by name
<a href="#">328</a>	MakeNameUnique	Create a unique field name starting from a base name
<a href="#">328</a>	Update	Force update of definitions

### 10.29.3 Property overview

Page	Property	Access	Description
<a href="#">328</a>	HiddenFields	rw	Should field instances be created for hidden fields
<a href="#">329</a>	Items	rw	Indexed access to the fielddef instances

### 10.29.4 TFieldDefs.Create

Synopsis: Create a new instance of `TFieldDefs`

Declaration: `constructor Create (ADataset: TDataSet)`



Visibility: public

Description: Create is used to create a new instance of TFieldDefs. The ADataset argument contains the dataset instance for which the collection contains the field definitions.

See also: TFieldDef ([322](#)), TDataset ([250](#))

### 10.29.5 TFieldDefs.Add

Synopsis: Add a new field definition to the collection.

Declaration: 

```
procedure Add(const AName: String; ADataType: TFieldType; ASize: Word;
              ARequired: Boolean); Overload
procedure Add(const AName: String; ADataType: TFieldType; ASize: Word)
              ; Overload
procedure Add(const AName: String; ADataType: TFieldType); Overload
```

Visibility: public

Description: Add adds a new item to the collection and fills in the Name, DataType, Size and Required properties of the newly added item with the provided parameters.

Errors: If an item with name AName already exists in the collection, then an exception will be raised.

See also: TFieldDefs.AddFieldDef ([327](#))

### 10.29.6 TFieldDefs.AddFieldDef

Synopsis: Add new TFieldDef

Declaration: 

```
function AddFieldDef : TFieldDef
```

Visibility: public

Description: AddFieldDef creates a new TFieldDef item and returns the instance.

See also: TFieldDefs.Add ([327](#))

### 10.29.7 TFieldDefs.Assign

Synopsis: Copy all items from one dataset to another

Declaration: 

```
procedure Assign(FieldDefs: TFieldDefs); Overload
```

Visibility: public

Description: Assign simply calls inherited Assign with the FieldDefs argument.

See also: TFieldDef.Assign ([323](#))

### 10.29.8 TFieldDefs.Find

Synopsis: Find item by name

Declaration: `function Find(const AName: String) : TFieldDef`

Visibility: public

Description: `Find` simply calls the inherited `TDefCollection.Find` (296) to find an item with name `AName` and typecasts the result to `TFieldDef`.

Errors:

See also: `TDefCollection.Find` (296), `TNamedItem.Name` (354)

### 10.29.9 TFieldDefs.Update

Synopsis: Force update of definitions

Declaration: `procedure Update; Overload`

Visibility: public

Description: `Update` notifies the dataset that the field definitions are updated, if it was not yet notified.

See also: `TDefCollection.Updated` (297)

### 10.29.10 TFieldDefs.MakeNameUnique

Synopsis: Create a unique field name starting from a base name

Declaration: `function MakeNameUnique(const AName: String) : String; Virtual`

Visibility: public

Description: `MakeNameUnique` uses `AName` to construct a name of a field that is not yet in the collection. If `AName` is not yet in the collection, then `AName` is returned. If a field definition with field name equal to `AName` already exists, then a new name is constructed by appending a sequence number to `AName` till the resulting name does not appear in the list of field definitions.

See also: `TFieldDefs.Find` (328), `TFieldDef.Name` (322)

### 10.29.11 TFieldDefs.HiddenFields

Synopsis: Should field instances be created for hidden fields

Declaration: `Property HiddenFields : Boolean`

Visibility: public

Access: Read, Write

Description: `HiddenFields` determines whether a field is created for fielddefs that have the `faHiddenCol` attribute set. If set to `False` (the default) then no `TField` instances will be created for hidden fields. If it is set to `True`, then a `TField` instance will be created for hidden fields.

See also: `TFieldDef.Attributes` (325)

### 10.29.12 TFieldDefs.Items

Synopsis: Indexed access to the fielddef instances

Declaration: `Property Items[Index: LongInt]: TFieldDef; default`

Visibility: public

Access: Read,Write

Description: `Items` provides zero-based indexed access to all `TFieldDef` instances in the collection. The index must vary between 0 and `Count-1`, or an exception will be raised.

See also: `TFieldDef` ([322](#))

## 10.30 Tfields

### 10.30.1 Description

`TFields` mimics a `TCollection` class for the `Fields` ([277](#)) property of `TDataset` ([250](#)) instance. Since `TField` ([298](#)) is a descendent of `TComponent`, it cannot be an item of a collection, and must be managed by another class.

### 10.30.2 Method overview

Page	Property	Description
<a href="#">330</a>	Add	Add a new field to the list
<a href="#">330</a>	CheckFieldName	Check field name for duplicate entries
<a href="#">330</a>	CheckFieldNames	Check a list of field names for duplicate entries
<a href="#">331</a>	Clear	Clear the list of fields
<a href="#">329</a>	Create	Create a new instance of <code>TFields</code>
<a href="#">330</a>	Destroy	Free the <code>TFields</code> instance
<a href="#">331</a>	FieldByName	Find a field based on its name
<a href="#">331</a>	FieldByNumber	Search field based on its fieldnumber
<a href="#">331</a>	FindField	Find a field based on its name
<a href="#">332</a>	GetEnumerator	
<a href="#">332</a>	GetFieldNames	Get the list of fieldnames
<a href="#">332</a>	IndexOf	Return the index of a field instance
<a href="#">332</a>	Remove	Remove an instance from the list

### 10.30.3 Property overview

Page	Property	Access	Description
<a href="#">333</a>	Count	r	Number of fields in the list
<a href="#">333</a>	Dataset	r	Dataset the fields belong to
<a href="#">333</a>	Fields	rw	Indexed access to the fields in the list

### 10.30.4 Tfields.Create

Synopsis: Create a new instance of `TFields`

Declaration: `constructor Create(ADataset: TDataSet)`

Visibility: public

**Description:** `Create` initializes a new instance of `TFields`. It stores the `ADataset` parameter, so it can be retrieved at any time in the `TFields.Dataset` (333) property, and initializes an internal list object to store the list of fields.

See also: `TDataset` (250), `TFields.Dataset` (333), `TField` (298)

### 10.30.5 Tfields.Destroy

**Synopsis:** Free the `TFields` instance

**Declaration:** `destructor Destroy; Override`

**Visibility:** `public`

**Description:** `Destroy` frees the field instances that it manages on behalf of the `Dataset` (333). After that it cleans up the internal structures and then calls the inherited destructor.

See also: `TDataset` (250), `TField` (298), `TFields.Clear` (331)

### 10.30.6 Tfields.Add

**Synopsis:** Add a new field to the list

**Declaration:** `procedure Add(Field: TField)`

**Visibility:** `public`

**Description:** `Add` must be used to add a new `TField` (298) instance to the list of fields. After a `TField` instance is added to the list, the `TFields` instance will free the field instance if it is cleared.

See also: `TField` (298), `TFields.Clear` (331)

### 10.30.7 Tfields.CheckFieldName

**Synopsis:** Check field name for duplicate entries

**Declaration:** `procedure CheckFieldName(const Value: String)`

**Visibility:** `public`

**Description:** `CheckFieldName` checks whether a field with name equal to `Value` (case insensitive) already appears in the list of fields (using `TFields.Find` (329)). If it does, then an `EDatabaseError` (220) exception is raised.

See also: `TField.FieldName` (317), `TFields.Find` (329)

### 10.30.8 Tfields.CheckFieldNames

**Synopsis:** Check a list of field names for duplicate entries

**Declaration:** `procedure CheckFieldNames(const Value: String)`

**Visibility:** `public`

**Description:** `CheckFieldNames` splits `Value` in a list of fieldnames, using semicolon as a separator. For each of the fieldnames obtained in this way, it calls `CheckFieldName` (330).

Errors: Spaces are not discarded, so leaving a space after or before a fieldname will not find the fieldname, and will yield a false negative result.

See also: [TField.FieldName \(317\)](#), [TFields.CheckFieldName \(330\)](#), [TFields.Find \(329\)](#)

### 10.30.9 Tfields.Clear

Synopsis: Clear the list of fields

Declaration: `procedure Clear`

Visibility: `public`

Description: `Clear` removes all [TField \(298\)](#) var instances from the list. All field instances are freed after they have been removed from the list.

See also: [TField \(298\)](#)

### 10.30.10 Tfields.FindField

Synopsis: Find a field based on its name

Declaration: `function FindField(const Value: String) : TField`

Visibility: `public`

Description: `FindField` searches the list of fields and returns the field instance whose [FieldName \(317\)](#) property matches `Value`. The search is performed case-insensitively. If no field instance is found, then `Nil` is returned.

See also: [TFields.FieldByName \(331\)](#)

### 10.30.11 Tfields.FieldByName

Synopsis: Find a field based on its name

Declaration: `function FieldByName(const Value: String) : TField`

Visibility: `public`

Description: `Fieldbyname` searches the list of fields and returns the field instance whose [FieldName \(317\)](#) property matches `Value`. The search is performed case-insensitively.

Errors: If no field instance is found, then an exception is raised. If this behaviour is undesired, use [TField.FindField \(298\)](#), where `Nil` is returned if no match is found.

See also: [TFields.FindField \(331\)](#), [TFields.FieldName \(329\)](#), [Tfields.FieldByNumber \(331\)](#), [TFields.IndexOf \(332\)](#)

### 10.30.12 Tfields.FieldByNumber

Synopsis: Search field based on its fieldnumber

Declaration: `function FieldByNumber(FieldNo: Integer) : TField`

Visibility: `public`

**Description:** `FieldByNumber` searches for the field whose `TField.FieldNo` (311) property matches the `FieldNo` parameter. If no such field is found, `Nil` is returned.

See also: `TFields.FieldByName` (331), `TFields.FindField` (331), `TFields.IndexOf` (332)

### 10.30.13 Tfields.GetEnumerator

**Declaration:** `function GetEnumerator : TFieldsEnumerator`

Visibility: public

### 10.30.14 Tfields.GetFieldNames

**Synopsis:** Get the list of fieldnames

**Declaration:** `procedure GetFieldNames(Values: TStrings)`

Visibility: public

**Description:** `GetFieldNames` fills `Values` with the fieldnames of all the fields in the list, each item in the list contains 1 fieldname. The list is cleared prior to filling it.

See also: `TField.FieldName` (317)

### 10.30.15 Tfields.IndexOf

**Synopsis:** Return the index of a field instance

**Declaration:** `function IndexOf(Field: TField) : LongInt`

Visibility: public

**Description:** `IndexOf` scans the list of fields and returns the index of the field instance in the list (it compares actual field instances, not field names). If the field does not appear in the list, -1 is returned.

See also: `TFields.FieldByName` (331), `TFields.FieldByNumber` (331), `TFields.FindField` (331)

### 10.30.16 Tfields.Remove

**Synopsis:** Remove an instance from the list

**Declaration:** `procedure Remove(Value: TField)`

Visibility: public

**Description:** `Remove` removes the field `Value` from the list. It does not free the field after it was removed. If the field is not in the list, then nothing happens.

See also: `Tields.Clear` (208)

### 10.30.17 Tfields.Count

Synopsis: Number of fields in the list

Declaration: `Property Count : Integer`

Visibility: public

Access: Read

Description: `Count` is the number of fields in the fieldlist. The items in the `Fields` (333) property are numbered from 0 to `Count-1`.

See also: `TFields.fields` (333)

### 10.30.18 Tfields.Dataset

Synopsis: Dataset the fields belong to

Declaration: `Property Dataset : TDataSet`

Visibility: public

Access: Read

Description: `Dataset` is the dataset instance that owns the fieldlist. It is set when the `TFields` (329) instance is created. This property is purely for informational purposes. When adding fields to the list, no check is performed whether the field's `Dataset` property matches this dataset.

See also: `TFields.Create` (329), `TField.Dataset` (310), `TDataSet` (250)

### 10.30.19 Tfields.Fields

Synopsis: Indexed access to the fields in the list

Declaration: `Property Fields[Index: Integer]: TField; default`

Visibility: public

Access: Read,Write

Description: `Fields` is the default property of the `TFields` class. It provides indexed access to the fields in the list: the index runs from 0 to `Count-1`.

Errors: Providing an index outside the allowed range will result in an `EListError` exception.

See also: `TFields.FieldName` (331)

## 10.31 TFieldsEnumerator

### 10.31.1 Method overview

Page	Property	Description
334	Create	
334	MoveNext	

### 10.31.2 Property overview

Page	Property	Access	Description
<a href="#">334</a>	Current	r	

### 10.31.3 TFieldsEnumerator.Create

Declaration: constructor Create(AFields: TFields)

Visibility: public

### 10.31.4 TFieldsEnumerator.MoveNext

Declaration: function MoveNext : Boolean

Visibility: public

### 10.31.5 TFieldsEnumerator.Current

Declaration: Property Current : TField

Visibility: public

Access: Read

## 10.32 TFloatField

### 10.32.1 Description

TFloatField is the class created when a dataset must manage floating point values of double precision. It exposes a few new properties such as Currency ([335](#)), MaxValue ([336](#)), MinValue ([336](#)) and overrides some TField ([298](#)) methods to work with floating point data.

It should never be necessary to create an instance of TFloatField manually, a field of this class will be instantiated automatically for each floating-point field when a dataset is opened.

### 10.32.2 Method overview

Page	Property	Description
<a href="#">335</a>	CheckRange	Check whether a value is in the allowed range of values for the field
<a href="#">335</a>	Create	Create a new instance of the TFloatField

### 10.32.3 Property overview

Page	Property	Access	Description
<a href="#">335</a>	Currency	rw	Is the field a currency field.
<a href="#">336</a>	MaxValue	rw	Maximum value for the field
<a href="#">336</a>	MinValue	rw	Minimum value for the field
<a href="#">336</a>	Precision	rw	Precision (number of digits) of the field in text representations
<a href="#">335</a>	Value	rw	Value of the field as a double type



### 10.32.4 TFloatField.Create

Synopsis: Create a new instance of the TFloatField

Declaration: constructor Create(AOwner: TComponent); Override

Visibility: public

Description: Create initializes a new instance of TFloatField. It calls the inherited constructor and then initializes some properties.

### 10.32.5 TFloatField.CheckRange

Synopsis: Check whether a value is in the allowed range of values for the field

Declaration: function CheckRange(AValue: Double) : Boolean

Visibility: public

Description: CheckRange returns True if AValue lies within the range defined by the MinValue (336) and MaxValue (336) properties. If the value lies outside of the allowed range, then False is returned.

See also: TFloatField.MaxValue (336), TFloatField.MinValue (336)

### 10.32.6 TFloatField.Value

Synopsis: Value of the field as a double type

Declaration: Property Value : Double

Visibility: public

Access: Read,Write

Description: Value is redefined by TFloatField to return a value of type Double. It returns the same value as TField.AsFloat (307)

See also: TField.AsFloat (307), TField.Value (314)

### 10.32.7 TFloatField.Currency

Synopsis: Is the field a currency field.

Declaration: Property Currency : Boolean

Visibility: published

Access: Read,Write

Description: Currency can be set to True to indicate that the field contains data representing an amount of currency. This affects the way the TField.DisplayText (311) and TField.Text (313) properties format the value of the field: if the Currency property is True, then these properties will format the value as a currency value (generally appending the currency sign) and if the Currency property is False, then they will format it as a normal floating-point value.

See also: TField.DisplayText (311), TField.Text (313), TNumericField.DisplayFormat (356), TNumericField.EditFormat (356)

**10.32.8 TFloatField.MaxValue**

Synopsis: Maximum value for the field

Declaration: `Property MaxValue : Double`

Visibility: published

Access: Read,Write

Description: `MaxValue` can be set to a value different from zero, it is then the maximum value for the field if set to any value different from zero. When setting the field's value, the value may not be larger than `MaxValue`. Any attempt to write a larger value as the field's content will result in an exception. By default `MaxValue` equals 0, i.e. any floating-point value is allowed.

If `MaxValue` is set, `MinField` (208) should also be set, because it will also be checked.

See also: `TFloatField.MinValue` (336)

**10.32.9 TFloatField.MinValue**

Synopsis: Minimum value for the field

Declaration: `Property MinValue : Double`

Visibility: published

Access: Read,Write

Description: `MinValue` can be set to a value different from zero, then it is the minimum value for the field. When setting the field's value, the value may not be less than `MinValue`. Any attempt to write a smaller value as the field's content will result in an exception. By default `MinValue` equals 0, i.e. any floating-point value is allowed.

If `MinValue` is set, `MaxField` (208) should also be set, because it will also be checked.

See also: `TFloatField.MaxValue` (336), `TFloatField.CheckRange` (335)

**10.32.10 TFloatField.Precision**

Synopsis: Precision (number of digits) of the field in text representations

Declaration: `Property Precision : LongInt`

Visibility: published

Access: Read,Write

Description: `Precision` is the maximum number of digits that should be used when the field is converted to a textual representation in `TField.Displaytext` (311) or `TField.Text` (313), it is used in the arguments to `FormatFloat` (??).

See also: `TField.Displaytext` (311), `TField.Text` (313), `#rtl.sysutils.FormatFloat` (??)

## 10.33 TGraphicField

### 10.33.1 Description

`TGraphicField` is the class used when a dataset must manage graphical BLOB data. (`TField.DataType` (310) equals `ftGraphic`). It initializes some of the properties of the `TField` (298) class. All methods to be able to work with graphical BLOB data have been implemented in the `TBlobField` (227) parent class.

It should never be necessary to create an instance of `TGraphicField` manually, a field of this class will be instantiated automatically for each graphical BLOB field when a dataset is opened.

### 10.33.2 Method overview

Page	Property	Description
<a href="#">337</a>	Create	Create a new instance of the <code>TGraphicField</code> class

### 10.33.3 TGraphicField.Create

Synopsis: Create a new instance of the `TGraphicField` class

Declaration: `constructor Create(AOwner: TComponent); Override`

Visibility: `public`

Description: `Create` initializes a new instance of the `TGraphicField` class. It calls the inherited destructor, and then sets some `TField` (298) properties to configure the instance for working with graphical BLOB values.

See also: `TField` (298)

## 10.34 TGUIDField

### 10.34.1 Description

`TGUIDField` is the class used when a dataset must manage native variant-typed data. (`TField.DataType` (310) equals `ftGUID`). It initializes some of the properties of the `TField` (298) class and overrides some of its methods to be able to work with variant data. It also adds a method to retrieve the field value as a native `TGUID` type.

It should never be necessary to create an instance of `TGUIDField` manually, a field of this class will be instantiated automatically for each GUID field when a dataset is opened.

### 10.34.2 Method overview

Page	Property	Description
<a href="#">338</a>	Create	Create a new instance of the <code>TGUIDField</code> class

### 10.34.3 Property overview

Page	Property	Access	Description
<a href="#">338</a>	AsGuid	rw	Field content as a GUID value

### 10.34.4 TGUIDField.Create

Synopsis: Create a new instance of the TGUIDField class

Declaration: constructor Create(AOwner: TComponent); Override

Visibility: public

Description: Create initializes a new instance of the TGUIDField class. It calls the inherited destructor, and then sets some TField (298) properties to configure the instance for working with GUID values.

See also: TField (298)

### 10.34.5 TGUIDField.AsGUID

Synopsis: Field content as a GUID value

Declaration: Property AsGUID : TGUID

Visibility: public

Access: Read,Write

Description: AsGUID can be used to get or set the field's content as a value of type TGUID.

See also: TField.AsString (308)

## 10.35 TIndexDef

### 10.35.1 Description

TIndexDef describes one index in a set of indexes of a TDataset (250) instance. The collection of indexes is described by the TIndexDefs (341) class. It just has the necessary properties to describe an index, but does not implement any functionality to maintain an index.

### 10.35.2 Method overview

Page	Property	Description
<a href="#">339</a>	Create	Create a new index definition
<a href="#">339</a>	Destroy	Remove the index from memory

### 10.35.3 Property overview

Page	Property	Access	Description
<a href="#">340</a>	CaseInsFields	rw	Fields in field list that are ordered case-insensitively
<a href="#">340</a>	DescFields	rw	Fields in field list that are ordered descending
<a href="#">339</a>	Expression	rw	Expression that makes up the index values
<a href="#">339</a>	Fields	rw	Fields making up the index
<a href="#">340</a>	Options	rw	Index options
<a href="#">341</a>	Source	rw	Source of the index

### 10.35.4 TIndexDef.Create

Synopsis: Create a new index definition

Declaration: `constructor Create(Owner: TIndexDefs; const AName: String;  
const TheFields: String; TheOptions: TIndexOptions)  
; Overload`

Visibility: public

Description: `Create` initializes a new `TIndexDef` (338) instance with the `AName` value as the index name, `AField` as the fields making up the index, and `TheOptions` as the options. `Owner` should be the `TIndexDefs` (341) instance to which the new `TIndexDef` can be added.

Errors: If an index with name `AName` already exists in the collection, an exception will be raised.

See also: `TIndexDefs` (341), `TIndexDef.Options` (340), `TIndexDef.Fields` (339)

### 10.35.5 TIndexDef.Destroy

Synopsis: Remove the index from memory

Declaration: `destructor Destroy; Override`

Visibility: public

Description: `Destroy` calls the inherited destructor, and removes the item from memory.

See also: `TIndexDef.Create` (339)

### 10.35.6 TIndexDef.Expression

Synopsis: Expression that makes up the index values

Declaration: `Property Expression : String`

Visibility: public

Access: Read, Write

Description: `Expression` is an SQL expression based on which the index values are computed. It is only used when `ixExpression` is in `TIndexDef.Options` (340)

See also: `TIndexDef.Options` (340), `TindexDef.Fields` (339)

### 10.35.7 TIndexDef.Fields

Synopsis: Fields making up the index

Declaration: `Property Fields : String`

Visibility: public

Access: Read, Write

**Description:** `Fields` is a list of fieldnames, separated by semicolons: the fields that make up the index, in case the index is not based on an expression. The list contains the names of all fields, regardless of whether the sort order for a particular field is ascending or descending. The fields should be in the right order, i.e. the first field is sorted on first, and so on.

The `TIndexDef.DescFields` (340) property can be used to determine the fields in the list that have a descending sort order. The `TIndexDef.CaseInsFields` (340) property determines which fields are sorted in a case-insensitive manner.

See also: `TIndexDef.DescFields` (340), `TIndexDef.CaseInsFields` (340), `TIndexDef.Expression` (339)

### 10.35.8 TIndexDef.CaseInsFields

**Synopsis:** Fields in field list that are ordered case-insensitively

**Declaration:** `Property CaseInsFields : String`

**Visibility:** public

**Access:** Read,Write

**Description:** `CaseInsFields` is a list of fieldnames, separated by semicolons. It contains the names of the fields in the `Fields` (339) property which are ordered in a case-insensitive manner. `CaseInsFields` may not contain fieldnames that do not appear in `Fields`.

See also: `TIndexDef.Fields` (339), `TIndexDef.Expression` (339), `TIndexDef.DescFields` (340)

### 10.35.9 TIndexDef.DescFields

**Synopsis:** Fields in field list that are ordered descending

**Declaration:** `Property DescFields : String`

**Visibility:** public

**Access:** Read,Write

**Description:** `DescFields` is a list of fieldnames, separated by semicolons. It contains the names of the fields in the `Fields` (339) property which are ordered in a descending manner. `DescFields` may not contain fieldnames that do not appear in `Fields`.

See also: `TIndexDef.Fields` (339), `TIndexDef.Expression` (339), `TIndexDef.DescFields` (340)

### 10.35.10 TIndexDef.Options

**Synopsis:** Index options

**Declaration:** `Property Options : TIndexOptions`

**Visibility:** public

**Access:** Read,Write

**Description:** `Options` describes the various properties of the index. This is usually filled by the dataset that provides the index definitions. For datasets that provide In-memory indexes, this should be set prior to creating the index: it cannot be changed once the index is created.

See the description of `TIndexOption` (216) for more information on the various available options.

See also: `TIndexOptions` (216)

### 10.35.11 TIndexDef.Source

Synopsis: Source of the index

Declaration: `Property Source : String`

Visibility: public

Access: Read,Write

Description: `Source` describes where the index comes from. This is a property for the convenience of the various datasets that provide indexes: they can use it to describe the source of the index.

## 10.36 TIndexDefs

### 10.36.1 Description

`TIndexDefs` is used to keep a collection of index (sort order) definitions. It can be used by classes that provide in-memory or on-disk indexes to provide a list of available indexes.

### 10.36.2 Method overview

Page	Property	Description
<a href="#">342</a>	Add	Add a new index definition with given name and options
<a href="#">342</a>	AddIndexDef	Add a new, empty, index definition
<a href="#">341</a>	Create	Create a new <code>TIndexDefs</code> instance
<a href="#">342</a>	Destroy	Remove the indexdefs from memory.
<a href="#">342</a>	Find	Find an index by name
<a href="#">343</a>	FindIndexForFields	Find index definition based on field names
<a href="#">343</a>	GetIndexForFields	Get index definition based on field names
<a href="#">343</a>	Update	Called whenever one of the items changes

### 10.36.3 Property overview

Page	Property	Access	Description
<a href="#">343</a>	Items	rw	Indexed access to the index definitions

### 10.36.4 TIndexDefs.Create

Synopsis: Create a new `TIndexDefs` instance

Declaration: `constructor Create(ADataset: TDataSet); Virtual; Overload`

Visibility: public

Description: `Create` initializes a new instance of the `TIndexDefs` class. It simply calls the inherited destructor with the appropriate item class, `TIndexDef` ([338](#)).

See also: `TIndexDef` ([338](#)), `TIndexDefs.Destroy` ([342](#))

### 10.36.5 TIndexDefs.Destroy

Synopsis: Remove the indexdefs from memory.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` removes the indexdefs from memory. If the `TIndexDefs` instance is created by a `TDataset` (250) instance, the dataset instance will also destroy it.

See also: `TIndexDefs.Create` (341)

### 10.36.6 TIndexDefs.Add

Synopsis: Add a new index definition with given name and options

Declaration: `procedure Add(const Name: String; const Fields: String;  
Options: TIndexOptions)`

Visibility: `public`

Description: `Add` adds a new `TIndexDef` (338) instance to the list of indexes. It initializes the index definition properties `Name`, `Fields` and `Options` with the values given in the parameters with the same names.

Errors: If an index with the same `Name` already exists in the list of indexes, an exception will be raised.

See also: `TIndexDef` (338), `TNamedItem.Name` (354), `TIndexDef.Fields` (339), `TIndexDef.Options` (340), `TIndexDefs.AddIndexDef` (342)

### 10.36.7 TIndexDefs.AddIndexDef

Synopsis: Add a new, empty, index definition

Declaration: `function AddIndexDef : TIndexDef`

Visibility: `public`

Description: `AddIndexDef` adds a new `TIndexDef` (338) instance to the list of indexes, and returns the newly created instance. It does not initialize any of the properties of the new index definition.

See also: `TIndexDefs.Add` (342)

### 10.36.8 TIndexDefs.Find

Synopsis: Find an index by name

Declaration: `function Find(const IndexName: String) : TIndexDef`

Visibility: `public`

Description: `Find` overloads the `TDefCollection.Find` (296) method to search and return a `TIndexDef` (338) instance based on the name. The search is case-insensitive and returns `Nil` if no matching index definition was found.

Errors:

See also: `TIndexDef` (338), `TDefCollection.Find` (296), `TIndexDefs.FindIndexForFields` (343)



### 10.36.9 TIndexDefs.FindIndexForFields

Synopsis: Find index definition based on field names

Declaration: `function FindIndexForFields(const Fields: String) : TIndexDef`

Visibility: public

Description: `FindIndexForFields` searches in the list of indexes for an index whose `TIndexDef.Fields` (339) property matches the list of fields in `Fields`. If it finds an index definition, then it returns the found instance.

Errors: If no matching definition is found, an exception is raised. This is different from other `Find` functionality, where `Find` usually returns `Nil` if nothing is found.

See also: `TIndexDef` (338), `TIndexDefs.Find` (342), `TIndexDefs.GetIndexForFields` (343)

### 10.36.10 TIndexDefs.GetIndexForFields

Synopsis: Get index definition based on field names

Declaration: `function GetIndexForFields(const Fields: String;  
CaseInsensitive: Boolean) : TIndexDef`

Visibility: public

Description: `GetIndexForFields` searches in the list of indexes for an index whose `TIndexDef.Fields` (339) property matches the list of fields in `Fields`. If `CaseInsensitive` is `True` it only searches for case-sensitive indexes. If it finds an index definition, then it returns the found instance. If it does not find a matching definition, `Nil` is returned.

See also: `TIndexDef` (338), `TIndexDefs.Find` (342), `TIndexDefs.FindIndexForFields` (343)

### 10.36.11 TIndexDefs.Update

Synopsis: Called whenever one of the items changes

Declaration: `procedure Update; Virtual; Overload`

Visibility: public

Description: `Update` can be called to have the dataset update its index definitions.

### 10.36.12 TIndexDefs.Items

Synopsis: Indexed access to the index definitions

Declaration: `Property Items[Index: Integer]: TIndexDef; default`

Visibility: public

Access: Read, Write

Description: `Items` is redefined by `TIndexDefs` using `TIndexDef` as the type for the elements. It is the default property of the `TIndexDefs` class.

See also: `TIndexDef` (338)

## 10.37 TLargeIntField

### 10.37.1 Description

`TLargeIntField` is instantiated when a dataset must manage a field with 64-bit signed data: the data type `ftLargeInt`. It overrides some methods of `TField` (298) to handle `int64` data, and sets some of the properties to values for `int64` data. It also introduces some methods and properties specific to 64-bit integer data such as `MinValue` (345) and `MaxValue` (208).

It should never be necessary to create an instance of `TLargeIntField` manually, a field of this class will be instantiated automatically for each `int64` field when a dataset is opened.

### 10.37.2 Method overview

Page	Property	Description
<a href="#">344</a>	<code>CheckRange</code>	Check whether a values falls within the allowed range
<a href="#">344</a>	<code>Create</code>	Create a new instance of the <code>TLargeIntField</code> class

### 10.37.3 Property overview

Page	Property	Access	Description
<a href="#">345</a>	<code>MaxValue</code>	rw	Maximum value for the field
<a href="#">345</a>	<code>MinValue</code>	rw	Minimum value for the field
<a href="#">345</a>	<code>Value</code>	rw	Field contents as a 64-bit integer value

### 10.37.4 TLargeIntField.Create

Synopsis: Create a new instance of the `TLargeIntField` class

Declaration: `constructor Create(AOwner: TComponent); Override`

Visibility: `public`

Description: `Create` initializes a new instance of the `TLargeIntField` class: it calls the inherited constructor and then initializes the various properties of `Tfield` (298) and `MinValue` (345) and `MaxValue` (208).

See also: `TField` (298), `TLargeIntField.MinValue` (345), `TLargeInField.MaxValue` (208)

### 10.37.5 TLargeIntField.CheckRange

Synopsis: Check whether a values falls within the allowed range

Declaration: `function CheckRange(AValue: LargeInt) : Boolean`

Visibility: `public`

Description: `CheckRange` returns `True` if `AValue` lies within the range defined by the `MinValue` (345) and `MaxValue` (345) properties. If the value lies outside of the allowed range, then `False` is returned.

See also: `TLargeIntField.MaxValue` (345), `TLargeIntField.MinValue` (345)

### 10.37.6 TLargeIntField.Value

Synopsis: Field contents as a 64-bit integer value

Declaration: `Property Value : LargeInt`

Visibility: public

Access: Read,Write

Description: `Value` is redefined by `TLargeIntField` as a 64-bit integer value. It returns the same value as `TField.AsLargeInt` (307).

See also: `TField.Value` (314), `TField.AsLargeInt` (307)

### 10.37.7 TLargeIntField.MaxValue

Synopsis: Maximum value for the field

Declaration: `Property MaxValue : LargeInt`

Visibility: published

Access: Read,Write

Description: `MaxValue` is the maximum value for the field if set to any value different from zero. When setting the field's value, the value may not be larger than `MaxValue`. Any attempt to write a larger value as the field's content will result in an exception. By default `MaxValue` equals 0, i.e. any integer value is allowed.

If `MaxValue` is set, `MinField` (208) should also be set, because it will also be checked.

See also: `TLargeIntField.MinValue` (345)

### 10.37.8 TLargeIntField.MinValue

Synopsis: Minimum value for the field

Declaration: `Property MinValue : LargeInt`

Visibility: published

Access: Read,Write

Description: `MinValue` is the minimum value for the field. When setting the field's value, the value may not be less than `MinValue`. Any attempt to write a smaller value as the field's content will result in an exception. By default `MinValue` equals 0, i.e. any integer value is allowed.

If `MinValue` is set, `MaxField` (208) should also be set, because it will also be checked.

See also: `TLargeIntField.MaxValue` (345)

## 10.38 TLongintField

### 10.38.1 Description

TLongintField is instantiated when a dataset must manage a field with 32-bit signed data: the data type `ftInteger`. It overrides some methods of TField (298) to handle integer data, and sets some of the properties to values for integer data. It also introduces some methods and properties specific to integer data such as MinValue (347) and MaxValue (347).

It should never be necessary to create an instance of TLongintField manually, a field of this class will be instantiated automatically for each integer field when a dataset is opened.

### 10.38.2 Method overview

Page	Property	Description
<a href="#">346</a>	CheckRange	Check whether a valid is in the allowed range of values for the field
<a href="#">346</a>	Create	Create a new instance of TLongintField

### 10.38.3 Property overview

Page	Property	Access	Description
<a href="#">347</a>	MaxValue	rw	Maximum value for the field
<a href="#">347</a>	MinValue	rw	Minimum value for the field
<a href="#">347</a>	Value	rw	Value of the field as longint

### 10.38.4 TLongintField.Create

Synopsis: Create a new instance of TLongintField

Declaration: `constructor Create(AOwner: TComponent); Override`

Visibility: public

Description: Create initializes a new instance of TLongintField. After calling the inherited constructor, it initializes the MinValue (347) and MaxValue (347) properties.

See also: TField (298), TLongintField.MaxValue (347), TLongintField.MinValue (347)

### 10.38.5 TLongintField.CheckRange

Synopsis: Check whether a valid is in the allowed range of values for the field

Declaration: `function CheckRange(AValue: LongInt) : Boolean`

Visibility: public

Description: CheckRange returns True if AValue lies within the range defined by the MinValue (347) and MaxValue (347) properties. If the value lies outside of the allowed range, then False is returned.

See also: TLongintField.MaxValue (347), TLongintField.MinValue (347)

### 10.38.6 TLongintField.Value

Synopsis: Value of the field as longint

Declaration: `Property Value : LongInt`

Visibility: public

Access: Read,Write

Description: `Value` is redefined by `TLongintField` as a 32-bit signed integer value. It returns the same value as the `TField.AsInteger` (308) property.

See also: `TField.Value` (314)

### 10.38.7 TLongintField.MaxValue

Synopsis: Maximum value for the field

Declaration: `Property MaxValue : LongInt`

Visibility: published

Access: Read,Write

Description: `MaxValue` is the maximum value for the field. When setting the field's value, the value may not be larger than `MaxValue`. Any attempt to write a larger value as the field's content will result in an exception. By default `MaxValue` equals `MaxInt`, i.e. any integer value is allowed.

See also: `TLongintField.MinValue` (347)

### 10.38.8 TLongintField.MinValue

Synopsis: Minimum value for the field

Declaration: `Property MinValue : LongInt`

Visibility: published

Access: Read,Write

Description: `MinValue` is the minimum value for the field. When setting the field's value, the value may not be less than `MinValue`. Any attempt to write a smaller value as the field's content will result in an exception. By default `MinValue` equals `-MaxInt`, i.e. any integer value is allowed.

See also: `TLongintField.MaxValue` (347)

## 10.39 TLookupList

### 10.39.1 Description

`TLookupList` is a list object used for storing values of lookup operations by lookup fields. There should be no need to create an instance of `TLookupList` manually, the `TField` instance will create an instance of `TLookupList` on demand.

**10.39.2 Method overview**

Page	Property	Description
<a href="#">348</a>	Add	Add a key, value pair to the list
<a href="#">348</a>	Clear	Remove all key, value pairs from the list
<a href="#">348</a>	Create	Create a new instance of TLookupList.
<a href="#">348</a>	Destroy	Free a TLookupList instance from memory
<a href="#">349</a>	FirstKeyByValue	Find the first key that matches a value
<a href="#">349</a>	ValueOfKey	Look up value based on a key
<a href="#">349</a>	ValuesToStrings	Convert values to stringlist

**10.39.3 TLookupList.Create**

Synopsis: Create a new instance of TLookupList.

Declaration: `constructor Create`

Visibility: `public`

Description: `Create` sets up the necessary structures to manage a list of lookup values for a lookup field.

See also: `TLookupList.Destroy` ([348](#))

**10.39.4 TLookupList.Destroy**

Synopsis: Free a TLookupList instance from memory

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` frees all resources (mostly memory) allocated by the lookup list, and calls then the inherited destructor.

See also: `TLookupList.Create` ([208](#))

**10.39.5 TLookupList.Add**

Synopsis: Add a key, value pair to the list

Declaration: `procedure Add(const AKey: Variant; const AValue: Variant)`

Visibility: `public`

Description: `Add` will add the value `AValue` to the list and associate it with key `AKey`. The same key cannot be added twice.

See also: `TLookupList.Clear` ([348](#))

**10.39.6 TLookupList.Clear**

Synopsis: Remove all key, value pairs from the list

Declaration: `procedure Clear`

Visibility: `public`

Description: `Clear` removes all keys and associated values from the list.

See also: `TLookupList.Add` ([348](#))

### 10.39.7 TLookupList.FirstKeyByValue

Synopsis: Find the first key that matches a value

Declaration: `function FirstKeyByValue(const AValue: Variant) : Variant`

Visibility: public

Description: `FirstKeyByValue` does a reverse lookup: it returns the first key value in the list that matches the `AValue` value. If none is found, `Null` is returned. This mechanism is quite slow, as a linear search is performed.

Errors: If no key is found, `Null` is returned.

See also: `TLookupList.ValueOfKey` (349)

### 10.39.8 TLookupList.ValueOfKey

Synopsis: Look up value based on a key

Declaration: `function ValueOfKey(const AKey: Variant) : Variant`

Visibility: public

Description: `ValueOfKey` does a value lookup based on a key: it returns the value in the list that matches the `AKey` key. If none is found, `Null` is returned. This mechanism is quite slow, as a linear search is performed.

See also: `TLookupList.FirstKeyByValue` (349), `TLookupList.Add` (348)

### 10.39.9 TLookupList.ValuesToStrings

Synopsis: Convert values to stringlist

Declaration: `procedure ValuesToStrings(AStrings: TStrings)`

Visibility: public

Description: `ValuesToStrings` converts the list of values to a stringlist, so they can be used e.g. in a drop-down list.

See also: `TLookupList.ValueOfKey` (349)

## 10.40 TMasterDataLink

### 10.40.1 Description

`TMasterDataLink` is a `TDatalink` descendent which handles master-detail relations. It can be used in `TDataset` (250) descendents that must have master-detail functionality: the detail dataset creates an instance of `TMasterDataLink` to point to the master dataset, which is subsequently available through the `TDatalink.Dataset` (249) property.

The class also provides functionality for keeping a list of fields that make up the master-detail functionality, in the `TMasterDataLink.FieldName` (350) and `TMasterDataLink.Fields` (351) properties.

This class should never be used in application code.

### 10.40.2 Method overview

Page	Property	Description
<a href="#">350</a>	Create	Create a new instance of TMasterDataLink
<a href="#">350</a>	Destroy	Free the datalink instance from memory

### 10.40.3 Property overview

Page	Property	Access	Description
<a href="#">350</a>	FieldNames	rw	List of fieldnames that make up the master-detail relationship
<a href="#">351</a>	Fields	r	List of fields as specified in FieldNames
<a href="#">351</a>	OnMasterChange	rw	Called whenever the master dataset data changes
<a href="#">351</a>	OnMasterDisable	rw	Called whenever the master dataset is disabled

### 10.40.4 TMasterDataLink.Create

Synopsis: Create a new instance of TMasterDataLink

Declaration: `constructor Create(ADataset: TDataSet); Virtual`

Visibility: `public`

Description: `Create` initializes a new instance of TMasterDataLink. The `ADataset` parameter is the detail dataset in the master-detail relation: it is saved in the `DetailDataset` ([298](#)) property. The master dataset must be set through the `DataSource` ([249](#)) property, and is usually set by the application programmer.

See also: `TDetailDataLink.DetailDataset` ([298](#)), `TDatalink.Datasource` ([249](#))

### 10.40.5 TMasterDataLink.Destroy

Synopsis: Free the datalink instance from memory

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` cleans up the resources used by TMasterDataLink and then calls the inherited destructor.

See also: `TMasterDataLink.Create` ([350](#))

### 10.40.6 TMasterDataLink.FieldNames

Synopsis: List of fieldnames that make up the master-detail relationship

Declaration: `Property FieldNames : String`

Visibility: `public`

Access: `Read, Write`

Description: `FieldNames` is a semicolon-separated list of fieldnames in the master dataset (`TDatalink.Dataset` ([249](#))) on which the master-detail relationship is based. Setting this property will fill the `TMasterDataLink.Fields` ([351](#)) property with the field instances of the master dataset.

See also: `TMasterDataLink.Fields` ([351](#)), `TDatalink.Dataset` ([249](#)), `TDataset.GetFieldList` ([264](#))



### 10.40.7 TMasterDataLink.Fields

Synopsis: List of fields as specified in `FieldNames`

Declaration: `Property Fields : TList`

Visibility: `public`

Access: `Read`

Description: `Fields` is filled with the `TField` (298) instances from the master dataset (`TDatalink.Dataset` (249)) when the `FieldNames` (350) property is set, and when the master dataset opens.

See also: `TField` (298), `TMasterDataLink.FieldNames` (350)

### 10.40.8 TMasterDataLink.OnMasterChange

Synopsis: Called whenever the master dataset data changes

Declaration: `Property OnMasterChange : TNotifyEvent`

Visibility: `public`

Access: `Read,Write`

Description: `OnMasterChange` is called whenever the field values in the master dataset changes, i.e. when it becomes active, or when the current record changes. If the `TMasterDataLink.Fields` (351) list is empty, `TMasterDataLink.OnMasterDisable` (351) is called instead.

See also: `TMasterDataLink.OnMasterDisable` (351)

### 10.40.9 TMasterDataLink.OnMasterDisable

Synopsis: Called whenever the master dataset is disabled

Declaration: `Property OnMasterDisable : TNotifyEvent`

Visibility: `public`

Access: `Read,Write`

Description: `OnMasterDisable` is called whenever the master dataset is disabled, or when it is active and the field list is empty.

See also: `TMasterDataLink.OnMasterChange` (351)

## 10.41 TMasterParamsDataLink

### 10.41.1 Description

`TMasterParamsDataLink` is a `TDataLink` (245) descendent that can be used to establish a master-detail relationship between 2 `TDataset` instances where the detail dataset is parametrized using a `TParams` instance. It takes care of closing and opening the detail dataset and copying the parameter values from the master dataset whenever the data in the master dataset changes.

**10.41.2 Method overview**

Page	Property	Description
<a href="#">352</a>	CopyParamsFromMaster	Copy parameter values from master dataset.
<a href="#">352</a>	Create	Initialize a new TMasterParamsDataLink instance
<a href="#">352</a>	RefreshParamNames	Refresh the list of parameter names

**10.41.3 Property overview**

Page	Property	Access	Description
<a href="#">353</a>	Params	rw	Parameters of detail dataset.

**10.41.4 TMasterParamsDataLink.Create**

Synopsis: Initialize a new TMasterParamsDataLink instance

Declaration: `constructor Create(ADataset: TDataSet); Override`

Visibility: `public`

Description: `Create` first calls the inherited constructor using `ADataset`, and then looks for a property named `Params` of type `TParams` ([368](#)) in the published properties of `ADataset` and assigns it to the `Params` ([353](#)) property.

See also: `TDataSet` ([250](#)), `TParams` ([368](#)), `TMasterParamsDataLink.Params` ([353](#))

**10.41.5 TMasterParamsDataLink.RefreshParamNames**

Synopsis: Refresh the list of parameter names

Declaration: `procedure RefreshParamNames; Virtual`

Visibility: `public`

Description: `RefreshParamNames` scans the `Params` ([353](#)) property and sets the `FieldNames` ([350](#)) property to the list of parameter names.

See also: `TMasterParamsDataLink.Params` ([353](#)), `TMasterDataLink.FieldNames` ([350](#))

**10.41.6 TMasterParamsDataLink.CopyParamsFromMaster**

Synopsis: Copy parameter values from master dataset.

Declaration: `procedure CopyParamsFromMaster(CopyBound: Boolean); Virtual`

Visibility: `public`

Description: `CopyParamsFromMaster` calls `TParams.CopyParamValuesFromDataset` ([371](#)), passing it the master dataset: it provides the parameters of the detail dataset with their new values. If `CopyBound` is `false`, then only parameters with their `Bound` ([364](#)) property set to `False` are copied. If it is `True` then the value is set for all parameters.

Errors: If the master dataset does not have a corresponding field for each parameter, then an exception will be raised.

See also: `TParams.CopyParamValuesFromDataset` ([371](#)), `TParam.Bound` ([364](#))

### 10.41.7 TMasterParamsDataLink.Params

Synopsis: Parameters of detail dataset.

Declaration: `Property Params : TParams`

Visibility: `public`

Access: `Read,Write`

Description: `Params` is the `TParams` instance of the detail dataset. If the detail dataset contains a property named `Params` of type `TParams`, then it will be set when the `TMasterParamsDataLink` instance was created. If the property is not published, or has another name, then the `Params` property must be set in code.

See also: `Tparams` (368), `TMasterParamsDataLink.Create` (352)

## 10.42 TMemoField

### 10.42.1 Description

`TMemoField` is the class used when a dataset must manage memo (Text BLOB) data. (`TField.DataType` (310) equals `ftMemo`). It initializes some of the properties of the `TField` (298) class. All methods to be able to work with memo fields have been implemented in the `TBlobField` (227) parent class.

It should never be necessary to create an instance of `TMemoField` manually, a field of this class will be instantiated automatically for each memo field when a dataset is opened.

### 10.42.2 Method overview

Page	Property	Description
<a href="#">353</a>	<code>Create</code>	Create a new instance of the <code>TMemoField</code> class

### 10.42.3 Property overview

Page	Property	Access	Description
<a href="#">354</a>	<code>Transliterate</code>		Should the contents of the field be transliterated

### 10.42.4 TMemoField.Create

Synopsis: Create a new instance of the `TMemoField` class

Declaration: `constructor Create(AOwner: TComponent); Override`

Visibility: `public`

Description: `Create` initializes a new instance of the `TMemoField` class. It calls the inherited destructor, and then sets some `TField` (298) properties to configure the instance for working with memo values.

See also: `TField` (298)

### 10.42.5 TMemoField.Transliterate

Synopsis: Should the contents of the field be transliterated

Declaration: `Property Transliterate :`

Visibility: `published`

Access:

Description: `Transliterate` is redefined from `TBlobField.Transliterate` (230) with a default value of `true`.

See also: `TBlobField.Transliterate` (230), `TStringField.Transliterate` (374), `TDataset.Translate` (270)

## 10.43 TNamedItem

### 10.43.1 Description

`NamedItem` is a `TCollectionItem` (??) descendent which introduces a `Name` (354) property. It automatically returns the value of the `Name` property as the value of the `DisplayName` (354) property.

### 10.43.2 Property overview

Page	Property	Access	Description
354	<code>DisplayName</code>	<code>rw</code>	Display name
354	<code>Name</code>	<code>rw</code>	Name of the item

### 10.43.3 TNamedItem.DisplayName

Synopsis: Display name

Declaration: `Property DisplayName : String`

Visibility: `public`

Access: `Read,Write`

Description: `DisplayName` is declared in `TCollectionItem` (??), and is made public in `TNamedItem`. The value equals the value of the `Name` (354) property.

See also: `TNamedItem.Name` (354)

### 10.43.4 TNamedItem.Name

Synopsis: Name of the item

Declaration: `Property Name : String`

Visibility: `published`

Access: `Read,Write`

Description: `Name` is the name of the item in the collection. This property is also used as the value for the `DisplayName` (354) property. If the `TNamedItem` item is owned by a `TDefCollection` (296) collection, then the name must be unique, i.e. each `Name` value may appear only once in the collection.

See also: `TNamedItem.DisplayName` (354), `TDefCollection` (296)

## 10.44 TNumericField

### 10.44.1 Description

TNumericField is an abstract class which overrides some of the methods of TField (298) to handle numerical data. It also introduces or publishes a couple of properties that are only relevant in the case of numerical data, such as TNumericalField.DisplayFormat (208) and TNumericalField.EditFormat (208).

Since TNumericalField is an abstract class, it must never be instantiated directly. Instead one of the descendent classes should be created.

### 10.44.2 Method overview

Page	Property	Description
<a href="#">355</a>	Create	Create a new instance of TNumericField

### 10.44.3 Property overview

Page	Property	Access	Description
<a href="#">355</a>	Alignment		Alignment of the field
<a href="#">356</a>	DisplayFormat	rw	Format string for display of numerical data
<a href="#">356</a>	EditFormat	rw	Format string for editing of numerical data

### 10.44.4 TNumericField.Create

Synopsis: Create a new instance of TNumericField

Declaration: `constructor Create(AOwner: TComponent); Override`

Visibility: `public`

Description: `Create` calls the inherited constructor and then initializes the `TField.Alignment` (315) property with

See also: `TField.Alignment` (315)

### 10.44.5 TNumericField.Alignment

Synopsis: Alignment of the field

Declaration: `Property Alignment :`

Visibility: `published`

Access:

Description: `Alignment` is published by TNumericalField with `taRightJustify` as a default value.

See also: `TField.Alignment` (315)

### 10.44.6 TNumericField.DisplayFormat

Synopsis: Format string for display of numerical data

Declaration: `Property DisplayFormat : String`

Visibility: published

Access: Read,Write

Description: `DisplayFormat` specifies a format string (such as used by the `Format (??)` and `FormatFloat (??)` functions) for display purposes: the `TField.DisplayText (311)` property will use this property to format the field's value. Which formatting function (and, consequently, which format can be entered) is used depends on the descendent of the `TNumericField` class.

See also: `#rtl.sysutils.Format (??)`, `#rtl.sysutils.FormatFloat (??)`, `TField.DisplayText (311)`, `TNumericField.EditFormat (356)`

### 10.44.7 TNumericField.EditFormat

Synopsis: Format string for editing of numerical data

Declaration: `Property EditFormat : String`

Visibility: published

Access: Read,Write

Description: `EditFormat` specifies a format string (such as used by the `Format (??)` and `FormatFloat (??)` functions) for editing purposes: the `TField.Text (313)` property will use this property to format the field's value. Which formatting function (and, consequently, which format can be entered) is used depends on the descendent of the `TNumericField` class.

See also: `#rtl.sysutils.Format (??)`, `#rtl.sysutils.FormatFloat (??)`, `TField.Text (313)`, `TNumericField.DisplayFormat (356)`

## 10.45 TParam

### 10.45.1 Description

`TParam` is one item in a `TParams (368)` collection. It describes the name (`TParam.Name (366)`), type (`ParamType (367)`) and value (`TParam.Value (365)`) of a parameter in a parametrized query or stored procedure. Under normal circumstances, it should never be necessary to create a `TParam` instance manually; the `TDataset (250)` descendent that owns the parameters should have created all necessary `TParam` instances.

### 10.45.2 Method overview

Page	Property	Description
358	Assign	Assign one parameter instance to another
358	AssignField	Copy value from field instance
359	AssignFieldValue	Assign field value to the parameter.
359	AssignFromField	Copy field type and value
358	AssignToField	Assign parameter value to field
359	Clear	Clear the parameter value
357	Create	Create a new parameter value
359	GetData	Get the parameter value from a memory buffer
360	GetDataSize	Return the size of the data.
360	LoadFromFile	Load a parameter value from file
360	LoadFromStream	Load a parameter value from stream
360	SetBlobData	Set BLOB data
361	SetData	Set the parameter value from a buffer

### 10.45.3 Property overview

Page	Property	Access	Description
361	AsBlob	rw	Return parameter value as a blob
361	AsBoolean	rw	Get/Set parameter value as a boolean value
361	AsCurrency	rw	Get/Set parameter value as a currency value
362	AsDate	rw	Get/Set parameter value as a date (TDateTime) value
362	AsDateTime	rw	Get/Set parameter value as a date/time (TDateTime) value
362	AsFloat	rw	Get/Set parameter value as a floating-point value
362	AsInteger	rw	Get/Set parameter value as an integer (32-bit) value
363	AsLargeInt	rw	Get/Set parameter value as a 64-bit integer value
363	AsMemo	rw	Get/Set parameter value as a memo (string) value
363	AsSmallInt	rw	Get/Set parameter value as a smallint value
363	AsString	rw	Get/Set parameter value as a string value
364	AsTime	rw	Get/Set parameter value as a time (TDateTime) value
366	AsWideString	rw	Get/Set the value as a widestring
364	AsWord	rw	Get/Set parameter value as a word value
364	Bound	rw	Is the parameter value bound (set to fixed value)
364	Dataset	r	Dataset to which this parameter belongs
366	DataType	rw	Data type of the parameter
365	IsNull	r	Is the parameter empty
366	Name	rw	Name of the parameter
365	NativeStr	rw	No description available
366	NumericScale	rw	Numeric scale
367	ParamType	rw	Type of parameter
367	Precision	rw	Precision of the BCD value
367	Size	rw	Size of the parameter
365	Text	rw	Read or write the value of the parameter as a string
365	Value	rws	Value as a variant

### 10.45.4 TParam.Create

Synopsis: Create a new parameter value

Declaration: `constructor Create(ACollection: TCollection); Override; Overload`  
`constructor Create(AParams: TParams; AParamType: TParamType); Overload`  
`; Reintroduce`

Visibility: public

**Description:** `Create` first calls the inherited `create`, and then initializes the parameter properties. The first form creates a default parameter, the second form is a convenience function and initializes a parameter of a certain kind (`AParamType`), in which case the owning `TParams` collection must be specified in `AParams`

See also: `TParams` (368)

### 10.45.5 TParam.Assign

**Synopsis:** Assign one parameter instance to another

**Declaration:** `procedure Assign(Source: TPersistent); Override`

Visibility: public

**Description:** `Assign` copies the `Name`, `ParamType`, `Bound`, `Value`, `SizePrecision` and `NumericScale` properties from `ASource` if it is of type `TParam`. If `Source` is of type `TField` (298), then it is passed to `TParam.AssignField` (358). If `Source` is of type `TStrings`, then it is assigned to `TParams.AsMemo` (368).

**Errors:** If `Source` is not of type `TParam`, `TField` or `TStrings`, an exception will be raised.

See also: `TField` (298), `TParam.Name` (366), `TParam.Bound` (364), `TParam.NumericScale` (366), `TParam.ParamType` (367), `TParam.value` (365), `TParam.Size` (367), `TParam.AssignField` (358), `TParam.AsMemo` (363)

### 10.45.6 TParam.AssignField

**Synopsis:** Copy value from field instance

**Declaration:** `procedure AssignField(Field: TField)`

Visibility: public

**Description:** `AssignField` copies the `Field`, `FieldName` (317) and `Value` (314) to the parameter instance. The parameter is bound after this operation. If `Field` is `Nil` then the parameter name and value are cleared.

See also: `TParam.assign` (358), `TParam.AssignToField` (358), `TParam.AssignFieldValue` (359)

### 10.45.7 TParam.AssignToField

**Synopsis:** Assign parameter value to field

**Declaration:** `procedure AssignToField(Field: TField)`

Visibility: public

**Description:** `AssignToField` copies the parameter value (365) to the field instance. If `Field` is `Nil`, nothing happens.

**Errors:** An `EDatabaseError` (220) exception is raised if the field has an unsupported field type (for types `ftCursor`, `ftArray`, `ftDataset`, `ftReference`).

See also: `TParam.Assign` (358), `TParam.AssignField` (358), `TParam.AssignFromField` (359)



### 10.45.8 TParam.AssignFieldValue

Synopsis: Assign field value to the parameter.

Declaration: `procedure AssignFieldValue(Field: TField; const AValue: Variant)`

Visibility: public

Description: `AssignFieldValue` copies only the field type from `Field` and the value from the `AValue` parameter. It sets the `TParam.Bound` (364) bound parameter to `True`. This method is called from `TParam.AssignField` (358).

See also: `TField` (298), `TParam.AssignField` (358), `TParam.Bound` (364)

### 10.45.9 TParam.AssignFromField

Synopsis: Copy field type and value

Declaration: `procedure AssignFromField(Field: TField)`

Visibility: public

Description: `AssignFromField` copies the field value (314) and data type (`TField.DataType` (310)) to the parameter instance. If `Field` is `Nil`, nothing happens. This is the reverse operation of `TParam.AssignToField` (358).

Errors: An `EDatabaseError` (220) exception is raised if the field has an unsupported field type (for types `ftCursor`, `ftArray`, `ftDataset`, `ftReference`).

See also: `TParam.Assign` (358), `TParam.AssignField` (358), `TParam.AssignToField` (358)

### 10.45.10 TParam.Clear

Synopsis: Clear the parameter value

Declaration: `procedure Clear`

Visibility: public

Description: `Clear` clears the parameter value, it is set to `UnAssigned`. The `Datatype`, parameter type or name are not touched.

See also: `TParam.Value` (365), `TParam.Name` (366), `TParam.ParamType` (367), `TParam.DataType` (366)

### 10.45.11 TParam.GetData

Synopsis: Get the parameter value from a memory buffer

Declaration: `procedure GetData(Buffer: Pointer)`

Visibility: public

Description: `GetData` retrieves the parameter value and stores it in `buffer`. It uses the same data layout as `TField` (298), and can be used to copy the parameter value to a record buffer.

Errors: Only basic field types are supported. Using an unsupported field type will result in an `EDatabaseError` (220) exception.

See also: `TParam.SetData` (361), `TField` (298)

**10.45.12 TParam.GetDataSize**

Synopsis: Return the size of the data.

Declaration: `function GetDataSize : Integer`

Visibility: `public`

Description: `GetDataSize` returns the size (in bytes) needed to store the current value of the parameter.

Errors: For an unsupported data type, an `EDatabaseError` (220) exception is raised when this function is called.

See also: `TParam.GetData` (359), `TParam.SetData` (361)

**10.45.13 TParam.LoadFromFile**

Synopsis: Load a parameter value from file

Declaration: `procedure LoadFromFile(const FileName: String; BlobType: TBlobType)`

Visibility: `public`

Description: `LoadFromFile` can be used to load a BLOB-type parameter from a file named `FileName`. The `BlobType` parameter can be used to set the exact data type of the parameter: it must be one of the BLOB data types. This function simply creates a `TFileStream` instance and passes it to `TParam.LoadFromStream` (360).

Errors: If the specified `FileName` is not a valid file, or the file is not readable, an exception will occur.

See also: `TParam.LoadFromStream` (360), `TBlobType` (210), `TParam.SaveToFile` (356)

**10.45.14 TParam.LoadFromStream**

Synopsis: Load a parameter value from stream

Declaration: `procedure LoadFromStream(Stream: TStream; BlobType: TBlobType)`

Visibility: `public`

Description: `LoadFromStream` can be used to load a BLOB-type parameter from a stream. The `BlobType` parameter can be used to set the exact data type of the parameter: it must be one of the BLOB data types.

Errors: If the stream does not support taking the `Size` of the stream, an exception will be raised.

See also: `TParam.LoadFromFile` (360), `TParam.SaveToStream` (356)

**10.45.15 TParam.SetBlobData**

Synopsis: Set BLOB data

Declaration: `procedure SetBlobData(Buffer: Pointer; ASize: Integer)`

Visibility: `public`

Description: `SetBlobData` reads the value of a BLOB type parameter from a memory buffer: the data is read from the memory buffer `Buffer` and is assumed to be `Size` bytes long.

Errors: No checking is performed on the validity of the data buffer. If the data buffer is invalid or the size is wrong, an exception may occur.

See also: `TParam.LoadFromStream` (360)

**10.45.16 TParam.SetData**

Synopsis: Set the parameter value from a buffer

Declaration: `procedure SetData(Buffer: Pointer)`

Visibility: public

Description: `SetData` performs the rever operation of `TParam.GetData` (359): it reads the parameter value from the memory area pointed to by `Buffer`. The size of the data read is determined by `TParam.GetDataSize` (360) and the type of data by `TParam.DataType` (366) : it is the same storage mechanism used by `TField` (298), and so can be used to copy the value from a `TDataset` (250) record buffer.

Errors: Not all field types are supported. If an unsupported field type is encountered, an `EDatabaseError` (220) exception is raised.

See also: `TDataset` (250), `TParam.GetData` (359), `TParam.DataType` (366), `TParam.GetDataSize` (360)

**10.45.17 TParam.AsBlob**

Synopsis: Return parameter value as a blob

Declaration: `Property AsBlob : TBlobData`

Visibility: public

Access: Read,Write

Description: `AsBlob` returns the parameter value as a blob: currently this is a string. It can be set to set the parameter value.

See also: `TParam.AsString` (363)

**10.45.18 TParam.AsBoolean**

Synopsis: Get/Set parameter value as a boolean value

Declaration: `Property AsBoolean : Boolean`

Visibility: public

Access: Read,Write

Description: `AsBoolean` will return the parameter value as a boolean value. If it is written, the value is set to the specified value and the data type is set to `ftBoolean`.

See also: `TParam.DataType` (366), `TParam.Value` (365)

**10.45.19 TParam.AsCurrency**

Synopsis: Get/Set parameter value as a currency value

Declaration: `Property AsCurrency : Currency`

Visibility: public

Access: Read,Write

Description: `AsCurrency` will return the parameter value as a currency value. If it is written, the value is set to the specified value and the data type is set to `ftCurrency`.

See also: `TParam.AsFloat` (362), `TParam.DataType` (366), `TParam.Value` (365)

**10.45.20 TParam.AsDate**

Synopsis: Get/Set parameter value as a date (TDateTime) value

Declaration: `Property AsDate : TDateTime`

Visibility: `public`

Access: `Read,Write`

Description: `AsDate` will return the parameter value as a date value. If it is written, the value is set to the specified value and the data type is set to `ftDate`.

See also: [TParam.AsDateTime \(362\)](#), [TParam.AsTime \(364\)](#), [TParam.DataType \(366\)](#), [TParam.Value \(365\)](#)

**10.45.21 TParam.AsDateTime**

Synopsis: Get/Set parameter value as a date/time (TDateTime) value

Declaration: `Property AsDateTime : TDateTime`

Visibility: `public`

Access: `Read,Write`

Description: `AsDateTime` will return the parameter value as a TDateTime value. If it is written, the value is set to the specified value and the data type is set to `ftDateTime`.

See also: [TParam.AsDate \(362\)](#), [TParam.asTime \(364\)](#), [TParam.DataType \(366\)](#), [TParam.Value \(365\)](#)

**10.45.22 TParam.AsFloat**

Synopsis: Get/Set parameter value as a floating-point value

Declaration: `Property AsFloat : Double`

Visibility: `public`

Access: `Read,Write`

Description: `AsFloat` will return the parameter value as a double floating-point value. If it is written, the value is set to the specified value and the data type is set to `ftFloat`.

See also: [TParam.AsCurrency \(361\)](#), [TParam.DataType \(366\)](#), [TParam.Value \(365\)](#)

**10.45.23 TParam.AsInteger**

Synopsis: Get/Set parameter value as an integer (32-bit) value

Declaration: `Property AsInteger : LongInt`

Visibility: `public`

Access: `Read,Write`

Description: `AsInteger` will return the parameter value as a 32-bit signed integer value. If it is written, the value is set to the specified value and the data type is set to `ftInteger`.

See also: [TParam.AsLargeInt \(363\)](#), [TParam.AsSmallInt \(363\)](#), [TParam.AsWord \(364\)](#), [TParam.DataType \(366\)](#), [TParam.Value \(365\)](#)

**10.45.24 TParam.AsLargeInt**

Synopsis: Get/Set parameter value as a 64-bit integer value

Declaration: `Property AsLargeInt : LargeInt`

Visibility: `public`

Access: `Read,Write`

Description: `AsLargeInt` will return the parameter value as a 64-bit signed integer value. If it is written, the value is set to the specified value and the data type is set to `ftLargeInt`.

See also: `TParam.asInteger` (362), `TParam.asSmallint` (363), `TParam.AsWord` (364), `TParam.DataType` (366), `TParam.Value` (365)

**10.45.25 TParam.AsMemo**

Synopsis: Get/Set parameter value as a memo (string) value

Declaration: `Property AsMemo : String`

Visibility: `public`

Access: `Read,Write`

Description: `AsMemo` will return the parameter value as a memo (string) value. If it is written, the value is set to the specified value and the data type is set to `ftMemo`.

See also: `TParam.asString` (363), `TParam.LoadFromStream` (360), `TParam.SaveToStream` (356), `TParam.DataType` (366), `TParam.Value` (365)

**10.45.26 TParam.AsSmallInt**

Synopsis: Get/Set parameter value as a smallint value

Declaration: `Property AsSmallInt : LongInt`

Visibility: `public`

Access: `Read,Write`

Description: `AsSmallint` will return the parameter value as a 16-bit signed integer value. If it is written, the value is set to the specified value and the data type is set to `ftSmallint`.

See also: `TParam.AsInteger` (362), `TParam.AsLargeInt` (363), `TParam.AsWord` (364), `TParam.DataType` (366), `TParam.Value` (365)

**10.45.27 TParam.AsString**

Synopsis: Get/Set parameter value as a string value

Declaration: `Property AsString : String`

Visibility: `public`

Access: `Read,Write`

Description: `AsString` will return the parameter value as a string value. If it is written, the value is set to the specified value and the data type is set to `ftString`.

See also: `TParam.DataType` (366), `TParam.Value` (365)

**10.45.28 TParam.AsTime**

Synopsis: Get/Set parameter value as a time (TDateTime) value

Declaration: `Property AsTime : TDateTime`

Visibility: `public`

Access: `Read,Write`

Description: `AsTime` will return the parameter value as a time (TDateTime) value. If it is written, the value is set to the specified value and the data type is set to `ftTime`.

See also: `TParam.AsDate` (362), `TParam.AsDateTime` (362), `TParam.DataType` (366), `TParam.Value` (365)

**10.45.29 TParam.AsWord**

Synopsis: Get/Set parameter value as a word value

Declaration: `Property AsWord : LongInt`

Visibility: `public`

Access: `Read,Write`

Description: `AsWord` will return the parameter value as an integer. If it is written, the value is set to the specified value and the data type is set to `ftWord`.

See also: `TParam.AsInteger` (362), `TParam.AsLargeInt` (363), `TParam.AsSmallint` (363), `TParam.DataType` (366), `TParam.Value` (365)

**10.45.30 TParam.Bound**

Synopsis: Is the parameter value bound (set to fixed value)

Declaration: `Property Bound : Boolean`

Visibility: `public`

Access: `Read,Write`

Description: `Bound` indicates whether a parameter has received a fixed value: setting the parameter value will set `Bound` to `True`. When creating master-detail relationships, parameters with their `Bound` property set to `True` will not receive a value from the master dataset: their value will be kept. Only parameters where `Bound` is `False` will receive a new value from the master dataset.

See also: `TParam.DataType` (366), `TParam.Value` (365)

**10.45.31 TParam.Dataset**

Synopsis: Dataset to which this parameter belongs

Declaration: `Property Dataset : TDataSet`

Visibility: `public`

Access: `Read`

Description: `Dataset` is the dataset that owns the `TParams` (368) instance of which this `TParam` instance is a part. It is `Nil` if the collection is not set, or is not a `TParams` instance.

See also: `TDataSet` (250), `TParams` (368)

### 10.45.32 TParam.IsNull

Synopsis: Is the parameter empty

Declaration: `Property IsNull : Boolean`

Visibility: `public`

Access: `Read`

Description: `IsNull` is `True` if the value is empty or not set (`Null` or `UnAssigned`).

See also: `TParam.Clear` ([359](#)), `TParam.Value` ([365](#))

### 10.45.33 TParam.NativeStr

Synopsis: No description available

Declaration: `Property NativeStr : String`

Visibility: `public`

Access: `Read,Write`

Description: No description available

### 10.45.34 TParam.Text

Synopsis: Read or write the value of the parameter as a string

Declaration: `Property Text : String`

Visibility: `public`

Access: `Read,Write`

Description: `AsText` returns the same value as `TParam.AsString` ([363](#)), but, when written, does not set the data type: instead, it attempts to convert the value to the type specified in `TParam.DataType` ([366](#)).

See also: `TParam.AsString` ([363](#)), `TParam.DataType` ([366](#))

### 10.45.35 TParam.Value

Synopsis: Value as a variant

Declaration: `Property Value : Variant`

Visibility: `public`

Access: `Read,Write`

Description: `Value` returns (or sets) the value as a variant value.

See also: `TParam.DataType` ([366](#))

### 10.45.36 TParam.AsWideString

Synopsis: Get/Set the value as a widestring

Declaration: `Property AsWideString : WideString`

Visibility: public

Access: Read,Write

Description: `AsWideString` returns the parameter value as a widestring value. Setting the property will set the value of the parameter and will also set the `DataType` (366) to `ftWideString`.

See also: `TParam.AsString` (363), `TParam.Value` (365), `TParam.DataType` (366)

### 10.45.37 TParam.DataType

Synopsis: Data type of the parameter

Declaration: `Property DataType : TFieldType`

Visibility: published

Access: Read,Write

Description: `DataType` is the current data type of the parameter value. It is set automatically when one of the various `AsXYZ` properties is written, or when the value is copied from a field value.

See also: `TParam.IsNull` (365), `TParam.Value` (365), `TParam.AssignField` (358)

### 10.45.38 TParam.Name

Synopsis: Name of the parameter

Declaration: `Property Name : String`

Visibility: published

Access: Read,Write

Description: `Name` is the name of the parameter. The name is usually determined automatically from the SQL statement the parameter is part of. Each parameter name should appear only once in the collection.

See also: `TParam.DataType` (366), `TParam.Value` (365), `TParams.ParamByName` (370)

### 10.45.39 TParam.NumericScale

Synopsis: Numeric scale

Declaration: `Property NumericScale : Integer`

Visibility: published

Access: Read,Write

Description: `NumericScale` can be used to store the numerical scale for BCD values. It is currently unused.

See also: `TParam.Precision` (367), `TParam.Size` (367)



**10.45.40 TParam.ParamType**

Synopsis: Type of parameter

Declaration: `Property ParamType : TParamType`

Visibility: published

Access: Read,Write

Description: `ParamType` specifies the type of parameter: is the parameter value written to the database engine, or is it received from the database engine, or both ? It can have the following value:

**ptUnknown**Unknown type

**ptInput**Input parameter

**ptOutput**Output parameter, filled on result

**ptInputOutput**Input/output parameter

**ptResult**Result parameter

The `ParamType` property is usually set by the database engine that creates the parameter instances.

See also: `TParam.DataType` (366), `TParam.DataSize` (356), `TParam.Name` (366)

**10.45.41 TParam.Precision**

Synopsis: Precision of the BCD value

Declaration: `Property Precision : Integer`

Visibility: published

Access: Read,Write

Description: `Precision` can be used to store the numerical precision for BCD values. It is currently unused.

See also: `TParam.NumericScale` (366), `TParam.Size` (367)

**10.45.42 TParam.Size**

Synopsis: Size of the parameter

Declaration: `Property Size : Integer`

Visibility: published

Access: Read,Write

Description: `Size` is the declared size of the parameter. In the current implementation, this parameter is ignored other than copying it from `TField.DataSize` (310) in the `TParam.AssignFieldValue` (359) method. The actual size can be retrieved through the `TParam.Datasize` (356) property.

See also: `TParam.Datasize` (356), `TField.DataSize` (310), `TParam.AssignFieldValue` (359)

## 10.46 TParams

### 10.46.1 Description

`TParams` is a collection of `TParam` (356) values. It is used to specify parameter values for parametrized SQL statements, but is also used to specify parameter values for stored procedures. Its default property is an array of `TParam` (356) values. The class also offers a method to scan a SQL statement for parameter names and replace them with placeholders understood by the SQL engine: `TParams.ParseSQL` (370).

`TDataset` (250) itself does not use `TParams`. The class is provided in the `DB` unit, so all `TDataset` descendents that need some kind of parametrization make use of the same interface. The `TMasterParamsDataLink` (351) class can be used to establish a master-detail relationship between a parameter-aware `TDataset` instance and another dataset; it will automatically refresh parameter values when the fields in the master dataset change. To this end, the `TParams.CopyParamValuesFromDataset` (371) method exists.

### 10.46.2 Method overview

Page	Property	Description
369	<code>AddParam</code>	Add a parameter to the collection
369	<code>AssignValues</code>	Copy values from another collection
371	<code>CopyParamValuesFromDataset</code>	Copy parameter values from a the fields in a dataset.
368	<code>Create</code>	Create a new instance of <code>TParams</code>
369	<code>CreateParam</code>	Create and add a new parameter to the collection
369	<code>FindParam</code>	Find a parameter with given name
370	<code>GetParamList</code>	Fetch a list of <code>TParam</code> instances
370	<code>IsEqual</code>	Is the list of parameters equal
370	<code>ParamByName</code>	Return a parameter by name
370	<code>ParseSQL</code>	Parse SQL statement, replacing parameter names with SQL parameter placeholders
371	<code>RemoveParam</code>	Remove a parameter from the collection

### 10.46.3 Property overview

Page	Property	Access	Description
372	<code>Dataset</code>	r	Dataset that owns the <code>TParams</code> instance
372	<code>Items</code>	rw	Indexed access to <code>TParams</code> instances in the collection
372	<code>ParamValues</code>	rw	Named access to the parameter values.

### 10.46.4 TParams.Create

Synopsis: Create a new instance of `TParams`

Declaration: `constructor Create(AOwner: TPersistent); Overload`  
`constructor Create; Overload`

Visibility: `public`

Description: `Create` initializes a new instance of `TParams`. It calls the inherited constructor with `TParam` (356) as the collection's item class, and sets `AOwner` as the owner of the collection. Usually, `AOwner` will be the dataset that needs parameters.

See also: `#rtl.classes.collection.create` (?), `TParam` (356)

### 10.46.5 TParams.AddParam

Synopsis: Add a parameter to the collection

Declaration: `procedure AddParam(Value: TParam)`

Visibility: public

Description: `AddParam` adds `Value` to the collection.

Errors: No checks are done on the `TParam` instance. If it is `Nil`, an exception will be raised.

See also: `TParam` (356), `#rtl.classes.tcollection.add` (??)

### 10.46.6 TParams.AssignValues

Synopsis: Copy values from another collection

Declaration: `procedure AssignValues(Value: TParams)`

Visibility: public

Description: `AssignValues` examines all `TParam` (356) instances in `Value`, and looks in its own items for a `TParam` instance with the same name. If it is found, then the value and type of the parameter are copied (using `TParam.Assign` (358)). If it is not found, nothing is done.

See also: `TParam` (356), `TParam.Assign` (358)

### 10.46.7 TParams.CreateParam

Synopsis: Create and add a new parameter to the collection

Declaration: `function CreateParam(FldType: TFieldType; const ParamName: String;  
ParamType: TParamType) : TParam`

Visibility: public

Description: `CreateParam` creates a new `TParam` (356) instance with datatype equal to `fldType`, Name equal to `ParamName` and sets its `ParamType` property to `ParamType`. The parameter is then added to the collection.

See also: `TParam` (356), `TParam.Name` (366), `TParam.Datatype` (366), `TParam.Paramtype` (367)

### 10.46.8 TParams.FindParam

Synopsis: Find a parameter with given name

Declaration: `function FindParam(const Value: String) : TParam`

Visibility: public

Description: `FindParam` searches the collection for the `TParam` (356) instance with property `Name` equal to `Value`. It will return the last instance with the given name, and will only return one instance. If no match is found, `Nil` is returned.

**Remark:** A `TParams` collection can have 2 `TParam` instances with the same name: no checking for duplicates is done.

See also: `TParam.Name` (366), `TParams.ParamByName` (370), `TParams.GetParamList` (370)

### 10.46.9 TParams.GetParamList

Synopsis: Fetch a list of TParam instances

Declaration: `procedure GetParamList(List: TList; const ParamNames: String)`

Visibility: public

Description: `GetParamList` examines the parameter names in the semicolon-separated list `ParamNames`. It searches each TParam instance from the names in the list and adds it to `List`.

Errors: If the `ParamNames` list contains an unknown parameter name, then an exception is raised. Whitespace is not discarded.

See also: TParam (356), TParam.Name (366), TParams.ParamByName (370)

### 10.46.10 TParams.IsEqual

Synopsis: Is the list of parameters equal

Declaration: `function IsEqual(Value: TParams) : Boolean`

Visibility: public

Description: `IsEqual` compares the parameter count of `Value` and if it matches, it compares all TParam items of `Value` with the items it owns. If all items are equal (all properties match), then `True` is returned. The items are compared on index, so the order is important.

See also: TParam (356)

### 10.46.11 TParams.ParamByName

Synopsis: Return a parameter by name

Declaration: `function ParamByName(const Value: String) : TParam`

Visibility: public

Description: `ParamByName` searches the collection for the TParam (356) instance with property `Name` equal to `Value`. It will return the last instance with the given name, and will only return one instance. If no match is found, an exception is raised.

**Remark:** A TParams collection can have 2 TParam instances with the same name: no checking for duplicates is done.

See also: TParam.Name (366), TParams.FindParam (369), TParams.GetParamList (370)

### 10.46.12 TParams.ParseSQL

Synopsis: Parse SQL statement, replacing parameter names with SQL parameter placeholders

Declaration: `function ParseSQL(SQL: String; DoCreate: Boolean) : String; Overload`  
`function ParseSQL(SQL: String; DoCreate: Boolean; EscapeSlash: Boolean;`  
`EscapeRepeat: Boolean; ParameterStyle: TParamStyle)`  
`: String; Overload`  
`function ParseSQL(SQL: String; DoCreate: Boolean; EscapeSlash: Boolean;`  
`EscapeRepeat: Boolean; ParameterStyle: TParamStyle;`  
`var ParamBinding: TParamBinding) : String; Overload`

```
function ParseSQL(SQL: String; DoCreate: Boolean; EscapeSlash: Boolean;
    EscapeRepeat: Boolean; ParameterStyle: TParamStyle;
    var ParamBinding: TParamBinding;
    var ReplaceString: String) : String; Overload
```

Visibility: public

**Description:** ParseSQL parses the SQL statement for parameter names in the form :ParamName. It replaces them with a SQL parameter placeholder. If DoCreate is True then a TParam instance is added to the collection with the found parameter name.

The parameter placeholder is determined by the ParameterStyle property, which can have the following values:

**psInterbaseParameters** are specified by a ? character

**psPostgreSQLParameters** are specified by a \$N character.

**psSimulatedParameters** are specified by a \$N character.

psInterbase is the default.

If the EscapeSlash parameter is True, then backslash characters are used to quote the next character in the SQL statement. If it is False, the backslash character is regarded as a normal character.

If the EscapeRepeat parameter is True (the default) then embedded quotes in string literals are escaped by repeating themselves. If it is false then they should be quoted with backslashes.

ParamBinding, if specified, is filled with the indexes of the parameter instances in the parameter collection: for each SQL parameter placeholder, the index of the corresponding TParam instance is returned in the array.

ReplaceString, if specified, contains the placeholder used for the parameter names (by default, \$). It has effect only when ParameterStyle equals psSimulated.

The function returns the SQL statement with the parameter names replaced by placeholders.

See also: TParam ([356](#)), TParam.Name ([366](#)), TParamStyle ([217](#))

### 10.46.13 TParams.RemoveParam

**Synopsis:** Remove a parameter from the collection

**Declaration:** procedure RemoveParam(Value: TParam)

Visibility: public

**Description:** RemoveParam removes the parameter Value from the collection, but does not free the instance.

**Errors:** Value must be a valid instance, or an exception will be raised.

See also: TParam ([356](#))

### 10.46.14 TParams.CopyParamValuesFromDataset

**Synopsis:** Copy parameter values from a the fields in a dataset.

**Declaration:** procedure CopyParamValuesFromDataset (ADataset: TDataSet;  
CopyBound: Boolean)

Visibility: public

**Description:** `CopyParamValuesFromDataset` assigns values to all parameters in the collection by searching in `ADataset` for fields with the same name, and assigning the value of the field to the `TParam` instances using `TParam.AssignField` (358). By default, this operation is only performed on `TParam` instances with their `Bound` (364) property set to `False`. If `CopyBound` is true, then the operation is performed on all `TParam` instances in the collection.

**Errors:** If, for some `TParam` instance, `ADataset` misses a field with the same name, an `EDatabaseError` exception will be raised.

**See also:** `TParam` (356), `TParam.Bound` (364), `TParam.AssignField` (358), `TDataset` (250), `TDataset.FieldName` (261)

### 10.46.15 TParams.Dataset

**Synopsis:** Dataset that owns the `TParams` instance

**Declaration:** `Property Dataset : TDataSet`

**Visibility:** public

**Access:** Read

**Description:** `Dataset` is the `TDataset` (250) instance that was specified when the `TParams` instance was created.

**See also:** `TParams.Create` (368), `TDataset` (250)

### 10.46.16 TParams.Items

**Synopsis:** Indexed access to `TParams` instances in the collection

**Declaration:** `Property Items[Index: Integer]: TParam; default`

**Visibility:** public

**Access:** Read,Write

**Description:** `Items` is overridden by `TParams` so it has the proper type (`TParam`). The `Index` runs from 0 to `Count-1`.

**See also:** `TParam` (208)

### 10.46.17 TParams.ParamValues

**Synopsis:** Named access to the parameter values.

**Declaration:** `Property ParamValues[ParamName: String]: Variant`

**Visibility:** public

**Access:** Read,Write

**Description:** `ParamValues` provides access to the parameter values (`TParam.Value` (365)) by name. It is equivalent to reading and writing

`ParamByName(ParamName).Value`

**See also:** `TParam.Value` (365), `TParams.ParamByName` (370)

## 10.47 TSmallIntField

### 10.47.1 Description

`TSmallIntField` is the class created when a dataset must manage 16-bit signed integer data, of datatype `ftSmallInt`. It exposes no new properties, but simply overrides some methods to manage 16-bit signed integer data.

It should never be necessary to create an instance of `TSmallIntField` manually, a field of this class will be instantiated automatically for each smallint field when a dataset is opened.

### 10.47.2 Method overview

Page	Property	Description
<a href="#">373</a>	Create	Create a new instance of the <code>TSmallIntField</code> class.

### 10.47.3 TSmallIntField.Create

Synopsis: Create a new instance of the `TSmallIntField` class.

Declaration: `constructor Create(AOwner: TComponent); Override`

Visibility: `public`

Description: `Create` initializes a new instance of the `TSmallIntField` ([373](#)) class. It calls the inherited constructor and then simply sets some of the `TField` ([298](#)) properties to work with 16-bit signed integer data.

See also: `TField` ([298](#))

## 10.48 TStringField

### 10.48.1 Description

`TStringField` is the class used whenever a dataset has to handle a string field type (data type `ftString`). This class overrides some of the standard `TField` ([298](#)) methods to handle string data, and introduces some properties that are only pertinent for data fields of string type. It should never be necessary to create an instance of `TStringField` manually, a field of this class will be instantiated automatically for each string field when a dataset is opened.

### 10.48.2 Method overview

Page	Property	Description
<a href="#">374</a>	Create	Create a new instance of the <code>TStringField</code> class
<a href="#">374</a>	SetFieldType	

### 10.48.3 Property overview

Page	Property	Access	Description
<a href="#">374</a>	FixedChar	rw	Is the string declared with a fixed length ?
<a href="#">375</a>	Size		Maximum size of the string
<a href="#">374</a>	Transliterate	rw	Should the field value be transliterated when reading or writing
<a href="#">374</a>	Value	rw	Value of the field as a string

### 10.48.4 TStringField.Create

Synopsis: Create a new instance of the TStringField class

Declaration: `constructor Create(AOwner: TComponent); Override`

Visibility: `public`

Description: `Create` is used to create a new instance of the TStringField class. It initializes some TField (298) properties after having called the inherited constructor.

### 10.48.5 TStringField.SetFieldType

Declaration: `procedure SetFieldType(AValue: TFieldType); Override`

Visibility: `public`

### 10.48.6 TStringField.FixedChar

Synopsis: Is the string declared with a fixed length ?

Declaration: `Property FixedChar : Boolean`

Visibility: `public`

Access: `Read,Write`

Description: `FixedChar` is `True` if the underlying data engine has declared the field with a fixed length, as in a SQL `CHAR()` declaration: the field's value will then always be padded with as many spaces as needed to obtain the declared length of the field. If it is `False` then the declared length is simply the maximum length for the field, and no padding with spaces is performed.

### 10.48.7 TStringField.Transliterate

Synopsis: Should the field value be transliterated when reading or writing

Declaration: `Property Transliterate : Boolean`

Visibility: `public`

Access: `Read,Write`

Description: `Transliterate` can be set to `True` if the field's contents should be transliterated prior to copying it from or to the field's buffer. Transliteration is done by a method of TDataset: `TDataset.Translate` (270).

See also: `TDataset.Translate` (270)

### 10.48.8 TStringField.Value

Synopsis: Value of the field as a string

Declaration: `Property Value : String`

Visibility: `public`

Access: `Read,Write`



**Description:** `Value` is overridden in `TField` to return the value of the field as a string. It returns the contents of `TField.AsString` (308) when read, or sets the `AsString` property when written to.

See also: `TField.AsString` (308), `TField.Value` (314)

### 10.48.9 TStringField.Size

**Synopsis:** Maximum size of the string

**Declaration:** `Property Size :`

**Visibility:** `published`

**Access:**

**Description:** `Size` is made published by the `TStringField` class so it can be set in the IDE: it is the declared maximum size of the string (in characters) and is used to calculate the size of the dataset buffer.

See also: `TField.Size` (313)

## 10.49 TTimeField

### 10.49.1 Description

`TimeField` is the class used when a dataset must manage data of type time. (`TField.DataType` (310) equals `ftTime`). It initializes some of the properties of the `TField` (298) class to be able to work with time fields.

It should never be necessary to create an instance of `TTimeField` manually, a field of this class will be instantiated automatically for each time field when a dataset is opened.

### 10.49.2 Method overview

Page	Property	Description
<a href="#">375</a>	<code>Create</code>	Create a new instance of a <code>TTimeField</code> class.

### 10.49.3 TTimeField.Create

**Synopsis:** Create a new instance of a `TTimeField` class.

**Declaration:** `constructor Create(AOwner: TComponent); Override`

**Visibility:** `public`

**Description:** `Create` initializes a new instance of the `TTimeField` class. It calls the inherited destructor, and then sets some `TField` (298) properties to configure the instance for working with time values.

See also: `TField` (298)

## 10.50 TVarBytesField

### 10.50.1 Description

`TVarBytesField` is the class used when a dataset must manage data of variable-size binary type. (`TField.DataType` (310) equals `ftVarBytes`). It initializes some of the properties of the `TField` (298) class to be able to work with variable-size byte fields.

It should never be necessary to create an instance of `TVarBytesField` manually, a field of this class will be instantiated automatically for each variable-sized binary data field when a dataset is opened.

### 10.50.2 Method overview

Page	Property	Description
<a href="#">376</a>	Create	Create a new instance of a <code>TVarBytesField</code> class.

### 10.50.3 TVarBytesField.Create

**Synopsis:** Create a new instance of a `TVarBytesField` class.

**Declaration:** `constructor Create(AOwner: TComponent); Override`

**Visibility:** public

**Description:** `Create` initializes a new instance of the `TVarBytesField` class. It calls the inherited destructor, and then sets some `TField` ([298](#)) properties to configure the instance for working with variable-size binary data values.

See also: `TField` ([298](#))

## 10.51 TVariantField

### 10.51.1 Description

`TVariantField` is the class used when a dataset must manage native variant-typed data. (`TField.DataType` ([310](#)) equals `ftVariant`). It initializes some of the properties of the `TField` ([298](#)) class and overrides some of its methods to be able to work with variant data.

It should never be necessary to create an instance of `TVariantField` manually, a field of this class will be instantiated automatically for each variant field when a dataset is opened.

### 10.51.2 Method overview

Page	Property	Description
<a href="#">376</a>	Create	Create a new instance of the <code>TVariantField</code> class

### 10.51.3 TVariantField.Create

**Synopsis:** Create a new instance of the `TVariantField` class

**Declaration:** `constructor Create(AOwner: TComponent); Override`

**Visibility:** public

**Description:** `Create` initializes a new instance of the `TVariantField` class. It calls the inherited destructor, and then sets some `TField` ([298](#)) properties to configure the instance for working with variant values.

See also: `TField` ([298](#))

## 10.52 TWideMemoField

### 10.52.1 Description

`TWideMemoField` is the class used when a dataset must manage memo (Text BLOB) data. (`TField.DataType` (310) equals `ftWideMemo`). It initializes some of the properties of the `TField` (298) class. All methods to be able to work with widestring memo fields have been implemented in the `TBlobField` (227) parent class.

It should never be necessary to create an instance of `TWideMemoField` manually, a field of this class will be instantiated automatically for each widestring memo field when a dataset is opened.

### 10.52.2 Method overview

Page	Property	Description
<a href="#">377</a>	Create	Create a new instance of the <code>TWideMemoField</code> class

### 10.52.3 Property overview

Page	Property	Access	Description
<a href="#">377</a>	Value	rw	Value of the field's contents as a widestring

### 10.52.4 TWideMemoField.Create

Synopsis: Create a new instance of the `TWideMemoField` class

Declaration: `constructor Create(aOwner: TComponent); Override`

Visibility: public

Description: `Create` initializes a new instance of the `TWideMemoField` class. It calls the inherited destructor, and then sets some `TField` (298) properties to configure the instance for working with widestring memo values.

See also: `TField` (298)

### 10.52.5 TWideMemoField.Value

Synopsis: Value of the field's contents as a widestring

Declaration: `Property Value : WideString`

Visibility: public

Access: Read,Write

Description: `Value` is redefined by `TWideMemoField` as a `WideString` value. Reading and writing this property is equivalent to reading and writing the `TField.AsWideString` (308) property.

See also: `TField.Value` (314), `TField.AsWideString` (308)

## 10.53 TWideStringField

### 10.53.1 Description

`TWideStringField` is the string field class instantiated for fields of data type `ftWideString`. This class overrides some of the standard `TField` (298) methods to handle widestring data, and introduces some properties that are only pertinent for data fields of widestring type. It should never be necessary to create an instance of `TWideStringField` manually, a field of this class will be instantiated automatically for each widestring field when a dataset is opened.

### 10.53.2 Method overview

Page	Property	Description
<a href="#">378</a>	Create	Create a new instance of the <code>TWideStringField</code> class.

### 10.53.3 Property overview

Page	Property	Access	Description
<a href="#">378</a>	Value	rw	Value of the field as a widestring

### 10.53.4 TWideStringField.Create

**Synopsis:** Create a new instance of the `TWideStringField` class.

**Declaration:** `constructor Create(aOwner: TComponent); Override`

**Visibility:** `public`

**Description:** `Create` is used to create a new instance of the `TWideStringField` class. It initializes some `TField` (298) properties after having called the inherited constructor.

### 10.53.5 TWideStringField.Value

**Synopsis:** Value of the field as a widestring

**Declaration:** `Property Value : WideString`

**Visibility:** `public`

**Access:** Read,Write

**Description:** `Value` is overridden by the `TWideStringField` to return a `WideString` value. It is the same value as the `TField.AsWideString` (308) property.

**See also:** `TField.AsWideString` (308), `TField.Value` (314)

## 10.54 TWordField

### 10.54.1 Description

`TWordField` is the class created when a dataset must manage 16-bit unsigned integer data, of datatype `ftWord`. It exposes no new properties, but simply overrides some methods to manage 16-bit unsigned integer data.

It should never be necessary to create an instance of `TWordField` manually, a field of this class will be instantiated automatically for each word field when a dataset is opened.

### 10.54.2 Method overview

Page	Property	Description
<a href="#">379</a>	Create	Create a new instance of the TWordField class.

### 10.54.3 TWordField.Create

**Synopsis:** Create a new instance of the TWordField class.

**Declaration:** `constructor Create(AOwner: TComponent); Override`

**Visibility:** public

**Description:** Create initializes a new instance of the TWordField ([378](#)) class. It calls the inherited constructor and then simply sets some of the TField ([298](#)) properties to work with 16-bit unsigned integer data.

**See also:** TField ([298](#))

Table 10.9: Enumeration values for type TFieldType

Value	Explanation
ftADT	ADT value
ftArray	Array data
ftAutoInc	Auto-increment integer value (4 bytes)
ftBCD	Binary Coded Decimal value (DECIMAL and NUMERIC SQL types)
ftBlob	Binary data value (no type, no size)
ftBoolean	Boolean value
ftBytes	Array of bytes value, fixed size (untyped)
ftCurrency	Currency value (4 decimal points)
ftCursor	Cursor data value (no size)
ftDataSet	Dataset data (blob)
ftDate	Date value
ftDateTime	Date/Time (timestamp) value
ftDBaseOle	Paradox OLE field data
ftFixedChar	Fixed character array (string)
ftFixedWideChar	Fixed wide character data (2 bytes per character)
ftFloat	Floating point value (double)
ftFMTBcd	Formatted BCD (Binary Coded Decimal) value.
ftFmtMemo	Formatted memo data value (no size)
ftGraphic	Graphical data value (no size)
ftGuid	GUID data value
ftIDispatch	Dispatch data value
ftInteger	Regular integer value (4 bytes, signed)
ftInterface	interface data value
ftLargeint	Large integer value (8-byte)
ftMemo	Binary text data (no size)
ftOraBlob	Oracle BLOB data
ftOraClob	Oracle CLOB data
ftParadoxOle	Paradox OLE field data (no size)
ftReference	Reference data
ftSmallint	Small integer value(1 byte, signed)
ftString	String data value (ansistring)
ftTime	Time value
ftTimeStamp	Timestamp data value
ftTypedBinary	Binary typed data (no size)
ftUnknown	Unknown data type
ftVarBytes	Array of bytes value, variable size (untyped)
ftVariant	Variant data value
ftWideMemo	Widestring memo data
ftWideString	Widestring (2 bytes per character)
ftWord	Word-sized value(2 bytes, unsigned)

Table 10.10: Enumeration values for type TFilterOption

Value	Explanation
foCaseInsensitive	Filter case insensitively.
foNoPartialCompare	Do not compare values partially, always compare completely.

Table 10.11: Enumeration values for type TGetMode

Value	Explanation
gmCurrent	Retrieve the current record
gmNext	Retrieve the next record.
gmPrior	Retrieve the previous record.

Table 10.12: Enumeration values for type TGetResult

Value	Explanation
grBOF	The beginning of the recordset is reached
grEOF	The end of the recordset is reached.
grError	An error occurred
grOK	The operation was completed succesfully

Table 10.13: Enumeration values for type TIndexOption

Value	Explanation
ixCaseInsensitive	The values in the index are sorted case-insensitively
ixDescending	The values in the index are sorted descending.
ixExpression	The values in the index are based on a calculated expression.
ixNonMaintained	The index is non-maintained, i.e. changing the data will not update the index.
ixPrimary	The index is the primary index for the data
ixUnique	The index is a unique index, i.e. each index value can occur only once

Table 10.14: Enumeration values for type TLocateOption

Value	Explanation
loCaseInsensitive	Perform a case-insensitive search
loPartialKey	Accept partial key matches

Table 10.15: Enumeration values for type TParamStyle

Value	Explanation
psInterbase	Parameters are specified by a ? character
psPostgreSQL	Parameters are specified by a \$N character.
psSimulated	Parameters are specified by a \$N character.

Table 10.16: Enumeration values for type TParamType

Value	Explanation
ptInput	Input parameter
ptInputOutput	Input/output parameter
ptOutput	Output paramete, filled on result
ptResult	Result parameter
ptUnknown	Unknown type

Table 10.17: Enumeration values for type TProviderFlag

Value	Explanation
pfHidden	
pfInKey	Field is a key field and used in the WHERE clause of an update statement
pfInUpdate	Changes to the field should be propagated to the database.
pfInWhere	Field should be used in the WHERE clause of an update statement in case of upWhereChanged.

Table 10.18: Enumeration values for type TResolverResponse

Value	Explanation
rrAbort	Abor the whole update process
rrApply	Replace the update with new values applied by the event handler
rrIgnore	Ignore the error and remove update from change log
rrMerge	Merge the update with existing changes on the server
rrSkip	Skip the current update, leave it in the change log

Table 10.19: Enumeration values for type TUpdateAction

Value	Explanation
uaAbort	The whole update operation should abort
uaApplied	Consider the update as applied
uaFail	Update operation should fail
uaRetry	Retry the update operation
uaSkip	The update of the current record should be skipped. (but not discarded)

Table 10.20: Enumeration values for type TUpdateKind

Value	Explanation
ukDelete	Delete a record in the database.
ukInsert	insert a new record in the database.
ukModify	Modify an existing record in the database.

Table 10.21: Enumeration values for type TUpdateMode

Value	Explanation
upWhereAll	Use all old field values
upWhereChanged	Use only old field values of modified fields
upWhereKeyOnly	Only use key fields in the where clause.



Table 10.22: Enumeration values for type TUpdateStatus

Value	Explanation
usDeleted	Record exists in the database, but is locally deleted.
usInserted	Record does not yet exist in the database, but is locally inserted
usModified	Record exists in the database but is locally modified
usUnmodified	Record is unmodified

# Chapter 11

## Reference for unit 'dbugintf'

### 11.1 Overview

Use `dbugintf` to add debug messages to your application. The messages are not sent to standard output, but are sent to a debug server process which collects messages from various clients and displays them somehow on screen.

The unit is transparent in its use: it does not need initialization, it will start the debug server by itself if it can find it: the program should be called `debugserver` and should be in the `PATH`. When the first debug message is sent, the unit will initialize itself.

The FCL contains a sample debug server (`dbugsvr`) which can be started in advance, and which writes debug message to the console (both on Windows and Linux). The Lazarus project contains a visual application which displays the messages in a GUI.

The `dbugintf` unit relies on the SimpleIPC (384) mechanism to communicate with the debug server, hence it works on all platforms that have a functional version of that unit. It also uses `TProcess` to start the debug server if needed, so the process (384) unit should also be functional.

### 11.2 Writing a debug server

Writing a debug server is relatively easy. It should instantiate a `TSimpleIPCServer` class from the SimpleIPC (384) unit, and use the `DebugServerID` as `ServerID` identification. This constant, as well as the record containing the message which is sent between client and server is defined in the `msgintf` unit.

The `dbugintf` unit relies on the SimpleIPC (384) mechanism to communicate with the debug server, hence it works on all platforms that have a functional version of that unit. It also uses `TProcess` to start the debug server if needed, so the process (384) unit should also be functional.

### 11.3 Constants, types and variables

#### 11.3.1 Resource strings

```
SEntering = '> Entering '
```

String used when sending method enter message.

```
SExiting = '< Exiting '
```

String used when sending method exit message.

`SProcessID = 'Process %s'`

String used when sending identification message to the server.

`SSeparator = '>-----<'`

String used when sending a separator line.

`SServerStartFailed = 'Failed to start debugserver. (%s)'`

String used to display an error message when the start of the debug server failed

### 11.3.2 Constants

`SendError : String = ''`

Whenever a call encounters an exception, the exception message is stored in this variable.

### 11.3.3 Types

`TDebugLevel = (dlInformation, dlWarning, dlError)`

Table 11.1: Enumeration values for type TDebugLevel

Value	Explanation
<code>dlError</code>	Error message
<code>dlInformation</code>	Informational message
<code>dlWarning</code>	Warning message

`TDebugLevel` indicates the severity level of the debug message to be sent. By default, an informational message is sent.

## 11.4 Procedures and functions

### 11.4.1 GetDebuggingEnabled

**Synopsis:** Check if sending of debug messages is enabled.

**Declaration:** `function GetDebuggingEnabled : Boolean`

**Visibility:** default

**Description:** `GetDebuggingEnabled` returns the value set by the last call to `SetDebuggingEnabled`. It is `True` by default.

See also: `SetDebuggingEnabled` ([389](#)), `SendDebug` ([386](#))

### 11.4.2 InitDebugClient

Synopsis: Initialize the debug client.

Declaration: `function InitDebugClient : Boolean`

Visibility: default

Description: `InitDebugClient` starts the debug server and then performs all necessary initialization of the debug IPC communication channel.

Normally this function should not be called. The `SendDebug` (386) call will initialize the debug client when it is first called.

Errors: None.

See also: `SendDebug` (386), `StartDebugServer` (389)

### 11.4.3 SendBoolean

Synopsis: Send the value of a boolean variable

Declaration: `procedure SendBoolean(const Identifier: String;const Value: Boolean)`

Visibility: default

Description: `SendBoolean` is a simple wrapper around `SendDebug` (386) which sends the name and value of a boolean value as an informational message.

Errors: None.

See also: `SendDebug` (386), `SendDateTime` (386), `SendInteger` (388), `SendPointer` (389)

### 11.4.4 SendDateTime

Synopsis: Send the value of a `TDateTime` variable.

Declaration: `procedure SendDateTime(const Identifier: String;const Value: TDateTime)`

Visibility: default

Description: `SendDateTime` is a simple wrapper around `SendDebug` (386) which sends the name and value of an integer value as an informational message. The value is converted to a string using the `DateTimeToStr` (??) call.

Errors: None.

See also: `SendDebug` (386), `SendBoolean` (386), `SendInteger` (388), `SendPointer` (389)

### 11.4.5 SendDebug

Synopsis: Send a message to the debug server.

Declaration: `procedure SendDebug(const Msg: String)`

Visibility: default

**Description:** `SendDebug` sends the message `Msg` to the debug server as an informational message (debug level `dlInformation`). If no debug server is running, then an attempt will be made to start the server first.

The binary that is started is called `debugserver` and should be somewhere on the `PATH`. A sample binary which writes received messages to standard output is included in the FCL, it is called `dbugsrv`. This binary can be renamed to `debugserver` or can be started before the program is started.

**Errors:** Errors are silently ignored, any exception messages are stored in `SendError` (385).

**See also:** `SendDebugEx` (387), `SendDebugFmt` (387), `SendDebugFmtEx` (387)

### 11.4.6 SendDebugEx

**Synopsis:** Send debug message other than informational messages

**Declaration:** `procedure SendDebugEx(const Msg: String; MType: TDebugLevel)`

**Visibility:** default

**Description:** `SendDebugEx` allows to specify the debug level of the message to be sent in `MType`. By default, `SendDebug` (386) uses informational messages.

Other than that the function of `SendDebugEx` is equal to that of `SendDebug`

**Errors:** None.

**See also:** `SendDebug` (386), `SendDebugFmt` (387), `SendDebugFmtEx` (387)

### 11.4.7 SendDebugFmt

**Synopsis:** Format and send a debug message

**Declaration:** `procedure SendDebugFmt(const Msg: String; const Args: Array of const)`

**Visibility:** default

**Description:** `SendDebugFmt` is a utility routine which formats a message by passing `Msg` and `Args` to `Format` (??) and sends the result to the debug server using `SendDebug` (386). It exists mainly to avoid the `Format` call in calling code.

**Errors:** None.

**See also:** `SendDebug` (386), `SendDebugEx` (387), `SendDebugFmtEx` (387), `#rtl.sysutils.format` (??)

### 11.4.8 SendDebugFmtEx

**Synopsis:** Format and send message with alternate type

**Declaration:** `procedure SendDebugFmtEx(const Msg: String; const Args: Array of const; MType: TDebugLevel)`

**Visibility:** default

**Description:** `SendDebugFmtEx` is a utility routine which formats a message by passing `Msg` and `Args` to `Format` (??) and sends the result to the debug server using `SendDebugEx` (387) with `Debug level MType`. It exists mainly to avoid the `Format` call in calling code.

**Errors:** None.

**See also:** `SendDebug` (386), `SendDebugEx` (387), `SendDebugFmt` (387), `#rtl.sysutils.format` (??)

### 11.4.9 SendInteger

Synopsis: Send the value of an integer variable.

Declaration: `procedure SendInteger(const Identifier: String; const Value: Integer;  
HexNotation: Boolean)`

Visibility: default

Description: `SendInteger` is a simple wrapper around `SendDebug` (386) which sends the name and value of an integer value as an informational message. If `HexNotation` is `True`, then the value will be displayed using hexadecimal notation.

Errors: None.

See also: `SendDebug` (386), `SendBoolean` (386), `SendDateTime` (386), `SendPointer` (389)

### 11.4.10 SendMethodEnter

Synopsis: Send method enter message

Declaration: `procedure SendMethodEnter(const MethodName: String)`

Visibility: default

Description: `SendMethodEnter` sends a "Entering MethodName" message to the debug server. After that it increases the message indentation (currently 2 characters). By sending a corresponding `SendMethodExit` (388), the indentation of messages can be decreased again.

By using the `SendMethodEnter` and `SendMethodExit` methods at the beginning and end of a procedure/method, it is possible to visually trace program execution.

Errors: None.

See also: `SendDebug` (386), `SendMethodExit` (388), `SendSeparator` (389)

### 11.4.11 SendMethodExit

Synopsis: Send method exit message

Declaration: `procedure SendMethodExit(const MethodName: String)`

Visibility: default

Description: `SendMethodExit` sends a "Exiting MethodName" message to the debug server. After that it decreases the message indentation (currently 2 characters). By sending a corresponding `SendMethodEnter` (388), the indentation of messages can be increased again.

By using the `SendMethodEnter` and `SendMethodExit` methods at the beginning and end of a procedure/method, it is possible to visually trace program execution.

Note that the indentation level will not be made negative.

Errors: None.

See also: `SendDebug` (386), `SendMethodEnter` (388), `SendSeparator` (389)

### 11.4.12 SendPointer

Synopsis: Send the value of a pointer variable.

Declaration: `procedure SendPointer(const Identifier: String; const Value: Pointer)`

Visibility: default

Description: `SendInteger` is a simple wrapper around `SendDebug` (386) which sends the name and value of a pointer value as an informational message. The pointer value is displayed using hexadecimal notation.

Errors: None.

See also: `SendDebug` (386), `SendBoolean` (386), `SendDateTime` (386), `SendInteger` (388)

### 11.4.13 SendSeparator

Synopsis: Send a separator message

Declaration: `procedure SendSeparator`

Visibility: default

Description: `SendSeparator` is a simple wrapper around `SendDebug` (386) which sends a short horizontal line to the debug server. It can be used to visually separate execution of blocks of code or blocks of values.

Errors: None.

See also: `SendDebug` (386), `SendMethodEnter` (388), `SendMethodExit` (388)

### 11.4.14 SetDebuggingEnabled

Synopsis: Temporary enables or disables debugging

Declaration: `procedure SetDebuggingEnabled(const AValue: Boolean)`

Visibility: default

Description: `SetDebuggingEnabled` can be used to temporarily enable or disable sending of debug messages: this allows to control the amount of messages sent to the debug server without having to remove the `SendDebug` (386) statements. By default, debugging is enabled. If set to false, debug messages are simply discarded till debugging is enabled again.

A value of `True` enables sending of debug messages. A value of `False` disables sending.

Errors: None.

See also: `GetDebuggingEnabled` (385), `SendDebug` (386)

### 11.4.15 StartDebugServer

Synopsis: Start the debug server

Declaration: `function StartDebugServer : Integer`

Visibility: default

**Description:** `StartDebugServer` attempts to start the debug server. The process started is called `debugserver` and should be located in the `PATH`.

Normally this function should not be called. The `SendDebug` (386) call will attempt to start the server by itself if it is not yet running.

**Errors:** On error, `False` is returned.

**See also:** `SendDebug` (386), `InitDebugClient` (386)



# Chapter 12

## Reference for unit 'dbugmsg'

### 12.1 Used units

Table 12.1: Used units by unit 'dbugmsg'

Name	Page
Classes	??

### 12.2 Overview

dbugmsg is an auxiliary unit used in the dbugintf ([384](#)) unit. It defines the message protocol used between the debug unit and the debug server.

### 12.3 Constants, types and variables

#### 12.3.1 Constants

```
DebugServerID : String = 'fpcdebugserver'
```

DebugServerID is a string which is used when creating the message protocol, it is used when identifying the server in the (platform dependent) client-server protocol.

```
lctError = 2
```

lctError is the identification of error messages.

```
lctIdentify = 3
```

lctIdentify is sent by the client to a server when it first connects. It's the first message, and contains the name of client application.

```
lctInformation = 0
```

`lctInformation` is the identification of informational messages.

`lctStop = -1`

`lctStop` is sent by the client to a server when it disconnects.

`lctWarning = 1`

`lctWarning` is the identification of warning messages.

### 12.3.2 Types

```
TDebugMessage = record
  MsgType : Integer;
  MsgTimeStamp : TDateTime;
  Msg : String;
end
```

`TDebugMessage` is a record that describes the message passed from the client to the server. It should not be passed directly in shared memory, as the string containing the message is allocated on the heap. Instead, the `WriteDebugMessageToStream` (393) and `ReadDebugMessageFromStream` (392) can be used to read or write the message from/to a stream.

## 12.4 Procedures and functions

### 12.4.1 DebugMessageName

**Synopsis:** Return the name of the debug message

**Declaration:** `function DebugMessageName(msgType: Integer) : String`

**Visibility:** default

**Description:** `DebugMessageName` returns the name of the message type. It can be used to examine the `MsgType` field of a `TDebugMessage` (392) record, and if `msgType` contains a known type, it returns a string describing this type.

**Errors:** If `MsgType` contains an unknown type, 'Unknown' is returned.

### 12.4.2 ReadDebugMessageFromStream

**Synopsis:** Read a message from stream

**Declaration:** `procedure ReadDebugMessageFromStream(AStream: TStream;
var Msg: TDebugMessage)`

**Visibility:** default

**Description:** `ReadDebugMessageFromStream` reads a `TDebugMessage` (392) record (`Msg`) from the stream `AStream`.

The record is not read in a byte-ordering safe way, i.e. it cannot be exchanged between little- and big-endian systems.

**Errors:** If the stream contains not enough bytes or is malformed, then an exception may be raised.

**See also:** `TDebugMessage` (392), `WriteDebugMessageToStream` (393)

### 12.4.3 WriteDebugMessageToStream

Synopsis: Write a message to stream

Declaration: `procedure WriteDebugMessageToStream(AStream: TStream;  
const Msg: TDebugMessage)`

Visibility: default

Description: `WriteDebugMessageFromStream` writes a `TDebugMessage` (392) record (`Msg`) to the stream `AStream`.

The record is not written in a byte-ordering safe way, i.e. it cannot be exchanged between little- and big-endian systems.

Errors: A stream write error may occur if the stream cannot be written to.

See also: `TDebugMessage` (392), `ReadDebugMessageToStream` (391)

# Chapter 13

## Reference for unit 'eventlog'

### 13.1 Used units

Table 13.1: Used units by unit 'eventlog'

Name	Page
Classes	??
sysutils	??

### 13.2 Overview

The EventLog unit implements the TEventLog (395) component, which is a component that can be used to send log messages to the system log (if it is available) or to a file.

### 13.3 Constants, types and variables

#### 13.3.1 Resource strings

`SErrLogFailedMsg = 'Failed to log entry (Error: %s)'`

Message used to format an error when an error exception is raised.

`SLogCustom = 'Custom (%d)'`

Custom message formatting string

`SLogDebug = 'Debug'`

Debug message name

`SLogError = 'Error'`

Error message name

`SLogInfo = 'Info'`

Informational message name

`SLogWarning = 'Warning'`

Warning message name

### 13.3.2 Types

`TLogCategoryEvent = procedure(Sender: TObject; var Code: Word) of object`

`TLogCategoryEvent` is the event type for the `TEventLog.OnGetCustomCategory` (402) event handler. It should return a OS event category code for the `etCustom` log event type in the `Code` parameter.

`TLogCodeEvent = procedure(Sender: TObject; var Code: DWord) of object`

`TLogCodeEvent` is the event type for the `OnGetCustomEvent` (402) and `OnGetCustomEventID` (402) event handlers. It should return a OS system log code for the `etCustom` log event or event ID type in the `Code` parameter.

`TLogType = (ltSystem, ltFile)`

Table 13.2: Enumeration values for type `TLogType`

Value	Explanation
<code>ltFile</code>	Write to file
<code>ltSystem</code>	Use the system log

`TLogType` determines where the log messages are written. It is the type of the `TEventLog.LogType` (399) property. It can have 2 values:

**ltFile** This is used to write all messages to file. if no system logging mechanism exists, this is used as a fallback mechanism.

**ltSystem** This is used to send all messages to the system log mechanism. Which log mechanism this is, depends on the operating system.

## 13.4 ELogError

### 13.4.1 Description

`ELogError` is the exception used in the `TEventLog` (395) component to indicate errors.

## 13.5 TEventLog

### 13.5.1 Description

`TEventLog` is a component which can be used to send messages to the system log. In case no system log exists (such as on Windows 95/98 or DOS), the messages are written to a file. Messages

can be logged using the general Log (398) call, or the specialized Warning (398), Error (398), Info (399) or Debug (399) calls, which have the event type predefined.

### 13.5.2 Method overview

Page	Property	Description
399	Debug	Log a debug message
396	Destroy	Clean up TEventLog instance
398	Error	Log an error message to
396	EventTypeToString	Create a string representation of an event type
399	Info	Log an informational message
398	Log	Log a message to the system log.
397	RegisterMessageFile	Register message file
398	Warning	Log a warning message.

### 13.5.3 Property overview

Page	Property	Access	Description
400	Active	rw	Activate the log mechanism
401	CustomLogType	rw	Custom log type ID
400	DefaultEventType	rw	Default event type for the Log (398) call.
401	EventIDOffset	rw	Offset for event ID messages identifiers
400	FileName	rw	File name for log file
399	Identification	rw	Identification string for messages
399	LogType	rw	Log type
402	OnGetCustomCategory	rw	Event to retrieve custom message category
402	OnGetCustomEvent	rw	Event to retrieve custom event Code
402	OnGetCustomEventID	rw	Event to retrieve custom event ID
400	RaiseExceptionOnError	rw	Determines whether logging errors are reported or ignored
401	TimeStampFormat	rw	Format for the timestamp string

### 13.5.4 TEventLog.Destroy

Synopsis: Clean up TEventLog instance

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: Destroy cleans up the TEventLog instance. It cleans any log structures that might have been set up to perform logging, by setting the Active (400) property to False.

See also: TEventLog.Active (400)

### 13.5.5 TEventLog.EventTypeToString

Synopsis: Create a string representation of an event type

Declaration: `function EventTypeToString(E: TEventType) : String`

Visibility: `public`

**Description:** `EventTypeToString` converts the event type `E` to a suitable string representation for logging purposes. It's mainly used when writing messages to file, as the system log usually has it's own mechanisms for displaying the various event types.

See also: `TEventType` (394)

### 13.5.6 TEventLog.RegisterMessageFile

**Synopsis:** Register message file

**Declaration:** `function RegisterMessageFile(AFileName: String) : Boolean; Virtual`

**Visibility:** public

**Description:** `RegisterMessageFile` is used on Windows to register the file `AFileName` containing the formatting strings for the system messages. This should be a file containing resource strings. If `AFileName` is empty, the filename of the application binary is substituted.

When a message is logged to the windows system log, Windows looks for a formatting string in the file registered with this call.

There are 2 kinds of formatting strings:

**Category strings** these should be numbered from 1 to 4

**1** Should contain the description of the `etInfo` event type.

**2** Should contain the description of the `etWarning` event type.

**4** Should contain the description of the `etError` event type.

**4** Should contain the description of the `etDebug` event type.

None of these strings should have a string substitution placeholder.

The second type of strings are the **message definitions**. Their number starts at `EventIDOffset` (401) (default is 1000) and each string should have 1 placeholder.

Free Pascal comes with a `fclel.res` resource file which contains default values for the 8 strings, in english. It can be linked in the application binary with the statement

```
{ $R fclel.res }
```

This file is generated from the `fclel.mc` and `fclel.rc` files that are distributed with the Free Pascal sources.

If the strings are not registered, windows will still display the event messages, but they will not be formatted nicely.

Note that while any messages logged with the event logger are displayed in the event viewer Windows locks the file registered here. This usually means that the binary is locked.

On non-windows operating systems, this call is ignored.

**Errors:** If `AFileName` is invalid, false is returned.

### 13.5.7 TEventLog.Log

Synopsis: Log a message to the system log.

Declaration: `procedure Log(EventType: TEventType;Msg: String); Overload`  
`procedure Log(EventType: TEventType;Fmt: String;Args: Array of const)`  
`; Overload`  
`procedure Log(Msg: String); Overload`  
`procedure Log(Fmt: String;Args: Array of const); Overload`

Visibility: public

Description: Log sends a log message to the system log. The message is either the parameter `Msg` as is, or is formatted from the `Fmt` and `Args` parameters. If `EventType` is specified, then it is used as the message event type. If `EventType` is omitted, then the event type is determined from `Default-EventType` (400).

If `EventType` is `etCustom`, then the `OnGetCustomEvent` (402), `OnGetCustomEventID` (402) and `OnGetCustomCategory` (402).

The other logging calls: `Info` (399), `Warning` (398), `Error` (398) and `Debug` (399) use the `Log` call to do the actual work.

See also: `TEventLog.Info` (399), `TEventLog.Warning` (398), `TEventLog.Error` (398), `TEventLog.Debug` (399), `TEventLog.OnGetCustomEvent` (402), `TEventLog.OnGetCustomEventID` (402), `TEventLog.OnGetCustomCategory` (402)

### 13.5.8 TEventLog.Warning

Synopsis: Log a warning message.

Declaration: `procedure Warning(Msg: String); Overload`  
`procedure Warning(Fmt: String;Args: Array of const); Overload`

Visibility: public

Description: `Warning` is a utility function which logs a message with the `etWarning` type. The message is either the parameter `Msg` as is, or is formatted from the `Fmt` and `Args` parameters.

See also: `TEventLog.Log` (398), `TEventLog.Info` (399), `TEventLog.Error` (398), `TEventLog.Debug` (399)

### 13.5.9 TEventLog.Error

Synopsis: Log an error message to

Declaration: `procedure Error(Msg: String); Overload`  
`procedure Error(Fmt: String;Args: Array of const); Overload`

Visibility: public

Description: `Error` is a utility function which logs a message with the `etError` type. The message is either the parameter `Msg` as is, or is formatted from the `Fmt` and `Args` parameters.

See also: `TEventLog.Log` (398), `TEventLog.Info` (399), `TEventLog.Warning` (398), `TEventLog.Debug` (399)



### 13.5.10 TEventLog.Debug

Synopsis: Log a debug message

Declaration: `procedure Debug(Msg: String); Overload`  
`procedure Debug(Fmt: String; Args: Array of const); Overload`

Visibility: public

Description: `Debug` is a utility function which logs a message with the `etDebug` type. The message is either the parameter `Msg` as is, or is formatted from the `Fmt` and `Args` parameters.

See also: `TEventLog.Log` (398), `TEventLog.Info` (399), `TEventLog.Warning` (398), `TEventLog.Error` (398)

### 13.5.11 TEventLog.Info

Synopsis: Log an informational message

Declaration: `procedure Info(Msg: String); Overload`  
`procedure Info(Fmt: String; Args: Array of const); Overload`

Visibility: public

Description: `Info` is a utility function which logs a message with the `etInfo` type. The message is either the parameter `Msg` as is, or is formatted from the `Fmt` and `Args` parameters.

See also: `TEventLog.Log` (398), `TEventLog.Warning` (398), `TEventLog.Error` (398), `TEventLog.Debug` (399)

### 13.5.12 TEventLog.Identification

Synopsis: Identification string for messages

Declaration: `Property Identification : String`

Visibility: published

Access: Read, Write

Description: `Identification` is used as a string identifying the source of the messages in the system log. If it is empty, the filename part of the application binary is used.

See also: `TEventLog.Active` (400), `TEventLog.TimeStampFormat` (401)

### 13.5.13 TEventLog.LogType

Synopsis: Log type

Declaration: `Property LogType : TLogType`

Visibility: published

Access: Read, Write

Description: `LogType` is the type of the log: if it is `ltSystem`, then the system log is used, if it is available. If it is `ltFile` or there is no system log available, then the log messages are written to a file. The name for the log file is taken from the `FileName` (400) property.

See also: `TEventLog.FileName` (400)

### 13.5.14 TEventLog.Active

Synopsis: Activate the log mechanism

Declaration: `Property Active : Boolean`

Visibility: published

Access: Read,Write

Description: `Active` determines whether the log mechanism is active: if set to `True`, the component connects to the system log mechanism, or opens the log file if needed. Any attempt to log a message while the log is not active will try to set this property to `True`. Disconnecting from the system log or closing the log file is done by setting the `Active` property to `False`.

If the connection to the system logger fails, or the log file cannot be opened, then setting this property may result in an exception.

See also: `TEventLog.Log` (398)

### 13.5.15 TEventLog.RaiseExceptionOnError

Synopsis: Determines whether logging errors are reported or ignored

Declaration: `Property RaiseExceptionOnError : Boolean`

Visibility: published

Access: Read,Write

Description: `RaiseExceptionOnError` determines whether an error during a logging operation will be signaled with an exception or not. If set to `False`, errors will be silently ignored, thus not disturbing normal operation of the program.

### 13.5.16 TEventLog.DefaultEventType

Synopsis: Default event type for the `Log` (398) call.

Declaration: `Property DefaultEventType : TEventType`

Visibility: published

Access: Read,Write

Description: `DefaultEventType` is the event type used by the `Log` (398) call if it's `EventType` parameter is omitted.

See also: `TEventLog.Log` (398)

### 13.5.17 TEventLog.FileName

Synopsis: File name for log file

Declaration: `Property FileName : String`

Visibility: published

Access: Read,Write

**Description:** `FileName` is the name of the log file used to log messages if no system logger is available or the `LogType` (394) is `ltFile`. If none is specified, then the name of the application binary is used, with the extension replaced by `.log`. The file is then located in the `/tmp` directory on unix-like systems, or in the application directory for Dos/Windows like systems.

See also: `TEventType.LogType` (394)

### 13.5.18 TEventLog.TimeStampFormat

**Synopsis:** Format for the timestamp string

**Declaration:** `Property TimeStampFormat : String`

**Visibility:** published

**Access:** Read,Write

**Description:** `TimeStampFormat` is the formatting string used to create a timestamp string when writing log messages to file. It should have a format suitable for the `FormatDateTime` (??) call. If it is left empty, then `yyyy-mm-dd hh:nn:ss.zzz` is used.

See also: `TEventLog.Identification` (399)

### 13.5.19 TEventLog.CustomLogType

**Synopsis:** Custom log type ID

**Declaration:** `Property CustomLogType : Word`

**Visibility:** published

**Access:** Read,Write

**Description:** `CustomLogType` is used in the `EventTypeToString` (396) to format the custom log event type string.

See also: `TEventLog.EventTypeToString` (396)

### 13.5.20 TEventLog.EventIDOffset

**Synopsis:** Offset for event ID messages identifiers

**Declaration:** `Property EventIDOffset : DWord`

**Visibility:** published

**Access:** Read,Write

**Description:** `EventIDOffset` is the offset for the message formatting strings in the windows resource file. This property is ignored on other platforms.

The message strings in the file registered with the `RegisterMessageFile` (397) call are windows resource strings. They each have a unique ID, which must be communicated to windows. In the resource file distributed by Free Pascal, the resource strings are numbered from 1000 to 1004. The actual number communicated to windows is formed by adding the ordinal value of the message's eventtype to `EventIDOffset` (which is by default 1000), which means that by default, the string numbers are:

**1000**Custom event types

**1001**Information event type

**1002**Warning event type

**1003**Error event type

**1004**Debug event type

See also: `TEventLog.RegisterMessageFile` ([397](#))

### 13.5.21 `TEventLog.OnGetCustomCategory`

Synopsis: Event to retrieve custom message category

Declaration: `Property OnGetCustomCategory : TLogCategoryEvent`

Visibility: published

Access: Read,Write

Description: `OnGetCustomCategory` is called on the windows platform to determine the category of a custom event type. It should return an ID which will be used by windows to look up the string which describes the message category in the file containing the resource strings.

See also: `TEventLog.OnGetCustomEventID` ([402](#)), `TEventLog.OnGetCustomEvent` ([402](#))

### 13.5.22 `TEventLog.OnGetCustomEventID`

Synopsis: Event to retrieve custom event ID

Declaration: `Property OnGetCustomEventID : TLogCodeEvent`

Visibility: published

Access: Read,Write

Description: `OnGetCustomEventID` is called on the windows platform to determine the category of a custom event type. It should return an ID which will be used by windows to look up the string which formats the message, in the file containing the resource strings.

See also: `TEventLog.OnGetCustomCategory` ([402](#)), `TEventLog.OnGetCustomEvent` ([402](#))

### 13.5.23 `TEventLog.OnGetCustomEvent`

Synopsis: Event to retrieve custom event Code

Declaration: `Property OnGetCustomEvent : TLogCodeEvent`

Visibility: published

Access: Read,Write

Description: `OnGetCustomEvent` is called on the windows platform to determine the event code of a custom event type. It should return an ID.

See also: `TEventLog.OnGetCustomCategory` ([402](#)), `TEventLog.OnGetCustomEventID` ([402](#))

## Chapter 14

# Reference for unit 'ezcgi'

### 14.1 Used units

Table 14.1: Used units by unit 'ezcgi'

Name	Page
Classes	??
strings	<a href="#">403</a>
sysutils	??

### 14.2 Overview

`ezcgi`, written by Michael Hess, provides a single class which offers simple access to the CGI environment which a CGI program operates under. It supports both GET and POST methods. It's intended for simple CGI programs which do not need full-blown CGI support. File uploads are not supported by this component.

To use the unit, a descendent of the `TEZCGI` class should be created and the `DoPost` ([406](#)) or `DoGet` ([406](#)) methods should be overridden.

### 14.3 Constants, types and variables

#### 14.3.1 Constants

```
hexTable = '0123456789ABCDEF'
```

String constant used to convert a number to a hexadecimal code or back.

### 14.4 ECGIException

#### 14.4.1 Description

Exception raised by `TEZcgi` ([404](#))

## 14.5 TEZcgi

### 14.5.1 Description

TEZcgi implements all functionality to analyze the CGI environment and query the variables present in it. It's main use is the exposed variables.

Programs wishing to use this class should make a descendent class of this class and override the DoPost (406) or DoGet (406) methods. To run the program, an instance of this class must be created, and it's Run (405) method should be invoked. This will analyze the environment and call the DoPost or DoGet method, depending on what HTTP method was used to invoke the program.

### 14.5.2 Method overview

Page	Property	Description
<a href="#">404</a>	Create	Creates a new instance of the TEZCGI component
<a href="#">404</a>	Destroy	Removes the TEZCGI component from memory
<a href="#">406</a>	DoGet	Method to handle GET requests
<a href="#">406</a>	DoPost	Method to handle POST requests
<a href="#">406</a>	GetValue	Return the value of a request variable.
<a href="#">405</a>	PutLine	Send a line of output to the web-client
<a href="#">405</a>	Run	Run the CGI application.
<a href="#">405</a>	WriteContent	Writes the content type to standard output

### 14.5.3 Property overview

Page	Property	Access	Description
<a href="#">408</a>	Email	rw	Email of the server administrator
<a href="#">408</a>	Name	rw	Name of the server administrator
<a href="#">407</a>	Names	r	Indexed array with available variable names.
<a href="#">406</a>	Values	r	Variables passed to the CGI script
<a href="#">408</a>	VariableCount	r	Number of available variables.
<a href="#">407</a>	Variables	r	Indexed array with variables as name=value pairs.

### 14.5.4 TEZcgi.Create

Synopsis: Creates a new instance of the TEZCGI component

Declaration: `constructor Create`

Visibility: `public`

Description: `Create` initializes the CGI program's environment: it reads the environment variables passed to the CGI program and stores them in the Variable (403) property.

See also: TZEZCGI.Variables (403), TZEZCGI.Names (403), TZEZCGI.Values (403)

### 14.5.5 TEZcgi.Destroy

Synopsis: Removes the TEZCGI component from memory

Declaration: `destructor Destroy;` `Override`

Visibility: `public`

**Description:** `Destroy` removes all variables from memory and then calls the inherited `destroy`, removing the `TEZCGI` instance from memory.

`Destroy` should never be called directly. Instead `Free` should be used, or `FreeAndNil`

See also: `TEZcgi.Create` (404)

### 14.5.6 TEZcgi.Run

**Synopsis:** Run the CGI application.

**Declaration:** `procedure Run`

**Visibility:** `public`

**Description:** `Run` analyses the variables passed to the application, processes the request variables (it stores them in the `Variables` (403) property) and calls the `DoPost` (406) or `DoGet` (406) methods, depending on the method passed to the web server.

After creating the instance of `TEZCGI`, the `Run` method is the only method that should be called when using this component.

See also: `TEZCGI.Variables` (403), `TEZCGI.DoPost` (406), `TEZCGI.DoGet` (406)

### 14.5.7 TEZcgi.WriteContent

**Synopsis:** Writes the content type to standard output

**Declaration:** `procedure WriteContent(cType: String)`

**Visibility:** `public`

**Description:** `WriteContent` writes the content type `cType` to standard output, followed by an empty line.

After this method was called, no more HTTP headers may be written to standard output. Any HTTP headers should be written before `WriteContent` is called. It should be called from the `DoPost` (406) or `DoGet` (406) methods.

See also: `TEZCGI.DoPost` (406), `TEZCGI.DoGet` (406), `TEZcgi.PutLine` (405)

### 14.5.8 TEZcgi.PutLine

**Synopsis:** Send a line of output to the web-client

**Declaration:** `procedure PutLine(sOut: String)`

**Visibility:** `public`

**Description:** `PutLine` writes a line of text (`sOut`) to the web client (currently, to standard output). It should be called only after `WriteContent` (405) was called with a content type of `text`. The sent text is not processed in any way, i.e. no HTML entities or so are inserted instead of special HTML characters. This should be done by the user.

**Errors:** No check is performed whether the content type is right.

See also: `TEZcgi.WriteContent` (405)

### 14.5.9 TEZcgi.GetValue

Synopsis: Return the value of a request variable.

Declaration: `function GetValue(Index: String; defaultValue: String) : String`

Visibility: public

Description: `GetValue` returns the value of the variable named `Index`, and returns `DefaultValue` if it is empty or does not exist.

See also: `TEZCGI.Values` (406)

### 14.5.10 TEZcgi.DoPost

Synopsis: Method to handle POST requests

Declaration: `procedure DoPost; Virtual`

Visibility: public

Description: `DoPost` is called by the `Run` (405) method the POST method was used to invoke the CGI application. It should be overridden in descendents of `TEZcgi` to actually handle the request.

See also: `TEZcgi.Run` (405), `TEZcgi.DoGet` (406)

### 14.5.11 TEZcgi.DoGet

Synopsis: Method to handle GET requests

Declaration: `procedure DoGet; Virtual`

Visibility: public

Description: `DoGet` is called by the `Run` (405) method the GET method was used to invoke the CGI application. It should be overridden in descendents of `TEZcgi` to actually handle the request.

See also: `TEZcgi.Run` (405), `TEZcgi.DoPost` (406)

### 14.5.12 TEZcgi.Values

Synopsis: Variables passed to the CGI script

Declaration: `Property Values[Index: String]: String`

Visibility: public

Access: Read

Description: `Values` is a name-based array of variables that were passed to the script by the web server or the HTTP request. The `Index` variable is the name of the variable whose value should be retrieved. The following standard values are available:

**AUTH\_TYPE**Authorization type

**CONTENT\_LENGTH**Content length

**CONTENT\_TYPE**Content type



**GATEWAY\_INTERFACE**Used gateway interface  
**PATH\_INFO**Requested URL  
**PATH\_TRANSLATED**Transformed URL  
**QUERY\_STRING**Client query string  
**REMOTE\_ADDR**Address of remote client  
**REMOTE\_HOST**DNS name of remote client  
**REMOTE\_IDENT**Remote identity.  
**REMOTE\_USER**Remote user  
**REQUEST\_METHOD**Request methods (POST or GET)  
**SCRIPT\_NAME**Script name  
**SERVER\_NAME**Server host name  
**SERVER\_PORT**Server port  
**SERVER\_PROTOCOL**Server protocol  
**SERVER\_SOFTWARE**Web server software  
**HTTP\_ACCEPT**Accepted responses  
**HTTP\_ACCEPT\_CHARSET**Accepted character sets  
**HTTP\_ACCEPT\_ENCODING**Accepted encodings  
**HTTP\_IF\_MODIFIED\_SINCE**Proxy information  
**HTTP\_REFERER**Referring page  
**HTTP\_USER\_AGENT**Client software name

Other than the standard list, any variables that were passed by the web-client request, are also available. Note that the variables are case insensitive.

See also: [TEZCGI.Variables \(407\)](#), [TEZCGI.Names \(407\)](#), [TEZCGI.GetValue \(406\)](#), [TEZcgi.VariableCount \(408\)](#)

### 14.5.13 TEZcgi.Names

Synopsis: Indexed array with available variable names.

Declaration: `Property Names[Index: Integer]: String`

Visibility: public

Access: Read

Description: `Names` provides indexed access to the available variable names. The `Index` may run from 0 to `VariableCount` ([408](#)). Any other value will result in an exception being raised.

See also: [TEZcgi.Variables \(407\)](#), [TEZcgi.Values \(406\)](#), [TEZcgi.GetValue \(406\)](#), [TEZcgi.VariableCount \(408\)](#)

### 14.5.14 TEZcgi.Variables

Synopsis: Indexed array with variables as name=value pairs.

Declaration: `Property Variables[Index: Integer]: String`

Visibility: public

Access: Read

Description: `Variables` provides indexed access to the available variable names and values. The variables are returned as `Name=Value` pairs. The `Index` may run from 0 to `VariableCount` (408). Any other value will result in an exception being raised.

See also: `TEZcgi.Names` (407), `TEZcgi.Values` (406), `TEZcgi.GetValue` (406), `TEZcgi.VariableCount` (408)

### 14.5.15 TEZcgi.VariableCount

Synopsis: Number of available variables.

Declaration: `Property VariableCount : Integer`

Visibility: public

Access: Read

Description: `TEZcgi.VariableCount` returns the number of available CGI variables. This includes both the standard CGI environment variables and the request variables. The actual names and values can be retrieved with the `Names` (407) and `Variables` (407) properties.

See also: `TEZcgi.Names` (407), `TEZcgi.Variables` (407), `TEZcgi.Values` (406), `TEZcgi.GetValue` (406)

### 14.5.16 TEZcgi.Name

Synopsis: Name of the server administrator

Declaration: `Property Name : String`

Visibility: public

Access: Read,Write

Description: `Name` is used when displaying an error message to the user. This should set prior to calling the `TEZcgi.Run` (405) method.

See also: `TEZcgi.Run` (405), `TEZcgi.Email` (408)

### 14.5.17 TEZcgi.Email

Synopsis: Email of the server administrator

Declaration: `Property Email : String`

Visibility: public

Access: Read,Write

Description: `Email` is used when displaying an error message to the user. This should set prior to calling the `TEZcgi.Run` (405) method.

See also: `TEZcgi.Run` (405), `TEZcgi.Name` (408)

## Chapter 15

# Reference for unit 'fpTimer'

### 15.1 Used units

Table 15.1: Used units by unit 'fpTimer'

Name	Page
Classes	??

### 15.2 Overview

The `fpTimer` unit implements a timer class `TFPTimer` (411) which can be used on all supported platforms. The timer class uses a driver class `TFPTimerDriver` (412) which does the actual work.

A default timer driver class is implemented on all platforms. It will work in GUI and non-gui applications, but only in the application's main thread.

An alternative driver class can be used by setting the `DefaultTimerDriverClass` (409) variable to the class pointer of the driver class. The driver class should descend from `TFPTimerDriver` (412).

### 15.3 Constants, types and variables

#### 15.3.1 Types

```
TFPTimerDriverClass = Class of TFPTimerDriver
```

`TFPTimerDriverClass` is the class pointer of `TFPTimerDriver` (412) it exists mainly for the purpose of being able to set `DefaultTimerDriverClass` (409), so a custom timer driver can be used for the timer instances.

#### 15.3.2 Variables

```
DefaultTimerDriverClass : TFPTimerDriverClass = nil
```

`DefaultTimerDriverClass` contains the `TFPTimerDriver` (412) class pointer that should be used when a new instance of `TFPCustomTimer` (410) is created. It is by default set to the system timer class.

Setting this class pointer to another descendent of `TFPTimerDriver` allows to customize the default timer implementation used in the entire application.

## 15.4 TFPCustomTimer

### 15.4.1 Description

`TFPCustomTimer` is the timer class containing the timer's implementation. It relies on an extra driver instance (of type `TFPTimerDriver` (412)) to do the actual work.

`TFPCustomTimer` publishes no events or properties, so it is unsuitable for handling in an IDE. The `TFPTimer` (411) descendent class publishes all needed events of `TFPCustomTimer`.

### 15.4.2 Method overview

Page	Property	Description
410	Create	Create a new timer
410	Destroy	Release a timer instance from memory
411	StartTimer	Start the timer
411	StopTimer	Stop the timer

### 15.4.3 TFPCustomTimer.Create

Synopsis: Create a new timer

Declaration: `constructor Create(AOwner: TComponent); Override`

Visibility: public

Description: `Create` instantiates a new `TFPCustomTimer` instance. It creates the timer driver instance from the `DefaultTimerDriverClass` class pointer.

See also: `TFPCustomTimer.Destroy` (410)

### 15.4.4 TFPCustomTimer.Destroy

Synopsis: Release a timer instance from memory

Declaration: `destructor Destroy; Override`

Visibility: public

Description: `Destroy` releases the timer driver component from memory, and then calls `Inherited` to clean the `TFPCustomTimer` instance from memory.

See also: `TFPCustomTimer.Create` (410)

### 15.4.5 TFPCustomTimer.StartTimer

Synopsis: Start the timer

Declaration: `procedure StartTimer; Virtual`

Visibility: `public`

Description: `StartTimer` starts the timer. After a call to `StartTimer`, the timer will start producing timer ticks.

The timer stops producing ticks only when the `StopTimer` (411) event is called.

See also: `TFPCustomTimer.StopTimer` (411), `TFPTimer.Enabled` (411), `TFPTimer.OnTimer` (412)

### 15.4.6 TFPCustomTimer.StopTimer

Synopsis: Stop the timer

Declaration: `procedure StopTimer; Virtual`

Visibility: `public`

Description: `StopTimer` stops a started timer. After a call to `StopTimer`, the timer no longer produces timer ticks.

See also: `TFPCustomTimer.StartTimer` (411), `TFPTimer.Enabled` (411), `TFPTimer.OnTimer` (412)

## 15.5 TFPTimer

### 15.5.1 Description

`TFPTimer` implements no new events or properties, but merely publishes events and properties already implemented in `TFPCustomTimer` (410): `Enabled` (411), `OnTimer` (412) and `Interval` (412).

The `TFPTimer` class is suitable for use in an IDE.

### 15.5.2 Property overview

Page	Property	Access	Description
411	<code>Enabled</code>		Start or stop the timer
412	<code>Interval</code>		Timer tick interval in milliseconds.
412	<code>OnTimer</code>		Event called on each timer tick.

### 15.5.3 TFPTimer.Enabled

Synopsis: Start or stop the timer

Declaration: `Property Enabled :`

Visibility: `published`

Access:

Description: `Enabled` controls whether the timer is active. Setting `Enabled` to `True` will start the timer (calling `StartTimer` (411)), setting it to `False` will stop the timer (calling `StopTimer` (411)).

See also: `TFPCustomTimer.StartTimer` (411), `TFPCustomTimer.StopTimer` (411), `TFPTimer.OnTimer` (412), `TFPTimer.Interval` (412)

### 15.5.4 TFPTimer.Interval

Synopsis: Timer tick interval in milliseconds.

Declaration: `Property Interval :`

Visibility: published

Access:

Description: `Interval` specifies the timer interval in milliseconds. Every `Interval` milliseconds, the `OnTimer` (412) event handler will be called.

Note that the milliseconds interval is a minimum interval. Under high system load, the timer tick may arrive later.

See also: `TFPTimer.OnTimer` (412), `TFPTimer.Enabled` (411)

### 15.5.5 TFPTimer.OnTimer

Synopsis: Event called on each timer tick.

Declaration: `Property OnTimer :`

Visibility: published

Access:

Description: `OnTimer` is called on each timer tick. The event handler must be assigned to a method that will do the actual work that should occur when the timer fires.

See also: `TFPTimer.Interval` (412), `TFPTimer.Enabled` (411)

## 15.6 TFPTimerDriver

### 15.6.1 Description

`TFPTimerDriver` is the abstract timer driver class: it simply provides an interface for the `TFP-CustomTimer` (410) class to use.

The `fpTimer` unit implements a descendent of this class which implements the default timer mechanism.

### 15.6.2 Method overview

Page	Property	Description
413	Create	Create new driver instance
413	StartTimer	Start the timer
413	StopTimer	Stop the timer

### 15.6.3 Property overview

Page	Property	Access	Description
413	Timer	r	Timer tick

### 15.6.4 TFPTimerDriver.Create

Synopsis: Create new driver instance

Declaration: `constructor Create(ATimer: TFPCustomTimer); Virtual`

Visibility: public

Description: `Create` should be overridden by descendents of `TFPTimerDriver` to do additional initialization of the timer driver. `Create` just stores (in `Timer` (413)) a reference to the `ATimer` instance which created the driver instance.

See also: `TFPTimerDriver.Timer` (413), `TFPTimer` (411)

### 15.6.5 TFPTimerDriver.StartTimer

Synopsis: Start the timer

Declaration: `procedure StartTimer; Virtual; Abstract`

Visibility: public

Description: `StartTimer` is called by `TFPCustomTimer.StartTimer` (411). It should be overridden by descendents of `TFPTimerDriver` to actually start the timer.

See also: `TFPCustomTimer.StartTimer` (411), `TFPTimerDriver.StopTimer` (413)

### 15.6.6 TFPTimerDriver.StopTimer

Synopsis: Stop the timer

Declaration: `procedure StopTimer; Virtual; Abstract`

Visibility: public

Description: `StopTimer` is called by `TFPCustomTimer.StopTimer` (411). It should be overridden by descendents of `TFPTimerDriver` to actually stop the timer.

See also: `TFPCustomTimer.StopTimer` (411), `TFPTimerDriver.StartTimer` (413)

### 15.6.7 TFPTimerDriver.Timer

Synopsis: Timer tick

Declaration: `Property Timer : TFPCustomTimer`

Visibility: public

Access: Read

Description: `Timer` calls the `TFPCustomTimer` (410) timer event. Descendents of `TFPTimerDriver` should call `Timer` whenever a timer tick occurs.

See also: `TFPTimer.OnTimer` (412), `TFPTimerDriver.StartTimer` (413), `TFPTimerDriver.StopTimer` (413)

# Chapter 16

## Reference for unit 'gettext'

### 16.1 Used units

Table 16.1: Used units by unit 'gettext'

Name	Page
Classes	??
sysutils	??

### 16.2 Overview

The `gettext` unit can be used to hook into the resource string mechanism of Free Pascal to provide translations of the resource strings, based on the GNU `gettext` mechanism. The unit provides a class (`TMOFile` ([416](#))) to read the `.mo` files with localizations for various languages. It also provides a couple of calls to translate all resource strings in an application based on the translations in a `.mo` file.

### 16.3 Constants, types and variables

#### 16.3.1 Constants

```
MOFileHeaderMagic = $950412de
```

This constant is found as the first integer in a `.mo`

#### 16.3.2 Types

```
PLongWordArray = ^TLongWordArray
```

Pointer to a `TLongWordArray` ([415](#)) array.

```
PMOStringTable = ^TMOStringTable
```



Pointer to a TMOStringTable (415) array.

```
PPCharArray = ^TPCharArray
```

Pointer to a TPCharArray (415) array.

```
TLongWordArray = Array[0..(1 shl 30) div SizeOf(LongWord)] of LongWord
```

TLongWordArray is an array used to define the PLongWordArray (414) pointer. A variable of type TLongWordArray should never be directly declared, as it would occupy too much memory. The PLongWordArray type can be used to allocate a dynamic number of elements.

```
TMOFileHeader = packed record
  magic : LongWord;
  revision : LongWord;
  nstrings : LongWord;
  OrigTabOffset : LongWord;
  TransTabOffset : LongWord;
  HashTabSize : LongWord;
  HashTabOffset : LongWord;
end
```

This structure describes the structure of a .mo file with string localizations.

```
TMOStringInfo = packed record
  length : LongWord;
  offset : LongWord;
end
```

This record is one element in the string tables describing the original and translated strings. It describes the position and length of the string. The location of these tables is stored in the TMOFileHeader (415) record at the start of the file.

```
TMOStringTable = Array[0..(1 shl 30) div SizeOf(TMOStringInfo)] of TMOStringInfo
```

TMOStringTable is an array type containing TMOStringInfo (415) records. It should never be used directly, as it would occupy too much memory.

```
TPCharArray = Array[0..(1 shl 30) div SizeOf(PChar)] of PChar
```

TLongWordArray is an array used to define the PPCharArray (415) pointer. A variable of type TPCharArray should never be directly declared, as it would occupy too much memory. The PPCharArray type can be used to allocate a dynamic number of elements.

## 16.4 Procedures and functions

### 16.4.1 GetLanguageIDs

Synopsis: Return the current language IDs

**Declaration:** `procedure GetLanguageIDs (var Lang: String; var FallbackLang: String)`

**Visibility:** default

**Description:** `GetLanguageIDs` returns the current language IDs (an ISO string) as returned by the operating system. On windows, the `GetUserDefaultLCID` and `GetLocaleInfo` calls are used. On other operating systems, the `LC_ALL`, `LC_MESSAGES` or `LANG` environment variables are examined.

## 16.4.2 TranslateResourceStrings

**Synopsis:** Translate the resource strings of the application.

**Declaration:** `procedure TranslateResourceStrings (AFile: TMOFile)`  
`procedure TranslateResourceStrings (const AFilename: String)`

**Visibility:** default

**Description:** `TranslateResourceStrings` translates all the resource strings in the application based on the values in the `.mo` file `AFileName` or `AFile`. The procedure creates an `TMOFile` (416) instance to read the `.mo` file if a filename is given.

**Errors:** If the file does not exist or is an invalid `.mo` file.

**See also:** `TranslateUnitResourceStrings` (416), `TMOFile` (416)

## 16.4.3 TranslateUnitResourceStrings

**Synopsis:** Translate the resource strings of a unit.

**Declaration:** `procedure TranslateUnitResourceStrings (const AUnitName: String;`  
`AFile: TMOFile)`  
`procedure TranslateUnitResourceStrings (const AUnitName: String;`  
`const AFilename: String)`

**Visibility:** default

**Description:** `TranslateUnitResourceStrings` is identical in function to `TranslateResourceStrings` (416), but translates the strings of a single unit (`AUnitName`) which was used to compile the application. This can be more convenient, since the resource string files are created on a unit basis.

**See also:** `TranslateResourceStrings` (416), `TMOFile` (416)

## 16.5 EMOFileError

### 16.5.1 Description

`EMOFileError` is raised in case an `TMOFile` (416) instance is created with an invalid `.mo`.

## 16.6 TMOFile

### 16.6.1 Description

`TMOFile` is a class providing easy access to a `.mo` file. It can be used to translate any of the strings that reside in the `.mo` file. The internal structure of the `.mo` is completely hidden.

### 16.6.2 Method overview

Page	Property	Description
<a href="#">417</a>	Create	Create a new instance of the <code>TMOFile</code> class.
<a href="#">417</a>	Destroy	Removes the <code>TMOFile</code> instance from memory
<a href="#">417</a>	Translate	Translate a string

### 16.6.3 TMOFile.Create

**Synopsis:** Create a new instance of the `TMOFile` class.

**Declaration:** `constructor Create(const AFilename: String)`  
`constructor Create(AStream: TStream)`

**Visibility:** `public`

**Description:** `Create` creates a new instance of the `MOFile` class. It opens the file `AFilename` or the stream `AStream`. If a stream is provided, it should be seekable.

The whole contents of the file is read into memory during the `Create` call. This means that the stream is no longer needed after the `Create` call.

**Errors:** If the named file does not exist, then an exception may be raised. If the file does not contain a valid `TMOFileHeader` ([415](#)) structure, then an `EMOFileError` ([416](#)) exception is raised.

See also: `TMOFile.Destroy` ([417](#))

### 16.6.4 TMOFile.Destroy

**Synopsis:** Removes the `TMOFile` instance from memory

**Declaration:** `destructor Destroy; Override`

**Visibility:** `public`

**Description:** `Destroy` cleans the internal structures with the contents of the `.mo`. After this the `TMOFile` instance is removed from memory.

See also: `TMOFile.Create` ([417](#))

### 16.6.5 TMOFile.Translate

**Synopsis:** Translate a string

**Declaration:** `function Translate(AOrig: PChar; ALen: Integer; AHash: LongWord) : String`  
`function Translate(AOrig: String; AHash: LongWord) : String`  
`function Translate(AOrig: String) : String`

**Visibility:** `public`

**Description:** `Translate` translates the string `AOrig`. The string should be in the `.mo` file as-is. The string can be given as a plain string, as a `PChar` (with length `ALen`). If the hash value (`AHash`) of the string is not given, it is calculated.

If the string is in the `.mo` file, the translated string is returned. If the string is not in the file, an empty string is returned.

**Errors:** None.

## Chapter 17

# Reference for unit 'idea'

### 17.1 Used units

Table 17.1: Used units by unit 'idea'

Name	Page
Classes	??
sysutils	??

### 17.2 Overview

Besides some low level IDEA encryption routines, the IDEA unit also offers 2 streams which offer on-the-fly encryption or decryption: there are 2 stream objects: A write-only encryption stream which encrypts anything that is written to it, and a decryption stream which decrypts anything that is read from it.

### 17.3 Constants, types and variables

#### 17.3.1 Constants

`IDEABLOCKSIZE = 8`

IDEA block size

`IDEAKEYSIZE = 16`

IDEA Key size constant.

`KEYLEN = (6*ROUNDS+4)`

Key length

`ROUNDS = 8`

Number of rounds to encrypt

### 17.3.2 Types

`IdeaCryptData = TideaCryptData`

Provided for backward functionality.

`IdeaCryptKey = TideaCryptKey`

Provided for backward functionality.

`IDEAkey = TIDEAKey`

Provided for backward functionality.

`TideaCryptData = Array[0..3] of Word`

`TideaCryptData` is an internal type, defined to hold data for encryption/decryption.

`TideaCryptKey = Array[0..7] of Word`

The actual encryption or decryption key for IDEA is 64-bit long. This type is used to hold such a key. It can be generated with the `EnKeyIDEA` (420) or `DeKeyIDEA` (419) algorithms depending on whether an encryption or decryption key is needed.

`TIDEAKey = Array[0..keylen-1] of Word`

The IDEA key should be filled by the user with some random data (say, a passphrase). This key is used to generate the actual encryption/decryption keys.

## 17.4 Procedures and functions

### 17.4.1 CipherIdea

**Synopsis:** Encrypt or decrypt a buffer.

**Declaration:** `procedure CipherIdea(Input: TideaCryptData; var outdata: TideaCryptData;  
z: TIDEAKey)`

**Visibility:** default

**Description:** `CipherIdea` encrypts or decrypts a buffer with data (`Input`) using key `z`. The resulting encrypted or decrypted data is returned in `Output`.

**Errors:** None.

**See also:** `EnKeyIdea` (420), `DeKeyIdea` (419), `TIDEAEncryptStream` (421), `TIDEADecryptStream` (420)

### 17.4.2 DeKeyIdea

**Synopsis:** Create a decryption key from an encryption key.

**Declaration:** `procedure DeKeyIdea(z: TIDEAKey; var dk: TIDEAKey)`

**Visibility:** default

**Description:** `DeKeyIdea` creates a decryption key based on the encryption key `z`. The decryption key is returned in `dk`. Note that only a decryption key generated from the encryption key that was used to encrypt the data can be used to decrypt the data.

Errors: None.

See also: `EnKeyIdea` ([420](#)), `CipherIdea` ([419](#))

### 17.4.3 EnKeyIdea

**Synopsis:** Create an IDEA encryption key from a user key.

**Declaration:** `procedure EnKeyIdea (UserKey: TIDEACryptKey; var z: TIDEAKey)`

Visibility: default

**Description:** `EnKeyIdea` creates an IDEA encryption key from user-supplied data in `UserKey`. The Encryption key is stored in `z`.

Errors: None.

See also: `DeKeyIdea` ([419](#)), `CipherIdea` ([419](#))

## 17.5 EIDEAError

### 17.5.1 Description

`EIDEAError` is used to signal errors in the IDEA encryption decryption streams.

## 17.6 TIDEADeCryptStream

### 17.6.1 Description

`TIDEADeCryptStream` is a stream which decrypts anything that is read from it using the IDEA mechanism. It reads the encrypted data from a source stream and decrypts it using the `CipherIDEA` ([419](#)) algorithm. It is a read-only stream: it is not possible to write data to this stream.

When creating a `TIDEADeCryptStream` instance, an IDEA decryption key should be passed to the constructor, as well as the stream from which encrypted data should be read written.

The encrypted data can be created with a `TIDEAEncryptStream` ([421](#)) encryption stream.

### 17.6.2 Method overview

Page	Property	Description
<a href="#">420</a>	Create	Constructor to create a new <code>TIDEADeCryptStream</code> instance
<a href="#">421</a>	Read	Reads data from the stream, decrypting it as needed
<a href="#">421</a>	Seek	Set position on the stream

### 17.6.3 TIDEADeCryptStream.Create

**Synopsis:** Constructor to create a new `TIDEADeCryptStream` instance

**Declaration:** `constructor Create (const AKey: String; Dest: TStream); Overload`

Visibility: public

**Description:** `Create` creates a new `TIDEADecryptStream` instance using the the string `AKey` to compute the encryption key (419), which is then passed on to the inherited constructor `TIDEAStream.Create` (424). It is an easy-access function which introduces no new functionality.

The string is truncated at the maximum length of the `TideaCryptKey` (419) structure, so it makes no sense to provide a string with length longer than this structure.

See also: `TideaCryptKey` (419), `TIDEAStream.Create` (424), `TIDEAEncryptStream.Create` (422)

### 17.6.4 TIDEADeCryptStream.Read

**Synopsis:** Reads data from the stream, decrypting it as needed

**Declaration:** `function Read(var Buffer; Count: LongInt) : LongInt; Override`

Visibility: public

**Description:** `Read` attempts to read `Count` bytes from the stream, placing them in `Buffer` the bytes are read from the source stream and decrypted as they are read. (bytes are read from the source stream in blocks of 8 bytes. The function returns the number of bytes actually read.

**Errors:** If an error occurs when reading data from the source stream, an exception may be raised.

See also: `TIDEADecryptStream.Write` (420), `TIDEADecryptStream.Seek` (421), `TIDEAEncryptStream` (421)

### 17.6.5 TIDEADeCryptStream.Seek

**Synopsis:** Set position on the stream

**Declaration:** `function Seek(Offset: LongInt; Origin: Word) : LongInt; Override`

Visibility: public

**Description:** `Seek` will only work on a forward seek. It emulates a forward seek by reading and discarding bytes from the input stream. The `TIDEADecryptStream` stream tries to provide seek capabilities for the following limited number of cases:

**Origin=soFromBeginning** If `Offset` is larger than the current position, then the remaining bytes are skipped by reading them from the stream and discarding them.

**Origin=soFromCurrent** If `Offset` is zero, the current position is returned. If it is positive, then `Offset` bytes are skipped by reading them from the stream and discarding them.

**Errors:** An `EIDEAError` (420) exception is raised if the stream does not allow the requested seek operation.

See also: `TIDEADeCryptStream.Read` (421)

## 17.7 TIDEAEncryptStream

### 17.7.1 Description

`TIDEAEncryptStream` is a stream which encrypts anything that is written to it using the IDEA mechanism, and then writes the encrypted data to the destination stream using the `CipherIDEA` (419) algorithm. It is a write-only stream: it is not possible to read data from this stream.

When creating a `TIDEAEncryptStream` instance, an IDEA encryption key should be passed to the constructor, as well as the stream to which encrypted data should be written.

The resulting encrypted data can be read again with a `TIDEADecryptStream` (420) decryption stream.

### 17.7.2 Method overview

Page	Property	Description
<a href="#">422</a>	Create	Constructor to create a new <code>TIDEAEncryptStream</code> instance
<a href="#">422</a>	Destroy	Flush data buffers and free the stream instance.
<a href="#">423</a>	Flush	Write remaining bytes from the stream
<a href="#">423</a>	Seek	Set stream position
<a href="#">422</a>	Write	Write bytes to the stream to be encrypted

### 17.7.3 TIDEAEncryptStream.Create

**Synopsis:** Constructor to create a new `TIDEAEncryptStream` instance

**Declaration:** `constructor Create(const AKey: String; Dest: TStream);` Overload

**Visibility:** public

**Description:** `Create` creates a new `TIDEAEncryptStream` instance using the the string `AKey` to compute the encryption key ([419](#)), which is then passed on to the inherited constructor `TIDEAStream.Create` ([424](#)). It is an easy-access function which introduces no new functionality.

The string is truncated at the maximum length of the `TIdeaCryptKey` ([419](#)) structure, so it makes no sense to provide a string with length longer than this structure.

See also: `TIdeaCryptKey` ([419](#)), `TIDEAStream.Create` ([424](#)), `TIDEADeCryptStream.Create` ([420](#))

### 17.7.4 TIDEAEncryptStream.Destroy

**Synopsis:** Flush data buffers and free the stream instance.

**Declaration:** `destructor Destroy;` Override

**Visibility:** public

**Description:** `Destroy` flushes any data still remaining in the internal encryption buffer, and then calls the inherited `Destroy`

By default, the destination stream is not freed when the encryption stream is freed.

**Errors:** None.

See also: `TIDEAStream.Create` ([424](#))

### 17.7.5 TIDEAEncryptStream.Write

**Synopsis:** Write bytes to the stream to be encrypted

**Declaration:** `function Write(const Buffer; Count: LongInt) : LongInt;` Override

**Visibility:** public

**Description:** `Write` writes `Count` bytes from `Buffer` to the stream, encrypting the bytes as they are written (encryption in blocks of 8 bytes).

**Errors:** If an error occurs writing to the destination stream, an error may occur.

See also: `TIDEADeCryptStream.Read` ([421](#))



### 17.7.6 TIDEAEncryptStream.Seek

Synopsis: Set stream position

Declaration: `function Seek(Offset: LongInt; Origin: Word) : LongInt; Override`

Visibility: public

Description: `Seek` return the current position if called with 0 and `soFromCurrent` as arguments. With all other values, it will always raise an exception, since it is impossible to set the position on an encryption stream.

Errors: An `EIDEAError` (420) will be raised unless called with 0 and `soFromCurrent` as arguments.

See also: `TIDEAEncryptStream.Write` (422), `EIDEAError` (420)

### 17.7.7 TIDEAEncryptStream.Flush

Synopsis: Write remaining bytes from the stream

Declaration: `procedure Flush`

Visibility: public

Description: `Flush` writes the current encryption buffer to the stream. Encryption always happens in blocks of 8 bytes, so if the buffer is not completely filled at the end of the writing operations, it must be flushed. It should never be called directly, unless at the end of all writing operations. It is called automatically when the stream is destroyed.

Errors: None.

See also: `TIDEAEncryptStream.Write` (422)

## 17.8 TIDEAStream

### 17.8.1 Description

Do not create instances of `TIDEAStream` directly. It implements no useful functionality: it serves as a common ancestor of the `TIDEAEncryptStream` (421) and `TIDEADeCryptStream` (420), and simply provides some fields that these descendent classes use when encrypting/decrypting. One of these classes should be created, depending on whether one wishes to encrypt or to decrypt.

### 17.8.2 Method overview

Page	Property	Description
424	Create	Creates a new instance of the <code>TIDEAStream</code> class

### 17.8.3 Property overview

Page	Property	Access	Description
424	Key	r	Key used when encrypting/decrypting

#### 17.8.4 TIDEAStream.Create

Synopsis: Creates a new instance of the `TIDEAStream` class

Declaration: `constructor Create(AKey: TIDEAKey; Dest: TStream);` Overload

Visibility: `public`

Description: `Create` stores the encryption/decryption key and then calls the inherited `Create` to store the `Dest` stream.

Errors: None.

See also: `TIDEAEncryptStream` ([421](#)), `TIDEADeCryptStream` ([420](#))

#### 17.8.5 TIDEAStream.Key

Synopsis: Key used when encrypting/decrypting

Declaration: `Property Key : TIDEAKey`

Visibility: `public`

Access: `Read`

Description: `Key` is the key as it was passed to the constructor of the stream. It cannot be changed while data is read or written. It is the key as it is used when encrypting/decrypting.

See also: `CipherIdea` ([419](#))

## Chapter 18

# Reference for unit 'inicol'

### 18.1 Used units

Table 18.1: Used units by unit 'inicol'

Name	Page
Classes	??
Inifiles	<a href="#">425</a>
sysutils	??

### 18.2 Overview

`inicol` contains an implementation of `TCollection` and `TCollectionItem` descendents which cooperate to read and write the collection from and to a `.ini` file. It uses the `TCustomIniFile` ([435](#)) class for this.

### 18.3 Constants, types and variables

#### 18.3.1 Constants

`KeyCount` = 'Count'

`KeyCount` is used as a key name when reading or writing the number of items in the collection from the global section.

`SGlobal` = 'Global'

`SGlobal` is used as the default name of the global section when reading or writing the collection.

## 18.4 EIniCol

### 18.4.1 Description

EIniCol is used to report error conditions in the load and save methods of TIniCollection (426).

## 18.5 TIniCollection

### 18.5.1 Description

TIniCollection is a collection (??) descendent which has the capability to write itself to an .ini file. It introduces some load and save mechanisms, which can be used to write all items in the collection to disk. The items should be descendents of the type TIniCollectionItem (429).

All methods work using a TCustomIniFile class, making it possible to save to alternate file formats, or even databases.

An instance of TIniCollection should never be used directly. Instead, a descendent should be used, which sets the FPrefix and FSectionPrefix protected variables.

### 18.5.2 Method overview

Page	Property	Description
426	Load	Loads the collection from the default filename.
428	LoadFromFile	Load collection from file.
428	LoadFromIni	Load collection from a file in .ini file format.
427	Save	Save the collection to the default filename.
427	SaveToFile	Save collection to a file in .ini file format
427	SaveToIni	Save the collection to a TCustomIniFile descendent

### 18.5.3 Property overview

Page	Property	Access	Description
429	FileName	rw	Filename of the collection
429	GlobalSection	rw	Name of the global section
428	Prefix	r	Prefix used in global section
429	SectionPrefix	r	Prefix string for section names

### 18.5.4 TIniCollection.Load

**Synopsis:** Loads the collection from the default filename.

**Declaration:** procedure Load

**Visibility:** public

**Description:** Load loads the collection from the file as specified in the FileName (429) property. It calls the LoadFromFile (428) method to do this.

**Errors:** If the collection was not loaded or saved to file before this call, an EIniCol exception will be raised.

**See also:** TIniCollection.LoadFromFile (428), TIniCollection.LoadFromIni (428), TIniCollection.Save (427), TIniCollection.FileName (429)

### 18.5.5 TIniCollection.Save

Synopsis: Save the collection to the default filename.

Declaration: `procedure Save`

Visibility: `public`

Description: `Save` writes the collection to the file as specified in the `FileName` (429) property, using `GlobalSection` (429) as the section. It calls the `SaveToFile` (427) method to do this.

Errors: If the collection was not loaded or saved to file before this call, an `EIniCol` exception will be raised.

See also: `TIniCollection.SaveToFile` (427), `TIniCollection.SaveToIni` (427), `TIniCollection.Load` (426), `TIniCollection.FileName` (429)

### 18.5.6 TIniCollection.SaveToIni

Synopsis: Save the collection to a `TCustomIniFile` descendent

Declaration: `procedure SaveToIni(Ini: TCustomInifile; Section: String); Virtual`

Visibility: `public`

Description: `SaveToIni` does the actual writing. It writes the number of elements in the global section (as specified by the `Section` argument), as well as the section name for each item in the list. The item names are written using the `Prefix` (428) property for the key. After this it calls the `SaveToIni` (430) method of all `TIniCollectionItem` (429) instances.

This means that the global section of the .ini file will look something like this:

```
[globalsection]
Count=3
Prefix1=SectionPrefixFirstItemName
Prefix2=SectionPrefixSecondItemName
Prefix3=SectionPrefixThirdItemName
```

This construct allows to re-use an ini file for multiple collections.

After this method is called, the `GlobalSection` (429) property contains the value of `Section`, it will be used in the `Save` (429) method.

See also: `TIniCollectionItem.SaveToIni` (430)

### 18.5.7 TIniCollection.SaveToFile

Synopsis: Save collection to a file in .ini file format

Declaration: `procedure SaveToFile(AFileName: String; Section: String)`

Visibility: `public`

Description: `SaveToFile` will create a `TMemIniFile` instance with the `AFileName` argument as a filename. This instance is passed on to the `SaveToIni` (427) method, together with the `Section` argument, to do the actual saving.

Errors: An exception may be raised if the path in `AFileName` does not exist.

See also: `TIniCollection.SaveToIni` (427), `TIniCollection.LoadFromFile` (428)

### 18.5.8 TIniCollection.LoadFromIni

Synopsis: Load collection from a file in .ini file format.

Declaration: `procedure LoadFromIni (Ini: TCustomInifile; Section: String); Virtual`

Visibility: public

Description: `LoadFromIni` will load the collection from the `Ini` instance. It first clears the collection, and reads the number of items from the global section with the name as passed through the `Section` argument. After this, an item is created and added to the collection, and its data is read by calling the `TIniCollectionItem.LoadFromIni` (430) method, passing the appropriate section name as found in the global section.

The description of the global section can be found in the `TIniCollection.SaveToIni` (427) method description.

See also: `TIniCollection.LoadFromFile` (428), `TIniCollectionItem.LoadFromIni` (430), `TIniCollection.SaveToIni` (427)

### 18.5.9 TIniCollection.LoadFromFile

Synopsis: Load collection from file.

Declaration: `procedure LoadFromFile (AFileName: String; Section: String)`

Visibility: public

Description: `LoadFromFile` creates a `TMemIniFile` instance using `AFileName` as the filename. It calls `LoadFromIni` (428) using this instance and `Section` as the parameters.

See also: `TIniCollection.LoadFromIni` (428), `TIniCollection.Load` (426), `TIniCollection.SaveToIni` (427), `TIniCollection.SaveToFile` (427)

### 18.5.10 TIniCollection.Prefix

Synopsis: Prefix used in global section

Declaration: `Property Prefix : String`

Visibility: public

Access: Read

Description: `Prefix` is used when writing the section names of the items in the collection to the global section, or when reading the names from the global section. If the prefix is set to `Item` then the global section might look something like this:

```
[MyCollection]
Count=2
Item1=FirstItem
Item2=SecondItem
```

A descendent of `TIniCollection` should set the value of this property, it cannot be empty.

See also: `TIniCollection.SectionPrefix` (429), `TIniCollection.GlobalSection` (429)

### 18.5.11 TIniCollection.SectionPrefix

Synopsis: Prefix string for section names

Declaration: `Property SectionPrefix : String`

Visibility: public

Access: Read

Description: `SectionPrefix` is a string that is prepended to the section name as returned by the `TIniCollectionItem.SectionName` (431) property to return the exact section name. It can be empty.

See also: `TIniCollection.Section` (426), `TIniCollection.GlobalSection` (429)

### 18.5.12 TIniCollection.FileName

Synopsis: Filename of the collection

Declaration: `Property FileName : String`

Visibility: public

Access: Read,Write

Description: `FileName` is the filename as used in the last `LoadFromFile` (428) or `SaveToFile` (427) operation. It is used in the `Load` (426) or `Save` (427) calls.

See also: `TIniCollection.Save` (427), `TIniCollection.LoadFromFile` (428), `TIniCollection.SaveToFile` (427), `TIniCollection.Load` (426)

### 18.5.13 TIniCollection.GlobalSection

Synopsis: Name of the global section

Declaration: `Property GlobalSection : String`

Visibility: public

Access: Read,Write

Description: `GlobalSection` contains the value of the `Section` argument in the `LoadFromIni` (428) or `SaveToIni` (427) calls. It's used in the `Load` (426) or `Save` (427) calls.

See also: `TIniCollection.Save` (427), `TIniCollection.LoadFromFile` (428), `TIniCollection.SaveToFile` (427), `TIniCollection.Load` (426)

## 18.6 TIniCollectionItem

### 18.6.1 Description

`TIniCollectionItem` is a `#rtl.classes.tcollectionitem` (??) descendent which has some extra methods for saving/loading the item to or from an .ini file.

To use this class, a descendent should be made, and the `SaveToIni` (430) and `LoadFromIni` (430) methods should be overridden. They should implement the actual loading and saving. The loading and saving is always initiated by the methods in `TIniCollection` (426), `TIniCollection.LoadFromIni` (428) and `TIniCollection.SaveToIni` (427) respectively.

### 18.6.2 Method overview

Page	Property	Description
<a href="#">431</a>	LoadFromFile	Load item from a file
<a href="#">430</a>	LoadFromIni	Method called when the item must be loaded
<a href="#">430</a>	SaveToFile	Save item to a file
<a href="#">430</a>	SaveToIni	Method called when the item must be saved

### 18.6.3 Property overview

Page	Property	Access	Description
<a href="#">431</a>	SectionName	rw	Default section name

### 18.6.4 TIniCollectionItem.SaveToIni

Synopsis: Method called when the item must be saved

Declaration: `procedure SaveToIni (Ini: TCustomIniFile; Section: String); Virtual  
; Abstract`

Visibility: public

Description: `SaveToIni` is called by `TIniCollection.SaveToIni` ([427](#)) when it saves this item. Descendent classes should override this method to save the data they need to save. All write methods of the `TCustomIniFile` instance passed in `Ini` can be used, as long as the writing happens in the section passed in `Section`.

Errors: No checking is done to see whether the values are actually written to the correct section.

See also: `TIniCollection.SaveToIni` ([427](#)), `TIniCollectionItem.LoadFromIni` ([430](#)), `TIniCollectionItem.SaveToFile` ([430](#)), `TIniCollectionItem.LoadFromFile` ([431](#))

### 18.6.5 TIniCollectionItem.LoadFromIni

Synopsis: Method called when the item must be loaded

Declaration: `procedure LoadFromIni (Ini: TCustomIniFile; Section: String); Virtual  
; Abstract`

Visibility: public

Description: `LoadFromIni` is called by `TIniCollection.LoadFromIni` ([428](#)) when it saves this item. Descendent classes should override this method to load the data they need to load. All read methods of the `TCustomIniFile` instance passed in `Ini` can be used, as long as the reading happens in the section passed in `Section`.

Errors: No checking is done to see whether the values are actually read from the correct section.

See also: `TIniCollection.LoadFromIni` ([428](#)), `TIniCollectionItem.SaveToIni` ([430](#)), `TIniCollectionItem.LoadFromFile` ([431](#)), `TIniCollectionItem.SaveToFile` ([430](#))

### 18.6.6 TIniCollectionItem.SaveToFile

Synopsis: Save item to a file

Declaration: `procedure SaveToFile (FileName: String; Section: String)`



Visibility: public

Description: `SaveToFile` creates an instance of `TIniFile` with the indicated `FileName` calls `SaveToIni` (430) to save the item to the indicated file in .ini format under the section `Section`

Errors: An exception can occur if the file is not writeable.

See also: `TIniCollectionItem.SaveToIni` (430), `TIniCollectionItem.LoadFromFile` (431)

### 18.6.7 TIniCollectionItem.LoadFromFile

Synopsis: Load item from a file

Declaration: `procedure LoadFromFile(FileName: String;Section: String)`

Visibility: public

Description: `LoadFromFile` creates an instance of `TMemIniFile` and calls `LoadFromIni` (430) to load the item from the indicated file in .ini format from the section `Section`.

Errors: None.

See also: `TIniCollectionItem.SaveToFile` (430), `TIniCollectionItem.LoadFromIni` (430)

### 18.6.8 TIniCollectionItem.SectionName

Synopsis: Default section name

Declaration: `Property SectionName : String`

Visibility: public

Access: Read,Write

Description: `SectionName` is the section name under which the item will be saved or from which it should be read. The read/write functions should be overridden in descendents to determine a unique section name within the .ini file.

See also: `TIniCollectionItem.SaveToFile` (430), `TIniCollectionItem.LoadFromIni` (430)

## 18.7 TNamedIniCollection

### 18.7.1 Description

`TNamedIniCollection` is the collection to go with the `TNamedIniCollectionItem` (433) item class. it provides some functions to look for items based on the `UserData` (432) or based on the `Name` (432).

### 18.7.2 Method overview

Page	Property	Description
432	<code>FindByName</code>	Return the item based on its name
433	<code>FindByUserData</code>	Return the item based on its <code>UserData</code>
432	<code>IndexOfName</code>	Search for an item, based on its name, and return its position
432	<code>IndexOfUserData</code>	Search for an item based on it's <code>UserData</code> property

### 18.7.3 Property overview

Page	Property	Access	Description
<a href="#">433</a>	NamedItems	rw	Indexed access to the <code>TNamedIniCollectionItem</code> items

### 18.7.4 `TNamedIniCollection.IndexOfUserData`

Synopsis: Search for an item based on it's `UserData` property

Declaration: `function IndexOfUserData(UserData: TObject) : Integer`

Visibility: `public`

Description: `IndexOfUserData` searches the list of items and returns the index of the item which has `UserData` in its `UserData` ([432](#)) property. If no such item exists, -1 is returned.

Note that the (linear) search starts at the last element and works it's way back to the first.

Errors: If no item exists, -1 is returned.

See also: `TNamedIniCollection.IndexOfName` ([432](#)), `TNamedIniCollectionItem.UserData` ([433](#))

### 18.7.5 `TNamedIniCollection.IndexOfName`

Synopsis: Search for an item, based on its name, and return its position

Declaration: `function IndexOfName(const AName: String) : Integer`

Visibility: `public`

Description: `IndexOfName` searches the list of items and returns the index of the item which has name equal to `AName` (case insensitive). If no such item exists, -1 is returned.

Note that the (linear) search starts at the last element and works it's way back to the first.

Errors: If no item exists, -1 is returned.

See also: `TNamedIniCollection.IndexOfUserData` ([432](#)), `TNamedIniCollectionItem.Name` ([434](#))

### 18.7.6 `TNamedIniCollection.FindByName`

Synopsis: Return the item based on its name

Declaration: `function FindByName(const AName: String) : TNamedIniCollectionItem`

Visibility: `public`

Description: `FindByName` returns the collection item whose name matches `AName` (case insensitive match). It calls `IndexOfName` ([432](#)) and returns the item at the found position. If no item is found, `Nil` is returned.

Errors: If no item is found, `Nil` is returned.

See also: `TNamedIniCollection.IndexOfName` ([432](#)), `TNamedIniCollection.FindByUserData` ([433](#))

### 18.7.7 TNamedIniCollection.FindByUserData

Synopsis: Return the item based on its `UserData`

Declaration: `function FindByUserData(UserData: TObject) : TNamedIniCollectionItem`

Visibility: `public`

Description: `FindByName` returns the collection item whose `UserData` (433) property value matches the `UserData` parameter. If no item is found, `Nil` is returned.

Errors: If no item is found, `Nil` is returned.

### 18.7.8 TNamedIniCollection.NamedItems

Synopsis: Indexed access to the `TNamedIniCollectionItem` items

Declaration: `Property NamedItems[Index: Integer]: TNamedIniCollectionItem; default`

Visibility: `public`

Access: `Read,Write`

Description: `NamedItem` is the default property of the `TNamedIniCollection` collection. It allows indexed access to the `TNamedIniCollectionItem` (433) items. The index is zero based.

See also: `TNamedIniCollectionItem` (433)

## 18.8 TNamedIniCollectionItem

### 18.8.1 Description

`TNamedIniCollectionItem` is a `TIniCollectionItem` (429) descent with a published name property. The name is used as the section name when saving the item to the ini file.

### 18.8.2 Property overview

Page	Property	Access	Description
434	<code>Name</code>	<code>rw</code>	Name of the item
433	<code>UserData</code>	<code>rw</code>	User-defined data

### 18.8.3 TNamedIniCollectionItem.UserData

Synopsis: User-defined data

Declaration: `Property UserData : TObject`

Visibility: `public`

Access: `Read,Write`

Description: `UserData` can be used to associate an arbitrary object with the item - much like the `Objects` property of a `TStrings`.

#### 18.8.4 TNamedIniCollectionItem.Name

Synopsis: Name of the item

Declaration: `Property Name : String`

Visibility: `published`

Access: `Read, Write`

Description: `Name` is the name of this item. It is also used as the section name when writing the collection item to the `.ini` file.

See also: `TNamedIniCollectionItem.UserData` ([433](#))

## Chapter 19

# Reference for unit 'IniFiles'

### 19.1 Used units

Table 19.1: Used units by unit 'IniFiles'

Name	Page
Classes	??
contnrs	<a href="#">98</a>
sysutils	??

### 19.2 Overview

IniFiles provides support for handling .ini files. It contains an implementation completely independent of the Windows API for handling such files. The basic (abstract) functionality is defined in TCustomIniFile ([435](#)) and is implemented in TIniFile ([447](#)) and TMemIniFile ([455](#)). The API presented by these components is Delphi compatible.

### 19.3 TCustomIniFile

#### 19.3.1 Description

TCustomIniFile implements all calls for manipulating a .ini. It does not implement any of this behaviour, the behaviour must be implemented in a descendent class like TIniFile ([447](#)) or TMemIniFile ([455](#)).

Since TCustomIniFile is an abstract class, it should never be created directly. Instead, one of the TIniFile or TMemIniFile classes should be created.

### 19.3.2 Method overview

Page	Property	Description
<a href="#">436</a>	Create	Instantiate a new instance of TCustomIniFile.
<a href="#">443</a>	DeleteKey	Delete a key from a section
<a href="#">437</a>	Destroy	Remove the TCustomIniFile instance from memory
<a href="#">443</a>	EraseSection	Clear a section
<a href="#">440</a>	ReadBinaryStream	Read binary data
<a href="#">438</a>	ReadBool	
<a href="#">439</a>	ReadDate	Read a date value
<a href="#">439</a>	ReadDateTime	Read a Date/Time value
<a href="#">440</a>	ReadFloat	Read a floating point value
<a href="#">438</a>	ReadInteger	Read an integer value from the file
<a href="#">442</a>	ReadSection	Read the key names in a section
<a href="#">443</a>	ReadSections	Read the list of sections
<a href="#">443</a>	ReadSectionValues	Read names and values of a section
<a href="#">437</a>	ReadString	Read a string valued key
<a href="#">440</a>	ReadTime	Read a time value
<a href="#">437</a>	SectionExists	Check if a section exists.
<a href="#">444</a>	UpdateFile	Update the file on disk
<a href="#">444</a>	ValueExists	Check if a value exists
<a href="#">442</a>	WriteBinaryStream	Write binary data
<a href="#">439</a>	WriteBool	Write boolean value
<a href="#">441</a>	WriteDate	Write date value
<a href="#">441</a>	WriteDateTime	Write date/time value
<a href="#">441</a>	WriteFloat	Write a floating-point value
<a href="#">438</a>	WriteInteger	Write an integer value
<a href="#">438</a>	WriteString	Write a string value
<a href="#">442</a>	WriteTime	Write time value

### 19.3.3 Property overview

Page	Property	Access	Description
<a href="#">445</a>	CaseSensitive	rw	Are key and section names case sensitive
<a href="#">445</a>	EscapeLineFeeds	r	Should linefeeds be escaped ?
<a href="#">444</a>	FileName	r	Name of the .ini file
<a href="#">445</a>	StripQuotes	rw	Should quotes be stripped from string values

### 19.3.4 TCustomIniFile.Create

Synopsis: Instantiate a new instance of TCustomIniFile.

Declaration: `constructor Create(const AFileName: String; AEscapeLineFeeds: Boolean)  
; Virtual`

Visibility: public

Description: Create creates a new instance of TCustomIniFile and loads it with the data from AFileName, if this file exists. If the AEscapeLineFeeds parameter is True, then lines which have their end-of-line markers escaped with a backslash, will be concatenated. This means that the following 2 lines

```
Description=This is a \
line with a long text
```

is equivalent to

```
Description=This is a line with a long text
```

By default, not escaping of linefeeds is performed (for Delphi compatibility)

Errors: If the file cannot be read, an exception may be raised.

See also: `TCustomIniFile.Destroy` ([437](#))

### 19.3.5 TCustomIniFile.Destroy

Synopsis: Remove the `TCustomIniFile` instance from memory

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` cleans up all internal structures and then calls the inherited `Destroy`.

See also: `TCustomIniFile` ([435](#))

### 19.3.6 TCustomIniFile.SectionExists

Synopsis: Check if a section exists.

Declaration: `function SectionExists(const Section: String) : Boolean; Virtual`

Visibility: `public`

Description: `SectionExists` returns `True` if a section with name `Section` exists, and contains keys. (comments are not considered keys)

See also: `TCustomIniFile.ValueExists` ([444](#))

### 19.3.7 TCustomIniFile.ReadString

Synopsis: Read a string valued key

Declaration: `function ReadString(const Section: String; const Ident: String;  
const Default: String) : String; Virtual; Abstract`

Visibility: `public`

Description: `ReadString` reads the key `Ident` in section `Section`, and returns the value as a string. If the specified key or section do not exist, then the value in `Default` is returned. Note that if the key exists, but is empty, an empty string will be returned.

See also: `TCustomIniFile.WriteString` ([438](#)), `TCustomIniFile.ReadInteger` ([438](#)), `TCustomIniFile.ReadBool` ([438](#)), `TCustomIniFile.ReadDate` ([439](#)), `TCustomIniFile.ReadDateTime` ([439](#)), `TCustomIniFile.ReadTime` ([440](#)), `TCustomIniFile.ReadFloat` ([440](#)), `TCustomIniFile.ReadBinaryStream` ([440](#))

### 19.3.8 TCustomIniFile.WriteString

Synopsis: Write a string value

Declaration: `procedure WriteString(const Section: String; const Ident: String;  
const Value: String); Virtual; Abstract`

Visibility: public

Description: `WriteString` writes the string `Value` with the name `Ident` to the section `Section`, overwriting any previous value that may exist there. The section will be created if it does not exist.

See also: `TCustomIniFile.ReadString` (437), `TCustomIniFile.WriteInteger` (438), `TCustomIniFile.WriteBool` (439), `TCustomIniFile.WriteDate` (441), `TCustomIniFile.WriteDateTime` (441), `TCustomIniFile.WriteTime` (442), `TCustomIniFile.WriteFloat` (441), `TCustomIniFile.WriteBinaryStream` (442)

### 19.3.9 TCustomIniFile.ReadInteger

Synopsis: Read an integer value from the file

Declaration: `function ReadInteger(const Section: String; const Ident: String;  
Default: LongInt) : LongInt; Virtual`

Visibility: public

Description: `ReadInteger` reads the key `Ident` in section `Section`, and returns the value as an integer. If the specified key or section do not exist, then the value in `Default` is returned. If the key exists, but contains an invalid integer value, `Default` is also returned.

See also: `TCustomIniFile.WriteInteger` (438), `TCustomIniFile.ReadString` (437), `TCustomIniFile.ReadBool` (438), `TCustomIniFile.ReadDate` (439), `TCustomIniFile.ReadDateTime` (439), `TCustomIniFile.ReadTime` (440), `TCustomIniFile.ReadFloat` (440), `TCustomIniFile.ReadBinaryStream` (440)

### 19.3.10 TCustomIniFile.WriteInteger

Synopsis: Write an integer value

Declaration: `procedure WriteInteger(const Section: String; const Ident: String;  
Value: LongInt); Virtual`

Visibility: public

Description: `WriteInteger` writes the integer `Value` with the name `Ident` to the section `Section`, overwriting any previous value that may exist there. The section will be created if it does not exist.

See also: `TCustomIniFile.ReadInteger` (438), `TCustomIniFile.WriteString` (438), `TCustomIniFile.WriteBool` (439), `TCustomIniFile.WriteDate` (441), `TCustomIniFile.WriteDateTime` (441), `TCustomIniFile.WriteTime` (442), `TCustomIniFile.WriteFloat` (441), `TCustomIniFile.WriteBinaryStream` (442)

### 19.3.11 TCustomIniFile.ReadBool

Synopsis:

Declaration: `function ReadBool(const Section: String; const Ident: String;  
Default: Boolean) : Boolean; Virtual`

Visibility: public



**Description:** `ReadString` reads the key `Ident` in section `Section`, and returns the value as a boolean (valid values are 0 and 1). If the specified key or section do not exist, then the value in `Default` is returned. If the key exists, but contains an invalid integer value, `False` is also returned.

**Errors:**

**See also:** `TCustomIniFile.WriteBool` (439), `TCustomIniFile.ReadInteger` (438), `TCustomIniFile.ReadString` (437), `TCustomIniFile.ReadDate` (439), `TCustomIniFile.ReadDateTime` (439), `TCustomIniFile.ReadTime` (440), `TCustomIniFile.ReadFloat` (440), `TCustomIniFile.ReadBinaryStream` (440)

### 19.3.12 TCustomIniFile.WriteBool

**Synopsis:** Write boolean value

**Declaration:** `procedure WriteBool(const Section: String; const Ident: String; Value: Boolean); Virtual`

**Visibility:** public

**Description:** `WriteBool` writes the boolean `Value` with the name `Ident` to the section `Section`, overwriting any previous value that may exist there. The section will be created if it does not exist.

**See also:** `TCustomIniFile.ReadBool` (438), `TCustomIniFile.WriteInteger` (438), `TCustomIniFile.WriteString` (438), `TCustomIniFile.WriteDate` (441), `TCustomIniFile.WriteDateTime` (441), `TCustomIniFile.WriteTime` (442), `TCustomIniFile.WriteFloat` (441), `TCustomIniFile.WriteBinaryStream` (442)

### 19.3.13 TCustomIniFile.ReadDate

**Synopsis:** Read a date value

**Declaration:** `function ReadDate(const Section: String; const Ident: String; Default: TDateTime) : TDateTime; Virtual`

**Visibility:** public

**Description:** `ReadDate` reads the key `Ident` in section `Section`, and returns the value as a date (`TDateTime`). If the specified key or section do not exist, then the value in `Default` is returned. If the key exists, but contains an invalid date value, `Default` is also returned. The international settings of the `SysUtils` are taken into account when deciding if the read value is a correct date.

**Errors:**

**See also:** `TCustomIniFile.WriteDate` (441), `TCustomIniFile.ReadInteger` (438), `TCustomIniFile.ReadBool` (438), `TCustomIniFile.ReadString` (437), `TCustomIniFile.ReadDateTime` (439), `TCustomIniFile.ReadTime` (440), `TCustomIniFile.ReadFloat` (440), `TCustomIniFile.ReadBinaryStream` (440)

### 19.3.14 TCustomIniFile.ReadDateTime

**Synopsis:** Read a Date/Time value

**Declaration:** `function ReadDateTime(const Section: String; const Ident: String; Default: TDateTime) : TDateTime; Virtual`

**Visibility:** public

**Description:** `ReadDateTime` reads the key `Ident` in section `Section`, and returns the value as a date/time (`TDateTime`). If the specified key or section do not exist, then the value in `Default` is returned. If the key exists, but contains an invalid date/time value, `Default` is also returned. The international settings of the `SysUtils` are taken into account when deciding if the read value is a correct date/time.

**See also:** `TCustomIniFile.WriteDateTime` (441), `TCustomIniFile.ReadInteger` (438), `TCustomIniFile.ReadBool` (438), `TCustomIniFile.ReadDate` (439), `TCustomIniFile.ReadString` (437), `TCustomIniFile.ReadTime` (440), `TCustomIniFile.ReadFloat` (440), `TCustomIniFile.ReadBinaryStream` (440)

### 19.3.15 TCustomIniFile.ReadFloat

**Synopsis:** Read a floating point value

**Declaration:** `function ReadFloat(const Section: String;const Ident: String;  
Default: Double) : Double; Virtual`

**Visibility:** public

**Description:** `ReadFloat` reads the key `Ident` in section `Section`, and returns the value as a float (`Double`). If the specified key or section do not exist, then the value in `Default` is returned. If the key exists, but contains an invalid float value, `Default` is also returned. The international settings of the `SysUtils` are taken into account when deciding if the read value is a correct float.

**See also:** `TCustomIniFile.WriteFloat` (441), `TCustomIniFile.ReadInteger` (438), `TCustomIniFile.ReadBool` (438), `TCustomIniFile.ReadDate` (439), `TCustomIniFile.ReadDateTime` (439), `TCustomIniFile.ReadTime` (440), `TCustomIniFile.ReadString` (437), `TCustomIniFile.ReadBinaryStream` (440)

### 19.3.16 TCustomIniFile.ReadTime

**Synopsis:** Read a time value

**Declaration:** `function ReadTime(const Section: String;const Ident: String;  
Default: TDateTime) : TDateTime; Virtual`

**Visibility:** public

**Description:** `ReadTime` reads the key `Ident` in section `Section`, and returns the value as a time (`TDateTime`). If the specified key or section do not exist, then the value in `Default` is returned. If the key exists, but contains an invalid time value, `Default` is also returned. The international settings of the `SysUtils` are taken into account when deciding if the read value is a correct time.

**Errors:**

**See also:** `TCustomIniFile.WriteTime` (442), `TCustomIniFile.ReadInteger` (438), `TCustomIniFile.ReadBool` (438), `TCustomIniFile.ReadDate` (439), `TCustomIniFile.ReadDateTime` (439), `TCustomIniFile.ReadString` (437), `TCustomIniFile.ReadFloat` (440), `TCustomIniFile.ReadBinaryStream` (440)

### 19.3.17 TCustomIniFile.ReadBinaryStream

**Synopsis:** Read binary data

**Declaration:** `function ReadBinaryStream(const Section: String;const Name: String;  
Value: TStream) : Integer; Virtual`

**Visibility:** public

**Description:** `ReadBinaryStream` reads the key `Name` in section `Section`, and returns the value in the stream `Value`. If the specified key or section do not exist, then the contents of `Value` are left untouched. The stream is not cleared prior to adding data to it.

The data is interpreted as a series of 2-byte hexadecimal values, each representing a byte in the data stream, i.e, it should always be an even number of hexadecimal characters.

See also: `TCustomIniFile.WriteBinaryStream` (442), `TCustomIniFile.ReadInteger` (438), `TCustomIniFile.ReadBool` (438), `TCustomIniFile.ReadDate` (439), `TCustomIniFile.ReadDateTime` (439), `TCustomIniFile.ReadTime` (440), `TCustomIniFile.ReadFloat` (440), `TCustomIniFile.ReadString` (437)

### 19.3.18 TCustomIniFile.WriteDate

**Synopsis:** Write date value

**Declaration:** `procedure WriteDate(const Section: String;const Ident: String;  
Value: TDateTime); Virtual`

**Visibility:** public

**Description:** `WriteDate` writes the date `Value` with the name `Ident` to the section `Section`, overwriting any previous value that may exist there. The section will be created if it does not exist. The date is written using the internationalization settings in the `SysUtils` unit.

**Errors:**

See also: `TCustomIniFile.ReadDate` (439), `TCustomIniFile.WriteInteger` (438), `TCustomIniFile.WriteBool` (439), `TCustomIniFile.WriteString` (438), `TCustomIniFile.WriteDateTime` (441), `TCustomIniFile.WriteTime` (442), `TCustomIniFile.WriteFloat` (441), `TCustomIniFile.WriteBinaryStream` (442)

### 19.3.19 TCustomIniFile.WriteDateTime

**Synopsis:** Write date/time value

**Declaration:** `procedure WriteDateTime(const Section: String;const Ident: String;  
Value: TDateTime); Virtual`

**Visibility:** public

**Description:** `WriteDateTime` writes the date/time `Value` with the name `Ident` to the section `Section`, overwriting any previous value that may exist there. The section will be created if it does not exist. The date/time is written using the internationalization settings in the `SysUtils` unit.

See also: `TCustomIniFile.ReadDateTime` (439), `TCustomIniFile.WriteInteger` (438), `TCustomIniFile.WriteBool` (439), `TCustomIniFile.WriteDate` (441), `TCustomIniFile.WriteString` (438), `TCustomIniFile.WriteTime` (442), `TCustomIniFile.WriteFloat` (441), `TCustomIniFile.WriteBinaryStream` (442)

### 19.3.20 TCustomIniFile.WriteFloat

**Synopsis:** Write a floating-point value

**Declaration:** `procedure WriteFloat(const Section: String;const Ident: String;  
Value: Double); Virtual`

**Visibility:** public

**Description:** `WriteFloat` writes the time `Value` with the name `Ident` to the section `Section`, overwriting any previous value that may exist there. The section will be created if it does not exist. The floating point value is written using the internationalization settings in the `SysUtils` unit.

See also: `TCustomIniFile.ReadFloat` (440), `TCustomIniFile.WriteInteger` (438), `TCustomIniFile.WriteBool` (439), `TCustomIniFile.WriteDate` (441), `TCustomIniFile.WriteDateTime` (441), `TCustomIniFile.WriteTime` (442), `TCustomIniFile.WriteString` (438), `TCustomIniFile.WriteBinaryStream` (442)

### 19.3.21 TCustomIniFile.WriteTime

**Synopsis:** Write time value

**Declaration:** `procedure WriteTime(const Section: String;const Ident: String;  
Value: TDateTime); Virtual`

**Visibility:** public

**Description:** `WriteTime` writes the time `Value` with the name `Ident` to the section `Section`, overwriting any previous value that may exist there. The section will be created if it does not exist. The time is written using the internationalization settings in the `SysUtils` unit.

See also: `TCustomIniFile.ReadTime` (440), `TCustomIniFile.WriteInteger` (438), `TCustomIniFile.WriteBool` (439), `TCustomIniFile.WriteDate` (441), `TCustomIniFile.WriteDateTime` (441), `TCustomIniFile.WriteString` (438), `TCustomIniFile.WriteFloat` (441), `TCustomIniFile.WriteBinaryStream` (442)

### 19.3.22 TCustomIniFile.WriteBinaryStream

**Synopsis:** Write binary data

**Declaration:** `procedure WriteBinaryStream(const Section: String;const Name: String;  
Value: TStream); Virtual`

**Visibility:** public

**Description:** `WriteBinaryStream` writes the binary data in `Value` with the name `Ident` to the section `Section`, overwriting any previous value that may exist there. The section will be created if it does not exist.

The binary data is encoded using a 2-byte hexadecimal value per byte in the data stream. The data stream must be seekable, so it's size can be determined. The data stream is not repositioned, it must be at the correct position.

See also: `TCustomIniFile.ReadBinaryStream` (440), `TCustomIniFile.WriteInteger` (438), `TCustomIniFile.WriteBool` (439), `TCustomIniFile.WriteDate` (441), `TCustomIniFile.WriteDateTime` (441), `TCustomIniFile.WriteTime` (442), `TCustomIniFile.WriteFloat` (441), `TCustomIniFile.WriteString` (438)

### 19.3.23 TCustomIniFile.ReadSection

**Synopsis:** Read the key names in a section

**Declaration:** `procedure ReadSection(const Section: String;Strings: TStrings); Virtual  
; Abstract`

**Visibility:** public

**Description:** `ReadSection` will return the names of the keys in section `Section` in `Strings`, one string per key. If a non-existing section is specified, the list is cleared. To return the values of the keys as well, the `ReadSectionValues` (443) method should be used.

See also: `TCustomIniFile.ReadSections` (443), `TCustomIniFile.SectionExists` (437), `TCustomIniFile.ReadSectionValues` (443)

### 19.3.24 TCustomIniFile.ReadSections

Synopsis: Read the list of sections

Declaration: `procedure ReadSections(Strings: TStrings); Virtual; Abstract`

Visibility: public

Description: `ReadSections` returns the names of existing sections in `Strings`. It also returns names of empty sections.

See also: `TCustomIniFile.SectionExists` (437), `TCustomIniFile.ReadSectionValues` (443), `TCustomIniFile.ReadSection` (442)

### 19.3.25 TCustomIniFile.ReadSectionValues

Synopsis: Read names and values of a section

Declaration: `procedure ReadSectionValues(const Section: String; Strings: TStrings)  
; Virtual; Abstract`

Visibility: public

Description: `ReadSectionValues` returns the keys and their values in the section `Section` in `Strings`. They are returned as `Key=Value` strings, one per key, so the `Values` property of the stringlist can be used to read the values. To retrieve just the names of the available keys, `ReadSection` (442) can be used.

See also: `TCustomIniFile.SectionExists` (437), `TCustomIniFile.ReadSections` (443), `TCustomIniFile.ReadSection` (442)

### 19.3.26 TCustomIniFile.EraseSection

Synopsis: Clear a section

Declaration: `procedure EraseSection(const Section: String); Virtual; Abstract`

Visibility: public

Description: `EraseSection` deletes all values from the section named `Section` and removes the section from the ini file. If the section didn't exist prior to a call to `EraseSection`, nothing happens.

See also: `TCustomIniFile.SectionExists` (437), `TCustomIniFile.ReadSections` (443), `TCustomIniFile.DeleteKey` (443)

### 19.3.27 TCustomIniFile.DeleteKey

Synopsis: Delete a key from a section

Declaration: `procedure DeleteKey(const Section: String; const Ident: String); Virtual  
; Abstract`

Visibility: public

**Description:** `DeleteKey` deletes the key `Ident` from section `Section`. If the key or section didn't exist prior to the `DeleteKey` call, nothing happens.

See also: `TCustomIniFile.EraseSection` ([443](#))

### 19.3.28 TCustomIniFile.UpdateFile

**Synopsis:** Update the file on disk

**Declaration:** `procedure UpdateFile; Virtual; Abstract`

**Visibility:** `public`

**Description:** `UpdateFile` writes the in-memory image of the ini-file to disk. To speed up operation of the inifile class, the whole ini-file is read into memory when the class is created, and all operations are performed in-memory. If `CacheUpdates` is set to `True`, any changes to the inifile are only in memory, until they are committed to disk with a call to `UpdateFile`. If `CacheUpdates` is set to `False`, then all operations which cause a change in the .ini file will immediately be committed to disk with a call to `UpdateFile`. Since the whole file is written to disk, this may have serious impact on performance.

See also: `TIniFile.CacheUpdates` ([450](#))

### 19.3.29 TCustomIniFile.ValueExists

**Synopsis:** Check if a value exists

**Declaration:** `function ValueExists(const Section: String;const Ident: String)  
: Boolean; Virtual`

**Visibility:** `public`

**Description:** `ValueExists` checks whether the key `Ident` exists in section `Section`. It returns `True` if a key was found, or `False` if not. The key may be empty.

See also: `TCustomIniFile.SectionExists` ([437](#))

### 19.3.30 TCustomIniFile.FileName

**Synopsis:** Name of the .ini file

**Declaration:** `Property FileName : String`

**Visibility:** `public`

**Access:** `Read`

**Description:** `FileName` is the name of the ini file on disk. It should be specified when the `TCustomIniFile` instance is created. Contrary to the Delphi implementation, if no path component is present in the filename, the filename is not searched in the windows directory.

See also: `TCustomIniFile.Create` ([436](#))

### 19.3.31 TCustomIniFile.EscapeLineFeeds

Synopsis: Should linefeeds be escaped ?

Declaration: Property EscapeLineFeeds : Boolean

Visibility: public

Access: Read

Description: EscapeLineFeeds determines whether escaping of linefeeds is enabled: For a description of this feature, see Create (436), as the value of this property must be specified when the TCustomIniFile instance is created.

By default, EscapeLineFeeds is False.

See also: TCustomIniFile.Create (436), TCustomIniFile.CaseSensitive (445)

### 19.3.32 TCustomIniFile.CaseSensitive

Synopsis: Are key and section names case sensitive

Declaration: Property CaseSensitive : Boolean

Visibility: public

Access: Read,Write

Description: CaseSensitive determines whether searches for sections and keys are performed case-sensitive or not. By default, they are not case sensitive.

See also: TCustomIniFile.EscapeLineFeeds (445)

### 19.3.33 TCustomIniFile.StripQuotes

Synopsis: Should quotes be stripped from string values

Declaration: Property StripQuotes : Boolean

Visibility: public

Access: Read,Write

Description: StripQuotes determines whether quotes around string values are stripped from the value when reading the values from file. By default, quotes are not stripped (this is Delphi and Windows compatible).

## 19.4 THashedStringList

### 19.4.1 Description

THashedStringList is a TStringList (??) descendent which creates has values for the strings and names (in the case of a name-value pair) stored in it. The IndexOf (446) and IndexOfName (446) functions make use of these hash values to quicklier locate a value.

### 19.4.2 Method overview

Page	Property	Description
<a href="#">446</a>	Create	Instantiates a new instance of THashedStringList
<a href="#">446</a>	Destroy	Clean up instance
<a href="#">446</a>	IndexOf	Returns the index of a string in the list of strings
<a href="#">446</a>	IndexOfName	Return the index of a name in the list of name=value pairs

### 19.4.3 THashedStringList.Create

Synopsis: Instantiates a new instance of THashedStringList

Declaration: `constructor Create`

Visibility: `public`

Description: `Create` calls the inherited `Create`, and then instantiates the hash tables.

Errors: If no enough memory is available, an exception may be raised.

See also: THashedStringList.Destroy ([446](#))

### 19.4.4 THashedStringList.Destroy

Synopsis: Clean up instance

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` cleans up the hash tables and then calls the inherited `Destroy`.

See also: THashedStringList.Create ([446](#))

### 19.4.5 THashedStringList.IndexOf

Synopsis: Returns the index of a string in the list of strings

Declaration: `function IndexOf(const S: String) : Integer; Override`

Visibility: `public`

Description: `IndexOf` overrides the TStringList.IndexOf ([435](#)) method and uses the hash values to look for the location of S.

See also: TStringList.IndexOf ([435](#)), THashedStringList.IndexOfName ([446](#))

### 19.4.6 THashedStringList.IndexOfName

Synopsis: Return the index of a name in the list of name=value pairs

Declaration: `function IndexOfName(const Name: String) : Integer; Override`

Visibility: `public`

Description: `IndexOfName` overrides the TStringList.IndexOfName ([435](#)) method and uses the hash values of the names to look for the location of Name.

See also: TStringList.IndexOfName ([435](#)), THashedStringList.IndexOf ([446](#))



## 19.5 TIniFile

### 19.5.1 Description

`TIniFile` is an implementation of `TCustomIniFile` (435) which does the same as `TMemIniFile` (455), namely it reads the whole file into memory. Unlike `TMemIniFile` it does not cache updates in memory, but immediately writes any changes to disk.

`TIniFile` introduces no new methods, it just implements the abstract methods introduced in `TCustomIniFile`

### 19.5.2 Method overview

Page	Property	Description
447	Create	Create a new instance of <code>TIniFile</code>
449	DeleteKey	Delete key
447	Destroy	Remove the <code>TIniFile</code> instance from memory
449	EraseSection	
448	ReadSection	Read the key names in a section
448	ReadSectionRaw	Read raw section
449	ReadSections	Read section names
449	ReadSectionValues	
448	ReadString	Read a string
450	UpdateFile	Update the file on disk
448	WriteString	Write string to file

### 19.5.3 Property overview

Page	Property	Access	Description
450	CacheUpdates	rw	Should changes be kept in memory
450	Stream	r	Stream from which ini file was read

### 19.5.4 TIniFile.Create

Synopsis: Create a new instance of `TIniFile`

Declaration: `constructor Create(const AFileName: String; AEscapeLineFeeds: Boolean)`  
                   `; Override`  
                   `constructor Create(AStream: TStream; AEscapeLineFeeds: Boolean)`

Visibility: public

Description: `Create` creates a new instance of `TIniFile` and initializes the class by reading the file from disk if the filename `AFileName` is specified, or from stream in case `AStream` is specified. It also sets most variables to their initial values, i.e. `AEscapeLineFeeds` is saved prior to reading the file, and `Cacheupdates` is set to `False`.

See also: `TCustomIniFile` (435), `TMemIniFile` (455)

### 19.5.5 TIniFile.Destroy

Synopsis: Remove the `TIniFile` instance from memory

Declaration: `destructor Destroy; Override`

Visibility: public

**Description:** `Destroy` writes any pending changes to disk, and cleans up the `TIniFile` structures, and then calls the inherited `Destroy`, effectively removing the instance from memory.

**Errors:** If an error happens when the file is written to disk, an exception will be raised.

**See also:** `TCustomIniFile.UpdateFile` ([444](#)), `TIniFile.CacheUpdates` ([450](#))

### 19.5.6 TIniFile.ReadString

**Synopsis:** Read a string

**Declaration:** `function ReadString(const Section: String;const Ident: String;  
const Default: String) : String; Override`

**Visibility:** public

**Description:** `ReadString` implements the `TCustomIniFile.ReadString` ([437](#)) abstract method by looking at the in-memory copy of the ini file and returning the string found there.

**See also:** `TCustomIniFile.ReadString` ([437](#))

### 19.5.7 TIniFile.WriteString

**Synopsis:** Write string to file

**Declaration:** `procedure WriteString(const Section: String;const Ident: String;  
const Value: String); Override`

**Visibility:** public

**Description:** `WriteString` implements the `TCustomIniFile.WriteString` ([438](#)) abstract method by writing the string to the in-memory copy of the ini file. If `CacheUpdates` ([450](#)) property is `False`, then the whole file is immediately written to disk as well.

**Errors:** If an error happens when the file is written to disk, an exception will be raised.

### 19.5.8 TIniFile.ReadSection

**Synopsis:** Read the key names in a section

**Declaration:** `procedure ReadSection(const Section: String;Strings: TStrings)  
; Override`

**Visibility:** public

**Description:** `ReadSection` reads the key names from `Section` into `Strings`, taking the in-memory copy of the ini file. This is the implementation for the abstract `TCustomIniFile.ReadSection` ([442](#))

**See also:** `TCustomIniFile.ReadSection` ([442](#)), `TIniFile.ReadSectionRaw` ([448](#))

### 19.5.9 TIniFile.ReadSectionRaw

**Synopsis:** Read raw section

**Declaration:** `procedure ReadSectionRaw(const Section: String;Strings: TStrings)`

**Visibility:** public

**Description:** `ReadSectionRaw` returns the contents of the section `Section` as it is: this includes the comments in the section. (these are also stored in memory)

See also: `TIniFile.ReadSection` (448), `TCustomIniFile.ReadSection` (442)

### 19.5.10 TIniFile.ReadSections

**Synopsis:** Read section names

**Declaration:** `procedure ReadSections(Strings: TStrings); Override`

**Visibility:** public

**Description:** `ReadSections` is the implementation of `TCustomIniFile.ReadSections` (443). It operates on the in-memory copy of the inifile, and places all section names in `Strings`.

See also: `TIniFile.ReadSection` (448), `TCustomIniFile.ReadSections` (443), `TIniFile.ReadSectionValues` (449)

### 19.5.11 TIniFile.ReadSectionValues

**Synopsis:**

**Declaration:** `procedure ReadSectionValues(const Section: String; Strings: TStrings)  
; Override`

**Visibility:** public

**Description:** `ReadSectionValues` is the implementation of `TCustomIniFile.ReadSectionValues` (443). It operates on the in-memory copy of the inifile, and places all key names from `Section` together with their values in `Strings`.

See also: `TIniFile.ReadSection` (448), `TCustomIniFile.ReadSectionValues` (443), `TIniFile.ReadSections` (449)

### 19.5.12 TIniFile.EraseSection

**Synopsis:**

**Declaration:** `procedure EraseSection(const Section: String); Override`

**Visibility:** public

**Description:** `EraseSection` deletes the section `Section` from memory, if `CacheUpdates` (450) is `False`, then the file is immediatly updated on disk. This method is the implementation of the abstract `TCustomIniFile.EraseSection` (443) method.

See also: `TCustomIniFile.EraseSection` (443), `TIniFile.ReadSection` (448), `TIniFile.ReadSections` (449)

### 19.5.13 TIniFile.DeleteKey

**Synopsis:** Delete key

**Declaration:** `procedure DeleteKey(const Section: String; const Ident: String)  
; Override`

**Visibility:** public

**Description:** `DeleteKey` deletes the `Ident` from the section `Section`. This operation is performed on the in-memory copy of the ini file. if `CacheUpdates` (450) is `False`, then the file is immediately updated on disk.

See also: `TIniFile.CacheUpdates` (450)

### 19.5.14 `TIniFile.UpdateFile`

**Synopsis:** Update the file on disk

**Declaration:** `procedure UpdateFile; Override`

**Visibility:** `public`

**Description:** `UpdateFile` writes the in-memory data for the ini file to disk. The whole file is written. If the ini file was instantiated from a stream, then the stream is updated. Note that the stream must be seekable for this to work correctly. The ini file is marked as 'clean' after a call to `UpdateFile` (i.e. not in need of writing to disk).

**Errors:** If an error occurs when writing to stream or disk, an exception may be raised.

See also: `TIniFile.CacheUpdates` (450)

### 19.5.15 `TIniFile.Stream`

**Synopsis:** Stream from which ini file was read

**Declaration:** `Property Stream : TStream`

**Visibility:** `public`

**Access:** `Read`

**Description:** `Stream` is the stream which was used to create the `IniFile`. The `UpdateFile` (450) method will use this stream to write changes to.

See also: `TIniFile.Create` (447), `TIniFile.UpdateFile` (450)

### 19.5.16 `TIniFile.CacheUpdates`

**Synopsis:** Should changes be kept in memory

**Declaration:** `Property CacheUpdates : Boolean`

**Visibility:** `public`

**Access:** `Read, Write`

**Description:** `CacheUpdates` determines how to deal with changes to the ini-file data: if set to `True` then changes are kept in memory till the file is written to disk with a call to `UpdateFile` (450). If it is set to `False` then each call that changes the data of the ini-file will result in a call to `UpdateFile`. This is the default behaviour, but it may adversely affect performance.

See also: `TIniFile.UpdateFile` (450)

## 19.6 TIniFileKey

### 19.6.1 Description

TIniFileKey is used to keep the key/value pairs in the ini file in memory. It is an internal structure, used internally by the TIniFile (447) class.

### 19.6.2 Method overview

Page	Property	Description
<a href="#">451</a>	Create	Create a new instance of TIniFileKey

### 19.6.3 Property overview

Page	Property	Access	Description
<a href="#">451</a>	Ident	rw	Key name
<a href="#">451</a>	Value	rw	Key value

### 19.6.4 TIniFileKey.Create

Synopsis: Create a new instance of TIniFileKey

Declaration: constructor Create(AIdent: String; AValue: String)

Visibility: public

Description: Create instantiates a new instance of TIniFileKey on the heap. It fills Ident (451) with AIdent and Value (451) with AValue.

See also: TIniFileKey.Ident (451), TIniFileKey.Value (451)

### 19.6.5 TIniFileKey.Ident

Synopsis: Key name

Declaration: Property Ident : String

Visibility: public

Access: Read,Write

Description: Ident is the key value part of the key/value pair.

See also: TIniFileKey.Value (451)

### 19.6.6 TIniFileKey.Value

Synopsis: Key value

Declaration: Property Value : String

Visibility: public

Access: Read,Write

Description: Value is the value part of the key/value pair.

See also: TIniFileKey.Ident (451)

## 19.7 TIniFileKeyList

### 19.7.1 Description

`TIniFileKeyList` maintains a list of `TIniFileKey` (451) instances on behalf of the `TIniFileSection` (453) class. It stores the keys of one section of the .ini files.

### 19.7.2 Method overview

Page	Property	Description
<a href="#">452</a>	<code>Clear</code>	Clear the list
<a href="#">452</a>	<code>Destroy</code>	Free the instance

### 19.7.3 Property overview

Page	Property	Access	Description
<a href="#">452</a>	<code>Items</code>	<code>r</code>	Indexed access to <code>TIniFileKey</code> items in the list

### 19.7.4 TIniFileKeyList.Destroy

Synopsis: Free the instance

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` clears up the list using `Clear` (452) and then calls the inherited `destroy`.

See also: `TIniFileKeyList.Clear` (452)

### 19.7.5 TIniFileKeyList.Clear

Synopsis: Clear the list

Declaration: `procedure Clear; Override`

Visibility: `public`

Description: `Clear` removes all `TIniFileKey` (451) instances from the list, and frees the instances.

See also: `TIniFileKey` (451)

### 19.7.6 TIniFileKeyList.Items

Synopsis: Indexed access to `TIniFileKey` items in the list

Declaration: `Property Items[Index: Integer]: TIniFileKey; default`

Visibility: `public`

Access: `Read`

Description: `Items` provides indexed access to the `TIniFileKey` (451) items in the list. The index is zero-based and runs from 0 to `Count-1`.

See also: `TIniFileKey` (451)

## 19.8 TIniFileSection

### 19.8.1 Description

`TIniFileSection` is a class which represents a section in the `.ini`, and is used internally by the `TIniFile` (447) class (one instance of `TIniFileSection` is created for each section in the file by the `TIniFileSectionList` (454) list). The name of the section is stored in the `Name` (454) property, and the key/value pairs in this section are available in the `KeyList` (454) property.

### 19.8.2 Method overview

Page	Property	Description
453	Create	Create a new section object
453	Destroy	Free the section object from memory
453	Empty	Is the section empty

### 19.8.3 Property overview

Page	Property	Access	Description
454	KeyList	r	List of key/value pairs in this section
454	Name	r	Name of the section

### 19.8.4 TIniFileSection.Empty

Synopsis: Is the section empty

Declaration: `function Empty : Boolean`

Visibility: `public`

Description: `Empty` returns `True` if the section contains no key values (even if they are empty). It may contain comments.

### 19.8.5 TIniFileSection.Create

Synopsis: Create a new section object

Declaration: `constructor Create (AName: String)`

Visibility: `public`

Description: `Create` instantiates a new `TIniFileSection` class, and sets the name to `AName`. It allocates a `TIniFileKeyList` (452) instance to keep all the key/value pairs for this section.

See also: `TIniFileKeyList` (452)

### 19.8.6 TIniFileSection.Destroy

Synopsis: Free the section object from memory

Declaration: `destructor Destroy; Override`

Visibility: `public`

**Description:** `Destroy` cleans up the key list, and then calls the inherited `Destroy`, removing the `TIniFileSection` instance from memory.

See also: `TIniFileSection.Create` ([453](#)), `TIniFileKeyList` ([452](#))

### 19.8.7 TIniFileSection.Name

**Synopsis:** Name of the section

**Declaration:** `Property Name : String`

**Visibility:** `public`

**Access:** `Read`

**Description:** `Name` is the name of the section in the file.

See also: `TIniFileSection.KeyList` ([454](#))

### 19.8.8 TIniFileSection.KeyList

**Synopsis:** List of key/value pairs in this section

**Declaration:** `Property KeyList : TIniFileKeyList`

**Visibility:** `public`

**Access:** `Read`

**Description:** `KeyList` is the `TIniFileKeyList` ([452](#)) instance that is used by the `TIniFileSection` to keep the key/value pairs of the section.

See also: `TIniFileSection.Name` ([454](#)), `TIniFileKeyList` ([452](#))

## 19.9 TIniFileSectionList

### 19.9.1 Description

`TIniFileSectionList` maintains a list of `TIniFileSection` ([453](#)) instances, one for each section in an `.ini` file. `TIniFileSectionList` is used internally by the `TIniFile` ([447](#)) class to represent the sections in the file.

### 19.9.2 Method overview

Page	Property	Description
<a href="#">455</a>	<code>Clear</code>	Clear the list
<a href="#">455</a>	<code>Destroy</code>	Free the object from memory

### 19.9.3 Property overview

Page	Property	Access	Description
<a href="#">455</a>	<code>Items</code>	<code>r</code>	Indexed access to all the section objects in the list



### 19.9.4 TIniFileSectionList.Destroy

Synopsis: Free the object from memory

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` calls `Clear` (455) to clear the section list and then calls the inherited `Destroy`

See also: `TIniFileSectionList.Clear` (455)

### 19.9.5 TIniFileSectionList.Clear

Synopsis: Clear the list

Declaration: `procedure Clear; Override`

Visibility: `public`

Description: `Clear` removes all `TIniFileSection` (453) items from the list, and frees the items it removes from the list.

See also: `TIniFileSection` (453), `TIniFileSectionList.Items` (455)

### 19.9.6 TIniFileSectionList.Items

Synopsis: Indexed access to all the section objects in the list

Declaration: `Property Items[Index: Integer]: TIniFileSection; default`

Visibility: `public`

Access: `Read`

Description: `Items` provides indexed access to all the section objects in the list. `Index` should run from 0 to `Count-1`.

See also: `TIniFileSection` (453), `TIniFileSectionList.Clear` (455)

## 19.10 TMemIniFile

### 19.10.1 Description

`TMemIniFile` is a simple descendent of `TIniFile` (447) which introduces some extra methods to be compatible to the Delphi implementation of `TMemIniFile`. The FPC implementation of `TIniFile` is implemented as a `TMemIniFile`, except that `TIniFile` does not cache its updates, and `TMemIniFile` does.

### 19.10.2 Method overview

Page	Property	Description
456	<code>Clear</code>	Clear the data
456	<code>Create</code>	Create a new instance of <code>TMemIniFile</code>
456	<code>GetStrings</code>	Get contents of ini file as stringlist
456	<code>Rename</code>	Rename the ini file
457	<code>SetStrings</code>	Set data from a stringlist

### 19.10.3 TMemIniFile.Create

Synopsis: Create a new instance of TMemIniFile

Declaration: `constructor Create(const AFileName: String; AEscapeLineFeeds: Boolean)  
; Override`

Visibility: public

Description: `Create` simply calls the inherited `Create` (447), and sets the `CacheUpdates` (450) to `True` so updates will be kept in memory till they are explicitly written to disk.

See also: `TIniFile.Create` (447), `TIniFile.CacheUpdates` (450)

### 19.10.4 TMemIniFile.Clear

Synopsis: Clear the data

Declaration: `procedure Clear`

Visibility: public

Description: `Clear` removes all sections and key/value pairs from memory. If `CacheUpdates` (450) is set to `False` then the file on disk will immediatly be emptied.

See also: `TMemIniFile.SetStrings` (457), `TMemIniFile.GetStrings` (456)

### 19.10.5 TMemIniFile.GetStrings

Synopsis: Get contents of ini file as stringlist

Declaration: `procedure GetStrings(List: TStrings)`

Visibility: public

Description: `GetStrings` returns the whole contents of the ini file in a single stringlist, `List`. This includes comments and empty sections.

The `GetStrings` call can be used to get data for a call to `SetStrings` (457), which can be used to copy data between 2 in-memory ini files.

See also: `TMemIniFile.SetStrings` (457), `TMemIniFile.Clear` (456)

### 19.10.6 TMemIniFile.Rename

Synopsis: Rename the ini file

Declaration: `procedure Rename(const AFileName: String; Reload: Boolean)`

Visibility: public

Description: `Rename` will rename the ini file with the new name `AFileName`. If `Reload` is `True` then the in-memory contents will be cleared and replaced with the contents found in `AFileName`, if it exists. If `Reload` is `False`, the next call to `UpdateFile` will replace the contents of `AFileName` with the in-memory data.

See also: `TIniFile.UpdateFile` (450)

### 19.10.7 TMemIniFile.SetStrings

Synopsis: Set data from a stringlist

Declaration: `procedure SetStrings(List: TStrings)`

Visibility: `public`

Description: `SetStrings` sets the in-memory data from the `List` stringlist. The data is first cleared.

The `SetStrings` call can be used to set the data of the ini file to a list of strings obtained with `GetStrings` ([456](#)). The two calls combined can be used to copy data between 2 in-memory ini files.

See also: `TMemIniFile.GetStrings` ([456](#)), `TMemIniFile.Clear` ([456](#))

## Chapter 20

# Reference for unit 'iostream'

### 20.1 Used units

Table 20.1: Used units by unit 'iostream'

Name	Page
Classes	??

### 20.2 Overview

The `iostream` implements a descendent of `THandleStream` (??) streams that can be used to read from standard input and write to standard output and standard diagnostic output (`stderr`).

### 20.3 Constants, types and variables

#### 20.3.1 Types

```
TIOSType = (iosInput, iosOutPut, iosError)
```

Table 20.2: Enumeration values for type `TIOSType`

Value	Explanation
<code>iosError</code>	The stream can be used to write to standard diagnostic output
<code>iosInput</code>	The stream can be used to read from standard input
<code>iosOutPut</code>	The stream can be used to write to standard output

`TIOSType` is passed to the `Create` (459) constructor of `TIOStream` (459), it determines what kind of stream is created.

## 20.4 EIOStreamError

### 20.4.1 Description

Error thrown in case of an invalid operation on a TIOStream ([459](#)).

## 20.5 TIOStream

### 20.5.1 Description

TIOStream can be used to create a stream which reads from or writes to the standard input, output or stderr file descriptors. It is a descendent of THandleStream. The type of stream that is created is determined by the TIOSType ([458](#)) argument to the constructor. The handle of the standard input, output or stderr file descriptors is determined automatically.

The TIOStream keeps an internal Position, and attempts to provide minimal Seek ([460](#)) behaviour based on this position.

### 20.5.2 Method overview

Page	Property	Description
<a href="#">459</a>	Create	Construct a new instance of TIOStream ( <a href="#">459</a> )
<a href="#">459</a>	Read	Read data from the stream.
<a href="#">460</a>	Seek	Set the stream position
<a href="#">460</a>	SetSize	Set the size of the stream
<a href="#">460</a>	Write	Write data to the stream

### 20.5.3 TIOStream.Create

Synopsis: Construct a new instance of TIOStream ([459](#))

Declaration: `constructor Create(aIOSType: TIOSType)`

Visibility: public

Description: Create creates a new instance of TIOStream ([459](#)), which can subsequently be used

Errors: No checking is performed to see whether the requested file descriptor is actually open for reading/writing. In that case, subsequent calls to Read or Write or seek will fail.

See also: TIOStream.Read ([459](#)), TIOStream.Write ([460](#))

### 20.5.4 TIOStream.Read

Synopsis: Read data from the stream.

Declaration: `function Read(var Buffer; Count: LongInt) : LongInt; Override`

Visibility: public

Description: Read checks first whether the type of the stream allows reading (type is iosInput). If not, it raises a EIOStreamError ([459](#)) exception. If the stream can be read, it calls the inherited Read to actually read the data.

Errors: An EIOStreamError exception is raised if the stream does not allow reading.

See also: TIOSType ([458](#)), TIOStream.Write ([460](#))

### 20.5.5 TIOStream.Write

Synopsis: Write data to the stream

Declaration: `function Write(const Buffer; Count: LongInt) : LongInt; Override`

Visibility: `public`

Description: `Write` checks first whether the type of the stream allows writing (type is `iosOutput` or `iosError`). If not, it raises a `EIOStreamError` (459) exception. If the stream can be written to, it calls the inherited `Write` to actually read the data.

Errors: An `EIOStreamError` exception is raised if the stream does not allow writing.

See also: `TIOStreamType` (458), `TIOStream.Read` (459)

### 20.5.6 TIOStream.SetSize

Synopsis: Set the size of the stream

Declaration: `procedure SetSize(NewSize: LongInt); Override`

Visibility: `public`

Description: `SetSize` overrides the standard `SetSize` implementation. It always raises an exception, because the standard input, output and stderr files have no size.

Errors: An `EIOStreamError` exception is raised when this method is called.

See also: `EIOStreamError` (459)

### 20.5.7 TIOStream.Seek

Synopsis: Set the stream position

Declaration: `function Seek(Offset: LongInt; Origin: Word) : LongInt; Override`

Visibility: `public`

Description: `Seek` overrides the standard `Seek` implementation. Normally, standard input, output and stderr are not seekable. The `TIOStream` stream tries to provide seek capabilities for the following limited number of cases:

**Origin=soFromBeginning** If `Offset` is larger than the current position, then the remaining bytes are skipped by reading them from the stream and discarding them, if the stream is of type `iosInput`.

**Origin=soFromCurrent** If `Offset` is zero, the current position is returned. If it is positive, then `Offset` bytes are skipped by reading them from the stream and discarding them, if the stream is of type `iosInput`.

All other cases will result in a `EIOStreamError` exception.

Errors: An `EIOStreamError` (459) exception is raised if the stream does not allow the requested seek operation.

See also: `EIOStreamError` (459)

# Chapter 21

## Reference for unit 'libtar'

### 21.1 Used units

Table 21.1: Used units by unit 'libtar'

Name	Page
BaseUnix	<a href="#">461</a>
Classes	??
sysutils	??
Unix	<a href="#">461</a>
UnixType	<a href="#">461</a>
Windows	<a href="#">461</a>

### 21.2 Overview

The `libtar` units provides 2 classes to read and write `.tar` archives: `TTarArchive` ([465](#)) class can be used to read a tar file, and the `TTarWriter` ([467](#)) class can be used to write a tar file. The unit was implemented originally by Stefan Heymann.

### 21.3 Constants, types and variables

#### 21.3.1 Constants

```
ALL_PERMISSIONS = [tpReadByOwner, tpWriteByOwner, tpExecuteByOwner, tpReadByGroup, tpWriteByGroup, tpExecuteByGroup, tpExecuteByOther]
```

`ALL_PERMISSIONS` is a set constant containing all possible permissions (read/write/execute, for all groups of users) for an archive entry.

```
EXECUTE_PERMISSIONS = [tpExecuteByOwner, tpExecuteByGroup, tpExecuteByOther]
```

`WRITE_PERMISSIONS` is a set constant containing all possible execute permissions set for an archive entry.

```
FILETYPE_NAME : Array[TFileType] of String = ('Regular', 'Link', 'Symbolic Link', 'Char
```

FILETYPE\_NAME can be used to get a textual description for each of the possible entry file types.

```
READ_PERMISSIONS = [tpReadByOwner, tpReadByGroup, tpReadByOther]
```

READ\_PERMISSIONS is a set constant containing all possible read permissions set for an archive entry.

```
WRITE_PERMISSIONS = [tpWriteByOwner, tpWriteByGroup, tpWriteByOther]
```

WRITE\_PERMISSIONS is a set constant containing all possible write permissions set for an archive entry.

### 21.3.2 Types

```
TFileType = (ftNormal, ftLink, ftSymbolicLink, ftCharacter, ftBlock,
             ftDirectory, ftFifo, ftContiguous, ftDumpDir, ftMultiVolume,
             ftVolumeHeader)
```

Table 21.2: Enumeration values for type TFileType

Value	Explanation
ftBlock	Block device file
ftCharacter	Character device file
ftContiguous	Contiguous file
ftDirectory	Directory
ftDumpDir	List of files
ftFifo	FIFO file
ftLink	Hard link
ftMultiVolume	Multi-volume file part
ftNormal	Normal file
ftSymbolicLink	Symbolic link
ftVolumeHeader	Volume header, can appear only as first entry in the archive

TFileType describes the file type of a file in the archive. It is used in the FileType field of the TTarDirRec (463) record.

```
TTarDirRec = record
  Name : String;
  Size : Int64;
  DateTime : TDateTime;
  Permissions : TTarPermissions;
  FileType : TFileType;
  LinkName : String;
  UID : Integer;
  GID : Integer;
  UserName : String;
  GroupName : String;
  ChecksumOK : Boolean;
```



```

Mode : TTarModes;
Magic : String;
MajorDevNo : Integer;
MinorDevNo : Integer;
FilePos : Int64;
end

```

TTarDirRec describes an entry in the tar archive. It is similar to a directory entry as in TSearchRec (??), and is returned by the TTarArchive.FindNext (466) call.

```
TTarMode = (tmSetUid, tmSetGid, tmSaveText)
```

Table 21.3: Enumeration values for type TTarMode

Value	Explanation
tmSaveText	Bit \$200 is set
tmSetGid	File has SetGID bit set
tmSetUid	File has SetUID bit set.

TTarMode describes extra file modes. It is used in the Mode field of the TTarDirRec (463) record.

```
TTarModes= Set of (tmSaveText, tmSetGid, tmSetUid)
```

TTarModes denotes the full set of permission bits for the file in the field Mode field of the TTarDirRec (463) record.

```

TTarPermission = (tpReadByOwner, tpWriteByOwner, tpExecuteByOwner,
tpReadByGroup, tpWriteByGroup, tpExecuteByGroup,
tpReadByOther, tpWriteByOther, tpExecuteByOther)

```

Table 21.4: Enumeration values for type TTarPermission

Value	Explanation
tpExecuteByGroup	Group can execute the file
tpExecuteByOther	Other people can execute the file
tpExecuteByOwner	Owner can execute the file
tpReadByGroup	Group can read the file
tpReadByOther	Other people can read the file.
tpReadByOwner	Owner can read the file
tpWriteByGroup	Group can write the file
tpWriteByOther	Other people can write the file
tpWriteByOwner	Owner can write the file

TTarPermission denotes part of a files permission as it stored in the .tar archive. Each of these enumerated constants correspond with one of the permission bits from a unix file permission.

```

TTarPermissions= Set of (tpExecuteByGroup, tpExecuteByOther,
tpExecuteByOwner, tpReadByGroup, tpReadByOther,
tpReadByOwner, tpWriteByGroup, tpWriteByOther,
tpWriteByOwner)

```

`TTarPermissions` describes the complete set of permissions that a file has. It is used in the `Permissions` field of the `TTarDirRec` (463) record.

## 21.4 Procedures and functions

### 21.4.1 ClearDirRec

Synopsis: Initialize tar archive entry

Declaration: `procedure ClearDirRec(var DirRec: TTarDirRec)`

Visibility: default

Description: `ClearDirRec` clears the `DirRec` entry, it basically zeroes out all fields.

See also: `TTarDirRec` (463)

### 21.4.2 ConvertFilename

Synopsis: Convert filename to archive format

Declaration: `function ConvertFilename(Filename: String) : String`

Visibility: default

Description: `ConvertFileName` converts the file name `FileName` to a format allowed by the tar archive. Basically, it converts directory specifiers to forward slashes.

### 21.4.3 FileTimeGMT

Synopsis: Extract filetime

Declaration: `function FileTimeGMT(FileName: String) : TDateTime; Overload`  
`function FileTimeGMT(SearchRec: TSearchRec) : TDateTime; Overload`

Visibility: default

Description: `FileTimeGMT` returns the timestamp of a filename (`FileName` must exist) or a search rec (`TSearchRec`) to a GMT representation that can be used in a tar entry.

See also: `TTarDirRec` (463)

### 21.4.4 PermissionString

Synopsis: Convert a set of permissions to a string

Declaration: `function PermissionString(Permissions: TTarPermissions) : String`

Visibility: default

Description: `PermissionString` can be used to convert a set of `Permissions` to a string in the same format as used by the unix `'ls'` command.

See also: `TTarPermissions` (464)

## 21.5 TTarArchive

### 21.5.1 Description

`TTarArchive` is the class used to read and examine `.tar` archives. It can be constructed from a stream or from a filename. Creating an instance will not perform any operation on the stream yet.

### 21.5.2 Method overview

Page	Property	Description
<a href="#">465</a>	Create	Create a new instance of the archive
<a href="#">465</a>	Destroy	Destroy <code>TTarArchive</code> instance
<a href="#">466</a>	FindNext	Find next archive entry
<a href="#">466</a>	GetFilePos	Return current archive position
<a href="#">466</a>	ReadFile	Read a file from the archive
<a href="#">465</a>	Reset	Reset archive
<a href="#">467</a>	SetFilePos	Set position in archive

### 21.5.3 TTarArchive.Create

Synopsis: Create a new instance of the archive

Declaration: `constructor Create(Stream: TStream); Overload`  
`constructor Create(Filename: String; FileMode: Word); Overload`

Visibility: public

Description: `Create` can be used to create a new instance of `TTarArchive` using either a `StreamTStream` (??) descendent or using a name of a file to open: `FileName`. In case of the filename, an open mode can be specified.

Errors: In case a filename is specified and the file cannot be opened, an exception will occur.

See also: `TTarArchive.FindNext` ([466](#))

### 21.5.4 TTarArchive.Destroy

Synopsis: Destroy `TTarArchive` instance

Declaration: `destructor Destroy; Override`

Visibility: public

Description: `Destroy` closes the archive stream (if it created a stream) and cleans up the `TTarArchive` instance.

See also: `TTarArchive.Create` ([465](#))

### 21.5.5 TTarArchive.Reset

Synopsis: Reset archive

Declaration: `procedure Reset`

Visibility: public

**Description:** `Reset` sets the archive file position on the beginning of the archive.

See also: `TTarArchive.Create` ([465](#))

### 21.5.6 `TTarArchive.FindNext`

**Synopsis:** Find next archive entry

**Declaration:** `function FindNext (var DirRec: TTarDirRec) : Boolean`

**Visibility:** public

**Description:** `FindNext` positions the file pointer on the next archive entry, and returns all information about the entry in `DirRec`. It returns `True` if the operation was successful, or `False` if not (for instance, when the end of the archive was reached).

**Errors:** In case there are no more entries, `False` is returned.

See also: `TTarArchive.ReadFile` ([466](#))

### 21.5.7 `TTarArchive.ReadFile`

**Synopsis:** Read a file from the archive

**Declaration:** `procedure ReadFile (Buffer: POINTER); Overload`  
`procedure ReadFile (Stream: TStream); Overload`  
`procedure ReadFile (Filename: String); Overload`  
`function ReadFile : String; Overload`

**Visibility:** public

**Description:** `ReadFile` can be used to read the current file in the archive. It can be called after the archive was successfully positioned on an entry in the archive. The file can be read in various ways:

- directly in a memory buffer. No checks are performed to see whether the buffer points to enough memory.
- It can be copied to a `Stream`.
- It can be copied to a file with name `FileName`.
- The file content can be copied to a string

**Errors:** An exception may occur if the buffer is not large enough, or when the file specified in `filename` cannot be opened.

### 21.5.8 `TTarArchive.GetFilePos`

**Synopsis:** Return current archive position

**Declaration:** `procedure GetFilePos (var Current: Int64; var Size: Int64)`

**Visibility:** public

**Description:** `GetFilePos` returns the position in the tar archive in `Current` and the complete archive size in `Size`.

See also: `TTarArchive.SetFilePos` ([467](#)), `TTarArchive.Reset` ([465](#))

### 21.5.9 TTarArchive.SetFilePos

Synopsis: Set position in archive

Declaration: `procedure SetFilePos(NewPos: Int64)`

Visibility: public

Description: `SetFilePos` can be used to set the absolute position in the tar archive.

See also: `TTarArchive.Reset` ([465](#)), `TTarArchive.GetFilePos` ([466](#))

## 21.6 TTarWriter

### 21.6.1 Description

`TTarWriter` can be used to create `.tar` archives. It can be created using a filename, in which case the archive will be written to the filename, or it can be created using a stream, in which case the archive will be written to the stream - for instance a compression stream.

### 21.6.2 Method overview

Page	Property	Description
<a href="#">469</a>	<code>AddDir</code>	Add directory to archive
<a href="#">468</a>	<code>AddFile</code>	Add a file to the archive
<a href="#">470</a>	<code>AddLink</code>	Add hard link to archive
<a href="#">468</a>	<code>AddStream</code>	Add stream contents to archive.
<a href="#">469</a>	<code>AddString</code>	Add string as file data
<a href="#">469</a>	<code>AddSymbolicLink</code>	Add a symbolic link to the archive
<a href="#">470</a>	<code>AddVolumeHeader</code>	Add volume header entry
<a href="#">467</a>	<code>Create</code>	Create a new archive
<a href="#">468</a>	<code>Destroy</code>	Close archive and clean up <code>TTarWriter</code>
<a href="#">470</a>	<code>Finalize</code>	Finalize the archive

### 21.6.3 Property overview

Page	Property	Access	Description
<a href="#">471</a>	<code>GID</code>	rw	Archive entry group ID
<a href="#">471</a>	<code>GroupName</code>	rw	Archive entry group name
<a href="#">472</a>	<code>Magic</code>	rw	Archive entry Magic constant
<a href="#">472</a>	<code>Mode</code>	rw	Archive entry mode
<a href="#">470</a>	<code>Permissions</code>	rw	Archive entry permissions
<a href="#">471</a>	<code>UID</code>	rw	Archive entry user ID
<a href="#">471</a>	<code>UserName</code>	rw	Archive entry user name

### 21.6.4 TTarWriter.Create

Synopsis: Create a new archive

Declaration: `constructor Create(TargetStream: TStream); Overload`  
`constructor Create(TargetFilename: String; Mode: Integer); Overload`

Visibility: public

**Description:** `Create` creates a new `TTarWriter` instance. This will start a new `.tar` archive. The archive will be written to the `TargetStream` stream or to a file with name `TargetFileName`, which will be opened with filemode `Mode`.

**Errors:** In case `TargetFileName` cannot be opened, an exception will be raised.

See also: `TTarWriter.Destroy` (468)

### 21.6.5 `TTarWriter.Destroy`

**Synopsis:** Close archive and clean up `TTarWriter`

**Declaration:** `destructor Destroy; Override`

**Visibility:** `public`

**Description:** `Destroy` will close the archive (i.e. it writes the end-of-archive marker, if it was not yet written), and then frees the `TTarWriter` instance.

See also: `TTarWriter.Finalize` (470)

### 21.6.6 `TTarWriter.AddFile`

**Synopsis:** Add a file to the archive

**Declaration:** `procedure AddFile(FileName: String; TarFilename: String)`

**Visibility:** `public`

**Description:** `AddFile` adds a file to the archive: the contents is read from `FileName`. Optionally, an alternative filename can be specified in `TarFileName`. This name should contain only forward slash path separators. If it is not specified, the name will be computed from `FileName`.

The archive entry is written with the current owner data and permissions.

**Errors:** If `FileName` cannot be opened, an exception will be raised.

See also: `TTarWriter.AddStream` (468), `TTarWriter.AddString` (469), `TTarWriter.AddLink` (470), `TTarWriter.AddSymbolicLink` (469), `TTarWriter.AddDir` (469), `TTarWriter.AddVolumeHeader` (470)

### 21.6.7 `TTarWriter.AddStream`

**Synopsis:** Add stream contents to archive.

**Declaration:** `procedure AddStream(Stream: TStream; TarFilename: String;  
FileDateGmt: TDateTime)`

**Visibility:** `public`

**Description:** `AddStream` will add the contents of `Stream` to the archive. The `Stream` will not be reset: only the contents of the stream from the current position will be written to the archive. The entry will be written with file name `TarFileName`. This name should contain only forward slash path separators. The entry will be written with timestamp `FileDateGmt`.

The archive entry is written with the current owner data and permissions.

See also: `TTarWriter.AddFile` (468), `TTarWriter.AddString` (469), `TTarWriter.AddLink` (470), `TTarWriter.AddSymbolicLink` (469), `TTarWriter.AddDir` (469), `TTarWriter.AddVolumeHeader` (470)

### 21.6.8 TTarWriter.AddString

Synopsis: Add string as file data

Declaration: `procedure AddString(Contents: String; TarFilename: String;  
FileDateGmt: TDateTime)`

Visibility: public

Description: `AddString` adds the string `Contents` as the data of an entry with file name `TarFileName`. This name should contain only forward slash path separators. The entry will be written with timestamp `FileDateGmt`.

The archive entry is written with the current owner data and permissions.

See also: `TTarWriter.AddFile` (468), `TTarWriter.AddStream` (468), `TTarWriter.AddLink` (470), `TTarWriter.AddSymbolicLink` (469), `TTarWriter.AddDir` (469), `TTarWriter.AddVolumeHeader` (470)

### 21.6.9 TTarWriter.AddDir

Synopsis: Add directory to archive

Declaration: `procedure AddDir(Dirname: String; DateGmt: TDateTime; MaxDirSize: Int64)`

Visibility: public

Description: `AddDir` adds a directory entry to the archive. The entry is written with name `DirName`, maximum directory size `MaxDirSize` (0 means unlimited) and timestamp `DateGmt`.

Note that this call only adds an entry for a directory to the archive: if `DirName` is an existing directory, it does not write all files in the directory to the archive.

The directory entry is written with the current owner data and permissions.

See also: `TTarWriter.AddFile` (468), `TTarWriter.AddStream` (468), `TTarWriter.AddLink` (470), `TTarWriter.AddSymbolicLink` (469), `TTarWriter.AddString` (469), `TTarWriter.AddVolumeHeader` (470)

### 21.6.10 TTarWriter.AddSymbolicLink

Synopsis: Add a symbolic link to the archive

Declaration: `procedure AddSymbolicLink(Filename: String; Linkname: String;  
DateGmt: TDateTime)`

Visibility: public

Description: `AddSymbolicLink` adds a symbolic link entry to the archive, with name `FileName`, pointing to `LinkName`. The entry is written with timestamp `DateGmt`.

The link entry is written with the current owner data and permissions.

Errors:

See also: `TTarWriter.AddFile` (468), `TTarWriter.AddStream` (468), `TTarWriter.AddLink` (470), `TTarWriter.AddDir` (469), `TTarWriter.AddString` (469), `TTarWriter.AddVolumeHeader` (470)

### 21.6.11 TTarWriter.AddLink

Synopsis: Add hard link to archive

Declaration: `procedure AddLink (Filename: String; Linkname: String; DateGmt: TDateTime)`

Visibility: public

Description: `AddLink` adds a hard link entry to the archive. The entry has name `FileName`, timestamp `DateGmt` and points to `LinkName`.

The link entry is written with the current owner data and permissions.

Errors:

See also: `TTarWriter.AddFile` ([468](#)), `TTarWriter.AddStream` ([468](#)), `TTarWriter.AddSymbolicLink` ([469](#)), `TTarWriter.AddDir` ([469](#)), `TTarWriter.AddString` ([469](#)), `TTarWriter.AddVolumeHeader` ([470](#))

### 21.6.12 TTarWriter.AddVolumeHeader

Synopsis: Add volume header entry

Declaration: `procedure AddVolumeHeader (VolumeId: String; DateGmt: TDateTime)`

Visibility: public

Description: `AddVolumeHeader` adds a volume header entry to the archive. The entry is written with name `VolumeID` and timestamp `DateGmt`.

The volume header entry is written with the current owner data and permissions.

Errors:

See also: `TTarWriter.AddFile` ([468](#)), `TTarWriter.AddStream` ([468](#)), `TTarWriter.AddSymbolicLink` ([469](#)), `TTarWriter.AddDir` ([469](#)), `TTarWriter.AddString` ([469](#)), `TTarWriter.AddLink` ([470](#))

### 21.6.13 TTarWriter.Finalize

Synopsis: Finalize the archive

Declaration: `procedure Finalize`

Visibility: public

Description: `Finalize` writes the end-of-archive marker to the archive. No more entries can be added after `Finalize` was called.

If the `TTarWriter` instance is destroyed, it will automatically call `finalize` if `finalize` was not yet called.

See also: `TTarWriter.Destroy` ([468](#))

### 21.6.14 TTarWriter.Permissions

Synopsis: Archive entry permissions

Declaration: `Property Permissions : TTarPermissions`

Visibility: public

Access: Read, Write



Description: `Permissions` is used for the `permissions` field of the archive entries.

See also: `TTarDirRec` ([463](#))

### 21.6.15 `TTarWriter.UID`

Synopsis: Archive entry user ID

Declaration: `Property UID : Integer`

Visibility: `public`

Access: `Read,Write`

Description: `UID` is used for the `UID` field of the archive entries.

See also: `TTarDirRec` ([463](#))

### 21.6.16 `TTarWriter.GID`

Synopsis: Archive entry group ID

Declaration: `Property GID : Integer`

Visibility: `public`

Access: `Read,Write`

Description: `GID` is used for the `GID` field of the archive entries.

See also: `TTarDirRec` ([463](#))

### 21.6.17 `TTarWriter.UserName`

Synopsis: Archive entry user name

Declaration: `Property UserName : String`

Visibility: `public`

Access: `Read,Write`

Description: `UserName` is used for the `UserName` field of the archive entries.

See also: `TTarDirRec` ([463](#))

### 21.6.18 `TTarWriter.GroupName`

Synopsis: Archive entry group name

Declaration: `Property GroupName : String`

Visibility: `public`

Access: `Read,Write`

Description: `GroupName` is used for the `GroupName` field of the archive entries.

See also: `TTarDirRec` ([463](#))

### 21.6.19 TTarWriter.Mode

Synopsis: Archive entry mode

Declaration: `Property Mode : TTarModes`

Visibility: `public`

Access: `Read,Write`

Description: `Mode` is used for the `Mode` field of the archive entries.

See also: `TTarDirRec` ([463](#))

### 21.6.20 TTarWriter.Magic

Synopsis: Archive entry Magic constant

Declaration: `Property Magic : String`

Visibility: `public`

Access: `Read,Write`

Description: `Magic` is used for the `Magic` field of the archive entries.

See also: `TTarDirRec` ([463](#))

## Chapter 22

# Reference for unit 'Pipes'

### 22.1 Used units

Table 22.1: Used units by unit 'Pipes'

Name	Page
Classes	??
sysutils	??

### 22.2 Overview

The Pipes unit implements streams that are wrappers around the OS's pipe functionality. It creates a pair of streams, and what is written to one stream can be read from another.

### 22.3 Constants, types and variables

#### 22.3.1 Constants

`ENoSeekMsg = 'Cannot seek on pipes'`

Constant used in `EPipeSeek` ([474](#)) exception.

`EPipeMsg = 'Failed to create pipe.'`

Constant used in `EPipeCreation` ([474](#)) exception.

### 22.4 Procedures and functions

#### 22.4.1 CreatePipeHandles

Synopsis: Function to create a set of pipe handles

**Declaration:** `function CreatePipeHandles(var InHandle: THandle; var OutHandle: THandle)  
: Boolean`

**Visibility:** default

**Description:** `CreatePipeHandles` provides an OS-independent way to create a set of pipe filehandles. These handles are inheritable to child processes. The reading end of the pipe is returned in `InHandle`, the writing end in `OutHandle`.

**Errors:** On error, `False` is returned.

**See also:** `CreatePipeStreams` (474)

## 22.4.2 CreatePipeStreams

**Synopsis:** Create a pair of pipe stream.

**Declaration:** `procedure CreatePipeStreams(var InPipe: TInputPipeStream;  
var OutPipe: TOutputPipeStream)`

**Visibility:** default

**Description:** `CreatePipeStreams` creates a set of pipe file descriptors with `CreatePipeHandles` (473), and if that call is successful, a pair of streams is created: `InPipe` and `OutPipe`.

**Errors:** If no pipe handles could be created, an `EPipeCreation` (474) exception is raised.

**See also:** `CreatePipeHandles` (473), `TInputPipeStream` (474), `TOutputPipeStream` (476)

## 22.5 EPipeCreation

### 22.5.1 Description

Exception raised when an error occurred during the creation of a pipe pair.

## 22.6 EPipeError

### 22.6.1 Description

Exception raised when an invalid operation is performed on a pipe stream.

## 22.7 EPipeSeek

### 22.7.1 Description

Exception raised when an invalid seek operation is attempted on a pipe.

## 22.8 TInputPipeStream

### 22.8.1 Description

`TInputPipeStream` is created by the `CreatePipeStreams` (474) call to represent the reading end of a pipe. It is a `TStream` (??) descendent which does not allow writing, and which mimics the seek operation.

### 22.8.2 Method overview

Page	Property	Description
<a href="#">476</a>	Read	Read data from the stream to a buffer.
<a href="#">475</a>	Seek	Set the current position of the stream
<a href="#">475</a>	Write	Write data to the stream.

### 22.8.3 Property overview

Page	Property	Access	Description
<a href="#">476</a>	NumBytesAvailable	r	Number of bytes available for reading.

### 22.8.4 TInputPipeStream.Write

Synopsis: Write data to the stream.

Declaration: `function Write(const Buffer; Count: LongInt) : LongInt; Override`

Visibility: public

Description: `Write` overrides the parent implementation of `Write`. On a `TInputPipeStream` will always raise an exception, as the pipe is read-only.

Errors: An `ENoWritePipe` ([473](#)) exception is raised when this function is called.

See also: `TInputPipeStream.Read` ([476](#)), `TInputPipeStream.Seek` ([475](#))

### 22.8.5 TInputPipeStream.Seek

Synopsis: Set the current position of the stream

Declaration: `function Seek(Offset: LongInt; Origin: Word) : LongInt; Override`

Visibility: public

Description: `Seek` overrides the standard `Seek` implementation. Normally, pipe streams stderr are not seekable. The `TInputPipeStream` stream tries to provide seek capabilities for the following limited number of cases:

**Origin=soFromBeginning** If `Offset` is larger than the current position, then the remaining bytes are skipped by reading them from the stream and discarding them.

**Origin=soFromCurrent** If `Offset` is zero, the current position is returned. If it is positive, then `Offset` bytes are skipped by reading them from the stream and discarding them, if the stream is of type `iosInput`.

All other cases will result in a `EPipeSeek` exception.

Errors: An `EPipeSeek` ([474](#)) exception is raised if the stream does not allow the requested seek operation.

See also: `EPipeSeek` ([474](#)), `#rtl.classes.tstream.seek` (??)

### 22.8.6 TInputPipeStream.Read

Synopsis: Read data from the stream to a buffer.

Declaration: `function Read(var Buffer; Count: LongInt) : LongInt; Override`

Visibility: `public`

Description: `Read` calls the inherited `read` and adjusts the internal position pointer of the stream.

Errors: None.

See also: `TInputPipeStream.Write` (475), `TInputPipeStream.Seek` (475)

### 22.8.7 TInputPipeStream.NumBytesAvailable

Synopsis: Number of bytes available for reading.

Declaration: `Property NumBytesAvailable : DWord`

Visibility: `public`

Access: `Read`

Description: `NumBytesAvailable` is the number of bytes available for reading. This is the number of bytes in the OS buffer for the pipe. It is not a number of bytes in an internal buffer.

If this number is nonzero, then reading `NumBytesAvailable` bytes from the stream will not block the process. Reading more than `NumBytesAvailable` bytes will block the process, while it waits for the requested number of bytes to become available.

See also: `TInputPipeStream.Read` (476)

## 22.9 TOutputPipeStream

### 22.9.1 Description

`TOutputPipeStream` is created by the `CreatePipeStreams` (474) call to represent the writing end of a pipe. It is a `TStream` (??) descendent which does not allow reading.

### 22.9.2 Method overview

Page	Property	Description
<a href="#">477</a>	<code>Read</code>	Read data from the stream.
<a href="#">476</a>	<code>Seek</code>	Sets the position in the stream

### 22.9.3 TOutputPipeStream.Seek

Synopsis: Sets the position in the stream

Declaration: `function Seek(Offset: LongInt; Origin: Word) : LongInt; Override`

Visibility: `public`

Description: `Seek` is overridden in `TOutputPipeStream`. Calling this method will always raise an exception: an output pipe is not seekable.

Errors: An `EPipeSeek` (474) exception is raised if this method is called.

### 22.9.4 TOutputPipeStream.Read

Synopsis: Read data from the stream.

Declaration: `function Read(var Buffer; Count: LongInt) : LongInt; Override`

Visibility: `public`

Description: `Read` overrides the parent `Read` implementation. It always raises an exception, because a output pipe is write-only.

Errors: An `ENoReadPipe` ([473](#)) exception is raised when this function is called.

See also: `TOutputPipeStream.Seek` ([476](#))

## Chapter 23

# Reference for unit 'pooledmm'

### 23.1 Used units

Table 23.1: Used units by unit 'pooledmm'

Name	Page
Classes	??

### 23.2 Overview

`pooledmm` is a memory manager class which uses pools of blocks. Since it is a higher-level implementation of a memory manager which works on top of the FPC memory manager, It also offers more debugging and analysis tools. It is used mainly in the LCL and Lazarus IDE.

### 23.3 Constants, types and variables

#### 23.3.1 Types

```
PPooledMemManagerItem = ^TPooledMemManagerItem
```

`PPooledMemManagerItem` is a pointer type, pointing to a `TPooledMemManagerItem` (479) item, used in a linked list.

```
TEnumItemsMethod = procedure(Item: Pointer) of object
```

`TEnumItemsMethod` is a prototype for the callback used in the `TNonFreePooledMemManager.EnumerateItems` (480) call. The parameter `Item` will be set to each of the pointers in the item list of `TNonFreePooledMemManager` (479).

```
TPooledMemManagerItem = record
  Next : PPooledMemManagerItem;
end
```



`TPooledMemManagerItem` is used internally by the `TPooledMemManager` (481) class to maintain the free list block. It simply points to the next free block.

## 23.4 TNonFreePooledMemManager

### 23.4.1 Description

`TNonFreePooledMemManager` keeps a list of fixed-size memory blocks in memory. Each block has the same size, making it suitable for storing a lot of records of the same type. It does not free the items stored in it, except when the list is cleared as a whole.

It allocates memory for the blocks in an exponential way, i.e. each time a new block of memory must be allocated, its size is the double of the last block. The first block will contain 8 items.

### 23.4.2 Method overview

Page	Property	Description
479	<code>Clear</code>	Clears the memory
479	<code>Create</code>	Creates a new instance of <code>TNonFreePooledMemManager</code>
480	<code>Destroy</code>	Removes the <code>TNonFreePooledMemManager</code> instance from memory
480	<code>EnumerateItems</code>	Enumerate all items in the list
480	<code>NewItem</code>	Return a pointer to a new memory block

### 23.4.3 Property overview

Page	Property	Access	Description
480	<code>ItemSize</code>	r	Size of an item in the list

### 23.4.4 TNonFreePooledMemManager.Clear

Synopsis: Clears the memory

Declaration: `procedure Clear`

Visibility: `public`

Description: `Clear` clears all blocks from memory, freeing the allocated memory blocks. None of the pointers returned by `NewItem` (480) is valid after a call to `Clear`

See also: `TNonFreePooledMemManager.NewItem` (480)

### 23.4.5 TNonFreePooledMemManager.Create

Synopsis: Creates a new instance of `TNonFreePooledMemManager`

Declaration: `constructor Create(TheItemSize: Integer)`

Visibility: `public`

Description: `Create` creates a new instance of `TNonFreePooledMemManager` and sets the item size to `TheItemSize`.

Errors: If not enough memory is available, an exception may be raised.

See also: `TNonFreePooledMemManager.ItemSize` (480)

### 23.4.6 TNonFreePooledMemManager.Destroy

Synopsis: Removes the `TNonFreePooledMemManager` instance from memory

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` clears the list, clears the internal structures, and then calls the inherited `Destroy`.

`Destroy` should never be called directly. Instead `Free` should be used, or `FreeAndNil`

See also: `TNonFreePooledMemManager.Create` ([479](#)), `TNonFreePooledMemManager.Clear` ([479](#))

### 23.4.7 TNonFreePooledMemManager.NewItem

Synopsis: Return a pointer to a new memory block

Declaration: `function NewItem : Pointer`

Visibility: `public`

Description: `NewItem` returns a pointer to an unused memory block of size `ItemSize` ([480](#)). It will allocate new memory on the heap if necessary.

Note that there is no way to mark the memory block as free, except by clearing the whole list.

Errors: If no more memory is available, an exception may be raised.

See also: `TNonFreePooledMemManager.Clear` ([479](#))

### 23.4.8 TNonFreePooledMemManager.EnumerateItems

Synopsis: Enumerate all items in the list

Declaration: `procedure EnumerateItems(const Method: TEnumItemsMethod)`

Visibility: `public`

Description: `EnumerateItems` will enumerate over all items in the list, passing the items to `Method`. This can be used to execute certain operations on all items in the list. (for example, simply list them)

### 23.4.9 TNonFreePooledMemManager.ItemSize

Synopsis: Size of an item in the list

Declaration: `Property ItemSize : Integer`

Visibility: `public`

Access: `Read`

Description: `ItemSize` is the size of a single block in the list. It's a fixed size determined when the list is created.

See also: `TNonFreePooledMemManager.Create` ([479](#))

## 23.5 TPooledMemManager

### 23.5.1 Description

`TPooledMemManager` is a class which maintains a linked list of blocks, represented by the `TPooledMemManagerItem` (479) record. It should not be used directly, but should be descended from and the descendent should implement the actual memory manager.

### 23.5.2 Method overview

Page	Property	Description
<a href="#">481</a>	<code>Clear</code>	Clears the list
<a href="#">481</a>	<code>Create</code>	Creates a new instance of the <code>TPooledMemManager</code> class
<a href="#">481</a>	<code>Destroy</code>	Removes an instance of <code>TPooledMemManager</code> class from memory

### 23.5.3 Property overview

Page	Property	Access	Description
<a href="#">483</a>	<code>AllocatedCount</code>	r	Total number of allocated items in the list
<a href="#">482</a>	<code>Count</code>	r	Number of items in the list
<a href="#">483</a>	<code>FreeCount</code>	r	Number of free items in the list
<a href="#">483</a>	<code>FreedCount</code>	r	Total number of freed items in the list.
<a href="#">482</a>	<code>MaximumFreeCountRatio</code>	rw	Maximum ratio of free items over total items
<a href="#">482</a>	<code>MinimumFreeCount</code>	rw	Minimum count of free items in the list

### 23.5.4 TPooledMemManager.Clear

Synopsis: Clears the list

Declaration: `procedure Clear`

Visibility: `public`

Description: `Clear` clears the list, it disposes all items in the list.

See also: `TPooledMemManager.FreedCount` ([483](#))

### 23.5.5 TPooledMemManager.Create

Synopsis: Creates a new instance of the `TPooledMemManager` class

Declaration: `constructor Create`

Visibility: `public`

Description: `Create` initializes all necessary properties and then calls the inherited `create`.

See also: `TPooledMemManager.Destroy` ([481](#))

### 23.5.6 TPooledMemManager.Destroy

Synopsis: Removes an instance of `TPooledMemManager` class from memory

Declaration: `destructor Destroy; Override`

Visibility: public

Description: `Destroy` calls `Clear` ([481](#)) and then calls the inherited `destroy`.

`Destroy` should never be called directly. Instead `Free` should be used, or `FreeAndNil`

See also: `TPooledMemManager.Create` ([481](#))

### 23.5.7 `TPooledMemManager.MinimumFreeCount`

Synopsis: Minimum count of free items in the list

Declaration: `Property MinimumFreeCount : Integer`

Visibility: public

Access: Read,Write

Description: `MinimumFreeCount` is the minimum number of free items in the linked list. When disposing an item in the list, the number of items is checked, and only if the required number of free items is present, the item is actually freed.

The default value is 100000

See also: `TPooledMemManager.MaximumFreeCountRatio` ([482](#))

### 23.5.8 `TPooledMemManager.MaximumFreeCountRatio`

Synopsis: Maximum ratio of free items over total items

Declaration: `Property MaximumFreeCountRatio : Integer`

Visibility: public

Access: Read,Write

Description: `MaximumFreeCountRatio` is the maximum ratio (divided by 8) of free elements over the total amount of elements: When disposing an item in the list, if the number of free items is higher than this ratio, the item is freed.

The default value is 8.

See also: `TPooledMemManager.MinimumFreeCount` ([482](#))

### 23.5.9 `TPooledMemManager.Count`

Synopsis: Number of items in the list

Declaration: `Property Count : Integer`

Visibility: public

Access: Read

Description: `Count` is the total number of items allocated from the list.

See also: `TPooledMemManager.FreeCount` ([483](#)), `TPooledMemManager.AllocatedCount` ([483](#)), `TPooledMemManager.FreedCount` ([483](#))

### 23.5.10 TPooledMemManager.FreeCount

Synopsis: Number of free items in the list

Declaration: `Property FreeCount : Integer`

Visibility: `public`

Access: `Read`

Description: `FreeCount` is the current total number of free items in the list.

See also: `TPooledMemManager.Count` ([482](#)), `TPooledMemManager.AllocatedCount` ([483](#)), `TPooledMemManager.FreedCount` ([483](#))

### 23.5.11 TPooledMemManager.AllocatedCount

Synopsis: Total number of allocated items in the list

Declaration: `Property AllocatedCount : Int64`

Visibility: `public`

Access: `Read`

Description: `AllocatedCount` is the total number of newly allocated items on the list.

See also: `TPooledMemManager.Count` ([482](#)), `TPooledMemManager.FreeCount` ([483](#)), `TPooledMemManager.FreedCount` ([483](#))

### 23.5.12 TPooledMemManager.FreedCount

Synopsis: Total number of freed items in the list.

Declaration: `Property FreedCount : Int64`

Visibility: `public`

Access: `Read`

Description: `FreedCount` is the total number of elements actually freed in the list.

See also: `TPooledMemManager.Count` ([482](#)), `TPooledMemManager.FreeCount` ([483](#)), `TPooledMemManager.AllocatedCount` ([483](#))

## Chapter 24

# Reference for unit 'process'

### 24.1 Used units

Table 24.1: Used units by unit 'process'

Name	Page
Classes	??
Pipes	<a href="#">473</a>
sysutils	??

### 24.2 Overview

The `Process` unit contains the code for the `TProcess` ([486](#)) component, a cross-platform component to start and control other programs, offering also access to standard input and output for these programs.

`TProcess` does not handle wildcard expansion, does not support complex pipelines as in Unix. If this behaviour is desired, the shell can be executed with the pipeline as the command it should execute.

### 24.3 Constants, types and variables

#### 24.3.1 Types

```
TProcessOption = (poRunSuspended, poWaitOnExit, poUsePipes,  
                  poStderrToOutPut, poNoConsole, poNewConsole,  
                  poDefaultErrorMode, poNewProcessGroup, poDebugProcess,  
                  poDebugOnlyThisProcess)
```

When a new process is started using `TProcess.Execute` ([488](#)), these options control the way the process is started. Note that not all options are supported on all platforms.

```
TProcessOptions= Set of (poDebugOnlyThisProcess, poDebugProcess,  
                          poDefaultErrorMode, poNewConsole,
```

Table 24.2: Enumeration values for type TProcessOption

Value	Explanation
poDebugOnlyThisProcess	Do not follow processes started by this process (Win32 only)
poDebugProcess	Allow debugging of the process (Win32 only)
poDefaultErrorMode	Use default error handling.
poNewConsole	Start a new console window for the process (Win32 only)
poNewProcessGroup	Start the process in a new process group (Win32 only)
poNoConsole	Do not allow access to the console window for the process (Win32 only)
poRunSuspended	Start the process in suspended state.
poStderrToOutPut	Redirect standard error to the standard output stream.
poUsePipes	Use pipes to redirect standard input and output.
poWaitOnExit	Wait for the process to terminate before returning.

```
poNewProcessGroup, poNoConsole, poRunSuspended,
poStderrToOutPut, poUsePipes, poWaitOnExit)
```

Set of TProcessOption (484).

```
TProcessPriority = (ppHigh, ppIdle, ppNormal, ppRealTime)
```

Table 24.3: Enumeration values for type TProcessPriority

Value	Explanation
ppHigh	The process runs at higher than normal priority.
ppIdle	The process only runs when the system is idle (i.e. has nothing else to do)
ppNormal	The process runs at normal priority.
ppRealTime	The process runs at real-time priority.

This enumerated type determines the priority of the newly started process. It translates to default platform specific constants. If finer control is needed, then platform-dependent mechanism need to be used to set the priority.

```
TShowWindowOptions = (swoNone, swoHIDE, swoMaximize, swoMinimize,
swoRestore, swoShow, swoShowDefault,
swoShowMaximized, swoShowMinimized,
swoshowMinNOActive, swoShowNA, swoShowNoActivate,
swoShowNormal)
```

This type describes what the new process' main window should look like. Most of these have only effect on Windows. They are ignored on other systems.

```
TStartupOption = (suoUseShowWindow, suoUseSize, suoUsePosition,
suoUseCountChars, suoUseFillAttribute)
```

These options are mainly for Win32, and determine what should be done with the application once it's started.

Table 24.4: Enumeration values for type TShowWindowOptions

Value	Explanation
swoHIDE	The main window is hidden.
swoMaximize	The main window is maximized.
swoMinimize	The main window is minimized.
swoNone	Allow system to position the window.
swoRestore	Restore the previous position.
swoShow	Show the main window.
swoShowDefault	When showing Show the main window on
swoShowMaximized	The main window is shown maximized
swoShowMinimized	The main window is shown minimized
swoshowMinNOActive	The main window is shown minimized but not activated
swoShowNA	The main window is shown but not activated
swoShowNoActivate	The main window is shown but not activated
swoShowNormal	The main window is shown normally

Table 24.5: Enumeration values for type TStartupOption

Value	Explanation
suoUseCountChars	Use the console character width as specified in TProcess (486).
suoUseFillAttribute	Use the console fill attribute as specified in TProcess (486).
suoUsePosition	Use the window sizes as specified in TProcess (486).
suoUseShowWindow	Use the Show Window options specified in TShowWindowOption (485)
suoUseSize	Use the window sizes as specified in TProcess (486)

```
TStartupOptions= Set of (suoUseCountChars,suoUseFillAttribute,
                        suoUsePosition,suoUseShowWindow,suoUseSize)
```

Set of TStartUpOption (485).

## 24.4 EProcess

### 24.4.1 Description

Exception raised when an error occurs in a TProcess routine.

## 24.5 TProcess

### 24.5.1 Description

TProcess is a component that can be used to start and control other processes (programs/binaries). It contains a lot of options that control how the process is started. Many of these are Win32 specific, and have no effect on other platforms, so they should be used with care.

The simplest way to use this component is to create an instance, set the CommandLine (494) property to the full pathname of the program that should be executed, and call Execute (488). To determine whether the process is still running (i.e. has not stopped executing), the Running (498) property can be checked.



More advanced techniques can be used with the Options (496) settings.

### 24.5.2 Method overview

Page	Property	Description
489	CloseInput	Close the input stream of the process
489	CloseOutput	Close the output stream of the process
489	CloseStderr	Close the error stream of the process
488	Create	Create a new instance of the <code>TProcess</code> class.
488	Destroy	Destroy this instance of <code>TProcess</code>
488	Execute	Execute the program with the given options
489	Resume	Resume execution of a suspended process
490	Suspend	Suspend a running process
490	Terminate	Terminate a running process
490	WaitOnExit	Wait for the program to stop executing.

### 24.5.3 Property overview

Page	Property	Access	Description
494	Active	rw	Start or stop the process.
494	ApplicationName	rw	Name of the application to start
494	CommandLine	rw	Command-line to execute
495	ConsoleTitle	rw	Title of the console window
495	CurrentDirectory	rw	Working directory of the process.
495	Desktop	rw	Desktop on which to start the process.
496	Environment	rw	Environment variables for the new process
493	ExitStatus	r	Exit status of the process.
501	FillAttribute	rw	Color attributes of the characters in the console window (Windows only)
491	Handle	r	Handle of the process
494	InheritHandles	rw	Should the created process inherit the open handles of the current process.
492	Input	r	Stream connected to standard input of the process.
496	Options	rw	Options to be used when starting the process.
493	Output	r	Stream connected to standard output of the process.
497	Priority	rw	Priority at which the process is running.
491	ProcessHandle	r	Alias for Handle (491)
492	ProcessID	r	ID of the process.
498	Running	r	Determines wheter the process is still running.
498	ShowWindow	rw	Determines how the process main window is shown (Windows only)
497	StartupOptions	rw	Additional (Windows) startup options
493	Stderr	r	Stream connected to standard diagnostic output of the process.
491	ThreadHandle	r	Main process thread handle
492	ThreadID	r	ID of the main process thread
499	WindowColumns	rw	Number of columns in console window (windows only)
499	WindowHeight	rw	Height of the process main window
499	WindowLeft	rw	X-coordinate of the initial window (Windows only)
491	WindowRect	rw	Positions for the main program window.
500	WindowRows	rw	Number of rows in console window (Windows only)
500	WindowTop	rw	Y-coordinate of the initial window (Windows only)
500	WindowWidth	rw	Height of the process main window (Windows only)

### 24.5.4 TProcess.Create

Synopsis: Create a new instance of the `TProcess` class.

Declaration: `constructor Create(AOwner: TComponent); Override`

Visibility: `public`

Description: `Create` creates a new instance of the `TProcess` class. After calling the inherited constructor, it simply sets some default values.

### 24.5.5 TProcess.Destroy

Synopsis: Destroy this instance of `TProcess`

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` cleans up this instance of `TProcess`. Prior to calling the inherited destructor, it cleans up any streams that may have been created. If a process was started and is still executed, it is *not* stopped, but the standard input/output/stderr streams are no longer available, because they have been destroyed.

Errors: None.

See also: `TProcess.Create` (488)

### 24.5.6 TProcess.Execute

Synopsis: Execute the program with the given options

Declaration: `procedure Execute; Virtual`

Visibility: `public`

Description: `Execute` actually executes the program as specified in `CommandLine` (494), applying as much as of the specified options as supported on the current platform.

If the `poWaitOnExit` option is specified in `Options` (496), then the call will only return when the program has finished executing (or if an error occurred). If this option is not given, the call returns immediately, but the `WaitOnExit` (490) call can be used to wait for it to close, or the `Running` (498) call can be used to check whether it is still running.

The `TProcess.Terminate` (490) call can be used to terminate the program if it is still running, or the `Suspend` (490) call can be used to temporarily stop the program's execution.

The `ExitStatus` (493) function can be used to check the program's exit status, after it has stopped executing.

Errors: On error a `EProcess` (486) exception is raised.

See also: `TProcess.Running` (498), `TProcess.WaitOnExit` (490), `TProcess.Terminate` (490), `TProcess.Suspend` (490), `TProcess.Resume` (489), `TProcess.ExitStatus` (493)

### 24.5.7 TProcess.CloseInput

Synopsis: Close the input stream of the process

Declaration: `procedure CloseInput; Virtual`

Visibility: `public`

Description: `CloseInput` closes the input file descriptor of the process, that is, it closes the handle of the pipe to standard input of the process.

See also: `TProcess.Input` (492), `TProcess.StdErr` (493), `TProcess.Output` (493), `TProcess.CloseOutput` (489), `TProcess.CloseStdErr` (489)

### 24.5.8 TProcess.CloseOutput

Synopsis: Close the output stream of the process

Declaration: `procedure CloseOutput; Virtual`

Visibility: `public`

Description: `CloseOutput` closes the output file descriptor of the process, that is, it closes the handle of the pipe to standard output of the process.

See also: `TProcess.Output` (493), `TProcess.Input` (492), `TProcess.StdErr` (493), `TProcess.CloseInput` (489), `TProcess.CloseStdErr` (489)

### 24.5.9 TProcess.CloseStderr

Synopsis: Close the error stream of the process

Declaration: `procedure CloseStderr; Virtual`

Visibility: `public`

Description: `CloseStdErr` closes the standard error file descriptor of the process, that is, it closes the handle of the pipe to standard error output of the process.

See also: `TProcess.Output` (493), `TProcess.Input` (492), `TProcess.StdErr` (493), `TProcess.CloseInput` (489), `TProcess.CloseStdErr` (489)

### 24.5.10 TProcess.Resume

Synopsis: Resume execution of a suspended process

Declaration: `function Resume : Integer; Virtual`

Visibility: `public`

Description: `Resume` should be used to let a suspended process resume its execution. It should be called in particular when the `poRunSuspended` flag is set in `Options` (496).

Errors: None.

See also: `TProcess.Suspend` (490), `TProcess.Options` (496), `TProcess.Execute` (488), `TProcess.Terminate` (490)

### 24.5.11 TProcess.Suspend

Synopsis: Suspend a running process

Declaration: `function Suspend : Integer; Virtual`

Visibility: public

Description: `Suspend` suspends a running process. If the call is successful, the process is suspended: it stops running, but can be made to execute again using the `Resume` (489) call.

`Suspend` is fundamentally different from `TProcess.Terminate` (490) which actually stops the process.

Errors: On error, a nonzero result is returned.

See also: `TProcess.Options` (496), `TProcess.Resume` (489), `TProcess.Terminate` (490), `TProcess.Execute` (488)

### 24.5.12 TProcess.Terminate

Synopsis: Terminate a running process

Declaration: `function Terminate(AExitCode: Integer) : Boolean; Virtual`

Visibility: public

Description: `Terminate` stops the execution of the running program. It effectively stops the program.

On Windows, the program will report an exit code of `AExitCode`, on other systems, this value is ignored.

Errors: On error, a nonzero value is returned.

See also: `TProcess.ExitStatus` (493), `TProcess.Suspend` (490), `TProcess.Execute` (488), `TProcess.WaitOnExit` (490)

### 24.5.13 TProcess.WaitOnExit

Synopsis: Wait for the program to stop executing.

Declaration: `function WaitOnExit : Boolean`

Visibility: public

Description: `WaitOnExit` waits for the running program to exit. It returns `True` if the wait was successful, or `False` if there was some error waiting for the program to exit.

Note that the return value of this function has changed. The old return value was a `DWord` with a platform dependent error code. To make things consistent and cross-platform, a boolean return type was used.

Errors: On error, `False` is returned. No extended error information is available, as it is highly system dependent.

See also: `TProcess.ExitStatus` (493), `TProcess.Terminate` (490), `TProcess.Running` (498)

#### 24.5.14 TProcess.WindowRect

Synopsis: Positions for the main program window.

Declaration: `Property WindowRect : Trect`

Visibility: `public`

Access: `Read,Write`

Description: `WindowRect` can be used to specify the position of

#### 24.5.15 TProcess.Handle

Synopsis: Handle of the process

Declaration: `Property Handle : THandle`

Visibility: `public`

Access: `Read`

Description: `Handle` identifies the process. In Unix systems, this is the process ID. On windows, this is the process handle. It can be used to signal the process.

The handle is only valid after `TProcess.Execute` (488) has been called. It is not reset after the process stopped.

See also: `TProcess.ThreadHandle` (491), `TProcess.ProcessID` (492), `TProcess.ThreadID` (492)

#### 24.5.16 TProcess.ProcessHandle

Synopsis: Alias for `Handle` (491)

Declaration: `Property ProcessHandle : THandle`

Visibility: `public`

Access: `Read`

Description: `ProcessHandle` equals `Handle` (491) and is provided for completeness only.

See also: `TProcess.Handle` (491), `TProcess.ThreadHandle` (491), `TProcess.ProcessID` (492), `TProcess.ThreadID` (492)

#### 24.5.17 TProcess.ThreadHandle

Synopsis: Main process thread handle

Declaration: `Property ThreadHandle : THandle`

Visibility: `public`

Access: `Read`

Description: `ThreadHandle` is the main process thread handle. On Unix, this is the same as the process ID, on Windows, this may be a different handle than the process handle.

The handle is only valid after `TProcess.Execute` (488) has been called. It is not reset after the process stopped.

See also: `TProcess.Handle` (491), `TProcess.ProcessID` (492), `TProcess.ThreadID` (492)

### 24.5.18 TProcess.ProcessID

Synopsis: ID of the process.

Declaration: `Property ProcessID : Integer`

Visibility: `public`

Access: `Read`

Description: `ProcessID` is the ID of the process. It is the same as the handle of the process on Unix systems, but on Windows it is different from the process Handle.

The ID is only valid after `TProcess.Execute` (488) has been called. It is not reset after the process stopped.

See also: `TProcess.Handle` (491), `TProcess.ThreadHandle` (491), `TProcess.ThreadID` (492)

### 24.5.19 TProcess.ThreadID

Synopsis: ID of the main process thread

Declaration: `Property ThreadID : Integer`

Visibility: `public`

Access: `Read`

Description: `ProcessID` is the ID of the main process thread. It is the same as the handle of the main process thread (or the process itself) on Unix systems, but on Windows it is different from the thread Handle.

The ID is only valid after `TProcess.Execute` (488) has been called. It is not reset after the process stopped.

See also: `TProcess.ProcessID` (492), `TProcess.Handle` (491), `TProcess.ThreadHandle` (491)

### 24.5.20 TProcess.Input

Synopsis: Stream connected to standard input of the process.

Declaration: `Property Input : TOutputPipeStream`

Visibility: `public`

Access: `Read`

Description: `Input` is a stream which is connected to the process' standard input file handle. Anything written to this stream can be read by the process.

The `Input` stream is only instantiated when the `poUsePipes` flag is used in `Options` (496).

Note that writing to the stream may cause the calling process to be suspended when the created process is not reading from it's input, or to cause errors when the process has terminated.

See also: `TProcess.OutPut` (493), `TProcess.StdErr` (493), `TProcess.Options` (496), `TProcessOption` (484)

### 24.5.21 TProcess.Output

Synopsis: Stream connected to standard output of the process.

Declaration: `Property Output : TInputPipeStream`

Visibility: `public`

Access: `Read`

Description: `Output` is a stream which is connected to the process' standard output file handle. Anything written to standard output by the created process can be read from this stream.

The `Output` stream is only instantiated when the `poUsePipes` flag is used in `Options` (496).

The `Output` stream also contains any data written to standard diagnostic output (`stderr`) when the `poStdErrToOutPut` flag is used in `Options` (496).

Note that reading from the stream may cause the calling process to be suspended when the created process is not writing anything to standard output, or to cause errors when the process has terminated.

See also: `TProcess.InPut` (492), `TProcess.StdErr` (493), `TProcess.Options` (496), `TProcessOption` (484)

### 24.5.22 TProcess.Stderr

Synopsis: Stream connected to standard diagnostic output of the process.

Declaration: `Property Stderr : TInputPipeStream`

Visibility: `public`

Access: `Read`

Description: `StdErr` is a stream which is connected to the process' standard diagnostic output file handle (`StdErr`). Anything written to standard diagnostic output by the created process can be read from this stream.

The `StdErr` stream is only instantiated when the `poUsePipes` flag is used in `Options` (496).

The `Output` stream equals the `Output` (493) when the `poStdErrToOutPut` flag is used in `Options` (496).

Note that reading from the stream may cause the calling process to be suspended when the created process is not writing anything to standard output, or to cause errors when the process has terminated.

See also: `TProcess.InPut` (492), `TProcess.Output` (493), `TProcess.Options` (496), `TProcessOption` (484)

### 24.5.23 TProcess.ExitStatus

Synopsis: Exit status of the process.

Declaration: `Property ExitStatus : Integer`

Visibility: `public`

Access: `Read`

Description: `ExitStatus` contains the exit status as reported by the process when it stopped executing. The value of this property is only meaningful when the process is no longer running. If it is not running then the value is zero.

See also: `TProcess.Running` (498), `TProcess.Terminate` (490)

#### 24.5.24 TProcess.InheritHandles

Synopsis: Should the created process inherit the open handles of the current process.

Declaration: `Property InheritHandles : Boolean`

Visibility: `public`

Access: `Read,Write`

Description: `InheritHandles` determines whether the created process inherits the open handles of the current process (value `True`) or not (`False`).

On Unix, setting this variable has no effect.

See also: `TProcess.InPut` ([492](#)), `TProcess.Output` ([493](#)), `TProcess.StdErr` ([493](#))

#### 24.5.25 TProcess.Active

Synopsis: Start or stop the process.

Declaration: `Property Active : Boolean`

Visibility: `published`

Access: `Read,Write`

Description: `Active` starts the process if it is set to `True`, or terminates the process if set to `False`. It's mostly intended for use in an IDE.

See also: `TProcess.Execute` ([488](#)), `TProcess.Terminate` ([490](#))

#### 24.5.26 TProcess.ApplicationName

Synopsis: Name of the application to start

Declaration: `Property ApplicationName : String`

Visibility: `published`

Access: `Read,Write`

Description: `ApplicationName` is an alias for `TProcess.CommandLine` ([494](#)). It's mostly for use in the Windows `CreateProcess` call. If `CommandLine` is not set, then `ApplicationName` will be used instead.

Note that either `CommandLine` or `ApplicationName` must be set prior to calling `Execute`.

See also: `TProcess.CommandLine` ([494](#))

#### 24.5.27 TProcess.CommandLine

Synopsis: Command-line to execute

Declaration: `Property CommandLine : String`

Visibility: `published`

Access: `Read,Write`



**Description:** `CommandLine` is the command-line to be executed: this is the name of the program to be executed, followed by any options it should be passed.

If the command to be executed or any of the arguments contains whitespace (space, tab character, linefeed character) it should be enclosed in single or double quotes.

If no absolute pathname is given for the command to be executed, it is searched for in the `PATH` environment variable. On Windows, the current directory always will be searched first. On other platforms, this is not so.

Note that either `CommandLine` or `ApplicationName` must be set prior to calling `Execute`.

See also: `TProcess.ApplicationName` ([494](#))

### 24.5.28 TProcess.ConsoleTitle

**Synopsis:** Title of the console window

**Declaration:** `Property ConsoleTitle : String`

**Visibility:** published

**Access:** Read,Write

**Description:** `ConsoleTitle` is used on Windows when executing a console application: it specifies the title caption of the console window. On other platforms, this property is currently ignored.

Changing this property after the process was started has no effect.

See also: `TProcess.WindowColumns` ([499](#)), `TProcess.WindowRows` ([500](#))

### 24.5.29 TProcess.CurrentDirectory

**Synopsis:** Working directory of the process.

**Declaration:** `Property CurrentDirectory : String`

**Visibility:** published

**Access:** Read,Write

**Description:** `CurrentDirectory` specifies the working directory of the newly started process.

Changing this property after the process was started has no effect.

See also: `TProcess.Environment` ([496](#))

### 24.5.30 TProcess.Desktop

**Synopsis:** Desktop on which to start the process.

**Declaration:** `Property Desktop : String`

**Visibility:** published

**Access:** Read,Write

**Description:** `Desktop` is used on Windows to determine on which desktop the process' main window should be shown. Leaving this empty means the process is started on the same desktop as the currently running process.

Changing this property after the process was started has no effect.

On unix, this parameter is ignored.

See also: [TProcess.Input \(492\)](#), [TProcess.Output \(493\)](#), [TProcess.StdErr \(493\)](#)

### 24.5.31 TProcess.Environment

Synopsis: Environment variables for the new process

Declaration: `Property Environment : TStrings`

Visibility: published

Access: Read,Write

Description: `Environment` contains the environment for the new process; it's a list of `Name=Value` pairs, one per line.

If it is empty, the environment of the current process is passed on to the new process.

See also: [TProcess.Options \(496\)](#)

### 24.5.32 TProcess.Options

Synopsis: Options to be used when starting the process.

Declaration: `Property Options : TProcessOptions`

Visibility: published

Access: Read,Write

Description: `Options` determine how the process is started. They should be set before the [Execute \(488\)](#) call is made.

Table 24.6:

Option	Meaning
<code>poRunSuspended</code>	Start the process in suspended state.
<code>poWaitOnExit</code>	Wait for the process to terminate before returning.
<code>poUsePipes</code>	Use pipes to redirect standard input and output.
<code>poStderrToOutPut</code>	Redirect standard error to the standard output stream.
<code>poNoConsole</code>	Do not allow access to the console window for the process (Win32 only)
<code>poNewConsole</code>	Start a new console window for the process (Win32 only)
<code>poDefaultErrorMode</code>	Use default error handling.
<code>poNewProcessGroup</code>	Start the process in a new process group (Win32 only)
<code>poDebugProcess</code>	Allow debugging of the process (Win32 only)
<code>poDebugOnlyThisProcess</code>	Do not follow processes started by this process (Win32 only)

See also: [TProcessOption \(484\)](#), [TProcessOptions \(485\)](#), [TProcess.Priority \(497\)](#), [TProcess.StartUpOptions \(497\)](#)

### 24.5.33 TProcess.Priority

Synopsis: Priority at which the process is running.

Declaration: `Property Priority : TProcessPriority`

Visibility: published

Access: Read,Write

Description: `Priority` determines the priority at which the process is running.

Table 24.7:

Priority	Meaning
<code>ppHigh</code>	The process runs at higher than normal priority.
<code>ppIdle</code>	The process only runs when the system is idle (i.e. has nothing else to do)
<code>ppNormal</code>	The process runs at normal priority.
<code>ppRealTime</code>	The process runs at real-time priority.

Note that not all priorities can be set by any user. Usually, only users with administrative rights (the root user on Unix) can set a higher process priority.

On unix, the process priority is mapped on `Nice` values as follows:

Table 24.8:

Priority	Nice value
<code>ppHigh</code>	20
<code>ppIdle</code>	20
<code>ppNormal</code>	0
<code>ppRealTime</code>	-20

See also: `TProcessPriority` ([485](#))

### 24.5.34 TProcess.StartupOptions

Synopsis: Additional (Windows) startup options

Declaration: `Property StartupOptions : TStartupOptions`

Visibility: published

Access: Read,Write

Description: `StartupOptions` contains additional startup options, used mostly on Windows system. They determine which other window layout properties are taken into account when starting the new process.

See also: `TProcess.ShowWindow` ([498](#)), `TProcess.WindowHeight` ([499](#)), `TProcess.WindowWidth` ([500](#)), `TProcess.WindowLeft` ([499](#)), `TProcess.WindowTop` ([500](#)), `TProcess.WindowColumns` ([499](#)), `TProcess.WindowRows` ([500](#)), `TProcess.FillAttribute` ([501](#))

Table 24.9:

Priority	Meaning
<code>suoUseShowWindow</code>	Use the Show Window options specified in <code>ShowWindow</code> (498)
<code>suoUseSize</code>	Use the specified window sizes
<code>suoUsePosition</code>	Use the specified window sizes.
<code>suoUseCountChars</code>	Use the specified console character width.
<code>suoUseFillAttribute</code>	Use the console fill attribute specified in <code>FillAttribute</code> (501).

### 24.5.35 TProcess.Running

**Synopsis:** Determines wheter the process is still running.

**Declaration:** `Property Running : Boolean`

**Visibility:** published

**Access:** Read

**Description:** `Running` can be read to determine whether the process is still running.

**See also:** `TProcess.Terminate` (490), `TProcess.Active` (494), `TProcess.ExitStatus` (493)

### 24.5.36 TProcess.ShowWindow

**Synopsis:** Determines how the process main window is shown (Windows only)

**Declaration:** `Property ShowWindow : TShowWindowOptions`

**Visibility:** published

**Access:** Read,Write

**Description:** `ShowWindow` determines how the process' main window is shown. It is useful only on Windows.

Table 24.10:

Option	Meaning
<code>swoNone</code>	Allow system to position the window.
<code>swoHIDE</code>	The main window is hidden.
<code>swoMaximize</code>	The main window is maximized.
<code>swoMinimize</code>	The main window is minimized.
<code>swoRestore</code>	Restore the previous position.
<code>swoShow</code>	Show the main window.
<code>swoShowDefault</code>	When showing Show the main window on a default position
<code>swoShowMaximized</code>	The main window is shown maximized
<code>swoShowMinimized</code>	The main window is shown minimized
<code>swoshowMinNOActive</code>	The main window is shown minimized but not activated
<code>swoShowNA</code>	The main window is shown but not activated
<code>swoShowNoActivate</code>	The main window is shown but not activated
<code>swoShowNormal</code>	The main window is shown normally

### 24.5.37 TProcess.WindowColumns

Synopsis: Number of columns in console window (windows only)

Declaration: `Property WindowColumns : Cardinal`

Visibility: published

Access: Read,Write

Description: `WindowColumns` is the number of columns in the console window, used to run the command in. This property is only effective if `suoUseCountChars` is specified in `StartupOptions` (497)

See also: `TProcess.WindowHeight` (499), `TProcess.WindowWidth` (500), `TProcess.WindowLeft` (499), `TProcess.WindowTop` (500), `TProcess.WindowRows` (500), `TProcess.FillAttribute` (501), `TProcess.StartupOptions` (497)

### 24.5.38 TProcess.WindowHeight

Synopsis: Height of the process main window

Declaration: `Property WindowHeight : Cardinal`

Visibility: published

Access: Read,Write

Description: `WindowHeight` is the initial height (in pixels) of the process' main window. This property is only effective if `suoUseSize` is specified in `StartupOptions` (497)

See also: `TProcess.WindowWidth` (500), `TProcess.WindowLeft` (499), `TProcess.WindowTop` (500), `TProcess.WindowColumns` (499), `TProcess.WindowRows` (500), `TProcess.FillAttribute` (501), `TProcess.StartupOptions` (497)

### 24.5.39 TProcess.WindowLeft

Synopsis: X-coordinate of the initial window (Windows only)

Declaration: `Property WindowLeft : Cardinal`

Visibility: published

Access: Read,Write

Description: `WindowLeft` is the initial X coordinate (in pixels) of the process' main window, relative to the left border of the desktop. This property is only effective if `suoUsePosition` is specified in `StartupOptions` (497)

See also: `TProcess.WindowHeight` (499), `TProcess.WindowWidth` (500), `TProcess.WindowTop` (500), `TProcess.WindowColumns` (499), `TProcess.WindowRows` (500), `TProcess.FillAttribute` (501), `TProcess.StartupOptions` (497)

### 24.5.40 TProcess.WindowRows

Synopsis: Number of rows in console window (Windows only)

Declaration: `Property WindowRows : Cardinal`

Visibility: published

Access: Read,Write

Description: `WindowRows` is the number of rows in the console window, used to run the command in. This property is only effective if `suoUseCountChars` is specified in `StartupOptions` (497)

See also: `TProcess.WindowHeight` (499), `TProcess.WindowWidth` (500), `TProcess.WindowLeft` (499), `TProcess.WindowTop` (500), `TProcess.WindowColumns` (499), `TProcess.FillAttribute` (501), `TProcess.StartupOptions` (497)

### 24.5.41 TProcess.WindowTop

Synopsis: Y-coordinate of the initial window (Windows only)

Declaration: `Property WindowTop : Cardinal`

Visibility: published

Access: Read,Write

Description: `WindowTop` is the initial Y coordinate (in pixels) of the process' main window, relative to the top border of the desktop. This property is only effective if `suoUsePosition` is specified in `StartupOptions` (497)

See also: `TProcess.WindowHeight` (499), `TProcess.WindowWidth` (500), `TProcess.WindowLeft` (499), `TProcess.WindowColumns` (499), `TProcess.WindowRows` (500), `TProcess.FillAttribute` (501), `TProcess.StartupOptions` (497)

### 24.5.42 TProcess.WindowWidth

Synopsis: Height of the process main window (Windows only)

Declaration: `Property WindowWidth : Cardinal`

Visibility: published

Access: Read,Write

Description: `WindowWidth` is the initial width (in pixels) of the process' main window. This property is only effective if `suoUseSize` is specified in `StartupOptions` (497)

See also: `TProcess.WindowHeight` (499), `TProcess.WindowLeft` (499), `TProcess.WindowTop` (500), `TProcess.WindowColumns` (499), `TProcess.WindowRows` (500), `TProcess.FillAttribute` (501), `TProcess.StartupOptions` (497)

### 24.5.43 TProcess.FillAttribute

Synopsis: Color attributes of the characters in the console window (Windows only)

Declaration: `Property FillAttribute : Cardinal`

Visibility: `published`

Access: `Read, Write`

Description: `FillAttribute` is a `WORD` value which specifies the background and foreground colors of the console window.

See also: `TProcess.WindowHeight` ([499](#)), `TProcess.WindowWidth` ([500](#)), `TProcess.WindowLeft` ([499](#)), `TProcess.WindowTop` ([500](#)), `TProcess.WindowColumns` ([499](#)), `TProcess.WindowRows` ([500](#)), `TProcess.StartupOptions` ([497](#))

## Chapter 25

# Reference for unit 'rttiutils'

### 25.1 Used units

Table 25.1: Used units by unit 'rttiutils'

Name	Page
Classes	??
StrUtils	<a href="#">502</a>
sysutils	??
typinfo	??

### 25.2 Overview

The `rttiutils` unit is a unit providing simplified access to the RTTI information from published properties using the `TPropInfoList` ([504](#)) class. This access can be used when saving or restoring form properties at runtime, or for persisting other objects whose RTTI is available: the `TPropsStorage` ([507](#)) class can be used for this. The implementation is based on the `apputils` unit from `RXLib` by *AO ROSNO* and *Master-Bank*

### 25.3 Constants, types and variables

#### 25.3.1 Constants

```
sPropNameDelimiter : String = '_'
```

Separator used when constructing section/key names

#### 25.3.2 Types

```
TEraseSectEvent = procedure(const ASection: String) of object
```



`TEraseSectEvent` is used by `TPropsStorage` (507) to clear a storage section, in a .ini file like fashion: The call should remove all keys in the section `ASection`, and remove the section from storage.

```
TFindComponentEvent = function(const Name: String) : TComponent
```

`TFindComponentEvent` should return the component instance for the component with name path `Name`. The name path should be relative to the global list of loaded components.

```
TReadStrEvent = function(const ASection: String;const Item: String;
                        const Default: String) : String of object
```

`TReadStrEvent` is used by `TPropsStorage` (507) to read strings from a storage mechanism, in a .ini file like fashion: The call should read the string in `ASection` with key `Item`, and if it does not exist, `Default` should be returned.

```
TWriteStrEvent = procedure(const ASection: String;const Item: String;
                          const Value: String) of object
```

`TWriteStrEvent` is used by `TPropsStorage` (507) to write strings to a storage mechanism, in a .ini file like fashion: The call should write the string `Value` in `ASection` with key `Item`. The section and key should be created if they didn't exist yet.

### 25.3.3 Variables

```
FindGlobalComponentCallBack : TFindComponentEvent
```

`FindGlobalComponentCallBack` is called by `UpdateStoredList` (504) whenever it needs to resolve component references. It should be set to a routine that locates a loaded component in the global list of loaded components.

## 25.4 Procedures and functions

### 25.4.1 CreateStoredItem

**Synopsis:** Concatenates component and property name

**Declaration:** `function CreateStoredItem(const CompName: String;const PropName: String) : String`

**Visibility:** default

**Description:** `CreateStoredItem` concatenates `CompName` and `PropName` if they are both empty. The names are separated by a dot (.) character. If either of the names is empty, an empty string is returned.

This function can be used to create items for the list of properties such as used in `UpdateStoredList` (504), `TPropsStorage.StoreObjectsProps` (509) or `TPropsStorage.LoadObjectsProps` (508).

**See also:** `ParseStoredItem` (504), `UpdateStoredList` (504), `TPropsStorage.StoreObjectsProps` (509), `TPropsStorage.LoadObjectsProps` (508)

### 25.4.2 ParseStoredItem

Synopsis: Split a property reference to component reference and property name

Declaration: `function ParseStoredItem(const Item: String; var CompName: String;  
var PropName: String) : Boolean`

Visibility: default

Description: `ParseStoredItem` parses the property reference `Item` and splits it in a reference to a component (returned in `CompName`) and a name of a property (returned in `PropName`). This function basically does the opposite of `CreateStoredItem` (503). Note that both names should be non-empty, i.e., at least 1 dot character must appear in `Item`.

Errors: If an error occurred during parsing, `False` is returned.

See also: `CreateStoredItem` (503), `UpdateStoredList` (504), `TPropsStorage.StoreObjectsProps` (509), `TPropsStorage.LoadObjectsProps` (508)

### 25.4.3 UpdateStoredList

Synopsis: Update a stringlist with object references

Declaration: `procedure UpdateStoredList (AComponent: TComponent; AStoredList: TStrings;  
FromForm: Boolean)`

Visibility: default

Description: `UpdateStoredList` will parse the strings in `AStoredList` using `ParseStoredItem` (504) and will replace the `Objects` properties with the instance of the object whose name each property path in the list refers to. If `FromForm` is `True`, then all instances are searched relative to `AComponent`, i.e. they must be owned by `AComponent`. If `FromForm` is `False` the instances are searched in the global list of streamed components. (the `FindGlobalComponentCallBack` (503) callback must be set for the search to work correctly in this case)

If a component cannot be found, the reference string to the property is removed from the stringlist.

Errors: If `AComponent` is `Nil`, an exception may be raised.

See also: `ParseStoredItem` (504), `TPropsStorage.StoreObjectsProps` (509), `TPropsStorage.LoadObjectsProps` (508), `FindGlobalComponentCallBack` (503)

## 25.5 TPropInfoList

### 25.5.1 Description

`TPropInfoList` is a class which can be used to maintain a list with information about published properties of a class (or an instance). It is used internally by `TPropsStorage` (507)

### 25.5.2 Method overview

Page	Property	Description
505	Contains	Check whether a certain property is included
505	Create	Create a new instance of <code>TPropInfoList</code>
506	Delete	Delete property information from the list
505	Destroy	Remove the <code>TPropInfoList</code> instance from memory
505	Find	Retrieve property information based on name
506	Intersect	Intersect 2 property lists

### 25.5.3 Property overview

Page	Property	Access	Description
<a href="#">506</a>	Count	r	Number of items in the list
<a href="#">506</a>	Items	r	Indexed access to the property type pointers

### 25.5.4 TPropInfoList.Create

Synopsis: Create a new instance of `TPropInfoList`

Declaration: `constructor Create(AObject: TObject; Filter: TTypeKinds)`

Visibility: `public`

Description: `Create` allocates and initializes a new instance of `TPropInfoList` on the heap. It retrieves a list of published properties from `AObject`: if `Filter` is empty, then all properties are retrieved. If it is not empty, then only properties of the kind specified in the set are retrieved. Instance should not be `Nil`

See also: `TPropInfoList.Destroy` ([505](#))

### 25.5.5 TPropInfoList.Destroy

Synopsis: Remove the `TPropInfoList` instance from memory

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` cleans up the internal structures maintained by `TPropInfoList` and then calls the inherited `Destroy`.

See also: `TPropInfoList.Create` ([505](#))

### 25.5.6 TPropInfoList.Contains

Synopsis: Check whether a certain property is included

Declaration: `function Contains(P: PPropInfo) : Boolean`

Visibility: `public`

Description: `Contains` checks whether `P` is included in the list of properties, and returns `True` if it does. If `P` cannot be found, `False` is returned.

See also: `TPropInfoList.Find` ([505](#)), `TPropInfoList.Intersect` ([506](#))

### 25.5.7 TPropInfoList.Find

Synopsis: Retrieve property information based on name

Declaration: `function Find(const AName: String) : PPropInfo`

Visibility: `public`

Description: `Find` returns a pointer to the type information of the property `AName`. If no such information is available, the function returns `Nil`. The search is performed case insensitive.

See also: `TPropInfoList.Intersect` ([506](#)), `TPropInfoList.Contains` ([505](#))

### 25.5.8 TPropInfoList.Delete

Synopsis: Delete property information from the list

Declaration: `procedure Delete(Index: Integer)`

Visibility: `public`

Description: `Delete` deletes the property information at position `Index` from the list. It's mainly of use in the `Intersect` (506) call.

Errors: No checking on the validity of `Index` is performed.

See also: `TPropInfoList.Intersect` (506)

### 25.5.9 TPropInfoList.Intersect

Synopsis: Intersect 2 property lists

Declaration: `procedure Intersect(List: TPropInfoList)`

Visibility: `public`

Description: `Intersect` reduces the list of properties to the ones also contained in `List`, i.e. all properties which are not also present in `List` are removed.

See also: `TPropInfoList.Delete` (506), `TPropInfoList.Contains` (505)

### 25.5.10 TPropInfoList.Count

Synopsis: Number of items in the list

Declaration: `Property Count : Integer`

Visibility: `public`

Access: `Read`

Description: `Count` is the number of property type pointers in the list.

See also: `TPropInfoList.Items` (506)

### 25.5.11 TPropInfoList.Items

Synopsis: Indexed access to the property type pointers

Declaration: `Property Items[Index: Integer]: PPropInfo; default`

Visibility: `public`

Access: `Read`

Description: `Items` provides access to the property type pointers stored in the list. `Index` runs from 0 to `Count-1`.

See also: `TPropInfoList.Count` (506)

## 25.6 TPropsStorage

### 25.6.1 Description

TPropsStorage provides a mechanism to store properties from any class which has published properties (usually a TPersistent descendent) in a storage mechanism.

TPropsStorage does not handle the storage by itself, instead, the storage is handled through a series of callbacks to read and/or write strings. Conversion of property types to string is handled by TPropsStorage itself: all that needs to be done is set the 3 handlers. The storage mechanism is assumed to have the structure of an .ini file : sections with key/value pairs. The three callbacks should take this into account, but they do not need to create an actual .ini file.

### 25.6.2 Method overview

Page	Property	Description
<a href="#">507</a>	LoadAnyProperty	Load a property value
<a href="#">508</a>	LoadObjectsProps	Load a list of component properties
<a href="#">508</a>	LoadProperties	Load a list of properties
<a href="#">507</a>	StoreAnyProperty	Store a property value
<a href="#">509</a>	StoreObjectsProps	Store a list of component properties
<a href="#">508</a>	StoreProperties	Store a list of properties

### 25.6.3 Property overview

Page	Property	Access	Description
<a href="#">510</a>	AObject	rw	Object to load or store properties from
<a href="#">511</a>	OnEraseSection	rw	Erase a section in storage
<a href="#">510</a>	OnReadString	rw	Read a string value from storage
<a href="#">511</a>	OnWriteString	rw	Write a string value to storage
<a href="#">510</a>	Prefix	rw	Prefix to use in storage
<a href="#">510</a>	Section	rw	Section name for storage

### 25.6.4 TPropsStorage.StoreAnyProperty

Synopsis: Store a property value

Declaration: `procedure StoreAnyProperty (PropInfo: PPropInfo)`

Visibility: public

Description: `StoreAnyProperty` stores the property with information specified in `PropInfo` in the storage mechanism. The property value is retrieved from the object instance specified in the `AObject` ([510](#)) property of `TPropsStorage`.

Errors: If the property pointer is invalid or `AObject` is invalid, an exception will be raised.

See also: `TPropsStorage.AObject` ([510](#)), `TPropsStorage.LoadAnyProperty` ([507](#)), `TPropsStorage.LoadProperties` ([508](#)), `TPropsStorage.StoreProperties` ([508](#))

### 25.6.5 TPropsStorage.LoadAnyProperty

Synopsis: Load a property value

Declaration: `procedure LoadAnyProperty (PropInfo: PPropInfo)`

Visibility: public

**Description:** `LoadAnyProperty` loads the property with information specified in `PropInfo` from the storage mechanism. The value is then applied to the object instance specified in the `AObject` (510) property of `TPropsStorage`.

**Errors:** If the property pointer is invalid or `AObject` is invalid, an exception will be raised.

**See also:** `TPropsStorage.AObject` (510), `TPropsStorage.StoreAnyProperty` (507), `TPropsStorage.LoadProperties` (508), `TPropsStorage.StoreProperties` (508)

### 25.6.6 TPropsStorage.StoreProperties

**Synopsis:** Store a list of properties

**Declaration:** `procedure StoreProperties(PropList: TStrings)`

Visibility: public

**Description:** `StoreProperties` stores the values of all properties in `PropList` in the storage mechanism. The list should contain names of published properties of the `AObject` (510) object.

**Errors:** If an invalid property name is specified, an exception will be raised.

**See also:** `TPropsStorage.AObject` (510), `TPropsStorage.StoreAnyProperty` (507), `TPropsStorage.LoadProperties` (508), `TPropsStorage.LoadAnyProperty` (507)

### 25.6.7 TPropsStorage.LoadProperties

**Synopsis:** Load a list of properties

**Declaration:** `procedure LoadProperties(PropList: TStrings)`

Visibility: public

**Description:** `LoadProperties` loads the values of all properties in `PropList` from the storage mechanism. The list should contain names of published properties of the `AObject` (510) object.

**Errors:** If an invalid property name is specified, an exception will be raised.

**See also:** `TPropsStorage.AObject` (510), `TPropsStorage.StoreAnyProperty` (507), `TPropsStorage.StoreProperties` (508), `TPropsStorage.LoadAnyProperty` (507)

### 25.6.8 TPropsStorage.LoadObjectsProps

**Synopsis:** Load a list of component properties

**Declaration:** `procedure LoadObjectsProps(AComponent: TComponent; StoredList: TStrings)`

Visibility: public

**Description:** `LoadObjectsProps` loads a list of component properties, relative to `AComponent`: the names of the component properties to load are specified as follows:

```
ComponentName1.PropertyName
ComponentName2.Subcomponent1.PropertyName
```

The component instances will be located relative to `AComponent`, and must therefore be names of components owned by `AComponent`, followed by a valid property of these components. If the `componentname` is missing, the property name will be assumed to be a property of `AComponent` itself.

The `Objects` property of the stringlist should be filled with the instances of the components the property references refer to: they can be filled with the `UpdateStoredList` (504) call.

For example, to load the checked state of a checkbox named 'CBCheckMe' and the caption of a button named 'BPressMe', both owned by a form, the following strings should be passed:

```
CBCheckMe.Checked
BPressMe.Caption
```

and the `AComponent` should be the form component that owns the button and checkbox.

Note that this call removes the value of the `AObject` (510) property.

**Errors:** If an invalid component is specified, an exception will be raised.

**See also:** `UpdateStoredList` (504), `TPropsStorage.StoreObjectsProps` (509), `TPropsStorage.LoadProperties` (508), `TPropsStorage.LoadAnyProperty` (507)

### 25.6.9 TPropsStorage.StoreObjectsProps

**Synopsis:** Store a list of component properties

**Declaration:** `procedure StoreObjectsProps(AComponent: TComponent; StoredList: TStrings)`

**Visibility:** public

**Description:** `StoreObjectsProps` stores a list of component properties, relative to `AComponent`: the names of the component properties to store are specified as follows:

```
ComponentName1.PropertyName
ComponentName2.Subcomponent1.PropertyName
```

The component instances will be located relative to `AComponent`, and must therefore be names of components owned by `AComponent`, followed by a valid property of these components. If the `componentname` is missing, the property name will be assumed to be a property of `AComponent` itself.

The `Objects` property of the stringlist should be filled with the instances of the components the property references refer to: they can be filled with the `UpdateStoredList` (504) call.

For example, to store the checked state of a checkbox named 'CBCheckMe' and the caption of a button named 'BPressMe', both owned by a form, the following strings should be passed:

```
CBCheckMe.Checked
BPressMe.Caption
```

and the `AComponent` should be the form component that owns the button and checkbox.

Note that this call removes the value of the `AObject` (510) property.

**See also:** `UpdateStoredList` (504), `TPropsStorage.LoadObjectsProps` (508), `TPropsStorage.LoadProperties` (508), `TPropsStorage.LoadAnyProperty` (507)

### 25.6.10 TPropsStorage.AObject

Synopsis: Object to load or store properties from

Declaration: `Property AObject : TObject`

Visibility: public

Access: Read,Write

Description: `AObject` is the object instance whose properties will be loaded or stored with any of the methods in the `TPropsStorage` class. Note that a call to `StoreObjectProps` (509) or `LoadObjectProps` (508) will destroy any value that this property might have.

See also: `TPropsStorage.LoadProperties` (508), `TPropsStorage.LoadAnyProperty` (507), `TPropsStorage.StoreProperties` (508), `TPropsStorage.StoreAnyProperty` (507), `TPropsStorage.StoreObjectsProps` (509), `TPropsStorage.LoadObjectsProps` (508)

### 25.6.11 TPropsStorage.Prefix

Synopsis: Prefix to use in storage

Declaration: `Property Prefix : String`

Visibility: public

Access: Read,Write

Description: `Prefix` is prepended to all property names to form the key name when writing a property to storage, or when reading a value from storage. This is useful when storing properties of multiple forms in a single section.

See also: `TPropsStorage.Section` (510)

### 25.6.12 TPropsStorage.Section

Synopsis: Section name for storage

Declaration: `Property Section : String`

Visibility: public

Access: Read,Write

Description: `Section` is used as the section name when writing values to storage. Note that when writing properties of subcomponents, their names will be appended to the value specified here.

See also: `TPropsStorage.Section` (510)

### 25.6.13 TPropsStorage.OnReadString

Synopsis: Read a string value from storage

Declaration: `Property OnReadString : TReadStrEvent`

Visibility: public

Access: Read,Write



**Description:** `OnReadString` is the event handler called whenever `TPropsStorage` needs to read a string from storage. It should be set whenever properties need to be loaded, or an exception will be raised.

See also: `TPropsStorage.OnWriteString` (511), `TPropsStorage.OnEraseSection` (511), `TReadStrEvent` (503)

#### 25.6.14 `TPropsStorage.OnWriteString`

**Synopsis:** Write a string value to storage

**Declaration:** `Property OnWriteString : TWriteStrEvent`

**Visibility:** public

**Access:** Read,Write

**Description:** `OnWriteString` is the event handler called whenever `TPropsStorage` needs to write a string to storage. It should be set whenever properties need to be stored, or an exception will be raised.

See also: `TPropsStorage.OnReadString` (510), `TPropsStorage.OnEraseSection` (511), `TWriteStrEvent` (503)

#### 25.6.15 `TPropsStorage.OnEraseSection`

**Synopsis:** Erase a section in storage

**Declaration:** `Property OnEraseSection : TEraseSectEvent`

**Visibility:** public

**Access:** Read,Write

**Description:** `OnEraseSection` is the event handler called whenever `TPropsStorage` needs to clear a complete storage section. It should be set whenever stringlist properties need to be stored, or an exception will be raised.

See also: `TPropsStorage.OnReadString` (510), `TPropsStorage.OnWriteString` (511), `TEraseSectEvent` (502)

## Chapter 26

# Reference for unit 'simpleipc'

### 26.1 Used units

Table 26.1: Used units by unit 'simpleipc'

Name	Page
Classes	??
sysutils	??

### 26.2 Overview

The SimpleIPC unit provides classes to implement a simple, one-way IPC mechanism using string messages. It provides a TSimpleIPCServer ([522](#)) component for the server, and a TSimpleIPCClient ([519](#)) component for the client. The components are cross-platform, and should work both on Windows and unix-like systems.

### 26.3 Constants, types and variables

#### 26.3.1 Resource strings

```
SErrActive = 'This operation is illegal when the server is active.'
```

Error message if client/server is active.

```
SErrInactive = 'This operation is illegal when the server is inactive.'
```

Error message if client/server is not active.

```
SErrServerNotActive = 'Server with ID %s is not active.'
```

Error message if server is not active

### 26.3.2 Constants

`MsgVersion = 1`

Current version of the messaging protocol

`mtString = 1`

String message type

`mtUnknown = 0`

Unknown message type

### 26.3.3 Types

`TIPCClientCommClass = Class of TIPCClientComm`

`TIPCClientCommClass` is used by `TSimpleIPCClient` (519) to decide which kind of communication channel to set up.

`TIPCServerCommClass = Class of TIPCServerComm`

`TIPCServerCommClass` is used by `TSimpleIPCServer` (522) to decide which kind of communication channel to set up.

`TMessageType = LongInt`

`TMessageType` is provided for backward compatibility with earlier versions of the `simpleipc` unit.

```
TMsgHeader = packed record
  Version : Byte;
  MsgType : TMessageType;
  MsgLen : Integer;
end
```

`TMsgHeader` is used internally by the IPC client and server components to transmit data. The `Version` field denotes the protocol version. The `MsgType` field denotes the type of data (`mtString` for string messages), and `MsgLen` is the length of the message which will follow.

### 26.3.4 Variables

`DefaultIPCClientClass : TIPCClientCommClass = nil`

`DefaultIPCClientClass` is filled with a class pointer indicating which kind of communication protocol class should be instantiated by the `TSimpleIPCClient` (519) class. It is set to a default value by the default implementation in the `SimpleIPC` unit, but can be set to another class if another method of transport is desired. (it should match the communication protocol used by the server, obviously).

`DefaultIPCServerClass : TIPCServerCommClass = nil`

`DefaultIPCServerClass` is filled with a class pointer indicating which kind of communication protocol class should be instantiated by the `TSimpleIPCServer` (522) class. It is set to a default value by the default implementation in the `SimpleIPC` unit, but can be set to another class if another method of transport is desired.

## 26.4 EIPCErrors

### 26.4.1 Description

`EIPCErrors` is the exception used by the various classes in the `SimpleIPC` unit to report errors.

## 26.5 TIPCCliantComm

### 26.5.1 Description

`TIPCCliantComm` is an abstract component which implements the client-side communication protocol. The behaviour expected of this class must be implemented in a platform-dependent descendent class.

The `TSimpleIPCCliant` (519) class does not implement the messaging protocol by itself. Instead, it creates an instance of a (platform dependent) descendent of `TIPCCliantComm` which handles the internals of the communication protocol.

The server side of the messaging protocol is handled by the `TIPCServerComm` (516) component. The descendent components must always be implemented in pairs.

### 26.5.2 Method overview

Page	Property	Description
514	Connect	Connect to the server
514	Create	Create a new instance of the <code>TIPCCliantComm</code>
515	Disconnect	Disconnect from the server
515	SendMessage	Send a message
515	ServerRunning	Check if the server is running.

### 26.5.3 Property overview

Page	Property	Access	Description
516	Owner	r	<code>TSimpleIPCCliant</code> instance for which communication must be handled.

### 26.5.4 TIPCCliantComm.Create

Synopsis: Create a new instance of the `TIPCCliantComm`

Declaration: `constructor Create(AOwner: TSimpleIPCCliant); Virtual`

Visibility: `public`

Description: `Create` instantiates a new instance of the `TIPCCliantComm` class, and stores the `AOwner` reference to the `TSimpleIPCCliant` (519) instance for which it will handle communication. It can be retrieved later using the `Owner` (516) property.

See also: `TIPCCliantComm.Owner` (516), `TSimpleIPCCliant` (519)

### 26.5.5 TIPCCliantComm.Connect

Synopsis: Connect to the server

**Declaration:** `procedure Connect; Virtual; Abstract`

**Visibility:** `public`

**Description:** `Connect` must establish a communication channel with the server. The server endpoint must be constructed from the `ServerID` (519) and `ServerInstance` (522) properties of the owning `TSimpleIPCClient` (519) instance.

`Connect` is called by the `TSimpleIPCClient.Connect` (520) call or when the `Active` (519) property is set to `True`

Messages can be sent only after `Connect` was called successfully.

**Errors:** If the connection setup fails, or the connection was already set up, then an exception may be raised.

See also: `TSimpleIPCClient.Connect` (520), `TSimpleIPC.Active` (519), `TIPCClientComm.Disconnect` (515)

### 26.5.6 TIPCClientComm.Disconnect

**Synopsis:** Disconnect from the server

**Declaration:** `procedure Disconnect; Virtual; Abstract`

**Visibility:** `public`

**Description:** `Disconnect` closes the communication channel with the server. Any calls to `SendMessage` are invalid after `Disconnect` was called.

`Disconnect` is called by the `TSimpleIPCClient.Disconnect` (521) call or when the `Active` (519) property is set to `False`.

Messages can no longer be sent after `Disconnect` was called.

**Errors:** If the connection shutdown fails, or the connection was already shut down, then an exception may be raised.

See also: `TSimpleIPCClient.Disconnect` (521), `TSimpleIPC.Active` (519), `TIPCClientComm.Connect` (514)

### 26.5.7 TIPCClientComm.ServerRunning

**Synopsis:** Check if the server is running.

**Declaration:** `function ServerRunning : Boolean; Virtual; Abstract`

**Visibility:** `public`

**Description:** `ServerRunning` returns `True` if the server endpoint of the communication channel can be found, or `False` if not. The server endpoint should be obtained from the `ServerID` and `InstanceID` properties of the owning `TSimpleIPCClient` (519) component.

See also: `TSimpleIPCClient.InstanceID` (519), `TSimpleIPCClient.ServerID` (519)

### 26.5.8 TIPCClientComm.SendMessage

**Synopsis:** Send a message

**Declaration:** `procedure SendMessage(MsgType: TMessageType; Stream: TStream); Virtual; Abstract`

**Visibility:** `public`

**Description:** `SendMessage` should deliver the message with type `MsgType` and data in `Stream` to the server. It should not return until the message was delivered.

**Errors:** If the delivery of the message fails, an exception will be raised.

### 26.5.9 TIPCCliantComm.Owner

**Synopsis:** `TSimpleIPCCliant` instance for which communication must be handled.

**Declaration:** `Property Owner : TSimpleIPCCliant`

**Visibility:** `public`

**Access:** `Read`

**Description:** `Owner` is the `TSimpleIPCCliant` (519) instance for which the communication must be handled. It cannot be changed, and must be specified when the `TIPCCliantComm` instance is created.

See also: `TSimpleIPCCliant` (519), `TIPCCliantComm.Create` (514)

## 26.6 TIPCTServerComm

### 26.6.1 Description

`TIPCTServerComm` is an abstract component which implements the server-side communication protocol. The behaviour expected of this class must be implemented in a platform-dependent descendent class.

The `TSimpleIPCServer` (522) class does not implement the messaging protocol by itself. Instead, it creates an instance of a (platform dependent) descendent of `TIPCTServerComm` which handles the internals of the communication protocol.

The client side of the messaging protocol is handled by the `TIPCCliantComm` (514) component. The descendent components must always be implemented in pairs.

### 26.6.2 Method overview

Page	Property	Description
516	<code>Create</code>	Create a new instance of the communication handler
517	<code>PeekMessage</code>	See if a message is available.
518	<code>ReadMessage</code>	Read message from the channel.
517	<code>StartServer</code>	Start the server-side of the communication channel
517	<code>StopServer</code>	Stop the server side of the communication channel.

### 26.6.3 Property overview

Page	Property	Access	Description
518	<code>InstanceID</code>	<code>r</code>	Unique identifier for the communication channel.
518	<code>Owner</code>	<code>r</code>	<code>TSimpleIPCServer</code> instance for which to handle transport

### 26.6.4 TIPCTServerComm.Create

**Synopsis:** Create a new instance of the communication handler

**Declaration:** `constructor Create(AOwner: TSimpleIPCServer); Virtual`

Visibility: public

Description: `Create` initializes a new instance of the communication handler. It simply saves the `AOwner` parameter in the `Owner` (518) property.

See also: `TIPCServerComm.Owner` (518)

### 26.6.5 `TIPCServerComm.StartServer`

Synopsis: Start the server-side of the communication channel

Declaration: `procedure StartServer; Virtual; Abstract`

Visibility: public

Description: `StartServer` sets up the server-side of the communication channel. After `StartServer` was called, a client can connect to the communication channel, and send messages to the server.

It is called when the `TSimpleIPC.Active` (519) property of the `TSimpleIPCServer` (522) instance is set to `True`.

Errors: In case of an error, an `EIPCError` (514) exception is raised.

See also: `TSimpleIPCServer` (522), `TSimpleIPC.Active` (519)

### 26.6.6 `TIPCServerComm.StopServer`

Synopsis: Stop the server side of the communication channel.

Declaration: `procedure StopServer; Virtual; Abstract`

Visibility: public

Description: `StartServer` closes down the server-side of the communication channel. After `StartServer` was called, a client can no longer connect to the communication channel, or even send messages to the server if it was previously connected (i.e. it will be disconnected).

It is called when the `TSimpleIPC.Active` (519) property of the `TSimpleIPCServer` (522) instance is set to `False`.

Errors: In case of an error, an `EIPCError` (514) exception is raised.

See also: `TSimpleIPCServer` (522), `TSimpleIPC.Active` (519)

### 26.6.7 `TIPCServerComm.PeekMessage`

Synopsis: See if a message is available.

Declaration: `function PeekMessage(TimeOut: Integer) : Boolean; Virtual; Abstract`

Visibility: public

Description: `PeekMessage` can be used to see if a message is available: it returns `True` if a message is available. It will wait maximum `TimeOut` milliseconds for a message to arrive. If no message was available after this time, it will return `False`.

If a message was available, it can be read with the `ReadMessage` (518) call.

See also: `TIPCServerComm.ReadMessage` (518)

### 26.6.8 TIPCTServerComm.ReadMessage

Synopsis: Read message from the channel.

Declaration: `procedure ReadMessage; Virtual; Abstract`

Visibility: `public`

Description: `ReadMessage` reads the message for the channel, and stores the information in the data structures in the `Owner` class.

`ReadMessage` is a blocking call: if no message is available, the program will wait till a message arrives. Use `PeekMessage` (517) to see if a message is available.

See also: `TSimpleIPCServer` (522)

### 26.6.9 TIPCTServerComm.Owner

Synopsis: `TSimpleIPCServer` instance for which to handle transport

Declaration: `Property Owner : TSimpleIPCServer`

Visibility: `public`

Access: `Read`

Description: `Owner` refers to the `TSimpleIPCServer` (522) instance for which this instance of `TSimpleIPCServer` handles the transport. It is specified when the `TIPCTServerComm` is created.

See also: `TSimpleIPCServer` (522)

### 26.6.10 TIPCTServerComm.InstanceID

Synopsis: Unique identifier for the communication channel.

Declaration: `Property InstanceID : String`

Visibility: `public`

Access: `Read`

Description: `InstanceID` returns a textual representation which uniquely identifies the communication channel on the server. The value is system dependent, and should be usable by the client-side to establish a communication channel with this instance.

## 26.7 TSimpleIPC

### 26.7.1 Description

`TSimpleIPC` is the common ancestor for the `TSimpleIPCServer` (522) and `TSimpleIPCClient` (519) classes. It implements some common properties between client and server.

### 26.7.2 Property overview

Page	Property	Access	Description
519	<code>Active</code>	<code>rw</code>	Communication channel active
519	<code>ServerID</code>	<code>rw</code>	Unique server identification



### 26.7.3 TSimpleIPC.Active

Synopsis: Communication channel active

Declaration: `Property Active : Boolean`

Visibility: published

Access: Read,Write

Description: `Active` can be set to `True` to set up the client or server end of the communication channel. For the server this means that the server end is set up, for the client it means that the client tries to connect to the server with `ServerID` (519) identification.

See also: `TSimpleIPC.ServerID` (519)

### 26.7.4 TSimpleIPC.ServerID

Synopsis: Unique server identification

Declaration: `Property ServerID : String`

Visibility: published

Access: Read,Write

Description: `ServerID` is the unique server identification: on the server, it determines how the server channel is set up, on the client it determines the server with which to connect.

See also: `TSimpleIPC.Active` (519)

## 26.8 TSimpleIPCClient

### 26.8.1 Description

`TSimpleIPCClient` is the client side of the simple IPC communication protocol. The client program should create a `TSimpleIPCClient` instance, set its `ServerID` (519) property to the unique name for the server it wants to send messages to, and then set the `Active` (519) property to `True` (or call `Connect` (519)).

After the connection with the server was established, messages can be sent to the server with the `SendMessage` (521) or `SendStringMessage` (521) calls.

### 26.8.2 Method overview

Page	Property	Description
520	<code>Connect</code>	Connect to the server
520	<code>Create</code>	Create a new instance of <code>TSimpleIPCClient</code>
520	<code>Destroy</code>	Remove the <code>TSimpleIPCClient</code> instance from memory
521	<code>Disconnect</code>	Disconnect from the server
521	<code>SendMessage</code>	Send a message to the server
521	<code>SendStringMessage</code>	Send a string message to the server
522	<code>SendStringMessageFmt</code>	Send a formatted string message
521	<code>ServerRunning</code>	Check if the server is running.

### 26.8.3 Property overview

Page	Property	Access	Description
<a href="#">522</a>	ServerInstance	rw	Server instance identification

### 26.8.4 TSimpleIPCClient.Create

Synopsis: Create a new instance of `TSimpleIPCClient`

Declaration: `constructor Create(AOwner: TComponent); Override`

Visibility: `public`

Description: `Create` instantiates a new instance of the `TSimpleIPCClient` class. It initializes the data structures needed to handle the client side of the communication.

See also: `TSimpleIPCClient.Destroy` ([520](#))

### 26.8.5 TSimpleIPCClient.Destroy

Synopsis: Remove the `TSimpleIPCClient` instance from memory

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` disconnects the client from the server if need be, and cleans up the internal data structures maintained by `TSimpleIPCClient` and then calls the inherited `Destroy`, which will remove the instance from memory.

Never call `Destroy` directly, use the `Free` method instead or the `FreeAndNil` procedure in `SysUtils`.

See also: `TSimpleIPCClient.Create` ([520](#))

### 26.8.6 TSimpleIPCClient.Connect

Synopsis: Connect to the server

Declaration: `procedure Connect`

Visibility: `public`

Description: `Connect` connects to the server indicated in the `ServerID` ([519](#)) and `InstanceID` ([519](#)) properties. `Connect` is called automatically if the `Active` ([519](#)) property is set to `True`.

After a successful call to `Connect`, messages can be sent to the server using `SendMessage` ([521](#)) or `SendStringMessage` ([521](#)).

Calling `Connect` if the connection is already open has no effect.

Errors: If creating the connection fails, an `EIPCErrors` ([514](#)) exception may be raised.

See also: `TSimpleIPC.ServerID` ([519](#)), `TSimpleIPCClient.InstanceID` ([519](#)), `TSimpleIPC.Active` ([519](#)), `TSimpleIPCClient.SendMessage` ([521](#)), `TSimpleIPCClient.SendStringMessage` ([521](#)), `TSimpleIPCClient.Disconnect` ([521](#))

### 26.8.7 TSimpleIPCClient.Disconnect

Synopsis: Disconnect from the server

Declaration: `procedure Disconnect`

Visibility: `public`

Description: `Disconnect` shuts down the connection with the server as previously set up with `Connect` (520). `Disconnect` is called automatically if the `Active` (519) property is set to `False`.

After a successful call to `Disconnect`, messages can no longer be sent to the server. Attempting to do so will result in an exception.

Calling `Disconnect` if there is no connection has no effect.

Errors: If creating the connection fails, an `EIPCErr` (514) exception may be raised.

See also: `TSimpleIPC.Active` (519), `TSimpleIPCClient.Connect` (520)

### 26.8.8 TSimpleIPCClient.ServerRunning

Synopsis: Check if the server is running.

Declaration: `function ServerRunning : Boolean`

Visibility: `public`

Description: `ServerRunning` verifies if the server indicated in the `ServerID` (519) and `InstanceID` (519) properties is running. It returns `True` if the server communication endpoint can be reached, `False` otherwise. This function can be called before a connection is made.

See also: `TSimpleIPCClient.Connect` (520)

### 26.8.9 TSimpleIPCClient.SendMessage

Synopsis: Send a message to the server

Declaration: `procedure SendMessage (MsgType: TMessageType; Stream: TStream)`

Visibility: `public`

Description: `SendMessage` sends a message of type `MsgType` and data from `stream` to the server. The client must be connected for this call to work.

Errors: In case an error occurs, or there is no connection to the server, an `EIPCErr` (514) exception is raised.

See also: `TSimpleIPCClient.Connect` (520), `TSimpleIPCClient.SendStringMessage` (521)

### 26.8.10 TSimpleIPCClient.SendStringMessage

Synopsis: Send a string message to the server

Declaration: `procedure SendStringMessage (const Msg: String)`  
`procedure SendStringMessage (MsgType: TMessageType; const Msg: String)`

Visibility: `public`

**Description:** `SendStringMessage` sends a string message with type `MsgTyp` and data `Msg` to the server. This is a convenience function: a small wrapper around the `SendMessage` (521) method

**Errors:** Same as for `SendMessage`.

**See also:** `TSimpleIPCClient.SendMessage` (521), `TSimpleIPCClient.Connect` (520), `TSimpleIPCClient.SendStringMessageFmt` (522)

### 26.8.11 TSimpleIPCClient.SendStringMessageFmt

**Synopsis:** Send a formatted string message

**Declaration:** `procedure SendStringMessageFmt(const Msg: String; Args: Array of const)`  
`procedure SendStringMessageFmt(MsgType: TMessageType; const Msg: String;`  
`Args: Array of const)`

**Visibility:** public

**Description:** `SendStringMessageFmt` sends a string message with type `MsgTyp` and message formatted from `Msg` and `Args` to the server. This is a convenience function: a small wrapper around the `SendStringMessage` (521) method

**Errors:** Same as for `SendMessage`.

**See also:** `TSimpleIPCClient.SendMessage` (521), `TSimpleIPCClient.Connect` (520), `TSimpleIPCClient.SendStringMessage` (521)

### 26.8.12 TSimpleIPCClient.ServerInstance

**Synopsis:** Server instance identification

**Declaration:** `Property ServerInstance : String`

**Visibility:** public

**Access:** Read, Write

**Description:** `ServerInstance` should be used in case a particular instance of the server identified with `ServerID` should be contacted. This must be used if the server has its `GLocal` (526) property set to `False`, and should match the server's `InstanceID` (525) property.

**See also:** `TSimpleIPC.ServerID` (519), `TSimpleIPCServer.Global` (526), `TSimpleIPCServer.InstanceID` (525)

## 26.9 TSimpleIPCServer

### 26.9.1 Description

`TSimpleIPCServer` is the server side of the simple IPC communication protocol. The server program should create a `TSimpleIPCServer` instance, set its `ServerID` (519) property to a unique name for the system, and then set the `Active` (519) property to `True` (or call `StartServer` (523)).

After the server was started, it can check for availability of messages with the `PeekMessage` (524) call, and read the message with `ReadMessage` (522).

### 26.9.2 Method overview

Page	Property	Description
<a href="#">523</a>	Create	Create a new instance of <code>TSimpleIPCServer</code>
<a href="#">523</a>	Destroy	Remove the <code>TSimpleIPCServer</code> instance from memory
<a href="#">524</a>	GetMessageData	Read the data of the last message in a stream
<a href="#">524</a>	PeekMessage	Check if a client message is available.
<a href="#">523</a>	StartServer	Start the server
<a href="#">524</a>	StopServer	Stop the server

### 26.9.3 Property overview

Page	Property	Access	Description
<a href="#">526</a>	Global	rw	Is the server reachable to all users or not
<a href="#">525</a>	InstanceID	r	Instance ID
<a href="#">525</a>	MsgData	r	Last message data
<a href="#">525</a>	MsgType	r	Last message type
<a href="#">526</a>	OnMessage	rw	Event triggered when a message arrives
<a href="#">525</a>	StringMessage	r	Last message as a string.

### 26.9.4 TSimpleIPCServer.Create

Synopsis: Create a new instance of `TSimpleIPCServer`

Declaration: `constructor Create(AOwner: TComponent); Override`

Visibility: `public`

Description: `Create` instantiates a new instance of the `TSimpleIPCServer` class. It initializes the data structures needed to handle the server side of the communication.

See also: `TSimpleIPCServer.Destroy` ([523](#))

### 26.9.5 TSimpleIPCServer.Destroy

Synopsis: Remove the `TSimpleIPCServer` instance from memory

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` stops the server, cleans up the internal data structures maintained by `TSimpleIPCServer` and then calls the inherited `Destroy`, which will remove the instance from memory.

Never call `Destroy` directly, use the `Free` method instead or the `FreeAndNil` procedure in `SysUtils`.

See also: `TSimpleIPCServer.Create` ([523](#))

### 26.9.6 TSimpleIPCServer.StartServer

Synopsis: Start the server

Declaration: `procedure StartServer`

Visibility: `public`

**Description:** `StartServer` starts the server side of the communication channel. It is called automatically when the `Active` property is set to `True`. It creates the internal communication object (a `TIPCServerComm` (516) descendent) and activates the communication channel.

After this method was called, clients can connect and send messages.

Prior to calling this method, the `ServerID` (519) property must be set.

**Errors:** If an error occurs a `EIPCErr` (514) exception may be raised.

**See also:** `TIPCServerComm` (516), `TSimpleIPC.Active` (519), `TSimpleIPC.ServerID` (519), `TSimpleIPCServer.StopServer` (524)

### 26.9.7 TSimpleIPCServer.StopServer

**Synopsis:** Stop the server

**Declaration:** `procedure StopServer`

**Visibility:** `public`

**Description:** `StopServer` stops the server side of the communication channel. It is called automatically when the `Active` property is set to `False`. It deactivates the communication channel and frees the internal communication object (a `TIPCServerComm` (516) descendent).

**See also:** `TIPCServerComm` (516), `TSimpleIPC.Active` (519), `TSimpleIPC.ServerID` (519), `TSimpleIPCServer.StartServer` (523)

### 26.9.8 TSimpleIPCServer.PeekMessage

**Synopsis:** Check if a client message is available.

**Declaration:** `function PeekMessage (TimeOut: Integer; DoReadMessage: Boolean) : Boolean`

**Visibility:** `public`

**Description:** `PeekMessage` checks if a message from a client is available. It will return `True` if a message is available. The call will wait for `TimeOut` milliseconds for a message to arrive: if after `TimeOut` milliseconds, no message is available, the function will return `False`.

If `DoReadMessage` is `True` then `PeekMessage` will read the message. If it is `False`, it does not read the message. The message should then be read manually with `ReadMessage` (522).

**See also:** `TSimpleIPCServer.ReadMessage` (522)

### 26.9.9 TSimpleIPCServer.GetMessageData

**Synopsis:** Read the data of the last message in a stream

**Declaration:** `procedure GetMessageData (Stream: TStream)`

**Visibility:** `public`

**Description:** `GetMessageData` reads the data of the last message from `TSimpleIPCServer.MsgData` (525) and stores it in stream `Stream`. If no data was available, the stream will be cleared.

This function will return valid data only after a succesful call to `ReadMessage` (522). It will also not clear the data buffer.

**See also:** `TSimpleIPCServer.StringMessage` (525), `TSimpleIPCServer.MsgData` (525), `TSimpleIPCServer.MsgType` (525)

### 26.9.10 TSimpleIPCServer.StringMessage

Synopsis: Last message as a string.

Declaration: Property StringMessage : String

Visibility: public

Access: Read

Description: StringMessage is the content of the last message as a string.

This property will contain valid data only after a succesful call to ReadMessage (522).

See also: TSimpleIPCServer.GetMessageData (524)

### 26.9.11 TSimpleIPCServer.MsgType

Synopsis: Last message type

Declaration: Property MsgType : TMessageType

Visibility: public

Access: Read

Description: MsgType contains the message type of the last message.

This property will contain valid data only after a succesful call to ReadMessage (522).

See also: TSimpleIPCServer.ReadMessage (522)

### 26.9.12 TSimpleIPCServer.MsgData

Synopsis: Last message data

Declaration: Property MsgData : TStream

Visibility: public

Access: Read

Description: MsgData contains the actual data from the last read message. If the data is a string, then StringMessage (525) is better suited to read the data.

This property will contain valid data only after a succesful call to ReadMessage (522).

See also: TSimpleIPCServer.StringMessage (525), TSimpleIPCServer.ReadMessage (522)

### 26.9.13 TSimpleIPCServer.InstanceID

Synopsis: Instance ID

Declaration: Property InstanceID : String

Visibility: public

Access: Read

Description: InstanceID is the unique identifier for this server communication channel endpoint, and will be appended to the ServerID (522) property to form the unique server endpoint which a client should use.

See also: TSimpleIPCServer.ServerID (522), TSimpleIPCServer.GlobalID (522)

### 26.9.14 TSimpleIPCServer.Global

Synopsis: Is the server reachable to all users or not

Declaration: `Property Global : Boolean`

Visibility: published

Access: Read, Write

Description: `Global` indicates whether the server is reachable to all users (`True`) or if it is private to the current process (`False`). In the latter case, the unique channel endpoint identification may change: a unique identification of the current process is appended to the `ServerID` name.

See also: `TSimpleIPCServer.ServerID` ([522](#)), `TSimpleIPCServer.InstanceID` ([525](#))

### 26.9.15 TSimpleIPCServer.OnMessage

Synopsis: Event triggered when a message arrives

Declaration: `Property OnMessage : TNotifyEvent`

Visibility: published

Access: Read, Write

Description: `OnMessage` is called by `ReadMessage` ([522](#)) when a message has been read. The actual message data can be retrieved with one of the `StringMessage` ([525](#)), `MsgData` ([525](#)) or `MsgType` ([525](#)) properties.

See also: `TSimpleIPCServer.StringMessage` ([525](#)), `TSimpleIPCServer.MsgData` ([525](#)), `TSimpleIPCServer.MsgType` ([525](#))



## Chapter 27

# Reference for unit 'streamcoll'

### 27.1 Used units

Table 27.1: Used units by unit 'streamcoll'

Name	Page
Classes	??
sysutils	??

### 27.2 Overview

The `streamcoll` unit contains the implementation of a collection (and corresponding collection item) which implements routines for saving or loading the collection to/from a stream. The collection item should implement 2 routines to implement the streaming; the streaming itself is not performed by the `TStreamCollection` (530) collection item.

The streaming performed here is not compatible with the streaming implemented in the `Classes` unit for components. It is independent of the latter and can be used without a component to hold the collection.

The collection item introduces mostly protected methods, and the unit contains a lot of auxiliary routines which aid in streaming.

### 27.3 Procedures and functions

#### 27.3.1 ColReadBoolean

Synopsis: Read a boolean value from a stream

Declaration: `function ColReadBoolean(S: TStream) : Boolean`

Visibility: default

Description: `ColReadBoolean` reads a boolean from the stream `S` as it was written by `ColWriteBoolean` (529) and returns the read value. The value cannot be read and written across systems that have different endian values.

See also: [ColReadDateTime \(528\)](#), [ColWriteBoolean \(529\)](#), [ColReadString \(529\)](#), [ColReadInteger \(528\)](#), [ColReadFloat \(528\)](#), [ColReadCurrency \(528\)](#)

### 27.3.2 ColReadCurrency

Synopsis: Read a currency value from the stream

Declaration: `function ColReadCurrency(S: TStream) : Currency`

Visibility: default

Description: `ColReadCurrency` reads a currency value from the stream `S` as it was written by `ColWriteCurrency (529)` and returns the read value. The value cannot be read and written across systems that have different endian values.

See also: [ColReadDateTime \(528\)](#), [ColReadBoolean \(527\)](#), [ColReadString \(529\)](#), [ColReadInteger \(528\)](#), [ColReadFloat \(528\)](#), [ColWriteCurrency \(529\)](#)

### 27.3.3 ColReadDateTime

Synopsis: Read a `TDateTime` value from a stream

Declaration: `function ColReadDateTime(S: TStream) : TDateTime`

Visibility: default

Description: `ColReadDateTime` reads a currency value from the stream `S` as it was written by `ColWriteDateTime (529)` and returns the read value. The value cannot be read and written across systems that have different endian values.

See also: [ColWriteDateTime \(529\)](#), [ColReadBoolean \(527\)](#), [ColReadString \(529\)](#), [ColReadInteger \(528\)](#), [ColReadFloat \(528\)](#), [ColReadCurrency \(528\)](#)

### 27.3.4 ColReadFloat

Synopsis: Read a floating point value from a stream

Declaration: `function ColReadFloat(S: TStream) : Double`

Visibility: default

Description: `ColReadFloat` reads a double value from the stream `S` as it was written by `ColWriteFloat (530)` and returns the read value. The value cannot be read and written across systems that have different endian values.

See also: [ColReadDateTime \(528\)](#), [ColReadBoolean \(527\)](#), [ColReadString \(529\)](#), [ColReadInteger \(528\)](#), [ColWriteFloat \(530\)](#), [ColReadCurrency \(528\)](#)

### 27.3.5 ColReadInteger

Synopsis: Read a 32-bit integer from a stream.

Declaration: `function ColReadInteger(S: TStream) : Integer`

Visibility: default

**Description:** `ColReadInteger` reads a 32-bit integer from the stream `S` as it was written by `ColWriteInteger` (530) and returns the read value. The value cannot be read and written across systems that have different endian values.

See also: `ColReadDateTime` (528), `ColReadBoolean` (527), `ColReadString` (529), `ColWriteInteger` (530), `ColReadFloat` (528), `ColReadCurrency` (528)

### 27.3.6 ColReadString

**Synopsis:** Read a string from a stream

**Declaration:** `function ColReadString(S: TStream) : String`

**Visibility:** default

**Description:** `ColReadStream` reads a string value from the stream `S` as it was written by `ColWriteString` (530) and returns the read value. The value cannot be read and written across systems that have different endian values.

See also: `ColReadDateTime` (528), `ColReadBoolean` (527), `ColWriteString` (530), `ColReadInteger` (528), `ColReadFloat` (528), `ColReadCurrency` (528)

### 27.3.7 ColWriteBoolean

**Synopsis:** Write a boolean to a stream

**Declaration:** `procedure ColWriteBoolean(S: TStream; AValue: Boolean)`

**Visibility:** default

**Description:** `ColWriteBoolean` writes the boolean `AValue` to the stream. `S`.

See also: `ColReadBoolean` (527), `ColWriteString` (530), `ColWriteInteger` (530), `ColWriteCurrency` (529), `ColWriteDateTime` (529), `ColWriteFloat` (530)

### 27.3.8 ColWriteCurrency

**Synopsis:** Write a currency value to stream

**Declaration:** `procedure ColWriteCurrency(S: TStream; AValue: Currency)`

**Visibility:** default

**Description:** `ColWriteCurrency` writes the currency `AValue` to the stream `S`.

See also: `ColWriteBoolean` (529), `ColWriteString` (530), `ColWriteInteger` (530), `ColWriteDateTime` (529), `ColWriteFloat` (530), `ColReadCurrency` (528)

### 27.3.9 ColWriteDateTime

**Synopsis:** Write a `TDateTime` value to stream

**Declaration:** `procedure ColWriteDateTime(S: TStream; AValue: TDateTime)`

**Visibility:** default

**Description:** `ColWriteDateTime` writes the `TDateTime` `AValue` to the stream `S`.

See also: `ColReadDateTime` (528), `ColWriteBoolean` (529), `ColWriteString` (530), `ColWriteInteger` (530), `ColWriteFloat` (530), `ColWriteCurrency` (529)

### 27.3.10 ColWriteFloat

Synopsis: Write floating point value to stream

Declaration: `procedure ColWriteFloat (S: TStream; AValue: Double)`

Visibility: default

Description: `ColWriteFloat` writes the double `AValue` to the stream `S`.

See also: `ColWriteDateTime` (529), `ColWriteBoolean` (529), `ColWriteString` (530), `ColWriteInteger` (530), `ColReadFloat` (528), `ColWriteCurrency` (529)

### 27.3.11 ColWriteInteger

Synopsis: Write a 32-bit integer to a stream

Declaration: `procedure ColWriteInteger (S: TStream; AValue: Integer)`

Visibility: default

Description: `ColWriteInteger` writes the 32-bit integer `AValue` to the stream `S`. No endianness is observed.

See also: `ColWriteBoolean` (529), `ColWriteString` (530), `ColReadInteger` (528), `ColWriteCurrency` (529), `ColWriteDateTime` (529)

### 27.3.12 ColWriteString

Synopsis: Write a string value to the stream

Declaration: `procedure ColWriteString (S: TStream; AValue: String)`

Visibility: default

Description: `ColWriteString` writes the string value `AValue` to the stream `S`.

See also: `ColWriteBoolean` (529), `ColReadStream` (529), `ColWriteInteger` (530), `ColWriteCurrency` (529), `ColWriteDateTime` (529), `ColWriteFloat` (530)

## 27.4 EStreamColl

### 27.4.1 Description

Exception raised when an error occurs when streaming the collection.

## 27.5 TStreamCollection

### 27.5.1 Description

`TStreamCollection` is a `TCollection` (??) descendent which implements 2 calls `LoadFromStream` (531) and `SaveToStream` (531) which load and save the contents of the collection to a stream.

The collection items must be descendents of the `TStreamCollectionItem` (532) class for the streaming to work correctly.

Note that the stream must be used to load collections of the same type.

### 27.5.2 Method overview

Page	Property	Description
<a href="#">531</a>	LoadFromStream	Load the collection from a stream
<a href="#">531</a>	SaveToStream	Load the collection from the stream.

### 27.5.3 Property overview

Page	Property	Access	Description
<a href="#">531</a>	Streaming	r	Indicates whether the collection is currently being written to stream

### 27.5.4 TStreamCollection.LoadFromStream

Synopsis: Load the collection from a stream

Declaration: `procedure LoadFromStream(S: TStream)`

Visibility: public

Description: `LoadFromStream` loads the collection from the stream `S`, if the collection was saved using `SaveToStream` ([531](#)). It reads the number of items in the collection, and then creates and loads the items one by one from the stream.

Errors: An exception may be raised if the stream contains invalid data.

See also: `TStreamCollection.SaveToStream` ([531](#))

### 27.5.5 TStreamCollection.SaveToStream

Synopsis: Load the collection from the stream.

Declaration: `procedure SaveToStream(S: TStream)`

Visibility: public

Description: `SaveToStream` saves the collection to the stream `S` so it can be read from the stream with `LoadFromStream` ([531](#)). It does this by writing the number of collection items to the stream, and then streaming all items in the collection by calling their `SaveToStream` method.

Errors: None.

See also: `TStreamCollection.LoadFromStream` ([531](#))

### 27.5.6 TStreamCollection.Streaming

Synopsis: Indicates whether the collection is currently being written to stream

Declaration: `Property Streaming : Boolean`

Visibility: public

Access: Read

Description: `Streaming` is set to `True` if the collection is written to or loaded from stream, and is set again to `False` if the streaming process is finished.

See also: `TStreamCollection.LoadFromStream` ([531](#)), `TStreamCollection.SaveToStream` ([531](#))

## 27.6 TStreamCollectionItem

### 27.6.1 Description

TStreamCollectionItem is a TCollectionItem (??) descendent which implements 2 abstract routines: LoadFromStream and SaveToStream which must be overridden in a descendent class.

These 2 routines will be called by the TStreamCollection ([530](#)) to save or load the item from the stream.

# Chapter 28

## Reference for unit 'streamex'

### 28.1 Used units

Table 28.1: Used units by unit 'streamex'

Name	Page
Classes	??

### 28.2 Overview

streamex implements some extensions to be used together with streams from the classes unit.

### 28.3 TBidirBinaryObjectReader

#### 28.3.1 Description

`TBidirBinaryObjectReader` is a class descendent from `TBinaryObjectReader` (??), which implements the necessary support for BiDi data: the position in the stream (not available in the standard streaming) is emulated.

#### 28.3.2 Property overview

Page	Property	Access	Description
<a href="#">533</a>	Position	rw	Position in the stream

#### 28.3.3 TBidirBinaryObjectReader.Position

Synopsis: Position in the stream

Declaration: `Property Position : LongInt`

Visibility: public

Access: Read,Write

Description: `Position` exposes the position of the stream in the reader for use in the `TDelphiReader` (534) class.

See also: `TDelphiReader` (534)

## 28.4 TBidirBinaryObjectWriter

### 28.4.1 Description

`TBidirBinaryObjectReader` is a class descendent from `TBinaryObjectWriter` (??), which implements the necessary support for BiDi data.

### 28.4.2 Property overview

Page	Property	Access	Description
534	<code>Position</code>	rw	Position in the stream

### 28.4.3 TBidirBinaryObjectWriter.Position

Synopsis: Position in the stream

Declaration: `Property Position : LongInt`

Visibility: public

Access: Read,Write

Description: `Position` exposes the position of the stream in the writer for use in the `TDelphiWriter` (535) class.

See also: `TDelphiWriter` (535)

## 28.5 TDelphiReader

### 28.5.1 Description

`TDelphiReader` is a descendent of `TReader` which has support for BiDi Streaming. It overrides the stream reading methods for strings, and makes sure the stream can be positioned in the case of strings. For this purpose, it makes use of the `TBidirBinaryObjectReader` (533) driver class.

### 28.5.2 Method overview

Page	Property	Description
535	<code>GetDriver</code>	Return the driver class as a <code>TBidirBinaryObjectReader</code> (533) class
535	<code>Read</code>	Read data from stream
535	<code>ReadStr</code>	Overrides the standard <code>ReadStr</code> method

### 28.5.3 Property overview

Page	Property	Access	Description
535	<code>Position</code>	rw	Position in the stream



### 28.5.4 TDelphiReader.GetDriver

Synopsis: Return the driver class as a `TBidirBinaryObjectReader` (533) class

Declaration: `function GetDriver : TBidirBinaryObjectReader`

Visibility: public

Description: `GetDriver` simply returns the used driver and typecasts it as `TBidirBinaryObjectReader` (533) class.

See also: `TBidirBinaryObjectReader` (533)

### 28.5.5 TDelphiReader.ReadStr

Synopsis: Overrides the standard `ReadStr` method

Declaration: `function ReadStr : String`

Visibility: public

Description: `ReadStr` makes sure the `TBidirBinaryObjectReader` (533) methods are used, to store additional information about the stream position when reading the strings.

See also: `TBidirBinaryObjectReader` (533)

### 28.5.6 TDelphiReader.Read

Synopsis: Read data from stream

Declaration: `procedure Read(var Buf; Count: LongInt); Override`

Visibility: public

Description: `Read` reads raw data from the stream. It reads `Count` bytes from the stream and places them in `Buf`. It forces the use of the `TBidirBinaryObjectReader` (533) class when reading.

See also: `TBidirBinaryObjectReader` (533), `TDelphiReader.Position` (535)

### 28.5.7 TDelphiReader.Position

Synopsis: Position in the stream

Declaration: `Property Position : LongInt`

Visibility: public

Access: Read, Write

Description: Position in the stream.

See also: `TDelphiReader.Read` (535)

## 28.6 TDelphiWriter

### 28.6.1 Description

`TDelphiWriter` is a descendent of `TWriter` which has support for BiDi Streaming. It overrides the stream writing methods for strings, and makes sure the stream can be positioned in the case of strings. For this purpose, it makes use of the `TBidirBinaryObjectWriter` (534) driver class.

### 28.6.2 Method overview

Page	Property	Description
<a href="#">536</a>	FlushBuffer	Flushes the stream buffer
<a href="#">536</a>	GetDriver	Return the driver class as a <code>TBidirBinaryObjectWriter</code> ( <a href="#">534</a> ) class
<a href="#">536</a>	Write	Write raw data to the stream
<a href="#">536</a>	WriteStr	Write a string to the stream
<a href="#">537</a>	WriteValue	Write value type

### 28.6.3 Property overview

Page	Property	Access	Description
<a href="#">537</a>	Position	rw	Position in the stream

### 28.6.4 TDelphiWriter.GetDriver

Synopsis: Return the driver class as a `TBidirBinaryObjectWriter` ([534](#)) class

Declaration: `function GetDriver : TBidirBinaryObjectWriter`

Visibility: public

Description: `GetDriver` simply returns the used driver and typecasts it as `TBidirBinaryObjectWriter` ([534](#)) class.

See also: `TBidirBinaryObjectWriter` ([534](#))

### 28.6.5 TDelphiWriter.FlushBuffer

Synopsis: Flushes the stream buffer

Declaration: `procedure FlushBuffer`

Visibility: public

Description: `FlushBuffer` flushes the internal buffer of the writer. It simply calls the `FlushBuffer` method of the driver class.

### 28.6.6 TDelphiWriter.Write

Synopsis: Write raw data to the stream

Declaration: `procedure Write(const Buf; Count: LongInt); Override`

Visibility: public

Description: `Write` writes `Count` bytes from `Buf` to the buffer, updating the position as needed.

### 28.6.7 TDelphiWriter.WriteStr

Synopsis: Write a string to the stream

Declaration: `procedure WriteStr(const Value: String)`

Visibility: public

**Description:** `WriteStr` writes a string to the stream, forcing the use of the `TBidirBinaryObjectWriter` (534) class methods, which update the position of the stream.

See also: `TBidirBinaryObjectWriter` (534)

### 28.6.8 `TDelphiWriter.WriteValue`

**Synopsis:** Write value type

**Declaration:** `procedure WriteValue(Value: TValueType)`

**Visibility:** public

**Description:** `WriteValue` overrides the same method in `TWriter` to force the use of the `TBidirBinaryObjectWriter` (534) methods, which update the position of the stream.

See also: `TBidirBinaryObjectWriter` (534)

### 28.6.9 `TDelphiWriter.Position`

**Synopsis:** Position in the stream

**Declaration:** `Property Position : LongInt`

**Visibility:** public

**Access:** Read, Write

**Description:** `Position` exposes the position in the stream as exposed by the `TBidirBinaryObjectWriter` (534) instance used when streaming.

See also: `TBidirBinaryObjectWriter` (534)

## Chapter 29

# Reference for unit 'StreamIO'

### 29.1 Used units

Table 29.1: Used units by unit 'StreamIO'

Name	Page
Classes	??
sysutils	??

### 29.2 Overview

The `StreamIO` unit implements a call to reroute the input or output of a text file to a descendent of `TStream` (??).

This allows to use the standard pascal `Read` (??) and `Write` (??) functions (with all their possibilities), on streams.

### 29.3 Procedures and functions

#### 29.3.1 AssignStream

Synopsis: Assign a text file to a stream.

Declaration: `procedure AssignStream(var F: Textfile; Stream: TStream)`

Visibility: default

Description: `AssignStream` assigns the stream `Stream` to file `F`. The file can subsequently be used to write to the stream, using the standard `Write` (??) calls.

Before writing, call `Rewrite` (??) on the stream. Before reading, call `Reset` (??).

Errors: if `Stream` is `Nil`, an exception will be raised.

See also: `#rtl.classes.TStream` (??), `GetStream` (539)

### 29.3.2 GetStream

Synopsis: Return the stream, associated with a file.

Declaration: `function GetStream(var F: TTextRec) : TStream`

Visibility: default

Description: `GetStream` returns the instance of the stream that was associated with the file `F` using `AssignStream` ([538](#)).

Errors: An invalid class reference will be returned if the file was not associated with a stream.

See also: `AssignStream` ([538](#)), `#rtl.classes.TStream` (??)

## Chapter 30

# Reference for unit 'syncobjs'

### 30.1 Used units

Table 30.1: Used units by unit 'syncobjs'

Name	Page
sysutils	??

### 30.2 Overview

The `syncobjs` unit implements some classes which can be used when synchronizing threads in routines or classes that are used in multiple threads at once. The `TCriticalSection` ([541](#)) class is a wrapper around low-level critical section routines (semaphores or mutexes). The `TEventObject` ([543](#)) class can be used to send messages between threads (also known as conditional variables in Posix threads).

### 30.3 Constants, types and variables

#### 30.3.1 Constants

`INFINITE = Cardinal(-1)`

Constant denoting an infinite timeout.

#### 30.3.2 Types

`PSecurityAttributes = Pointer`

`PSecurityAttributes` is a dummy type used in non-windows implementations, so the calls remain Delphi compatible.

`TEvent = TEventObject`

`TEvent` is a simple alias for the `TEventObject` ([543](#)) class.

`TEventHandle = Pointer`

`TEventHandle` is an opaque type and should not be used in user code.

`TWaitResult = (wrSignaled, wrTimeout, wrAbandoned, wrError)`

Table 30.2: Enumeration values for type `TWaitResult`

Value	Explanation
<code>wrAbandoned</code>	Wait operation was abandoned.
<code>wrError</code>	An error occurred during the wait operation.
<code>wrSignaled</code>	Event was signaled (triggered)
<code>wrTimeout</code>	Time-out period expired

`TWaitResult` is used to report the result of a wait operation.

## 30.4 TCriticalSection

### 30.4.1 Description

`TCriticalSection` is a class wrapper around the low-level `TRTLCriticalSection` routines. It simply calls the RTL routines in the system unit for critical section support.

A critical section is a resource which can be owned by only 1 caller: it can be used to make sure that in a multithreaded application only 1 thread enters pieces of code protected by the critical section.

Typical usage is to protect a piece of code with the following code (`MySection` is a `TCriticalSection` instance):

```
// Previous code
MySection.Acquire;
Try
  // Protected code
Finally
  MySection.Release;
end;
// Other code.
```

The protected code can be executed by only 1 thread at a time. This is useful for instance for list operations in multithreaded environments.

### 30.4.2 Method overview

Page	Property	Description
<a href="#">542</a>	<code>Acquire</code>	Enter the critical section
<a href="#">543</a>	<code>Create</code>	Create a new critical section.
<a href="#">543</a>	<code>Destroy</code>	Destroy the criticalsection instance
<a href="#">542</a>	<code>Enter</code>	Alias for <code>Acquire</code>
<a href="#">543</a>	<code>Leave</code>	Alias for <code>Release</code>
<a href="#">542</a>	<code>Release</code>	Leave the critical section
<a href="#">542</a>	<code>TryEnter</code>	Try and obtain the critical section

### 30.4.3 TCriticalSection.Acquire

Synopsis: Enter the critical section

Declaration: `procedure Acquire; Override`

Visibility: `public`

Description: `Acquire` attempts to enter the critical section. It will suspend the calling thread if the critical section is in use by another thread, and will resume as soon as the other thread has released the critical section.

See also: `TCriticalSection.Release` ([542](#))

### 30.4.4 TCriticalSection.Release

Synopsis: Leave the critical section

Declaration: `procedure Release; Override`

Visibility: `public`

Description: `Release` leaves the critical section. It will free the critical section so another thread waiting to enter the critical section will be awakened, and will enter the critical section. This call always returns immediately.

See also: `TCriticalSection.Acquire` ([542](#))

### 30.4.5 TCriticalSection.Enter

Synopsis: Alias for `Acquire`

Declaration: `procedure Enter`

Visibility: `public`

Description: `Enter` just calls `Acquire` ([542](#)).

See also: `TCriticalSection.Leave` ([543](#)), `TCriticalSection.Acquire` ([542](#))

### 30.4.6 TCriticalSection.TryEnter

Synopsis: Try and obtain the critical section

Declaration: `function TryEnter : Boolean`

Visibility: `public`

Description: `TryEnter` tries to enter the critical section: it returns at once and does not wait if the critical section is owned by another thread; if the current thread owns the critical section or the critical section was obtained successfully, `true` is returned. If the critical section is currently owned by another thread, `False` is returned.

Errors: None.

See also: `TCriticalSection.Enter` ([542](#))



### 30.4.7 TCriticalSection.Leave

Synopsis: Alias for `Release`

Declaration: `procedure Leave`

Visibility: `public`

Description: `Leave` just calls `Release` ([542](#))

See also: `TCriticalSection.Release` ([542](#)), `TCriticalSection.Enter` ([542](#))

### 30.4.8 TCriticalSection.Create

Synopsis: Create a new critical section.

Declaration: `constructor Create`

Visibility: `public`

Description: `Create` initializes a new critical section, and initializes the system objects for the critical section. It should be created only once for all threads, all threads should use the same critical section instance.

See also: `TCriticalSection.Destroy` ([543](#))

### 30.4.9 TCriticalSection.Destroy

Synopsis: Destroy the criticalsection instance

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` releases the system critical section resources, and removes the `TCriticalSection` instance from memory.

Errors: Any threads trying to enter the critical section when it is destroyed, will start running with an error (an exception should be raised).

See also: `TCriticalSection.Create` ([543](#)), `TCriticalSection.Acquire` ([542](#))

## 30.5 TEventObject

### 30.5.1 Description

`TEventObject` encapsulates the `BasicEvent` implementation of the system unit in a class. The event can be used to notify other threads of a change in conditions. (in POSIX terms, this is a conditional variable). A thread that wishes to notify other threads creates an instance of `TEventObject` with a certain name, and posts events to it. Other threads that wish to be notified of these events should create their own instances of `TEventObject` with the same name, and wait for events to arrive.

### 30.5.2 Method overview

Page	Property	Description
<a href="#">544</a>	Create	Create a new event object
<a href="#">544</a>	destroy	Clean up the event and release from memory
<a href="#">544</a>	ResetEvent	Reset the event
<a href="#">545</a>	SetEvent	Set the event
<a href="#">545</a>	WaitFor	Wait for the event to be set.

### 30.5.3 Property overview

Page	Property	Access	Description
<a href="#">545</a>	ManualReset	r	Should the event be reset manually

### 30.5.4 TEventObject.Create

Synopsis: Create a new event object

Declaration: `constructor Create(EventAttributes: PSecurityAttributes;  
                                  AManualReset: Boolean;InitialState: Boolean;  
                                  const Name: String)`

Visibility: public

Description: `Create` creates a new event object with unique name `AName`. The object will be created security attributes `EventAttributes` (windows only).

The `AManualReset` indicates whether the event must be reset manually (if it is `False`, the event is reset immediatly after the first thread waiting for it is notified). `InitialState` determines whether the event is initially set or not.

See also: `TEventObject.ManualReset` ([545](#)), `TEventObject.ResetEvent` ([544](#))

### 30.5.5 TEventObject.destroy

Synopsis: Clean up the event and release from memory

Declaration: `destructor destroy; Override`

Visibility: public

Description: `Destroy` cleans up the low-level resources allocated for this event and releases the event instance from memory.

See also: `TEventObject.Create` ([544](#))

### 30.5.6 TEventObject.ResetEvent

Synopsis: Reset the event

Declaration: `procedure ResetEvent`

Visibility: public

Description: `ResetEvent` turns off the event. Any `WaitFor` ([545](#)) operation will suspend the calling thread.

See also: `TEventObject.SetEvent` ([545](#)), `TEventObject.WaitFor` ([545](#))

### 30.5.7 TEventObject.SetEvent

Synopsis: Set the event

Declaration: `procedure SetEvent`

Visibility: `public`

Description: `SetEvent` sets the event. If the `ManualReset` (545) is `True` any thread that was waiting for the event to be set (using `WaitFor` (545)) will resume it's operation. After the event was set, any thread that executes `WaitFor` will return at once. If `ManualReset` is `False`, only one thread will be notified that the event was set, and the event will be immediatly reset after that.

See also: `TEventObject.WaitFor` (545), `TEventObject.ManualReset` (545)

### 30.5.8 TEventObject.WaitFor

Synopsis: Wait for the event to be set.

Declaration: `function WaitFor(Timeout: Cardinal) : TWaitResult`

Visibility: `public`

Description: `WaitFor` should be used in threads that should be notified when the event is set. When `WaitFor` is called, and the event is not set, the thread will be suspended. As soon as the event is set by some other thread (using `SetEvent` (545)) or the timeout period (`TimeOut`) has expired, the `WaitFor` function returns. The return value depends on the condition that caused the `WaitFor` function to return.

The calling thread will wait indefinitely when the constant `INFINITE` is specified for the `TimeOut` parameter.

See also: `TEventObject.SetEvent` (545)

### 30.5.9 TEventObject.ManualReset

Synopsis: Should the event be reset manually

Declaration: `Property ManualReset : Boolean`

Visibility: `public`

Access: `Read`

Description: Should the event be reset manually

## 30.6 THandleObject

### 30.6.1 Description

`THandleObject` is a parent class for synchronization classes that need to store an operating system handle. It introduces a property `Handle` (546) which can be used to store the operating system handle. The handle is in no way manipulated by `THandleObject`, only storage is provided.

### 30.6.2 Method overview

Page	Property	Description
546	<code>destroy</code>	Free the instance

### 30.6.3 Property overview

Page	Property	Access	Description
<a href="#">546</a>	Handle	r	Handle for this object
<a href="#">546</a>	LastError	r	Last operating system error

### 30.6.4 THandleObject.destroy

Synopsis: Free the instance

Declaration: `destructor destroy; Override`

Visibility: `public`

Description: `Destroy` does nothing in the Free Pascal implementation of `THandleObject`.

### 30.6.5 THandleObject.Handle

Synopsis: Handle for this object

Declaration: `Property Handle : TEventHandle`

Visibility: `public`

Access: Read

Description: `Handle` provides read-only access to the operating system handle of this instance. The public access is read-only, descendent classes should set the handle by accessing it's protected field `FHandle` directly.

### 30.6.6 THandleObject.LastError

Synopsis: Last operating system error

Declaration: `Property LastError : Integer`

Visibility: `public`

Access: Read

Description: `LastError` provides read-only access to the last operating system error code for operations on `Handle` ([546](#)).

See also: `THandleObject.Handle` ([546](#))

## 30.7 TSimpleEvent

### 30.7.1 Description

`TSimpleEvent` is a simple descendent of the `TEventObject` ([543](#)) class. It creates an event with no name, which must be reset manually, and which is initially not set.

### 30.7.2 Method overview

Page	Property	Description
<a href="#">547</a>	Create	Creates a new <code>TSimpleEvent</code> instance

### 30.7.3 TSimpleEvent.Create

Synopsis: Creates a new TSimpleEvent instance

Declaration: constructor Create

Visibility: default

Description: Create instantiates a new TSimpleEvent instance. It simply calls the inherited Create (544) with Nil for the security attributes, an empty name, AManualReset set to True, and InitialState to False.

See also: TEventObject.Create (544)

## 30.8 TSynchroObject

### 30.8.1 Description

TSynchroObject is an abstract synchronization resource object. It implements 2 virtual methods Acquire (547) which can be used to acquire the resource, and Release (547) to release the resource.

### 30.8.2 Method overview

Page	Property	Description
<a href="#">547</a>	Acquire	Acquire synchronization resource
<a href="#">547</a>	Release	Release previously acquired synchronization resource

### 30.8.3 TSynchroObject.Acquire

Synopsis: Acquire synchronization resource

Declaration: procedure Acquire; Virtual

Visibility: default

Description: Acquire does nothing in TSynchroObject. Descendent classes must override this method to acquire the resource they manage.

See also: TSynchroObject.Release (547)

### 30.8.4 TSynchroObject.Release

Synopsis: Release previously acquired synchronization resource

Declaration: procedure Release; Virtual

Visibility: default

Description: Release does nothing in TSynchroObject. Descendent classes must override this method to release the resource they acquired through the Acquire (547) call.

See also: TSynchroObject.Acquire (547)

## Chapter 31

# Reference for unit 'URIParser'

### 31.1 Overview

The `URIParser` unit contains a basic type (`TURI` ([548](#))) and some routines for the parsing (`ParseURI` ([549](#))) and construction (`EncodeURI` ([548](#))) of Uniform Resource Indicators, commonly referred to as URL: Uniform Resource Location. It is used in various other units, and in itself contains no classes. It supports all protocols, username/password/port specification, query parameters and bookmarks etc..

### 31.2 Constants, types and variables

#### 31.2.1 Types

```
TURI = record
  Protocol : String;
  Username : String;
  Password : String;
  Host : String;
  Port : Word;
  Path : String;
  Document : String;
  Params : String;
  Bookmark : String;
  HasAuthority : Boolean;
end
```

`TURI` is the basic record that can be filled by the `ParseURI` ([549](#)) call. It contains the contents of a URI, parsed out in it's various pieces.

### 31.3 Procedures and functions

#### 31.3.1 EncodeURI

Synopsis: Form a string representation of the URI

Declaration: `function EncodeURI(const URI: TURI) : String`

Visibility: default

Description: `EncodeURI` will return a valid text representation of the URI in the URI record.

See also: `ParseURI` ([549](#))

### 31.3.2 FilenameToURI

Synopsis: Construct a URI from a filename

Declaration: `function FilenameToURI(const Filename: String) : String`

Visibility: default

Description: `FilenameToURI` takes `Filename` and constructs a `file:` protocol URI from it.

Errors: None.

See also: `URIToFilename` ([550](#))

### 31.3.3 IsAbsoluteURI

Synopsis: Check whether a URI is absolute.

Declaration: `function IsAbsoluteURI(const UriReference: String) : Boolean`

Visibility: default

Description: `IsAbsoluteURI` returns `True` if the URI in `UriReference` is absolute, i.e. contains a protocol part.

Errors: None.

See also: `FilenameToURI` ([549](#)), `URIToFileName` ([550](#))

### 31.3.4 ParseURI

Synopsis: Parse a URI and split it into its constituent parts

Declaration: `function ParseURI(const URI: String) : TURI; Overload`  
`function ParseURI(const URI: String; const DefaultProtocol: String;`  
`DefaultPort: Word) : TURI; Overload`

Visibility: default

Description: `ParseURI` decodes URI and returns the various parts of the URI in the result record.

The function accepts the most general URI scheme:

```
proto://user:pwd@host:port/path/document?params#bookmark
```

Missing (optional) parts in the URI will be left blank in the result record. If a default protocol and port are specified, they will be used in the record if the corresponding part is not present in the URI.

See also: `EncodeURI` ([548](#))

### 31.3.5 ResolveRelativeURI

Synopsis: Return a relative link

Declaration: 

```
function ResolveRelativeURI(const BaseUri: WideString;
                           const RelUri: WideString;
                           out ResultUri: WideString) : Boolean
; Overload
function ResolveRelativeURI(const BaseUri: UTF8String;
                           const RelUri: UTF8String;
                           out ResultUri: UTF8String) : Boolean
; Overload
```

Visibility: default

Description: `ResolveRelativeURI` returns in `ResultUri` an absolute link constructed from a base URI `BaseURI` and a relative link `RelURI`. One of the two URI names must have a protocol specified. If the `RelURI` argument contains a protocol, it is considered a complete (absolute) URI and is returned as the result.

The function returns `True` if a link was successfully returned.

Errors: If no protocols are specified, the function returns `False`

### 31.3.6 URIToFilename

Synopsis: Convert a URI to a filename

Declaration: 

```
function URIToFilename(const URI: String;out Filename: String) : Boolean
```

Visibility: default

Description: `URIToFilename` returns a filename (using the correct Path Delimiter character) from URI. The URI must be of protocol `File` or have no protocol.

Errors: If the URI contains an unsupported protocol, `False` is returned.

See also: `ResolveRelativeURI` (550), `FilenameToURI` (549)



## Chapter 32

# Reference for unit 'zstream'

### 32.1 Used units

Table 32.1: Used units by unit 'zstream'

Name	Page
Classes	??
gzio	<a href="#">551</a>
zbase	<a href="#">551</a>

### 32.2 Overview

The `ZStream` unit implements a `TStream` (??) descendent (`TCompressionStream` ([552](#))) which uses the deflate algorithm to compress everything that is written to it. The compressed data is written to the output stream, which is specified when the compressor class is created.

Likewise, a `TStream` descendent is implemented which reads data from an input stream (`TDecompressionStream` ([555](#))) and decompresses it with the inflate algorithm.

### 32.3 Constants, types and variables

#### 32.3.1 Types

`Tcompressionlevel = (clnone, clfastest, cldefault, clmax)`

Compression level for the deflate algorithm

`Tgzopenmode = (gzopenread, gzopenwrite)`

Open mode for gzip file.

Table 32.2: Enumeration values for type `Tcompressionlevel`

Value	Explanation
<code>cldefault</code>	Use default compression
<code>clfastest</code>	Use fast (but less) compression.
<code>clmax</code>	Use maximum compression
<code>clnone</code>	Do not use compression, just copy data.

Table 32.3: Enumeration values for type `Tgzopenmode`

Value	Explanation
<code>gzopenread</code>	Open file for reading
<code>gzopenwrite</code>	Open file for writing

## 32.4 `Ecompressionerror`

### 32.4.1 Description

`ECompressionError` is the exception class used by the `TCompressionStream` ([552](#)) class.

## 32.5 `Edecompressionerror`

### 32.5.1 Description

`EDecompressionError` is the exception class used by the `TDeCompressionStream` ([555](#)) class.

## 32.6 `Egzfileerror`

### 32.6.1 Description

`Egzfileerror` is the exception class used to report errors by the `Tgzfilestream` ([557](#)) class.

## 32.7 `Ezliberror`

### 32.7.1 Description

Errors which occur in the `zstream` unit are signaled by raising an `EZLibError` exception descendent.

## 32.8 `Tcompressionstream`

### 32.8.1 Description

`TCompressionStream`

### 32.8.2 Method overview

Page	Property	Description
<a href="#">553</a>	create	Create a new instance of the compression stream.
<a href="#">553</a>	destroy	Flushe data to the output stream and destroys the compression stream.
<a href="#">554</a>	flush	Flush remaining data to the target stream
<a href="#">554</a>	get\_compressionrate	Get the current compression rate
<a href="#">553</a>	write	Write data to the stream

### 32.8.3 Tcompressionstream.create

Synopsis: Create a new instance of the compression stream.

Declaration: `constructor create(level: Tcompressionlevel; dest: TStream; Askipheader: Boolean)`

Visibility: public

Description: `Create` creates a new instance of the compression stream. It merely calls the inherited constructor with the destination stream `Dest` and stores the compression level.

If `ASkipHeader` is set to `True`, the method will not write the block header to the stream. This is required for deflated data in a zip file.

Note that the compressed data is only completely written after the compression stream is destroyed.

See also: `TCompressionStream.Destroy` ([553](#))

### 32.8.4 Tcompressionstream.destroy

Synopsis: Flushe data to the output stream and destroys the compression stream.

Declaration: `destructor destroy; Override`

Visibility: public

Description: `Destroy` flushes the output stream: any compressed data not yet written to the output stream are written, and the deflate structures are cleaned up.

Errors: None.

See also: `TCompressionStream.Create` ([553](#))

### 32.8.5 Tcompressionstream.write

Synopsis: Write data to the stream

Declaration: `function write(const buffer; count: LongInt) : LongInt; Override`

Visibility: public

Description: `Write` takes `Count` bytes from `Buffer` and comresseses (deflates) them. The compressed result is written to the output stream.

Errors: If an error occurs, an `ECompressionError` ([552](#)) exception is raised.

See also: `TCompressionStream.Read` ([552](#)), `TCompressionStream.Seek` ([552](#))

### 32.8.6 Tcompressionstream.flush

Synopsis: Flush remaining data to the target stream

Declaration: `procedure flush`

Visibility: `public`

Description: `flush` writes any remaining data in the memory buffers to the target stream, and clears the memory buffer.

### 32.8.7 Tcompressionstream.get\_compressionrate

Synopsis: Get the current compression rate

Declaration: `function get_compressionrate : single`

Visibility: `public`

Description: `get_compressionrate` returns the percentage of the number of written compressed bytes relative to the number of written bytes.

Errors: If no bytes were written, an exception is raised.

## 32.9 Tcustomzlibstream

### 32.9.1 Description

`TCustomZlibStream` serves as the ancestor class for the `TCompressionStream` (552) and `TDecompressionStream` (555) classes.

It introduces support for a progress handler, and stores the input or output stream.

### 32.9.2 Method overview

Page	Property	Description
<a href="#">554</a>	<code>create</code>	Create a new instance of <code>TCustomZlibStream</code>
<a href="#">555</a>	<code>destroy</code>	Clear up instance

### 32.9.3 Tcustomzlibstream.create

Synopsis: Create a new instance of `TCustomZlibStream`

Declaration: `constructor create(stream: TStream)`

Visibility: `public`

Description: `Create` creates a new instance of `TCustomZlibStream`. It stores a reference to the input/output stream, and initializes the deflate compression mechanism so they can be used by the descendents.

See also: `TCompressionStream` (552), `TDecompressionStream` (555)

### 32.9.4 Tcustomzlibstream.destroy

Synopsis: Clear up instance

Declaration: `destructor destroy; Override`

Visibility: `public`

Description: `Destroy` cleans up the internal memory buffer and calls the inherited `destroy`.

See also: `Tcustomzlibstream.create` ([554](#))

## 32.10 Tdecompressionstream

### 32.10.1 Description

`TDecompressionStream` performs the inverse operation of `TCompressionStream` ([552](#)). A read operation reads data from an input stream and decompresses (inflates) the data it as it goes along.

The decompression stream reads it's compressed data from a stream with deflated data. This data can be created e.g. with a `TCompressionStream` ([552](#)) compression stream.

### 32.10.2 Method overview

Page	Property	Description
<a href="#">555</a>	<code>create</code>	Creates a new instance of the <code>TDecompressionStream</code> stream
<a href="#">555</a>	<code>destroy</code>	Destroys the <code>TDecompressionStream</code> instance
<a href="#">557</a>	<code>get\_compressionrate</code>	Get the current compression rate
<a href="#">556</a>	<code>read</code>	Read data from the compressed stream
<a href="#">556</a>	<code>seek</code>	Move stream position to a certain location in the stream.

### 32.10.3 Tdecompressionstream.create

Synopsis: Creates a new instance of the `TDecompressionStream` stream

Declaration: `constructor create(Asource: TStream; Askipheader: Boolean)`

Visibility: `public`

Description: `Create` creates and initializes a new instance of the `TDecompressionStream` class. It calls the inherited `Create` and passes it the `Source` stream. The source stream is the stream from which the compressed (deflated) data is read.

If `ASkipHeader` is true, then the gzip data header is skipped, allowing `TDecompressionStream` to read deflated data in a .zip file. (this data does not have the gzip header record prepended to it).

Note that the source stream is by default not owned by the decompression stream, and is not freed when the decompression stream is destroyed.

See also: `TDecompressionStream.Destroy` ([555](#))

### 32.10.4 Tdecompressionstream.destroy

Synopsis: Destroys the `TDecompressionStream` instance

Declaration: `destructor destroy; Override`

Visibility: public

Description: `Destroy` cleans up the inflate structure, and then simply calls the inherited `destroy`.

By default the source stream is not freed when calling `Destroy`.

See also: `TDecompressionStream.Create` (555)

### 32.10.5 Tdecompressionstream.read

Synopsis: Read data from the compressed stream

Declaration: `function read(var buffer; count: LongInt) : LongInt; Override`

Visibility: public

Description: `Read` will read data from the compressed stream until the decompressed data size is `Count` or there is no more compressed data available. The decompressed data is written in `Buffer`. The function returns the number of bytes written in the buffer.

Errors: If an error occurs, an `EDeCompressionError` (552) exception is raised.

See also: `TCompressionStream.Write` (553)

### 32.10.6 Tdecompressionstream.seek

Synopsis: Move stream position to a certain location in the stream.

Declaration: `function seek(offset: LongInt; origin: Word) : LongInt; Override`

Visibility: public

Description: `Seek` overrides the standard `Seek` implementation. There are a few differences between the implementation of `Seek` in Free Pascal compared to Delphi:

- In Free Pascal, you can perform any seek. In case of a forward seek, the Free Pascal implementation will read some bytes until the desired position is reached, in case of a backward seek it will seek the source stream backwards to the position it had at the creation time of the `TDecompressionStream` and then again read some bytes until the desired position has been reached.
- In Free Pascal, a seek with `soFromBeginning` will reset the source stream to the position it had when the `TDecompressionStream` was created. In Delphi, the source stream is reset to position 0. This means that at creation time the source stream must always be at the start of the `zstream`, you cannot use `TDecompressionStream.Seek` to reset the source stream to the begin of the file.

Errors: An `EDeCompressionError` (552) exception is raised if the stream does not allow the requested seek operation.

See also: `TDecompressionStream.Read` (556)

### 32.10.7 Tdecompressionstream.get\_compressionrate

Synopsis: Get the current compression rate

Declaration: `function get_compressionrate : single`

Visibility: public

Description: `get_compressionrate` returns the percentage of the number of read compressed bytes relative to the total number of read bytes.

Errors: If no bytes were written, an exception is raised.

## 32.11 TGZFileStream

### 32.11.1 Description

`TGZFileStream` can be used to read data from a gzip file, or to write data to a gzip file.

### 32.11.2 Method overview

Page	Property	Description
<a href="#">557</a>	<code>create</code>	Create a new instance of <code>TGZFileStream</code>
<a href="#">558</a>	<code>destroy</code>	Removes <code>TGZFileStream</code> instance
<a href="#">557</a>	<code>read</code>	Read data from the compressed file
<a href="#">558</a>	<code>seek</code>	Set the position in the compressed stream.
<a href="#">558</a>	<code>write</code>	Write data to be compressed

### 32.11.3 TGZFileStream.create

Synopsis: Create a new instance of `TGZFileStream`

Declaration: `constructor create(filename: ansistring; filemode: Tgzopenmode)`

Visibility: public

Description: `Create` creates a new instance of the `TGZFileStream` class. It opens `FileName` for reading or writing, depending on the `FileMode` parameter. It is not possible to open the file read-write. If the file is opened for reading, it must exist.

If the file is opened for reading, the `TGZFileStream.Read` ([557](#)) method can be used for reading the data in uncompressed form.

If the file is opened for writing, any data written using the `TGZFileStream.Write` ([558](#)) method will be stored in the file in compressed (deflated) form.

Errors: If the file is not found, an `EZlibError` ([552](#)) exception is raised.

See also: `TGZFileStream.Destroy` ([558](#)), `TGZOpenMode` ([551](#))

### 32.11.4 TGZFileStream.read

Synopsis: Read data from the compressed file

Declaration: `function read(var buffer; count: LongInt) : LongInt; Override`

Visibility: public

**Description:** `Read` overrides the `Read` method of `TStream` to read the data from the compressed file. The `Buffer` parameter indicates where the read data should be stored. The `Count` parameter specifies the number of bytes (*uncompressed*) that should be read from the compressed file. Note that it is not possible to read from the stream if it was opened in write mode.

The function returns the number of uncompressed bytes actually read.

**Errors:** If `Buffer` points to an invalid location, or does not have enough room for `Count` bytes, an exception will be raised.

See also: `TGZFileStream.Create` (557), `TGZFileStream.Write` (558), `TGZFileStream.Seek` (558)

### 32.11.5 `TGZFileStream.write`

**Synopsis:** Write data to be compressed

**Declaration:** `function write(const buffer; count: LongInt) : LongInt; Override`

**Visibility:** public

**Description:** `Write` writes `Count` bytes from `Buffer` to the compressed file. The data is compressed as it is written, so ideally, less than `Count` bytes end up in the compressed file. Note that it is not possible to write to the stream if it was opened in read mode.

The function returns the number of (uncompressed) bytes that were actually written.

**Errors:** In case of an error, an `EZlibError` (552) exception is raised.

See also: `TGZFileStream.Create` (557), `TGZFileStream.Read` (557), `TGZFileStream.Seek` (558)

### 32.11.6 `TGZFileStream.seek`

**Synopsis:** Set the position in the compressed stream.

**Declaration:** `function seek(offset: LongInt; origin: Word) : LongInt; Override`

**Visibility:** public

**Description:** `Seek` sets the position to `Offset` bytes, starting from `Origin`. Not all combinations are possible, see `TDecompressionStream.Seek` (556) for a list of possibilities.

**Errors:** In case an impossible combination is asked, an `EZlibError` (552) exception is raised.

See also: `TDecompressionStream.Seek` (556)

### 32.11.7 `TGZFileStream.destroy`

**Synopsis:** Removes `TGZFileStream` instance

**Declaration:** `destructor destroy; Override`

**Visibility:** public

**Description:** `Destroy` closes the file and releases the `TGZFileStream` instance from memory.

See also: `TGZFileStream.Create` (557)